

# **Ingress Gateway**

🐧 8 minute read 🗸 page test

This task shows you how to enforce IP-based access control on an Istio ingress gateway using an authorization policy.

## Before you begin

- Read the Istio authorization concepts.
- Install Istio using the Istio installation guide.

Before you begin this task, do the following:

 Deploy a workload, httpbin in a namespace, for example foo, and expose it through the Istio ingress gateway with this command:

```
$ kubectl create ns foo
$ kubectl apply -f <(istioctl kube-inject -f @samples/httpb
in/httpbin.yaml@) -n foo
$ kubectl apply -f <(istioctl kube-inject -f @samples/httpb
in/httpbin-gateway.yaml@) -n foo</pre>
```

Turn on RBAC debugging in Envoy for the ingress

# gateway: \$ kubectl get pods -n istio-system -o name -l istio=ingress

```
gateway | sed 's|pod/||' | while read -r pod; do isticctl p roxy-config log "$pod" -n istio-system --level rbac:debug; done
```

and ports to define the INGRESS\_HOST and INGRESS\_PORT environment variables.

Follow the instructions in Determining the ingress IP

 Verify that the httpbin workload and ingress gateway are working as expected using this command:

```
$ curl "$INGRESS_HOST:$INGRESS_PORT"/headers -s -o /dev/nul
1 -w "%{http_code}\n"
200
```

If you don't see the expected output, retry

after a few seconds. Caching and propagation overhead can cause a delay.

## Getting traffic into Kubernetes and Istio

features that accomplish this are the NodePort service and the LoadBalancer service. Even the Kubernetes Ingress resource must be backed by an Ingress controller that will create either a NodePort or a LoadBalancer service.

• A NodePort just opens up a port in the range

All methods of getting traffic into Kubernetes involve

opening a port on all worker nodes. The main

30000-32767 on each worker node and uses a label selector to identify which Pods to send the traffic to. You have to manually create some kind of load balancer in front of your worker nodes or use Round-Robin DNS.

creates an environment specific external load balancer to handle distributing traffic to the worker nodes. For example, in AWS EKS, the LoadBalancer service will create a Classic ELB with your worker nodes as targets. If your Kubernetes environment does not have a LoadBalancer implementation, then it will just behave like a NodePort. An Istio ingress gateway creates a LoadBalancer service. What if the Pod that is handling traffic from the

NodePort or LoadBalancer isn't running on the worker node that received the traffic? Kubernetes has its own

• A LoadBalancer is just like a NodePort, except it also

internal proxy called kube-proxy that receives the packets and forwards them to the correct node.

# Source IP address of the original client

If a packet goes through an external proxy load balancer and/or kube-proxy, then the original source IP address of the client is lost. Below are some strategies for preserving the original client IP for logging or security purposes.

#### TCP/UDP Proxy Load Balancer

Network Load Balancer
HTTP/HTTPS Load Balancer

A critical bug has been identified in Envoy that the proxy protocol downstream address is restored incorrectly for non-HTTP connections.

Please DO NOT USE the remotelpBlocks field and remote ip attribute with proxy



until a newer version of Istio is released with a proper fix.

Note that Istio doesn't support the proxy protocol and it can be enabled only with the EnvoyFilter API and should be used at your own risk.

If you are using a TCP/UDP Proxy external load balancer (AWS Classic ELB), it can use the Proxy Protocol to embed the original client IP address in the packet data. Both the external load

balancer and the Istio ingress gateway must

support the proxy protocol for it to work. In Istio, you can enable it with an EnvoyFilter like below:

```
apiVersion: networking.istio.io/v1alpha3
kind: EnvoyFilter
metadata:
  name: proxy-protocol
  namespace: istio-system
spec:
  configPatches:
  - applyTo: LISTENER
    patch:
      operation: MERGE
      value:
        listener filters:
        - name: envoy.listener.proxy protocol
        - name: envoy.listener.tls_inspector
  workloadSelector:
    lahels:
      istio: ingressgateway
```

#### Here is a sample of the IstioOperator that shows

# how to configure the Istio ingress gateway on AWS EKS to support the Proxy Protocol:

```
apiVersion: install.istio.io/v1alpha1
kind: IstioOperator
spec:
  meshConfig:
    accessLogEncoding: JSON
    accessLogFile: /dev/stdout
  components:
    ingressGateways:
    - enabled: true
      k8s:
        hpaSpec:
          maxReplicas: 10
          minReplicas: 5
        serviceAnnotations:
          service.beta.kubernetes.io/aws-load-balancer-ac
cess-log-emit-interval: "5"
```

```
service.beta.kubernetes.io/aws-load-balancer-ac
cess-log-enabled: "true"
          service, beta, kubernetes, io/aws-load-balancer-ac
cess-log-s3-bucket-name: elb-logs
          service.beta.kubernetes.io/aws-load-balancer-ac
cess-log-s3-bucket-prefix: k8sELBIngressGW
          service.beta.kubernetes.io/aws-load-balancer-pr
oxy-protocol: "*"
        affinity:
          podAntiAffinity:
            preferredDuringSchedulingIgnoredDuringExecuti
on:
            - podAffinityTerm:
                labelSelector:
                  matchLahels:
                    istio: ingressgateway
                topologyKey: failure-domain.beta.kubernet
es.io/zone
              weight: 1
```

name: istio-ingressgateway

С	For reference, here are the types of load balancers reated by Istio with a LoadBalancer service on popular nanaged Kubernetes environments:							
	Cloud Provider	Load Balancer Name	Load Balanc					
	AWS EKS	Classic Elastic Load Balancer	TCP Proxy					
	GCP GKE	TCP/UDP Network Load Balancer	Network					

	DO DOKS	Load Balancer	N	etwork	
4					Þ

Azure Load Balancer

Network

Azure AKS

You can instruct AWS EKS to create a Network Load Balancer when you install Istio by using a serviceAnnotation like below:

```
apiVersion: install.istio.io/v1alpha1
kind: IstioOperator
spec:
  meshConfig:
    accessLogEncoding: JSON
    accessLogFile: /dev/stdout
  components:
    ingressGateways:
    - enabled: true
      k8s:
        hpaSpec:
          maxReplicas: 10
          minReplicas: 5
        serviceAnnotations:
          service.beta.kubernetes.io/aws-load-balance
r-type: "nlb"
```

## IP-based allow list and deny list

using the X-Forwarded-For HTTP header or the Proxy Protocol to determine the original client IP address, then you should use remoteIpBlocks in your AuthorizationPolicy. If you are using

When to use ipBlocks vs. remoteIpBlocks: If you are

externalTrafficPolicy: Local, then you should use ipBlocks in your AuthorizationPolicy.

Source of Client IP

ipBlocks V

Load Balancer Type

TCP Proxy	Proxy Protocol	remoteIpBl			
Network	packet source address	ipBlocks			
HTTP/HTTPS	X-Forwarded-For	remoteIpBl			
4		•			
• The following command creates the authorization					
policy, ingress-policy, for the Istio ingress gateway. The following policy sets the action field					
ipBlocks to access the ingress gateway. IP					
addresses not in the list will be denied. The					

ipBlocks supports both single IP address and CIDR notation.

**ipBlocks** remoteIpBlocks

Create the AuthorizationPolicy:

```
$ kubectl apply -f - <<EOF
apiVersion: security.istio.io/v1beta1
kind: AuthorizationPolicy
metadata:
   name: ingress-policy
   namespace: istio-system
spec:
   selector:</pre>
```

app: istio-ingressgateway

ipBlocks: ["1.2.3.4", "5.6.7.0/24"]

matchLabels:

action: ALLOW
rules:
- from:
- source:

EOF

 Verify that a request to the ingress gateway is denied:
 \$ curl "\$INGRESS\_HOST:\$INGRESS\_PORT"/headers -s -o /dev/nul

```
1 -w "%{http_code}\n"
403

• Update the ingress-policy to include your client IP
```

address:

ipBlocks
remoteIpBlocks

```
Find your original client IP address if you don't know it and assign it to a variable:
```

```
istio=ingressgateway | sed 's|pod/||' | while read -r po
d; do kubectl logs "$pod" -n istio-system | grep remoteIP
; done | tail -1 | awk -F, '{print $3}' | awk -F: '{print
$2}' | sed 's/ //') && echo "$CLIENT_IP"
192.168.10.15
```

\$ CLIENT\_IP=\$(kubectl get pods -n istio-system -o name -l

```
kind: AuthorizationPolicy
metadata:
  name: ingress-policy
  namespace: istio-system
spec:
  selector:
    matchLabels:
      app: istio-ingressgateway
  action: ALLOW
  rules:
  - from:
```

ipBlocks: ["1.2.3.4", "5.6.7.0/24", "\$CLIENT IP"]

\$ kubectl apply -f - <<EOF

- source:

EOF

apiVersion: security.istio.io/v1beta1

 Verify that a request to the ingress gateway is allowed:

```
$ curl "$INGRESS_HOST:$INGRESS_PORT"/headers -s -o /dev/nul
1 -w "%{http_code}\n"
200
```

 Update the ingress-policy authorization policy to set the action key to DENY so that the IP addresses specified in the ipBlocks are not allowed to access the ingress gateway:

ipBlocks remoteIpBlocks

```
$ kubectl apply -f - <<EOF
apiVersion: security.istio.io/v1beta1
kind: AuthorizationPolicy
metadata:
  name: ingress-policy
  namespace: istio-system
spec:
  selector:
    matchLabels:
      app: istio-ingressgateway
  action: DENY
  rules:
  - from:
    - source:
        ipBlocks: ["$CLIENT_IP"]
EOF
```

 Verify that a request to the ingress gateway is denied:
 \$\sum\_{\text{surl "\$INGRESS HOST:\$INGRESS PORT"/headers -s -o /dev/nul}}\$

```
1 -w "%{http_code}\n"
403
```

- You could use an online proxy service to access the ingress gateway using a different client IP to verify the request is allowed.
- If you are not getting the responses you expect, view the ingress gateway logs which should show RBAC debugging information:

```
\ kubectl get pods -n istio-system -o name -l istio=ingress gateway | sed 's|pod/||' | while read -r pod; do kubectl lo gs "$pod" -n istio-system; done
```

### Clean up

• Remove the namespace foo:

```
$ kubectl delete namespace foo
```

Remove the authorization policy:

\$ kubectl delete authorizationpolicy ingress-policy -n isti
o-system