# **BMDFM**Comprehensive Manual

2025

http://bmdfm.com

This page is intentionally left blank. Contents of the document begins on the next page.

## **Table of Contents**

About This Manual and License Terms	vii
Chapter 1 Introduction	1
Chapter 2 Architectural Overview	5
2.1 Static Scheduler	
2.2 Dynamic Scheduler	
2.3 Configuration	
2.4 Top Screen of the Running System	13
Chapter 3	
Installation and Use	15
3.1 Structure of Modules on the Disk	15
3.2 Programming and Compilation	17
3.3 Singlethreaded Engine	20
3.4 Server Unit	22
3.5 External Task Unit	25
3.6 External Tracer Unit	27
Appendix A	
Programming Language Reference	29
A.1 Program	29
A.2 Constant definition	
A.3 Variables	31
A.4 Special construction functions	33
A.5 Input/Output functions	
A.6 Built-in comparison functions	
A.7 Built-in boolean functions	
A.8 Built-in integer functions	
A.9 Built-in float functions	
A.10 Built-in string functions	45

# **Table of Contents (cont.)**

A.11 Built-in asynchronous memory heap functions	50
A.12 Built-in mapcar function	52
A.13 Built-in terminal capabilities functions	
A.14 Built-in constant and info functions	
A.15 Built-in rise runtime error functions	58
A.16 C Interface	59
Appendix B	
Example of Application Programming	69
Appendix C	
List of Target Deployments	81

# **List of Figures**

Figure 1-1. Running BMDFM on different machines	3
Figure 2-1. BMDFM architecture	5
Figure 2-2. Architecture of static scheduler	6
Figure 2-3. Architecture of dynamic scheduler	7
Figure 2-4. Configuration example for a 1024-way SMP machine	12
Figure 2-5. BMDFM running on a 4-way SMP machine	13
Figure 3-1. BMDFM modules	15
Figure 3-2. BMDFM directory tree	16
Figure 3-3. BMDFM user application life cycle	17
Figure 3-4. BMDFM user application structure	18
Figure 3-5. Recompilation of the BMDFM modules	19
Figure 3-6. BMDFM singlethreaded engine command line syntax	20
Figure 3-7. BMDFM singlethreaded engine work flow	21
Figure 3-8. BMDFM Server command line syntax	22
Figure 3-9. BMDFM Server unit work flow	23
Figure 3-10. BMDFM Server console view	24
Figure 3-11. External task unit command line syntax	25
Figure 3-12. External task unit work flow	26
Figure 3-13. External tracer unit command line syntax	27
Figure 3-14. External tracer unit work flow	
Figure 3-15. External tracer console view	28
Figure B-1. Computation example of discrete Hartley transforms	69

# **List of Figures (cont.)**

# **About This Manual and License Terms**

This manual gives an overview of the BMDFM software. The BMDFM architecture, installation procedure and programming language are described.



Use of the BMDFM software is subject to license restrictions. Carefully read End User License Agreement (EULA) before using this software.

If you do not agree to the terms and conditions specified in the EULA, please destroy all your copies of the BMDFM software from any drives, disks, tapes or other storage media and recycle all related printouts immediately.

#### **End User License Agreement (EULA)**

- 1. The BMDFM Software is distributed to an end user ("End User") as a binary code at no charge.
- 2. End User accepts a non-exclusive, non-transferable, royalty-free use of the BMDFM Software for non-commercial purposes. Any commercial use requires a separate license. End User may build own applications and create derivative works based on the BMDFM Software. End User has specific rights to create additional copies of the BMDFM Software as necessary for archival purposes and to modify the BMDFM Software as necessary to allow it to operate on the End User's equipment. End User may not reproduce and distribute the BMDFM Software.

- 3. End User agrees to respect and not to remove, obliterate, or cancel from view any copyright, trademark, confidentiality or other proprietary notice, mark, or legend appearing on the BMDFM Software or output generated by the BMDFM Software, and to reproduce and include same on each copy of the BMDFM Software.
- 4. End User agrees not to disassemble, decompile or reverse engineer the BMDFM Software, or any portion thereof.
- 5. End User further acknowledges that all copies of the BMDFM Software in any provided form are the sole property of the BMDFM official suppliers. End User shall not have any right, title, or interest to any such BMDFM Software or copies thereof except as provided in this EULA, and further shall secure and protect all BMDFM Software and documentation consistent with maintenance of the BMDFM proprietary rights therein.
- 6. The BMDFM Software is provided AS IS. End User agrees that the BMDFM official suppliers shall not be liable for any costs, damages, fees, or other liability, nor for any direct, indirect, special, incidental, or consequential damages with respect to any claim by End User or any third party on account of or arising from this EULA or use of (or inability to use) any portion of the BMDFM Software.
- 7. THE EXPRESS WARRANTY STATED IMMEDIATELY ABOVE IS GIVEN IN LIEU OF ALL OTHER WARRANTIES, EITHER EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

# Chapter 1 Introduction

#### What is BMDFM?

BMDFM (Binary Modular DataFlow Machine) is software, which enables running an application in parallel on shared memory symmetric multiprocessors (SMP) using the multiple processor cores to speed up the execution of single applications.

BMDFM automatically identifies and exploits parallelism due to the static and mainly DYNAMIC SCHEDULING of the data flow instruction sequences derived from the formerly sequential program ensuring unique parallel correctness.

No directives for parallel execution are required! No highly knowledgeable parallel programmers are required!

#### What does BMDFM provide to a user?

A user understands BMDFM as a virtual machine, which runs every statement of an application program in parallel having all parallelization and synchronization mechanisms fully transparent. The statements of an application program are normal operators, which any singlethreaded program might consist of - they are variable assignments, conditional executions, loops, function calls, etc. BMDFM has a rich set of standard operators/functions, which can be extended by user functions written in C/C++.

In comparison with the recent general methodology of sequential code parallelization, which is based on static analysis, BMDFM uses dynamic scheduling to define and to run code fragments in parallel. It means that data computed at run time will define further branches for parallel processing (DataFlow principle). It also means that loops of an application program will be dynamically unrolled to process several iterations in parallel.

#### Which granularity of parallelism is used in BMDFM?

BMDFM exploits fine-grain parallelism. All instructions of an application will be processed in parallel. In addition, it is possible to exploit coarse-grain parallelism that will decrease costs spent on dynamic scheduling. In order to achieve this a portion of C code can be defined as a user function, which will be treated by the dynamic scheduler as one seamless instruction.

#### Which platforms may run BMDFM?

# Every machine supporting ANSI C and POSIX/SVR4-IPC may run BMDFM.

Obviously, BMDFM is able to accelerate the execution time of an application only when installed on a multiprocessor computer implementing an SMP paradigm (hardware mapping of distributed memory into virtual shared memory, cache coherent non-uniform memory access ccNUMA, UMA!, etc.)

BMDFM is provided as compiled multi-threaded versions for:

• x86: Linux/32, FreeBSD/32, OpenBSD/32, NetBSD/32, MacOS/32,

SunOS/32, UnixWare/32, Minix/32, Android/32, Win-Cygwin/32,

Win-UWIN/32, Win-SFU-SUA/32;

• x86-64: Linux/64, FreeBSD/64, OpenBSD/64, NetBSD/64, MacOS/64,

SunOS/64, Android/64, Win-Cygwin/64;

• VAX: <u>Ultrix/32;</u>

• Alpha: Tru64OSF1/64, Linux/64, FreeBSD/64, OpenBSD/64;

• IA-64: HP-UX/32, HP-UX/64, Linux/64, FreeBSD/64;

• XeonPhiMIC: Linux/64;

• MCST-Elbrus: Linux/32, Linux/64;

• PA-RISC: HP-UX/32, HP-UX/64, Linux/32;

• SPARC: SunOS/32, SunOS/64, Linux/32, Linux/64, FreeBSD/64,

OpenBSD/64;

• MIPS: IRIX/32, IRIX/64, Linux/32, Linux/64;

• MIPSel: Linux/32, Linux/64, Android/32, Android/64;

• PowerPC: AIX/32, AIX/64, MacOS/32, MacOS/64, Linux/32, Linux/64,

FreeBSD/32, FreeBSD/64;

PowerPCle: Linux/32, Linux/64;
 S/390: Linux/32, Linux/64;

• M68000: Linux/32;

• ARM: Linux/32, Linux/64, FreeBSD/64, Android/32, Android/64,

MacOS/64;

• ARMbe: Linux/64;

• RISC-V: Linux/32, Linux/64;

• LoongArch: Linux/64;

and<sup>1</sup> a limited single-threaded version for:

• x86: Win/32.

A machine with one CPU can be used for development and test purposes only as it is not possible to get real acceleration on one CPU. But as soon the application program has reached a certain state of maturity it can be moved to BMDFM running on a wide range of multicore/many-core computers (from tiny embedded devices to multiprocessor big iron mainframes) as shown in Figure 1-1.



Figure 1-1. Running BMDFM on different machines



BMDFM Official Web Site: http://bmdfm.com

BMDFM Support: email to: bmdfm@bmdfm.de

<sup>1.</sup> Actual BMDFM installation factory package can provide additional compiled platform-specific versions.

This page is intentionally left blank.

# Chapter 2 Architectural Overview

BMDFM uses both highly efficient dynamic and static scheduling combining SMP (Shared Memory Symmetric Multi Processing), MIMD (Multiple Instruction Stream, Multiple Data Stream) and DFM (DataFlow Machine) paradigms. The BMDFM architecture is shown in Figure 2-1.




Figure 2-1. BMDFM architecture

A pool of processes is divided into two subsets: Work Processes, which execute parallel instruction streams, and Dynamic Scheduling Processes, which automatically convert sequential instruction streams into parallel ones.

Running under an SMP OS the processes will occupy all available real machine processors.

All processes share the Shared Memory Pool containing Instructions and Data. Each Work Process also has its own Local Memory, which may contain user subroutines to implement additional coarse-grain levels of parallelization. The External Loader/Listener Pair performs preprocessing and static scheduling of the input program instructions and stores them clustered in the Task Connection Zone. The Listener is responsible for the ordered output after the out-of-order processing in the Multithreaded Engine. Clustered instructions and data are fetched by the Dynamic Scheduling Processes into the Shared Memory Pool. Additionally, Dynamic Scheduling Processes release (garbage collect) resources after the data contexts and speculative branches are processed. Lastly, the External Tracers assist in debugging of the multithreaded out-of-order processing of the input program. The External Tracers are connected via the Ports of the Trace Plugging Area. The Tracer can operate in various modes of full/partial and master/slave debugging.

### 2.1 Static Scheduler

Figure 2-2 shows the static scheduling part of BMDFM. An application program (Input Sequential Program) is processed in three stages: preliminary code reorganization (Code Reorganizer), static scheduling of the statements (Static Scheduler) and compiling/loading (Compiler). The output after the static scheduling stages is a **Multiple Clusters Flow** that feeds the Multithreaded Engine via the Interface designed in a way to avoid bottlenecks. For some special cases, such as development of loaders, the Interface can be published. Multiple Clusters Flow can be understood as a compiled input program split on the marshaled clusters, in which all addresses are resolved and extended with context information. Splitting on the marshaled clusters enables loading them multithreadedly. Context information lets iterations be processed in parallel.



Figure 2-2. Architecture of static scheduler

## 2.2 Dynamic Scheduler

Figure 2-3 shows the part of BMDFM responsible for the dynamic scheduling in more detail. The BMDFM dynamic scheduling subsystem performs an efficient SMP emulation of the Tagged-Token Dataflow Machine as described below.




Figure 2-3. Architecture of dynamic scheduler

The Shared Memory Pool is divided in three main parts: Input/Output Ring Buffer Port (IORBP), Data Buffer (DB) and Operation Queue (OQ).

The external static scheduler (External Task Loader/Listener Pair) puts clustered instructions and data of an input program into the IORBP. The ring buffer service processes (IORBP PROC) move data into the DB and instructions into the OQ. The operation queue service processes (OQ PROC) tag the instructions as ready for execution if the required operands' data is accessible. The execution processes (CPU PROC) execute instructions, which are tagged as ready and output computed data into the DB or to the IORBP. Additionally, IORBP PROC and OQ PROC are responsible for freeing memory after contexts have been processed. The context is a special unique identifier representing a copy of data within

different iteration bodies. This allows the dynamic scheduler to handle several iterations in parallel.

In order to allow several processes accessing the same data concurrently, BMDFM locks objects in the Shared Memory Pool via POSIX/SVR4 semaphore operations. Locking policy provides multiple read-only access and exclusive access for modification.

# 2.3 Configuration



Please, ensure suitable amount of SVR4 IPC resources when running BMDFM (note that BMDFM can be configured with POSIX/SVR4-IPC-synchronization).

#### Example for SunOS:

```
/etc/system
set shmsys:shminfo_shmmax=2147483647
set semsys:seminfo_semmni=128
set semsys:seminfo_semmsl=256
set semsys:seminfo_semmns=32768
```

Configuration parameters are gathered in the BMDFM configuration profile. The configuration parameters are explained below:

SHMEM\_POOL\_SIZE defines maximal shared memory pool size. Bigger values ensure that BMDFM will operate for larger amounts of data. Note that 2147483647 (2GB) shmmax value is normally a limit for 32-bit mode. Run 64-bit BMDFM that allows you to configure more shared memory space.

**SHMEM\_POOL\_MNTADDR** defines explicit mounting address of the shared memory pool. By default, the mounting address is chosen by the BMDFM Server and the OS automatically.

**SHMEM\_POOL\_PERMS** defines permissions of the shared memory pool in a form of traditional Unix-like and otherwise POSIX-compliant system permissions (e.g. decimal 432 is equal to octal 0660 and means "rw-rw----").

**SHMEM\_POOL\_BANKS** defines the number of banks in shared memory pool. Several banks together work faster than one, however, the memory bank restricts maximal memory block size that can be allocated.

**POSIX\_SEMA4\_SYNC** defines whether POSIX semaphores should be used instead of SVR4 semaphores.

**ARRAYBLOCK\_SIZE** defines the policy of the memory allocation. Memory is allocated in chunks. Bigger values cause less intensive and faster memory allocation, however at the same time, cause more inefficient memory usage.

- **OQ\_FUNC\_ARG\_COUNT** defines the default number of the function arguments statically allocated in the OQ. In case where the actual number of arguments exceeds, they will be allocated dynamically.
- **Q\_OQ** defines OQ size. Bigger values allow the running of tasks with more complex data dependencies, however, a big OQ requires additional memory space, an additional number of semaphores and can slow down associative searches in the dynamic scheduling subsystem.
- **Q\_DB** defines DB size. Bigger values allow running tasks with more variables, however, a big DB requires additional memory space and an additional number of semaphores.
- **Q\_IORBP** defines IORBP size. Bigger values allow more intensive loading of data via the Task Connection Zone, however, a big IORBP requires additional memory space and an additional number of semaphores.
- **N\_IORBP** defines the number of IORBPs, thus the number of tasks, which can be processed in parallel. Processing several tasks simultaneously uses system resources more efficiently.
- **N\_TRACEPORT** defines how many tracers can be attached at the same time. Bigger values allow one to have more tracers working in separate windows displaying different resources.

**N\_CPUPROC** defines the number of CPUPROC processes. Usually, it makes sense to set this value equal or doubled to the number of system logical processors (processors \* cores \* threads\_per\_core). An additional tuning can be done after analysis of STALL WARNINGS in the generated log files.

**N\_OQPROC** defines the number of OQPROC processes. Usually, it makes sense to set this value equal or doubled to the number of system logical processors (processors \* cores \* threads\_per\_core). An additional tuning can be done after analysis of STALL WARNINGS in the generated log files.

**N\_IORBPPROC** defines the number of IORBPROC processes. Usually, it makes sense to set this value equal or doubled to the number of system logical processors (processors \* cores \* threads\_per\_core). An additional tuning can be done after analysis of STALL WARNINGS in the generated log files.

**CPUPROC\_MTHREAD** specifies multithreading model (if switched on) or multi-process model (if switched off) for the CPUPROC processes.

**OQPROC\_MTHREAD** specifies multithreading model (if switched on) or multi-process model (if switched off) for the OQPROC processes.

**IORBPPROC\_MTHREAD** specifies multithreading model (if switched on) or multi-process model (if switched off) for the IORBPROC processes.

**BMDFMLDR\_MTHREAD** specifies multithreading model (if switched on) or multi-process model (if switched off) for the BMDFMldr static scheduler processes.

MTHREAD\_TLS\_CHECK switches verification for Thread-Local Storage (TLS) on/off. The verification is done at startup.

**ALLOW\_CPUPROC\_ASLR** allows CPUPROC processes to use Address Space Layout Randomization (ASLR) provided by the OS (if switched on).

**T\_STATISTIC** defines time interval between attempts of collecting statistics. Less values make the statistics more precise but increase costs for this.

**CONSOLE\_OUT\_UTF8** adjusts console output for UTF8 (if switched on) or ASCII (if switched off).

**PROC\_HEARTBEATS** switches process heartbeats on/off. The heartbeats are sent between CPUPROC, OQPROC and IORBPROC processes in order to detect whether the processes are alive.

**DFSTLHAZARD\_DETECT** switches detection of dataflow stall hazards on/off. All stalled dataflow instructions will be purged after a stall hazard is detected.

**ALLOW\_DROP\_NONPROD** allows dropping nonproductive instructions (if switched on). Nonproductive instructions are those that do not influence any execution path for achieving results of an application program (the results of an application program are VM native inputs and outputs of this application program).

**PROC\_CPU\_LOGS** switches Data Flow Logging Facility on/off. This facility allows logging the CPUPROC and IORBPROC process activities into log files.

**HARD\_ARRAY\_SYNCHRO** ensures correct array processing where the multiple assignments are applied to the same array members. As a rule, the BMDFM system asks to switch this option on if it is necessary.

**EXT\_IN\_OUT\_SYNCHRO** synchronizes console messages that are generated by the Loader/Listener Pair. If this configuration parameter is switched on, the Loader always waits until the Listener releases console.

**OQ\_DB\_SEM\_LIMIT** defines the maximal allowed number of SVR4 semaphores in the OS kernel that are owned by the BMDFM instance. By default, no limitation is set. Note that BMDFM can be configured with POSIX/SVR4-IPC-synchronization.

**RELAXED\_CNSTN\_SM\_MODEL** compensates relaxed consistency model of shared memory (if switched on). The compensation mechanisms are activated by default. It is strongly recommended to keep them activated if the consistency model of SMP machine is not clear enough.

**DEFOP** configures user-defined functions to be loaded into CPUPROC local memory.

Figure 2-4 shows configuration example for a 1024-way SMP machine.

```
SHMEM POOL SIZE = 10995116277760 # (10TB) Shared memory pool size
   SHMEM POOL MNTADDR = 0 # ShMemPool mount address (0=auto)
  SHMEM_POOL_PERMS = 432 # ShMemPool permissions (0660=="rw-rw---")

SHMEM_POOL_BANKS = 500 # Number of banks in pool

POSIX_SEMA4_SYNC = RW+Count # Replace None/RW/RW+Count SVR4 with POSIX sema4

ARRAYBLOCK_SIZE = 64 # Array block size [Entities]

OQ_FUNC_ARG_COUNT = 32 # OQ functions arguments count [Entities]
with POSIX sen

[Entities]

" of iunctions arguments count [Entities]

" of iunctions arguments [Entities]

" of iunctions [Entities]

" of iunctions [Entities]

" of iunctions [Entities]

"
  N_CPUPROC = 2048 # Number of the CPU PROCs
N_OQPROC = 2048 # Number of the OQ PROCs
N_IORBPPROC = 2048 # Number of the IORBP PROCs
  CPUPROC_MTHREAD = No # CPU PROC is multithreaded
OQPROC_MTHREAD = No # OQ PROC is multithreaded
IORBPPROC_MTHREAD = No # IORBP PROC is multithreaded
BMDFMLDR_MTHREAD = No # BMDFMldr is multithreaded
   MTHREAD_TLS_CHECK = No # Check for Thread-Local Storage (TLS)
ALLOW_CPUPROC_ASLR = No # Allow CPU PROC Address Space Layout
                                                                                                                                                                      # Randomization (ASLR)
  T_STATISTIC = 1 # Time to scan DFM for statistic [Seconds]

CONSOLE_OUT_UTF8 = No # Adjust console output for ASCII or UTF8

PROC_HEARTBEATS = Yes # Heartbeats for the CPU, OQ && IORBP PROCS

DFSTLHAZARD_DETECT = Yes # Detection of dataflow stall hazards

ALLOW_DROP_NONPROD = No # Allow dropping nonproductive instructions

PROC_CPU_LOGS = No # Logs registration for the CPU && IORBP PROCS

HARD_ARRAY_SYNCHRO = No # Hard synchronization of the arrays

EXT_IN_OUT_SYNCHRO = Yes # I/O synchronization of external task

OQ_DB_SEM_LIMIT = 0 # Max number of OQ&&DB semaphores (0=unlim.)
    RELAXED CNSTN SM MODEL = Yes # Compensate ShMem relaxed consistency
    DEFOR
                                                                                                                    (defun true (progn 1))
                                                                                                                       (defun false (progn 0))
                                                                                                                       # (defun ...)
```

Figure 2-4. Configuration example for a 1024-way SMP machine

# 2.4 Top Screen of the Running System

The *top* screen of the running BMDFM is shown in Figure 2-5. It clearly demonstrates that BMDFM is built according to the MIMD architecture and has negligible dynamic scheduling overhead!




Figure 2-5. BMDFM running on a 4-way SMP machine

This page is intentionally left blank.

# Chapter 3 Installation and Use

### 3.1 Structure of Modules on the Disk

BMDFM modules shown in Figure 3-1. All modules are given as executables and some of them additionally as object files and sources. Recompilation is necessary only if a new application (interface and implementation) is written in C/C++. Singlethreaded version of BMDFM consists of only one module, all the rest belongs to the multithreaded engine. The multithreaded BMDFM starts with the BMDFMsrv server, which automatically starts multiple copies of the daemons (CPUPROC, OQPROC, IORBPROC and PROCstat). The BMDFMldr, BMDFMtrc and freeIPC (as well as the fastlisp and BMDFMsrv themselves) are standalone utilities.

```
cflp_udf.h cflp_udf.c
Makefile

fastlisp.o fastlisp
BMDFM singlethreaded engine
BMDFMsrv.o BMDFMsrv
BMDFM multithreaded engine server unit
CPUPROC.o CPUPROC
OQPROC
```

Figure 3-1. BMDFM modules

Normally, the BMDFM files are gathered in a \$BMDFM\_HOME/ working directory. The directory structure is shown in Figure 3-2. Choose a BMDFM build by linking Bin directory to the correct target directory (default link is Bin -> Build/x86\_Linux\_32\_gccV485/), e.g. delete default link and create another one: rm Bin; ln -s Build\_ExtendedInterface/x86-64\_Linux\_64\_gccV1021 Bin

```
$BMDFM HOME/
    EULA.txt
    READ_ME.1ST
    Doc/
         BMDFMmission.pdf
         BMDFMdoc.pdf
         BMDFMfaq.pdf
         <Examples>/
    Bin/ -> Build/x86_Linux_32_gccV485/
    fastlisp
                       -> Bin/fastlisp
    BMDFMsrv
                        -> Bin/BMDFMsrv
    CPUPROC
                       -> Bin/CPUPROC
                        -> Bin/OQPROC
    OQPROC
    IORBPROC
                        -> Bin/IORB PROC
    PROCstat
                        -> Bin/PROCstat
                        -> Bin/BMDFMldr
                        -> Bin/BMDFMtrc
                        -> Bin/free IPC
    fastlisp.cfg -> Bin/fastlisp.cfg
    BMDFMsrv.cfg -> Bin/BMDFMsrv.cfg
    Build/ Build_MultiProcess/
x86_WindowsCygnus_32_gccV291/
x86_WindowsCygwin_32_gccV640/
                                                  Build_ExtendedInterface/
                                                       IA-64_HP-UX_32_ccVa0628/
                                                                                                       PowerPC AIX 32 x1cV1313/
                                                       IA-64 HP-UX 32 gccV472/
                                                                                                       PowerPC AIX 32 gccV494
         x86_WindowsUWIN_32_gccV295/
                                                       IA-64_HP-UX_64_ccVa0628/
                                                                                                       PowerPC_AIX_64_x1cV1313/
                                                       IA-64_HP-UX_64_gccV472/
IA-64_Linux_64_gccV412/
                                                                                                       PowerPC_AIX_64_gccV494/
PowerPC_MacOS_32_gccV421/
         x86 WindowsSFU-SUA 32 gccV33/
         x86_Linux_32_gccV485/
         x86_Linux_32_gccV1021/
                                                       IA-64_Linux_64_gccV463/
                                                                                                       PowerPC MacOS 64 gccV421/
         x86_Linux_32_clangV1101/
x86_Linux_32_iccVxe2019u3/
x86_FreeBSD_32_gccV920/
                                                       IA-64 Linux 64 gccV1021/
                                                                                                       PowerPC Linux 32 gccV492/
                                                       IA-64_FreeBSD_64_gccV421/
XeonPhiMIC_Linux_64_iccVxe2017u5/
                                                                                                      PowerPC_Linux_32_gccV1021/
PowerPC_Linux_32_clangV350/
         x86_FreeBSD_32_clangV801/
                                                       XeonPhiMIC_Linux_64_gccV470/
                                                                                                       PowerPC_Linux_32_clangV1101/
         x86_OpenBSD_32_gccV830/
x86_OpenBSD_32_clangV801/
                                                       MCSTelbrus Linux 32 lccV120/
MCSTelbrus Linux 32 lccV125/
                                                                                                       PowerPC_Linux_64_gccV492/
PowerPC_Linux_64_gccV1021/
         x86_NetBSD_32_gccV830/
x86_NetBSD_32_clangV900/
                                                                                                       PowerPC_Linux_64_clangV350/
PowerPC_Linux_64_clangV1101/
                                                       MCSTelbrus_Linux_64_lccV120/
                                                       MCSTelbrus Linux 64 lccV125/
                                                       PA-RISC_HP-UX_32_ccVc0370/
         x86_MacOS_32_clangV702/
                                                                                                       PowerPC_FreeBSD_32_gccV920/
         x86_SunOS_32_ccV510/
x86_SunOS_32_gccV343/
x86_UnixwareSCO_32_ccsV42/
x86_UnixwareSCO_32_gccV295/
                                                                                                      PowerPC FreeBSD 32 clangV801/
PowerPC FreeBSD 64 gccV920/
PowerPC FreeBSD 64_clangV801/
PowerPCle_Linux_32_gccV930/
                                                       PA-RISC HP-UX 32 gccV471/
                                                       PA-RISC HP-UX 64 ccVc0370/
PA-RISC HP-UX 64 gccV471/
                                                       PA-RISC Linux 32 gccV492/
                                                                                                       PowerPCle Linux 64 gccV1021/
PowerPCle Linux 64 clangV1101/
PowerPCle Linux 64 xlcV1611/
         x86_Minix_32_clangV36/
                                                       PA-RISC_Linux_32_gccV1021/
         x86_Android_32_gccV49x/
x86_Android_32_clangV503/
                                                       SPARC Sun OS 32 ccV510/
                                                       SPARC_Sun OS_32_gccV343/
         x86-64_WindowsCygwin_64_gccV640/
x86-64_Linux_64_gccV485/
                                                       SPARC_Sun OS 64 ccV510/
SPARC_Sun OS 64 gccV343/
                                                                                                       S390_Linux_32_gccV930/
S390_Linux_64_gccV930/
         x86-64 Linux 64 gccV1021/
x86-64 Linux 64 clangV1101/
x86-64 Linux 64_iccVxe2019u3/
                                                       SPARC_Linux_32_gccV1021/
SPARC_Linux_32_clangV1101/
                                                                                                       S390_Linux_64_clangV381/
M68000_Linux_32_gccV930/
                                                       SPARC_Linux_64_gccV1021/
                                                                                                       ARMeabi_Linux_32_gccV1021/
                                                                                                      ARMeabihf Linux 32 gccV1021/
ARMeabihf Linux 32 clangV381/
         x86-64 FreeBSD 64_gccV920/
                                                       SPARC Linux 64 clangV1101/
         x86-64_FreeBSD_64_clangV801/
                                                       SPARC_FreeBSD_64_gccV421/
         x86-64_OpenBSD_64_gccV830/
x86-64_OpenBSD_64_clangV801/
                                                       SPARC_OpenBSD_64_gccV830/
SPARC_OpenBSD_64_clangV801/
                                                                                                       ARM_Linux_64_gccV1021/
ARM_Linux_64_clangV1101/
         x86-64_NetBSD_64_gccV830/
x86-64_NetBSD_64_clangV900/
                                                                                                      ARM_FreeBSD_64_gccV920/
ARM_FreeBSD_64_clangV801/
                                                       MIPS_IRIX_32_ccV744m/
                                                       MIPS IRIX 32 gccV471/
         x86-64_MacOS_64_clangV702/
x86-64_MacOS_64_clangV1200/
                                                       MIPS_IRIX_32_gccV471_TLS/
MIPS_IRIX_64_ccV744m/
                                                                                                       ARM_Android_32_gccV49x/
ARM_Android_32_clangV503/
         x86-64_SunOS_64_ccV510/
                                                       MIPS_IRIX_64_gccV471/
                                                                                                       ARM_Android_64_gccV49x/
         x86-64_SunOS_64_gccV343/
x86-64_Android_64_gccV49x/
                                                       MIPS_IRIX_64_gccV471_TLS/
MIPS_Linux_32_gccV930/
                                                                                                       ARM_Android_64_clangV503/
ARM_MacOS_64_clangV1200/
         x86-64_Android_64_clangV503/
                                                       MIPS_Linux_32_gccV830_sgi/
                                                                                                       ARMe_MacOS_64_clangV1200/
                                                                                                      ARMbe_Linux_64_gccV930/
RISCV_Linux_32_gccV930/
         VAX Ultrix 32 gccV272/
                                                       MIPS Linux 64 gccV930/
         Alpha_Tru64OSF1_64_ccV65303/
                                                       MIPSel_Linux_32_gccV930/
         Alpha Tru640SF1 64 gccV423/
                                                       MIPSel_Linux_64_gccV930/
MIPSel_Android_32_gccV49x/
                                                                                                       RISCV_Linux_64_gccV930/
         Alpha Linux 64 gccV424/
                                                                                                       LoongArch Linux 64 gccV1300/
         Alpha_Linux_64_gccV1021/
                                                       MIPSel_Android_32_clangV503/
                                                                                                       <Arch>_<OS>_<Bits>_<Compiler>[_<Feat.>]/
         Alpha FreeBSD 64 gccV346/
Alpha OpenBSD 64 gccV421/
                                                       MIPSel Android 64 gccV49x/
                                                       MIPSel Android 64 clangV503/
             fastlisp.cfg cflp_udf.h fastlisp.o fastlisp OQPROC
                                                                                                          [OQPROC.o]
             BMDFMsrv.cfg cflp_udf.c BMDFMsrv.o BMDFMsrv IORBPROC
                                                                                                          [IORBPROC.o]
                                                      CPUPROC. o CPUPROC PROCStat
BMDFMldr. o BMDFMldr BMDFMtrc
                                   Makefile
                                                                                                          [PROCstat.o]
                                                                                                          [BMDFMtrc.ol
                                                                                          freeIPC
                                                                                                          [freeIPC.o]
```

Figure 3-2. BMDFM directory tree

# 3.2 Programming and Compilation

Normally, the life cycle of a BMDFM user application has two major steps as shown in Figure 3-3. At first the application is developed and tested using the BMDFM singlethreaded engine, then if it works properly it can be moved without any modifications to the BMDFM multithreaded engine.




Figure 3-3. BMDFM user application life cycle

A BMDFM user application itself can be built according to the three schemes in Figure 3-4 (actually, the application can be structured as any combination of these three schemes).




Figure 3-4. BMDFM user application structure

**Scheme A.** A complete application is written in pure virtual machine language. In this case BMDFM will exploit fine-grain parallelism, thus BMDFM will try to unroll the loops and to execute all statements in parallel. If it runs on a non-UMA (non-Uniform Memory Access) machine the dynamic scheduling can be expensive.

**Scheme B.** According to this scheme some UDFs (User Defined Functions) are located in the configuration profile, thus BMDFM will upload them into CPU PROCs Local Memory and their bodies will be prevented from scheduling for parallel processing (such a UDF will be treated as one seamless statement). In this case less time is obviously spent on dynamic scheduling.

**Scheme C.** This scheme enables using the C code directly instead of the virtual machine code. Of course the C code compiled and optimized by a local C compiler is faster than virtual machine code. In this case some BMDFM modules should be recompiled as shown in Figure 3-5.




Figure 3-5. Recompilation of the BMDFM modules

## 3.3 Singlethreaded Engine

The BMDFM singlethreaded engine can be used from a command line according to the syntax shown in Figure 3-6. The help option creates a documentation file and a set of examples on the disk. The compile2disk and compileMinimized2disk options create a machine dependent compiled code of the application on the disk. The showDebugInfo option displays additional debug information of the application. Optionally, the environment variables define location of the configuration profile and further configuration parameters.

```
Usage0: fastlisp -h --help
  Usage1: fastlisp -V --versions
  Usage2: fastlisp [-q|--quiet] <FastLisp_file_name> [args...]
  Usage3: fastlisp [-sd|--showDebugInfo] <FastLisp_file_name> [args...]
  Usage4: fastlisp [-c|--compile2disk] <FastLisp_file_name> [args...]
  Usage5: fastlisp [-cm --compileMinimized2disk] <FastLisp file name> [args...]
  Usage6: fastlisp [-q|--quiet] < Precompiled FastLisp file name>
  Usage7: fastlisp [-sd|--showDebugInfo] < Precompiled FastLisp file name>
Runtime environment variable dump:
  FAST_LISP_CODE_PRINT__TERM_WIDE=0;
  FAST_LISP_CODE_PRINT__CFG_UDF=1;
FAST_LISP_CODE_PRINT__MODIFIED_SRC=1;
FAST_LISP_CODE_PRINT__DUMPED_SRC=1;
FAST_LISP_CODE_PRINT__COMPILED=1;
  FAST LISP CODE PRINT LINKED=1;
  FAST_LISP_CODE_PRINT DECOMPILED=1;
  FAST LISP MAPCAR WITH DECOMPILER=1;
  FAST LISP COMPILE WITH DEBUGINFO=1;
The following environment variable:
  FAST LISP CFGPROFILE path="fastlisp.cfg"
specifies a configuration profile that can be used for the Global FastLisp
function definitions. The format of the configuration profile is:
  <(DEFUN ...)>{ <(DEFUN ...)>} # <EOF>.
```

Figure 3-6. BMDFM singlethreaded engine command line syntax

The BMDFM singlethreaded engine compiles, links and runs a user application in a standalone mode as shown in Figure 3-7.




Figure 3-7. BMDFM singlethreaded engine work flow

3.4 Server Unit Installation and Use

### 3.4 Server Unit

There is only one way to start the BMDFM multithreaded engine correctly. It should be started by the BMDFM Server from a command line according to the syntax shown in Figure 3-8. The BMDFM Server may also run as a daemon. Additional logfile options enable/disable logging of console information on the disk. Optionally, the environment variables define connection pathes of the BMDFM Server, locations of all daemons, which will be started in the background, and further configuration parameters.

```
Usage0: BMDFMsrv
 Usage1: BMDFMsrv -h --help
 Usage2: BMDFMsrv -V --versions
 Usage3: BMDFMsrv [-d --daemonize]
 Usage4: BMDFMsrv [-d --daemonize] -n --no-logs
 Usage5: BMDFMsrv [-d|--daemonize] -1|--logfile <log file name>
Runtime environment variable dump:
 BM DFM MAPCAR WITH DECOMPILER=1;
 BM DFM COMPILE WITH DEBUGINFO=1;
 BM DFM CFGPROFILE path="./BMDFMsrv.cfg";
 BM DFM PROCstat path="./PROCstat";
 BM DFM CPUPROC path="./CPUPROC";
 BM DFM OQPROC path="./OQPROC";
 BM DFM IORBPROC path="./IORBPROC";
 BM DFM CONNECTION_FILE_path="/tmp/.BMDFMsrv";
 BM DFM CONNECTION NPIP path="/tmp/.BMDFMsrv npipe";
 BM DFM EMERGENCY IPC_FILE_path="./freeIPC.inf";
 BM DFM LOGFILE KEEP NxSIZE="10x10000000";
 BM DFM PROCLOGFILE KEEP NxSIZE="10x10000000";
 BM DFM PROCLOGFILE path="./PROCs.log";
```

Figure 3-8. BMDFM Server command line syntax

The BMDFM Server unit reads the configuration profile, initializes the Shared Memory Pool, starts multiple copies of the daemons in the background and enters a console mode. The BMDFM Server unit is also responsible for shutting down the whole multithreaded engine correctly. This procedure is illustrated in Figure 3-9. A screen shot of the BMDFM Server console, when it operates typical routines, is shown in Figure 3-10.

Installation and Use 3.4 Server Unit




Figure 3-9. BMDFM Server unit work flow

3.4 Server Unit Installation and Use




Figure 3-10. BMDFM Server console view

### 3.5 External Task Unit

The external task unit (Loader/Listener Pair) can be used from a command line according to the syntax shown in Figure 3-11. The compile2disk option creates a machine dependent compiled code of the application on the disk. The showDebugInfo option displays additional debug information of the application. Optionally, the environment variables define connection pathes to the BMDFM Server running instance and further configuration parameters.

```
Usage0: BMDFMldr -h|--help
  Usage1: BMDFMldr -V | --versions
  Usage2: BMDFMldr [-q|--quiet] <FastLisp file name> [args...]
  Usage3: BMDFMldr [-sd|--showDebugInfo] <FastLisp_file_name> [args...]
  Usage4: BMDFMldr [-c|--compile2disk] <FastLisp file name> [args...]
 Usage5: BMDFMldr [-q --quiet] < Precompiled FastLisp file name>
  Usage6: BMDFMldr [-sd --showDebugInfo] < Precompiled FastLisp file name >
Runtime environment variable dump:
 BM DFM CODE PRINT TERM WIDE=0;
  BM DFM CODE PRINT CFG UDF=1;
  BM_DFM_CODE_PRINT_MODIFIED_SRC=1;
  BM_DFM_CODE_PRINT__DUMPED_SRC=1;
 BM DFM CODE PRINT LINKED=1;
BM DFM CODE PRINT DFM UNICODE=1;
  BM DFM MAPCAR WITH DECOMPILER=1;
  BM DFM COMPILE WITH DEBUGINFO=1;
  BM DFM_CONNECTION_FILE_path="/tmp/.BMDFMsrv";
  BM DFM CONNECTION NPIP path="/tmp/.BMDFMsrv npipe";
```

Figure 3-11. External task unit command line syntax

The external task unit reorganizes the user code, makes static scheduling, compiles, connects multithreaded engine, links, starts listener thread and uploads the user application into the multithreaded engine as shown in Figure 3-12.




Figure 3-12. External task unit work flow

### 3.6 External Tracer Unit

The external tracer unit can be used from a command line according to the syntax shown in Figure 3-13. Additional logscreen options enable/disable information logging on the disk. The environment variables serve like in the external task unit.

```
Usage0: BMDFMtrc
Usage1: BMDFMtrc -h --help
Usage2: BMDFMtrc -V --versions
Usage3: BMDFMtrc -l --log-last-screen [<log_file_name>]
Usage4: BMDFMtrc -L --log-all-screens [<log_file_name>]
Runtime environment variable dump:
BM_DFM_TRACER_LOG__TERM_WIDE=0;
BM_DFM_CONNECTION_FILE_path="/tmp/.BMDFMsrv";
BM_DFM_CONNECTION_NPIP_path="/tmp/.BMDFMsrv npipe";
```

Figure 3-13. External tracer unit command line syntax

The external tracer unit connects the multithreaded engine and enters the tracer console as shown in Figure 3-14. The external tracer is shown in Figure 3-15.




Figure 3-14. External tracer unit work flow




Figure 3-15. External tracer console view

# Appendix A Programming Language Reference

The BMDFM virtual machine language is based on a prefix form syntax and uses **transparent dataflow semantics**.

### A.1 Program

A program is a function:

```
| "<FuncName>"
| (<FuncName> <Val_argument1> <Val_argument2> ... <Val_argumentN>) |
| --> <Val_calculated_value>
```

It returns its calculated value as a result. It is possible to specify a formal argument, a constant value, a variable name or some other function at the place of the function argument. Formal arguments appear like \$1 ... \$N. All argument types will be automatically converted to the required types when the function is called.

`#' is a comment symbol. It indicates that all text following the `#' symbol (until the carriage return) is a comment. All symbols in the same line after the `#' symbol will be ignored.

Use (comments | comment | remarks | remark | rem ...) for multiple line comments.

#### A.2 Constant definition

Integer constants:

```
[<+|->]<digit>[{<digit>}]
```

Float constants:

```
[<+|->][{<digit>}][.{<digit>}][e[<+|->]{<digit>}]
```

String constants:

```
"<char>{<char>}"
 Special symbols are:
   \a - beep;
\b - back space;
   \e - escape;
   \f - page feed;
   \n - new line;
   \r
       - return;
   \t
       - tab;
       vertical tab;
   \v
   \\
       - \;
   \ n
        - ";
   0xNN - symbol by its hex code (e.g.: 0x25 == %', 0x5C == ()').
Use ("<string>"{ "<string>"}) concatenation for a long string.
```

Special void type constant:

```
nil
```

Appendix A A.3 Variables

### A.3 Variables

Variable names are not case sensitive. A variable name starts with a letter followed by letters, numbers and other symbols except `(', `)', `"', `@' and `:' symbols. Variables change their types dynamically among integers, floats, strings and nil.

Boolean 'TRUE' is considered to be an integer non-zero value.

Boolean `FALSE' is considered to be an integer zero value.

A variable can also be an array. An array changes its own size (number of members) dynamically. Array members can be integers, floats, strings, NIL's and arrays themselves that allows one creating list and tree structures.

First(zero) array member cannot be an array itself.

Predefined terminal control variables (same names like the corresponding terminal capabilities functions) are:

A.3 Variables Appendix A

Variable assignment and index functions:

## A.4 Special construction functions

Argument types will be casted.

Ordered grouping:

Conditional execution:

While-loop:

```
"while"

(while <IVal_condition> <Val_to_be_evaluated_while_true>)

--> <IVal_0>
```

For-loop:

User Defined Function (UDF). UDF names are not case sensitive. A UDF name may consist of letters, numbers and other symbols except `(', `)', `"', `@' and `:' symbols. A UDF can be nested inside of another UDF. Formal arguments appear like \$1 ... \$N in the UDF body. A UDF may access only its own private local variables, or in other words, all variables that are referenced in the UDF body are private local variables of this UDF.

```
"defun"
| (defun <FuncName> <Val_to_be_evaluated>)
--> <SVal_empty_string>
```

Break iteration loop or UDF execution of the current nested level:

```
| "break"
| (break)
| --> <SVal_empty_string>
```

Cancel program execution and exit:

```
"exit"
  (exit)
   --> <SVal_empty_string>
```

## A.5 Input/Output functions

```
"accept"
 (accept <SVal prompt message for console or empty for stdin>)
   --> <SVal_input_string>
  (scan_console <IVal_wait_key_forever_if_1_or_useconds_if_positive>)
    --> <SVal keypressed string>
  (outf <SVal printf format> <Val value>)
    --> <SVal_printf_formatted_string_that_was_printed_to_stdout>
"file create"
 (file create <SVal file name>)
    --> <IVal file descriptor or -1>
"file open"
  (file_open <SVal_file_name>)
    --> <IVal_file_descriptor_or_-1>
  (file write <IVal file descriptor> <SVal string to be written>)
    --> <IVal number of bytes written or -1>
"file read"
 (file read <IVal file descriptor> <IVal number of bytes to be read>)
   --> <SVal_string_read_or_empty_string>
```

```
"file seek beg"
 (file_seek_beg <IVal_file_descriptor>
                <IVal_offset_in_bytes_from_file_beginning>)
   --> <IVal_offset_in_bytes_from_file_beginning_or_-1>
"file_seek_cur"
  (file seek cur <IVal file descriptor>
                 <IVal offset in bytes from file current offset>)
    --> <IVal offset in bytes from file beginning or -1>
"file seek end"
  (file_seek_end <IVal_file_descriptor>
                <IVal_offset_in_bytes_from_file_end>)
    --> <IVal offset in bytes from file beginning or -1>
"file close"
  (file close <IVal file descriptor>)
    --> <IVal 0 or -1>
"file remove"
 (file_remove <SVal_file_name>)
   --> <IVal_0_or_-1>
(user io <IVal user defined integer> <IVal user defined string>)
   --> <SVal string returned by user defined io c function>
```

## A.6 Built-in comparison functions

Second argument type will be casted to first argument type:

```
"==" "equal"
 (== <Val value1> <Val value2>)
    --> <IVal_true_if_value1_and_value2_are_equal_otherwise_false>
______
"!=" "notequal"
  (!= <Val value1> <Val value2>)
    --> <IVal true if value1 and value2 are not equal otherwise false>
  (< <Val value1> <Val value2>)
    --> <IVal true if value1 is less than value2 otherwise false>
">" "greater"
 (> <Val value1> <Val value2>)
    --> <IVal_true_if_value1_is_greater_than_value2_otherwise_false>
"<=" "lessorequal"
  (<= <Val_value1> <Val_value2>)
    --> <IVal_true_if_value1_is_less_than_value2_or_
              _if_value1_and_value2_are_equal_otherwise false>
">=" "greaterorequal"
  (>= <Val value1> <Val value2>)
   --> <IVal_true_if_value1_is_greater_than_value2_or_
               _if_value1_and_value2_are_equal_otherwise_false>
```

### A.7 Built-in boolean functions

## A.8 Built-in integer functions

```
"ival"
 (ival <Val value>)
   --> <IVal_integer>
"indices"
  (indices <Val value>)
    --> <IVal_number_of_array_indices>
  (irnd <IVal_maxrange_or_negative_to_reset_random_generator>)
    --> <IVal random value within the range of 0 to maxrange>
"+" "iadd"
  (+ <IVal integer1> <IVal integer2>)
    --> <IVal addition integer1+integer2>
"-" "isub"
  (- <IVal_integer1> <IVal_integer2>)
    --> <IVal_subtraction_integer1-integer2>
  (* <IVal integer1> <IVal integer2>)
    --> <IVal multiplication integer1*integer2>
"/" "idiv"
  (/ <IVal integer1> <IVal integer2>)
    --> <IVal_division_integer1/integer2>
"*+" "ima"
 (*+ <IVal integer1> <IVal integer2> <IVal integer3>)
   --> <IVal MultiplyAccumulateOperation integer1*integer2+integer3>
```

```
(% <IVal integer1> <IVal integer2>)
    --> <IVal_modulo_integer_remainder_integer1%integer2>
"++" "iincr"
  (++ <IVal integer>)
    --> <IVal increment>
"--" "idecr"
  (-- <IVal integer>)
    --> <IVal_decrement>
"0-" "ineg"
 (0- <IVal integer>)
   --> <IVal additive inverse>
"iabs"
  (iabs <IVal_integer>)
    --> <IVal absolute value>
"&" "iand"
  (& <IVal integer1> <IVal integer2>)
    --> <IVal bitwise AND>
"|" "ior"
  (| <IVal_integer1> <IVal_integer2>)
   --> <IVal_bitwise_OR>
  (^ <IVal_integer1> <IVal_integer2>)
    --> <IVal bitwise exclusive OR>
"~" "inot"
 (~ <IVal integer>)
   --> <IVal_bitwise_inversion>
```

```
">>" "ishr"
| (>> <IVal_integer> <IVal_shift_positions>)
| --> <IVal_bitwise_right_shift>
| "<<" "ishl"
| (<< <IVal_integer> <IVal_shift_positions>)
| --> <IVal_bitwise_left_shift>
```

### A.9 Built-in float functions

```
"fval"
 (fval <Val value>)
   --> <FVal float>
  (frnd <FVal_maxrange_or_negative_to_reset_random_generator>)
    --> <FVal random value within the range of 0 to maxrange>
  (+. <FVal_float1> <FVal_float2>)
    --> <FVal addition float1+float2>
"-." "fsub"
  (-. <FVal float1> <FVal float2>)
    --> <FVal subtraction float1-float2>
"*." "fmul"
  (*. <FVal_float1> <FVal_float2>)
    --> <FVal_multiplication_float1*float2>
  (/. <FVal float1> <FVal float2>)
    --> <FVal division float1/float2>
"*+." "fma"
  (*+. <FVal float1> <FVal float2> <FVal float3>)
    --> <FVal_MultiplyAccumulateOperation_float*float2+float3>
"fabs"
 (fabs <FVal_float>)
   --> <FVal absolute value>
```

```
"fint" "int"
(fint <FVal float>)
   --> <FVal_integer_part>
"fround" "round"
  (fround <FVal float>)
    --> <FVal rounded value>
"fcos" "cos"
  (fcos <FVal radians>)
   --> <FVal_cosine>
"fsin" "sin"
 (fsin <FVal radians>)
   --> <FVal sine>
"fcas" "cas"
 (fcas <FVal_radians>)
   --> <FVal sine+cosine>
"fatn" "atn"
  (fatn <FVal float>)
    --> <FVal arctangent radians>
"fexp" "exp"
 (fexp <FVal float>)
   --> <FVal_exponential>
"fpow" "pow" "^." "**"
 (fpow <FVal_base> <FVal_exponent>)
   --> <FVal base raised to the power of exponent>
```

```
"fln" "ln"
(fln <FVal_float>)
    --> <FVal_natural_logarithm_base_E>

"fsqrt" "sqrt" "sqr"
(fsqrt <FVal_float>)
    --> <FVal_square_root>
```

## A.10 Built-in string functions

```
"str"
 (str <Val value>)
   --> <SVal_string>
  (chr <IVal integer>)
    --> <SVal one character string>
  (asc <SVal_string>)
    --> <IVal code of first character>
"crcsum"
 (crcsum <SVal string>)
   --> <IVal CRC of string>
"type"
 (type <Val_value>)
    --> <SVal_type_among_I_F_S_Z>
  (dump i2s <IVal integer>)
    --> <SVal_memory_dump_of_integer>
"dump f2s"
  (dump f2s <FVal float>)
   --> <SVal_memory_dump_of_float>
"dump_s2i"
  (dump s2i <SVal string>)
   --> <IVal integer dumped from string>
"dump s2f"
 (dump s2f <SVal string>)
   --> <FVal float dumped from string>
```

```
"notempty"
 (notempty <SVal string>)
   --> <IVal true if not empty>
"len"
  (len <SVal_string>)
    --> <IVal length>
"at"
  (at <SVal substring to be found> <SVal string to be searched in>)
    --> <IVal found first occurrence position from left or zero>
  (rat <SVal substring to be found> <SVal string to be searched in>)
    --> <IVal found first occurrence position from right or zero>
"cat"
  (cat <SVal string1> <SVal string2>)
    --> <SVal concatenation string1+string2>
"space"
  (space <IVal length>)
    --> <SVal empty string filled with spaces>
  (replicate <SVal pattern> <IVal number of copies>)
    --> <SVal_string_filled_with_patterns>
"left"
  (left <SVal_string> <IVal_position_from_left>)
    --> <SVal left part of string>
"leftr"
  (leftr <SVal string> <IVal position from right>)
   --> <SVal_left_part_of_string>
```

```
"right"
 (right <SVal string> <IVal position from right>)
    --> <SVal_right_part_of_string>
"rightl"
  (rightl <SVal string> <IVal position from left>)
    --> <SVal right part of string>
"substr"
  (substr <SVal string> <IVal position from left> <IVal length>)
    --> <SVal_substring_derived_from_string>
  (strtran <SVal string> <SVal pattern> <SVal substitution>)
    --> <SVal string where patterns are replaced with substitutions>
"str raw"
  (str raw <SVal string>)
    --> <SVal string with no escape characters for special symbols>
"str unraw"
  (str unraw <SVal string>)
    --> <SVal string with escape characters for special symbols>
"str dump"
  (str dump <SVal string>)
   --> <SVal semihexadecimal string dump>
"str fmt"
  (str_fmt <SVal_printf_format> <Val_value>)
    --> <SVal printf formatted string>
"ltrim"
  (ltrim <SVal string>)
    --> <SVal_string_with_no_leading_blanks>
"rtrim"
 (rtrim <SVal_string>)
   --> <SVal string with no ending blanks>
```

```
(alltrim <SVal string>)
    --> <SVal_string_with_neither_leading_nor_ending_blanks>
"pack"
  (pack <SVal string>)
    --> <SVal string with no redundant blanks>
"head"
  (head <SVal string>)
   --> <SVal_first_token>
 (tail <SVal string>)
   --> <SVal remaining tokens>
"lsp head"
  (lsp_head <SVal_string>)
    --> <SVal first FastLisp token>
"lsp_tail"
  (lsp tail <SVal string>)
    --> <SVal remaining FastLisp tokens>
 (upper <SVal_string>)
   --> <SVal_upper_case_string>
"lower"
  (lower <SVal_string>)
    --> <SVal lower case string>
"upper utf8"
  (upper <SVal UTF8 string>)
    --> <SVal_upper_case_UTF8_string>
"lower utf8"
 (lower <SVal_UTF8_string>)
   --> <SVal lower case UTF8 string>
```

```
"is utf8char"
  (is utf8char <SVal string>)
    --> <IVal_size_of_first_UTF8_character_or_zero>
"ltrim utf8"
  (ltrim utf8 <SVal string>)
    --> <SVal_string_with_legal_leading_UTF8 character>
"rtrim utf8"
  (rtrim utf8 <SVal string>)
    --> <SVal_string_with_legal_ending_UTF8_character>
  (alltrim utf8 <SVal string>)
    --> <SVal string with legal leading and ending UTF8 characters>
"rev"
  (rev <SVal string>)
    --> <SVal reverse ordered string>
"padl"
  (padl <SVal string> <IVal length>)
   --> <SVal left justified string>
  (padr <SVal string> <IVal length>)
   --> <SVal_right_justified_string>
"padc"
  (padc <SVal_string> <IVal_length>)
    --> <SVal centered string>
"time"
    --> <SVal current system time>
 (getenv <SVal_environment_variable_name>)
   --> <SVal environment variable value>
```

## A.11 Built-in asynchronous memory heap functions

```
"asyncheap create"
 (asyncheap create <IVal size bytes>)
    --> <IVal descriptor or 0>
"asyncheap getaddress"
  (asyncheap getaddress <IVal descriptor>)
   --> <IVal address>
  (asyncheap putint <IVal descriptor> <IVal offset> <IVal integer>)
"asyncheap getint"
  (asyncheap_getint <IVal_descriptor> <IVal_offset>)
    --> <IVal integer>
"asyncheap putfloat"
  (asyncheap_putfloat <IVal_descriptor> <IVal_offset> <FVal_float>)
   --> <IVal 1>
"asyncheap getfloat"
  (asyncheap getfloat <IVal descriptor> <IVal offset>)
    --> <FVal float>
"asyncheap putstring"
  (asyncheap_putstring <IVal_descriptor> <IVal_offset> <SVal_string>)
"asyncheap getstring"
  (asyncheap getstring <IVal descriptor> <IVal offset> <IVal length>)
   --> <SVal string>
```

```
"asyncheap_reallocate"
  (asyncheap_reallocate <IVal_descriptor> <IVal_new_size_bytes>)
    --> <IVal_new_descriptor>

"asyncheap_replicate"
  (asyncheap_replicate <IVal_descriptor>)
    --> <IVal_new_descriptor>

"asyncheap_delete"
  (asyncheap_delete <IVal_descriptor>)
    --> <IVal_1</pre>
```

## A.12 Built-in mapcar function

## A.13 Built-in terminal capabilities functions

```
"reinit terminal"
  (reinit terminal <SVal terminal type or empty for default terminal>)
    --> <SVal terminal capabilities status>
"term_type"
  (term type)
    --> <SVal TERM environment configured terminal name>
"lines term"
 (lines term)
    --> <IVal terminal capability li>
"columns term"
  (columns term)
    --> <IVal terminal capability co>
"clrscr_term"
  (clrscr term)
    --> <SVal terminal capability cl>
"reverse term"
  (reverse term)
    --> <SVal_terminal_capability_mr>
"blink term"
  (blink_term)
    --> <SVal terminal capability mb>
"bold term"
 (bold term)
   --> <SVal terminal capability md>
```

```
"normal term"
(normal term)
   --> <SVal_terminal_capability_me>
"hidecursor term"
  (hidecursor_term)
    --> <SVal terminal capability vi>
"showcursor term"
  (showcursor term)
   --> <SVal_terminal_capability_ve>
  (gotocursor term <IVal y coordinate> <IVal x coordinate>)
    --> <SVal filled with coordinates terminal capability cm
         or unfilled terminal capability cm if input is negative>
"gotocursor1 term"
  (gotocursor1 term <SVal unfilled terminal capability cm>
                    <IVal y coordinate> <IVal x coordinate>)
   --> <SVal_filled_with_coordinates_terminal_capability_cm>
```

#### A.14 Built-in constant and info functions

```
"ee"
    --> <FVal base of natural logarithm e>
  (gamma)
    --> <FVal Euler Mascheroni constant gamma>
"phi"
  (phi)
   --> <FVal golden ratio constant phi>
"pi"
   --> <FVal constant pi>
"prn integer fmt"
  (prn_integer_fmt)
    --> <SVal_preconfigured_printf_format_for_integer>
"prn float fmt"
  (prn float fmt)
    --> <SVal preconfigured printf format for float>
"prn string fmt"
  (prn string fmt)
   --> <SVal_preconfigured_printf_format_for_string>
"version fstlisp"
 (version fstlisp)
   --> <SVal FastLisp version>
```

```
"version termcap"
 (version termcap)
    --> <SVal_termcap_library_version>
"version strglib"
  (version strglib)
    --> <SVal string library version>
"version mempool"
  (version mempool)
    --> <SVal_memory_pool_library_version>
"compiled on"
  (compiled on)
    --> <SVal compilation related machine os kernel specific info>
"compiled by"
  (compiled by)
    --> <SVal compilation related machine compiler specific info>
"n_cpuproc"
  (n cpuproc)
    --> <IVal number of configured parallel processing units>
"id cpuproc"
  (id cpuproc)
    --> <IVal_id_of_current_parallel_processing_unit>
"n taskjob"
  (n_taskjob)
    --> <IVal number of maximal parallel task jobs>
"id taskjob"
 (id taskjob)
    --> <IVal_id_of_current_task_job>
```

```
"am_I_in_the_fastlisp_module"
    (am_I_in_the_fastlisp_module)
    --> <IVal_true_if_running_in_the_fastlisp_module>

"am_I_in_the_BMDFMldr_module"
    (am_I_in_the_BMDFMldr_module)
    --> <IVal_true_if_running_in_the_BMDFMldr_module>

"am_I_in_the_BMDFMsrv_module"
    (am_I_in_the_BMDFMsrv_module)
    --> <IVal_true_if_running_in_the_BMDFMsrv_module>

"am_I_in_the_CPUPROC_module"
    (am_I_in_the_CPUPROC_module)
    --> <IVal_true_if_running_in_the_CPUPROC_module>

"am_I_in_the_multithreaded_module"
    (am_I_in_the_multithreaded_module)
    --> <IVal_true_if_running_in_the_multithreaded_module>

--> <IVal_true_if_running_in_the_multithreaded_module>
```

### A.15 Built-in rise runtime error functions

```
"set error"
 (set error)
   --> <SVal_error_text>
"rise error"
  (rise error)
"set error dbg"
  (set_error_dbg)
   --> <SVal_error_text>
"rise_error_dbg"
 (rise error dbg)
"set error info"
  (set error info <IVal error code> <SVal error text>)
    --> <SVal error text>
"rise_error info"
  (rise_error_info <IVal_error_code> <SVal_error_text>)
"set error info dbg"
  (set_error_info_dbg <IVal_error_code> <SVal_error_text>)
    --> <SVal error text>
"rise_error_info_dbg"
  (rise_error_info_dbg <IVal_error_code> <SVal_error_text>)
"get error code"
  (get error code)
   --> <IVal error code>
"get error text"
 (get_error_text)
   --> <SVal_error_text>
```

Appendix A A.16 C Interface

#### A.16 C Interface

See cflp\_udf.h/cflp\_udf.c for details.

In order to simplify declaration constructions the following abbreviations are used for the standard types:

```
#define CHR char

#define UCH unsigned char

#define SCH signed char

#define USH unsigned short int

#define SSH signed short int

#define ULO unsigned long int

#define SLO signed long int

#define DFL double
```

Each variable is stored in a universal structure that enables it to change data types dynamically and to have a single value or an array with different types of members, thus supporting lists and trees.

A.16 C Interface Appendix A

The declaration of a variable of the universal structure type allocates a single value on the stack and an array in the heap that is very convenient assuming most variables store only single values. No memory overhead is needed for storing arrays with members of the same type.

A user C function can be defined through the following type declaration:

```
typedef void (*fcall)(const ULO*, struct fastlisp_data*);
```

The first argument is a pointer to the passed function arguments and the second argument is a pointer to the result structure.

Appendix A A.16 C Interface

Passed arguments can be obtained from inside the function via the following set:

```
/* get universal data structure (see ret_val implementation below) */
void (*fcall)(const ULO*, struct fastlisp_data*);

/* get integer or pointer value */
void ret_ival(const ULO *dat_ptr, SLO *targ);

/* get float value */
void ret_fval(const ULO *dat_ptr, DFL *targ);

/* get string value */
void ret_sval(const ULO *dat_ptr, CHR **targ);
```

#### Additionally, there are:

- two helper functions to be called from each created user thread;
- two functions for copying and deleting the universal data structure;
- three callback functions;
- four info functions for the processing units and task jobs;
- five info functions for the modules;
- five functions to handle runtime errors.

A.16 C Interface Appendix A

```
/* called at startup */
  void startup_callback(void);

/* called at task job end */
  void taskjob_end_callback(ULO id_taskjob);

/* (user_io <IVal> <SVal>) callee */
  void user_io_callback(SLO usr_id, CHR **usr_buff);
```

```
/* get the number of configured parallel processing units
    ('N_CPUPROC' configuration parameter) */
    ULO get_n_cpuproc(void);

/* get ID of the current parallel processing unit
    (within the range of [0; 'N_CPUPROC'[) */
    ULO get_id_cpuproc(void);

/* get the number of maximal parallel task jobs
    ('N_IORBP' configuration parameter) */
    ULO get_n_taskjob(void);

/* get ID of the current task job
    (within the range of [0; 'N_IORBP'[) */
    ULO get_id_taskjob(void);
```

```
/* info functions for the modules */

UCH am_I_in_the_fastlisp_module(void);

UCH am_I_in_the_BMDFMldr_module(void);

UCH am_I_in_the_BMDFMsrv_module(void);

UCH am_I_in_the_CPUPROC_module(void);

UCH am_I_in_the_multithreaded_module(void);
```

Appendix A A.16 C Interface

```
/* check whether no runtime error occurred */
 UCH noterror(void);
/* set runtime error */
  CHR *set error(CHR **targ errtext);
/* rise runtime error */
  void rise_error(void);
/* set runtime error with dbg info */
  CHR *set error dbg(CHR **targ errtext, const ULO *dat ptr);
/* rise runtime error with dbg info */
  void rise error dbg(const ULO *dat ptr);
/* set runtime error with info */
  CHR *set error info(UCH errcode, CHR **targ errtext,
    const CHR *src errtext);
/* rise runtime error with info */
  void rise error info(UCH errcode, const CHR *src errtext);
/* set runtime error with info and with dbg info */
  CHR *set error info dbg(UCH errcode, CHR **targ errtext,
    const CHR *src errtext, const ULO *dat ptr);
/* rise runtime error with info and with dbg info */
  void rise error info dbg(UCH errcode, const CHR *src errtext,
    const ULO *dat ptr);
/* get runtime error code */
  UCH get error code(void);
/* get runtime error text */
  CHR *get error text(CHR **targ errtext);
/* Reserved runtime error codes:
  ECODE RT INT DIVZERO 1 ECODE RT ARR NEGINDEX 13
ECODE RT INT MODZERO 2 ECODE RT ARR ZEROMEMB 14
ECODE RT FLOAT DIVZERO 3 ECODE RT ARR WRONGINDICES 15
ECODE RT FLOAT POWER 4 ECODE RT ARR TYPEMISMATCH 16
ECODE RT FLOAT LOGARITHM 5
ECODE RT FLOAT SQRT 6 ECODE RT RESERVED6 249
ECODE RT AND WRONGDESCR 7 ECODE RT RESERVED6 249
  ECODE_RT__AHEAP_WRONGDESCR 7 ECODE_RT__RESERVED5
                                                                     250
  ECODE RT AHEAP OUTOFRANGE 8 ECODE RT RESERVED4
                                                                     251
  ECODE RT WRONG FMT STRING 9 ECODE RT RESERVED3
  ECODE RT VAR NOTINIT 10 ECODE RT RESERVED2
ECODE RT ARR NOTINIT 11 ECODE RT RESERVED1
                                                                     253
                                                                     254
  ECODE_RT__ARR_MEMBSNOTINIT 12 ECODE_RT__RESERVED0
                                                                     255 */
```

A.16 C Interface Appendix A

The final step, which should be performed after a user C function is defined, is to fill the instruction database according to the following structure:

```
typedef struct{
   const CHR *fnc_name; /* function name */
   const SSH operands; /* number of arguments */
   const UCH ret_type; /* result type: 'I', 'F', 'S', 'Z' */
   const UCH *op_type; /* flags 'IFSZ' for every argument */
   const fcall func_ptr; /* pointer to the function */
} INSTRUCTION_STRU;
```

See an example of a user defined C function below. Passed function arguments are obtained sequentially through the incremented "dat\_ptr". Internal calls to "ret\_ival", "ret\_fval" and "ret\_sval" provide dynamic type casting if required. A direct "fcall" function invocation omits the dynamic casting and returns a universal data structure.

Finally, "my\_function" is registered in the instruction database. The corresponding record states that the function has five arguments and returns an integer value. Argument types are integer, integer, float, string and integer respectively.

Appendix A A.16 C Interface

```
if(noterror()){
   /* data processing to compute `result': */
   ret dat->single=1;
   ret dat->type='I';
   ret dat->value.ival=result;
   /* or an error occurred: */
   rise error info dbg(USER DEFINED UNRESERVED ERRCODE, "ERROR TEXT",
     dat ptr);
  }
  if(dat.disable ptr)
   free flp data(&dat);
  free_string(&str);
  return;
}
/* Users may implement their own ret val() like:
    void ret val(const ULO *dat ptr, struct fastlisp data *ret dat){
      dat ptr=*((ULO**)dat ptr);
      (*(fcall)*dat ptr)(dat ptr+1,ret dat);
      return;
     }
  or like:
    void ret val(const ULO *dat ptr, struct fastlisp data *ret dat){
      if(noterror()){
        dat ptr=*((ULO**)dat ptr);
        (*(fcall)*dat_ptr)(dat_ptr+1,ret_dat);
      }
      return;
     }
  in order to simplify reading universal data args, e.g.:
    ret val(dat ptr+4,&dat);
*/
INSTRUCTION STRU INSTRUCTION SET[] ={
 /* ... */
  {"MY FUNCTION", 5, 'I', (UCH*) "IIFSI", &my function},
 /* ... */
};
const ULO INSTRUCTIONS=
        sizeof(INSTRUCTION SET)/sizeof(INSTRUCTION STRU);
```

A.16 C Interface Appendix A

And last but not least is string processing. Internally, strings are stored in the following format:

The implemented set of the string processing functions is basically equal to the same set on the FastLisp level:

```
CHR *mk std buff(CHR **buff, ULO size);
CHR *mk std buff secure(CHR **buff, ULO size);
CHR *mk fst buff(CHR **buff, ULO size);
CHR *mk fst buff secure(CHR **buff, ULO size);
CHR *get std buff(CHR **targ, const CHR *buff);
CHR *get std buff secure(CHR **targ, const CHR *buff);
UCH notempty(const CHR *string);
ULO len(const CHR *string);
ULO at(const CHR *pattern, const CHR *among);
ULO rat(const CHR *pattern, const CHR *among);
UCH cmp(const CHR *string1, const CHR *string2);
SCH cmp s(const CHR *string1, const CHR *string2);
CHR *equ(CHR **targ, const CHR *source);
CHR *equ secure(CHR **targ, const CHR *source);
CHR *equ num(CHR **targ, SLO num);
CHR *equ unum(CHR **targ, ULO num);
CHR *equ numhex(CHR **targ, ULO num);
CHR *equ fnum(CHR **targ, DFL fnum);
CHR *cat(CHR **targ, const CHR *source);
CHR *lcat(CHR **targ, const CHR *source);
CHR *space(CHR **targ, ULO pos);
CHR *replicate(CHR **targ, const CHR *source, ULO num);
CHR *left(CHR **targ, const CHR *source, ULO pos);
CHR *leftr(CHR **targ, const CHR *source, ULO posr);
CHR *right(CHR **targ, const CHR *source, ULO pos);
CHR *rightl(CHR **targ, const CHR *source, ULO posl);
CHR *substr(CHR **targ, const CHR *source, ULO from, ULO pos);
CHR *strtran(CHR **targ, const CHR *source, const CHR *pattern,
  const CHR *subst);
CHR *ltrim(CHR **targ, const CHR *source);
CHR *rtrim(CHR **targ, const CHR *source);
CHR *alltrim(CHR **targ, const CHR *source);
CHR *pack(CHR **targ, const CHR *source);
CHR *head(CHR **targ, const CHR *source);
CHR *tail(CHR **targ, const CHR *source);
CHR *lsp head(CHR **targ, const CHR *source);
```

Appendix A A.16 C Interface

```
CHR *lsp tail(CHR **targ, const CHR *source);
CHR *upper(CHR **targ, const CHR *source);
CHR *lower(CHR **targ, const CHR *source);
CHR *upper utf8(CHR **targ, const CHR *source);
CHR *lower utf8(CHR **targ, const CHR *source);
UCH is utf8char(const CHR *utf8char);
CHR *ltrim utf8(CHR **targ, const CHR *source);
CHR *rtrim utf8 (CHR **targ, const CHR *source);
CHR *alltrim utf8(CHR **targ, const CHR *source);
CHR *rev(CHR **targ, const CHR *source);
CHR *padl(CHR **targ, const CHR *source, ULO width);
CHR *padr(CHR **targ, const CHR *source, ULO width);
CHR *padc(CHR **targ, const CHR *source, ULO width);
CHR *strraw(CHR **targ, const CHR *source);
CHR *strunraw(CHR **targ, const CHR *source);
CHR *strdump(CHR **targ, const CHR *source);
CHR *string time(CHR **targ);
CHR *strings version(CHR **targ);
CHR *sch2str(CHR **targ, SCH num);
CHR *ssh2str(CHR **targ, SSH num);
CHR *slo2str(CHR **targ, SLO num);
CHR *ptr2str(CHR **targ, void *ptr);
CHR *dfl2str(CHR **targ, DFL num);
SCH str2sch(const CHR *string);
SSH str2ssh(const CHR *string);
SLO str2slo(const CHR *string);
void *str2ptr(const CHR *string);
DFL str2dfl(const CHR *string);
ULO crcsum(const CHR *string);
CHR *free string(CHR **targ);
```

An example of string processing is given below:

```
CHR *str0=NULL,*str1=NULL,*str2=NULL;

get_std_buff(&str0,"To be or not to be");

get_std_buff(&str1,"be");

get_std_buff(&str2,"compute");

upper(&str0,strtran(&str0,str1,str2));

printf("`%s'\n",str0); /* Result: `TO COMPUTE OR NOT TO COMPUTE' */

free_string(&str0);

free_string(&str1);

free_string(&str2);
```

A.16 C Interface Appendix A

This page is intentionally left blank.

## Appendix B Example of Application Programming

This is a simple application example, which computes direct and inverse 2D nonseparative discrete Hartley transforms (DHT and IDHT) according to the computation flow shown in Figure B-1.

$$H[p,q] = \sum_{n=0}^{N-1} \sum_{m=0}^{M-1} x[n,m] \cdot cas\left(\frac{2 \cdot \pi}{N} \cdot p \cdot n + \frac{2 \cdot \pi}{M} \cdot q \cdot m\right),$$

$$p = 0..N - 1, \ q = 0.M - 1$$

$$H_{inv}[p,q] = \frac{1}{N \cdot M} H[p,q]$$
Compute IDHT
Compute IDHT
Compare

Figure B-1. Computation example of discrete Hartley transforms

Four functions from Figure B-1 can be implemented in C as follows:

```
void func dhtpipe0 generate(const ULO *dat ptr, struct fastlisp data *ret dat) {
  SLO i,j,n,m;
  DFL *array;
  ret_ival(dat_ptr,(SLO*)&array);
  ret_ival(dat_ptr+1,&n);
  ret_ival (dat_ptr+2,&m);
  if (noterror()) {
    for (i=0; i<n;i++)</pre>
      for (j=0; j < m; j++)</pre>
        *(array+i*m+j)=1.*rand()/RAND_MAX;
    ret dat->single=1;
    ret dat->type='I';
    ret dat->value.ival=(SLO)array;
  return:
}
void func dhtpipe0 dht(const ULO *dat ptr, struct fastlisp data *ret dat) {
  SLO i,j,p,q,n,m;
  DFL *target array, *source array, pi, c1, s1, sum, tmp;
  ret_ival(dat_ptr,(SLO*)&target_array);
  ret_ival(dat_ptr+1,&n);
  ret_ival(dat_ptr+2,&m);
  ret ival(dat ptr+3,(SLO*)&source array);
  if (noterror()){
    pi=3.1415926535897932;
    c1=2*pi/n;
    s1=2*pi/m;
    for (p=0;p<n;p++)
      for (q=0; q < m; q++) {
        sum=0;
        for(i=0;i<n;i++)</pre>
           for (j = 0; j < m; j++)</pre>
             sum += (*(source\_array + i*m + j)*(cos(tmp = c1*p*i + s1*q*j) + sin(tmp)));
         *(target array+p*m+q)=sum;
    ret_dat->single=1;
    ret dat->type='I';
    ret_dat->value.ival=(SLO) target_array;
  return;
}
```

```
void func__dhtpipe0_idht(const ULO *dat_ptr, struct fastlisp_data *ret_dat){
  SLO i,j,p,q,n,m;
  DFL *target_array,*source_array,pi,c1,s1,sum,tmp;
  ret_ival(dat_ptr, (SLO*) &target_array);
  ret_ival(dat_ptr+1,&n);
  ret_ival(dat_ptr+2,&m);
  ret_ival(dat_ptr+3, (SLO*)&source_array);
  if(noterror()){
    pi=3.1415926535897932;
    c1=2*pi/n;
    s1=2*pi/m;
    for(p=0;p<n;p++)
      for (q=0; q<m; q++) {
        sum=0:
        for (i=0;i<n;i++)</pre>
          for(j=0;j<m;j++)
            sum+=(*(source array+i*m+j)*(cos(tmp=c1*p*i+s1*q*j)+sin(tmp)));
        *(target_array+p*m+q)=sum/n/m;
    ret dat->single=1;
    ret dat->type='I';
    ret dat->value.ival=(SLO) target array;
  return;
void func dhtpipe0 compare(const ULO *dat ptr, struct fastlisp data *ret dat) {
  SLO result=1,n,m;
  DFL *array0, *array1;
 ret ival(dat ptr, (SLO*) &array0);
 ret_ival(dat_ptr+1, (SLO*)&array1);
  ret_ival(dat_ptr+2,&n);
  ret_ival(dat_ptr+3,&m);
  if(noterror()){
    if((fabs(*array0-*array1)>1.e-10)
       | (fabs(*(array0+n*m-1)-*(array1+n*m-1))>1.e-10))
      result=0;
    ret dat->single=1;
    ret dat->type='I';
    ret dat->value.ival=result;
  return;
INSTRUCTION STRU INSTRUCTION SET[] ={
  {"DHTPIPEO_GENERATE",3,'I',(UCH*)"III", &func__dhtpipeO_generate},
                     4,'I',(UCH*)"IIII",&func_dhtpipe0_dht},
4,'I',(UCH*)"IIII",&func_dhtpipe0_idht},
  {"DHTPIPE0 DHT",
  {"DHTPIPEO IDHT",
  {"DHTPIPE0_COMPARE", 4,'I', (UCH*)"IIII",&func_dhtpipe0_compare}
};
const ULO INSTRUCTIONS=sizeof(INSTRUCTION SET)/sizeof(INSTRUCTION STRU);
```

After recompilation of the virtual machine the following trivial implementation of the function main() will work properly. Please notice two things:

- Some speculative SMP RISC architectures require aligned memory addresses for allocated float arrays in the shared memory pool.
- Access to the asynchronous heaps can be synchronized e.g. via some additional synchronization helper variables that create artificial dataflow dependencies enabling parallel function calls where possible:
  - every pointer variable "\_addr" has a corresponding synchronization helper variable "\_sync";
  - o an "\_addr" pointer variable to a read-only area can be passed directly to a function call;
  - o an "\_addr" pointer variable to a modified area is passed to a function call being dependent on the corresponding "\_sync" helper variable;
  - o after the function call is finished, both "\_sync" helper variables (for all pointers involved in the call) and "\_addr" pointer variables (only for pointers to the modified areas) are re-assigned.

```
(setq m (ival (accept "M-value of M*N-matrix: ")))
(setq n (ival (accept "N-value of M*N-matrix: ")))
(setq numb (ival (accept "How many input data packs: ")))
(setq arrays size (* (++ (* m n)) (setq floatlen (len (dump f2s 0.)))))
(for i 1 1 numb (progn # main pipeline loop
 (outf "Sequence %ld: " i)
 # 1. This is the way how we create an input array. #
 # 1.1. This is the way how we get address.
 (setq inp array addr (setq inp array addr
  (asyncheap create arrays size)))
 # 1.2. This is the way how we align the address.
     (optional: float might be misaligned on some architectures). #
 (setq inp array sync (& 0
  (setq inp array addr
    (+ inp array addr (- floatlen (iabs (% inp array addr floatlen)))))
 ))
 # 2. This is the way how we generate input sequence. #
 (setq inp_array_sync (& 0
  (setq inp array addr
   (dhtpipe0 generate (| inp array sync inp array addr) n m))
 ))
 # 3. This is the way how we create a DHT array. #
 # 3.1. This is the way how we get address.
 (setq dht array addr (setq dht array addr
  (asyncheap create arrays size)))
 # 3.2. This is the way how we align the address.
     (optional: float might be misaligned on some architectures). #
 (setq dht array sync (& 0
  (setq dht_array_addr
   (+ dht array addr (- floatlen (iabs (% dht array addr floatlen)))))
```

```
# 4. This is the way how we compute DHT. #
 (setq dht array sync (setq inp array sync (& 0
   (setq dht array add
    (dhtpipe0 dht (| dht array sync dht array addr) n m inp array addr))
 ))))
 # 5. This is the way how we create an IDHT array. #
 # 5.1. This is the way how we get address.
 (setq idht array addr (setq idht array addr
  (asyncheap create arrays size)))
 # 5.2. This is the way how we align the address.
      (optional: float might be misaligned on some architectures). #
 (setq idht_array_sync (& 0
  (setq idht array addr
    (+ idht array addr (- floatlen (iabs (% idht array addr floatlen)))))
 ))
 # 6. This is the way how we compute IDHT. #
 (setq idht array sync (setq dht array sync (& 0
   (setq idht array addr
    (dhtpipe0_idht (| idht_array_sync idht_array_addr) n m dht_array_addr))
 # 7. This is the way how we compare input sequence with #
    IDHT(DHT(input sequence)).
 (setq inp_array_sync (setq idht_array_sync (& 0
  (setq cmp res (dhtpipe0 compare inp array addr idht array addr n m))
 (outf " %s.\n" (if cmp_res "Ok" "Fail"))
 # 8. This is the way how we release memory. #
 (asyncheap delete ( inp array sync inp array addr ))
 (asyncheap_delete (| dht_array_sync dht_array_addr_))
 (asyncheap delete (| idht array sync idht array addr ))
  # "end progn" of main pipeline loop; "end for" of main pipeline loop
))
11/11
# "end progn" of main()
```

The above version of the application exploits a coarse-grain parallelism of the iterations of the main pipeline loop. In the next version of the same application the computation loops written in C are interleaved. This modification enables using a coarse-grain parallelism within each iteration of the main pipeline loop.

```
void func dhtpipel generate(const ULO *dat ptr, struct fastlisp data *ret dat) {
  SLO step,interleave,i,j,n,m;
  DFL *array;
  ret ival(dat ptr,(SLO*)&array);
  ret_ival(dat_ptr+1,&step);
  ret ival (dat ptr+2,&interleave);
  ret_ival(dat_ptr+3,&n);
  ret ival (dat ptr+4,&m);
  if (noterror()){
    for (i=step; i<n; i+=interleave)</pre>
      for (j=0; j<m; j++)
        *(array+i*m+j)=1.*rand()/RAND_MAX;
    ret dat->single=1;
    ret dat->type='I';
    ret dat->value.ival=0;
  return;
}
void func dhtpipe1 dht(const ULO *dat ptr, struct fastlisp data *ret dat) {
  SLO step,interleave,i,j,p,q,n,m;
  DFL *target array, *source array, pi, c1, s1, sum, tmp;
  ret ival(dat ptr,(SLO*)&target array);
  ret_ival (dat_ptr+1,&step);
  ret_ival (dat_ptr+2,&interleave);
  ret_ival(dat_ptr+3,&n);
  ret_ival(dat_ptr+4,&m);
  ret ival(dat ptr+5,(SLO*)&source array);
  if (noterror()) {
    pi=3.1415926535897932;
    c1=2*pi/n;
    s1=2*pi/m;
    for (p=step;p<n;p+=interleave)</pre>
      for (q=0;q<m;q++) {
        sum=0;
        for(i=0;i<n;i++)</pre>
          for(j=0;j<m;j++)
            sum+=(*(source array+i*m+j)*(cos(tmp=c1*p*i+s1*q*j)+sin(tmp)));
        *(target array+p*m+q)=sum;
    ret_dat->single=1;
    ret_dat->type='I';
    ret dat->value.ival=0;
  return;
}
```

```
void func dhtpipel idht(const ULO *dat ptr, struct fastlisp data *ret dat) {
  SLO step,interleave,i,j,p,q,n,m;
  DFL *target_array,*source_array,pi,c1,s1,sum,tmp;
  ret_ival(dat_ptr,(SLO*)&target_array);
  ret ival(dat ptr+1,&step);
  ret_ival (dat_ptr+2,&interleave);
  ret_ival(dat_ptr+3,&n);
  ret_ival(dat_ptr+4,&m);
  ret_ival (dat_ptr+5, (SLO*) &source_array);
  if (noterror()){
    pi=3.1415926535897932;
    c1=2*pi/n;
    s1=2*pi/m;
    for (p=step;p<n;p+=interleave)</pre>
      for (q=0;q<m;q++) {
        sum=0;
         for(i=0;i<n;i++)</pre>
           for(j=0;j<m;j++)
             sum+= (*(source_array+i*m+j)*(cos(tmp=c1*p*i+s1*q*j)+sin(tmp)));
         *(target array+p*m+q)=sum/n/m;
    ret dat->single=1;
    ret dat->type='I';
    ret_dat->value.ival=0;
  return:
INSTRUCTION STRU INSTRUCTION SET[] = {
  {"DHTPIPE1_GENERATE",5,'I', (UCH*)"IIIII", &func__dhtpipe1_generate},
  {"DHTPIPE1_DHT", 6,'I', (UCH*)"IIIIII",&func__dhtpipe1_dht},
{"DHTPIPE1_IDHT", 6,'I', (UCH*)"IIIIII",&func__dhtpipe1_idht},
const ULO INSTRUCTIONS=sizeof(INSTRUCTION SET)/sizeof(INSTRUCTION STRU);
```

In the function main() all interleaved functions are called in a way of the threaded loops:

```
# dhtpipe1.flp
# Pipeline calculation of the 2D nonseparative Hartley transform.
#
 Direct Hartley transform:
                     2Pi 2Pi
#
         N-1 \quad M-1
  H[p,q] = E \quad E \quad x[n,m] \quad cas \quad (---pn + ---qm), \quad p=0..N-1, \quad q=0..M-1.
#
         n=0 m=0
                            N
#
 Inverse Hartley transform:
  Hinv[p,q] = --- H[p,q].
(progn # main()
 (outf
  "Pipeline calculation of the 2D nonseparative Hartley transform.\n\n" 0)
 (setq m (ival (accept "M-value of M*N-matrix: ")))
 (setq n (ival (accept "N-value of M*N-matrix: ")))
 (setq numb (ival (accept "How many input data packs: ")))
 (setq arrays size (* (++ (* m n)) (setq floatlen (len (dump f2s 0.)))))
 (setq threads (if (< n (n cpuproc)) n (n cpuproc)))</pre>
 (for i 1 1 numb (progn # main pipeline loop
   (outf "Sequence %ld:" i)
   # 1. This is the way how we create an input array. #
   # 1.1. This is the way how we get address. #
   (setq inp_array_addr (setq inp_array_addr_
    (asyncheap create arrays size)))
   # 1.2. This is the way how we align the address. #
        (optional: float might be misaligned on some architectures). #
   (setq inp array sync (& 0
    (setq inp array addr
      (+ inp_array_addr (- floatlen (iabs (% inp_array_addr floatlen)))))
   ))
```

```
# 2. This is the way how we generate input sequence. #
(setq inp array addr (| inp array sync inp array addr))
(for thread 1 1 threads
 (setq inp_array_sync (+ inp_array_sync
   (dhtpipe1 generate inp array addr (-- thread) threads n m)))
(setq inp array addr (| inp array sync inp array addr))
# 3. This is the way how we create a DHT array. #
# 3.1. This is the way how we get address.
(setq dht array addr (setq dht array addr
 (asyncheap create arrays size)))
# 3.2. This is the way how we align the address.
    (optional: float might be misaligned on some architectures). #
(setq dht array sync (& 0
 (setq dht array addr
  (+ dht array addr (- floatlen (iabs (% dht array addr floatlen)))))
# 4. This is the way how we compute DHT. #
(setq dht_array_addr (| dht_array_sync dht_array_addr))
(for thread 1 1 threads
 (setq dht_array_sync (+ dht_array_sync
  (dhtpipel dht dht array addr (-- thread) threads n m inp array addr)))
(setq inp_array_sync dht_array_sync)
(setq dht_array_addr (| dht_array_sync dht_array_addr))
# 5. This is the way how we create an IDHT array. #
# 5.1. This is the way how we get address.
(setq idht array addr (setq idht array addr
 (asyncheap create arrays size)))
```

```
***
  # 5.2. This is the way how we align the address.
        (optional: float might be misaligned on some architectures). #
  ***
   (setq idht array sync (& 0
    (setq idht_array_addr
     (+ idht array addr (- floatlen (iabs (% idht array addr floatlen)))))
  ))
  # 6. This is the way how we compute IDHT. #
  (setq idht_array_addr (| idht_array_sync idht_array_addr))
   (for thread 1 1 threads
    (setq idht_array_sync (+ idht_array_sync (dhtpipel_idht
     idht array addr (-- thread) threads n m dht array addr)))
   (setq dht array sync idht array sync)
   (setq idht array addr (| idht array sync idht array addr))
  # 7. This is the way how we compare input sequence with #
      IDHT(DHT(input sequence)).
  (setq inp_array_sync (setq idht_array_sync (& 0
   (setq cmp_res (dhtpipe0_compare inp_array addr idht_array addr n m))
  )))
   (if cmp res
    (outf " Ok.\n" nil)
    (outf " Fail.\n" nil)
  # 8. This is the way how we release memory. #
  (asyncheap_delete (| inp_array_sync inp_array_addr_))
   (asyncheap delete ( | dht array sync dht array addr ))
   (asyncheap delete (| idht array sync idht array addr ))
 )) # "end proqn" of main pipeline loop; "end for" of main pipeline loop
) # "end progn" of main()
```

This page is intentionally left blank.

## Appendix C List of Target Deployments

The target deployments are listed for the following release of BMDFM:

• BMDFM v.5.9.9 R25 (Revision 2025), build 20250613.

Deployment	Build Details
x86_WindowsCygnus_32_gccV291	gcc version egcs-2.91.57 19980901 (egcs-1. 1 release) as [PE32 executable (console) I ntel 80386, for MS Windows] at systime Fri Jun 13 13:01:07 CEST 2025 on [CYGWIN NT-6 .1 WINDOWS7VM 20.1 (0.3/1/1) 1998-12-3 20: 39:18 i686]
x86_WindowsCygwin_32_gccV640	gcc version 6.4.0 (GCC) as [PE32 executable (console) Intel 80386 (stripped to exter nal PDB), for MS Windows] at systime Fri Jun 13 13:01:18 CEST 2025 on [CYGWIN_NT-6.1-WOW WINDOWS7VM 2.10.0(0.325/5/3) 2018-02-02 15:21 i686 Cygwin]
x86_WindowsUWIN_32_gccV295	gcc version 2.95.2 19991024 (release) as [ win32 386 executable] at systime Fri Jun 1 3 13:01:26 CEST 2025 on [UWIN-XP WINXPVM 3 .1-5.1 2600 i586]
x86_WindowsSFU-SUA_32_gccV33	gcc version 3.3 as [Windows NT PE format (EXE), dynamically linked executable Intel Posix-CUI] at systime Fri Jun 13 13:01:25 CEST 2025 on [Interix WINDOWS7VM 6.1 10.0. 7063.0 x86]
x86_Linux_32_gccV485	gcc version 4.8.5 20150623 (Red Hat 4.8.5-4) (GCC) as [ELF 32-bit LSB executable, In tel 80386, version 1 (SYSV), dynamically 1 inked (uses shared libs), for GNU/Linux 2.6.32, stripped] at systime Fri Jun 13 13:0 1:13 CEST 2025 on [Linux RedHatELS72VM 3.1 0.0-327.el7.x86_64 #1 SMP Thu Oct 29 17:29 :29 EDT 2015 x86_64]
x86_Linux_32_gccV1021	gcc version 10.2.1 20210110 (Debian 10.2.1 -6) as [ELF 32-bit LSB executable, Intel 8 0386, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3.2.0, stripped] at systime Fri Jun 13 13:01:15 C EST 2025 on [Linux Linux64core 5.10.0-6-am d64 #1 SMP Debian 5.10.28-1 (2021-04-09) x 86_64]

x86_Linux_32_clangV1101	Debian clang version 11.0.1-2 as [ELF 32-b it LSB executable, Intel 80386, version 1 (SYSV), dynamically linked (uses shared li bs), for GNU/Linux 3.2.0, stripped] at sys time Fri Jun 13 13:01:18 CEST 2025 on [Lin ux Linux64core 5.10.0-6-amd64 #1 SMP Debia n 5.10.28-1 (2021-04-09) x86_64]
x86_Linux_32_iccVxe2019u3	icc version 19.0.3.199 (gcc version 4.8.5 compatibility) Intel(R) C Intel(R) 64 Comp iler for applications running on Intel(R) 64, Version 19.0.3.199 Build 20190206 (Cop yright (C) 1985-2019 Intel Corporation. All rights reserved.) as [ELF 32-bit LSB exe cutable, Intel 80386, version 1 (SYSV), dy namically linked (uses shared libs), for G NU/Linux 2.6.32, stripped] at systime Fri Jun 13 13:01:17 CEST 2025 on [Linux RedHat ELS72VM 3.10.0-327.el7.x86_64 #1 SMP Thu O ct 29 17:29:29 EDT 2015 x86_64]
x86_FreeBSD_32_gccV920	gcc version 9.2.0 (FreeBSD Ports Collectio n) as [ELF 32-bit LSB executable, Intel 80 386, version 1 (FreeBSD), dynamically link ed (uses shared libs), for FreeBSD 12.1, F reeBSD-style, stripped] at systime Fri Jun 13 13:01:14 CEST 2025 on [FreeBSD FreeBSD 12VM 12.1-RELEASE FreeBSD 12.1-RELEASE r35 4233 GENERIC amd64]
x86_FreeBSD_32_clangV801	FreeBSD clang version 8.0.1 (tags/RELEASE_801/final 366581) (based on LLVM 8.0.1) as [ELF 32-bit LSB executable, Intel 80386, version 1 (FreeBSD), dynamically linked (u ses shared libs), for FreeBSD 12.1, FreeBSD-style, stripped] at systime Fri Jun 13 1 3:01:12 CEST 2025 on [FreeBSD FreeBSD12VM 12.1-RELEASE FreeBSD 12.1-RELEASE r354233 GENERIC amd64]
x86_OpenBSD_32_gccV830	gcc version 8.3.0 (GCC) as [ELF 32-bit LSB executable, Intel 80386, version 1, dynam ically linked (uses shared libs), for Open BSD 6.6, stripped] at systime Fri Jun 13 1 3:01:39 CEST 2025 on [OpenBSD OpenBSD66VM. ESXsrv.net 6.6 (GENERIC.MP) #304: Sat Oct 12 11:18:21 MDT 2019 deraadt@i386.openbsd.org:/usr/src/sys/arch/i386/compile/GENERIC.MP i386]
x86_OpenBSD_32_clangV801	clang version 8.0.1 (tags/RELEASE_801/fina 1) (based on LLVM 8.0.1) as [ELF 32-bit LS B executable, Intel 80386, version 1, dyna mically linked (uses shared libs), for Ope nBSD 6.6, stripped] at systime Fri Jun 13 13:01:33 CEST 2025 on [OpenBSD OpenBSD66VM .ESXsrv.net 6.6 (GENERIC.MP) #304: Sat Oct 12 11:18:21 MDT 2019 deraadt@i386.openbsd .org:/usr/src/sys/arch/i386/compile/GENERI C.MP i386]

x86_NetBSD_32_gccV830	gcc version 8.3.0 (GCC) as [ELF 32-bit LSB executable, Intel 80386, version 1 (SYSV), dynamically linked (uses shared libs), f or NetBSD 8.1, stripped] at systime Fri Ju n 13 13:01:15 CEST 2025 on [NetBSD NetBSD8 1VM.ESXsrv.net 8.1 NetBSD 8.1 (GENERIC) #0: Fri May 31 08:43:59 UTC 2019 mkrepro@mkrepro.NetBSD.org:/usr/src/sys/arch/amd64/compile/GENERIC amd64]
x86_NetBSD_32_clangV900	clang version 9.0.0 (tags/RELEASE_900/fina 1) (based on LLVM 9.0.0) as [ELF 32-bit LS B executable, Intel 80386, version 1 (SYSV), dynamically linked (uses shared libs), for NetBSD 8.1, stripped] at systime Fri J un 13 13:01:20 CEST 2025 on [NetBSD NetBSD 81VM.ESXsrv.net 8.1 NetBSD 8.1 (GENERIC) # 0: Fri May 31 08:43:59 UTC 2019 mkrepro@mk repro.NetBSD.org:/usr/src/sys/arch/amd64/c ompile/GENERIC amd64]
x86_MacOS_32_clangV702	Apple LLVM version 7.0.2 (clang-700.1.81) as [Mach-O executable i386] at systime Fri Jun 13 13:01:16 CEST 2025 on [Darwin MacI ntel 14.5.0 Darwin Kernel Version 14.5.0: Tue Apr 11 16:12:42 PDT 2017; root:xnu-278 2.50.9.2.3~1/RELEASE_X86_64 x86_64]
x86_SunOS_32_ccV510	cc: Sun C 5.10 SunOS_i386 Patch 142363-09 2012/08/15 as [ELF 32-bit LSB executable 8 0386 Version 1 [FPU], dynamically linked, stripped] at systime Fri Jun 13 13:01:18 C EST 2025 on [SunOS SunOSx86 5.11 11.1 i86p c i386 Solaris]
x86_SunOS_32_gccV343	gcc version 3.4.3 (csl-sol210-3_4-branch+s ol_rpath) as [ELF 32-bit LSB executable 80 386 Version 1, dynamically linked, strippe d] at systime Fri Jun 13 13:01:02 CEST 202 5 on [SunOS SunOSx86 5.11 11.1 i86pc i386 Solaris]
x86_UnixwareSCO_32_ccsV42	Optimizing C Compilation System (CCS) 4.2 05/13/08 (uw714mp4.bl3h) as [ELF 32-bit LS B executable 80386, dynamically linked, st ripped, no debug (SVR5 ABI)] at systime Fr i Jun 13 13:12:06 CET 2025 on [UnixWare un ixware 5 7.1.4 i386 x86at SCO UNIX_SVR5]
x86_UnixwareSCO_32_gccV295	gcc version 2.95.2 19991024 (release) as [ ELF 32-bit LSB executable 80386, dynamical ly linked, stripped, no debug (SVR5 ABI)] at systime Fri Jun 13 13:12:54 CET 2025 on [UnixWare unixware 5 7.1.4 i386 x86at SCO UNIX_SVR5]
x86_Minix_32_clangV36	clang version 3.6 (branches/release_36 237 755) [i386-elf32-minix] as [ELF 32-bit LSB executable (Minix), Intel 80386, version 1 (SYSV), dynamically linked, stripped] at systime Fri Jun 13 13:01:43 CEST 2025 on [Minix MinixVM.ESXsrv.net 3.4.0 (GENERIC) i386]

x86_Android_32_gccV49x	gcc version 4.9.x 20150123 (prerelease) (G CC) (cross-toolchain) (m32 i686-linux-andr oid -D_ANDROID_API_=26) as [ELF 32-bit L SB executable, Intel 80386, version 1 (SYS V), dynamically linked (uses shared libs), stripped] at systime Fri Jun 13 13:01:17 CEST 2025 on [Linux Linux64core 5.10.0-6-a md64 #1 SMP Debian 5.10.28-1 (2021-04-09) x86_64 GNU/Linux]	
x86_Android_32_clangV503	clang version 5.0.300080 (based on LLVM 5.0.300080) (cross-toolchain) (m32 i686-linu x-android -D_ANDROID_API_=26) as [ELF 32 -bit LSB executable, Intel 80386, version 1 (SYSV), dynamically linked (uses shared libs), stripped] at systime Fri Jun 13 13:01:14 CEST 2025 on [Linux Linux64core 5.10.0-6-amd64 #1 SMP Debian 5.10.28-1 (2021-0 4-09) x86_64 GNU/Linux]	
x86-64_WindowsCygwin_64_gccV640	gcc version 6.4.0 (GCC) as [PE32+ executab le (console) x86-64 (stripped to external PDB), for MS Windows] at systime Fri Jun 1 3 13:01:18 CEST 2025 on [CYGWIN NT-6.1 WIN DOWS7VM 2.10.0(0.325/5/3) 2018-02-02 15:16 x86_64 Cygwin]	
x86-64_Linux_64_gccV485	gcc version 4.8.5 20150623 (Red Hat 4.8.5-4) (GCC) as [ELF 64-bit LSB executable, x8 6-64, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 2.6.32, stripped] at systime Fri Jun 13 13:01:10 CEST 2025 on [Linux RedHatELS72VM 3.10.0-3 27.el7.x86_64 #1 SMP Thu Oct 29 17:29:29 EDT 2015 x86_64]	
x86-64_Linux_64_gccV1021	gcc version 10.2.1 20210110 (Debian 10.2.1 -6) as [ELF 64-bit LSB executable, x86-64, version 1 (SYSV), dynamically linked (use s shared libs), for GNU/Linux 3.2.0, strip ped] at systime Fri Jun 13 13:01:19 CEST 2 025 on [Linux Linux64core 5.10.0-6-amd64 # 1 SMP Debian 5.10.28-1 (2021-04-09) x86_64 ]	
x86-64_Linux_64_clangV1101	Debian clang version 11.0.1-2 as [ELF 64-b it LSB executable, x86-64, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3.2.0, stripped] at systime Fri Jun 13 13:01:24 CEST 2025 on [Linux Linux64core 5.10.0-6-amd64 #1 SMP Debian 5.1 0.28-1 (2021-04-09) x86_64]	
x86-64_Linux_64_iccVxe2019u3	icc version 19.0.3.199 (gcc version 4.8.5 compatibility) Intel(R) C Intel(R) 64 Comp iler for applications running on Intel(R) 64, Version 19.0.3.199 Build 20190206 (Cop yright (C) 1985-2019 Intel Corporation. All rights reserved.) as [ELF 64-bit LSB exe cutable, x86-64, version 1 (SYSV), dynamic ally linked (uses shared libs), for GNU/Linux 2.6.32, stripped] at systime Fri Jun 1 3 13:01:17 CEST 2025 on [Linux RedHatELS72 VM 3.10.0-327.el7.x86_64 #1 SMP Thu Oct 29 17:29:29 EDT 2015 x86_64]	

	L
x86-64_FreeBSD_64_gccV920	gcc version 9.2.0 (FreeBSD Ports Collection) as [ELF 64-bit LSB executable, x86-64, version 1 (FreeBSD), dynamically linked (uses shared libs), for FreeBSD 12.1, FreeBSD-style, stripped] at systime Fri Jun 13 13:01:14 CEST 2025 on [FreeBSD FreeBSD12VM 12.1-RELEASE FreeBSD 12.1-RELEASE r354233 GENERIC amd64]
x86-64_FreeBSD_64_clangV801	FreeBSD clang version 8.0.1 (tags/RELEASE_801/final 366581) (based on LLVM 8.0.1) as [ELF 64-bit LSB executable, x86-64, versi on 1 (FreeBSD), dynamically linked (uses s hared libs), for FreeBSD 12.1, FreeBSD-sty le, stripped] at systime Fri Jun 13 13:01: 13 CEST 2025 on [FreeBSD FreeBSD12VM 12.1-RELEASE FreeBSD 12.1-RELEASE r354233 GENER IC amd64]
x86-64_OpenBSD_64_gccV830	gcc version 8.3.0 (GCC) as [ELF 64-bit LSB executable, x86-64, version 1, dynamicall y linked (uses shared libs), for OpenBSD 6.6, stripped] at systime Fri Jun 13 13:01: 17 CEST 2025 on [OpenBSD OpenBSD66VM.ESXsr v.net 6.6 (GENERIC.MP) #372: Sat Oct 12 10:56:27 MDT 2019 deraadt@amd64.openbsd.org:/usr/src/sys/arch/amd64/compile/GENERIC.MP amd64]
x86-64_OpenBSD_64_clangV801	clang version 8.0.1 (tags/RELEASE_801/fina 1) (based on LLVM 8.0.1) as [ELF 64-bit LS B executable, x86-64, version 1, dynamical ly linked (uses shared libs), for OpenBSD 6.6, stripped] at systime Fri Jun 13 13:01 :24 CEST 2025 on [OpenBSD OpenBSD66VM.ESXs rv.net 6.6 (GENERIC.MP) #372: Sat Oct 12 1 0:56:27 MDT 2019 deraadt@amd64.openbsd.org :/usr/src/sys/arch/amd64/compile/GENERIC.M P amd64]
x86-64_NetBSD_64_gccV830	gcc version 8.3.0 (GCC) as [ELF 64-bit LSB executable, x86-64, version 1 (SYSV), dyn amically linked (uses shared libs), for Ne tBSD 8.1, stripped] at systime Fri Jun 13 13:01:13 CEST 2025 on [NetBSD NetBSD81VM.E SXsrv.net 8.1 NetBSD 8.1 (GENERIC) #0: Fri May 31 08:43:59 UTC 2019 mkrepro@mkrepro. NetBSD.org:/usr/src/sys/arch/amd64/compile /GENERIC amd64]
x86-64_NetBSD_64_clangV900	clang version 9.0.0 (tags/RELEASE_900/fina 1) (based on LLVM 9.0.0) as [ELF 64-bit LS B executable, x86-64, version 1 (SYSV), dy namically linked (uses shared libs), for N etBSD 8.1, stripped] at systime Fri Jun 13 13:01:21 CEST 2025 on [NetBSD NetBSD81VM. ESXsrv.net 8.1 NetBSD 8.1 (GENERIC) #0: Fr i May 31 08:43:59 UTC 2019 mkrepro@mkrepro .NetBSD.org:/usr/src/sys/arch/amd64/compil e/GENERIC amd64]

x86-64_MacOS_64_clangV702	Apple LLVM version 7.0.2 (clang-700.1.81) as [Mach-0 64-bit executable x86_64] at sy stime Fri Jun 13 13:01:11 CEST 2025 on [Darwin MacIntel 14.5.0 Darwin Kernel Version 14.5.0: Tue Apr 11 16:12:42 PDT 2017; root:xnu-2782.50.9.2.3~1/RELEASE_X86_64 x86_64]
x86-64_MacOS_64_clangV1200	Apple clang version 12.0.0 (clang-1200.0.3 2.29) (Target: x86_64-apple-darwin20.0.0) as [Mach-0 64-bit executable x86_64] at sy stime Fri Jun 13 13:01:45 CEST 2025 on [Darwin MacOS11_BigSur 20.0.0 Darwin Kernel Version 20.0.0: Thu Jul 30 22:49:28 PDT 202 0; root:xnu-7195.0.0.141.5~1/RELEASE_X86_6 4 x86_64]
x86-64_SunOS_64_ccV510	cc: Sun C 5.10 SunOS_i386 Patch 142363-09 2012/08/15 as [ELF 64-bit LSB executable A MD64 Version 1 [SSE2 SSE FXSR CMOV FPU], d ynamically linked, stripped] at systime Fr i Jun 13 13:01:17 CEST 2025 on [SunOS SunO Sx86 5.11 11.1 i86pc i386 Solaris]
x86-64_SunOS_64_gccV343	gcc version 3.4.3 (csl-sol210-3_4-branch+s ol_rpath) as [ELF 64-bit LSB executable AM D64 Version 1, dynamically linked, strippe d] at systime Fri Jun 13 13:01:02 CEST 202 5 on [SunOS SunOSx86 5.11 11.1 i86pc i386 Solaris]
x86-64_Android_64_gccV49x	gcc version 4.9.x 20150123 (prerelease) (G CC) (cross-toolchain) (m64 x86_64-linux-an droid -D_ANDROID_API_=26) as [ELF 64-bit LSB executable, x86-64, version 1 (SYSV), dynamically linked (uses shared libs), st ripped] at systime Fri Jun 13 13:01:18 CES T 2025 on [Linux Linux64core 5.10.0-6-amd6 4 #1 SMP Debian 5.10.28-1 (2021-04-09) x86_64 GNU/Linux]
x86-64_Android_64_clangV503	clang version 5.0.300080 (based on LLVM 5.0.300080) (cross-toolchain) (m64 x86_64-linux-android -D_ANDROID_API_=26) as [ELF 64-bit LSB executable, x86-64, version 1 (SYSV), dynamically linked (uses shared libs), stripped] at systime Fri Jun 13 13:01: 17 CEST 2025 on [Linux Linux64core 5.10.0-6-amd64 #1 SMP Debian 5.10.28-1 (2021-04-09) x86_64 GNU/Linux]
VAX_Ultrix_32_gccV272	gcc version 2.7.2 as [VAX demand paged pur e executable] at systime Fri Jun 13 13:07: 15 MET 2025 on [ULTRIX DECultrixVAX 4.5 0 VAX]
Alpha_Tru64OSF1_64_ccV65303	Compaq C V6.5-303 (dtk) on HP Tru64 UNIX V 5.1B (Rev. 2650) Compiler Driver V6.5-302 (dtk) cc Driver as [COFF format alpha dyna mically linked, demand paged executable or object module stripped - version 3.14-2] at systime Fri Jun 13 13:01:28 CEST 2025 on [OSF1 DECtru64alpha V5.1 2650 alpha]

Alpha_Tru640SF1_64_gccV423	gcc version 4.2.3 (alpha-dec-osf5.1b) as [ COFF format alpha dynamically linked, dema nd paged executable or object module strip ped - version 3.14-2] at systime Fri Jun 1 3 13:01:47 CEST 2025 on [OSFI DECtru64alph a V5.1 2650 alpha]
Alpha_Linux_64_gccV424	gcc version 4.2.4 (Debian 4.2.4-6) as [ELF 64-bit LSB executable, Alpha (unofficial), version 1 (SYSV), dynamically linked (us es shared libs), for GNU/Linux 2.6.9, stri pped] at systime Fri Jun 13 13:01:45 CEST 2025 on [Linux AlphaLinux 2.6.26-2-alpha-g eneric #1 Sun Mar 4 21:08:03 UTC 2012 alph a]
Alpha_Linux_64_gccV1021	gcc version 10.2.1 20210110 (Debian 10.2.1 -6) as [ELF 64-bit LSB executable, Alpha (unofficial), version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3.2.0, stripped] at systime Fri Jun 13 13: 03:41 CEST 2025 on [Linux AlphaServer 5.10 .0-8-alpha-smp #1 SMP Debian 5.10.46-1 (20 21-06-24) alpha]
Alpha_FreeBSD_64_gccV346	gcc version 3.4.6 [FreeBSD] 20060305 (Configured with: FreeBSD/alpha system compiler) as [ELF 64-bit LSB executable, Alpha (un official), version 1 (FreeBSD), for FreeBSD 6.4, dynamically linked (uses shared libs), FreeBSD-style, stripped] at systime Fri Jun 13 13:01:59 CEST 2025 on [FreeBSD AlphaBSD 6.4-RELEASE FreeBSD 6.4-RELEASE #0: Sun Nov 30 07:00:37 UTC 2008 root@ds10.wb net:/usr/obj/usr/src/sys/GENERIC alpha]
Alpha_OpenBSD_64_gccV421	gcc version 4.2.1 20070719 (OpenBSD/alpha system compiler) as [ELF 64-bit LSB execut able, Alpha (unofficial), version 1, dynam ically linked (uses shared libs), for Open BSD 6.6, stripped] at systime Fri Jun 13 1 3:02:22 CEST 2025 on [OpenBSD OpenBSD66alp ha.ALPHApurgatory.net 6.6 (GENERIC.MP) #74 1: Sat Oct 12 05:34:08 MDT 2019 deraadt@al pha.openbsd.org:/usr/src/sys/arch/alpha/compile/GENERIC.MP alpha]
IA-64_HP-UX_32_ccVa0628	cc: HP C/aC++ B3910B A.06.28 [Nov 21 2013] as [ELF-32 executable object file - IA64] at systime Fri Jun 13 13:04:18 MESZ 2025 on [HP-UX IA64hpux B.11.31 U ia64 28971902 01]
IA-64_HP-UX_32_gccV472	gcc version 4.7.2 (GCC) (ia64-hp-hpux11.31) as [ELF-32 executable object file - IA64] at systime Fri Jun 13 13:01:21 MESZ 2025 on [HP-UX IA64hpux B.11.31 U ia64 2897190 201]
IA-64_HP-UX_64_ccVa0628	cc: HP C/aC++ B3910B A.06.28 [Nov 21 2013] as [ELF-64 executable object file - IA64] at systime Fri Jun 13 13:04:21 MESZ 2025 on [HP-UX IA64hpux B.11.31 U ia64 28971902 01]

	<b>+</b>
IA-64_HP-UX_64_gccV472	gcc version 4.7.2 (GCC) (ia64-hp-hpux11.31 ) as [ELF-64 executable object file - IA64 ] at systime Fri Jun 13 13:02:30 MESZ 2025 on [HP-UX IA64hpux B.11.31 U ia64 2897190 201]
IA-64_Linux_64_gccV412	gcc version 4.1.2 20080704 (Red Hat 4.1.2-50) as [ELF 64-bit LSB executable, IA-64, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 2.6.9, stripp ed] at systime Fri Jun 13 13:01:24 CEST 20 25 on [Linux LinuxIA64 2.6.18-238.el5 #1 S MP Sun Dec 19 14:23:48 EST 2010 ia64]
IA-64_Linux_64_gccV463	gcc version 4.6.3 (Debian 4.6.3-14) as [EL F 64-bit LSB executable, IA-64, version 1 (SYSV), dynamically linked (uses shared li bs), for GNU/Linux 2.6.26, stripped] at sy stime Fri Jun 13 13:02:16 CEST 2025 on [Li nux IA64-Linux 2.6.32-5-mckinley #1 SMP Tu e May 13 19:10:46 UTC 2014 ia64]
IA-64_Linux_64_gccV1021	gcc version 10.2.1 20210110 (Debian 10.2.1 -6+b1) as [ELF 64-bit LSB executable, IA-6 4, version 1 (SYSV), dynamically linked (u ses shared libs), for GNU/Linux 3.2.18, st ripped] at systime Fri Jun 13 13:02:04 CES T 2025 on [Linux SR870BN4-Linux 5.10.0-8-m ckinley #1 SMP Debian 5.10.46-1 (2021-06-2 4) ia64]
IA-64_FreeBSD_64_gccV421	gcc version 4.2.1 20070831 patched [FreeBS D] (Configured with: FreeBSD/ia64 system c ompiler) as [ELF 64-bit LSB executable, IA -64, version 1 (FreeBSD), dynamically link ed (uses shared libs), for FreeBSD 10.3, s tripped] at systime Fri Jun 13 13:01:45 CE ST 2025 on [FreeBSD ItaniumBSD 10.3-RELEAS E FreeBSD 10.3-RELEASE #0 r297264: Fri Mar 25 04:43:22 UTC 2016 root@releng1.nyi.fre ebsd.org:/usr/obj/ia64.ia64/usr/src/sys/GE NERIC ia64]
XeonPhiMIC_Linux_64_iccVxe2017u5	icc version 17.0.5 (gcc version 4.8.5 comp atibility) Intel(R) C Intel(R) 64 Compiler for applications running on Intel(R) 64, Version 17.0.5.239 Build 20170817 (Copyrig ht (C) 1985-2017 Intel Corporation. All rights reserved.) as [ELF 64-bit LSB executa ble, Intel K10M, version 1 (SYSV), dynamic ally linked (uses shared libs), for GNU/Linux 2.6.32, stripped] at systime Fri Jun 1 3 13:01:26 CEST 2025 on [Linux RedHatELS72 VM 3.10.0-327.el7.x86_64 #1 SMP Thu Oct 29 17:29:29 EDT 2015 x86_64]
XeonPhiMIC_Linux_64_gccV470	gcc version 4.7.0 20110509 (experimental) 4.7.0 (GCC) (cross-toolchain) as [ELF 64-b it LSB executable, Intel K10M, version 1 (SYSV), dynamically linked (uses shared lib s), for GNU/Linux 2.6.32, stripped] at sys time Fri Jun 13 13:01:15 CEST 2025 on [Lin ux RedHatELS72VM 3.10.0-327.el7.x86_64 #1 SMP Thu Oct 29 17:29:29 EDT 2015 x86_64]

	<b>+</b>
MCSTelbrus_Linux_32_1ccV120	lcc:1.20.17:Mar-3-2016:e2k-generic-linux (gcc version 4.4.0 compatible) as [ELF 32-b it LSB executable, MCST Elbrus, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 2.6.33, stripped] at systime Fri Jun 13 14:04:23 MSK 2025 on [Linux debian4babayan-64 2.6.33-elbrus.033.3.4 2 #1 SMP Thu Apr 23 22:28:28 MSK 2015 e2k]
MCSTelbrus_Linux_32_lccV125	<pre>lcc:1.25.14:Feb-13-2021:e2k-v4-linux (gcc version 7.3.0 compatible) as [ELF 32-bit L SB executable, MCST Elbrus, version 1 (SYS V), dynamically linked (uses shared libs), for GNU/Linux 2.6.33, stripped] at systim e Fri Jun 13 14:07:11 MSK 2025 on [Linux c hassis0CF-babayan-elbrus804 5.4.0-1.9-e8c #1 SMP Thu Oct 29 07:34:25 GMT 2020 e2k E8 C]</pre>
MCSTelbrus_Linux_64_lccV120	lcc:1.20.17:Mar-3-2016:e2k-generic-linux (gcc version 4.4.0 compatible) as [ELF 64-b it LSB executable, MCST Elbrus, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 2.6.33, stripped] at systime Fri Jun 13 14:03:27 MSK 2025 on [Linux debian4babayan-64 2.6.33-elbrus.033.3.4 2 #1 SMP Thu Apr 23 22:28:28 MSK 2015 e2k]
MCSTelbrus_Linux_64_lccV125	<pre>lcc:1.25.14:Feb-13-2021:e2k-v4-linux (gcc version 7.3.0 compatible) as [ELF 64-bit L SB executable, MCST Elbrus, version 1 (SYS V), dynamically linked (uses shared libs), for GNU/Linux 2.6.33, stripped] at systim e Fri Jun 13 14:07:26 MSK 2025 on [Linux c hassis0CF-babayan-elbrus804 5.4.0-1.9-e8c #1 SMP Thu Oct 29 07:34:25 GMT 2020 e2k E8 C]</pre>
PA-RISC_HP-UX_32_ccVc0370	HP ANSI C / C++ B3910B C.03.70 (HP92453-01 B.11.11.16 HP C Compiler) as [PA-RISC1.1 shared executable dynamically linked] at s ystime Fri Jun 13 13:02:04 METDST 2025 on [HP-UX c8k-HPUX B.11.23 U 9000/785 4042425 048]
PA-RISC_HP-UX_32_gccV471	gcc version 4.7.1 (GCC) (hppa1.1-hp-hpux11 .11) as [PA-RISC1.1 shared executable dyna mically linked] at systime Fri Jun 13 13:0 2:08 METDST 2025 on [HP-UX c8k-HPUX B.11.2 3 U 9000/785 4042425048]
PA-RISC_HP-UX_64_ccVc0370	HP ANSI C / C++ B3910B C.03.70 (HP92453-01 B.11.11.16 HP C Compiler) as [ELF-64 exec utable object file - PA-RISC 2.0 (LP64) / HPPA64 (PA-RISC2.0W)] at systime Fri Jun 1 3 13:02:01 METDST 2025 on [HP-UX c8k-HPUX B.11.23 U 9000/785 4042425048]
PA-RISC_HP-UX_64_gccV471	gcc version 4.7.1 (GCC) (hppa64-hp-hpux11. 11) as [ELF-64 executable object file - PA -RISC 2.0 (LP64) / HPPA64 (PA-RISC2.0W)] a t systime Fri Jun 13 13:02:00 METDST 2025 on [HP-UX c8k-HPUX B.11.23 U 9000/785 4042 425048]

PA-RISC_Linux_32_gccV492	gcc version 4.9.2 (Debian 4.9.2-10+b2) as [ELF 32-bit MSB executable, PA-RISC, versi on 1 (GNU/Linux), dynamically linked (uses shared libs), for GNU/Linux 2.6.32, strip ped] at systime Fri Jun 13 13:02:00 CEST 2 025 on [Linux c8k-Linux 3.16.0-4-parisc64-smp #1 SMP Debian 3.16.7-ckt4-3 (2015-02-0 3) parisc64]
PA-RISC_Linux_32_gccV1021	gcc version 10.2.1 20210110 (Debian 10.2.1 -6) as [ELF 32-bit MSB executable, PA-RISC, version 1 (GNU/Linux), dynamically linked (uses shared libs), for GNU/Linux 3.2.0, stripped] at systime Fri Jun 13 13:02:26 CEST 2025 on [Linux c8k-Linux 5.10.0-8-parisc64 #1 SMP Debian 5.10.46-1 (2021-06-24) parisc64]
SPARC_SunOS_32_ccV510	cc: Sun C 5.10 SunOS_sparc Patch 141861-09 2012/08/15 as [ELF 32-bit MSB executable SPARC32PLUS Version 1, V8+ Required, dynam ically linked, stripped] at systime Fri Ju n 13 13:02:33 CEST 2025 on [SunOS SunOS_U] tra45 5.10 Generic_147147-26 sun4u sparc]
SPARC_SunOS_32_gccV343	gcc version 3.4.3 (csl-sol210-3_4-branch+s ol_rpath) as [ELF 32-bit MSB executable SP ARC Version 1, dynamically linked, strippe d] at systime Fri Jun 13 13:01:09 CEST 202 5 on [SunOS SunOS_Ultra45 5.10 Generic_147 147-26 sun4u sparc]
SPARC_SunOS_64_ccV510	cc: Sun C 5.10 SunOS_sparc Patch 141861-09 2012/08/15 as [ELF 64-bit MSB executable SPARCV9 Version 1, dynamically linked, stripped] at systime Fri Jun 13 13:02:31 CEST 2025 on [SunOS SunOS_Ultra45 5.10 Generic 147147-26 sun4u sparc]
SPARC_SunOS_64_gccV343	gcc version 3.4.3 (csl-sol210-3_4-branch+s ol_rpath) as [ELF 64-bit MSB executable SP ARCV9 Version 1, dynamically linked, strip ped] at systime Fri Jun 13 13:01:08 CEST 2 025 on [SunOS SunOS_Ultra45 5.10 Generic_1 47147-26 sun4u sparc]
SPARC_Linux_32_gccV1021	gcc version 10.2.1 20210110 (Debian 10.2.1 -6) as [ELF 32-bit MSB executable, SPARC32 PLUS, V8+ Required, total store ordering, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3.2.0, stripp ed] at systime Fri Jun 13 13:01:28 CEST 20 25 on [Linux LinuxSPARC64 5.10.0-8-sparc64 -smp #1 SMP Debian 5.10.46-1 (2021-06-24) sparc64]
SPARC_Linux_32_clangV1101	Debian clang version 11.0.1-2 as [ELF 32-b it MSB executable, SPARC32PLUS, V8+ Requir ed, total store ordering, version 1 (SYSV), dynamically linked (uses shared libs), f or GNU/Linux 3.2.0, stripped] at systime F ri Jun 13 13:01:28 CEST 2025 on [Linux Lin uxSPARC64 5.10.0-8-sparc64-smp #1 SMP Debi an 5.10.46-1 (2021-06-24) sparc64]

SPARC_Linux_64_gccV1021	gcc version 10.2.1 20210110 (Debian 10.2.1 -6) as [ELF 64-bit MSB executable, SPARC V 9, relaxed memory ordering, version 1 (SYS V), dynamically linked (uses shared libs), for GNU/Linux 3.2.0, stripped] at systime Fri Jun 13 13:02:57 CEST 2025 on [Linux L inuxSPARC64 5.10.0-8-sparc64-smp #1 SMP De bian 5.10.46-1 (2021-06-24) sparc64]
SPARC_Linux_64_clangV1101	Debian clang version 11.0.1-2 as [ELF 64-b it MSB executable, SPARC V9, relaxed memor y ordering, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3 .2.0, stripped] at systime Fri Jun 13 13:0 3:49 CEST 2025 on [Linux LinuxSPARC64 5.10 .0-8-sparc64-smp #1 SMP Debian 5.10.46-1 (2021-06-24) sparc64]
SPARC_FreeBSD_64_gccV421	gcc version 4.2.1 20070831 patched [FreeBS D] (Configured with: FreeBSD/sparc64 syste m compiler) as [ELF 64-bit MSB executable, SPARC V9, relaxed memory ordering, versio n 1 (FreeBSD), dynamically linked, FreeBSD-style, for FreeBSD 12.1, stripped] at sys time Fri Jun 13 13:05:34 CEST 2025 on [FreeBSD SparcBSD 12.1-RELEASE FreeBSD 12.1-RELEASE r354233 GENERIC sparc64]
SPARC_OpenBSD_64_gccV830	gcc version 8.3.0 (GCC) as [ELF 64-bit MSB executable, SPARC V9, version 1, dynamica lly linked (uses shared libs), for OpenBSD 6.6, stripped] at systime Fri Jun 13 13:1 0:12 CEST 2025 on [OpenBSD OpenBSD66VM.ESX srv.net 6.6 (GENERIC.MP) #86: Sat Oct 12 0 9:59:04 MDT 2019 deraadt@sparc64.openbsd.org:/usr/src/sys/arch/sparc64/compile/GENER IC.MP sparc64]
SPARC_OpenBSD_64_clangV801	clang version 8.0.1 (tags/RELEASE_801/fina 1) (based on LLVM 8.0.1) as [ELF 64-bit MS B executable, SPARC V9, version 1, dynamic ally linked (uses shared libs), for OpenBS D 6.6, stripped] at systime Fri Jun 13 13: 07:57 CEST 2025 on [OpenBSD OpenBSD66VM.ES Xsrv.net 6.6 (GENERIC.MP) #86: Sat Oct 12 09:59:04 MDT 2019 deraadt@sparc64.openbsd. org:/usr/src/sys/arch/sparc64/compile/GENE RIC.MP sparc64]
MIPS_IRIX_32_ccV744m	MIPSpro Compilers: Version 7.4.4m as [ELF N32 MSB mips-4 dynamic executable MIPS - v ersion 1] at systime Fri Jun 13 13:02:11 M ET DST 2025 on [IRIX64 SGImipsIRIX 6.5 072 02013 IP35]
MIPS_IRIX_32_gccV471	gcc version 4.7.1 (GCC) (mips-sgi-irix6.5) as [ELF N32 MSB mips-4 dynamic executable MIPS - version 1] at systime Fri Jun 13 1 3:01:42 MET DST 2025 on [IRIX64 SGImipsIRI X 6.5 07202013 IP35]
MIPS_IRIX_32_gccV471_TLS	gcc version 4.7.1 (GCC) (mips-sgi-irix6.5) as [ELF N32 MSB mips-4 dynamic executable MIPS - version 1] at systime Fri Jun 13 1 3:01:41 MET DST 2025 on [IRIX64 SGImipsIRI X 6.5 07202013 IP35]

	<del> </del>
MIPS_IRIX_64_ccV744m	MIPSpro Compilers: Version 7.4.4m as [ELF 64-bit MSB mips-4 dynamic executable MIPS - version 1] at systime Fri Jun 13 13:02:1 1 MET DST 2025 on [IRIX64 SGImipsIRIX 6.5 07202013 IP35]
MIPS_IRIX_64_gccV471	gcc version 4.7.1 (GCC) (mips-sgi-irix6.5) as [ELF 64-bit MSB mips-4 dynamic executa ble MIPS - version 1] at systime Fri Jun 1 3 13:03:49 MET DST 2025 on [IRIX64 SGImips IRIX 6.5 07202013 IP35]
MIPS_IRIX_64_gccV471_TLS	gcc version 4.7.1 (GCC) (mips-sgi-irix6.5) as [ELF 64-bit MSB mips-4 dynamic executa ble MIPS - version 1] at systime Fri Jun 1 3 13:03:50 MET DST 2025 on [IRIX64 SGImips IRIX 6.5 07202013 IP35]
MIPS_Linux_32_gccV930	gcc version 9.3.0 (GCC) (cross-toolchain) as [ELF 32-bit MSB executable, MIPS, MIPS-I version 1 (SYSV), dynamically linked (us es shared libs), for GNU/Linux 3.2.0, stri pped] at systime Fri Jun 13 13:01:22 CEST 2025 on [Linux IBMpowerCHRP 5.10.0-8-power pc64 #1 SMP Debian 5.10.46-1 (2021-06-24) ppc64]
MIPS_Linux_32_gccV830_sgi	gcc version 8.3.0 (Gentoo 8.3.0 pl.0) as [ ELF 32-bit MSB executable, MIPS, N32 MIPS- IV version 1 (SYSV), dynamically linked (u ses shared libs), for GNU/Linux 3.2.0, str ipped] at systime Fri Jun 13 13:07:48 CEST 2025 on [Linux SGIserver 4.12.0 #1 SMP Mo n Feb 25 13:10:05 CET 2019 mips64 R12000 V 2.3 FPU V0.0 SGI Octane2]
MIPS_Linux_64_gccV930	gcc version 9.3.0 (GCC) (cross-toolchain) as [ELF 64-bit MSB executable, MIPS, MIPS-III version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3.2.0, stripped] at systime Fri Jun 13 13:01:20 CES T 2025 on [Linux IBMpowerCHRP 5.10.0-8-powerpc64 #1 SMP Debian 5.10.46-1 (2021-06-24) ppc64]
MIPSel_Linux_32_gccV930	gcc version 9.3.0 (GCC) (cross-toolchain) as [ELF 32-bit LSB executable, MIPS, MIPS-I version 1 (SYSV), dynamically linked (us es shared libs), for GNU/Linux 3.2.0, stri pped] at systime Fri Jun 13 13:01:22 CEST 2025 on [Linux IBMpowerCHRP 5.10.0-8-power pc64 #1 SMP Debian 5.10.46-1 (2021-06-24) ppc64]
MIPSel_Linux_64_gccV930	gcc version 9.3.0 (GCC) (cross-toolchain) as [ELF 64-bit LSB executable, MIPS, MIPS-III version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3.2.0, st ripped] at systime Fri Jun 13 13:01:19 CES T 2025 on [Linux IBMpowerCHRP 5.10.0-8-pow erpc64 #1 SMP Debian 5.10.46-1 (2021-06-24) ppc64]

	<u> </u>
MIPSel_Android_32_gccV49x	gcc version 4.9.x 20150123 (prerelease) (G CC) (cross-toolchain) (mips32 mipsel-linux -android -D_ANDROID_API=26) as [ELF 32-bit LSB executable, MIPS, MIPS32 version 1 (SYSV), dynamically linked (uses shared 1 ibs), stripped] at systime Fri Jun 13 13:0 1:18 CEST 2025 on [Linux Linux64core 5.10.0-6-amd64 #1 SMP Debian 5.10.28-1 (2021-04-09) x86_64 GNU/Linux]
MIPSel_Android_32_clangV503	clang version 5.0.300080 (based on LLVM 5.0.300080) (cross-toolchain) (mips32 mipsel -linux-android -D_ANDROID_API_=26) as [ELF 32-bit LSB executable, MIPS, MIPS32 version 1 (SYSV), dynamically linked (uses shared libs), stripped] at systime Fri Jun 1 3 13:01:12 CEST 2025 on [Linux Linux64core 5.10.0-6-amd64 #1 SMP Debian 5.10.28-1 (2 021-04-09) x86_64 GNU/Linux]
MIPSel_Android_64_gccV49x	gcc version 4.9.x 20150123 (prerelease) (G CC) (cross-toolchain) (mips64 mips64el-lin ux-android -D_ANDROID_API_=26) as [ELF 6 4-bit LSB executable, MIPS, version 1 (SYS V), dynamically linked (uses shared libs), stripped] at systime Fri Jun 13 13:01:19 CEST 2025 on [Linux Linux64core 5.10.0-6-a md64 #1 SMP Debian 5.10.28-1 (2021-04-09) x86_64 GNU/Linux]
MIPSel_Android_64_clangV503	clang version 5.0.300080 (based on LLVM 5.0.300080) (cross-toolchain) (mips64 mips64 el-linux-android -D_ANDROID_API_=26) as [ELF 64-bit LSB executable, MIPS, version 1 (SYSV), dynamically linked (uses shared libs), stripped] at systime Fri Jun 13 13:01:13 CEST 2025 on [Linux Linux64core 5.10.0-6-amd64 #1 SMP Debian 5.10.28-1 (2021-0 4-09) x86_64 GNU/Linux]
PowerPC_AIX_32_xlcV1313	IBM XL C/C++ for AIX, V13.1.3 (5725-C72, 5 765-J07) Version: 13.01.0003.0000 as [exec utable (RISC System/6000) or object module ] at systime Fri Jun 13 13:03:36 CEST 2025 on [AIX IBMpowerCHRP 1 7 00F68D574C00]
PowerPC_AIX_32_gccV494	gcc version 4.9.4 (GCC) (powerpc-ibm-aix7. 1.0.0) as [executable (RISC System/6000) o r object module] at systime Fri Jun 13 13: 02:38 CEST 2025 on [AIX IBMpowerCHRP 1 7 0 0F68D574C00]
PowerPC_AIX_64_xlcV1313	IBM XL C/C++ for AIX, V13.1.3 (5725-C72, 5 765-J07) Version: 13.01.0003.0000 as [64-b it XCOFF executable or object module] at s ystime Fri Jun 13 13:02:32 CEST 2025 on [A IX IBMpowerCHRP 1 7 00F68D574C00]
PowerPC_AIX_64_gccV494	gcc version 4.9.4 (GCC) (powerpc-ibm-aix7. 1.0.0) as [64-bit XCOFF executable or obje ct module] at systime Fri Jun 13 13:02:27 CEST 2025 on [AIX IBMpowerCHRP 1 7 00F68D5 74C00]

PowerPC_MacOS_32_gccV421	gcc version 4.2.1 (Apple Inc. build 5577) as [Mach-O executable ppc] at systime Fri Jun 13 13:01:35 CEST 2025 on [Darwin Power G5MacOSX 9.8.0 Darwin Kernel Version 9.8.0 : Wed Jul 15 16:57:01 PDT 2009; root:xnu-1 228.15.4~1/RELEASE_PPC Power Macintosh]
PowerPC_MacOS_64_gccV421	gcc version 4.2.1 (Apple Inc. build 5577) as [Mach-O 64-bit executable ppc64] at sys time Fri Jun 13 13:01:35 CEST 2025 on [Dar win PowerG5MacOSX 9.8.0 Darwin Kernel Vers ion 9.8.0: Wed Jul 15 16:57:01 PDT 2009; r oot:xnu-1228.15.4~1/RELEASE_PPC Power Macintosh]
PowerPC_Linux_32_gccV492	gcc version 4.9.2 (Debian 4.9.2-10+deb8ul) as [ELF 32-bit MSB executable, PowerPC or cisco 4500, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 2.6.32, stripped] at systime Fri Jun 13 13 :01:29 CEST 2025 on [Linux IBMpowerCHRP 3. 16.0-6-powerpc64 #1 SMP Debian 3.16.56-1+d eb8u1 (2018-05-08) ppc64]
PowerPC_Linux_32_gccV1021	gcc version 10.2.1 20210110 (Debian 10.2.1 -6) as [ELF 32-bit MSB executable, PowerPC or cisco 4500, version 1 (SYSV), dynamica lly linked (uses shared libs), for GNU/Lin ux 3.2.0, stripped] at systime Fri Jun 13 13:01:15 CEST 2025 on [Linux IBMpowerCHRP 5.10.0-8-powerpc64 #1 SMP Debian 5.10.46-1 (2021-06-24) ppc64]
PowerPC_Linux_32_clangV350	Debian clang version 3.5.0-10 (tags/RELEAS E_350/final) (based on LLVM 3.5.0) as [ELF 32-bit MSB executable, PowerPC or cisco 4 500, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 2.6.32, stripped] at systime Fri Jun 13 13:01:14 C EST 2025 on [Linux IBMpowerCHRP 3.16.0-6-p owerpc64 #1 SMP Debian 3.16.56-1+deb8u1 (2 018-05-08) ppc64]
PowerPC_Linux_32_clangV1101	Debian clang version 11.0.1-2 as [ELF 32-b it MSB executable, PowerPC or cisco 4500, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3.2.0, stripp ed] at systime Fri Jun 13 13:01:28 CEST 20 25 on [Linux IBMpowerCHRP 5.10.0-8-powerpc 64 #1 SMP Debian 5.10.46-1 (2021-06-24) pp c64]
PowerPC_Linux_64_gccV492	gcc version 4.9.2 (Debian 4.9.2-10+deb8u1) as [ELF 64-bit MSB executable, 64-bit Pow erPC or cisco 7500, version 1 (SYSV), dyna mically linked (uses shared libs), for GNU /Linux 2.6.32, stripped] at systime Fri Ju n 13 13:01:27 CEST 2025 on [Linux IBMpower CHRP 3.16.0-6-powerpc64 #1 SMP Debian 3.16 .56-1+deb8u1 (2018-05-08) ppc64]

PowerPC_Linux_64_gccV1021	gcc version 10.2.1 20210110 (Debian 10.2.1 -6) as [ELF 64-bit MSB executable, 64-bit PowerPC or cisco 7500, version 1 (SYSV), d ynamically linked (uses shared libs), for GNU/Linux 3.2.0, stripped] at systime Fri Jun 13 13:01:15 CEST 2025 on [Linux IBMpow erCHRP 5.10.0-8-powerpc64 #1 SMP Debian 5. 10.46-1 (2021-06-24) ppc64]
PowerPC_Linux_64_clangV350	Debian clang version 3.5.0-10 (tags/RELEAS E_350/final) (based on LLVM 3.5.0) as [ELF 64-bit MSB executable, 64-bit PowerPC or cisco 7500, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 2.6.32, stripped] at systime Fri Jun 13 13: 01:14 CEST 2025 on [Linux IBMpowerCHRP 3.1 6.0-6-powerpc64 #1 SMP Debian 3.16.56-1+de b8u1 (2018-05-08) ppc64]
PowerPC_Linux_64_clangV1101	Debian clang version 11.0.1-2 as [ELF 64-b it MSB executable, 64-bit PowerPC or cisco 7500, version 1 (SYSV), dynamically linke d (uses shared libs), for GNU/Linux 3.2.0, stripped] at systime Fri Jun 13 13:01:27 CEST 2025 on [Linux IBMpowerCHRP 5.10.0-8-powerpc64 #1 SMP Debian 5.10.46-1 (2021-06-24) ppc64]
PowerPC_FreeBSD_32_gccV920	gcc version 9.2.0 (FreeBSD Ports Collectio n) as [ELF 32-bit MSB executable, PowerPC or cisco 4500, version 1 (FreeBSD), dynami cally linked (uses shared libs), FreeBSD-s tyle, for FreeBSD 12.1, stripped] at systi me Fri Jun 13 13:13:39 CEST 2025 on [FreeB SD FreeBSD12VM 12.1-RELEASE FreeBSD 12.1-R ELEASE r354233 GENERIC powerpc]
PowerPC_FreeBSD_32_clangV801	clang version 8.0.1 (tags/RELEASE_801/fina 1) (based on LLVM 8.0.1) as [ELF 32-bit MS B executable, PowerPC or cisco 4500, versi on 1 (FreeBSD), dynamically linked (uses s hared libs), FreeBSD-style, for FreeBSD 12 .1, stripped] at systime Fri Jun 13 13:27: 54 CEST 2025 on [FreeBSD FreeBSD12VM 12.1- RELEASE FreeBSD 12.1-RELEASE r354233 GENER IC powerpc]
PowerPC_FreeBSD_64_gccV920	gcc version 9.2.0 (FreeBSD Ports Collectio n) as [ELF 64-bit MSB executable, 64-bit P owerPC or cisco 7500, version 1 (FreeBSD), dynamically linked (uses shared libs), Fr eeBSD-style, for FreeBSD 12.1, stripped] a t systime Fri Jun 13 13:14:35 CEST 2025 on [FreeBSD FreeBSD12VM 12.1-RELEASE FreeBSD 12.1-RELEASE r354233 GENERIC powerpc]
PowerPC_FreeBSD_64_clangV801	clang version 8.0.1 (tags/RELEASE_801/fina 1) (based on LLVM 8.0.1) as [ELF 64-bit MS B executable, 64-bit PowerPC or cisco 7500 , version 1 (FreeBSD), dynamically linked (uses shared libs), FreeBSD-style, for Fre eBSD 12.1, stripped] at systime Fri Jun 13 13:28:29 CEST 2025 on [FreeBSD FreeBSD12V M 12.1-RELEASE FreeBSD 12.1-RELEASE r35423 3 GENERIC powerpc]

	+
PowerPCle_Linux_32_gccV930	gcc version 9.3.0 (GCC) (cross-toolchain) as [ELF 32-bit LSB executable, PowerPC or cisco 4500, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3 .2.0, stripped] at systime Fri Jun 13 13:0 1:19 CEST 2025 on [Linux IBMpowerCHRP 5.10 .0-8-powerpc64 #1 SMP Debian 5.10.46-1 (20 21-06-24) ppc64]
PowerPCle_Linux_64_gccV1021	gcc version 10.2.1 20210110 (Debian 10.2.1 -6) as [ELF 64-bit LSB executable, 64-bit PowerPC or cisco 7500, version 1 (SYSV), d ynamically linked (uses shared libs), for GNU/Linux 3.10.0, stripped] at systime Fri Jun 13 13:01:18 CEST 2025 on [Linux Linux PPC641e 5.10.0-20-powerpc641e #1 SMP Debia n 5.10.158-2 (2022-12-13) ppc641e]
PowerPCle_Linux_64_clangV1101	Debian clang version 11.0.1-2 as [ELF 64-b it LSB executable, 64-bit PowerPC or cisco 7500, version 1 (SYSV), dynamically linke d (uses shared libs), for GNU/Linux 3.10.0, stripped] at systime Fri Jun 13 13:01:29 CEST 2025 on [Linux LinuxPPC641e 5.10.0-2 0-powerpc641e #1 SMP Debian 5.10.158-2 (20 22-12-13) ppc641e]
PowerPCle_Linux_64_xlcV1611	IBM XL C/C++ for Linux, V16.1.1 (Community Edition) Version: 16.01.0001.0003 as [ELF 64-bit LSB executable, 64-bit PowerPC or cisco 7500, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3 .10.0, stripped] at systime Fri Jun 13 13: 01:42 CEST 2025 on [Linux LinuxPPC64le 5.1 0.0-20-powerpc64le #1 SMP Debian 5.10.158-2 (2022-12-13) ppc64le]
S390_Linux_32_gccV930	gcc version 9.3.0 (GCC) (cross-toolchain) as [ELF 32-bit MSB executable, IBM S/390, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3.2.0, stripp ed] at systime Fri Jun 13 13:01:18 CEST 20 25 on [Linux IBMpowerCHRP 5.10.0-8-powerpc 64 #1 SMP Debian 5.10.46-1 (2021-06-24) pp c64]
S390_Linux_64_gccV930	gcc version 9.3.0 (GCC) (cross-toolchain) as [ELF 64-bit MSB executable, IBM S/390, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3.2.0, stripp ed] at systime Fri Jun 13 13:01:18 CEST 20 25 on [Linux IBMpowerCHRP 5.10.0-8-powerpc 64 #1 SMP Debian 5.10.46-1 (2021-06-24) pp c64]
S390_Linux_64_clangV381	clang version 3.8.1-24 (tags/RELEASE_381/f inal) as [ELF 64-bit MSB executable, IBM S /390, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3.2.0, stripped] at systime Fri Jun 13 13:08:23 C EST 2025 on [Linux debian-QEMU 4.9.0-3-s39 0x #1 SMP Debian 4.9.30-2+deb9u1 (2017-06-18) s390x]

	+
M68000_Linux_32_gccV930	gcc version 9.3.0 (GCC) (cross-toolchain) as [ELF 32-bit MSB executable, Motorola m6 8k, 68020, version 1 (SYSV), dynamically 1 inked (uses shared libs), for GNU/Linux 3. 2.0, stripped] at systime Fri Jun 13 13:01:15 CEST 2025 on [Linux IBMpowerCHRP 5.10. 0-8-powerpc64 #1 SMP Debian 5.10.46-1 (202 1-06-24) ppc64]
ARMeabi_Linux_32_gccV1021	gcc version 10.2.1 20210110 (Debian 10.2.1 -6) (cross-toolchain) as [ELF 32-bit LSB e xecutable, ARM, EABI5 version 1 (SYSV), dy namically linked (uses shared libs), for G NU/Linux 3.2.0, stripped] at systime Fri J un 13 13:01:25 CEST 2025 on [Linux Linux64 core 5.10.0-6-amd64 #1 SMP Debian 5.10.28-1 (2021-04-09) x86_64]
ARMeabihf_Linux_32_gccV1021	gcc version 10.2.1 20210110 (Debian 10.2.1 -6) (cross-toolchain) as [ELF 32-bit LSB e xecutable, ARM, EABI5 version 1 (SYSV), dy namically linked (uses shared libs), for G NU/Linux 3.2.0, stripped] at systime Fri J un 13 13:01:18 CEST 2025 on [Linux Linux64 core 5.10.0-6-amd64 #1 SMP Debian 5.10.28-1 (2021-04-09) x86_64]
ARMeabihf_Linux_32_clangV381	clang version 3.8.1-24 (tags/RELEASE_381/f inal) as [ELF 32-bit LSB executable, ARM, EABI5 version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3.2.0, stripped] at systime Fri Jun 13 13:08:03 C EST 2025 on [Linux debian-QEMU 4.9.0-3-arm mp-lpae #1 SMP Debian 4.9.30-2+deb9u1 (201 7-06-18) armv71]
ARM_Linux_64_gccV1021	gcc version 10.2.1 20210110 (Debian 10.2.1 -6) as [ELF 64-bit LSB executable, ARM aar ch64, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3.7.0, stripped] at systime Fri Jun 13 13:02:21 C EST 2025 on [Linux ARM64debian 5.10.0-8-ar m64 #1 SMP Debian 5.10.46-1 (2021-06-24) a arch64]
ARM_Linux_64_clangV1101	Debian clang version 11.0.1-2 as [ELF 64-b it LSB executable, ARM aarch64, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 3.7.0, stripped] at systime Fri Jun 13 13:02:17 CEST 2025 on [Linux ARM64debian 5.10.0-8-arm64 #1 SMP Debian 5.10.46-1 (2021-06-24) aarch64]
ARM_FreeBSD_64_gccV920	gcc version 9.2.0 (FreeBSD Ports Collectio n) as [ELF 64-bit LSB executable, ARM aarc h64, version 1 (SYSV), dynamically linked, (uses shared libs), for FreeBSD 12.1, Fre eBSD-style, stripped] at systime Fri Jun 1 3 13:07:27 CEST 2025 on [FreeBSD FreeBSD12 VM 12.1-RELEASE FreeBSD 12.1-RELEASE r3542 33 GENERIC arm64]

ARM_FreeBSD_64_clangV801	FreeBSD clang version 8.0.1 (tags/RELEASE_801/final 366581) (based on LLVM 8.0.1) as [ELF 64-bit LSB executable, ARM aarch64, version 1 (SYSV), dynamically linked, (use s shared libs), for FreeBSD 12.1, FreeBSD-style, stripped] at systime Fri Jun 13 13: 06:53 CEST 2025 on [FreeBSD FreeBSD12VM 12 .1-RELEASE FreeBSD 12.1-RELEASE r354233 GE NERIC arm64]
ARM_Android_32_gccV49x	gcc version 4.9.x 20150123 (prerelease) (G CC) (cross-toolchain) (arm arm-linux-andro ideabi -D_ ANDROID_API_ =26) as [ELF 32-bi t LSB executable, ARM, EABI5 version 1 (SY SV), dynamically linked (uses shared libs), stripped] at systime Fri Jun 13 13:01:21 CEST 2025 on [Linux Linux64core 5.10.0-6-amd64 #1 SMP Debian 5.10.28-1 (2021-04-09) x86_64 GNU/Linux]
ARM_Android_32_clangV503	clang version 5.0.300080 (based on LLVM 5.0.300080) (cross-toolchain) (arm arm-linux -androideabi -D_ANDROID_API_ =26) as [ELF 32-bit LSB executable, ARM, EABI5 version 1 (SYSV), dynamically linked (uses shared libs), stripped] at systime Fri Jun 13 13:01:13 CEST 2025 on [Linux Linux64core 5.1 0.0-6-amd64 #1 SMP Debian 5.10.28-1 (2021-04-09) x86_64 GNU/Linux]
ARM_Android_64_gccV49x	gcc version 4.9.x 20150123 (prerelease) (G CC) (cross-toolchain) (arm64 aarch64-linux -android -D_ANDROID_API_=26) as [ELF 64-bit LSB executable, ARM aarch64, version 1 (SYSV), dynamically linked (uses shared 1 ibs), stripped] at systime Fri Jun 13 13:0 1:20 CEST 2025 on [Linux Linux64core 5.10.0-6-amd64 #1 SMP Debian 5.10.28-1 (2021-04-09) x86_64 GNU/Linux]
ARM_Android_64_clangV503	clang version 5.0.300080 (based on LLVM 5.0.300080) (cross-toolchain) (arm64 aarch64-linux-android -D_ANDROID_API_=26) as [ELF 64-bit LSB executable, ARM aarch64, version 1 (SYSV), dynamically linked (uses shared libs), stripped] at systime Fri Jun 1 3 13:01:15 CEST 2025 on [Linux Linux64core 5.10.0-6-amd64 #1 SMP Debian 5.10.28-1 (2 021-04-09) x86_64 GNU/Linux]
ARM_MacOS_64_clangV1200	Apple clang version 12.0.0 (clang-1200.0.3 2.29) (Target: arm64-apple-darwin20.0.0) a s [Mach-0 64-bit executable arm64] at syst ime Fri Jun 13 13:02:22 CEST 2025 on [Darw in MacOS11_BigSur 20.0.0 Darwin Kernel Ver sion 20.0.0: Thu Jul 30 22:49:28 PDT 2020; root:xnu-7195.0.0.141.5~1/RELEASE_X86_64 x86_64]
ARMe_MacOS_64_clangV1200	Apple clang version 12.0.0 (clang-1200.0.3 2.29) (Target: arm64e-apple-darwin20.0.0) as [Mach-0 64-bit executable arm64e] at sy stime Fri Jun 13 13:01:57 CEST 2025 on [Darwin MacOS11_BigSur 20.0.0 Darwin Kernel V ersion 20.0.0: Thu Jul 30 22:49:28 PDT 202 0; root:xnu-7195.0.0.141.5~1/RELEASE_X86_6 4 x86_64]

ARMbe_Linux_64_gccV930	gcc version 9.3.0 (GCC) (cross-toolchain) as [ELF 64-bit MSB executable, ARM aarch64, version 1 (SYSV), dynamically linked (us es shared libs), for GNU/Linux 3.7.0, stri pped] at systime Fri Jun 13 13:01:23 CEST 2025 on [Linux IBMpowerCHRP 5.10.0-8-power pc64 #1 SMP Debian 5.10.46-1 (2021-06-24) ppc64]
RISCV_Linux_32_gccV930	gcc version 9.3.0 (GCC) (cross-toolchain) as [ELF 32-bit LSB executable, UCB RISC-V, version 1 (SYSV), dynamically linked (use s shared libs), for GNU/Linux 5.4.0, strip ped] at systime Fri Jun 13 13:01:17 CEST 2 025 on [Linux IBMpowerCHRP 5.10.0-8-powerp c64 #1 SMP Debian 5.10.46-1 (2021-06-24) p pc64]
RISCV_Linux_64_gccV930	gcc version 9.3.0 (GCC) (cross-toolchain) as [ELF 64-bit LSB executable, UCB RISC-V, version 1 (SYSV), dynamically linked (use s shared libs), for GNU/Linux 4.15.0, stri pped] at systime Fri Jun 13 13:01:17 CEST 2025 on [Linux IBMpowerCHRP 5.10.0-8-power pc64 #1 SMP Debian 5.10.46-1 (2021-06-24) ppc64]
LoongArch_Linux_64_gccV1300	gcc version 13.0.0 20221018 (experimental) (GCC) (cross-toolchain) as [ELF 64-bit LS B executable, LoongArch, version 1 (SYSV), dynamically linked (uses shared libs), for GNU/Linux 5.19.0, stripped] at systime F ri Jun 13 13:01:17 CEST 2025 on [Linux Linux64core 5.10.0-6-amd64 #1 SMP Debian 5.10 .28-1 (2021-04-09) x86_64]

This page is intentionally left blank. This is the last page of the document.