

INTRODUCTION TO HIGH PERFORMANCE SCIENTIFIC COMPUTING

Evolving Copy - open for comments

VICTOR EIJKHOUT
WITH
EDMOND CHOW, ROBERT VAN DE GEIJN

1ST EDITION 2011 – revision425



Introduction to High-Performance Scientific Computing © Victor Eijkhout, distributed under a Creative Commons Attribution 3.0 Unported (CC BY 3.0) license and made possible by funding from The Saylor Foundation <http://www.saylor.org>.

Preface

The field of high performance scientific computing lies at the crossroads of a number of disciplines and skill sets, and correspondingly, for someone to be successful at using high performance computing in science requires at least elementary knowledge of and skills in all these areas. Computations stem from an application context, so some acquaintance with physics and engineering sciences is desirable. Then, problems in these application areas are typically translated into linear algebraic, and sometimes combinatorial, problems, so a computational scientist needs knowledge of several aspects of numerical analysis, linear algebra, and discrete mathematics. An efficient implementation of the practical formulations of the application problems requires some understanding of computer architecture, both on the CPU level and on the level of parallel computing. Finally, in addition to mastering all these sciences, a computational scientist needs some specific skills of software management.

While good texts exist on numerical modeling, numerical linear algebra, computer architecture, parallel computing, performance optimization, no book brings together these strands in a unified manner. The need for a book such as the present became apparent to the author working at a computing center: users are domain experts who not necessarily have mastery of all the background that would make them efficient computational scientists. This book, then, teaches those topics that seem indispensable for scientists engaging in large-scale computations.

The contents of this book are a combination of theoretical material and self-guided tutorials on various practical skills. The theory chapters have exercises that can be assigned in a classroom, however, their placement in the text is such that a reader not inclined to do exercises can simply take them as statement of fact.

The tutorials should be done while sitting at a computer. Given the practice of scientific computing, they have a clear Unix bias.

Public draft This book is open for comments. What is missing or incomplete or unclear? Is material presented in the wrong sequence? Kindly mail me with any comments you may have.

You may have found this book in any of a number of places; the authoritative download location is <http://www.tacc.utexas.edu/~eijkhout/istc/istc.html>. It is also possible to get a nicely printed copy from lulu.com:

<http://www.lulu.com/shop/victor-eijkhout/introduction-to-high-performance-scientific-paperback/product-20452679.html>

Victor Eijkhout eijkhout@tacc.utexas.edu
Research Scientist
Texas Advanced Computing Center
The University of Texas at Austin

Acknowledgement Helpful discussions with Kazushige Goto and John McCalpin are gratefully acknowledged. Thanks to Dan Stanzione for his notes on cloud computing, Ernie Chan for his notes on scheduling

of block algorithms, and John McCalpin for his analysis of the top500. Thanks to Elie de Brauwer, Susan Lindsey, and Lorenzo Pesce for proofreading and many comments.

Introduction

Scientific computing is the cross-disciplinary field at the intersection of modeling scientific processes, and the use of computers to produce quantitative results from these models. It is what takes a domain science and turns it into a computational activity. As a definition, we may posit

The efficient computation of constructive methods in applied mathematics.

This clearly indicates the three branches of science that scientific computing touches on:

- Applied mathematics: the mathematical modeling of real-world phenomena. Such modeling often leads to implicit descriptions, for instance in the form of partial differential equations. In order to obtain actual tangible results we need a constructive approach.
- Numerical analysis provides algorithmic thinking about scientific models. It offers a constructive approach to solving the implicit models, with an analysis of cost and stability.
- Computing takes numerical algorithms and analyzes the efficacy of implementing them on actually existing, rather than hypothetical, computing engines.

One might say that ‘computing’ became a scientific field in its own right, when the mathematics of real-world phenomena was asked to be constructive, that is, to go from proving the existence of solutions to actually obtaining them. At this point, algorithms become an object of study themselves, rather than a mere tool.

The study of algorithms became especially important when computers were invented. Since mathematical operations now were endowed with a definable time cost, complexity of algorithms became a field of study; since computing was no longer performed in ‘real’ numbers but in representations in finite bitstrings, the accuracy of algorithms needed to be studied. Some of these considerations in fact predate the existence of computers, having been inspired by computing with mechanical calculators.

A prime concern in scientific computing is efficiency. While to some scientists the abstract fact of the existence of a solution is enough, in computing we actually want that solution, and preferably yesterday. For this reason, in this book we will be quite specific about the efficiency of both algorithms and hardware. It is important not to limit the concept of efficiency to that of efficient use of hardware. While this is important, the difference between two algorithmic approaches can make optimization for specific hardware a secondary concern.

This book aims to cover the basics of this gamut of knowledge that a successful computational scientist needs to master. It is set up as a textbook for graduate students or advanced undergraduate students; others can use it as a reference text, reading the exercises for their information content.

Contents

1	Sequential Computing	9
1.1	<i>The Von Neumann architecture</i>	9
1.2	<i>Modern floating point units</i>	11
1.3	<i>Memory Hierarchies</i>	16
1.4	<i>Multicore architectures</i>	29
1.5	<i>Locality and data reuse</i>	32
1.6	<i>Programming strategies for high performance</i>	37
1.7	<i>Power consumption</i>	50
2	Parallel Computing	52
2.1	<i>Introduction</i>	52
2.2	<i>Parallel Computers Architectures</i>	55
2.3	<i>Different types of memory access</i>	58
2.4	<i>Granularity of parallelism</i>	62
2.5	<i>Parallel programming</i>	66
2.6	<i>Topologies</i>	91
2.7	<i>Efficiency of parallel computing</i>	102
2.8	<i>Multi-threaded architectures</i>	108
2.9	<i>GPU computing</i>	108
2.10	<i>Remaining topics</i>	111
3	Computer Arithmetic	125
3.1	<i>Integers</i>	125
3.2	<i>Representation of real numbers</i>	127
3.3	<i>Round-off error analysis</i>	132
3.4	<i>More about floating point arithmetic</i>	138
3.5	<i>Conclusions</i>	140
4	Numerical treatment of differential equations	141
4.1	<i>Initial value problems</i>	141
4.2	<i>Boundary value problems</i>	147
4.3	<i>Initial boundary value problem</i>	155
5	Numerical linear algebra	161
5.1	<i>Elimination of unknowns</i>	161
5.2	<i>Linear algebra in computer arithmetic</i>	164
5.3	<i>LU factorization</i>	166
5.4	<i>Sparse matrices</i>	174

5.5	<i>Iterative methods</i>	185
5.6	<i>Further Reading</i>	204
6	High performance linear algebra	205
6.1	<i>Parallel dense matrix-vector product</i>	205
6.2	<i>Scalability of the dense matrix-vector product</i>	208
6.3	<i>Scalability of LU factorization</i>	216
6.4	<i>Parallel sparse matrix-vector product</i>	218
6.5	<i>Computational aspects of iterative methods</i>	223
6.6	<i>Parallel preconditioners</i>	226
6.7	<i>Ordering strategies and parallelism</i>	229
6.8	<i>Operator splitting</i>	238
6.9	<i>Parallelism and implicit operations</i>	239
6.10	<i>Block algorithms on multicore architectures</i>	244
7	Molecular dynamics	248
7.1	<i>Force Computation</i>	249
7.2	<i>Parallel Decompositions</i>	253
7.3	<i>Parallel Fast Fourier Transform</i>	259
7.4	<i>Integration for Molecular Dynamics</i>	262
8	Combinatorics	266
8.1	<i>Sorting</i>	266
8.2	<i>Graph problems</i>	269
9	Discrete systems	273
10	Monte Carlo Methods	274
10.1	<i>Parallel Random Number Generation</i>	274
10.2	<i>Examples</i>	275
	Appendices	278
A	Theoretical background	278
A.1	<i>Linear algebra</i>	279
A.2	<i>Complexity</i>	285
A.3	<i>Partial Differential Equations</i>	286
A.4	<i>Taylor series</i>	288
A.5	<i>Graph theory</i>	290
A.6	<i>Fourier Transforms</i>	296
A.7	<i>Finite State Automatons</i>	298
B	Practical tutorials	299
B.1	<i>Unix intro</i>	300
B.2	<i>Compilers and libraries</i>	317
B.3	<i>Managing projects with Make</i>	320
B.4	<i>Source control</i>	330
B.5	<i>Scientific Data Storage</i>	338
B.6	<i>Scientific Libraries</i>	344
B.7	<i>Plotting with GNUploat</i>	355
B.8	<i>Good coding practices</i>	358

CONTENTS

B.9	<i>Debugging</i>	365
B.10	<i>Performance measurement</i>	372
B.11	<i>C/Fortran interoperability</i>	374
B.12	<i>L^AT_EX for scientific documentation</i>	378
C	Class projects	391
C.1	<i>Cache simulation and analysis</i>	391
C.2	<i>Evaluation of Bulk Synchronous Programming</i>	393
C.3	<i>Heat equation</i>	394
D	Codes	397
D.1	<i>Hardware event counting</i>	397
D.2	<i>Cache size</i>	397
D.3	<i>Cachelines</i>	397
D.4	<i>Cache associativity</i>	398
D.5	<i>TLB</i>	398
E	Index and list of acronyms	406

Chapter 1

Sequential Computing

In order to write efficient scientific codes, it is important to understand computer architecture. The difference in speed between two codes that compute the same result can range from a few percent to orders of magnitude, depending only on factors relating to how well the algorithms are coded for the processor architecture. Clearly, it is not enough to have an algorithm and ‘put it on the computer’: some knowledge of computer architecture is advisable, sometimes crucial.

Some problems can be solved on a single CPU, others need a parallel computer that comprises more than one processor. We will go into detail on parallel computers in the next chapter, but even for parallel processing, it is necessary to understand the individual CPUs.

In this chapter, we will focus on what goes on inside a CPU and its memory system. We start with a brief general discussion of how instructions are handled, then we will look into the arithmetic processing in the processor core; last but not least, we will devote much attention to the movement of data between memory and the processor, and inside the processor. This latter point is, maybe unexpectedly, very important, since memory access is typically much slower than executing the processor’s instructions, making it the determining factor in a program’s performance; the days when ‘flop¹ counting’ was the key to predicting a code’s performance are long gone. This discrepancy is in fact a growing trend, so the issue of dealing with memory traffic has been becoming more important over time, rather than going away.

This chapter will give you a basic understanding of the issues involved in CPU design, how it affects performance, and how you can code for optimal performance. For much more detail, see an online book about PC architecture [78], and the standard work about computer architecture, Hennessy and Patterson [68].

1.1 The Von Neumann architecture

While computers, and most relevantly for this chapter, their processors, can differ in any number of details, they also have many aspects in common. On a very high level of abstraction, many architectures can be described as *von Neumann architectures*. This describes a design with an undivided memory that stores both program and data (‘stored program’), and a processing unit that executes the instructions, operating on the data.

1. Floating Point Operation.

1. Sequential Computing

This setup distinguishes modern processors for the very earliest, and some special purpose contemporary, designs where the program was hard-wired. It also allows programs to modify themselves or generate other programs, since instructions and data are in the same storage. This allows us to have editors and compilers: the computer treats program code as data to operate on. In this book we will not explicitly discuss compilers, the programs that translate high level languages to machine instructions. However, on occasion we will discuss how a program at high level can be written to ensure efficiency at the low level.

In scientific computing, however, we typically do not pay much attention to program code, focusing almost exclusively on data and how it is moved about during program execution. For most practical purposes it is as if program and data are stored separately. The little that is essential about instruction handling can be described as follows.

The machine instructions that a processor executes, as opposed to the higher level languages users write in, typically specify the name of an operation, as well as of the locations of the operands and the result. These locations are not expressed as memory locations, but as *registers*: a small number of named memory locations that are part of the CPU². As an example, here is a simple C routine

```
void store(double *a, double *b, double *c) {  
    *c = *a + *b;  
}
```

and its X86 assembler output, obtained by³ `gcc -O2 -S -o - store.c:`

```
.text  
.p2align 4,,15  
.globl store  
.type store, @function  
store:  
    movsd (%rdi), %xmm0 # Load *a to %xmm0  
    addsd (%rsi), %xmm0 # Load *b and add to %xmm0  
    movsd %xmm0, (%rdx) # Store to *c  
    ret
```

The instructions here are:

- A load from memory to register;
- Another load, combined with an addition;
- Writing back the result to memory.

Each instruction is processed as follows:

- Instruction fetch: the next instruction according to the *program counter* is loaded into the processor. We will ignore the questions of how and from where this happens.

2. Direct-to-memory architectures are rare, though they have existed. The Cyber 205 supercomputer in the 1980s could have 3 data streams, two from memory to the processor, and one back from the processor to memory, going on at the same time. Such an architecture is only feasible if memory can keep up with the processor speed, which is no longer the case these days.

3. This is 64-bit output; add the option `-m64` on 32-bit systems.

- Instruction decode: the processor inspects the instruction to determine the operation and the operands.
- Memory fetch: if necessary, data is brought from memory into a register.
- Execution: the operation is executed, reading data from registers and writing it back to a register.
- Write-back: for store operations, the register contents is written back to memory.

The case of array data is a little more complicated: the element loaded (or stored) is then determined as the base address of the array plus an offset.

In a way, then, the modern CPU looks to the programmer like a von Neumann machine. There are various ways in which this is not so. For one, while memory looks randomly addressable⁴, in practice there is a concept of *locality*: once a data item has been loaded, nearby items are more efficient to load, and reloading the initial item is also faster.

Another complication to this story of simple loading of data is that contemporary CPUs operate on several instructions simultaneously, which are said to be ‘in flight’, meaning that they are in various stages of completion. Of course, together with these simultaneous instructions, their inputs and outputs are also being moved between memory and processor in an overlapping manner. This is the basic idea of the *superscalar* CPU architecture, and is also referred to as *Instruction Level Parallelism (ILP)*. Thus, while each instruction can take several clock cycles to complete, a processor can complete one instruction per cycle in favourable circumstances; in some cases more than one instruction can be finished per cycle.

The main statistic that is quoted about CPUs is their Gigahertz rating, implying that the speed of the processor is the main determining factor of a computer’s performance. While speed obviously correlates with performance, the story is more complicated. Some algorithms are *cpu-bound*, and the speed of the processor is indeed the most important factor; other algorithms are *memory-bound*, and aspects such as bus speed and cache size, to be discussed later, become important.

In scientific computing, this second category is in fact quite prominent, so in this chapter we will devote plenty of attention to the process that moves data from memory to the processor, and we will devote relatively little attention to the actual processor.

1.2 Modern floating point units

In the Von Neumann model no distinction is made between one type of instruction and another. In scientific computing, we are mostly interested in floating point instructions, so we will now consider the Floating Point Unit (FPU) of the processor in some detail.

Many modern processors are capable of doing multiple operations simultaneously, and this holds in particular for the arithmetic part. For instance, often there are separate addition and multiplication units; if the compiler can find addition and multiplication operations that are independent, it can schedule them so as to be executed simultaneously, thereby doubling the performance of the processor. In some cases, a processor will have multiple addition or multiplication units.

4. There is in fact a theoretical model for computation called the ‘Random Access Machine’; we will briefly see its parallel generalization in section 2.7.2.

Another way to increase performance is to have a ‘fused multiply-add’ unit, which can execute the instruction $x \leftarrow ax + b$ in the same amount of time as a separate addition or multiplication. Together with pipelining (see below), this means that a processor has an asymptotic speed of several floating point operations per clock cycle.

Processor	floating point units	max operations per cycle
Intel Pentium4	2 add or 2 mul	2
Intel Woodcrest, AMD Barcelona	2 add + 2 mul	4
IBM POWER4, POWER5, POWER6	2 FMA	4
IBM BG/L, BG/P	1 SIMD FMA	4
SPARC IV	1 add + 1 mul	2
Itanium2	2 FMA	4

Table 1.1: Floating point capabilities of several current processor architectures

Incidentally, there are few algorithms in which division operations are a limiting factor. Correspondingly, the division operation is not nearly as much optimized in a modern CPU as the additions and multiplications are. Division operations can take 10 or 20 clock cycles, while a CPU can have multiple addition and/or multiplication units that (asymptotically) can produce a result per cycle.

1.2.1 Pipelining

The floating point add and multiply units of a processor are pipelined, which has the effect that a stream of independent operations can be performed at an asymptotic speed of one result per clock cycle.

The idea behind a pipeline is as follows. Assume that an operation consists of multiple simpler operations, and that for each suboperation there is separate hardware in the processor. For instance, an addition instruction can have the following components:

- Decoding the instruction, including finding the locations of the operands.
- Copying the operands into registers (‘data fetch’).
- Aligning the exponents; the addition $.35 \times 10^{-1} + .6 \times 10^{-2}$ becomes $.35 \times 10^{-1} + .06 \times 10^{-1}$.
- Executing the addition of the mantissas, in this case giving .41.
- Normalizing the result, in this example to $.41 \times 10^{-1}$. (Normalization in this example does not do anything. Check for yourself that in $.3 \times 10^0 + .8 \times 10^0$ and $.35 \times 10^{-3} + (-.34) \times 10^{-3}$ there is a non-trivial adjustment.)
- Storing the result.

These parts are often called the ‘stages’ or ‘segments’ of the pipeline.

If every component is designed to finish in 1 clock cycle, the whole instruction takes 6 cycles. However, if each has its own hardware, we can execute two operations in less than 12 cycles:

- Execute the decode stage for the first operation;
- Do the data fetch for the first operation, and at the same time the decode for the second.
- Execute the third stage for the first operation and the second stage of the second operation simultaneously.
- Et cetera.

You see that the first operation still takes 6 clock cycles, but the second one is finished a mere 1 cycle later.

Let us make a formal analysis of the speedup you can get from a pipeline. On a traditional FPU, producing n results takes $t(n) = n\ell\tau$ where ℓ is the number of stages, and τ the clock cycle time. The rate at which results are produced is the reciprocal of $t(n)/n$: $r_{\text{serial}} \equiv (\ell\tau)^{-1}$.

On the other hand, for a pipelined FPU the time is $t(n) = [s + \ell + n - 1]\tau$ where s is a setup cost: the first operation still has to go through the same stages as before, but after that one more result will be produced each cycle. We can also write this formula as

$$t(n) = [n + n_{1/2}]\tau.$$




Figure 1.1: Schematic depiction of a pipelined operation

Exercise 1.1. Let us compare the speed of a classical FPU, and a pipelined one. Show that the result rate is now dependent on n : give a formula for $r(n)$, and for $r_\infty = \lim_{n \rightarrow \infty} r(n)$. What is the asymptotic improvement in r over the non-pipelined case?

Next you can wonder how long it takes to get close to the asymptotic behaviour. Show that for $n = n_{1/2}$ you get $r(n) = r_\infty/2$. This is often used as the definition of $n_{1/2}$.

Since a vector processor works on a number of instructions simultaneously, these instructions have to be independent. The operation $\forall_i: a_i \leftarrow b_i + c_i$ has independent additions; the operation $\forall_i: a_{i+1} \leftarrow a_i b_i + c_i$ feeds the result of one iteration (a_i) to the input of the next ($a_{i+1} = \dots$), so the operations are not independent.

A pipelined processor can speed up operations by a factor of 4, 5, 6 with respect to earlier CPUs. Such numbers were typical in the 1980s when the first successful vector computers came on the market. These

days, CPUs can have 20-stage pipelines. Does that mean they are incredibly fast? This question is a bit complicated. Chip designers continue to increase the clock rate, and the pipeline segments can no longer finish their work in one cycle, so they are further split up. Sometimes there are even segments in which nothing happens: that time is needed to make sure data can travel to a different part of the chip in time.

The amount of improvement you can get from a pipelined CPU is limited, so in a quest for ever higher performance several variations on the pipeline design have been tried. For instance, the Cyber 205 had separate addition and multiplication pipelines, and it was possible to feed one pipe into the next without data going back to memory first. Operations like $\forall_i: a_i \leftarrow b_i + c \cdot d_i$ were called ‘linked triads’ (because of the number of paths to memory, one input operand had to be scalar).

Exercise 1.2. Analyse the speedup and $n_{1/2}$ of linked triads.

Another way to increase performance is to have multiple identical pipes. This design was perfected by the NEC SX series. With, for instance, 4 pipes, the operation $\forall_i: a_i \leftarrow b_i + c_i$ would be split modulo 4, so that the first pipe operated on indices $i = 4 \cdot j$, the second on $i = 4 \cdot j + 1$, et cetera.

Exercise 1.3. Analyze the speedup and $n_{1/2}$ of a processor with multiple pipelines that operate in parallel. That is, suppose that there are p independent pipelines, executing the same instruction, that can each handle a stream of operands.

(You may wonder why we are mentioning some fairly old computers here: true pipeline supercomputers hardly exist anymore. In the US, the Cray X1 was the last of that line, and in Japan only NEC still makes them. However, the functional units of a CPU these days are pipelined, so the notion is still important.)

Exercise 1.4. The operation

```
for (i) {
    x[i+1] = a[i]*x[i] + b[i];
}
```

can not be handled by a pipeline because there is a *dependency* between input of one iteration of the operation and the output of the previous. However, you can transform the loop into one that is mathematically equivalent, and potentially more efficient to compute. Derive an expression that computes $x[i+2]$ from $x[i]$ without involving $x[i+1]$. This is known as *recursive doubling*. Assume you have plenty of temporary storage. You can now perform the calculation by

- Doing some preliminary calculations;
- computing $x[i], x[i+2], x[i+4], \dots$, and from these,
- compute the missing terms $x[i+1], x[i+3], \dots$

Analyze the efficiency of this scheme by giving formulas for $T_0(n)$ and $T_s(n)$. Can you think of an argument why the preliminary calculations may be of lesser importance in some circumstances?

1.2.2 Peak performance

Thanks to pipelining, for modern CPUs there is a simple relation between the *clock speed* and the *peak performance*. Since each FPU can produce one result per cycle asymptotically, the peak performance is the clock speed times the number of independent FPUs. The measure of floating point performance is ‘floating

point operations per second’, abbreviated *flops*. Considering the speed of computers these days, you will mostly hear floating point performance being expressed in ‘gigaflops’: multiples of 10^9 flops.

1.2.3 Pipelining beyond arithmetic: instruction-level parallelism

In fact, nowadays, the whole CPU is pipelined. Not only floating point operations, but any sort of instruction will be put in the *instruction pipeline* as soon as possible. Note that this pipeline is no longer limited to identical instructions: the notion of pipeline is now generalized to any stream of partially executed instructions that are simultaneously “in flight”.

This concept is also known as *Instruction Level Parallelism (ILP)*, and it is facilitated by various mechanisms:

- multiple-issue: instructions that are independent can be started at the same time;
- pipelining: already mentioned, arithmetic units can deal with multiple operations in various stages of completion;
- branch prediction and speculative execution: a compiler can ‘guess’ whether a conditional instruction will evaluate to true, and execute those instructions accordingly;
- out-of-order execution: instructions can be rearranged if they are not dependent on each other, and if the resulting execution will be more efficient;
- prefetching: data can be speculatively requested before any instruction needing it is actually encountered (this is discussed further in section 1.3.5).

As clock frequency has gone up, the processor pipeline has grown in length to make the segments executable in less time. You have already seen that longer pipelines have a larger $n_{1/2}$, so more independent instructions are needed to make the pipeline run at full efficiency. As the limits to instruction-level parallelism are reached, making pipelines longer (sometimes called ‘deeper’) no longer pays off. This is generally seen as the reason that chip designers have moved to *multicore* architectures as a way of more efficiently using the transistors on a chip; section 1.4.

There is a second problem with these longer pipelines: if the code comes to a branch point (a conditional or the test in a loop), it is not clear what the next instruction to execute is. At that point the pipeline can stall. CPUs have taken to *speculative execution* for instance, by always assuming that the test will turn out true. If the code then takes the other branch (this is called a *branch misprediction*), the pipeline has to be cleared and restarted. The resulting delay in the execution stream is called the *branch penalty*.

1.2.4 8-bit, 16-bit, 32-bit, 64-bit

Processors are often characterized in terms of how big a chunk of data they can process as a unit. This can relate to

- The width of the path between processor and memory: can a 64-bit floating point number be loaded in one cycle, or does it arrive in pieces at the processor.
- The way memory is addressed: if addresses are limited to 16 bits, only 64,000 bytes can be identified. Early PCs had a complicated scheme with segments to get around this limitation: an address was specified with a segment number and an offset inside the segment.

- The number of bits in a register, in particular the size of the integer registers which manipulate data address; see the previous point. (Floating point register are often larger, for instance 80 bits in the x86 architecture.) This also corresponds to the size of a chunk of data that a processor can operate on simultaneously.
- The size of a floating point number. If the arithmetic unit of a CPU is designed to multiply 8-byte numbers efficiently ('double precision'; see section 3.2) then numbers half that size ('single precision') can sometimes be processed at higher efficiency, and for larger numbers ('quadruple precision') some complicated scheme is needed. For instance, a quad precision number could be emulated by two double precision numbers with a fixed difference between the exponents.

These measurements are not necessarily identical. For instance, the original Pentium processor had 64-bit data busses, but a 32-bit processor. On the other hand, the Motorola 68000 processor (of the original Apple Macintosh) had a 32-bit CPU, but 16-bit data busses.

The first Intel microprocessor, the 4004, was a 4-bit processor in the sense that it processed 4 bit chunks. These days, 64 bit processors are becoming the norm.

1.3 Memory Hierarchies

We will now refine the picture of the Von Neuman architecture, in which data is loaded immediately from memory to the processor, where it is operated on. This picture is unrealistic because of the so-called *memory wall*: the memory is too slow to load data into the process at the rate the processor can absorb it. Specifically, a single load can take 1000 cycles, while a processor can perform several operations per cycle. (After this long wait for a load, the next load can come faster, but still too slow for the processor. This matter of wait time versus throughput will be addressed below in section 1.3.2.)


In reality, there will be various memory levels in between the FPU and the main memory: the registers and the caches, together called the *memory hierarchy*. These try to alleviate the memory wall problem by making recently used data available quicker than it would be from main memory. Of course, this presupposes that the algorithm and its implementation allow for data to be used multiple times. Such questions of *data reuse* will be discussed in more detail below.

Both registers and caches are faster to a degree than main memory; unfortunately, the faster the memory on a certain level, the smaller it will be. This leads to interesting programming problems, which we will discuss later in this chapter, and particularly section 1.6.

We will now discuss the various components of the memory hierarchy and the theoretical concepts needed to analyze their behaviour.

1.3.1 Busses

The wires that move data around in a computer, from memory to cpu or to a disc controller or screen, are called *busses*. The most important one for us is the *Front-Side Bus (FSB)* which connects the processor to memory. In one popular architecture, this is called the 'north bridge', as opposed to the 'south bridge' which connects to external devices, with the exception of the graphics controller.



The bus is typically slower than the processor, operating with clock frequencies slightly in excess of 1GHz, which is a fraction of the CPU clock frequency. This is one reason that caches are needed; the fact that a processors can consume many data items per clock tick contributes to this. Apart from the frequency, the bandwidth of a bus is also determined by the number of bits that can be moved per clock cycle. This is typically 64 or 128 in current architectures. We will now discuss this in some more detail.

1.3.2 Latency and Bandwidth

Above, we mentioned in very general terms that accessing data in registers is almost instantaneous, whereas loading data from memory into the registers, a necessary step before any operation, incurs a substantial delay. We will now make this story slightly more precise.

There are two important concepts to describe the movement of data: *latency* and *bandwidth*. The assumption here is that requesting an item of data incurs an initial delay; if this item was the first in a stream of data, usually a consecutive range of memory addresses, the remainder of the stream will arrive with no further delay at a regular amount per time period.

Latency is the delay between the processor issuing a request for a memory item, and the item actually arriving. We can distinguish between various latencies, such as the transfer from memory to cache, cache to register, or summarize them all into the latency between memory and processor. Latency is measured in (nano) seconds, or clock periods.

If a processor executes instructions in the order they are found in the assembly code, then execution will often *stall* while data is being fetched from memory; this is also called *memory stall*. For this reason, a low latency is very important. In practice, many processors have ‘out-of-order execution’ of instructions, allowing them to perform other operations while waiting for the requested data. Programmers can take this into account, and code in a way that achieves *latency hiding*. Graphics Processing Units (GPUs) (see section 2.9) can switch very quickly between threads in order to achieve latency hiding.

Bandwidth is the rate at which data arrives at its destination, after the initial latency is overcome. Bandwidth is measured in bytes (kilobytes, megabytes, gigabytes) per second or per clock cycle. The bandwidth between two memory levels is usually the product of the cycle speed of the channel

1. Sequential Computing

(the *bus speed*) and the *bus width*: the number of bits that can be sent simultaneously in every cycle of the bus clock.

The concepts of latency and bandwidth are often combined in a formula for the time that a message takes from start to finish:

$$T(n) = \alpha + \beta n$$

where α is the latency and β is the inverse of the bandwidth: the time per byte.

Typically, the further away from the processor one gets, the longer the latency is, and the lower the bandwidth. These two factors make it important to program in such a way that, if at all possible, the processor uses data from cache or register, rather than from main memory. To illustrate that this is a serious matter, consider a vector addition

```
for (i)
    a[i] = b[i]+c[i]
```

Each iteration performs one floating point operation, which modern CPUs can do in one clock cycle by using pipelines. However, each iteration needs two numbers loaded and one written, for a total of 24 bytes⁵ of memory traffic. Typical memory bandwidth figures (see for instance figure 1.2) are nowhere near 24 (or 32) bytes per cycle. This means that, without caches, algorithm performance can be bounded by memory performance. Of course, caches will not speed up every operations, and in fact will have no effect on the above example. Strategies for programming that lead to significant cache use are discussed in section 1.6.

The concepts of latency and bandwidth will also appear in parallel computers, when we talk about sending data from one processor to the next.

1.3.3 Registers

Every processor has a small amount of memory that is internal to the processor: the *registers*, or together the *register file*. The registers are what the processor actually operates on: an operation such as

```
a := b + c
```

is actually implemented as

- load the value of *b* from memory into a register,
- load the value of *c* from memory into another register,
- compute the sum and write that into yet another register, and
- write the sum value back to the memory location of *c*.

Looking at assembly code (for instance the output of a compiler), you see the explicit load, compute, and store instructions. Compute instructions such as add or multiply only operate on registers; for instance

```
addl %eax, %edx
```

5. Actually, *a[i]* is loaded before it can be written, so there are 4 memory access, with a total of 32 bytes, per iteration.

is an instruction to add the content of one register to another. As you see in this sample instruction, registers are not numbered in memory, but have distinct names that are referred to in the assembly instruction. Typically, a processor has 16 or 32 floating point registers; the *Intel Itanium* was exceptional with 128 floating point registers.

Registers have a high bandwidth and low latency because they are part of the processor. You can consider data movement to and from registers as essentially instantaneous.

In this chapter you will see stressed that moving data from memory is relatively expensive. Therefore, it would be a simple optimization to leave data in register when possible. For instance, if the above computation is followed by a statement

```
a := b + c  
d := a + e
```

the computed value of *a* could be left in register. This optimization is typically performed as a *compiler optimization*: the compiler will simply not generate the instructions for storing and reloading *a*. We say that *a* stays *resident in register*.

Keeping values in register is often done to avoid recomputing a quantity. For instance, in

```
t1 = sin(alpha) * x + cos(alpha) * y;  
t2 = -cos(alph) * x + sin(alpha) * y;
```

the sine and cosine quantity will probably be kept in register. You can help the compiler by explicitly introducing temporary quantities:

```
s = sin(alpha); c = cos(alpha);  
t1 = s * x + c * y;  
t2 = -c * x + s * y
```

Of course, there is a limit to how many quantities can be kept in register; trying to keep too many quantities in register is called *register spill* and lowers the performance of a code.

Keeping a variable in register is especially important if that variable appears in an inner loop. In the computation

```
for i=1,length  
a[i] = b[i] * c
```

the quantity *c* will probably be kept in register by the compiler, but in

```
for k=1,nvectors  
for i=1,length  
a[i,k] = b[i,k] * c[k]
```

it is a good idea to introduce explicitly a temporary variable to hold *c*[*k*].

1.3.4 Caches

In between the registers, which contain the immediate input and output data for instructions, and the main memory where lots of data can reside for a long time, are various levels of *cache* memory, that have lower latency and higher bandwidth than main memory and where data are kept for an intermediate amount of time. Data from memory travels through the caches to wind up in registers. The advantage to having cache memory is that if a data item is reused shortly after it was first needed, it will still be in cache, and therefore it can be accessed much faster than if it would have to be brought in from memory.

1.3.4.1 A motivating example

As an example, let's suppose a variable *x* is used twice, and its uses are too far apart that it would stay *resident in register*:

```
... = ... x ..... // instruction using x
.....           // several instructions not involving x
... = ... x ..... // instruction using x
```

The assembly code would then be

- load *x* from memory into register; operate on it;
- do the intervening instructions;
- load *x* from memory into register; operate on it;

With a cache, the assembly code stays the same, but the actual behaviour of the memory system now becomes:

- load *x* from memory into cache, and from cache into register; operate on it;
- do the intervening instructions;
- request *x* from memory, but since it is still in the cache, load it from the cache into register; operate on it.

Since loading from cache is faster than loading from main memory, the computation will now be faster. Caches are fairly small, so values can not be kept there indefinitely. We will see the implications of this in the following discussion.

There is an important difference between cache memory and registers: while data is moved into register by explicit assembly instructions, the move from main memory to cache is entirely done by hardware. Thus cache use and reuse is outside of direct programmer control. Later, especially in sections 1.5.2 and 1.6, you will see how it is possible to influence cache use indirectly.

1.3.4.2 Cache levels, speed and size

The caches are called ‘level 1’ and ‘level 2’ (or, for short, L1 and L2) cache; some processors can have an L3 cache. The L1 and L2 caches are part of the *die*, the processor chip, although for the L2 cache that is a relatively recent development; the L3 cache is off-chip. The L1 cache is small, typically around 16Kbyte. Level 2 (and, when present, level 3) cache is more plentiful, up to several megabytes, but it is also slower.




Figure 1.2: Memory hierarchy of an AMD Xeon, characterized by speed and size.

Unlike main memory, which is expandable, caches are fixed in size. If a version of a processor chip exists with a larger cache, it is usually considerably more expensive.

Data needed in some operation gets copied into the various caches on its way to the processor. If, some instructions later, a data item is needed again, it is first searched for in the L1 cache; if it is not found there, it is searched for in the L2 cache; if it is not found there, it is loaded from main memory. Finding data in cache is called a *cache hit*, and not finding it a *cache miss*.

Figure 1.2 illustrates the basic facts of the *cache hierarchy*, in this case for the *AMD Opteron* chip: the closer caches are to the FPUs, the faster, but also the smaller they are. Some points about this figure.

- Loading data from registers is so fast that it does not constitute a limitation on algorithm execution speed. On the other hand, there are few registers. The Opteron⁶ has 16 general purpose registers, 8 media and floating point registers, and 16 SIMD registers.
- The L1 cache is small, but sustains a bandwidth of 32 bytes, that is 4 double precision number, per cycle. This is enough to load two operands each for two operations, but note that the Opteron can actually perform 4 operations per cycle. Thus, to achieve peak speed, certain operands need to stay in register. The latency from L1 cache is around 3 cycles.
- The bandwidth from L2 and L3 cache is not documented and hard to measure due to cache policies (see below). Latencies are around 15 cycles for L2 and 50 for L3.
- Main memory access has a latency of more than 100 cycles, and a bandwidth of 4.5 bytes per cycle, which is about 1/7th of the L1 bandwidth. However, this bandwidth is shared by the 4 cores of the opteron chip, so effectively the bandwidth is a quarter of this number. In a machine like Ranger, which has 4 chips per node, some bandwidth is spent on maintaining *cache coherence* (see section 1.4) reducing the bandwidth for each chip again by half.

6. Specifically the server chip used in the Ranger supercomputer; desktop versions may have different specifications.

1. Sequential Computing

On level 1, there are separate caches for instructions and data; the L2 and L3 cache contain both data and instructions.

You see that the larger caches are increasingly unable to supply data to the processors fast enough. For this reason it is necessary to code in such a way that data is kept as much as possible in the highest cache level possible. We will discuss this issue in detail in the rest of this chapter.

Exercise 1.5. The L1 cache is smaller than the L2 cache, and if there is an L3, the L2 is smaller than the L3. Give a practical and a theoretical reason why this is so.

1.3.4.3 Reuse is the name of the game

The presence of one or more caches is not immediately a guarantee for high performance: this largely depends on the *memory access pattern* of the code, and how well this exploits the caches. The first time that an item is referenced, it is copied from memory into cache, and through to the processor registers. The latency and bandwidth for this are not mitigated in any way by the presence of a cache. When the same item is referenced a second time, it may be found in cache, at a considerably reduced cost in terms of latency and bandwidth: caches have shorter latency and higher bandwidth than main memory.

We conclude that, first, an algorithm has to have an opportunity for data reuse. If every data item is used only once (as in addition of two vectors), there can be no reuse, and the presence of caches is largely irrelevant. A code will only benefit from the increased bandwidth and reduced latency of a cache if items in cache are referenced more than once; see section 1.5.1 for a detailed discussion.. An example would be the matrix-vector multiplication $y = Ax$ where each element of x is used in n operations, where n is the matrix dimension.

Secondly, an algorithm may theoretically have an opportunity for reuse, but it needs to be coded in such a way that the reuse is actually exposed. We will address these points in section 1.5.2. This second point especially is not trivial.

Some problems are small enough that they fit completely in cache, at least in the L3 cache. This is something to watch out for when *benchmarking*, since it gives a too rosy picture of processor performance.

1.3.4.4 Replacement policies

Data in cache and registers is placed there by the system, outside of programmer control. Likewise, the system decides when to overwrite data in the cache or in registers if it is not referenced in a while, and as other data needs to be placed there. Below, we will go into detail on how caches do this, but as a general principle, a Least Recently Used (LRU) cache replacement policy is used: if a cache is full and new data needs to be placed into it, the data that was least recently used is *flushed*, meaning that it is overwritten with the new item, and therefore no longer accessible. LRU is by far the most common replacement policy; other possibilities are FIFO (first in first out) or random replacement.

Exercise 1.6. Sketch a simple scenario, and give some (pseudo) code, to argue that LRU is preferable over FIFO as a replacement strategy.

1.3.4.5 Cache lines

Data movement between memory and cache, or between caches, is not done in single bytes, or even words. Instead, the smallest unit of data moved is called a *cache line*, sometimes called a *cache block*. A typical cache line is 64 or 128 bytes long, which in the context of scientific computing implies 8 or 16 double precision floating point numbers. The cache line size for data moved into L2 cache can be larger than for data moved into L1 cache.

It is important to acknowledge the existence of cache lines in coding, since any memory access costs the transfer of several words (see section 1.6.4 for some examples). An efficient program then tries to use the other items on the cache line, since access to them is effectively free. This phenomenon is visible in code that accesses arrays by *stride*: elements are read or written at regular intervals.

Stride 1 corresponds to sequential access of an array:

```
for (i=0; i<N; i++)
    ... = ... x[i] ...
```

Let us use as illustration a case with 4 words per cache-line. Requesting the first elements loads the whole cacheline that contains it into cache. A request for the 2nd, 3rd, and 4th element can then be satisfied from cache, meaning with high bandwidth and low latency.

A larger stride

```
for (i=0; i<N; i+=stride)
    ... = ... x[i] ...
```

implies that in every cache line only certain elements are used. We illustrate that with stride 3: requesting the first elements loads a cacheline, and this cacheline also contains the second element. However, the third element is on the next cacheline, so loading this incurs the latency and bandwidth of main memory. The same holds for the fourth element. Loading four elements now needed loading three cache lines instead of one, meaning that two-thirds of the available bandwidth has been wasted. (This second case would also incur three times the latency of the first, if it weren't for a hardware mechanism that notices the regular access patterns, and pre-emptively loads further cachelines; see section 1.3.5.)

Some applications naturally lead to strides greater than 1, for instance, accessing only the real parts of an array of complex numbers (for some remarks on the practical realization of complex numbers see section 3.4.4). Also, methods that use *recursive doubling* often have a code structure that exhibits non-unit strides

```
for (i=0; i<N/2; i++)
    x[i] = y[2*i];
```




Figure 1.3: Accessing 4 elements at stride 1




Figure 1.4: Accessing 4 elements at stride 3

1. Sequential Computing

In this discussion of cachelines, we have implicitly assumed the beginning of a cacheline is also the beginning of a word, be that an integer or a floating point number. This need not be true: an 8-byte floating point number can be placed straddling the boundary between two cachelines. You can image that this is not good for performance. To force allocated space to be *aligned* with a *cacheline boundary alignment*, you can do the following:

```
double *a;
a = malloc( /* some number of bytes */ +8 );
if ( (int)a % 8 != 0 ) { /* it is not 8-byte aligned */
    a += 1; /* advance address by 8 bytes, then */
    /* either: */
    a = ( (a>>3) <<3 );
    /* or: */
    a = 8 * ( ( (int)a )/8 );
}
```

This code allocates a block of memory, and, if necessary, shfits it right to have a starting address that is a multiple of 8. This sort of alignment can sometimes be forced by compiler options.

1.3.4.6 Cache mapping

Caches get faster, but also smaller, the closer to the FPUs they get, yet even the largest cache is considerably smaller than the main memory size. We already noted that this has implications for the cache replacement strategy. Another issue we need to address in this context is that of *cache mapping*, which is the question of ‘if an item is placed in cache, where does it get placed’. This problem is generally addressed by mapping the (main memory) address of the item to an address in cache, leading to the question ‘what if two items get mapped to the same address’.

1.3.4.7 Direct mapped caches

The simplest cache mapping strategy is *direct mapping*. Suppose that memory addresses are 32 bits long, so that they can address 4G bytes⁷; suppose further that the cache has 8K words, that is, 64K bytes, needing 16 bits to address. Direct mapping then takes from each memory address the last (‘least significant’) 16 bits, and uses these as the address of the data item in cache.

Direct mapping is very efficient because of its address calculations can be performed very quickly, leading to low latency, but it has a problem in practical applications. If two items are addressed that are separated by 8K words, they will be mapped to the same cache location, which will make certain calculations inefficient. Example:

```
double A[3][8192];
for (i=0; i<512; i++)
    a[2][i] = ( a[0][i]+a[1][i] )/2.;
```

7. We implicitly use the convention that K,M,G suffixes refer to powers of 2 rather than 10: 1K=1024, 1M=1,048,576, 1G=4,294,967,296.

or in Fortran:

```
real*8 A(8192,3);
do i=1,512
    a(i,3) = ( a(i,1)+a(i,2) )/2
end do
```

Here, the locations of $a[0][i]$, $a[1][i]$, and $a[2][i]$ (or $a(i,1), a(i,2), a(i,3)$) are 8K from each other for every i , so the last 16 bits of their addresses will be the same, and hence they will be mapped to the same location in cache. The execution of the loop will now go as follows:

- The data at $a[0][0]$ is brought into cache and register. This engenders a certain amount of latency. Together with this element, a whole cache line is transferred.
- The data at $a[1][0]$ is brought into cache (and register, as we will not remark anymore from now on), together with its whole cache line, at cost of some latency. Since this cache line is mapped to the same location as the first, the first cache line is overwritten.
- In order to write the output, the cache line containing $a[2][0]$ is brought into memory. This is again mapped to the same location, causing flushing of the cache line just loaded for $a[1][0]$.
- In the next iteration, $a[0][1]$ is needed, which is on the same cache line as $a[0][0]$. However, this cache line has been flushed, so it needs to be brought in anew from main memory or a deeper cache level. In doing so, it overwrites the cache line that holds $a[2][0]$.
- A similar story hold for $a[1][1]$: it is on the cache line of $a[1][0]$, which unfortunately has been overwritten in the previous step.

If a cache line holds four words, we see that each four iterations of the loop involve eight transfers of elements of a , where two would have sufficed, if it were not for the cache conflicts.

Exercise 1.7. In the example of direct mapped caches, mapping from memory to cache was done by using the final 16 bits of a 32 bit memory address as cache address. Show that the problems in this example go away if the mapping is done by using the first ('most significant') 16 bits as the cache address. Why is this not a good solution in general?

1.3.4.8 Associative caches

The problem of cache conflicts, outlined in the previous section, would be solved if any data item could go to any cache location. In that case there would be no conflicts, other than the cache filling up, in which case a cache replacement policy (section 1.3.4.4) would flush data to make room for the incoming item. Such a cache is called *fully associative*, and while it seems optimal, it is also very costly to build, and much slower in use than a direct mapped cache.

For this reason, the most common solution is to have a *k-way associative cache*, where k is at least two. In this case, a data item can go to any of k cache locations. Code would have to have a $k + 1$ -way conflict before data would be flushed prematurely as in the above example. In that example, a value of $k = 2$ would suffice, but in practice higher values are often encountered.

For instance, the *Intel Woodcrest* processor has

- an L1 cache of 32K bytes, that is 8-way set associative with a 64 byte cache line size;

- an L2 cache of 4M bytes, that is 8-way set associative with a 64 byte cache line size.

On the other hand, the *AMD Barcelona* chip has 2-way associativity for the L1 cache, and 8-way for the L2. A higher associativity ('way-ness') is obviously desirable, but makes a processor slower, since determining whether an address is already in cache becomes more complicated. For this reason, the associativity of the L1 cache, where speed is of the greatest importance, is typically lower than of the L2.

Exercise 1.8. Write a small cache simulator in your favourite language. Assume a k -way associative cache of 32 entries and an architecture with 16 bit addresses. Run the following experiment for $k = 1, 2, 4, \dots$:

1. Let k be the associativity of the simulated cache.
2. Write the translation from 16 bit memory addresses to $32/k$ cache addresses.
3. Generate 32 random machine addresses, and simulate storing them in cache.

Since the cache has 32 entries, optimally the 32 addresses can all be stored in cache. The chance of this actually happening is small, and often the data of one address will be evicted from the cache (meaning that it is overwritten) when another address conflicts with it. Record how many addresses, out of 32, are actually stored in the cache at the end of the simulation. Do step 3 100 times, and plot the results; give median and average value, and the standard deviation. Observe that increasing the associativity improves the number of addresses stored. What is the limit behaviour? (For bonus points, do a formal statistical analysis.)

1.3.5 Prefetch streams

In the traditional von Neumann model (section 1.1), each instruction contains the location of its operands, so a CPU implementing this model would make a separate request for each new operand. In practice, often subsequent data items are adjacent or regularly spaced in memory. The memory system can try to detect such data patterns by looking at cache miss points, and request a *prefetch data stream*.

In its simplest form, the CPU will detect that consecutive loads come from two consecutive cache lines, and automatically issue a request for the next following cache line. This process can be repeated or extended if the code makes an actual request for that third cache line. Since these cache lines are now brought from memory well before they are needed, prefetch has the possibility of eliminating the latency for all but the first couple of data items.

The concept of *cache miss* now needs to be revisited a little. From a performance point of view we are only interested in *stalls* on cache misses, that is, the case where the computation has to wait for the data to be brought in. Data that is not in cache, but can be brought in while other instructions are still being processed, is not a problem. If an 'L1 miss' is understood to be only a 'stall on miss', then the term 'L1 cache refill' is used to describe all cacheline loads, whether the processor is stalling on them or not.

Since prefetch is controlled by the hardware, it is also described as *hardware prefetch*. Prefetch streams can sometimes be controlled from software, though often it takes assembly code to do so. On the *IBM BlueGene Q* prefetch can be activated by program directives.

1.3.6 Concurrency and memory transfer

In the discussion about the memory hierarchy we made the point that memory is slower than the processor. As if that is not bad enough, it is not even trivial to exploit all the bandwidth that memory offers. In other words, if you don't program carefully you will get even less performance than you would expect based on the available bandwidth. Let's analyze this.

The memory system typically has a bandwidth of more than one floating point number per cycle, so you need to issue that many requests per cycle to utilize the available bandwidth. This would be true even with zero latency; since there is latency, it takes a while for data to make it from memory and be processed. Consequently, any data requested based on computations on the first data has to be requested with a delay at least equal the memory latency.

For full utilization of the bandwidth, at all times a volume of data equal to the bandwidth times the latency has to be in flight. Since these data have to be independent, we get a statement of *Little's law* [93]:

$$\text{Concurrency} = \text{Bandwidth} \times \text{Latency}.$$

This is illustrated in figure 1.5. The problem with maintaining this concurrency is not that a program does




Figure 1.5: Illustration of Little's Law that states how much independent data needs to be in flight

not have it; rather, the program is to get the compiler and runtime system recognize it. For instance, if a loop traverses a long array, the compiler will not issue a large number of memory requests. The prefetch mechanism (section 1.3.5) will issue some memory requests ahead of time, but typically not enough. Thus, in order to use the available bandwidth, multiple streams of data need to be under way simultaneously. Therefore, we can also phrase Little's law as

$$\text{Effectivethroughput} = \text{Expressedconcurrency}/\text{Latency}.$$

1.3.7 Memory banks

Above, we discussed issues relating to bandwidth. You saw that memory, and to a lesser extent caches, have a bandwidth that is less than what a processor can maximally absorb. The situation is actually even worse

than the above discussion made it seem. For this reason, memory is often divided into *memory banks* that are interleaved: with four memory banks, words 0, 4, 8, ... are in bank 0, words 1, 5, 9, ... are in bank 1, et cetera.

Suppose we now access memory sequentially, then such 4-way interleaved memory can sustain four times the bandwidth of a single memory bank. Unfortunately, accessing by stride 2 will halve the bandwidth, and larger strides are even worse. In practice the number of memory banks will be higher, so that strided memory access with small strides will still have the full advertised bandwidth.

This concept of banks can also apply to caches. For instance, the cache lines in the L1 cache of the *AMD Barcelona* chip are 16 words long, divided into two interleaved banks of 8 words. This means that sequential access to the elements of a cache line is efficient, but strided access suffers from a deteriorated performance.

1.3.8 TLB and virtual memory

All of a program's data may not be in memory simultaneously. This can happen for a number of reasons:

- The computer serves multiple users, so the memory is not dedicated to any one user;
- The computer is running multiple programs, which together need more than the physically available memory;
- One single program can use more data than the available memory.

For this reason, computers use *Virtual memory*: if more memory is needed than is available, certain blocks of memory are written to disc. In effect, the disc acts as an extension of the real memory. This means that a block of data can be anywhere in memory, and in fact, if it is *swapped* in and out, it can be in different locations at different times. Swapping does not act on individual memory locations, but rather on *memory pages*: contiguous blocks of memory, from a few kilobytes to megabytes in size. (In an earlier generation of operating systems, moving memory to disc was a programmer's responsibility. Pages that would replace each other were called *overlays*.)

For this reason, we need a translation mechanism from the memory addresses that the program uses to the actual addresses in memory, and this translation has to be dynamic. A program has a 'logical data space' (typically starting from address zero) of the addresses used in the compiled code, and this needs to be translated during program execution to actual memory addresses. For this reason, there is a *page table* that specifies which memory pages contain which logical pages.

However, address translation by lookup in this table is slow, so CPUs have a *Translation Look-aside Buffer (TLB)*. The TLB is a cache of frequently used Page Table Entries: it provides fast address translation for a number of pages. If a program needs a memory location, the TLB is consulted to see whether this location is in fact on a page that is remembered in the TLB. If this is the case, the logical address is translated to a physical one; this is a very fast process. The case where the page is not remembered in the TLB is called a *TLB miss*, and the page lookup table is then consulted, if necessary bringing the needed page into memory. The TLB is (sometimes fully) associative (section 1.3.4.8), using an LRU policy (section 1.3.4.4).

A typical TLB has between 64 and 512 entries. If a program accesses data sequentially, it will typically alternate between just a few pages, and there will be no TLB misses. On the other hand, a program that access many random memory locations can experience a slowdown because of such misses.

Section 1.6.5 and appendix D.5 discuss some simple code illustrating the behaviour of the TLB.

[There are some complications to this story. For instance, there is usually more than one TLB. The first one is associated with the L2 cache, the second one with the L1. In the *AMD Opteron*, the L1 TLB has 48 entries, and is fully (48-way) associative, while the L2 TLB has 512 entries, but is only 4-way associative. This means that there can actually be TLB conflicts. In the discussion above, we have only talked about the L2 TLB. The reason that this can be associated with the L2 cache, rather than with main memory, is that the translation from memory to L2 cache is deterministic.]

1.4 Multicore architectures

In recent years, the limits of performance have been reached for the traditional processor chip design.

- Clock frequency can not be increased further, since it increases energy consumption, heating the chips too much; see section 1.7.
- It is not possible to extract more Instruction Level Parallelism (ILP) from codes, either because of compiler limitations, because of the limited amount of intrinsically available parallelism, or because branch prediction makes it impossible (see section 1.2.3).

One of the ways of getting a higher utilization out of a single processor chip is then to move from a strategy of further sophistication of the single processor, to a division of the chip into multiple processing ‘cores’⁸. The separate cores can work on unrelated tasks, or, by introducing what is in effect data parallelism (section 2.2.1), collaborate on a common task at a higher overall efficiency.

This solves the above two problems:

- Two cores at a lower frequency can have the same throughput as a single processor at a higher frequency; hence, multiple cores are more energy-efficient.
- Discovered ILP is now replaced by explicit task parallelism, managed by the programmer.

While the first multicore CPUs were simply two processors on the same die, later generations incorporated L3 or L2 caches that were shared between the two processor cores; see figure 1.6. This design makes it efficient for the cores to work jointly on the same problem. The cores would still have their own L1 cache, and these separate caches lead to a *cache coherence* problem; see section 1.4.1 below.

We note that the term ‘processor’ is now ambiguous: it can refer to either the chip, or the processor core on the chip. For this reason, we mostly talk about a *socket* for the whole chip and *core* for the part containing one arithmetic and logic unit and having its own registers. Currently, CPUs with 4 or 6 cores are common, even in laptops, and Intel and AMD are marketing 12-core chips. The core count is likely to go up in the future: Intel has already shown an 80-core prototype that is developed into the 48 core ‘Single-chip Cloud Computer’, illustrated in fig 1.7. This chip has a structure with 24 dual-core ‘tiles’ that are connected through a 2D mesh network. Only certain tiles are connected to a memory controller, others can not reach memory other than through the on-chip network.

8. Another solution is Intel’s *Hyperthreading*, which lets a processor mix the instructions of several instruction streams. The benefits of this are strongly dependent on the individual case. However, this same mechanism is exploited with great success in GPUs; see section 2.9.

1. Sequential Computing




Figure 1.6: Cache hierarchy in a single-core and dual-core chip




Figure 1.7: Structure of the Intel Single-chip Cloud Computer chip

With this mix of shared and private caches, the programming model for multicore processors is becoming a hybrid between shared and distributed memory:

- Core* The cores have their own private L1 cache, which is a sort of distributed memory. The above mentioned Intel 80-core prototype has the cores communicating in a distributed memory fashion.
- Socket* On one socket, there is often a shared L2 cache, which is shared memory for the cores.
- Node* There can be multiple sockets on a single ‘node’ or motherboard, accessing the same shared memory.
- Network* Distributed memory programming (see the next chapter) is needed to let nodes communicate. Historically, multicore architectures have a precedent in multiprocessor shared memory designs (section 2.3.1) such as the *Sequent Symmetry* and the *Alliant FX/8*. Conceptually the program model is the same, but the technology now allows to shrink a multiprocessor board to a multicore chip.

1.4.1 Cache coherence

With parallel processing, there is the potential for a conflict if more than one processor has a copy of the same data item. The problem of ensuring that all cached data are an accurate copy of main memory, is referred to as *cache coherence*: if one processor alters its copy, the other copy needs to be updated.

In distributed memory architectures, a dataset is usually partitioned disjointly over the processors, so conflicting copies of data can only arise with knowledge of the user, and it is up to the user to deal with the problem. The case of shared memory is more subtle: since processes access the same main memory, it would seem that conflicts are in fact impossible. However, processor typically have some private cache, which contains copies of data from memory, so conflicting copies can occur. This situation arises in particular in multicore designs.

Suppose that two cores have a copy of the same data item in their (private) L1 cache, and one modifies its copy. Now the other has cached data that is no longer an accurate copy of its counterpart, so it needs to reload that item. This is known as *maintaining cache coherence*, and it is done on a very low level of the processor, with no programmer involvement needed. (This makes updating memory locations an *atomic operation*; more about this in section 2.5.1.2.) However, it will slow down the computation, and it wastes bandwidth to the core that could otherwise be used for loading or storing operands.

The state of a cache line with respect to a data item in main memory is usually described as one of the following:

- Scratch: the cache line does not contain a copy of the item;
- Valid: the cache line is a correct copy of data in main memory;
- Reserved: the cache line is the *only* copy of that piece of data;
- Dirty: the cache line has been modified, but not yet written back to main memory;
- Invalid: the data on the cache line is also present on other processors (it is not reserved), and another process has modified its copy of the data.

Exercise 1.9. Consider two processors, a data item x in memory, and cachelines x_1, x_2 in the private caches of the two processors to which x is mapped. Describe the transitions between the states of x_1 and x_2 under reads and writes of x on the two processors. Also indicate which actions cause memory bandwidth to be used. (This list of transitions is a *Finite State Automaton* (FSA); see section A.7.)

The cache coherence problem can even appear if the cores access different items. For instance, a declaration

```
double x, y;
```

will likely allocate `x` and `y` next to each other in memory, so there is a high chance they fall on the same cacheline. Now if one core updates `x` and the other `y`, this cacheline will continuously be moved between the cores. This is called *false sharing*.

1.4.2 Computations on multicore chips

Multicore chips offer a form of shared memory parallelism and can be programmed as such, for instance using OpenMP (section 2.5.2). We will go discuss in some detail the scheduling of linear algebra operations on multicore chips; section 6.10.

1.5 Locality and data reuse

By now it should be clear that there is more to the execution of an algorithm than counting the operations: the data transfer involved is important, and can in fact dominate the cost. Since we have caches and registers, the amount of data transfer can be minimized by programming in such a way that data stays as close to the processor as possible. Partly this is a matter of programming cleverly, but we can also look at the theoretical question: does the algorithm allow for it to begin with.

It turns out that in scientific computing there is often data often interacts mostly with data that is close by in some sense, which will lead to data locality; section 1.5.2. Often such locality derives from the nature of the application, as in the case of the Partial Differential Equations (PDEs) you will see in chapter 4. In other cases such as molecular dynamics (chapter 7) there is no such intrinsic locality because all particles interact with all others, and considerable programming cleverness is needed to get high performance.

1.5.1 Data reuse

In this section we will take a look at *data reuse*: are data items involved in a calculation used more than once, so that caches and registers can be exploited? What precisely is the ratio between the number of operations and the amount of data transferred.

We define the data reuse ratio of an algorithm as follows:

If n is the number of data items that an algorithm operates on, and $f(n)$ the number of operations it takes, then the reuse ratio is $f(n)/n$.

Consider for example the vector addition

$$\forall_i: x_i \leftarrow x_i + y_i.$$

This involves three memory accesses (two loads and one store) and one operation per iteration, giving a data reuse of 1/3. The *axpy* (for ‘ a times x plus y ’) operation

$$\forall_i: x_i \leftarrow x_i + a \cdot y_i$$

has two operations, but the same number of memory access since the one-time load of a is amortized. It is therefore more efficient than the simple addition, with a reuse of 2/3.

The inner product calculation

$$\forall_i: s \leftarrow s + x_i \cdot y_i$$

is similar in structure to the axpy operation, involving one multiplication and addition per iteration, on two vectors and one scalar. However, now there are only two load operations, since s can be kept in register and only written back to memory at the end of the loop. The reuse here is 1.

Next, consider the matrix-matrix product:

$$\forall_{i,j}: c_{ij} = \sum_k a_{ik} b_{kj}.$$

This involves $3n^2$ data items and $2n^3$ operations, which is of a higher order. The data reuse is $O(n)$, meaning that every data item will be used $O(n)$ times. This has the implication that, with suitable programming, this operation has the potential of overcoming the bandwidth/clock speed gap by keeping data in fast cache memory.

Exercise 1.10. The matrix-matrix product, considered as *operation*, clearly has data reuse by the above definition. Argue that this reuse is not trivially attained by a simple implementation. What determines whether the naive implementation has reuse of data that is in cache?

[In this discussion we were only concerned with the number of operations of a given *implementation*, not the mathematical *operation*. For instance, there are ways of performing the matrix-matrix multiplication and Gaussian elimination algorithms in fewer than $O(n^3)$ operations [121, 106]. However, this requires a different implementation, which has its own analysis in terms of memory access and reuse.]

The matrix-matrix product is the heart of the *LINPACK benchmark* [31]; see section 2.10.6. Using this as the solve measure of *benchmarking* a computer may give an optimistic view of its performance: the matrix-matrix product is an operation that has considerable data reuse, so it is relatively insensitive to memory bandwidth and, for parallel computers, properties of the network. Typically, computers will attain 60–90% of their *peak performance* on the Linpack benchmark. Other benchmark may give considerably lower figures.

1.5.2 Locality

Since using data in cache is cheaper than getting data from main memory, a programmer obviously wants to code in such a way that data in cache is reused. While placing data in cache is not under explicit programmer control, even from assembly language, in most CPUs⁹, it is still possible, knowing the behaviour of the caches, to know what data is in cache, and to some extent to control it.

The two crucial concepts here are *temporal locality* and *spatial locality*. Temporal locality is the easiest to explain: this describes the use of a data element within a short time of its last use. Since most caches have

9. Low level memory access can be controlled by the programmer in the Cell processor and in some GPUs.

a LRU replacement policy (section 1.3.4.4), if in between the two references less data has been referenced than the cache size, the element will still be in cache and therefore be quickly accessible. With other replacement policies, such as random replacement, this guarantee can not be made.

1.5.2.1 Temporal locality

As an example of temporal locality, consider the repeated use of a long vector:

```
for (loop=0; loop<10; loop++) {
    for (i=0; i<N; i++) {
        ... = ... x[i] ...
    }
}
```

Each element of x will be used 10 times, but if the vector (plus other data accessed) exceeds the cache size, each element will be flushed before its next use. Therefore, the use of $x[i]$ does not exhibit temporal locality: subsequent uses are spaced too far apart in time for it to remain in cache.

If the structure of the computation allows us to exchange the loops:

```
for (i=0; i<N; i++) {
    for (loop=0; loop<10; loop++) {
        ... = ... x[i] ...
    }
}
```

the elements of x are now repeatedly reused, and are therefore more likely to remain in the cache. This rearranged code displays better temporal locality in its use of $x[i]$.

1.5.2.2 Spatial locality

The concept of *spatial locality* is slightly more involved. A program is said to exhibit spatial locality if it references memory that is ‘close’ to memory it already referenced. In the classical von Neumann architecture with only a processor and memory, spatial locality should be irrelevant, since one address in memory can be as quickly retrieved as any other. However, in a modern CPU with caches, the story is different. Above, you have seen two examples of spatial locality:

- Since data is moved in *cache lines* rather than individual words or bytes, there is a great benefit to coding in such a manner that all elements of the cacheline are used. In the loop

```
for (i=0; i<N*s; i+=s) {
    ... x[i] ...
}
```

spatial locality is a decreasing function of the *stride* s .

Let S be the cacheline size, then as s ranges from $1 \dots S$, the number of elements used of each cacheline goes down from S to 1. Relatively speaking, this increases the cost of memory traffic

- in the loop: if $s = 1$, we load $1/S$ cachelines per element; if $s = S$, we load one cacheline for each element. This effect is demonstrated in section 1.6.4.
- A second example of spatial locality worth observing involves the TLB (section 1.3.8). If a program references elements that are close together, they are likely on the same memory page, and address translation through the TLB will be fast. On the other hand, if a program references many widely disparate elements, it will also be referencing many different pages. The resulting TLB misses are very costly; see also section 1.6.5.

1.5.2.3 Examples of locality

Exercise 1.11. Consider the following pseudocode of an algorithm for summing n numbers $x[i]$ where n is a power of 2:

```
for s=2,4,8,...,n/2,n:
    for i=0 to n-1 with steps s:
        x[i] = x[i] + x[i+s/2]
    sum = x[0]
```

Analyze the spatial and temporal locality of this algorithm, and contrast it with the standard algorithm

```
sum = 0
for i=0,1,2,...,n-1
    sum = sum + x[i]
```

Let us examine locality issues for a realistic example. The matrix-matrix multiplication $C \leftarrow A \cdot B$ can be computed in several ways. We compare two implementations, assuming that all matrices are stored by rows, and that the cache size is insufficient to store a whole row or column.

<pre>for i=1..n for j=1..n for k=1..n c[i,j] += a[i,k]*b[k,j]</pre>	<pre>for i=1..n for k=1..n for j=1..n c[i,j] += a[i,k]*b[k,j]</pre>
---	---

These implementations are illustrated in figure 1.8. The first implementation constructs the (i, j) element




Figure 1.8: Two loop orderings for the $C \leftarrow A \cdot B$ matrix-matrix product

of C by the inner product of a row of A and a column of B , in the second a row of C is updated by scaling

rows of B by elements of A .

Our first observation is that both implementations indeed compute $C \leftarrow C + A \cdot B$, and that they both take roughly $2n^3$ operations. However, their memory behaviour, including spatial and temporal locality is very different.

- c[i, j] In the first implementation, $c[i, j]$ is invariant in the inner iteration, which constitutes temporal locality, so it can be kept in register. As a result, each element of C will be loaded and stored only once.
In the second implementation, $c[i, j]$ will be loaded and stored in each inner iteration. In particular, this implies that there are now n^3 store operations, a factor of n more than the first implementation.
- a[i, k] In both implementations, $a[i, k]$ elements are accessed by rows, so there is good spatial locality, as each loaded cacheline will be used entirely. In the second implementation, $a[i, k]$ is invariant in the inner loop, which constitutes temporal locality; it can be kept in register. As a result, in the second case A will be loaded only once, as opposed to n times in the first case.
- b[k, j] The two implementations differ greatly in how they access the matrix B . First of all, $b[k, j]$ is never invariant so it will not be kept in register, and B engenders n^3 memory loads in both cases. However, the access patterns differ.
In second case, $b[k, j]$ is access by rows so there is good spatial locality: cachelines will be fully utilized after they are loaded.
In the first implementation, $b[k, j]$ is accessed by columns. Because of the row storage of the matrices, a cacheline contains a part of a row, so for each cacheline loaded, only one element is used in the columnwise traversal. This means that the first implementation has more loads for B by a factor of the cacheline length. There may also be TLB effects.

Note that we are not making any absolute predictions on code performance for these implementations, or even relative comparison of their runtimes. Such predictions are very hard to make. However, the above discussion identifies issues that are relevant for a wide range of classical CPUs.

Exercise 1.12. There are more algorithms for computing the product $C \leftarrow A \cdot B$. Consider the following:

```
for k=1..n:
    for i=1..n:
        for j=1..n:
            c[i, j] += a[i, k]*b[k, j]
```

Analyze the memory traffic for the matrix C , and show that it is worse than the two algorithms given above.

1.5.2.4 Core locality

The above concepts of spatial and temporal locality were mostly properties of programs, although hardware properties such as cacheline length and cache size play a role in analyzing the amount of locality. There is a third type of locality that is more intimately tied to hardware: *core locality*.

A code's execution is said to exhibit core locality if write accesses that are spatially or temporally close are performed on the same core or processing unit. The issue here is that of *cache coherence* (section 1.4.1)

where two cores both have a copy of a certain cacheline in their local stores. If they both read from it there is no problem. However, if one of them writes to it, the coherence protocol will copy the cacheline to the other core's local store. This takes up precious memory bandwidth, so it is to be avoided.

Core locality is not just a property of a program, but also to a large extent of how the program is executed in parallel.

1.6 Programming strategies for high performance

In this section we will look at how different ways of programming can influence the performance of a code. This will only be an introduction to the topic; for further discussion see the book by Goedeker and Hoisie [52].

The full listings of the codes and explanations of the data graphed here can be found in appendix D. All performance results were obtained on the *AMD Opteron* processors of the Ranger computer [111].

1.6.1 Peak performance

For marketing purposes, it may be desirable to define a ‘top speed’ for a CPU. Since a pipelined floating point unit can yield one result per cycle asymptotically, you would calculate the theoretical *peak performance* as the product of the clock speed (in ticks per second), number of floating point units, and the number of cores; see section 1.4. This top speed is unobtainable in practice, and very few codes come even close to it. The *Linpack benchmark* is one of the measures how close you can get to it; the parallel version of this benchmark is reported in the ‘top 500’; see section 2.10.6.

1.6.2 Pipelining

In section 1.2.1 you learned that the floating point units in a modern CPU are pipelined, and that pipelines require a number of independent operations to function efficiently. The typical pipelineable operation is a vector addition; an example of an operation that can not be pipelined is the inner product accumulation

```
for (i=0; i<N; i++)
    s += a[i]*b[i]
```

The fact that *s* gets both read and written halts the addition pipeline. One way to fill the *floating point pipeline* is to apply *loop unrolling*:

```
for (i = 0; i < N/2-1; i++) {
    sum1 += a[2*i] * b[2*i];
    sum2 += a[2*i+1] * b[2*i+1];
}
```

Now there are two independent multiplies in between the accumulations. With a little indexing optimization this becomes:

1. Sequential Computing

```
for (i = 0; i < N/2-1; i++) {
    sum1 += *(a + 0) * *(b + 0);
    sum2 += *(a + 1) * *(b + 1);

    a += 2; b += 2;
}
```

A first observation about this code is that we are implicitly using associativity and commutativity of addition: while the same quantities are added, they are now in effect added in a different order. As you will see in chapter 3, in computer arithmetic this is not guaranteed to give the exact same result.

In a further optimization, we disentangle the addition and multiplication part of each instruction. The hope is that while the accumulation is waiting for the result of the multiplication, the intervening instructions will keep the processor busy, in effect increasing the number of operations per second.

```
for (i = 0; i < N/2-1; i++) {
    temp1 = *(a + 0) * *(b + 0);
    temp2 = *(a + 1) * *(b + 1);

    sum1 += temp1; sum2 += temp2;

    a += 2; b += 2;
}
```

Finally, we realize that the furthest we can move the addition away from the multiplication, is to put it right in front of the multiplication *of the next iteration*:

```
for (i = 0; i < N/2-1; i++) {
    sum1 += temp1;
    temp1 = *(a + 0) * *(b + 0);

    sum2 += temp2;
    temp2 = *(a + 1) * *(b + 1);

    a += 2; b += 2;
}
s = temp1 + temp2;
```

Of course, we can unroll the operation by more than a factor of two. While we expect an increased performance because of the longer sequence of pipelined operations, large unroll factors need large numbers of registers. Asking for more registers than a CPU has is called *register spill*, and it will decrease performance.

Another thing to keep in mind is that the total number of operations is unlikely to be divisible by the unroll factor. This requires *cleanup code* after the loop to account for the final iterations. Thus, unrolled code is harder to write than straight code, and people have written tools to perform such *source-to-source transformations* automatically.

Cycle times for unrolling the inner product operation up to six times are given in table 1.2. Note that the timings do not show a monotone behaviour at the unrolling by four. This sort of variation is due to various memory-related factors.

1	2	3	4	5	6
6794	507	340	359	334	528

Table 1.2: Cycle times for the inner product operation, unrolled up to six times

1.6.3 Cache size

Above, you learned that data from L1 can be moved with lower latency and higher bandwidth than from L2, and L2 is again faster than L3 or memory. This is easy to demonstrate with code that repeatedly access the same data:

```
for (i=0; i<NRUNS; i++)
    for (j=0; j<size; j++)
        array[j] = 2.3*array[j]+1.2;
```

If the size parameter allows the array to fit in cache, the operation will be relatively fast. As the size of the dataset grows, parts of it will evict other parts from the L1 cache, so the speed of the operation will be determined by the latency and bandwidth of the L2 cache. This can be seen in figure 1.9. The full code is




Figure 1.9: Average cycle count per operation as function of the dataset size

given in section D.2.

1. Sequential Computing

Exercise 1.13. Argue that with a large enough problem and an LRU replacement policy (section 1.3.4.4) essentially all data in the L1 will be replaced in every iteration of the outer loop. Can you write an example code that will let some of the L1 data stay resident?

Often, it is possible to arrange the operations to keep data in L1 cache. For instance, in our example, we could write

```
for (b=0; b<size/l1size; b++) {  
    blockstart = 0;  
    for (i=0; i<NRUNS; i++) {  
        for (j=0; j<l1size; j++)  
            array[blockstart+j] = 2.3*array[blockstart+j]+1.2;  
    }  
    blockstart += l1size;  
}
```

assuming that the L1 size divides evenly in the dataset size. This strategy is called *cache blocking* or *blocking for cache reuse*.

Exercise 1.14. To arrive at the blocked code, the loop over j was split into a loop over blocks and an inner loop over the elements of the block; the outer loop over i was then exchanged with the loop over the blocks. In this particular example you could also simply exchange the i and j loops. Why may this not be optimal for performance?

1.6.4 Cache lines

Since data is moved from memory to cache in consecutive chunks named cachelines (see section 1.3.4.5), code that does not utilize all data in a cacheline pays a bandwidth penalty. This is born out by a simple code

```
for (i=0, n=0; i<L1WORDS; i++, n+=stride)  
    array[n] = 2.3*array[n]+1.2;
```

Here, a fixed number of operations is performed, but on elements that are at distance $stride$. As this $stride$ increases, we expect an increasing runtime, which is born out by the graph in figure 1.10.

The graph also shows a decreasing reuse of cachelines, defined as the number of vector elements divided by the number of L1 misses (on stall; see section 1.3.5).

The full code is given in section D.3.

1.6.5 TLB

As explained in section 1.3.8, the Translation Look-aside Buffer (TLB) maintains a small list of frequently used memory pages and their locations; addressing data that are located on one of these pages is much faster than data that are not. Consequently, one wants to code in such a way that the number of pages accessed is kept low.

Consider code for traversing the elements of a two-dimensional array in two different ways.




Figure 1.10: Run time in kcycles and L1 reuse as a function of stride

```

#define INDEX(i, j, m, n) i+j*m
array = (double*) malloc(m*n*sizeof(double));

/* traversal #1 */
for (j=0; j<n; j++)
    for (i=0; i<m; i++)
        array[INDEX(i, j, m, n)] = array[INDEX(i, j, m, n)]+1;

/* traversal #2 */
for (i=0; i<m; i++)
    for (j=0; j<n; j++)
        array[INDEX(i, j, m, n)] = array[INDEX(i, j, m, n)]+1;
    
```

The results (see Appendix D.5 for the source code) are plotted in figures 1.12 and 1.11.

Using $m = 1000$ means that, on the *AMD Opteron* which has pages of 512 doubles, we need roughly two pages for each column. We run this example, plotting the number ‘TLB misses’, that is, the number of times a page is referenced that is not recorded in the TLB.

1. In the first traversal this is indeed what happens. After we touch an element, and the TLB records the page it is on, all other elements on that page are used subsequently, so no further TLB misses occur. Figure 1.12 shows that, with increasing n , the number of TLB misses per column is roughly two.
2. In the second traversal, we touch a new page for every element of the first row. Elements of the second row will be on these pages, so, as long as the number of columns is less than the number




Figure 1.11: Number of TLB misses per column as function of the number of columns; columnwise traversal of the array.




Figure 1.12: Number of TLB misses per column as function of the number of columns; rowwise traversal of the array.




Figure 1.13: The number of L1 cache misses and the number of cycles for each j column accumulation, vector length 4096

of TLB entries, these pages will still be recorded in the TLB. As the number of columns grows, the number of TLB increases, and ultimately there will be one TLB miss for each element access. Figure 1.11 shows that, with a large enough number of columns, the number of TLB misses per column is equal to the number of elements per column.

1.6.6 Cache associativity

There are many algorithms that work by recursive division of a problem, for instance the *Fast Fourier Transform (FFT)* algorithm. As a result, code for such algorithms will often operate on vectors whose length is a power of two. Unfortunately, this can cause conflicts with certain architectural features of a CPU, many of which involve powers of two.

In section 1.3.4.7 you saw how the operation of adding a small number of vectors

$$\forall_j: y_j = y_j + \sum_{i=1}^m x_{i,j}$$

is a problem for direct mapped caches or set-associative caches with associativity.

As an example we take the *AMD Opteron*, which has an L1 cache of 64K bytes, and which is two-way set associative. Because of the set associativity, the cache can handle two addresses being mapped to the same cache location, but not three or more. Thus, we let the vectors be of size $n = 4096$ doubles, and we measure the effect in cache misses and cycles of letting $m = 1, 2, \dots$.

First of all, we note that we use the vectors sequentially, so, with a cacheline of eight doubles, we should ideally see a cache miss rate of $1/8$ times the number of vectors m . Instead, in figure 1.13 we see a rate




Figure 1.14: The number of L1 cache misses and the number of cycles for each j column accumulation, vector length $4096 + 8$

approximately proportional to m , meaning that indeed cache lines are evicted immediately. The exception here is the case $m = 1$, where the two-way associativity allows the cachelines of two vectors to stay in cache.

Compare this to figure 1.14, where we used a slightly longer vector length, so that locations with the same j are no longer mapped to the same cache location. As a result, we see a cache miss rate around $1/8$, and a smaller number of cycles, corresponding to a complete reuse of the cache lines.

Two remarks: the cache miss numbers are in fact lower than the theory predicts, since the processor will use prefetch streams. Secondly, in figure 1.14 we see a decreasing time with increasing m ; this is probably due to a progressively more favourable balance between load and store operations. Store operations are more expensive than loads, for various reasons.

1.6.7 Loop tiling

In some cases performance can be increased by breaking up a loop into two nested loops, an outer one for the blocks in the iteration space, and an inner one that goes through the block:

```
for (i=0; i<n; i++)
    ...

```

becomes

```
bs = ... /* the blocksize */
nblocks = n/bs /* assume that n is a multiple of bs */
for (b=0; b<nblocks; b++)
```

```

for (i=b*bs, j=0; j<bs; i++, j++)
    ...

```

For a single loop this may not make any difference, but given the right context it may. For instance, if an array is repeatedly used, but it is too large to fit into cache:

```

for (n=0; n<10; n++)
    for (i=0; i<100000; i++)
        ... = ...x[i] ...

```

then loop tiling may lead to a situation where the array is divided into blocks that will fit in cache:

```

bs = ... /* the blocksize */
for (b=0; b<100000/bs; b++)
    for (n=0; n<10; n++)
        for (i=b*bs; i<(b+1)*bs; i++)
            ... = ...x[i] ...

```

For this reason, loop tiling is also known as *cache blocking*. The block size depends on how much data is accessed in the loop body; ideally you would try to make data reused in L1 cache, but it is also possible to block for L2 reuse. Of course, L2 reuse will not give as high a performance as L1 reuse.

Exercise 1.15. Analyze this example. When is *x* brought into cache, when is it reused, and when is it flushed? What is the required cache size in this example? Rewrite this example, using a constant

```
#define L1SIZE 65536
```

In section 1.5.2 we looked at the matrix-matrix multiplication, and concluded that little data could be kept in cache. With loop tiling we can improve this situation. For instance, the standard way of writing this product

```

for i=1..n
    for j=1..n
        for k=1..n
            c[i, j] += a[i, k]*b[k, j]

```

can only be optimized to keep *c*[*i*, *j*] in register:

```

for i=1..n
    for j=1..n
        s = 0
        for k=1..n
            s += a[i, k]*b[k, j]
        c[i, j] += s

```

1. Sequential Computing

Using loop tiling we can easily keep parts of $a[i, :]$ in cache, assuming that a is stored by rows:

```
for kk=1..n/bs
    for i=1..n
        for j=1..n
            s = 0
            for k=(kk-1)*bs+1..kk*bs
                s += a[i,k]*b[k,j]
            c[i,j] += s
```

1.6.8 Case study: Matrix-vector product

Let us consider in some detail the matrix-vector product

$$\forall_{i,j} : y_i \leftarrow a_{ij} \cdot x_j$$

This involves $2n^2$ operations on $n^2 + 2n$ data items, so reuse is $O(1)$: memory accesses and operations are of the same order. However, we note that there is a double loop involved, and the x, y vectors have only a single index, so each element in them is used multiple times.

Exploiting this theoretical reuse is not trivial. In

```
/* variant 1 */
for (i)
    for (j)
        y[i] = y[i] + a[i][j] * x[j];
```

the element $y[i]$ seems to be reused. However, the statement as given here would write $y[i]$ to memory in every inner iteration, and we have to write the loop as

```
/* variant 2 */
for (i) {
    s = 0;
    for (j)
        s = s + a[i][j] * x[j];
    y[i] = s;
}
```

to ensure reuse. This variant uses $2n^2$ loads and n stores.

This code fragment only exploits the reuse of y explicitly. If the cache is too small to hold the whole vector x plus a column of a , each element of x is still repeatedly loaded in every outer iteration.

Reversing the loops as

```
/* variant 3 */
for (j)
```

```

for (i)
    y[i] = y[i] + a[i][j] * x[j];

```

exposes the reuse of x , especially if we write this as

```

/* variant 3 */
for (j) {
    t = x[j];
    for (i)
        y[i] = y[i] + a[i][j] * t;
}

```

but now y is no longer reused. Moreover, we now have $2n^2+n$ loads, comparable to variant 2, but n^2 stores, which is of a higher order.

It is possible to get reuse both of x and y , but this requires more sophisticated programming. The key here is split the loops into blocks. For instance:

```

for (i=0; i<M; i+=2) {
    s1 = s2 = 0;
    for (j) {
        s1 = s1 + a[i][j] * x[j];
        s2 = s2 + a[i+1][j] * x[j];
    }
    y[i] = s1; y[i+1] = s2;
}

```

This is also called *loop unrolling*, or *strip mining*. The amount by which you unroll loops is determined by the number of available registers.

1.6.9 Optimization strategies

Figures 1.15 and 1.16 show that there can be wide discrepancy between the performance of naive implementations of an operation (sometimes called the ‘reference implementation’), and optimized implementations. Unfortunately, optimized implementations are not simple to find. For one, since they rely on blocking, their loop nests are double the normal depth: the matrix-matrix multiplication becomes a six-deep loop. Then, the optimal block size is dependent on factors like the target architecture.

We make the following observations:

- Compilers are not able to extract anywhere close to optimal performance¹⁰.
- There are *autotuning* projects for automatic generation of implementations that are tuned to the architecture. This approach can be moderately to very successful. Some of the best known of these projects are Atlas [131] for Blas kernels, and Spiral [110] for transforms.

10. Presenting a compiler with the reference implementation may still lead to high performance, since some compilers are trained to recognize this operation. They will then forego translation and simply replace it by an optimized variant.

1. Sequential Computing




Figure 1.15: Performance of naive and optimized implementations of the Discrete Fourier Transform




Figure 1.16: Performance of naive and optimized implementations of the matrix-matrix product

1.6.10 Cache aware and cache oblivious programming

Unlike registers and main memory, both of which can be addressed in (assembly) code, use of caches is implicit. There is no way a programmer can load data explicitly to a certain cache, even in assembly language.

However, it is possible to code in a ‘cache aware’ manner. Suppose a piece of code repeatedly operates on an amount of data that less than the cache size. We can assume that the first time the data is accessed, it is brought into cache; the next time it is accessed it will already be in cache. On the other hand, if the amount of data is more than the cache size¹¹, it will partly or fully be flushed out of cache in the process of accessing it.

We can experimentally demonstrate this phenomenon. With a very accurate counter, the code fragment

11. We are conveniently ignoring matters of set-associativity here, and basically assuming a fully associative cache.

```

for (x=0; x<NX; x++)
    for (i=0; i<N; i++)
        a[i] = sqrt(a[i]);
    
```

will take time linear in N up to the point where a fills the cache. An easier way to picture this is to compute a normalized time, essentially a time per execution of the inner loop:

```

t = time();
for (x=0; x<NX; x++)
    for (i=0; i<N; i++)
        a[i] = sqrt(a[i]);
t = time() - t;
t_normalized = t / (N * NX);
    
```

The normalized time will be constant until the array a fills the cache, then increase and eventually level off again. (See section 1.6.3 for an elaborate discussion.)

The explanation is that, as long as $a[0] \dots a[N-1]$ fit in L1 cache, the inner loop will use data from the L1 cache. Speed of access is then determined by the latency and bandwidth of the L1 cache. As the amount of data grows beyond the L1 cache size, some or all of the data will be flushed from the L1, and performance will be determined by the characteristics of the L2 cache. Letting the amount of data grow even further, performance will again drop to a linear behaviour determined by the bandwidth from main memory.

If you know the cache size, it is possible in cases such as above to arrange the algorithm to use the cache optimally. However, the cache size is different per processor, so this makes your code not portable, or at least its high performance is not portable. Also, blocking for multiple levels of cache is complicated. For these reasons, some people advocate *cache oblivious programming* [47].

Cache oblivious programming can be described as a way of programming that automatically uses all levels of the *cache hierarchy*. This is typically done by using a *divide-and-conquer* strategy, that is, recursive subdivision of a problem.

As a simple example of cache oblivious programming is the matrix transpose operation $B \leftarrow A^t$. First we observe that each element of either matrix is accessed once, so the only reuse is in the utilization of cache lines. If both matrices are stored by rows and we traverse B by rows, then A is traversed by columns, and for each element accessed one cacheline is loaded. If the number of rows times the number of elements per cacheline is more than the cachesize, lines will be evicted before they can be reused.

In a cache oblivious implementation we divide A and B as 2×2 block matrices, and recursively compute $B_{11} \leftarrow A_{11}^t$, $B_{12} \leftarrow A_{21}^t$, et cetera; see figure 1.17. At some point in the recursion, blocks A_{ij} will now be small enough that they fit in cache, and the cachelines of A will be fully used. Hence, this algorithm improves on the simple one by a factor equal to the cacheline size.

The cache oblivious strategy can often yield improvement, but it is not necessarily optimal. In the matrix-matrix product it improves on the naive algorithm, but it is not as good as an algorithm that is explicitly designed to make optimal use of caches [57].




Figure 1.17: Matrix transpose operation, with simple and recursive traversal of the source matrix

1.7 Power consumption

Another important topic in high performance computers is their power consumption. Here we need to distinguish between the power consumption of a single processor chip, and that of a complete cluster.

As the number of components on a chip grows, its power consumption would also grow. Fortunately, in a counter acting trend, miniaturization of the chip features has simultaneously been reducing the necessary power. Suppose that the feature size λ (think: thickness of wires) is scaled down to $s\lambda$ with $s < 1$. In order to keep the electric field in the transistor constant, the length and width of the channel, the oxide thickness, substrate concentration density and the operating voltage are all scaled by the same factor.

This is known as *constant field scaling* or *Dennard scaling* [11, 26], and it can be considered the driving force behing *Moore's law*, which states that the number of transistors in a processor doubles every 18 months.

The net result is that the dynamic power consumption P is scaled to s^2P , circuit delay T is scaled to sT , and operating frequency F is changed to F/s . Correspondingly, the energy consumption is scaled by s^3 , and this gives us the space to put more components on a chip.

At the time of this writing (circa 2010), miniaturization of components has almost come to a standstill, because further lowering of the voltage would give prohibitive leakage. Conversely, the frequency can not be scaled up since this would raise the heat production of the chip too far. Figure 1.18 gives a dramatic illustration of the heat that a chip would give off, if single-processor trends had continued.

One conclusion is that computer design is running into a *power wall*, where the sophistication of a single core can not be increased any further (so we can for instance no longer increase *ILP* and *pipeline depth*) and the only way to increase pwerformance is to increase the amount of explicitly visible parallelism. This development has led to the current generation of *multicore* processors; see section 1.4. It is also the reason GPUs with their simplified processor design and hence lower energy consumption are attractive; the same holds for Field-Programmable Gate Arrays (FPGAs).

We can characterize this shift as one from larger cores, higher frequency, and higher power, to one where process technology, larger integration, and new micro-architectures come together for more power-efficient performance [?].

The total power consumption of a parallel computer is determined by the consumption per processor and




Figure 1.18: Projected heat dissipation of a CPU if trends had continued – this graph courtesy Pat Helsingr

the number of processors in the full machine. At present, this is commonly several Megawatts. By the above reasoning, the increase in power needed from increasing the number of processors can no longer be offset by more power-effective processors, so power is becoming the overriding consideration as parallel computers move from the petascale (attained in 2008 by the *IBM Roadrunner*) to a projected exascale.

In the most recent generations of processors, power is becoming an overriding consideration, with influence in unlikely places. For instance, the Single Instruction Multiple Data (SIMD) design of processors (see section 2.2.1, in particular section 2.2.1.2) is dictated by the power cost of instruction decoding.

Chapter 2

Parallel Computing

The largest and most powerful computers are sometimes called ‘supercomputers’. For the last two decades, this has, without exception, referred to parallel computers: machines with more than one CPU that can be set to work on the same problem.

Parallelism is hard to define precisely, since it can appear on several levels. In the previous chapter you already saw how inside a CPU several instructions can be ‘in flight’ simultaneously. This is called *instruction-level parallelism*, and it is outside explicit user control: it derives from the compiler and the CPU deciding which instructions, out of a single instruction stream, can be processed simultaneously. At the other extreme is the sort of parallelism where more than one instruction stream is handled by multiple processors, often each on their own circuit board. This type of parallelism is typically explicitly scheduled by the user.

In this chapter, we will analyze this more explicit type of parallelism, the hardware that supports it, the programming that enables it, and the concepts that analyze it.

For further reading, a good introduction to parallel computers and parallel programming is Wilkinson and Allen [133].

2.1 Introduction

In scientific codes, there is often a large amount of work to be done, and it is often regular to some extent, with the same operation being performed on many data. The question is then whether this work can be sped up by use of a parallel computer. If there are n operations to be done, and they would take time t on a single processor, can they be done in time t/p on p processors?

Let us start with a very simple example. Adding two vectors of length n

```
for (i=0; i<n; i++)
    a[i] = b[i] + c[i];
```

can be done with up to n processors. In the idealized case with n processors, each processor has local scalars a, b, c and executes the single instruction $a=b+c$. This is depicted in figure 2.1.

In the general case, where each processor executes something like




Figure 2.1: Parallelization of a vector addition

```
for (i=my_low; i<my_high; i++)
    a[i] = b[i] + c[i];
```

execution time is linearly reduced with the number of processors. If each operation takes a unit time, the original algorithm takes time n , and the parallel execution on p processors n/p . The parallel algorithm is faster by a factor of p^1 .

Next, let us consider summing the elements of a vector. We again assume that each processor contains just a single array element. The sequential code:

```
s = 0;
for (i=0; i<n; i++)
    s += x[i]
```

is no longer obviously parallel, but if we recode the loop as

```
for (s=2; s<n; s*=2)
    for (i=0; i<n; i+=s)
        x[i] += x[i+s/2]
```

there is a way to parallelize it: every iteration of the outer loop is now a loop that can be done by n/s processors in parallel. Since the outer loop will go through $\log_2 n$ iterations, we see that the new algorithm has a reduced runtime of $n/p \cdot \log_2 n$. The parallel algorithm is now faster by a factor of $p/\log_2 n$. This is depicted in figure 2.2.

Even from these two simple examples we can see some of the characteristics of parallel computing:

- Sometimes algorithms need to be rewritten slightly to make them parallel.
- A parallel algorithm may not show perfect speedup.

1. We ignore lower order errors in this result when p does not divide perfectly in n . We will also, in general, ignore matters of loop overhead.




Figure 2.2: Parallelization of a vector addition

There are other things to remark on. In the first case, if each processor has its x_i, y_i in a local store the algorithm can be executed without further complications. In the second case, processors need to communicate data among each other and we haven't assigned a cost to that yet.

First let us look systematically at communication. We can take the second half of figure 2.2 and turn it into a tree graph (see Appendix A.5) by defining the inputs as leave nodes, all partial sums as interior nodes, and the root as the total sum. This is illustrated in figure 2.3. In this figure nodes are horizontally aligned with other computations that can be performed simultaneously; each level is sometimes called a *superstep* in the computation. Nodes are vertically aligned if they are computed on the same processor, and an arrow corresponds to a communication if it goes from one processor to another. The vertical alignment in




Figure 2.3: Communication structure of a parallel vector addition

figure 2.3 is not the only one possible. If nodes are shuffled within a superstep or horizontal level, a different communication pattern arises.

Exercise 2.1. Consider placing the nodes within a superstep on random processors. Show that,

if no two nodes wind up on the same processor, at most twice the number of communications is performed from the case in figure 2.3.

Exercise 2.2. Can you draw the graph of a computation that leaves the sum result on each processor? There is a solution that takes twice the number of supersteps, and there is one that takes the same number. In both cases the graph is no longer a tree, but a more general Directed Acyclic Graph (DAG).

Processors are often connected through a network, and moving data through this network takes time. This introduces a concept of distance between the processors. This is easily see in figure 2.3 where the processors are linearly ordered. If the network only connects a processor with its immediate neighbours, each iteration of the outer loop increases the distance over which communication takes place.

Exercise 2.3. Assume that an addition takes a certain unit time, and that moving a number from one processor to another takes that same unit time. Show that the communication time equals the computation time.

Now assume that sending a number from processor p to $p \pm k$ takes time k . Show that the execution time of the parallel algorithm now is of the same order as the sequential time.

The summing example made the unrealistic assumption that every processor initially stored just one vector element: in practice we will have $P < N$, and every processor stores a number of vector elements. The obvious strategy is to give each processor a consecutive stretch of elements, but sometimes the obvious strategy is not the best.

Exercise 2.4. Consider the case of summing 8 elements with 4 processors. Show that some of the edges in the graph of figure 2.3 no longer correspond to actual communications. Now consider summing 16 elements with, again, 4 processors. What is the number of communication edges this time?

These matters of algorithm adaptation, efficiency, and communication, are crucial to all of parallel computing. We will return to these issues in various guises throughout this chapter.

2.2 Parallel Computers Architectures

For quite a while now, the top computers have been some sort of parallel computer, that is, an architecture that allows the simultaneous execution of multiple instructions or instruction sequences. One way of characterizing the various forms this can take is due to Flynn [43]. Flynn's taxonomy distinguishes between whether one or more different instructions are executed simultaneously, and between whether that happens on one or more data items. The following four types result, which we will discuss in more detail below:

SISD Single Instruction Single Data: this is the traditional CPU architecture: at any one time only a single instruction is executed, operating on a single data item.

SIMD Single Instruction Multiple Data: in this computer type there can be multiple processors, each operating on its own data item, but they are all executing the same instruction on that data item. Vector computers (section 2.2.1.1) are typically also characterized as SIMD.

MISD Multiple Instruction Single Data. No architectures answering to this description exist; one could argue that redundant computations for safety-critical applications are an example of MISD.

MIMD Multiple Instruction Multiple Data: here multiple CPUs operate on multiple data items, each executing independent instructions. Most current parallel computers are of this type.

2.2.1 SIMD

Parallel computers of the SIMD type apply the same operation simultaneously to a number of data items. The design of the CPUs of such a computer can be quite simple, since the arithmetic unit does not need separate logic and instruction decoding units: all CPUs execute the same operation in lock step. This makes SIMD computers excel at operations on arrays, such as

```
for (i=0; i<N; i++) a[i] = b[i]+c[i];
```

and, for this reason, they are also often called *array processors*. Scientific codes can often be written so that a large fraction of the time is spent in array operations.

On the other hand, there are operations that cannot be executed efficiently on an array processor. For instance, evaluating a number of terms of a recurrence $x_{i+1} = ax_i + b_i$ involves many additions and multiplications, but they alternate, so only one operation of each type can be processed at any one time. There are no arrays of numbers here that are simultaneously the input of an addition or multiplication.

In order to allow for different instruction streams on different parts of the data, the processor would have a ‘mask bit’ that could be set to prevent execution of instructions. In code, this typically looks like

```
where (x>0) {
    x[i] = sqrt(x[i])
```

The programming model where identical operations are applied to a number of data items simultaneously, is known as *data parallelism*.

Such array operations can occur in the context of physics simulations, but another important source is graphics applications. For this application, the processors in an array processor can be much weaker than the processor in a PC: often they are in fact bit processors, capable of operating on only a single bit at a time. Along these lines, ICL had the 4096 processor DAP [75] in the 1980s, and Goodyear built a 16K processor MPP [6] in the 1970s.

Later, the Connection Machine (CM-1, CM-2, CM-5) were quite popular. While the first Connection Machine had bit processors (16 to a chip), the later models had traditional processors capable of floating point arithmetic, and were not true SIMD architectures. All were based on a hyper-cube interconnection network; see section 2.6.4. Another manufacturer that had a commercially successful array processor was MasPar.

Supercomputers based on array processing do not exist anymore, but the notion of SIMD lives on in various guises. For instance, GPUs are SIMD-based, enforced through their CUDA programming language. Also, the *Intel Xeon Phi* has a strong SIMD component. While early SIMD architectures were motivated by minimizing the number of transistors necessary, these modern co-processors are motivated by *power efficiency* considerations. Processing instructions (known as *instruction issue*) is actually expensive compared to a floating point operation. Using SIMD is then a way to economize.

2.2.1.1 Pipelining

A number of computers have been based on a *vector processor* or *pipeline processor* design. The first commercially successful supercomputers, the Cray-1 and the Cyber-205 were of this type. In recent times, the Cray-X1 and the NEC SX series have featured vector pipes. The ‘Earth Simulator’ computer [115], which led the TOP500 (section 2.10.6) for 3 years, was based on NEC SX processors. The general idea behind pipelining was described in section 1.2.1.

While supercomputers based on pipeline processors are in a distinct minority, pipelining is now mainstream in the superscalar CPUs that are the basis for clusters. A typical CPU has pipelined floating point units, often with separate units for addition and multiplication; see section 1.2.1.

However, there are some important differences between pipelining in a modern superscalar CPU and in, more old-fashioned, vector units. The pipeline units in these vector computers are not integrated floating point units in the CPU, but can better be considered as attached vector units to a CPU that itself has a floating point unit. The vector unit has vector registers² with a typical length of 64 floating point numbers; there is typically no ‘vector cache’. The logic in vector units is also simpler, often addressable by explicit vector instructions. Superscalar CPUs, on the other hand, are fully integrated in the CPU and geared towards exploiting data streams in unstructured code.

2.2.1.2 True SIMD in CPUs and GPUs

True SIMD array processing can be found in modern CPUs and GPUs, in both cases inspired by the parallelism that is needed in graphics applications.

Modern CPUs from Intel and AMD, as well as PowerPC chips, have instructions that can perform multiple instances of an operation simultaneously. On Intel processors this is known as *SIMD Streaming Extensions* (SSE) or *Advanced Vector Extensions* (AVX). These extensions were originally intended for graphics processing, where often the same operation needs to be performed on a large number of pixels. Often, the data has to be a total of, say, 128 bits, and this can be divided into two 64-bit reals, four 32-bit reals, or a larger number of even smaller chunks such as 4 bits.

The AVX instructions are based on up to 512-bit wide SIMD, that is, eight floating point numbers can be processed simultaneously. Somewhat surprisingly, this is mostly motivated by power considerations. Decoding instructions is actually more power consuming than executing them, so SIMD parallelism is a way to save power.

Current compilers can generate SSE or AVX instructions automatically; sometimes it is also possible for the user to insert pragmas, for instance with the Intel compiler:

```
void func(float *restrict c, float *restrict a,
          float *restrict b, int n)
{
    #pragma vector always
    for (int i=0; i<n; i++)
        c[i] = a[i] * b[i];
```

2. The Cyber205 was an exception, with direct-to-memory architecture.

}

Use of these extensions often requires data to be aligned with cache line boundaries (section 1.3.4.5), so there are special allocate and free calls that return aligned memory.

Array processing on a larger scale can be found in *GPUs*. A GPU contains a large number of simple processors, ordered in groups of 32, typically. Each processor group is limited to executing the same instruction. Thus, this is true example of SIMD processing. For further discussion, see section 2.9.

2.2.2 MIMD / SPMD computers

By far the most common parallel computer architecture these days is called Multiple Instruction Multiple Data (MIMD): the processors execute multiple, possibly differing instructions, each on their own data. Saying that the instructions differ does not mean that the processors actually run different programs: most of these machines operate in *Single Program Multiple Data (SPMD)* mode, where the programmer starts up the same executable on the parallel processors. Since the different instances of the executable can take differing paths through conditional statements, or execute differing numbers of iterations of loops, they will in general not be completely in sync as they were on SIMD machines. If this lack of synchronization is due to processors working on different amounts of data, it is called *load unbalance*, and it is a major source of less than perfect *speedup*; see section 2.10.1.

There is a great variety in MIMD computers. Some of the aspects concern the way memory is organized, and the network that connects the processors. Apart from these hardware aspects, there are also differing ways of programming these machines. We will see all these aspects below. Many machines these days are called *clusters*. They can be built out of custom or commodity processors (if they consist of PCs, running Linux, and connected with Ethernet, they are referred to as Beowulf clusters [62]); since the processors are independent they are examples of the MIMD or SPMD model.

2.2.3 The commoditization of supercomputers

In the 1980s and 1990s supercomputers were radically different from personal computer and mini or super-mini computers such as the DEC PDP and VAX series. The SIMD vector computers had one (*CDC Cyber205* or *Cray-1*), or at most a few (*ETA-10*, *Cray-2*, *Cray X/MP*, *Cray Y/MP*), extremely powerful processors, often a vector processor. Around the mid-1990s clusters with thousands of simpler (micro) processors started taking over from the machines with relative small numbers of vector pipes (see <http://www.top500.org/lists/1994/11>). At first these microprocessors (*IBM Power series*, *Intel i860*, *MIPS*, *DEC Alpha*) were still much more powerful than ‘home computer’ processors, but later this distinction also faded to an extent. Currently, many of the most powerful clusters are powered by essentially the same Intel Xeon and AMD Opteron chips that are available on the consumer market. Others use IBM Power Series or other ‘server’ chips. See section 2.10.6 for illustrations of this history since 1993.

2.3 Different types of memory access

In the introduction we defined a parallel computer as a setup where multiple processors work together on the same problem. In all but the simplest cases this means that these processors need access to a joint pool




Figure 2.4: References to identically named variables in the distributed and shared memory case

of data. In the previous chapter you saw how, even on a single processor, memory can have a hard time keeping up with processor demands. For parallel machines, where potentially several processors want to access the same memory location, this problem becomes even worse. We can characterize parallel machines by the approach they take to the problem of reconciling multiple accesses, by multiple processes, to a joint pool of data.

The main distinction here is between *distributed memory* and *shared memory*. With distributed memory, each processor has its own physical memory, and more importantly its own *address space*. Thus, if two processors refer to a variable x , they access a variable in their own local memory. On the other hand, with shared memory, all processors access the same memory; we also say that they have a *shared address space*. Thus, if two processors both refer to a variable x , they access the same memory location.

2.3.1 Symmetric Multi-Processors: Uniform Memory Access

Parallel programming is fairly simple if any processor can access any memory location. For this reason, there is a strong incentive for manufacturers to make architectures where processors see no difference between one memory location and another: any memory location is accessible to every processor, and the access times do not differ. This is called *Uniform Memory Access (UMA)*, and the programming model for architectures on this principle is often called *Symmetric Multi Processing (SMP)*.

There are a few ways to realize an SMP architecture. Current desktop computers can have a few processors accessing a shared memory through a single memory bus; for instance Apple markets a model with 2 six-core processors. Having a memory bus that is shared between processors works only for small numbers of processors; for larger numbers one can use a *crossbar* that connects multiple processors to multiple memory banks; see section 2.6.5.

On *multicore* processors there is uniform memory access of a different type: the cores typically have a *shared cache*, typically the L3 or L2 cache.

2.3.2 Non-Uniform Memory Access

The UMA approach based on shared memory is obviously limited to a small number of processors. The crossbar networks are expandable, so they would seem the best choice. However, in practice one puts




Figure 2.5: Non-uniform memory access in a four-socket motherboard

processors with a local memory in a configuration with an exchange network. This leads to a situation where a processor can access its own memory fast, and other processors' memory slower. This is one case of so-called *Non-Uniform Memory Access (NUMA)*: a strategy that uses physically distributed memory, abandoning the uniform access time, but maintaining the logically shared address space: each processor can still access any memory location.

Figure 2.5 illustrates NUMA in the case of the four-socket motherboard of the Ranger supercomputer. Each chip has its own memory (8Gb) but the motherboard acts as if the processors have access to a shared pool of 32Gb. Obviously, accessing the memory of another processor is slower than accessing local memory. In addition, note that each processor has three connections that could be used to access other memory, but the rightmost two chips use one connection to connect to the network. This means that accessing each other's memory can only happen through an intermediate processor, slowing down the transfer, and tying up that processor's connections.

While the NUMA approach is convenient for the programmer, it offers some challenges for the system. Imagine that two different processors each have a copy of a memory location in their local (cache) memory. If one processor alters the content of this location, this change has to be propagated to the other processors. If both processors try to alter the content of the one memory location, the behaviour of the program can become undetermined.

Keeping copies of a memory location synchronized is known as *cache coherence* (see section 1.4.1); a multi-processor system using it is sometimes called a 'cache-coherent NUMA' or ccNUMA architecture.

Cache coherence is obviously desirable, since it facilitates parallel programming. However, it carries costs on several levels. It probably requires hardware support from the processors and the network and it complicates the Operating System software. Moreover, keeping caches coherent means that there is data traveling through the network, taking up precious bandwidth.

Among current vendors only SGI (the UV line) and Cray (the XE6) market products with large scale NUMA. Both offer strong support for *Partitioned Global Address Space (PGAS)* languages; see section 2.5.6.

2.3.3 Logically and physically distributed memory

The most extreme solution to the memory access problem is to offer memory that is not just physically, but that is also logically distributed: the processors have their own address space, and can not directly see another processor's memory. This approach is often called 'distributed memory', but this term is unfortunate, since we really have to consider the questions separately whether memory *is* distributed and whether it *appears* distributed. Note that NUMA also has physically distributed memory; the distributed nature of it is just not apparent to the programmer.

With logically *and* physically distributed memory, the only way one processor can exchange information with another is through passing information explicitly through the network. You will see more about this in section 2.5.3.3.

This type of architecture has the significant advantage that it can scale up to large numbers of processors: the *IBM BlueGene* has been built with over 200,000 processors. On the other hand, this is also the hardest kind of parallel system to program.

Various kinds of hybrids between the above types exist. For instance, the *Columbia* computer at NASA consists of twenty nodes, connected by a switch, where each node is an NUMA architecture of 512 processors.

2.3.4 Latency hiding

Communication between processors is typically slow, slower than data transfer from memory on a single processor, and much slower than operating on data. For this reason, it is good to think about the relative volumes of network traffic versus 'useful' operations when designing a parallel program. There has to be enough work per processor to offset the communication.

Another way of coping with the relative slowness of communication is to arrange the program so that the communication actually happens while some computation is going on. This is referred to as *overlapping computation with communication* or *latency hiding*.

For example, consider the parallel execution of a matrix-vector product $y = Ax$ (there will be further discussion of this operation in section 6.1). Assume that the vectors are distributed, so each processor p executes

$$\forall_{i \in I_p} : y_i = \sum_j a_{ij} x_j.$$

Since x is also distributed, we can write this as

$$\forall_{i \in I_p} : y_i = \left(\sum_{j \text{ local}} + \sum_{j \text{ not local}} \right) a_{ij} x_j.$$

This scheme is illustrated in figure 2.6. We can now proceed as follows:

- Start the transfer of non-local elements of x ;
- Operate on the local elements of x while data transfer is going on;




Figure 2.6: The parallel matrix-vector product with a blockrow distribution.

- Make sure that the transfers are finished;
- Operate on the non-local elements of x .

Of course, this scenario presupposes that there is software and hardware support for this overlap. MPI allows for this (see section 2.5.3.6), through so-called *asynchronous communication* or *non-blocking communication* routines. This does not immediately imply that overlap will actually happen, since hardware support is an entirely separate question.

2.4 Granularity of parallelism

Let us take a look at the question ‘how much parallelism is there in a program execution’. There is the theoretical question of the absolutely maximum number of actions that can be taken in parallel, but we also need to wonder what kind of actions these are and how hard it is to actually execute them in parallel, as well as how efficient the resulting execution is.

The discussion in this section will be mostly on a conceptual level; in section 2.5 we will go into some detail on how parallelism can actually be programmed.

2.4.1 Data parallelism

It is fairly common for a program that have loops with a simple body, that gets executed for all elements in a large data set:

```
for (i=0; i<1000000; i++)
    a[i] = 2*b[i];
```

Such code is considered an instance of *data parallelism* or *fine-grained parallelism*. If you had as many processors as array elements, this code would look very simple: each processor would execute the statement

```
a = 2*b
```

on its local data.

If your code consists predominantly of such loops over arrays, it can be executed efficiently with all processors in lockstep. Architectures based on this idea, where the processors can in fact *only* work in lockstep, have existed, see section 2.2.1. Such fully parallel operations on arrays appear in computer graphics, where every pixel of an image is processed independently. For this reason, GPUs (section 2.9) are strongly based on data parallelism.

Continuing the above example for a little bit, consider the operation

```
for  $0 \leq i < \text{max}$  do
     $i_{\text{left}} = \text{mod}(i - 1, \text{max})$ 
     $i_{\text{right}} = \text{mod}(i + 1, \text{max})$ 
     $a_i = (b_{i_{\text{left}}} + b_{i_{\text{right}}})/2$ 
```

On a data parallel machine, that could be implemented as

```
bleft  $\leftarrow \text{shiftright}(\mathbf{b})$ 
bright  $\leftarrow \text{shiftleft}(\mathbf{b})$ 
a  $\leftarrow (\text{bleft} + \text{bright})/2$ 
```

where the `shiftleft/right` instructions cause a data item to be sent to the processor with a number lower or higher by 1. For this second example to be efficient, it is necessary that each processor can communicate quickly with its immediate neighbours, and the first and last processor with each other.

In various contexts such a ‘blurr’ operations in graphics, it makes sense to have operations on 2D data:

```
for  $0 < i < m$  do
    for  $0 < j < n$  do
         $a_{ij} \leftarrow (b_{ij-1} + b_{ij+1} + b_{i-1j} + b_{i+1j})$ 
```

and consequently processors have be able to move data to neighbours in a 2D grid.

2.4.2 Instruction-level parallelism

In *ILP*, the parallelism is still on the level of individual instructions, but these need not be similar. For instance, in

```
 $a \leftarrow b + c$ 
 $d \leftarrow e * f$ 
```

the two assignments are independent, and can therefore be executed simultaneously. This kind of parallelism is too cumbersome for humans to identify, but compilers are very good at this. In fact, identifying ILP is crucial for getting good performance out of modern *superscalar* CPUs.

2.4.3 Task-level parallelism

At the other extreme from data and instruction-level parallelism, *task parallelism* is about identifying whole subprograms that can be executed in parallel. As an example, searching in a tree data structure could be

implemented as follows:

```

if optimal (root) then
    exit

else
    parallel: SearchInTree (leftchild),SearchInTree (rightchild)
        Procedure SearchInTree(root)
    
```

The search tasks in this example are not synchronized, and the number of tasks is not fixed: it can grow arbitrarily. In practice, having too many tasks is not a good idea, since processors are most efficient if they work on just a single task. Tasks can then be scheduled as follows:

```

while there are tasks left do
    wait until a processor becomes inactive;
    spawn a new task on it
    
```

Unlike in the data parallel example above, the assignment of data to processor is not determined in advance in such a scheme. Therefore, this mode of parallelism is most suited for thread-programming, for instance through the OpenMP library; section 2.5.2.

Let us consider a more serious example of task-level parallelism.

A finite element mesh is, in the simplest case, a collection of triangles that covers a 2D object. Since angles that are too acute should be avoided, the *Delaunay mesh refinement* process can take certain triangles, and replace them by better shaped ones. This is illustrated in figure 2.7: the black triangles violate some angle condition, so either they themselves get subdivided, or they are joined with some neighbouring ones (rendered in grey) and then redivided.




Figure 2.7: A mesh before and after refinement

In pseudo-code, this can be implemented as in figure 2.8. (This figure and code are to be found in [82], which also contains a more detailed discussion.)

```

Mesh m /* read in initial mesh */
WorkList wl;
wl.add(mesh.badTriangles());
while (wl.size() != 0) do
    Element e = wl.get(); //get bad triangle
    if (e no longer in mesh) continue;
    Cavity c = new Cavity(e);
    c.expand();
    c.retriangulate();
    mesh.update(c);
    wl.add(c.badTriangles());

```

Figure 2.8: Task queue implementation of Delauney refinement

It is clear that this algorithm is driven by a worklist (or *task queue*) data structure that has to be shared between all processes. Together with the dynamic assignment of data to processes, this implies that this type of *irregular parallelism* is suited to shared memory programming, and is much harder to do with distributed memory.

2.4.4 Conveniently parallel computing

In certain contexts, a simple, often single processor, calculation needs to be performed on many different inputs. Since the computations have no data dependencies and need not done in any particular sequence, this is often called *embarrassingly parallel* or *conveniently parallel* computing. This sort of parallelism can happen at several levels. In examples such as calculation of the *Mandelbrot* set or evaluating moves in a *chess* game, a subroutine-level computation is invoked for many parameter values. On a coarser level it can be the case that a simple program needs to be run for many inputs. In this case, the overall calculation is referred to as a *parameter sweep*.

2.4.5 Medium-grain data parallelism

The above strict realization of data parallelism assumes that there are as many processors as data elements. In practice, processors will have much more memory than that, and the number of data elements is likely to be far larger than the processor count of even the largest computers. Therefore, arrays are grouped onto processors in subarrays. The code then looks like this:

```

my_lower_bound = // some processor-dependent number
my_upper_bound = // some processor-dependent number
for (i=my_lower_bound; i<my_upper_bound; i++)
    // the loop body goes here

```

This model has some characteristics of data parallelism, since the operation performed is identical on a large number of data items. It can also be viewed as task parallelism, since each processor executes a larger section of code, and does not necessarily operate on equal sized chunks of data.

2.5 Parallel programming

Parallel programming is more complicated than sequential programming. While for sequential programming most programming languages operate on similar principles (some exceptions such as functional or logic languages aside), there is a variety of ways of tackling parallelism. Let's explore some of the concepts and practical aspects.

There are various approaches to parallel programming. First of all, there does not seem to be any hope of a *parallelizing compiler* that can automagically transform a sequential program into a parallel one. Apart from the problem of figuring out which operations are independent, the main problem is that the problem of locating data in a parallel context is very hard. A compiler would need to consider the whole code, rather than a subroutine at a time. Even then, results have been disappointing.

More productive is the approach where the user writes mostly a sequential program, but gives some indications about what computations can be parallelized, and how data should be distributed. Indicating parallelism of operations explicitly is done in OpenMP (section 2.5.2); indicating the data distribution and leaving parallelism to the compiler and runtime is the basis for PGAS languages (section 2.5.6). Such approaches work best with shared memory.

By far the hardest way to program in parallel, but with the best results in practice, is to expose the parallelism to the programmer and let the programmer manage everything explicitly. This approach is necessary in the case of distributed memory programming. We will have a general discussion of distributed programming in section 2.5.3.1; section 2.5.3.3 will discuss the MPI library.

2.5.1 Thread parallelism

As a preliminary to OpenMP (section 2.5.2), we will briefly go into ‘threads’. A *thread* is an independent instruction stream, but as part of a Unix process. While processes can belong to different users, or be different programs that a single user is running concurrently, and therefore have their own data space, threads are part of one process and therefore share each other’s data. Threads do have a possibility of having private data, for instance by have their own data stack, but their main characteristic is that they can collaborate on the same data.

Threads have long existed, even on a single processor. By having more than one thread on a single processor, a higher processor utilization can result, since the instructions of one thread can be processed while another thread is waiting for data. On traditional CPUs, switching between threads is fairly expensive (an exception is the *hyper-threading* mechanism) but on GPUs it is not, and in fact they *need* many threads to attain high performance.

In the context of parallel processing we are also interested in threads, sinc in a shared memory context multiple threads running on multiple processors or processor cores can be an easy way to parallelize a computation. The shared memory allows the threads to all see the same data. This can also lead to problems; see section 2.5.1.2.

2.5.1.1 Threads example

The following example³ uses the *pthreads* library to spawn a number of tasks that all update a global counter. Since threads share the same memory space, they indeed see and update the same memory location.

```
#include <stdlib.h>
#include <stdio.h>
#include "pthread.h"

int sum=0;

void adder() {
    sum = sum+1;
    return;
}

#define NTHREADS 50
int main() {
    int i;
    pthread_t threads[NTHREADS];
    printf("forking\n");
    for (i=0; i<NTHREADS; i++)
        if (pthread_create(threads+i, NULL, &adder, NULL) !=0) return i+1;
    printf("joining\n");
    for (i=0; i<NTHREADS; i++)
        if (pthread_join(threads[i], NULL) !=0) return NTHREADS+i+1;
    printf("Sum computed: %d\n", sum);

    return 0;
}
```

The fact that this code gives the right result is a coincidence: it only happens because updating the variable is so much quicker than creating the thread. (On a multicore processor the chance of errors will greatly increase.) If we artificially increase the time for the update, we will no longer get the right result:

```
void adder() {
    int t = sum; sleep(1); sum = t+1;
    return;
}
```

Now all threads read out the value of `sum`, wait a while (presumably calculating something) and then update.

This can be fixed by having a lock on the code region that should be ‘mutually exclusive’:

3. This is strictly Unix-centric and will not work on Windows.

```

pthread_mutex_t lock;

void adder() {
    int t,r;
    pthread_mutex_lock(&lock);
    t = sum; sleep(1); sum = t+1;
    pthread_mutex_unlock(&lock);
    return;
}

int main() {
    ....
    pthread_mutex_init(&lock,NULL);
}

```

The lock and unlock commands guarantee that no two threads can interfere with each other's update.

For more information on pthreads, see for instance <https://computing.llnl.gov/tutorials-public/pthreads>.

2.5.1.2 Atomic operations

Shared memory makes life easy for the programmer, since every processor has access to all of the data: no explicit data traffic between the processor is needed. On the other hand, multiple processes/processors can also write to the same variable, which is a source of potential problems.

Suppose that two processes both try to increment an integer variable I :

process 1: $I=I+2$

process 2: $I=I+3$

The result depends on the sequence in which the processors read and write the variable. Here are three scenarios:

scenario 1.	scenario 2.	scenario 3.
$I = 0$		
read $I = 0$ compute $I = 2$ write $I = 2$	read $I = 0$ compute $I = 2$ write $I = 3$	read $I = 0$ compute $I = 3$ write $I = 3$
	read $I = 2$ write $I = 2$	
$I = 3$	$I = 2$	$I = 5$

A very practical example of such conflicting updates is the inner product calculation:

```

for (i=0; i<1000; i++)
    sum = sum+a[i]*b[i];

```

Here the products are truly independent, so we could choose to have the loop iterations do them in parallel, for instance by their own threads. However, all threads need to update the same variable `sum`.

For this reason, such updates of a shared variable are called a *critical section* of code. This means that the instructions in the critical section (in the inner product example ‘read `sum` from memory, update it, write back to memory’) need to be executed entirely by one thread before any other thread can start them.

OpenMP has a mechanism to declare a *critical section*, so that it will be executed by only one process at a time.

One way of implementing this, is to set a temporary *lock* on certain memory areas. Locks can for instance be implemented through the *semaphore* mechanism [28]. Surrounding each critical section there will be two atomic operations controlling a semaphore, a sign post. The first process to encounter the semaphore will lower it, and start executing the critical section. Other processes see the lowered semaphore, and wait. When the first process finishes the critical section, it executes the second instruction which raises the semaphore, allowing one of the waiting processes to enter the critical section.

The problem with locks is that they typically exist on the operating system level, so they are relatively slow. Since we hope that iterations of the inner product loop above would be executed at the speed of the floating point unit, or at least that of the memory bus, this is unacceptable.

Another solution to the update problem, is to have *atomic operations*: the update would be implemented in such a way that a second process can not get hold of the data item being updated. One implementation of this is *transactional memory*, where the hardware itself supports atomic operations; the term derives from database transactions, which have a similar integrity problem.

2.5.1.3 Affinity

Thread programming is very flexible, effectively creating parallelism as needed. However, a large part of this book is about the importance of data movement in scientific computations, and that aspect can not be ignored in thread programming.

In the context of a multicore processor, any thread can be scheduled to any core, and there is no immediate problem with this. The problem in cases where we have two subsequent regions that are handled with thread-level parallelism. If the first region computes data, and the second uses that data, then we have to make sure that the thread producing a particular data item and the thread consuming (or updating) it are scheduled to the same core.

We call *affinity* the maintaining of a fixed mapping between threads (*thread affinity*) or processes (*process affinity*) and cores.

Maintaining thread affinity is easy in some cases. If the loop structure that is being parallelized stays the same, a fixed mapping of threads to cores makes sense:

```
for (i=0; i<ndata; i++) // this loop will be done by threads  
    x[i] = ....  
for (i=0; i<ndata; i++) // as will this one
```

```
... = .... x[i] ...
```

In other cases a fixed mapping is not the right solution:

```
for (i=0; i<n; i++) // produces loop
    x[i] = ....
for (i=0; i<n; i+=2) // use even indices
    ... = ... x[i] ...
for (i=1; i<n; i+=2) // use odd indices
    ... = ... x[i] ...
```

In this second example, either the program has to be transformed, or the programmer has to maintain in effect a *task queue*.

2.5.1.4 Sequential consistency

Thread programs often look very much like fully sequential programs. Creating a thread for a function is much like invoking that function directly, and *OpenMP* programs (see below) only differ from sequential programs in directives that are hidden in comments and pragmas. Thus, it has been proposed to solve the problem of conflicts such as described above by enforcing *sequential consistency* [84]: a parallel program should compute the same result as when its source is executed sequentially, with all the parallel statements in sequence.

This means that a program

```
integer n
n = 0
!$omp parallel shared(n)
n = n + 1
!$omp end parallel
```

should have the same effect as

```
n = 0
n = n+1 ! for processor 0
n = n+1 ! for processoe 1
    ! et cetera
```

With sequential consistency it is no longer necessary to declare atomic operations or critical sections; however, this puts strong demands on the implementation of the model, so it may lead to inefficient code.

2.5.1.5 Concurrency

In this book, we discuss threads in the context of scientific computing. However, threads also facilitate parallelism in other contexts, such as operating systems. In this case, the term *concurrency* is often used, rather than ‘parallelism’. Concurrent tasks are typically asynchronous, rather than tightly coupled.

Concurrency has been studied for a long time. Often, the question addressed is that of *resource contention*: what if two processes, for instance users on the same system, request access to the same resource, for instance a printer. This means that the system call to print is another example of a critical section of code; see section 2.5.1.2 above. Another problem with concurrency is that two processes can both request access to two devices with exclusive use, for instance a printer and some hardware input device. If one process gets hold of the one resource first, and the other process the other resource, we have another case of *deadlock*.

2.5.1.6 Cilk

Other programming models based on threads exist. For instance, *Cilk* is a set of extensions of C/C++ with which a programmer can create threads.

<i>Sequential code:</i> <pre>int fib(int n){ if (n<2) return 1; else { int rst=0; rst += fib(n-1); rst += fib(n-2); return rst; } }</pre>	<i>Cilk code:</i> <pre>cilk int fib(int n){ if (n<2) return 1; else { int rst=0; rst += spawn fib(n-1); rst += spawn fib(n-2); sync; return rst; } }</pre>
---	--

In this example, the variable `rst` is updated by two, potentially independent threads. The semantics of this update, that is, the precise definition of how conflicts such as simultaneous writes are resolved, is defined by *sequential consistency*; see section 2.5.1.4.

2.5.2 OpenMP

OpenMP is an extension to the programming languages C and Fortran. Its main approach to parallelism is the parallel execution of loops: based on compiler directives, a preprocessor can schedule the parallel execution of the loop iterations.

The amount of parallelism is flexible: the user merely specifies a parallel region, indicating that all iterations are independent to some extent, and the runtime system will then use whatever resources are available. Because of this dynamic nature, and because no data distribution is specified, OpenMP can only work with threads on shared memory.

OpenMP is not a language, but an extension to the existing C and Fortran languages. It mostly operates by inserting directives into source code, which are interpreted by the compiler. It also has a modest number of library calls, but these are not the main point, unlike in MPI (section 2.5.3.3). Finally, there is a runtime system that manages the parallel execution.

Many compilers, such as GCC or the Intel compiler, support the OpenMP extensions. In Fortran, OpenMP directives are placed in comment statements; in C, they are placed in `#pragma CPP` directives, which indicate compiler specific extensions. As a result, OpenMP code still looks like legal C or Fortran to a

compiler that does not support OpenMP. Programs need to be linked to an OpenMP runtime library, and their behaviour can be controlled through environment variables.

OpenMP features *dynamic parallelism*: the number of execution streams operating in parallel can vary from one part of the code to another.

For more information about OpenMP, see [18].

2.5.2.1 OpenMP examples

The simplest example of OpenMP use is the parallel loop.

```
#pragma omp for
for (i=0; i<ProblemSize; i++) {
    a[i] = b[i];
}
```

Clearly, all iterations can be executed independently and in any order. The pragma CPP directive then conveys this fact to the compiler.

Some loops are fully parallel conceptually, but not in implementation:

```
for (i=0; i<ProblemSize; i++) {
    t = b[i]*b[i];
    a[i] = sin(t) + cos(t);
}
```

Here it looks as if each iteration writes to, and reads from, a shared variable t . However, t is really a temporary variable, local to each iteration. Code that should be parallelizable, but is not due to such constructs, is called not *thread safe*.

OpenMP indicates that the temporary is private to each iteration as follows:

```
#pragma parallel for shared(a,b), private(t)
for (i=0; i<ProblemSize; i++) {
    t = b[i]*b[i];
    a[i] = sin(t) + cos(t);
}
```

If a scalar *is* indeed shared, OpenMP has various mechanisms for dealing with that. For instance, shared variables commonly occur in *reduction operations*:

```
s = 0;
#pragma parallel for reduction(+:sum)
for (i=0; i<ProblemSize; i++) {
    s = s + a[i]*b[i];
}
```




Figure 2.9: Static or round-robin (left) vs dynamic (right) thread scheduling; the task numbers are indicated.

As you see, a sequential code can be easily parallelized this way.

The assignment of iterations to threads is done by the runtime system, but the user can guide this assignment. We are mostly concerned with the case where there are more iterations than threads: if there are P threads and N iterations and $N > P$, how is iteration i going to be assigned to a thread?

The simplest assignment uses *round-robin task scheduling*, a *static scheduling* strategy where thread p get iterations $p \times (N/P), \dots, (p+1) \times (N/P) - 1$. This has the advantage that if some data is reused between iterations, it will stay in the data cache of the processor executing that thread. On the other hand, if the iterations differ in the amount of work involved, the process may suffer from *load unbalance* with static scheduling. In that case, a *dynamic scheduling* strategy would work better, where each thread starts work on the next unprocessed iteration as soon as it finishes its current iteration. The example in figure 2.9 shows static versus dynamic scheduling of a number of tasks that gradually decrease in individual running time. In static scheduling, the first thread gets tasks 1 and 4, the second 2 and 5, et cetera. In dynamic scheduling, any thread that finishes its task gets the next task. This clearly gives a better running time in this particular example. On the other hand, dynamic scheduling is likely to have a higher overhead.

2.5.3 Distributed memory programming through message passing

While OpenMP programs, and programs written using other shared memory paradigms, still look very much like sequential programs, this does not hold true for message passing code. Before we discuss the Message Passing Interface (MPI) library in some detail, we will take a look at this shift the way parallel code is written.

2.5.3.1 The global versus the local view in distributed programming

There can be a marked difference between how a parallel algorithm looks to an observer, and how it is actually programmed. Consider the case where we have an array of processors $\{P_i\}_{i=0..p-1}$, each containing one element of the arrays x and y , and P_i computes

$$\begin{cases} y_i \leftarrow y_i + x_{i-1} & i > 0 \\ y_i \text{ unchanged} & i = 0 \end{cases} \quad (2.1)$$

The global description of this could be

- Every processor P_i except the last sends its x element to P_{i+1} ;
- every processor P_i except the first receive an x element from their neighbour P_{i-1} , and




Figure 2.10: Local and resulting global view of an algorithm for sending data to the right

- they add it to their y element.

However, in general we can not code in these global terms. In the SPMD model (section 2.2.2) each processor executes the same code, and the overall algorithm is the result of these individual behaviours. The local program has access only to local data – everything else needs to be communicated with send and receive operations – and the processor knows its own number.

One possible way of writing this would be

- If I am processor 0 do nothing, otherwise receive a y element from the left, add it to my x element.
- If I am the last processor do nothing, otherwise send my y element to the right.

At first we look at the case where sends and receives are so-called *blocking communication* instructions: a send instruction does not finish until the sent item is actually received, and a receive instruction waits for the corresponding send. This means that sends and receives between processors have to be carefully paired. We will now see that this can lead to various problems on the way to an efficient code.

The above solution is illustrated in figure 2.10, where we show the local timelines depicting the local processor code, and the resulting global behaviour. You see that the processors are not working at the same time: we get *serialized execution*.

What if we reverse the send and receive operations?

- If I am not the last processor, send my x element to the right;
- If I am not the first processor, receive an x element from the left and add it to my y element.

This is illustrated in figure 2.11 and you see that again we get a serialized execution, except that now the processor are activated right to left.

If the algorithm in equation 2.1 had been cyclic:

$$\begin{cases} y_i \leftarrow y_i + x_{i-1} & i = 1 \dots n-1 \\ y_0 \leftarrow y_0 + x_{n-1} & i = 0 \end{cases} \quad (2.2)$$




Figure 2.11: Local and resulting global view of an algorithm for sending data to the right




Figure 2.12: Local and resulting global view of an algorithm for sending data to the right

the problem would be even worse. Now the last processor can not start its receive since it is blocked sending x_{n-1} to processor 0. This situation, where the program can not progress because every processor is waiting for another, is called *deadlock*.

The solution to getting an efficient code is to make as much of the communication happen simultaneously as possible. After all, there are no serial dependencies in the algorithm. Thus we program the algorithm as follows:

- If I am an odd numbered processor, I send first, then receive;
- If I am an even numbered processor, I receive first, then send.

This is illustrated in figure 2.12, and we see that the execution is now parallel.

2.5.3.2 Blocking and non-blocking communication

The reason for blocking instructions is to prevent accumulation of data in the network. If a send instruction were to complete before the corresponding receive started, the network would have to store the data somewhere in the mean time. Consider a simple example:

```
buffer = ... ; // generate some data
send(buffer,0); // send to processor 0
buffer = ... ; // generate more data
send(buffer,1); // send to processor 1
```

After the first send, we start overwriting the buffer. If the data in it hasn't been received, the first set of values would have to be buffered somewhere in the network, which is not realistic. By having the send operation block, the data stays in the sender's buffer until it is guaranteed to have been copied to the recipient's buffer.

One way out of the problem of sequentialization or deadlock that arises from blocking instruction is the use of *non-blocking communication* instructions, which include explicit buffers for the data. With non-blocking send instruction, the user needs to allocate a buffer for each send, and check when it is safe to overwrite the buffer.

```
buffer0 = ... ; // data for processor 0
send(buffer0,0); // send to processor 0
buffer1 = ... ; // data for processor 1
send(buffer1,1); // send to processor 1
...
// wait for completion of all send operations.
```

2.5.3.3 The MPI library

If OpenMP is the way to program shared memory, Message Passing Interface (MPI) [119] is the standard solution for programming distributed memory. MPI ('Message Passing Interface') is a specification for a library interface for moving data between processes that do not otherwise share data. The MPI routines can be divided roughly in the following categories:

- Process management. This includes querying the parallel environment and constructing subsets of processors.
- Point-to-point communication. This is a set of calls where two processes interact. These are mostly variants of the send and receive calls.
- Collective calls. In these routines, all processors (or the whole of a specified subset) are involved. Examples are the *broadcast* call, where one processor shares its data with every other processor, or the *gather* call, where one processor collects data from all participating processors.

Let us consider how the OpenMP examples can be coded in MPI⁴. First of all, we no longer allocate

```
double a[ProblemSize];
```

but

```
double a[LocalProblemSize];
```

4. This is not a course in MPI programming, and consequently the examples will leave out many details of the MPI calls. If you want to learn MPI programming, consult for instance [60].

where the local size is roughly a $1/P$ fraction of the global size. (Practical considerations dictate whether you want this distribution to be as evenly as possible, or rather biased in some way.)

The parallel loop is trivially parallel, with the only difference that it now operates on a fraction of the arrays:

```
for (i=0; i<LocalProblemSize; i++) {  
    a[i] = b[i];  
}
```

However, if the loop involves a calculation based on the iteration number, we need to map that to the global value:

```
for (i=0; i<LocalProblemSize; i++) {  
    a[i] = b[i]+f(i+MyFirstVariable);  
}
```

(We will assume that each process has somehow calculated the values of `LocalProblemSize` and `MyFirstVariable`.) Local variables are now automatically local, because each process has its own instance:

```
for (i=0; i<LocalProblemSize; i++) {  
    t = b[i]*b[i];  
    a[i] = sin(t) + cos(t);  
}
```

However, shared variables are harder to implement. Since each process has its own data, the local accumulation has to be explicitly assembled:

```
for (i=0; i<LocalProblemSize; i++) {  
    s = s + a[i]*b[i];  
}  
MPI_Allreduce(s, globals, 1, MPI_DOUBLE, MPI_SUM);
```

The ‘reduce’ operation sums together all local values `s` into a variable `globals` that receives an identical value on each processor. This is known as a *collective operation*.

Let us make the example slightly more complicated:

```
for (i=0; i<ProblemSize; i++) {  
    if (i==0)  
        a[i] = (b[i]+b[i+1])/2  
    else if (i==ProblemSize-1)  
        a[i] = (b[i]+b[i-1])/2  
    else  
        a[i] = (b[i]+b[i-1]+b[i+1])/3
```

If we had shared memory, we could write the following parallel code:

2. Parallel Computing

```
for (i=0; i<LocalProblemSize; i++) {  
    bleft = b[i-1]; bright = b[i+1];  
    a[i] = (b[i]+bleft+bright)/3
```

To turn this into valid distributed memory code, first we account for the fact that `bleft` and `bright` need to be obtained from a different processor for `i==0` (`bleft`), and for `i==LocalProblemSize-1` (`bright`). We do this with a exchange operation with our left and right neighbour processor:

```
// get bfromleft and bfromright from neighbour processors, then  
for (i=0; i<LocalProblemSize; i++) {  
    if (i==0) bleft=bfromleft;  
    else bleft = b[i-1]  
    if (i==LocalProblemSize-1) bright=bfromright;  
    else bright = b[i+1];  
    a[i] = (b[i]+bleft+bright)/3
```

Obtaining the neighbour values is done as follows. First we need to ask our processor number, so that we can start a communication with the processor with a number one higher and lower.

```
MPI_Comm_rank(MPI_COMM_WORLD, &myTaskID);  
MPI_Sendrecv( /* to be sent: */ &b[LocalProblemSize-1],  
             /* destination */ myTaskID+1,  
             /* to be recv'd: */ &bfromleft,  
             /* source: */      myTaskID-1,  
             /* some parameters omitted */  
             );  
MPI_Sendrecv(&b[0], myTaskID-1,  
             &bfromright, /* ... */ );
```

There are still two problems with this code. First, the `sendrecv` operations need exceptions for the first and last processors. This can be done elegantly as follows:

```
MPI_Comm_rank(MPI_COMM_WORLD, &myTaskID);  
MPI_Comm_size(MPI_COMM_WORLD, &nTasks);  
if (myTaskID==0) leftproc = MPI_PROC_NULL;  
else leftproc = myTaskID-1;  
if (myTaskID==nTasks-1) rightproc = MPI_PROC_NULL;  
else rightproc = myTaskID+1;  
MPI_Sendrecv( &b[LocalProblemSize-1], &bfromleft, rightproc );  
MPI_Sendrecv( &b[0], &bfromright, leftproc );
```

Exercise 2.5. There is still a problem left with this code: the boundary conditions from the original, global, version have not been taken into account. Give code that solves that problem.

MPI gets complicated if different processes need to take different actions, for example, if one needs to send data to another. The problem here is that each process executes the same executable, so it needs to contain both the send and the receive instruction, to be executed depending on what the rank of the process is.

```

if (myTaskID==0) {
    MPI_Send(myInfo, 1, MPI_INT, /* to: */ 1, /* labeled: */, 0,
             MPI_COMM_WORLD);
} else {
    MPI_Recv(myInfo, 1, MPI_INT, /* from: */ 0, /* labeled: */, 0,
             /* not explained here: */ &status, MPI_COMM_WORLD);
}

```

2.5.3.4 Blocking

Although MPI is sometimes called the ‘assembly language of parallel programming’, for its perceived difficulty and level of explicitness, it is not all that hard to learn, as evinced by the large number of scientific codes that use it. The main issues that make MPI somewhat intricate to use, are buffer management and blocking semantics.

These issues are related, and stem from the fact that, ideally, data should not be in two places at the same time. Let us briefly consider what happens if processor 1 sends data to processor 2. The safest strategy is for processor 1 to execute the send instruction, and then wait until processor 2 acknowledges that the data was successfully received. This means that processor 1 is temporarily blocked until processor 2 actually executes its receive instruction, and the data has made its way through the network. This is the standard behaviour of the `MPI_Send` and `MPI_Recv` calls, which are said to use *blocking communication*.

Alternatively, processor 1 could put its data in a buffer, tell the system to make sure that it gets sent at some point, and later checks to see that the buffer is safe to reuse. This second strategy is called *non-blocking communication*, and it requires the use of a temporary buffer.

2.5.3.5 Collective operations

In the above examples, you saw the `MPI_Allreduce` call, which computed a global sum and left the result on each processor. There is also a local version `MPI_Reduce` which computes the result only on one processor. These calls are examples of *collective operations* or collectives. The collectives are:

reduction : each processor has a data item, and these items need to be combined arithmetically with an addition, multiplication, max, or min operation. The result can be left on one processor, or on all, in which case we call this an **allreduce** operation.

broadcast : one processor has a data item that all processors need to receive.

gather : each processor has a data item, and these items need to be collected in an array, without combining them in an operations such as an addition. The result can be left on one processor, or on all, in which case we call this an **allgather**.

scatter : one processor has an array of data items, and each processor receives one element of that array.

all-to-all : each processor has an array of items, to be scattered to all other processors.

Collective operations are blocking (see section 2.5.3.4), although MPI 3.0 (which is currently only a draft) will have non-blocking collectives. We will analyze the cost of collective operations in detail in section 6.2.1.

2.5.3.6 Non-blocking communication

In a simple computer program, each instruction takes some time to execute, in a way that depends on what goes on in the processor. In parallel programs the situation is more complicated. A send operation, in its simplest form, declares that a certain buffer of data needs to be sent, and program execution will then stop until that buffer has been safely sent and received by another processor. This sort of operation is called a *non-local operation* since it depends on the actions of other processes, and a *blocking communication* operation since execution will halt until a certain event takes place.

Blocking operations have the disadvantage that they can lead to *deadlock*, if two processes wind up waiting for each other. Even without deadlock, they can lead to considerable *idle time* in the processors, as they wait without performing any useful work. On the other hand, they have the advantage that it is clear when the buffer can be reused: after the operation completes, there is a guarantee that the data has been safely received at the other end.

The blocking behaviour can be avoided, at the cost of complicating the buffer semantics, by using *non-blocking communication* operations. A non-blocking send (`MPI_Isend`) declares that a data buffer needs to be sent, but then does not wait for the completion of the corresponding receive. There is a second operation `MPI_Wait` that will actually block until the receive has been completed. The advantage of this decoupling of sending and blocking is that it now becomes possible to write:

```
MPI_Isend(somebuffer, &handle); // start sending, and
                                // get a handle to this particular communication
{ ... } // do useful work on local data
MPI_Wait(handle); // block until the communication is completed;
{ ... } // do useful work on incoming data
```

With a little luck, the local operations take more time than the communication, and you have completely eliminated the communication time.

In addition to non-blocking sends, there are non-blocking receives. A typical piece of code then looks like

```
MPI_Isend(sendbuffer, &sendhandle);
MPI_IReceive(recvbuffer, &recvhandle);
{ ... } // do useful work on local data
MPI_Wait(sendhandle); Wait(recvhandle);
{ ... } // do useful work on incoming data
```

Exercise 2.6. Take another look at equation (2.2) and give pseudocode that solves the problem using non-blocking sends and receives. What is the disadvantage of this code over a blocking solution?

2.5.3.7 MPI version 1 and 2

The first MPI standard [103] had a number of notable omissions, which are included in the MPI 2 standard [61]. One of these concerned parallel input/output: there was no facility for multiple processes to access the same file, even if the underlying hardware would allow that. A separate project MPI-I/O has now been rolled into the MPI-2 standard. We will discuss parallel I/O in this book.

A second facility missing in MPI, though it was present in PVM [30, 48] which predates MPI, is process management: there is no way to create new processes and have them be part of the parallel run.

Finally, MPI-2 has support for one-sided communication: one process put data into the memory of another, without the receiving process doing an actual receive instruction. We will have a short discussion in section 2.5.5 below.

2.5.4 Hybrid shared/distributed memory computing

Modern architectures are often a mix of shared and distributed memory. For instance, a cluster will be distributed on the level of the nodes, but sockets and cores on a node will have shared memory. One level up, each socket can have a shared L3 cache but separate L2 and L1 caches. Intuitively it seems clear that a mix of shared and distributed programming techniques would give code that is optimally matched to the architecture. In this section we will discuss such hybrid programming models, and discuss their efficacy.

A common setup of clusters uses distributed memory *nodes*, where each node contains several sockets, that share memory. This suggests using MPI to communicate between the nodes (*inter-node communication*) and OpenMP for parallelism on the node (*intra-node communication*).

In practice this is realized as follows:

- On each node a single MPI process is started (rather than one per socket or core);
- This one MPI process then uses OpenMP (or another threading protocol) to spawn as many threads as there are independent sockets or cores on the node.
- The OpenMP threads can then easily access the same shared memory.

The alternative would be to have an MPI process on each core or socket, and do all communication through message passing, even between processes that can see the same shared memory.

This hybrid strategy may sound like a good idea but the truth is complicated.

- Message passing between MPI processes sounds like it's more expensive than communicating through shared memory. However, optimized versions of MPI can typically detect when processes are on the same node, and they will replace the message passing by a simple data copy. The only argument against using MPI is then that each process has its own data space, so there is memory overhead because each process has to allocate space for buffers and duplicates of the data that is copied.
- Threading is more flexible: if a certain part of the code needs more memory per process, an OpenMP approach could limit the number of threads on that part. On the other hand, flexible handling of threads incurs a certain amount of Operating System (OS) overhead that MPI does not have with its fixed processes.

- If a program reaches a point where all processes communicate, then the hybrid approach offers some advantage since it bundles messages. For instance, if two MPI processes on one node send messages to each of two processes on another node there would be four messages; in the hybrid model these would be bundled into one message. The distributed sparse matrix-vector product would be a good illustration of this scenario; see section 6.4.
- Shared memory programming is conceptually simple, but there can be unexpected performance pitfalls. For instance, the performance of two processes now can be impeded by the need for maintaining cache coherence and by *false sharing*.

Exercise 2.7. Analyze the discussion in the last item above. Assume that the bandwidth between the two nodes is only enough to sustain one message at a time. What is the cost savings of the hybrid model over the purely distributed model? Hint: consider bandwidth and latency separately.

2.5.5 One-sided communication

The MPI way of writing matching send and receive instructions is not ideal for a number of reasons. First of all, it requires the programmer to give the same data description twice, once in the send and once in the receive call. Secondly, it requires a rather precise orchestration of communication if deadlock is to be avoided; the alternative of using asynchronous calls is tedious to program, requiring the program to manage a lot of buffers. Lastly, it requires a receiving processor to know how many incoming messages to expect, which can be tricky in irregular applications. Life would be so much easier if it was possible to pull data from another processor, or conversely to put it on another processor, without that other processor being explicitly involved.

This style of programming is further encouraged by the existence of *Remote Direct Memory Access (RDMA)* support on some hardware. An early example was the *Cray T3E*. These days, one-sided communication is widely available through its incorporation in the MPI-2 library; section 2.5.3.7.

Let us take a brief look at one-sided communication in MPI-2, using averaging of array values as an example:

$$\forall_i: a_i \leftarrow (a_i + a_{i-1} + a_{i+1})/3.$$

The MPI parallel code will look like

```
// do data transfer
a_local = (a_local+left+right) / 3
```

It is clear what the transfer has to accomplish: the `a_local` variable needs to become the `left` variable on the processor with the next higher rank, and the `right` variables on the one with the next lower rank.

First of all, processors need to declare explicitly what memory area is available for one-sided transfer, the so-called ‘window’. In this example, that consists of the `a_local`, `left`, and `right` variables on the processors:

```
MPI_Win_create(&a_local, ..., &data_window);
MPI_Win_create(&left, ..., &left_window);
```

```
MPI_Win_create(&right, ..., &right_window);
```

The code now has two options: it is possible to push data out

```
target = my_tid-1;
MPI_Put(&a_local, ..., target, right_window);
target = my_tid+1;
MPI_Put(&a_local, ..., target, left_window);
```

or to pull it in

```
data_window = a_local;
source = my_tid-1;
MPI_Get(&right, ..., data_window);
source = my_tid+1;
MPI_Get(&left, ..., data_window);
```

The above code will have the right semantics if the Put and Get calls are blocking; see section 2.5.3.4. However, part of the attraction of one-sided communication is that it makes it easier to express communication, and for this, a non-blocking semantics is assumed.

The problem with non-blocking one-sided calls is that it becomes necessary to ensure explicitly that communication is successfully completed. For instance, if one processor does a one-sided *put* operation on another, the other processor has no way of checking that the data has arrived, or indeed that transfer has begun at all. Therefore it is necessary to insert a global barrier in the program, for which every package has its own implementation. In MPI-2 the relevant call is the MPI_Win_fence routine. These barriers in effect divide the program execution in *supersteps*; see section 2.5.9.

Another form of one-sided communication is used in the Charm++ package; see section 2.5.8.

2.5.5.1 The Global Arrays library

The Global Arrays library (<http://www.emsl.pnl.gov/docs/global/>) is another example of *one-sided communication*, and in fact it predates MPI. This library has as its prime data structure *cartesian product arrays*⁵, distributed over a processor grid of the same or lower dimension. Through library calls, any processor can access any sub-brick out of the array in either a put or get operation. These operations are non-collective. As with any one-sided protocol, a barrier sync is necessary to ensure completion of the sends/receives.

2.5.6 Parallel languages

One approach to mitigating the difficulty of parallel programming is the design of languages that offer explicit support for parallelism. There are several approaches, and we will see some examples.

5. This means that if the array is three-dimensional, it can be described by three integers n_1, n_2, n_3 , and each point has a coordinate (i_1, i_2, i_3) with $1 \leq i_1 \leq n_1$ et cetera.

- Some languages reflect the fact that many operations in scientific computing are data parallel (section 2.4.1). Languages such as *High Performance Fortran (HPF)* (section 2.5.6.4) have an array syntax, where operations such addition of arrays can be expressed $A = B+C$. This syntax simplifies programming, but more importantly, it specifies operations at an abstract level, so that a lower level can make specific decision about how to handle parallelism. However, the data parallelism expressed in HPF is only of the simplest sort, where the data are contained in regular arrays. Irregular data parallelism is harder; the *Chapel* language (section 2.5.6.6) makes an attempt at addressing this.
- Another concept in parallel languages, not necessarily orthogonal to the previous, is that of Partitioned Global Address Space (PGAS) model: there is only one address space (unlike in the MPI model), but this address space is partitioned, and each partition has affinity with a thread or process. Thus, this model encompasses both SMP and distributed shared memory. A typical PGAS language, *Unified Parallel C (UPC)*, allows you to write programs that for the most part looks like regular C code. However, by indicating how the major arrays are distributed over processors, the program can be executed in parallel.

2.5.6.1 Discussion

Parallel languages hold the promise of making parallel programming easier, since they make communication operations appear as simple copies or arithmetic operations. However, by doing so they invite the user to write code that may not be efficient, for instance by inducing many small messages.




Figure 2.13: Data shift that requires communication

As an example, consider arrays a, b that have been horizontally partitioned over the processors, and that are shifted (see figure 2.13):

```
for (i=0; i<N; i++)
```

```

for (j=0; j<N/np; j++)
    a[i][j+joffset] = b[i][j+1+joffset]

```

If this code is executed on a shared memory machine, it will be efficient, but a naive translation in the distributed case will have a single number being communicated in each iteration of the *i* loop. Clearly, these can be combined in a single buffer send/receive operation, but compilers are usually unable to make this transformation. As a result, the user is forced to, in effect, re-implement the blocking that needs to be done in an MPI implementation:

```

for (i=0; i<N; i++)
    t[i] = b[i][N/np+joffset]
for (i=0; i<N; i++) {
    for (j=0; j<N/np-1; j++) {
        a[i][j] = b[i][j+1]
        a[i][N/np] = t[i]
    }
}

```

On the other hand, certain machines support direct memory copies through global memory hardware. In that case, PGAS languages can be more efficient than explicit message passing, even with physically distributed memory.

2.5.6.2 Unified Parallel C

Unified Parallel C (UPC) [123] is an extension to the C language. Its main source of parallelism is *data parallelism*, where the compiler discovers independence of operations on arrays, and assigns them to separate processors. The language has an extended array declaration, which allows the user to specify whether the array is partitioned by blocks, or in a *round-robin* fashion.

The following program in UPC performs a vector-vector addition.

```

//vect_add.c
#include <upc_relaxed.h>
#define N 100*THREADS
shared int v1[N], v2[N], v1plusv2[N];
void main() {
    int i;
    for(i=MYTHREAD; i<N; i+=THREADS)
        v1plusv2[i]=v1[i]+v2[i];
}

```

The same program with an explicitly parallel loop construct:

```

//vect_add.c
#include <upc_relaxed.h>
#define N 100*THREADS
shared int v1[N], v2[N], v1plusv2[N];

```

2. Parallel Computing

```
void main()
{
    int i;
    upc_forall(i=0; i<N; i++, i)
        v1plusv2[i]=v1[i]+v2[i];
}
```

2.5.6.3 Titanium

Titanium is comparable to UPC in spirit, but based on Java rather than on C.

2.5.6.4 High Performance Fortran

High Performance Fortran⁶ (HPF) is an extension of Fortran 90 with constructs that support parallel computing, published by the High Performance Fortran Forum (HPFF). The HPFF was convened and chaired by Ken Kennedy of Rice University. The first version of the HPF Report was published in 1993.

Building on the array syntax introduced in Fortran 90, HPF uses a data parallel model of computation to support spreading the work of a single array computation over multiple processors. This allows efficient implementation on both SIMD and MIMD style architectures. HPF features included:

- New Fortran statements, such as FORALL, and the ability to create PURE (side effect free) procedures
- *Compiler directives* for recommended distributions of array data
- Extrinsic procedure interface for interfacing to non-HPF parallel procedures such as those using message passing
- Additional library routines - including environmental inquiry, parallel prefix/suffix (e.g., 'scan'), data scattering, and sorting operations

Fortran 95 incorporated several HPF capabilities. While some vendors did incorporate HPF into their compilers in the 1990s, some aspects proved difficult to implement and of questionable use. Since then, most vendors and users have moved to OpenMP-based parallel processing. However, HPF continues to have influence. For example the proposed BIT data type for the upcoming Fortran-2008 standard contains a number of new intrinsic functions taken directly from HPF.

2.5.6.5 Co-array Fortran

Co-array Fortran (CAF) is an extension to the Fortran 95/2003 language. The main mechanism to support parallelism is an extension to the array declaration syntax, where an extra dimension indicates the parallel distribution. For instance,

```
real,allocatable,dimension(:,:,:,:)[:,:] :: A
```

6. This section quoted from Wikipedia

declares an array that is three-dimensional on each processor, and that is distributed over a two-dimensional processor grid.

Communication between processors is now done through copies along the dimensions that describe the processor grid:

```
COMMON/XCTILB4/ B(N,4) [*]
SAVE /XCTILB4/
C
CALL SYNC_ALL( WAIT=(/IMG_S,IMG_N/) )
B(:,3) = B(:,1)[IMG_S]
B(:,4) = B(:,2)[IMG_N]
CALL SYNC_ALL( WAIT=(/IMG_S,IMG_N/) )
```

The Fortran 2008 standard will include co-arrays.

2.5.6.6 Chapel

Chapel [17] is a new parallel programming language⁷ being developed by Cray Inc. as part of the DARPA-led High Productivity Computing Systems program (HPCS). Chapel is designed to improve the productivity of high-end computer users while also serving as a portable parallel programming model that can be used on commodity clusters or desktop multicore systems. Chapel strives to vastly improve the programmability of large-scale parallel computers while matching or beating the performance and portability of current programming models like MPI.

Chapel supports a multithreaded execution model via high-level abstractions for data parallelism, task parallelism, concurrency, and nested parallelism. Chapel's locale type enables users to specify and reason about the placement of data and tasks on a target architecture in order to tune for locality. Chapel supports global-view data aggregates with user-defined implementations, permitting operations on distributed data structures to be expressed in a natural manner. In contrast to many previous higher-level parallel languages, Chapel is designed around a multiresolution philosophy, permitting users to initially write very abstract code and then incrementally add more detail until they are as close to the machine as their needs require. Chapel supports code reuse and rapid prototyping via object-oriented design, type inference, and features for generic programming.

Chapel was designed from first principles rather than by extending an existing language. It is an imperative block-structured language, designed to be easy to learn for users of C, C++, Fortran, Java, Perl, Matlab, and other popular languages. While Chapel builds on concepts and syntax from many previous languages, its parallel features are most directly influenced by ZPL, High-Performance Fortran (HPF), and the Cray MTA's extensions to C and Fortran.

Here is vector-vector addition in Chapel:

```
const BlockDist= newBlock1D(bbox=[1..m], tasksPerLocale=...);
const ProblemSpace: domain(1, 64)) distributed BlockDist = [1..m];
```

7. This section quoted from the Chapel homepage.

```
var A, B, C: [ProblemSpace] real;
forall(a, b, c) in(A, B, C) do
    a = b + alpha * c;
```

2.5.6.7 Fortress

Fortress [44] is a programming language developed by Sun Microsystems. Fortress⁸ aims to make parallelism more tractable in several ways. First, parallelism is the default. This is intended to push tool design, library design, and programmer skills in the direction of parallelism. Second, the language is designed to be more friendly to parallelism. Side-effects are discouraged because side-effects require synchronization to avoid bugs. Fortress provides transactions, so that programmers are not faced with the task of determining lock orders, or tuning their locking code so that there is enough for correctness, but not so much that performance is impeded. The Fortress looping constructions, together with the library, turns "iteration" inside out; instead of the loop specifying how the data is accessed, the data structures specify how the loop is run, and aggregate data structures are designed to break into large parts that can be effectively scheduled for parallel execution. Fortress also includes features from other languages intended to generally help productivity – test code and methods, tied to the code under test; contracts that can optionally be checked when the code is run; and properties, that might be too expensive to run, but can be fed to a theorem prover or model checker. In addition, Fortress includes safe-language features like checked array bounds, type checking, and garbage collection that have been proven-useful in Java. Fortress syntax is designed to resemble mathematical syntax as much as possible, so that anyone solving a problem with math in its specification can write a program that can be more easily related to its original specification.

2.5.6.8 X10

X10 is an experimental new language currently under development at IBM in collaboration with academic partners. The X10 effort is part of the IBM PERCS project (Productive Easy-to-use Reliable Computer Systems) in the DARPA program on High Productivity Computer Systems. The PERCS project is focused on a hardware-software co-design methodology to integrate advances in chip technology, architecture, operating systems, compilers, programming language and programming tools to deliver new adaptable, scalable systems that will provide an order-of-magnitude improvement in development productivity for parallel applications by 2010.

X10 aims to contribute to this productivity improvement by developing a new programming model, combined with a new set of tools integrated into Eclipse and new implementation techniques for delivering optimized scalable parallelism in a managed runtime environment. X10 is a type-safe, modern, parallel, distributed object-oriented language intended to be very easily accessible to Java(TM) programmers. It is targeted to future low-end and high-end systems with nodes that are built out of multi-core SMP chips with non-uniform memory hierarchies, and interconnected in scalable cluster configurations. A member of the Partitioned Global Address Space (PGAS) family of languages, X10 highlights the explicit reification of locality in the form of places; lightweight activities embodied in `async`, `future`, `foreach`, and `ateach` constructs; constructs for termination detection (`finish`) and phased computation (`clocks`); the use of lock-free synchronization (`atomic blocks`); and the manipulation of global arrays and data structures.

8. This section quoted from the Fortress homepage.

2.5.6.9 Linda

As should be clear by now, the treatment of data is by far the most important aspect of parallel programming, far more important than algorithmic considerations. The programming system *Linda* [49, 50], also called a *coordination language*, is designed to address the data handling explicitly. Linda is not a language as such, but can, and has been, incorporated into other languages.

The basic concept of Linda is *tuple space*: data is added to a pool of globally accessible information by adding a label to it. Processes then retrieve data by their label, and without needing to know which processes added them to the tuple space.

Linda is aimed primarily at a different computation model than is relevant for *High-Performance Computing (HPC)*: it addresses the needs of asynchronous communicating processes. However, it has been used for scientific computation [27]. For instance, in parallel simulations of the heat equation (section 4.3), processors can write their data into tuple space, and neighbouring processes can retrieve their *ghost region* without having to know its provenance. Thus, Linda becomes one way of implementing *one-sided communication*.

2.5.7 OS-based approaches

It is possible to design an architecture with a shared address space, and let the data movement be handled by the operating system. The Kendall Square computer [80] had an architecture name ‘all-cache’, where no data was natively associated with any processor. Instead, all data was considered to be cached on a processor, and moved through the network on demand, much like data is moved from main memory to cache in a regular CPU. This idea is analogous to the numa support in current SGI architectures.

2.5.8 Active messages

The MPI paradigm (section 2.5.3.3) is traditionally based on two-sided operations: each data transfer requires an explicit send and receive operation. This approach works well with relatively simple codes, but for complicated problems it becomes hard to orchestrate all the data movement. One of the ways to simplify consists of using *active messages*. This is used in the package *Charm++*[77].

With active messages, one processor can send data to another, without that second processor doing an explicit receive operation. Instead, the recipient declares code that handles the incoming data, a ‘method’ in objective orientation parlance, and the sending processor calls this method with the data that it wants to send. Since the sending processor in effect activates code on the other processor, this is also known as *remote method invocation*. A big advantage of this method is that overlap of communication and computation becomes easier to realize.

As an example, consider the matrix-vector multiplication with a tridiagonal matrix

$$\forall_i: y_i \leftarrow 2x_i - x_{i+1} - x_{i-1}.$$

See section 4.2.2.1 for an explanation of the origin of this problem in PDEs. Assuming that each processor has exactly one index i , the MPI code could look like:

```

if ( /* I am the first or last processor */ )
    n_neighbours = 1;
else
    n_neighbours = 2;

/* do the MPI_Isend operations on my local data */

sum = 2*local_x_data;
received = 0;
for (neighbour=0; neighbour<n_neighbours; neighbour++) {
    MPI_WaitAny( /* wait for any incoming data */ )
    sum = sum - /* the element just received */
    received++
    if (received==n_neighbours)
        local_y_data = sum
}

```

With active messages this looks like

```

void incorporate_neighbour_data(x) {
    sum = sum-x;
    if (received==n_neighbours)
        local_y_data = sum
}
sum = 2*local_xdata;
received = 0;
all_processors[myid+1].incorporate_neighbour_data(local_x_data);
all_processors[myid-1].incorporate_neighbour_data(local_x_data);

```

2.5.9 Bulk synchronous parallelism

The MPI library (section 2.5.3.3 can lead to very efficient code. The price for this is that the programmer needs to spell out the communication in great detail. On the other end of the spectrum, PGAS languages (section 2.5.6) ask very little of the programmer, but give not much performance in return. One attempt to find a middle ground is the *Bulk Synchronous Parallel (BSP)* model [124, 118]. Here the programmer needs to spell out the communications, but not their ordering.

The BSP model orders the program into a sequence of *supersteps*, each of which ends with a *barrier* synchronization. The communications that are started in one superstep are all asynchronous and rely on the barrier to be completed. This makes programming easier and removes the possibility of deadlock.

Exercise 2.8. Consider the parallel summing example in section 2.1. Argue that a BSP implementation needs $\log_2 n$ supersteps.

Because of its synchronization of the processors through the barriers concluding the supersteps the BSP model can do a simple cost analysis of parallel algorithms. Also, in its originally proposed form the BSP

model called for an *overdecomposition* of the problem which assigns multiple processes to each processor, as well as *random placement* of data and tasks. A statistical argument tells us then that with high likelihood this will give a good balance of work and communication.

The BSP model is implemented in BSPlib [71], and recently was also used for Google's *Pregel* [95].

2.6 Topologies

If a number of processors are working together on a single task, most likely they need to communicate data. For this reason there needs to be a way for data to make it from any processor to any other. In this section we will discuss some of the possible schemes to connect the processors in a parallel machine.

In order to get an appreciation for the fact that there is a genuine problem here, consider two simple schemes that do not 'scale up':

- Ethernet is a connection scheme where all machines on a network are on a single cable⁹. If one machine puts a signal on the wire to send a message, and another also wants to send a message, the latter will detect that the sole available communication channel is occupied, and it will wait some time before retrying its send operation. Receiving data on ethernet is simple: messages contain the address of the intended recipient, so a processor only has to check whether the signal on the wire is intended for it.

The problems with this scheme should be clear. The capacity of the communication channel is finite, so as more processors are connected to it, the capacity available to each will go down. Because of the scheme for resolving conflicts, the average delay before a message can be started will also increase¹⁰.

- In a *fully connected* configuration, each processor has one wire for the communications with each other processor. This scheme is perfect in the sense that messages can be sent in the minimum amount of time, and two messages will never interfere with each other. The amount of data that can be sent from one processor is no longer a decreasing function of the number of processors; it is in fact an increasing function, and if the network controller can handle it, a processor can even engage in multiple simultaneous communications.

The problem with this scheme is of course that the design of the network interface of a processor is no longer fixed: as more processors are added to the parallel machine, the network interface gets more connecting wires. The network controller similarly becomes more complicated, and the cost of the machine increases faster than linearly in the number of processors.

In this section we will see a number of schemes that *can* be increased to large numbers of processors.

2.6.1 Some graph theory

The network that connects the processors in a parallel computer can conveniently be described with some elementary graph theory concepts. We describe the parallel machine with a graph where each processor is

9. We are here describing the original design of Ethernet. With the use of switches, especially in an HPC context, this description does not really apply anymore.

10. It was initially thought that ethernet would be inferior to other solutions such as IBM's 'token ring'. It takes fairly sophisticated statistical analysis to prove that it works a lot better than was naively expected.

a node, and two nodes are connected¹¹ if there is a direct connection between them.

We can then analyze two important concepts of this graph.

First of all, the *degree* of a node in a graph is the number of other nodes it is connected to. With the nodes representing processors, and the edges the wires, it is clear that a high degree is not just desirable for efficiency of computing, but also costly from an engineering point of view. We assume that all processors have the same degree.

Secondly, a message traveling from one processor to another, through one or more intermediate nodes, will most likely incur some delay at each stage of the path between the nodes. For this reason, the *diameter* of the graph is important. The diameter is defined as the maximum shortest distance, counting numbers of links, between any two nodes:

$$d(G) = \max_{i,j} |\text{shortest path between } i \text{ and } j|.$$

If d is the diameter, and if sending a message over one wire takes unit time, this means a message will always arrive in at most time d .

Exercise 2.9. Find a relation between the number of processors, their degree, and the diameter of the connectivity graph.

In addition to the question ‘how long will a message from processor A to processor B take’, we often worry about conflicts between two simultaneous messages: is there a possibility that two messages, under way at the same time, will need to use the same network link? In figure 2.14 we illustrate what happens if every processor p_i with $i < n/2$ send a message to $p_{i+n/2}$: there will be $n/2$ messages trying to get through the wire between $p_{n/2-1}$ and $p_{n/2}$. This sort of conflict is called *congestion* or *contention*. Clearly, the more




Figure 2.14: Contention for a network link due to simultaneous messages

links a parallel computer has, the smaller the chance of congestion.

A precise way to describe the likelihood of congestion, is to look at the *bisection width*. This is defined as the minimum number of links that have to be removed to partition the processor graph into two unconnected graphs. For instance, consider processors connected as a linear array, that is, processor P_i is connected to P_{i-1} and P_{i+1} . In this case the bisection width is 1.

The bisection width w describes how many messages can, guaranteed, be under way simultaneously in a parallel computer. Proof: take w sending and w receiving processors. The w paths thus defined are disjoint: if they were not, we could separate the processors into two groups by removing only $w - 1$ links.

11. We assume that connections are symmetric, so that the network is an *undirected graph*.

In practice, of course, more than w messages can be under way simultaneously. For instance, in a linear array, which has $w = 1$, $P/2$ messages can be sent and received simultaneously if all communication is between neighbours, and if a processor can only send or receive, but not both, at any one time. If processors can both send and receive simultaneously, P messages can be under way in the network.

Bisection width also describes *redundancy* in a network: if one or more connections are malfunctioning, can a message still find its way from sender to receiver?

While bisection width is a measure express as a number of wires, in practice we care about the capacity through those wires. The relevant concept here is *bisection bandwidth*: the bandwidth across the bisection width, which is the product of the bisection width, and the capacity (in bits per second) of the wires. Bisection bandwidth can be considered as a measure for the bandwidth that can be attained if an arbitrary half of the processors communicates with the other half. Bisection bandwidth is a more realistic measure than the *aggregate bandwidth* which is sometimes quoted and which is defined as the total data rate if every processor is sending: the number of processors times the bandwidth of a connection times the number of simultaneous sends a processor can perform. This can be quite a high number, and it is typically not representative of the communication rate that is achieved in actual applications.

2.6.2 Linear arrays and rings

A simple way to hook up multiple processors is to connect them in a *linear array*: every processor has a number i , and processor P_i is connected to P_{i-1} and P_{i+1} . The first and last processor are possible exceptions: if they are connected to each other, we call the architecture a *ring network*.

This solution requires each processor to have two network connections, so the design is fairly simple.

Exercise 2.10. What is the bisection width of a linear array? Of a ring?

Exercise 2.11. With the limited connections of a linear array, you may have to be clever about how to program parallel algorithms. For instance, consider a ‘broadcast’ operation: processor 0 has a data item that needs to be sent to every other processor.

We make the following simplifying assumptions:

- a processor can send any number of messages simultaneously,
- but a wire can carry only one message at a time; however,
- communication between any two processors takes unit time, regardless the number of processors in between them.

In a fully connected network or a star network you can simply write

for $i = 1 \dots N - 1$:

send the message to processor i

With the assumption that a processor can send multiple messages, this means that the operation is done in one step.

Now consider a linear array. Show that, even with this unlimited capacity for sending, the above algorithm runs into trouble because of congestion.

Find a better way to organize the send operations. Hint: pretend that your processors are connected as a binary tree. Assume that there are $N = 2^n - 1$ processors. Show that the broadcast can be done in $\log N$ stages, and that processors only need to be able to send a single message simultaneously.

This exercise is an example of *embedding* a ‘logical’ communication pattern in a physical one.

2.6.3 2D and 3D arrays

A popular design for parallel computers is to organize the processors in a two-dimensional or three-dimensional *cartesian mesh*. This means that every processor has a coordinate (i, j) or (i, j, k) , and it is connected to its neighbours in all coordinate directions. The processor design is still fairly simple: the number of network connections (the degree of the connectivity graph) is twice the number of space dimensions (2 or 3) of the network.

It is a fairly natural idea to have 2D or 3D networks, since the world around us is three-dimensional, and computers are often used to model real-life phenomena. If we accept for now that the physical model requires *nearest neighbour* type communications (which we will see is the case in section 4.2.2.2), then a mesh computer is a natural candidate for running physics simulations.

Exercise 2.12. What is the diameter of a 3D cube of $n \times n \times n$ processors? What is the bisection width? How does that change if you add wraparound torus connections?

Exercise 2.13. Your parallel computer has its processors organized in a 2D grid. The chip manufacturer comes out with a new chip with same clock speed that is dual core instead of single core, and that will fit in the existing sockets. Critique the following argument: “the amount work per second that can be done (that does not involve communication) doubles; since the network stays the same, the bisection bandwidth also stays the same, so I can reasonably expect my new machine to become twice as fast¹².”

Grid-based designs often have so-called *wrap-around* or *torus* connections, which connect the left and right sides of a 2D grid, as well as the top and bottom. This is illustrated in figure 2.15.




Figure 2.15: A 2D grid with torus connections

Some computer designs claim to be a grid of high dimensionality, for instance 5D, but not all dimensional are equal here. For instance a 3D grid where each node is quad-socket quad-core can be considered as a 5D grid. However, the last two dimensions are fully connected.

12. With the numbers one and two replaced by higher numbers, this is actually not a bad description of current trends in processor design.

2.6.4 Hypercubes

Above we gave a hand-waving argument for the suitability of mesh-organized processors, based on the prevalence of nearest neighbour communications. However, sometimes sends and receives between arbitrary processors occur. One example of this is the above-mentioned broadcast. For this reason, it is desirable to have a network with a smaller diameter than a mesh. On the other hand we want to avoid the complicated design of a fully connected network.

A good intermediate solution is the *hypercube* design. An n -dimensional hypercube computer has 2^n processors, with each processor connected to one other in each dimension; see figure 2.16.




Figure 2.16: Hypercubes




Figure 2.17: Numbering of the nodes of a hypercube

An easy way to describe this is to give each processor an address consisting of d bits: we give each node of a hypercube a number that is the bit pattern describing its location in the cube; see figure 2.17.

With this numbering scheme, a processor is then connected to all others that have an address that differs by

exactly one bit. This means that, unlike in a grid, a processor's neighbours do not have numbers that differ by 1 or \sqrt{P} , but by 1, 2, 4, 8, ...

The big advantages of a hypercube design are the small diameter and large capacity for traffic through the network.

Exercise 2.14. What is the diameter of a hypercube? What is the bisection width?

One disadvantage is the fact that the processor design is dependent on the total machine size. In practice, processors will be designed with a maximum number of possible connections, and someone buying a smaller machine then will be paying for unused capacity. Another disadvantage is the fact that extending a given machine can only be done by doubling it: other sizes than 2^p are not possible.

Exercise 2.15. Consider the parallel summing example of section 2.1, and give the execution time of a parallel implementation on a hypercube. Show that the theoretical speedup from the example is attained (up to a factor) for the implementation on a hypercube.

2.6.4.1 Embedding grids in a hypercube

Above we made the argument that mesh-connected processors are a logical choice for many applications that model physical phenomena. Hypercubes do not look like a mesh, but they have enough connections that they can simply pretend to be a mesh by ignoring certain connections.

Let's say that we want the structure of a 1D array: we want processors with a numbering so that processor i can directly send data to $i - 1$ and $i + 1$. We can not use the obvious numbering of nodes as in figure 2.17. For instance, node 1 is directly connected to node 0, but has a distance of 2 to node 2. The right neighbour of node 3 in a ring, node 4, even has the maximum distance of 3 in this hypercube. Clearly we need to renumber the nodes in some way.

What we will show is that it's possible to walk through a hypercube, touching every corner exactly once, which is equivalent to embedding a 1D mesh in the hypercube.

The basic concept here is a (binary reflected) *Gray code* [58]. This is a way of ordering the binary numbers $0 \dots 2^d - 1$ as g_0, \dots, g_{2^d-1} so that g_i and g_{i+1} differ in only one bit. Clearly, the ordinary binary numbers do not satisfy this: the binary representations for 1 and 2 already differ in two bits. Why do Gray codes help us? Well, since g_i and g_{i+1} differ only in one bit, it means they are the numbers of nodes in the hypercube that are directly connected.

Figure 2.18 illustrates how to construct a Gray code. The procedure is recursive, and can be described informally as 'divide the cube into two subcubes, number the one subcube, cross over to the other subcube, and number its nodes in the reverse order of the first one'.

Since a Gray code offers us a way to embed a one-dimensional 'mesh' into a hypercube, we can now work our way up.

Exercise 2.16. Show how a square mesh of 2^{2d} nodes can be embedded in a hypercube by appending the bit patterns of the embeddings of two 2^d node cubes. How would you accomodate a mesh of $2^{d_1+d_2}$ nodes? A three-dimensional mesh of $2^{d_1+d_2+d_3}$ nodes?

1D Gray code :	0 1
2D Gray code :	1D code and reflection: 0 1 : 1 0 append 0 and 1 bit: 0 0 : 1 1
	2D code and reflection: 0 1 1 0 : 0 1 1 0
3D Gray code :	0 0 1 1 : 1 1 0 0 append 0 and 1 bit: 0 0 0 0 : 1 1 1 1

Figure 2.18: Gray codes

2.6.5 Switched networks

Above, we briefly discussed fully connected processors. They are impractical if the connection is made by making a large number of wires between all the processors. There is another possibility, however, by connecting all the processors to a *switch* or switching network. Some popular network designs are the *crossbar*, the *butterfly exchange*, and the *fat tree*.

Switching networks are made out of switching elements, each of which have a small number (up to about a dozen) of inbound and outbound links. By hooking all processors up to some switching element, and having multiple stages of switching, it then becomes possible to connect any two processors by a path through the network.

2.6.5.1 Cross bar




Figure 2.19: A simple cross bar connecting 6 inputs to 6 outputs

The simplest switching network is a cross bar, an arrangement of n horizontal and vertical lines, with a switch element on each intersection that determines whether the lines are connected; see figure 2.19. If we designate the horizontal lines as inputs the vertical as outputs, this is clearly a way of having n inputs be mapped to n outputs. Every combination of inputs and outputs (sometimes called a ‘permutation’) is allowed.




Figure 2.20: A butterfly exchange network for two and four processors/memories

2.6.5.2 Butterfly exchange

Butterfly exchanges are typically built out of small switching elements, and they have multiple stages; as the number of processors grows, the number of stages grows with it. Figure 2.20 shows a one-stage butterfly used to implement both shared memory and distributed (or distributed shared) memory, and the extension of the latter to two stages.

As you can see in figure 2.21, butterfly exchanges allow several processors to access memory simultaneously. Also, their access times are identical, so exchange networks are a way of implementing a *UMA* architecture; see section 2.3.1. One computer that was based on a Butterfly exchange network was the *BBN Butterfly*¹³.




Figure 2.21: Two independent routes through a butterfly exchange network

Exercise 2.17. For both the simple cross bar and the butterfly exchange, the network needs to be expanded as the number of processors grows. Give the number of wires (of some unit length) and the number of switching elements that is needed in both cases to connect n processors and memories. What is the time that a data packet needs to go

13. http://en.wikipedia.org/wiki/BBN_Butterfly

from memory to processor, expressed in the unit time that it takes to traverse a unit length of wire and the time to traverse a switching element?

Routing through a butterfly network is done based on considering the bits in the destination address. On the i -th level the i -th digit is considered; if this is 1, the left exit of the switch is taken, if 0, the right exit. This




Figure 2.22: Routing through a three-stage butterfly exchange network

is illustrated in figure 2.22. If we attach the memories to the processors, as in figure 2.21, we need only two bits (to the last switch) but a further three bits to describe the reverse route.

2.6.5.3 Fat-trees

If we were to connect switching nodes like a tree, there would be a big problem with congestion close to the root since there are only two wires attached to the root note. Say we have a k -level tree, so there are 2^k leaf nodes. If all leaf nodes in the left subtree try to communicate with nodes in the right subtree, we have 2^{k-1} messages going through just one wire into the root, and similarly out through one wire. A fat-tree is a tree network where each level has the same total bandwidth, so that this congestion problem does not occur: the root will actually have 2^{k-1} incoming and outgoing wires attached [59]; see figure 2.23. The first successful computer architecture based on a fat-tree was the Connection Machines CM5.

In fat-trees, as in other switching networks, each message carries its own routing information. Since in a fat-tree the choices are limited to going up a level, or switching to the other subtree at the current level, a message needs to carry only as many bits routing information as there are levels, which is $\log_2 n$ for n processors.




Figure 2.23: A fat tree with a three-level interconnect




Figure 2.24: A fat-tree built from simple switching elements

The theoretical exposition of fat-trees in [90] shows that fat-trees are optimal in some sense: it can deliver messages as fast (up to logarithmic factors) as any other network that takes the same amount of space to build. The underlying assumption of this statement is that switches closer to the root have to connect more wires, therefore take more components, and correspondingly are larger.

This argument, while theoretically interesting, is of no practical significance, as the physical size of the network hardly plays a role in the biggest currently available computers that use fat-tree interconnect. For instance, in the Ranger supercomputer of The University of Texas at Austin, the fat-tree switch connects 60,000 cores, yet takes less than 10 percent of the floor space.

A fat tree, as sketched above, would be costly to build, since for every next level a new, bigger, switch would have to be designed. In practice, therefore, a network with the characteristics of a fat-tree is constructed from simple switching elements; see figure 2.24. This network is equivalent in its bandwidth and routing possibilities to a fat-tree. Routing algorithms will be slightly more complicated: in a fat-tree, a data packet can go up in only one way, but here a packet has to know to which of the two higher switches to route.

This type of switching network is one case of a *Clos network* [21].

2.6.6 Co-processors

Current CPUs are built to be moderately efficient at just about any conceivable computation. This implies that by restricting the functionality of a processor it may be possible to raise its efficiency, or lower its power consumption at similar efficiency. Thus, the idea of incorporating a *co-processor* has been explored many times. For instance, Intel's 8086 chip, which powered the first generation of IBM PCs, could have a numerical co-processor, the 80287, added to it. This processor was very efficient at transcendental functions and it also incorporated SIMD technology. Using a separate processor for graphics has also been popular¹⁴, leading to the SSE instructions for the x86 processor, and separate GPU units to be attached to the PCI-X bus.

Co-processors can be programmed in two different ways: sometimes it is seamlessly integrated, and certain instructions are automatically executed there, rather than on the ‘host’ processor. On the other hand, it is also possible that co-processor functions need to be explicitly invoked, and it may even be possible to overlap co-processor functions with host functions. The latter case may sound attractive from an efficiency point of view, but it raises a serious problem of programmability. The programmer now needs to identify explicitly two streams of work: one for the host processor and one for the co-processor.

Some notable parallel machines with co-processors were:

- The *Intel Paragon* (1993) had two processors per node, one for communication and the other for computation. These were in fact identical, the *Intel i860* processor. In a later revision, it became possible to pass data and function pointers to the communication processors.
- The *IBM Roadrunner* at Los Alamos was the first machine to reach a PetaFlop¹⁵. It achieved this speed through the use of Cell co-processors. Incidentally, the Cell processor is in essence the engine of the Sony Playstation3, showing again the commoditization of supercomputers (section 2.2.3).
- The Chinese *Tianhe-1A* topped the Top 500 list in 2010, reaching about 2.5 PetaFlops through the use of NVidia GPUs.

The Roadrunner and Tianhe-1A are examples of co-processors that are very powerful, and that need to be explicitly programmed independently of the host CPU. For instance, code running on the GPUs of the Tianhe-1A is programmed in *CUDA* and compiled separately.

In both cases the programmability problem is further exacerbated by the fact that the co-processor can not directly talk to the network. To send data from one co-processor to another it has to be passed to a host processor, from there through the network to the other host processor, and only then moved to the target co-processor.

14. Further examples are the use of co-processors for Digital Signal Processing (DSP) instructions, as well as FPGA boards which can be reconfigured to accommodate specific needs. We will not go into these.

15. The *Grape computer* had reached this point earlier, but that was a special purpose machine for molecular dynamics calculations.

2.6.7 Bandwidth and latency

The statement above that sending a message can be considered a unit time operation, is of course unrealistic. A large message will take longer to transmit than a short one. There are two concepts to arrive at a more realistic description of the transmission process; we have already seen this in section 1.3.2 in the context of transferring data between cache levels of a processor.

latency Setting up a communication between two processors takes an amount of time that is independent of the message size. The time that this takes is known as the *latency* of a message. There are various causes for this delay.

- The two processors engage in ‘hand-shaking’, to make sure that the recipient is ready, and that appropriate buffer space is available for receiving the message.
- The message needs to be encoded for transmission by the sender, and decoded by the receiver.
- The actual transmission may take time: parallel computers are often big enough that, even at lightspeed, the first byte of a message can take hundreds of cycles to traverse the distance between two processors.

bandwidth After a transmission between two processors has been initiated, the main number of interest is the number of bytes per second that can go through the channel. This is known as the *bandwidth*. The bandwidth can usually be determined by the *channel rate*, the rate at which a physical link can deliver bits, and the *channel width*, the number of physical wires in a link. The channel width is typically a multiple of 16, usually 64 or 128. This is also expressed by saying that a channel can send one or two 8-byte words simultaneously.

Bandwidth and latency are formalized in the expression

$$T(n) = \alpha + \beta n$$

for the transmission time of an n -byte message. Here, α is the latency and β is the time per byte, that is, the inverse of bandwidth. Sometimes we consider data transfers that involve communication, for instance in the case of a *collective operation*; see section 6.2.1. We then extend the transmission time formula to

$$T(n) = \alpha + \beta n + \gamma n$$

where γ is the time per operation, that is, the inverse of the *computation rate*.

It would also be possible to refine this formulas as

$$T(n, p) = \alpha + \beta n + \delta p$$

where p is the number of network ‘hops’ that is traversed. However, on most networks the value of δ is far lower than of α , so we will ignore it here. Also, in fat-tree networks (section 2.6.5.3) the number of hops is of the order of $\log P$, where P is the total number of processors, so it can never be very large anyway.

2.7 Efficiency of parallel computing

There are two important reasons for using a parallel computer: to have access to more memory or to obtain higher performance. It is easy to characterize the gain in memory, as the total memory is the sum of the

individual memories. The speed of a parallel computer is harder to characterize. This section will have an extended discussion on theoretical measures for expressing and judging the gain in execution speed from going to a parallel architecture.

2.7.1 Definitions

A simple approach to defining speedup is to let the same program run on a single processor, and on a parallel machine with p processors, and to compare runtimes. With T_1 the execution time on a single processor and T_p the time on p processors, we define the *speedup* as $S_p = T_1/T_p$. (Sometimes T_1 is defined as ‘the best time to solve the problem on a single processor’, which allows for using a different algorithm on a single processor than in parallel.) In the ideal case, $T_p = T_1/p$, but in practice we don’t expect to attain that, so $S_p \leq p$. To measure how far we are from the ideal speedup, we introduce the *efficiency* $E_p = S_p/p$. Clearly, $0 < E_p \leq 1$.

There is a practical problem with this definition: a problem that can be solved on a parallel machine may be too large to fit on any single processor. Conversely, distributing a single processor problem over many processors may give a distorted picture since very little data will wind up on each processor. Below we will discuss more realistic measures of speed-up.

There are various reasons why the actual speed is less than P . For one, using more than one processors necessitates communication, which is overhead that was not part of the original computation. Secondly, if the processors do not have exactly the same amount of work to do, they may be idle part of the time (this is known as *load unbalance*), again lowering the actually attained speedup. Finally, code may have sections that are inherently sequential.

Communication between processors is an important source of a loss of efficiency. Clearly, a problem that can be solved without communication will be very efficient. Such problems, in effect consisting of a number of completely independent calculations, is called *embarrassingly parallel*; it will have close to a perfect speedup and efficiency.

Exercise 2.18. The case of speedup larger than the number of processors is called *superlinear speedup*. Give a theoretical argument why this can never happen.

In practice, superlinear speedup can happen. For instance, suppose a problem is too large to fit in memory, and a single processor can only solve it by swapping data to disc. If the same problem fits in the memory of two processors, the speedup may well be larger than 2 since disc swapping no longer occurs. Having less, or more localized, data may also improve the cache behaviour of a code.

2.7.2 Asymptotics

If we ignore limitations such as that the number of processors has to be finite, or the physicalities of the interconnect between them, we can derive theoretical results on the limits of parallel computing. This section will give a brief introduction to such results, and discuss their connection to real life high performance computing.

Consider for instance the matrix-matrix multiplication $C = AB$, which takes $2N^3$ operations where N is the matrix size. Since there are no dependencies between the operations for the elements of C , we can

2. Parallel Computing

perform them all in parallel. If we had N^2 processors, we could assign each to an (i, j) coordinate in C , and have it compute c_{ij} in $2N$ time. Thus, this parallel operation has efficiency 1, which is optimal.

Exercise 2.19. Show that this algorithm ignores some serious issues about memory usage:

- If the matrix is kept in shared memory, how many simultaneous reads from each memory locations are performed?
- If the processors keep the input and output to the local computations in local storage, how much duplication is there of the matrix elements?

Adding N numbers $\{x_i\}_{i=1\dots N}$ can be performed in $\log_2 N$ time with $N/2$ processors. As a simple example, consider the sum of n numbers: $s = \sum_{i=1}^n a_i$. If we have $n/2$ processors we could compute:

1. Define $s_i^{(0)} = a_i$.
2. Iterate with $j = 1, \dots, \log_2 n$:
3. Compute $n/2^j$ partial sums $s_i^{(j)} = s_{2i}^{(j-1)} + s_{2i+1}^{(j-1)}$

We see that the $n/2$ processors perform a total of n operations (as they should) in $\log_2 n$ time. The efficiency of this parallel scheme is $O(1/\log_2 n)$, a slowly decreasing function of n .

Exercise 2.20. Show that, with the scheme for parallel addition just outlined, you can multiply two matrices in $\log_2 N$ time with $N^3/2$ processors. What is the resulting efficiency?

It is now a legitimate theoretical question to ask

- If we had infinitely many processors, what is the lowest possible time complexity for matrix-matrix multiplication, or
- Are there faster algorithms that still have $O(1)$ efficiency?

Such questions have been researched (see for instance [67]), but they have little bearing on high performance computing.

A first objection to these kinds of theoretical bounds is that they implicitly assume some form of shared memory. In fact, the formal model for these algorithms is called a *Parallel Random Access Machine (PRAM)*, where the assumption is that every memory location is accessible to any processor. Often an additional assumption is made that multiple access to the same location are in fact possible¹⁶. These assumptions are unrealistic in practice, especially in the context of scaling up the problem size and the number of processors. A further objection to the PRAM model is that even on a single processor it ignores the memory hierarchy; section 1.3.

But even if we take distributed memory into account, theoretical results can still be unrealistic. The above summation algorithm can indeed work unchanged in distributed memory, except that we have to worry about the distance between active processors increasing as we iterate further. If the processors are connected by a linear array, the number of ‘hops’ between active processors doubles, and with that, asymptotically, the computation time of the iteration. The total execution time then becomes $n/2$, a disappointing result given that we throw so many processors at the problem.

What if the processors are connected with a hypercube topology? It is not hard to see that the summation algorithm can then indeed work in $\log_2 n$ time. However, as $n \rightarrow \infty$, can we build a sequence of hypercubes of n nodes and keep the communication time between two connected constant? Since communication time

16. This notion can be made precise; for instance, one talks of a CREW-PRAM, for Concurrent Read, Exclusive Write PRAM.

depends on latency, which partly depends on the length of the wires, we have to worry about the physical distance between nearest neighbours.

The crucial question here is whether the hypercube (an n -dimensional object) can be embedded in 3-dimensional space, while keeping the distance (measured in meters) constant between connected neighbours. It is easy to see that a 3-dimensional grid can be scaled up arbitrarily while maintaining a unit wire length, but the question is not clear for a hypercube. There, the length of the wires may have to increase as n grows, which runs afoul of the finite speed of electrons.

We sketch a proof (see [42] for more details) that, in our three dimensional world and with a finite speed of light, speedup is limited to $\sqrt[4]{n}$ for a problem on n processors, no matter the interconnect. The argument goes as follows. Consider an operation that involves collecting a final result on one processor. Assume that each processor takes a unit volume of space, produces one result per unit time, and can send one data item per unit time. Then, in an amount of time t , at most the processors in a ball with radius t , that is, $O(t^3)$ processors can contribute to the final result; all others are too far away. In time T , then, the number of operations that can contribute to the final result is $\int_0^T t^3 dt = O(T^4)$. This means that the maximum achievable speedup is the fourth root of the sequential time.

Finally, the question ‘what if we had infinitely many processors’ is not realistic as such, but we will allow it in the sense that we will ask the *weak scaling* question (section 2.7.4) ‘what if we let the problem size and the number of processors grow proportional to each other’. This question is legitimate, since it corresponds to the very practical deliberation whether buying more processors will allow one to run larger problems, and if so, with what ‘bang for the buck’.

2.7.3 Amdahl’s law

One reason for less than perfect speedup is that parts of a code can be inherently sequential. This limits the parallel efficiency as follows. Suppose that 5% of a code is sequential, then the time for that part can not be reduced, no matter how many processors are available. Thus, the speedup on that code is limited to a factor of 20. This phenomenon is known as *Amdahl’s Law* [2], which we will now formulate.

Let F_s be the *sequential fraction* and F_p be the *parallel fraction* (or more strictly: the ‘parallelizable’ fraction) of a code, respectively. Then $F_p + F_s = 1$. The parallel execution time T_p on p processors is the sum of the part that is sequential $T_1 F_s$ and the part that can be parallelized $T_1 F_p / P$:

$$T_p = T_1(F_s + F_p/P). \quad (2.3)$$

As the number of processors grows $P \rightarrow \infty$, the parallel execution time now approaches that of the sequential fraction of the code: $T_p \downarrow T_1 F_s$. We conclude that speedup is limited by $S_P \leq 1/F_s$ and efficiency is a decreasing function $E \sim 1/P$.

The sequential fraction of a code can consist of things such as I/O operations. However, there are also parts of a code that in effect act as sequential. Consider a program that executes a single loop, where all iterations can be computed independently. Clearly, this code is easily parallelized. However, by splitting the loop in a number of parts, one per processor, each processor now has to deal with loop overhead: calculation of bounds, and the test for completion. This overhead is replicated as many times as there are processors. In effect, loop overhead acts as a sequential part of the code.

Exercise 2.21. Investigate the implications of Amdahls's law: if the number of processors P increases, how does the parallel fraction of a code have to increase to maintain a fixed efficiency?

2.7.3.1 Amdahl's law with communication overhead

In a way, Amdahl's law, sobering as it is, is even optimistic. Parallelizing a code will give a certain speedup, but it also introduces *communication overhead* that will lower the speedup attained. Let us refine our model of equation (2.3) (see [87, p. 367]):

$$T_p = T_1(F_s + F_p/P) + T_c,$$

where T_c is a fixed communication time.

To assess the influence of this communication overhead, we assume that the code is fully parallelizable, that is, $F_p = 1$. We then find that

$$S_p = \frac{T_1}{T_1/p + T_c}.$$

For this to be close to p , we need $T_c \ll T_1/p$ or $p \ll T_1/T_c$. In other words, the number of processors should not grow beyond the ratio of scalar execution time and communication overhead.

2.7.3.2 Gustafson's law

Amdahl's law was thought to show that large numbers of processors would never pay off. However, the implicit assumption in Amdahl's law is that there is a fixed computation which gets executed on more and more processors. In practice this is not the case: typically there is a way of scaling up a problem (in chapter 4 you will learn the concept of ‘discretization’), and one tailors the size of the problem to the number of available processors.

A more realistic assumption would be to say that the sequential fraction is independent of the problem size, and the parallel fraction can be arbitrarily extended. To formalize this, instead of starting with the execution time of the sequential program, let us start with the execution time of the parallel program, and say that

$$T_p = F_s + F_p \equiv 1,$$

and the execution time of this problem on a sequential processor would then be

$$T_1 = F_s + p \cdot F_p.$$

This gives us a speedup of

$$S_p = \frac{T_1}{T_p} = \frac{F_s + p \cdot F_p}{F_s + F_p} = F_s + p \cdot F_p = p - (p - 1) \cdot F_s.$$

That is, speedup is now a function that decreases from p , linearly with p .

2.7.3.3 Amdahl's law and hybrid programming

Above, you learned about hybrid programming, a mix between distributed and shared memory programming. This leads to a new form of Amdahl's law.

Suppose we have p nodes with c cores each, and F_p describes the fraction of the code that uses c -way thread parallelism. We assume that the whole code is fully parallel over the p nodes. The ideal speed up would be pc , and the ideal parallel running time $T_1/(pc)$, but the actual running time is

$$T_{p,c} = T_1 \left(\frac{F_s}{p} + \frac{F_p}{pc} \right) = \frac{T_1}{pc} (F_s c + F_p) = \frac{T_1}{pc} (1 + F_s(c - 1)).$$

Exercise 2.22. Show that the speedup $T_1/T_{p,c}$ can be approximated by p/F_s .

In the original Amdahl's law, speedup was limited by the sequential portion to a fixed number $1/F_s$, in hybrid programming it is limited by the task parallel portion to p/F_s .

2.7.4 Scalability

Above, we remarked that splitting a given problem over more and more processors does not make sense: at a certain point there is just not enough work for each processor to operate efficiently. Instead, in practice, users of a parallel code will either choose the number of processors to match the problem size, or they will solve a series of increasingly larger problems on correspondingly growing numbers of processors. In both cases it is hard to talk about speedup. Instead, the concept of *scalability* is used.

We distinguish two types of scalability. So-called *strong scalability* is in effect the same as speedup, discussed above. We say that a program shows strong scalability if, partitioned over more and more processors, it shows perfect or near perfect speedup. Typically, one encounters statements like 'this problem scales up to 500 processors', meaning that up to 500 processors the speedup will not noticeably decrease from optimal. It is not necessary for this problem to fit on a single processor: often a smaller number such as 64 processors is used as the baseline from which scalability is judged.

More interestingly, *weak scalability* is a more vaguely defined term. It describes that, as problem size and number of processors grow in such a way that the amount of data per processor stays constant, the speed in operations per second of each processor also stays constant. This measure is somewhat hard to report, since the relation between the number of operations and the amount of data can be complicated. If this relation is linear, one could state that the amount of data per processor is kept constant, and report that parallel execution time is constant as the number of processors grows.

Although in industry parlance the term 'scalability' is sometimes applied to architectures or whole computer systems¹⁷, in scientific computing scalability is a property of an algorithm and the way it is parallelized on an architecture, in particular noting the way data is distributed. In section 6.2 you will find an analysis of the matrix-vector product operation: distributing a matrix by block rows turns out not to be scalable, but a two-dimensional distribution by submatrices is.

17. "A scalable computer is a computer designed from a small number of basic components, without a single bottleneck component, so that the computer can be incrementally expanded over its designed scaling range, delivering linear incremental performance for a well-defined set of scalable applications. General-purpose scalable computers provide a wide range of processing, memory size, and I/O resources. Scalability is the degree to which performance increments of a scalable computer are linear" [7].

2.8 Multi-threaded architectures

The architecture of modern CPUs is largely dictated by the fact that getting data from memory is much slower than processing it. Hence, a hierarchy of ever faster and smaller tries to keep data as close to the processing unit as possible, mitigating the long latency and small bandwidth of main memory. The ILP in the processing unit also helps to hide the latency and more fully utilize the available bandwidth.

However, finding ILP is a job for the compiler and there is a limit to what it can practically find. On the other hand, scientific codes are often very *data parallel* in a sense that is obvious to the programmer, though not necessarily to the compiler. Would it be possible for the programmer to specify this parallelism explicitly and for the processor to use it?

In section 2.2.1 you saw that SIMD architectures can be programmed in an explicitly data parallel way. What if we have a great deal of data parallelism but not that many processing units? In that case, we could turn the parallel instruction streams into threads (see section 2.5.1) and have multiple threads be executed on each processing unit. Whenever a thread would stall because of an outstanding memory request, the processor could switch to another thread for which all the necessary inputs are available. This is called *multi-threading*. While it sounds like a way of preventing the processor from waiting for memory, it can also be viewed as a way of keeping memory maximally occupied.

Exercise 2.23. If you consider the long latency and limited bandwidth of memory as two separate problems, does multi-threading address them both?

The problem here is that most CPUs are not good at switching quickly between threads. A *context switch* (switching between one thread and another) takes a large number of cycles, comparable to a wait for data from main memory. In a so-called *Multi-Threaded Architecture (MTA)* a context-switch is very efficient, sometimes as little as a single cycle, which makes it possible for one processor to work on many threads simultaneously.

The multi-threaded concept was explored in the *Tera Computer MTA* machine, which evolved into the current *Cray XMT*¹⁸.

The other example of an MTA is the GPU, where the processors work as SIMD units, while being themselves multi-threaded; see section 2.9.

2.9 GPU computing

A *Graphics Processing Unit (GPU)* (or sometimes *General Purpose Graphics Processing Unit (GPGPU)*) is a special purpose processor, designed for fast graphics processing. However, since the operations done for graphics are a form of arithmetic, GPUs have gradually evolved a design that is also useful for non-graphics computing. The general design of a GPU is motivated by the ‘graphics pipeline’: identical operations are performed on many data elements in a form of *data parallelism* (section 2.4.1), and a number of such blocks of data parallelism can be active at the same time.

The basic limitations that hold for a CPU hold for a GPU: accesses to memory incur a long latency. The solution to this problem in a CPU is to introduce levels of cache; in the case of a GPU a different approach

18. Tera Computer renamed itself *Cray Inc.* after acquiring *Cray Research* from *SGI*.

is taken (see also section 2.8). GPUs are concerned with *throughput computing*, delivering large amounts of data with high average rates, rather than any single result as quickly as possible. This is made possible by supporting many threads (section 2.5.1) and having very fast switching between them. While one thread is waiting for data from memory, another thread that already has its data can proceed with its computations.

Present day GPUs¹⁹ have an architecture that combines SIMD and SPMD parallelism. Threads are not completely independent, but are ordered in *thread blocks*, where all threads in the block execute the same instruction, making the execution SIMD. It is also possible to schedule the same instruction stream (a ‘kernel’ in Cuda terminology) on more than one thread block. In this case, thread blocks can be out of sync, much like processes in an SPMD context. However, since we are dealing with threads here, rather than processes, the term *Single Instruction Multiple Thread (SIMT)* is used.

This software design is apparent in the hardware; for instance, an NVidia GPU has 16–30 Streaming Multiprocessors (SMs), and a SMs consists of 8 Streaming Processors (SPs), which correspond to processor cores; see figure 2.25. The SPs act in true SIMD fashion. The number of cores in a GPU is typically larger than in traditional multi-core processors, but the cores are more limited. Hence, the term *manycore* is used here.




Figure 2.25: Diagram of a GPU

The SIMD, or *data parallel*, nature of GPUs becomes apparent in the way CUDA starts processes. A *kernel*, that is, a function that will be executed on the GPU, is started on mn cores by:

```
KernelProc<< m, n >> (args)
```

The collection of mn cores executing the kernel is known as a *grid*, and it is structured as m *thread blocks* of n threads each. A thread block can have up to 512 threads.

19. The most popular GPUs today are made by NVidia, and are programmed in CUDA, an extension of the C language.

Recall that threads share an address space (see section 2.5.1), so they need a way to identify what part of the data each thread will operate on. For this, the blocks in a thread are numbered with x, y coordinates, and the threads in a block are numbered with x, y, z coordinates. Each thread knows its coordinates in the block, and its block's coordinates in the grid.

We illustrate this with a vector addition example:

```
// Each thread performs one addition
__global__ void vecAdd(float* A, float* B, float* C)
{
    int i = threadIdx.x + blockDim.x * blockIdx.x;
    C[i] = A[i] + B[i];
}
int main()
{
    // Run grid of N/256 blocks of 256 threads each
    vecAdd<<< N/256, 256>>>(d_A, d_B, d_C);
}
```

This shows the SIMD nature of GPUs: every thread executes the same scalar program, just on different data.

Threads in a thread block are truly data parallel: if there is a conditional that makes some threads take the *true* branch and others the *false* branch, then one branch will be executed first, with all threads in the other branch stopped. Subsequently, *and not simultaneously*, the threads on the other branch will then execute their code. This may induce a severe performance penalty.

GPUs rely on large amount of data parallelism and the ability to do a fast *context switch*. This means that they will thrive in graphics and scientific applications, where there is lots of data parallelism. However they are unlikely to do well on ‘business applications’ and operating systems, where the parallelism is of the Instruction Level Parallelism (ILP) type, which is usually limited.

2.9.1 GPUs versus CPUs

These are some of the differences between GPUs and regular CPUs:

- First of all, as of this writing (late 2010), GPUs are attached processors, for instance over a *PCI-X bus*, so any data they operate on has to be transferred from the CPU. Since the memory *bandwidth* of this transfer is low, at least 10 times lower than the memory bandwidth in the GPU, sufficient work has to be done on the GPU to overcome this overhead.
- Since GPUs are graphics processors, they put an emphasis on *single precision* floating point arithmetic. To accomodate the scientific computing community, *double precision* support is increasing, but double precision speed is typically half the single precision flop rate. This discrepancy is likely to be addressed in future generations.
- A CPU is optimized to handle a single stream of instructions that can be very heterogeneous in character; a GPU is made explicitly for data parallelism, and will perform badly on traditional codes.

- A CPU is made to handle one *thread*, or at best a small number of threads. A GPU *needs* a large number of threads, far larger than the number of computational cores, to perform efficiently.

2.9.2 Expected benefit from GPUs

GPUs have rapidly gained a reputation for achieving high performance, highly cost effectively. Stories abound of codes that were ported with minimal effort to CUDA, with a resulting speedup of sometimes 400 times. Is the GPU really such a miracle machine? Were the original codes badly programmed? Why don't we use GPUs for everything if they are so great?

The truth has several aspects.

First of all, a GPU is not as general-purpose as a regular CPU: GPUs are very good at doing *data parallel* computing, and CUDA is good at expressing this fine-grained parallelism elegantly. In other words, GPUs are suitable for a certain type of computation, and will be a poor fit for many others.

Conversely, a regular CPU is not necessarily good at data parallelism. Unless the code is very carefully written, performance can degrade from optimal by approximately the following factors:

- Unless directives or explicit parallel constructs are used, compiled code will only use 1 out of the available cores, say 4.
- If instructions are not pipelined, the latency because of the floating point pipeline adds another factor of 4.
- If the core has independent add and multiply pipelines, another factor of 2 will be lost if they are not both used simultaneously.
- Failure to use SIMD registers can add more to the slowdown with respect to peak performance.

Writing the optimal CPU implementation of a computational kernel often requires writing in assembler, whereas straightforward CUDA code will achieve high performance with comparatively little effort, provided of course the computation has enough data parallelism.

2.10 Remaining topics

2.10.1 Load balancing

In much of this chapter, we assumed that a problem could be perfectly divided over processors, that is, a processor would always be performing useful work, and only be *idle* because of latency in communication. In practice, however, a processor may be idle because it is waiting for a message, and the sending processor has not even reached the send instruction in its code. Such a situation, where one processor is working and another is idle, is described as *load unbalance*: there is no intrinsic reason for the one processor to be idle, and it could have been working if we had distributed the work load differently.

There is an asymmetry between processors having too much work and having not enough work: it is better to have one processor that finishes a task early, than having one that is overloaded so that all others wait for it.

Exercise 2.24. Make this notion precise. Suppose a parallel task takes time 1 on all processors but one.

- Let $0 < \alpha < 1$ and let one processor take time $1 + \alpha$. What is the speedup and efficiency as function of the number of processors? Consider this both in the Amdahl and Gustafsson sense (section 2.7.3).
- Answer the same questions if one processor takes time $1 - \alpha$.

Load balancing is often expensive since it requires moving relatively large amounts of data. For instance, section 6.4 has an analysis showing that the data exchanges during a sparse matrix-vector product is of a lower order than what is stored on the processor. However, we will not go into the actual cost of moving: our main concerns here are to balance the workload, and to preserve any locality in the original load distribution.

2.10.1.1 Load balancing of independent tasks

Let us first consider the case of a job that can be partitioned into independent tasks that do not communicate. An example would be computing the pixels of a *Mandelbrot set* picture, where each pixel is set according to a mathematical function that does not depend on surrounding pixels. If we could predict the time it would take to draw an arbitrary part of the picture, we could make a perfect division of the work and assign it to the processors. This is known as *static load balancing*.

More realistically, we can not predict the running time of a part of the job perfectly, and we use an *overdecomposition* of the work: we divide the work in more tasks than there are processors. These tasks are then assigned to a *work pool*, and processors take the next job from the pool whenever they finish a job. This is known as *dynamic load balancing*. Many graph and combinatorial problems can be approached this way; see section 2.4.3. For task assignment in a multicore context, see section 6.10.

There are results that show that randomized assignment of tasks to processors is statistically close to optimal [79], but this ignores the aspect that in scientific computing tasks typically communicate frequently.

2.10.1.2 Load balancing as graph problem

Next let us consider a parallel job where the parts do communicate. In this case we need to balance both the scalar workload and the communication.

A parallel computation can be formulated as a graph (see Appendix A.5 for an introduction to graph theory) where the processors are the vertices, and there is an edge between two vertices if their processors need to communicate at some point. Such a graph is often derived from an underlying graph of the problem being solved. As an example consider the matrix-vector product $y = Ax$ where A is a sparse matrix, and look in detail at the processor that is computing y_i for some i . The statement $y_i \leftarrow y_i + A_{ij}x_j$ implies that this processor will need the value x_j , so, if this variable is on a different processor, it needs to be sent over.

We can formalize this: Let the vectors x and y be distributed disjointly over the processors, and define uniquely $P(i)$ as the processor that owns index i . Then there is an edge (P, Q) if there is a nonzero element a_{ij} with $P = P(i)$ and $Q = P(j)$. This graph is undirected if the matrix is *structurally symmetric*, that is $a_{ij} \neq 0 \Leftrightarrow a_{ji} \neq 0$.

The distribution of indices over the processors now gives us vertex and edge weights: a processor has a vertex weight that is the number of indices owned by it; an edge (P, Q) has a weight that is the number of vector components that need to be sent from Q to P , as described above.

The load balancing problem can now be formulated as follows:

Find a partitioning $\mathbb{P} = \cup_i \mathbb{P}_i$, such the variation in vertex weights is minimal, and simultaneously the edge weights are as low as possible.

Minimizing the variety in vertex weights implies that all processor have approximately the same amount of work. Keeping the edge weights low means that the amount of communication is low. These two objectives need not be satisfiable at the same time: some trade-off is likely.

Exercise 2.25. Consider the limit case where processors are infinitely fast and bandwidth between processors is also unlimited. What is the sole remaining factor determining the runtime? What graph problem do you need to solve now to find the optimal load balance? What property of a sparse matrix gives the worst case behaviour?

An interesting approach to load balancing comes from spectral graph theory (section A.5.5): if A_G is the adjacency matrix of an undirected graph and $D_G - A_G$ the *graph Laplacian*, then the eigenvector u_1 to the smallest eigenvalue zero is positive, and the eigenvector u_2 to the next eigenvalue is orthogonal to it. Therefore u_2 has to have elements of alternating sign; further analysis shows that the elements with positive sign are connected, as are the negative ones. This leads to a natural bisection of the graph.

2.10.1.3 Load redistributing

In certain applications an initial load distribution is clear, but later adjustments are needed. A typical example is in Finite Element Method (FEM) codes, where load can be distributed by a partitioning of the physical domain; see section 6.4.1. If later the discretization of the domain changes, the load has to be *rebalanced* or *redistributed*. In the next subsection we will see one technique for load balancing and rebalancing that is aimed at preserving locality.

2.10.1.4 Load balancing with space-filling curves

In the previous sections we considered two aspects of load balancing: making sure all processors have an approximately equal amount of work, and letting the distribution reflect the structure of the problem so that communication is kept within reason. We can phrase the second point as follows: we try to preserve the locality of the problem when we distribute it over a parallel machine.

Striving to preserve locality is not obviously the right strategy. In BSP (see section 2.5.9) a statistical argument is made that *random placement* will give a good load balance as well as balance of communication.

Exercise 2.26. Consider the assignment of processes to processors, where the structure of the problem is such that each processes only communicates with its nearest neighbours, and let processors be ordered in a two-dimensional grid. If we do the obvious assignment of the process grid to the processor grid, there will be no contention. Now write a program that assigns processes to random processors, and evaluate how much contention there will be.

In the previous section you saw how graph partitioning techniques can help with the second point of preserving problem locality. In this section you will see a different technique that is attractive both for the initial load assignment and for subsequent *load rebalancing*. In the latter case, a processor's work may increase or decrease, necessitating moving some of the load to a different processor.

2. Parallel Computing

For instance, some problems are adaptively refined²⁰. This is illustrated in figure 2.26. If we keep track




Figure 2.26: Adaptive refinement of a domain in subsequent levels

of these refinement levels, the problem gets a tree structure, where the leaves contain all the work. Load balancing becomes a matter of partitioning the leaves of the tree over the processors; figure 2.27. Now we




Figure 2.27: Load distribution of an adaptively refined domain

observe that the problem has a certain locality: the subtrees of any non-leaf node are physically close, so there will probably be communication between them.

- Likely there will be more subdomains than processors; to minimize communication between processors, we want each processor to contain a simply connected group of subdomains. Moreover, we want each processor to cover a part of the domain that is ‘compact’ in the sense that it has low aspect ratio, and low surface-to-volume ratio.

20. For a detailed discussion see [15].

- When a subdomain gets further subdivided, part of the load of its processor may need to be shifted to another processor. This process of *load redistributing* should preserve locality.

To fulfill these requirements we use Space-Filling Curves (SFCs). A Space-Filling Curve (SFC) for the load balanced tree is shown in figure 2.28. We will not give a formal discussion of SFCs; instead we will let




Figure 2.28: A space filling curve for the load balanced tree

figure 2.29 stand for a definition: a SFC is a recursively defined curve that touches each subdomain once²¹. The SFC has the property that domain elements that are close together physically will be close together




Figure 2.29: Space filling curves, regularly and irregularly refined

on the curve, so if we map the SFC to a linear ordering of processors we will preserve the locality of the problem.

More importantly, if the domain is refined by another level, we can refine the curve accordingly. Load can then be redistributed to neighbouring processors on the curve, and we will still have locality preserved.

21. Space-Filling Curves (SFCs) were introduced by Peano as a mathematical device for constructing a continuous surjective function from the line segment $[0, 1]$ to a higher dimensional cube $[0, 1]^d$. This upset the intuitive notion of dimension that ‘you can not stretch and fold a line segment to fill up the square’. A proper treatment of the concept of dimension was later given by Brouwer.

2.10.2 Distributed computing, grid computing, cloud computing

In this section we will take a short look at terms such as *cloud computing*, and an earlier term *distributed computing*. These are concepts that have a relation to parallel computing in the scientific sense, but that differ in certain fundamental ways.

Distributed computing can be traced back as coming from large database servers, such as airline reservations systems, which had to be accessed by many travel agents simultaneously. For a large enough volume of database accesses a single server will not suffice, so the mechanism of *remote procedure call* was invented, where the central server would call code (the procedure in question) on a different (remote) machine. The remote call could involve transfer of data, the data could be already on the remote machine, or there would be some mechanism that data on the two machines would stay synchronized. This gave rise to the *Storage Area Network (SAN)*. A generation later than distributed database systems, web servers had to deal with the same problem of many simultaneous accesses to what had to act like a single server.

We already see one big difference between distributed computing and high performance parallel computing. Scientific computing needs parallelism because a single simulation becomes too big or slow for one machine; the business applications sketched above deal with many users executing small programs (that is, database or web queries) against a large data set. For scientific needs, the processors of a parallel machine (the nodes in a cluster) have to have a very fast connection to each other; for business needs no such network is needed, as long as the central dataset stays coherent.

Both in *HPC* and in business computing, the server has to stay available and operative, but in distributed computing there is considerably more liberty in how to realize this. For a user connecting to a service such as a database, it does not matter what actual server executes their request. Therefore, distributed computing can make use of *virtualization*: a virtual server can be spawned off on any piece of hardware.

An analogy can be made between remote servers, which supply computing power wherever it is needed, and the electric grid, which supplies electric power wherever it is needed. This has led to *grid computing* or *utility computing*, with the Teragrid, owned by the US National Science Foundation, as an example. Grid computing was originally intended as a way of hooking up computers connected by a *Local Area Network (LAN)* or *Wide Area Network (WAN)*, often the Internet. The machines could be parallel themselves, and were often owned by different institutions. More recently, it has been viewed as a way of sharing resources, both datasets, software resources, and scientific instruments, over the network.

The notion of utility computing as a way of making services available, which you recognize from the above description of distributed computing, went mainstream with Google's search engine, which indexes the whole of the Internet. Another example is the GPS capability of Android mobile phones, which combines GIS, GPS, and mashup data. The computing model by which Google's gathers and processes data has been formalized in MapReduce [23]. It combines a data parallel aspect (the 'map' part) and a central accumulation part ('reduce'). Neither involves the tightly coupled neighbour-to-neighbour communication that is common in scientific computing. An open source framework for MapReduce computing exists in Hadoop [63]. Amazon offers a commercial Hadoop service.

The concept of having a remote computer serve user needs is attractive even if no large datasets are involved, since it absolves the user from the need of maintaining software on their local machine. Thus, Google Docs offers various 'office' applications without the user actually installing any software. This idea is sometimes

called *Software as-a Service* (SaaS), where the user connects to an ‘application server’, and accesses it through a client such as a web browser. In the case of Google Docs, there is no longer a large central dataset, but each user interacts with their own data, maintained on Google’s servers. This of course has the large advantage that the data is available from anywhere the user has access to a web browser.

The SaaS concept has several connections to earlier technologies. For instance, after the mainframe and workstation eras, the so-called *thin client* idea was briefly popular. Here, the user would have a workstation rather than a terminal, yet work on data stored on a central server. One product along these lines was Sun’s *Sun Ray* (circa 1999) where users relied on a smartcard to establish their local environment on an arbitrary, otherwise stateless, workstation.

The term *cloud computing* usually refers to the internet-based model of SaaS where the data is not maintained by the user. However, it can span some or all of the above concepts, depending on who uses the term. Here is a list of characteristics:

- A cloud is centrally administered and maintained, involving applications running on servers that are not owned by the user. The user has local and homogeneous access to services on a subscription basis, as pay-as-you-go.
- Cloud computing is typically associated with large amounts of data, either a single central dataset such as an airline database server, or many independent datasets such as for Google Docs, each of which are used by a single user or a small group of users. In the case of large datasets, they are stored distributedly, with concurrent access for the clients.
- Cloud computing, like earlier grid computing, allows the user freedom of choice in the client platform. In an extreme example, Amazon’s Kindle books allow one to read the same book on a PC, and a smartphone; the cloud-stored book ‘remembers’ where the reader left off, regardless the platform.
- Cloud computing makes a whole datacenter appear as a single computer to the user [108].
- The services offered by cloud computing are typically business applications and IT services, rather than scientific computing. Cloud service providers are starting to offer clusters that allow tightly coupled parallelism, but tests show that this is not yet efficient.
- Computing in a cloud is probably virtualized, or at least the client interfaces to an abstract notion of a server. These strategies often serve to ‘move the work to the data’.
- Server processes are loosely coupled, at best synchronized through working on the same dataset.
- Cloud computing can be interfaced through a web browser; it can involve a business model that is ‘pay as you go’.

Cloud computing clearly depends on the following factors:

- The ubiquity of the internet;
- Virtualization of servers;
- Commoditization of processors and hard drives.

The model where services are available on demand is attractive for businesses, which increasingly are using cloud services. The advantages are that it requires no initial monetary and time investment, and that no decisions about type and size of equipment have to be made. At the moment, cloud services are mostly focused on databases and office applications, but scientific clouds with a high performance interconnect are under development.

The following is a broad classification of usage scenarios of cloud resources²².

- Scaling. Here the cloud resources are used as a platform that can be expanded based on user demand. This can be considered Platform-as-a-Service (PaaS): the cloud provides software and development platforms, eliminating the administration and maintenance for the user.
We can distinguish between two cases: if the user is running single jobs and is actively waiting for the output, resources can be added to minimize the wait time for these jobs (capability computing). On the other hand, if the user is submitting jobs to a queue and the time-to-completion of any given job is not crucial (capacity computing), resources can be added as the queue grows. In HPC applications, users can consider the cloud resources as a cluster; this falls under Infrastructure-as-a-Service (IaaS): the cloud service is a computing platforms allowing customization at the operating system level.
- Multi-tenancy. Here the same software is offered to multiple users, giving each the opportunity for individual customizations. This falls under Software-as-a-Service (SaaS): software is provided on demand; the customer does not purchase software, but only pays for its use.
- Batch processing. This is a limited version of one of the Scaling scenarios above: the user has a large amount of data to process in batch mode. The cloud then becomes a batch processor. This model is a good candidate for MapReduce computations; section 2.10.5.
- Storage. Most cloud providers offer database services, so this model absolves the user from maintaining their own database, just like the Scaling and Batch processing models take away the user's concern with maintaining cluster hardware.
- Synchronization. This model is popular for commercial user applications. Netflix and Amazon's Kindle allow users to consume online content (streaming movies and ebooks respectively); after pausing the content they can resume from any other platform. Apple's recent iCloud provides synchronization for data in office applications, but unlike Google Docs the applications are not 'in the cloud' but on the user machine.

The first Cloud to be publicly accessible was Amazon's Elastic Compute cloud (EC2), launched in 2006. EC2 offers a variety of different computing platforms and storage facilities. Nowadays more than a hundred companies provide cloud based services, well beyond the initial concept of computers-for-rent.

The infrastructure for cloud computing can be interesting from a computer science point of view, involving distributed file systems, scheduling, virtualization, and mechanisms for ensuring high reliability.

An interesting project, combining aspects of grid and cloud computing is the Canadian Advanced Network For Astronomical Research[116]. Here large central datasets are being made available to astronomers as in a grid, together with compute resources to perform analysis on them, in a cloud-like manner. Interestingly, the cloud resources even take the form of user-configurable virtual clusters.

2.10.3 Capability versus capacity computing

Large parallel computers can be used in two different ways. In later chapters you will see how scientific problems can be scaled up almost arbitrarily. This means that with an increasing need for accuracy or scale, increasingly large computers are needed. The use of a whole machine for a single problem, with only time-to-solution as the measure of success, is known as *capability computing*.

22. Based on a blog post by Ricky Ho: <http://blogs.globallogic.com/five-cloud-computing-patterns>.

On the other hand, many problems need less than a whole supercomputer to solve, so typically a computing center will set up a machine so that it serves a continuous stream of user problems, each smaller than the full machine. In this mode, the measure of success is the sustained performance per unit cost. This is known as *capacity computing*, and it requires a finely tuned job scheduling strategy. This topic, while interesting, is not further discussed in this book.

2.10.4 FPGA computing

Field-Programmable Gate Arrays (FPGAs) are reconfigurable devices: the electronics are organized in low level building block whose function can be changed dynamically. Even the connections between the building blocks can be changed. Thus, FPGAs are suitable for experimenting with hardware before an actual chip is built; see <http://ramp.eecs.berkeley.edu/> for one example.

The fact that FPGAs are typically much slower than regular CPUs is not a major concern when they are used for prototyping. However, they are in fact suitable for certain calculations. Since the computation is ‘hard-wired’ in an FPGA, no silicon is wasted, making the device very energy efficient. Not all computations are candidates for realization in an FPGA, but as one example they are popular for certain calculations in *computational finance*.

2.10.5 MapReduce

MapReduce [23] is a programming model for certain parallel operations. One of its distinguishing characteristics is that it is implemented using *functional programming*. The MapReduce model handles computations of the following form:

- For all available data, select items that satisfy a certain criterium;
- and emit a key-value pair for them. This is the mapping stage.
- Optionally there can be a combine/sort stage where all pairs with the same key value are grouped together.
- Then do a global reduction on the keys, yielding one or more of the corresponding values. This is the reduction stage.

We will now give a few examples of using MapReduce, and present the functional programming model that underlies the MapReduce abstraction.

Expressive power of the MapReduce model The reduce part of the MapReduce model makes it a prime candidate for computing global statistics on a dataset. One example would be to count how many times each of a set of words appears in some set of documents. The function being mapped knows the set of words, and outputs for each document a pair of document name and a list with the occurrence counts of the words. The reduction then does a componentwise sum of the occurrence counts.

The combine stage of MapReduce makes it possible to transform data. An example is a ‘Reverse Web-Link Graph’: the map function outputs target-source pairs for each link to a target URL found in a page named “source”. The reduce function concatenates the list of all source URLs associated with a given target URL and emits the pair target-list(source).

A less obvious example is computing PageRank (section 8.2.2) with MapReduce. Here we use the fact that the PageRank computation relies on a distributed sparse matrix-vector product. Each web page corresponds to a column of the web matrix W ; given a probability p_j of being on page j , that page can then compute tuples $\langle i, w_{ij}p_j \rangle$. The combine stage of MapReduce then sums together $(Wp)_i = \sum_j w_{ij}p_j$.

Database operations can be implemented with MapReduce but since it has a relatively large latency, it is unlikely to be competitive with standalone databases, which are optimized for fast processing of a single query, rather than bulk statistics. For other applications see <http://horicky.blogspot.com/2010/08/designing-algorithmis-for-map-reduce.html>.

Functional programming The mapping and reduction operations are easily implemented on any type of parallel architecture, using a combination of threading and message passing. However, at Google where this model was developed traditional parallelism was not attractive for two reasons. First of all, processors could fail during the computation, so a traditional model of parallelism would have to be enhanced with *fault tolerance* mechanisms. Secondly, the computing hardware could already have a load, so parts of the computation may need to be migrated, and in general any type of synchronization between tasks would be very hard.

MapReduce is one way to abstract from such details of parallel computing, namely through adopting a functional programming model. In such a model the only operation is the evaluation of a function, applied to some arguments, where the arguments are themselves the result of a function application, and the result of the computation is again used as argument for another function application. In particular, in a strict functional model there are no variables, so there is no static data.

A function application, written in *Lisp* style as $(f\ a\ b)$ (meaning that the function f is applied to arguments a and b) would then be executed by collecting the inputs from wherever they are to the processor that evaluates the function f . The mapping stage of a MapReduce process is denoted

```
(map f (some list of arguments))
```

and the result is a list of the function results of applying f to the input list. All details of parallelism and of guaranteeing that the computation successfully finishes are handled by the `map` function.

Now we are only missing the reduction stage, which is just as simple:

```
(reduce g (map f (the list of inputs)))
```

The `reduce` function takes a list of inputs and performs a reduction on it.

The attractiveness of this functional model lies in the fact that functions can not have *side effects*: because they can only yield a single output result, they can not change their environment, and hence there is no coordination problem of multiple tasks accessing the same data.

Thus, MapReduce is a useful abstraction for programmers dealing with large amounts of data. Of course, on an implementation level the MapReduce software uses familiar concepts such as decomposing the data space, keeping a work list, assigning tasks to processors, retrying failed operations, et cetera.

2.10.6 The top500 list

There are several informal ways of measuring just ‘how big’ a computer is. The most popular is the TOP500 list, maintained at <http://www.top500.org/>, which records a computer’s performance on the *Linpack benchmark*. *Linpack* is a package for linear algebra operations, and no longer in use, since it has been superseded by *Lapack* for shared memory and *Scalapack* for distributed memory computers. The benchmark operation is the solution of a (square, nonsingular, dense) linear system through LU factorization with partial pivoting, with subsequent forward and backward solution.

The LU factorization operation is one that has great opportunity for cache reuse, since it is based on the matrix-matrix multiplication kernel discussed in section 1.5.1. It also has the property that the amount of work outweighs the amount of communication: $O(n^3)$ versus $O(n^2)$. As a result, the Linpack benchmark is likely to run at a substantial fraction of the peak speed of the machine. Another way of phrasing this is to say that the Linpack benchmark is a *CPU-bound algorithm*.

Typical efficiency figures are between 60 and 90 percent. However, it should be noted that many scientific codes do not feature the dense linear solution kernel, so the performance on this benchmark is not indicative of the performance on a typical code. Linear system solution through iterative methods (section 5.5), for instance, is much less efficient in a flops-per-second sense, being dominated by the bandwidth between CPU and memory (a *bandwidth bound algorithm*).

One implementation of the Linpack benchmark that is often used is ‘High-Performance LINPACK’ (<http://www.netlib.org/benchmark/hpl/>), which has several parameters such as blocksize that can be chosen to tune the performance.

2.10.6.1 The top500 list as a recent history of supercomputing

The top500 list offers a history of almost 20 years of supercomputing. In this section we will take a brief look at historical developments²³. First of all, figure 2.30 shows the evolution of architecture types by charting what portion of the aggregate peak performance of the whole list is due to each type.

- Vector machines feature a relatively small number of very powerful vector pipeline processors (section 2.2.1.1). This type of architecture has largely disappeared; the last major machine of this type was the Japanese *Earth Simulator* which is seen as the spike in the graph around 2002, and which was at the top of the list for two years.
- Micro-processor based architectures get their power from the large number of processors in one machine. The graph distinguishes between *x86* (*Intel* and *AMD* processors with the exception of the *Intel Itanium*) processors and others; see also the next graph.
- A number of systems were designed as highly scalable architectures: these are denoted MPP for ‘massively parallel processor’. In the early part of the timeline this includes architectures such as the *Connection Machine*, later it is almost exclusively the *IBM BlueGene*.
- In recent years ‘accelerated systems’ are the upcoming trend. Here, a processing unit such as a *GPU* is attached to the networked main processor.

Next, figure 2.31 shows the dominance of the *x86* processor type relative to other micro-processors. (Since we classified the *IBM BlueGene* as an MPP, its processors are not in the ‘Power’ category here.)

23. The graphs contain John McCalpin’s analysis of the top500 data.




Figure 2.30: Evolution of the architecture types on the top500 list

Finally, figure 2.32 shows the gradual increase in core count. Here we can make the following observations:

- In the 1990s many processors consisted of more than one chip. In the rest of the graph, we count the number of cores per ‘package’, that is, per socket. In some cases a socket can actually contain two separate dies.
- With the advent of multi-core processors, it is remarkable how close to vertical the sections in the graph are. This means that new processor types are very quickly adopted, and the lower core counts equally quickly completely disappear.
- For accelerated systems (mostly systems with GPUs) the concept of ‘core count’ is harder to define; the graph merely shows the increasing importance of this type of architecture.

2.10.7 Heterogeneous computing

You have now seen several computing models: single core, shared memory multicore, distributed memory clusters, GPUs. These models all have in common that, if there is more than one instruction stream active, all streams are interchangeable. With regard to GPUs we need to refine this statement: all instruction streams *on the GPU* are interchangeable. However, a GPU is not a standalone device, but can be considered a *co-processor* to a *host processor*.

If we want to let the host perform useful work while the co-processor is active, we now have two different instruction streams or types of streams. This situation is known as *heterogeneous computing*. In the GPU




Figure 2.31: Evolution of the architecture types on the top500 list

case, these instruction streams are even programmed by a slightly different mechanisms – using *CUDA* for the GPU – but this need not be the case: the Intel Many Integrated Cores (MIC) architecture is programmed in ordinary C.




Figure 2.32: Evolution of the architecture types on the top500 list

Chapter 3

Computer Arithmetic

Of the various types of data that one normally encounters, the ones we are concerned with in the context of scientific computing are the numerical types: integers (or whole numbers) $\dots, -2, -1, 0, 1, 2, \dots$, real numbers $0, 1, -1.5, 2/3, \sqrt{2}, \log 10, \dots$, and complex numbers $1 + 2i, \sqrt{3} - \sqrt{5}i, \dots$. Computer memory is organized to give only a certain amount of space to represent each number, in multiples of *bytes*, each containing 8 *bits*. Typical values are 4 bytes for an integer, 4 or 8 bytes for a real number, and 8 or 16 bytes for a complex number.

Since only a certain amount of memory is available to store a number, it is clear that not all numbers of a certain type can be stored. For instance, for integers only a range is stored. In the case of real numbers, even storing a range is not possible since any interval $[a, b]$ contains infinitely many numbers. Therefore, any *representation of real numbers* will cause gaps between the numbers that are stored. As a result, any computation that results in a number that is not representable will have to be dealt with by issuing an error or by approximating the result. In this chapter we will look at the ramifications of such approximations of the ‘true’ outcome of numerical calculations.

3.1 Integers

In scientific computing, most operations are on real numbers. Computations on integers rarely add up to any serious computation load¹. It is mostly for completeness that we start with a short discussion of integers.

Integers are commonly stored in 16, 32, or 64 bits, with 16 becoming less common and 64 becoming more and more so. The main reason for this increase is not the changing nature of computations, but the fact that integers are used to index arrays. As the size of data sets grows (in particular in parallel computations), larger indices are needed. For instance, in 32 bits one can store the numbers zero through $2^{32} - 1 \approx 4 \cdot 10^9$. In other words, a 32 bit index can address 4 gigabytes of memory. Until recently this was enough for most purposes; these days the need for larger data sets has made 64 bit indexing necessary.

When we are indexing an array, only positive integers are needed. In general integer computations, of course, we need to accomodate the negative integers too. We will now discuss several strategies for implementing negative integers. Our motivation here will be that arithmetic on positive and negative integers

1. Some computations are done on bit strings. We will not mention them at all.

should be as simple as on positive integers only: the circuitry that we have for comparing and operating on bitstrings should be usable for (signed) integers.

There are several ways of implementing negative integers. The simplest solution is to reserve one bit as a *sign bit*, and use the remaining 31 (or 15 or 63; from now on we will consider 32 bits the standard) bits to store the absolute magnitude. By comparison, we will call the straightforward interpretation of bitstring *unsigned* integers.

bitstring	00 ··· 0	...	01 ··· 1	10 ··· 0	...	11 ··· 1
interpretation as unsigned int	0	...	$2^{31} - 1$	2^{31}	...	$2^{32} - 1$
interpretation as signed integer	0	...	$2^{31} - 1$	-0	...	$-(2^{31} - 1)$

This scheme has some disadvantages, one being that there is both a positive and negative number zero. This means that a test for equality becomes more complicated than simply testing for equality as a bitstring. More importantly, in the second half of the bitstrings, the interpretation as signed integer *decreases*, going to the right. This means that a test for greater-than becomes complex; also adding a positive number to a negative number now has to be treated differently from adding it to a positive number.

Another solution would be to let an unsigned number n be interpreted as $n - B$ where B is some plausible base, for instance 2^{31} .

bitstring	00 ··· 0	...	01 ··· 1	10 ··· 0	...	11 ··· 1
interpretation as unsigned int	0	...	$2^{31} - 1$	2^{31}	...	$2^{32} - 1$
interpretation as shifted int	-2^{31}	...	-1	0	...	$-2^{31} + 1$

This shifted scheme does not suffer from the ± 0 problem, and addition now works properly. However, it would be nice if for positive numbers `int n` and `unsigned int n` had the same bit pattern. To get this, we flip the first and second half of the number line.

The resulting scheme, which is the one that is used most commonly, is called *2's complement*. Using this scheme, the representation of integers is formally defined as follows.

- If $0 \leq m \leq 2^{31} - 1$, the normal bit pattern for m is used.
- For $-2^{31} \leq n \leq -1$, n is represented by the bit pattern for $2^{32} - |n|$.

The following diagram shows the correspondence between bitstrings and their interpretation as 2's complement integer:

bitstring	00 ··· 0	...	01 ··· 1	10 ··· 0	...	11 ··· 1
interpretation as unsigned int	0	...	$2^{31} - 1$	2^{31}	...	$2^{32} - 1$
interpretation as 2's comp. integer	0	...	$2^{31} - 1$	-2^{31}	...	-1

Some observations:

- There is no overlap between the bit patterns for positive and negative integers, in particular, there is only one pattern for zero.
- The positive numbers have a leading bit zero, the negative numbers have the leading bit set.

Exercise 3.1. For the ‘naive’ scheme and the 2’s complement scheme for negative numbers, give pseudocode for the comparison test $m < n$, where m and n are integers. Be careful to distinguish between all cases of m, n positive, zero, or negative.

Adding two numbers with the same sign, or multiplying two numbers of any sign, may lead to a result that is too large or too small to represent. This is called *overflow*.

Exercise 3.2. Investigate what happens when you perform such a calculation. What does your compiler say if you try to write down a nonrepresentable number explicitly, for instance in an assignment statement?

In exercise 3.1 above you explored comparing two integers. Let us know explore how subtracting numbers in two’s complement is implemented. Consider $0 \leq m \leq 2^{31} - 1$ and $1 \leq n \leq 2^{31}$ and let us see what happens in the computation of $m - n$.

Suppose we have an algorithm for adding and subtracting unsigned 32-bit numbers. Can we use that to subtract two’s complement integers? We start by observing that the integer subtraction $m - n$ becomes the unsigned addition $m + (2^{32} - n)$.

- Case: $m < n$. In this case, $m - n$ is negative and $1 \leq |m - n| \leq 2^{31}$, so the bit pattern for $m - n$ is that of $2^{32} - (n - m)$. Now, $2^{32} - (n - m) = m + (2^{32} - n)$, so we can compute $m - n$ in 2’s complement by adding the bit patterns of m and $-n$ as unsigned integers.
- Case: $m > n$. Here we observe that $m + (2^{32} - n) = 2^{32} + m - n$. Since $m - n > 0$, this is a number $> 2^{32}$ and therefore not a legitimate representation of a negative number. However, if we store this number in 33 bits, we see that it is the correct result $m - n$, plus a single bit in the 33-rd position. Thus, by performing the unsigned addition, and ignoring the *overflow bit*, we again get the correct result.

In both cases we conclude that we can perform the subtraction $m - n$ by adding the unsigned number that represent m and $-n$ and ignoring overflow if it occurs.

3.2 Representation of real numbers

In this section we will look at how various kinds of numbers are represented in a computer, and the limitations of various schemes. The next section will then explore the ramifications of this for arithmetic involving computer numbers.

Real numbers are stored using a scheme that is analogous to what is known as ‘scientific notation’, where a number is represented as a *significant* and an *exponent*, for instance $6.022 \cdot 10^{23}$, which has a significant 6022 with a *radix point* after the first digit, and an exponent 23. This number stands for

$$6.022 \cdot 10^{23} = [6 \times 10^0 + 0 \times 10^{-1} + 2 \times 10^{-2} + 2 \times 10^{-3}] \cdot 10^{23}.$$

We introduce a *base*, a small integer number, 10 in the preceding example, and 2 in computer numbers, and write numbers in terms of it as a sum of t terms:

$$x = \pm 1 \times [d_1\beta^0 + d_2\beta^{-1} + d_3\beta^{-2} + \cdots + d_t\beta^{-t+1}b] \times \beta^e = \pm \sum_{i=1}^t d_i \beta^{1-i} \times \beta^e \quad (3.1)$$

where the components are

- the *sign bit*: a single bit storing whether the number is positive or negative;
- β is the base of the number system;
- $0 \leq d_i \leq \beta - 1$ the digits of the *mantissa* or *significant* – the location of the radix point (decimal point in decimal numbers) is implicitly assumed to the immediately following the first digit;
- t is the length of the mantissa;
- $e \in [L, U]$ exponent; typically $L < 0 < U$ and $L \approx -U$.

Note that there is an explicit sign bit for the whole number; the sign of the exponent is handled differently. For reasons of efficiency, e is not a signed number; instead it is considered as an unsigned number in excess of a certain minimum value. For instance, the bit pattern for the number zero is interpreted as $e = L$.

3.2.1 Some examples

Let us look at some specific examples of floating point representations. Base 10 is the most logical choice for human consumption, but computers are binary, so base 2 predominates there. Old IBM mainframes grouped bits to make for a base 16 representation.

	β	t	L	U
IEEE single precision (32 bit)	2	24	-126	127
IEEE double precision (64 bit)	2	53	-1022	1023
Old Cray 64 bit	2	48	-16383	16384
IBM mainframe 32 bit	16	6	-64	63
packed decimal	10	50	-999	999
Setun	3			

Of these, the single and double precision formats are by far the most common. We will discuss these in section 3.2.6 and further.

3.2.1.1 Binary coded decimal

Decimal numbers are not relevant in scientific computing, but they are useful in financial calculations, where computations involving money absolutely have to be exact. Binary arithmetic is at a disadvantage here, since numbers such as $1/10$ are repeating fractions in binary. With a finite number of bits in the mantissa, this means that the number $1/10$ can not be represented exactly in binary. For this reason, *binary-coded-decimal* schemes were used in old IBM mainframes, and are in fact being standardized in revisions of IEEE754 [73]; see also section 3.2.6.

In BCD schemes, one or more decimal digits are encoded in a number of bits. The simplest scheme would encode the digits $0 \dots 9$ in four bits. This has the advantage that in a BCD number each digit is readily identified; it has the disadvantage that about $1/3$ of all bits are wasted, since 4 bits can encode the numbers $0 \dots 15$. More efficient encodings would encode $0 \dots 999$ in ten bits, which could in principle store the numbers $0 \dots 1023$. While this is efficient in the sense that few bits are wasted, identifying individual digits in such a number takes some decoding. For this reason, BCD arithmetic needs hardware support from the processor, which is rarely found these days; one example is the IBM Power architecture, starting with the *IBM Power6*.

3.2.1.2 Other number bases for computer arithmetic

There have been some experiments with *ternary arithmetic* (see http://en.wikipedia.org/wiki/Ternary_computer and <http://www.computer-museum.ru/english/setun.htm>), however, no practical hardware exists.

3.2.2 Limitations

Since we use only a finite number of bits to store floating point numbers, not all numbers can be represented. The ones that can not be represented fall into two categories: those that are too large or too small (in some sense), and those that fall in the gaps. Numbers can be too large or too small in the following ways.

Overflow The largest number we can store is

$$(\beta - 1) \cdot 1 + (\beta - 1) \cdot \beta^{-1} + \cdots + (\beta - 1) \cdot \beta^{-(t-1)} = \beta - 1 \cdot \beta^{-(t-1)},$$

and the smallest number (in an absolute sense) is $-(\beta - \beta^{-(t-1)})$; anything larger than the former or smaller than the latter causes a condition called *overflow*.

Underflow The number closest to zero is $\beta^{-(t-1)} \cdot \beta^L$. A computation that has a result less than that (in absolute value) causes a condition called *underflow*. In fact, most computers use *normalized floating point numbers*: the first digit d_1 is taken to be nonzero; see section 3.2.5 for more about this. In this case, any number less than $1 \cdot \beta^L$ causes underflow. Trying to compute a number less than that in absolute value is sometimes handled by using *unnormalized floating point numbers* (a process known as *gradual underflow*), but this is typically tens or hundreds of times slower than computing with regular floating point numbers². At the time of this writing, only the IBM Power6 has hardware support for gradual underflow.

The fact that only a small number of real numbers can be represented exactly is the basis of the field of round-off error analysis. We will study this in some detail in the following sections.

For detailed discussions, see the book by Overton [104]; it is easy to find online copies of the essay by Goldberg [54]. For extensive discussions of round-off error analysis in algorithms, see the books by Higham [70] and Wilkinson [134].

3.2.3 Normalized numbers

The general definition of floating point numbers, equation (3.1), leaves us with the problem that numbers have more than one representation. For instance, $.5 \times 10^2 = .05 \times 10^3$. Since this would make computer arithmetic needlessly complicated, for instance in testing equality of numbers, we use *normalized floating point numbers*. A number is normalized if its first digit is nonzero. This implies that the mantissa part is $\beta > x_m \geq 1$.

A practical implication in the case of binary numbers is that the first digit is always 1, so we do not need to store it explicitly. In the IEEE 754 standard, this means that every floating point number is of the form

$$1.d_1d_2 \dots d_t \times 2^{\text{exp}}.$$

2. In real-time applications such as audio processing this phenomenon is especially noticeable; see <http://phonophunk.com/articles/pentium4-denormalization.php?pg=3>.

3.2.4 Representation error

Let us consider a real number that is not representable in a computer's number system.

An unrepresentable number is approximated either by *rounding* or *truncation*. This means that a machine number \tilde{x} is the representation for all x in an interval around it. With t digits in the mantissa, this is the interval of numbers that differ from \tilde{x} in the $t + 1$ st digit. For the mantissa part we get:

$$\begin{cases} x \in [\tilde{x}, \tilde{x} + \beta^{-t+1}) & \text{truncation} \\ x \in [\tilde{x} - \frac{1}{2}\beta^{-t+1}, \tilde{x} + \frac{1}{2}\beta^{-t+1}) & \text{rounding} \end{cases}$$

If x is a number and \tilde{x} its representation in the computer, we call $x - \tilde{x}$ the *representation error* or *absolute representation error*, and $\frac{x - \tilde{x}}{x}$ the *relative representation error*. Often we are not interested in the sign of the error, so we may apply the terms error and relative error to $|x - \tilde{x}|$ and $|\frac{x - \tilde{x}}{x}|$ respectively.

Often we are only interested in bounds on the error. If ϵ is a bound on the error, we will write

$$\tilde{x} = x \pm \epsilon \stackrel{\text{D}}{\Leftrightarrow} |x - \tilde{x}| \leq \epsilon \Leftrightarrow \tilde{x} \in [x - \epsilon, x + \epsilon]$$

For the relative error we note that

$$\tilde{x} = x(1 + \epsilon) \Leftrightarrow \left| \frac{\tilde{x} - x}{x} \right| \leq \epsilon$$

Let us consider an example in decimal arithmetic, that is, $\beta = 10$, and with a 3-digit mantissa: $t = 3$. The number $x = 1.256$ has a representation that depends on whether we round or truncate: $\tilde{x}_{\text{round}} = 1.26$, $\tilde{x}_{\text{truncate}} = 1.25$. The error is in the 4th digit: if $\epsilon = x - \tilde{x}$ then $|\epsilon| < \beta^{t-1}$.

Exercise 3.3. The number in this example had no exponent part. What are the error and relative error if there had been one?

3.2.5 Machine precision

Often we are only interested in the order of magnitude of the representation error, and we will write $\tilde{x} = x(1 + \epsilon)$, where $|\epsilon| \leq \beta^{-t}$. This maximum relative error is called the *machine precision*, or sometimes *machine epsilon*. Typical values are:

$$\begin{cases} \epsilon \approx 10^{-7} & \text{32-bit single precision} \\ \epsilon \approx 10^{-16} & \text{64-bit double precision} \end{cases}$$

Machine precision can be defined another way: ϵ is the smallest number that can be added to 1 so that $1 + \epsilon$ has a different representation than 1. A small example shows how aligning exponents can shift a too small operand so that it is effectively ignored in the addition operation:

$$\begin{array}{r} 1.0000 \times 10^0 \\ + 1.0000 \times 10^{-5} \\ \hline \end{array} \Rightarrow \begin{array}{r} 1.0000 \times 10^0 \\ + 0.00001 \times 10^0 \\ = 1.0000 \times 10^0 \end{array}$$

$(e_1 \dots e_8)$	numerical value
$(0 \dots 0) = 0$	$\pm 0.s_1 \dots s_{23} \times 2^{-126}$
$(0 \dots 01) = 1$	$\pm 1.s_1 \dots s_{23} \times 2^{-126}$
$(0 \dots 010) = 2$	$\pm 1.s_1 \dots s_{23} \times 2^{-125}$
...	
$(01111111) = 127$	$\pm 1.s_1 \dots s_{23} \times 2^0$
$(10000000) = 128$	$\pm 1.s_1 \dots s_{23} \times 2^1$
...	
$(11111110) = 254$	$\pm 1.s_1 \dots s_{23} \times 2^{127}$
$(11111111) = 255$	$\pm\infty$ if $s_1 \dots s_{23} = 0$, otherwise NaN

Figure 3.1: Single precision arithmetic

Yet another way of looking at this is to observe that, in the addition $x + y$, if the ratio of x and y is too large, the result will be identical to x .

The machine precision is the maximum attainable accuracy of computations: it does not make sense to ask for more than 6-or-so digits accuracy in single precision, or 15 in double.

Exercise 3.4. Write a small program that computes the machine epsilon. Does it make any difference if you set the *compiler optimization levels* low or high?

Exercise 3.5. The number $e \approx 2.72$, the base for the natural logarithm, has various definitions.

One of them is

$$e = \lim_{n \rightarrow \infty} (1 + 1/n)^n.$$

Write a single precision program that tries to compute e in this manner. Evaluate the expression for $n = 10^k$ with $k = 1, \dots, 10$. Explain the output for large n . Comment on the behaviour of the error.

3.2.6 The IEEE 754 standard for floating point numbers

Some decades ago, issues like the length of the mantissa and the rounding behaviour of operations could differ between computer manufacturers, and even between models from one manufacturer. This was obviously a bad situation from a point of portability of codes and reproducibility of results. The IEEE standard 754³⁴ codified all this, for instance stipulating 24 and 53 bits for the mantissa in single and double precision arithmetic, using a storage sequence of sign bit, exponent, mantissa.

3. IEEE 754 is a standard for binary arithmetic; there is a further standard, IEEE 854, that allows decimal arithmetic.

4. “It was remarkable that so many hardware people there, knowing how difficult p754 would be, agreed that it should benefit the community at large. If it encouraged the production of floating-point software and eased the development of reliable software, it would help create a larger market for everyone’s hardware. This degree of altruism was so astonishing that MATLAB’s creator Dr. Cleve Moler used to advise foreign visitors not to miss the country’s two most awesome spectacles: the Grand Canyon, and meetings of IEEE p754.” W. Kahan, <http://www.cs.berkeley.edu/~wkahan/ieee754status/754story.html>.

The standard also declared the rounding behaviour to be *correct rounding*: the result of an operation should be the rounded version of the exact result. There will be much more on the influence of rounding (and truncation) on numerical computations, below.

Above (section 3.2.2), we have seen the phenomena of overflow and underflow, that is, operations leading to unrepresentable numbers. There is a further exceptional situation that needs to be dealt with: what result should be returned if the program asks for illegal operations such as $\sqrt{-4}$? The IEEE 754 standard has two special quantities for this: `Inf` and `NaN` for ‘infinity’ and ‘not a number’. Infinity is the result of overflow or dividing by zero, not-a-number is the result of, for instance, subtracting infinity from infinity. If `NaN` appears in an expression, the whole expression will evaluate to that value. The rule for computing with `Inf` is a bit more complicated [54].

An inventory of the meaning of all bit patterns in IEEE 754 double precision is given in figure 3.1. Note that for normalized numbers the first nonzero digit is a 1, which is not stored, so the bit pattern $d_1d_2\dots d_t$ is interpreted as $1.d_1d_2\dots d_t$.

Exercise 3.6. Every programmer, at some point in their life, makes the mistake of storing a real number in an integer or the other way around. This can happen for instance if you call a function differently from how it was defined.

```
void a(float x) { . . . }
int main() {
    int i;
    . . . a(i) . . .
}
```

What happens when you print `x` in the function? Consider the bit pattern for a small integer, and use the table in figure 3.1 to interpret it as a floating point number. Explain that it will be an unnormalized number⁵.

These days, almost all processors adhere to the IEEE 754 standard, with only occasional exceptions. For instance, Nvidia Tesla *GPUs* are not standard-conforming in single precision; see http://en.wikipedia.org/wiki/Nvidia_Tesla. The justification for this is that single precision is more likely used for graphics, where exact compliance matters less. For many scientific computations, double precision is necessary, since the precision of calculations gets worse with increasing problem size or runtime. This is true for the sort of calculations in chapter 4, but not for others such as Lattice-Boltzmann.

3.3 Round-off error analysis

Numbers that are too large or too small to be represented, leading to overflow and underflow, are uncommon; usually computations can be arranged so that this situation will not occur. By contrast, the case that the result of a computation between computer numbers (even something as simple as a single addition) is not representable is very common. Thus, looking at the implementation of an algorithm, we need to analyze the effect of such small errors propagating through the computation. This is commonly called *round-off error analysis*.

5. This is one of those errors you won’t forget after you make it. In the future, whenever you see a number on the order of 10^{-305} you’ll recognize that you made this error.

3.3.1 Correct rounding

The IEEE 754 standard, mentioned in section 3.2.6, does not only declare the way a floating point number is stored, it also gives a standard for the accuracy of operations such as addition, subtraction, multiplication, division. The model for arithmetic in the standard is that of *correct rounding*: the result of an operation should be as if the following procedure is followed:

- The exact result of the operation is computed, whether this is representable or not;
- This result is then rounded to the nearest computer number.

In short: the representation of the result of an operation is the rounded exact result of that operation. (Of course, after two operations it no longer needs to hold that the computed result is the exact rounded version of the exact result.)

If this statement sounds trivial or self-evident, consider subtraction as an example. In a decimal number system with two digits in the mantissa, the computation $1.0 - 9.4 \cdot 10^{-1} = 1.0 - 0.94 = 0.06 = 0.6 \cdot 10^{-2}$. Note that in an intermediate step the mantissa .094 appears, which has one more digit than the two we declared for our number system. The extra digit is called a *guard digit*.

Without a guard digit, this operation would have proceeded as $1.0 - 9.4 \cdot 10^{-1}$, where $9.4 \cdot 10^{-1}$ would be rounded to 0.9, giving a final result of 0.1, which is almost double the correct result.

Exercise 3.7. Consider the computation $1.0 - 9.5 \cdot 10^{-1}$, and assume again that numbers are rounded to fit the 2-digit mantissa. Why is this computation in a way a lot worse than the example?

One guard digit is not enough to guarantee correct rounding. An analysis that we will not reproduce here shows that three extra bits are needed [53].

3.3.2 Addition

Addition of two floating point numbers is done in a couple of steps. First the exponents are aligned: the smaller of the two numbers is written to have the same exponent as the larger number. Then the mantissas are added. Finally, the result is adjusted so that it again is a normalized number.

As an example, consider $1.00 + 2.00 \times 10^{-2}$. Aligning the exponents, this becomes $1.00 + 0.02 = 1.02$, and this result requires no final adjustment. We note that this computation was exact, but the sum $1.00 + 2.55 \times 10^{-2}$ has the same result, and here the computation is clearly not exact: the exact result is 1.0255, which is not representable with three digits to the mantissa.

In the example $6.15 \times 10^1 + 3.98 \times 10^1 = 10.13 \times 10^1 = 1.013 \times 10^2 \rightarrow 1.01 \times 10^2$ we see that after addition of the mantissas an adjustment of the exponent is needed. The error again comes from truncating or rounding the first digit of the result that does not fit in the mantissa: if x is the true sum and \tilde{x} the computed sum, then $\tilde{x} = x(1 + \epsilon)$ where, with a 3-digit mantissa $|\epsilon| < 10^{-3}$.

Formally, let us consider the computation of $s = x_1 + x_2$, and we assume that the numbers x_i are represented

as $\tilde{x}_i = x_i(1 + \epsilon_i)$. Then the sum s is represented as

$$\begin{aligned}\tilde{s} &= (\tilde{x}_1 + \tilde{x}_2)(1 + \epsilon_3) \\ &= x_1(1 + \epsilon_1)(1 + \epsilon_3) + x_2(1 + \epsilon_2)(1 + \epsilon_3) \\ &\approx x_1(1 + \epsilon_1 + \epsilon_3) + x_2(1 + \epsilon_2 + \epsilon_3) \\ &\approx s(1 + 2\epsilon)\end{aligned}$$

under the assumptions that all ϵ_i are small and of roughly equal size, and that both $x_i > 0$. We see that the relative errors are added under addition.

3.3.3 Multiplication

Floating point multiplication, like addition, involves several steps. In order to multiply two numbers $m_1 \times \beta^{e_1}$ and $m_2 \times \beta^{e_2}$, the following steps are needed.

- The exponents are added: $e \leftarrow e_1 + e_2$.
- The mantissas are multiplied: $m \leftarrow m_1 \times m_2$.
- The mantissa is normalized, and the exponent adjusted accordingly.

For example: $1.23 \cdot 10^0 \times 5.67 \cdot 10^1 = 0.69741 \cdot 10^1 \rightarrow 6.9741 \cdot 10^0 \rightarrow 6.97 \cdot 10^0$.

Exercise 3.8. Analyze the relative error of multiplication.

3.3.4 Subtraction

Subtraction behaves very differently from addition. Whereas in addition errors are added, giving only a gradual increase of overall roundoff error, subtraction has the potential for greatly increased error in a single operation.

For example, consider subtraction with 3 digits to the mantissa: $1.24 - 1.23 = .001 \rightarrow 1.00 \cdot 10^{-2}$. While the result is exact, it has only one significant digit⁶. To see this, consider the case where the first operand 1.24 is actually the rounded result of a computation that should have resulted in 1.235. In that case, the result of the subtraction should have been $5.00 \cdot 10^{-3}$, that is, there is a 100% error, even though the relative error of the inputs was as small as could be expected. Clearly, subsequent operations involving the result of this subtraction will also be inaccurate. We conclude that subtracting almost equal numbers is a likely cause of numerical roundoff.

There are some subtleties about this example. Subtraction of almost equal numbers is exact, and we have the correct rounding behaviour of IEEE arithmetic. Still, the correctness of a single operation does not imply that a sequence of operations containing it will be accurate. While the addition example showed only modest decrease of numerical accuracy, the cancellation in this example can have disastrous effects.

6. Normally, a number with 3 digits to the mantissa suggests an error corresponding to rounding or truncating the fourth digit. We say that such a number has *3 significant digits*. In this case, the last two digits have no meaning, resulting from the normalization process.

3.3.5 Examples

From the above, the reader may get the impression that roundoff errors only lead to serious problems in exceptional circumstances. In this section we will discuss some very practical examples where the inexactness of computer arithmetic becomes visible in the result of a computation. These will be fairly simple examples; more complicated examples exist that are outside the scope of this book, such as the instability of matrix inversion. The interested reader is referred to [134, 70].

3.3.5.1 The ‘abc-formula’

As a practical example, consider the quadratic equation $ax^2 + bx + c = 0$ which has solutions $x = \frac{-b \pm \sqrt{b^2 - 4ac}}{2a}$. Suppose $b > 0$ and $b^2 \gg 4ac$ then $\sqrt{b^2 - 4ac} \approx b$ and the ‘+’ solution will be inaccurate. In this case it is better to compute $x_- = \frac{-b - \sqrt{b^2 - 4ac}}{2a}$ and use $x_+ \cdot x_- = -c/a$.

Exercise 3.9. Program a simulator for decimal d -digit arithmetic and experiment with the accuracy of the two ways of computing the solution of a quadratic equation. Simulating d -digit decimal arithmetic can be done as follows. Let x be a floating point number, then:

- Normalize x by finding an integer e such that $x' := |x| \cdot 10^e \in [.1, 1)$.
- Now truncate this number to d digits by multiplying x' by 10^d , truncating the result to an integer, and multiplying that result again by 10^{-d} .
- Multiply this truncated number by 10^{-e} to revert the normalization.

3.3.5.2 Summing series

The previous example was about preventing a large roundoff error in a single operation. This example shows that even gradual buildup of roundoff error can be handled in different ways.

Consider the sum $\sum_{n=1}^{10000} \frac{1}{n^2} = 1.644834$ and assume we are working with single precision, which on most computers means a machine precision of 10^{-7} . The problem with this example is that both the ratio between terms, and the ratio of terms to partial sums, is ever increasing. In section 3.2.5 we observed that a too large ratio can lead to one operand of an addition in effect being ignored.

If we sum the series in the sequence it is given, we observe that the first term is 1, so all partial sums ($\sum_{n=1}^N$ where $N < 10000$) are at least 1. This means that any term where $1/n^2 < 10^{-7}$ gets ignored since it is less than the machine precision. Specifically, the last 7000 terms are ignored, and the computed sum is 1.644725. The first 4 digits are correct.

However, if we evaluate the sum in reverse order we obtain the exact result in single precision. We are still adding small quantities to larger ones, but now the ratio will never be as bad as one-to- ϵ , so the smaller number is never ignored. To see this, consider the ratio of two terms subsequent terms:

$$\frac{n^2}{(n-1)^2} = \frac{n^2}{n^2 - 2n + 1} = \frac{1}{1 - 2/n + 1/n^2} \approx 1 + \frac{2}{n}$$

Since we only sum 10^5 terms and the machine precision is 10^{-7} , in the addition $1/n^2 + 1/(n-1)^2$ the second term will not be wholly ignored as it is when we sum from large to small.

Exercise 3.10. There is still a step missing in our reasoning. We have shown that in adding two subsequent terms, the smaller one is not ignored. However, during the calculation we add partial sums to the next term in the sequence. Show that this does not worsen the situation.

The lesson here is that series that are monotone (or close to monotone) should be summed from small to large, since the error is minimized if the quantities to be added are closer in magnitude. Note that this is the opposite strategy from the case of subtraction, where operations involving similar quantities lead to larger errors. This implies that if an application asks for adding and subtracting series of numbers, and we know a priori which terms are positive and negative, it may pay off to rearrange the algorithm accordingly.

3.3.5.3 Unstable algorithms

We will now consider an example where we can give a direct argument that the algorithm can not cope with problems due to inexactly represented real numbers.

Consider the recurrence $y_n = \int_0^1 \frac{x^n}{x-5} dx = \frac{1}{n} - 5y_{n-1}$. This is easily seen to be monotonically decreasing; the first term can be computed as $y_0 = \ln 6 - \ln 5$.

Performing the computation in 3 decimal digits we get:

computation	correct result
$y_0 = \ln 6 - \ln 5 = .182 322 \times 10^1 \dots$	1.82
$y_1 = .900 \times 10^{-1}$.884
$y_2 = .500 \times 10^{-1}$.0580
$y_3 = .830 \times 10^{-1}$	going up? .0431
$y_4 = -.165$	negative? .0343

We see that the computed results are quickly not just inaccurate, but actually nonsensical. We can analyze why this is the case.

If we define the error ϵ_n in the n -th step as

$$\tilde{y}_n - y_n = \epsilon_n,$$

then

$$\tilde{y}_n = 1/n - 5\tilde{y}_{n-1} = 1/n + 5n_{n-1} + 5\epsilon_{n-1} = y_n + 5\epsilon_{n-1}$$

so $\epsilon_n \geq 5\epsilon_{n-1}$. The error made by this computation shows exponential growth.

3.3.5.4 Linear system solving

Sometimes we can make statements about the numerical precision of a problem even without specifying what algorithm we use. Suppose we want to solve a linear system, that is, we have an $n \times n$ matrix A and a vector b of size n , and we want to compute the vector x such that $Ax = b$. (We will actually consider algorithms for this in chapter 5.) Since the vector b will be the result of some computation or measurement, we are actually dealing with a vector \tilde{b} , which is some perturbation of the ideal b :

$$\tilde{b} = b + \Delta b.$$

The perturbation vector Δb can be of the order of the machine precision if it only arises from representation error, or it can be larger, depending on the calculations that produced \tilde{b} .

We now ask what the relation is between the exact value of x , which we would have obtained from doing an exact calculation with A and b , which is clearly impossible, and the computed value \tilde{x} , which we get from computing with A and \tilde{b} . (In this discussion we will assume that A itself is exact, but this is a simplification.)

Writing $\tilde{x} = x + \Delta x$, the result of our computation is now

$$A\tilde{x} = \tilde{b}$$

or

$$A(x + \Delta x) = b + \Delta b.$$

Since $Ax = b$, we get $A\Delta x = \Delta b$. From this, we get (see appendix A.1 for details)

$$\left\{ \begin{array}{l} \Delta x = A^{-1}\Delta b \\ Ax = b \end{array} \right\} \Rightarrow \left\{ \begin{array}{l} \|A\| \|x\| \geq \|b\| \\ \|\Delta x\| \leq \|A^{-1}\| \|\Delta b\| \end{array} \right\} \Rightarrow \frac{\|\Delta x\|}{\|x\|} \leq \|A\| \|A^{-1}\| \frac{\|\Delta b\|}{\|b\|} \quad (3.2)$$

The quantity $\|A\| \|A^{-1}\|$ is called the *condition number* of a matrix. The bound (3.2) then says that any perturbation in the right hand side can lead to a perturbation in the solution that is at most larger by the condition number of the matrix A . Note that it does not say that the perturbation in x *needs* to be anywhere close to that size, but we can not rule it out, and in some cases it indeed happens that this bound is attained.

Suppose that b is exact up to machine precision, and the condition number of A is 10^4 . The bound (3.2) is often interpreted as saying that the last 4 digits of x are unreliable, or that the computation ‘loses 4 digits of accuracy’.

Equation (3.2) can also be interpreted as follows: when we solve a linear system $Ax = b$ we get an approximate solution $x + \Delta x$ which is the exact solution of a perturbed system $A(x + \Delta x) = b + \Delta b$. The fact that the perturbation in the solution can be related to the perturbation in the system, is expressed by saying that the algorithm exhibits *backwards stability*.

The analysis of the accuracy of linear algebra algorithms is a field of study in itself; see for instance the book by Higham [70].

3.3.6 Roundoff error in parallel computations

From the above example of summing a series we saw that addition in computer arithmetic is not associative. A similar fact holds for multiplication. This has an interesting consequence for parallel computations: the way a computation is spread over parallel processors influences the result. For instance, consider computing the sum of a large number N of terms. With P processors at our disposition, we can let each compute N/P terms, and combine the partial results. We immediately see that for no two values of P will the results be identical. This means that reproducibility of results in a parallel context is elusive.

3.4 More about floating point arithmetic

3.4.1 Programming languages

Different languages have different approaches to declaring integers and floating point numbers.

Fortran In Fortran there are various ways of specifying the storage format for integer and real variables. For instance, it is possible to declare the number of bytes that it takes to store a variable: INTEGER*2, REAL*8. One advantage of this approach is the easy interoperability with other languages, or the MPI library.

Often it is possible to write a code using only INTEGER, REAL, and use *compiler flags* to indicate the size of an integer and real number in bytes.

More sophisticated, modern versions of Fortran can indicate the number of digits of precision a floating point number needs to have:

```
integer, parameter :: k9 = selected_real_kind(9)
real(kind=k9) :: r
r = 2._k9; print *, sqrt(r) ! prints 1.4142135623730
```

The ‘kind’ values will usually be 4,8,16 but this is compiler dependent.

C In C, the type identifiers have no standard length. For integers there is short int, int, long int, and for floating point float, double. The sizeof() operator gives the number of bytes used to store a datatype.

C99, Fortran2003 Recent standards of the C and Fortran languages incorporate the C/Fortran interoperability standard, which can be used to declare a type in one language so that it is compatible with a certain type in the other language.

3.4.2 Other computer arithmetic systems

Other systems have been proposed to dealing with the problems of inexact arithmetic on computers. One solution is extended precision arithmetic, where numbers are stored in more bits than usual. A common use of this is in the calculation of inner products of vectors: the accumulation is internally performed in extended precision, but returned as a regular floating point number. Alternatively, there are libraries such as GMPlib [51] that allow for any calculation to be performed in higher precision.

Another solution to the imprecisions of computer arithmetic is ‘interval arithmetic’ [74], where for each calculation interval bounds are maintained. While this has been researched for considerable time, it is not practically used other than through specialized libraries [12].

3.4.3 Fixed-point arithmetic

A fixed-point number (for a more thorough discussion than found here, see [136]) can be represented as $\langle N, F \rangle$ where $N \geq \beta^0$ is the integer part and $F < 1$ is the fractional part. Another way of looking at this, is that a fixed-point number is an integer stored in $N + F$ digits, with an implied decimal point after the first N digits.

Fixed-point calculations can overflow, with no possibility to adjust an exponent. Consider the multiplication $\langle N_1, F_1 \rangle \times \langle N_2, F_2 \rangle$, where $N_1 \geq \beta^{n_1}$ and $N_2 \geq \beta^{n_2}$. This overflows if $n_1 + n_2$ is more than the number

of positions available for the integer part. (Informally, the number of digits of the product is the sum of the digits of the operands.) This means that, in a program that uses fixed-point, numbers will need to have a number of zero digits, if you are ever going to multiply them, which lowers the numerical accuracy. It also means that the programmer has to think harder about calculations, arranging them in such a way that overflow will not occur, and that numerical accuracy is still preserved to a reasonable extent.

So why would people use fixed-point numbers? One important application is in embedded low-power devices, think a battery-powered digital thermometer. Since fixed-point calculations are essentially identical to integer calculations, they do not require a floating-point unit, thereby lowering chip size and lessening power demands. Also, many early video game systems had a processor that either had no floating-point unit, or where the integer unit was considerably faster than the floating-point unit. In both cases, implementing non-integer calculations as fixed-point, using the integer unit, was the key to high throughput.

Another area where fixed point arithmetic is still used is in signal processing. In modern CPUs, integer and floating point operations are of essentially the same speed, but converting between them is relatively slow. Now, if the sine function is implemented through table lookup, this means that in $\sin(\sin x)$ the output of a function is used to index the next function application. Obviously, outputting the sine function in fixed point obviates the need for conversion between real and integer quantities, which simplifies the chip logic needed, and speeds up calculations.

3.4.4 Complex numbers

Some programming languages have complex numbers as a native data type, others not, and others are in between. For instance, in Fortran you can declare

```
COMPLEX z1, z2, z (32)
COMPLEX*16 zz1, zz2, zz (36)
```

A complex number is a pair of real numbers, the real and imaginary part, allocated adjacent in memory. The first declaration then uses 8 bytes to store to `REAL*4` numbers, the second one has `REAL*8`s for the real and imaginary part. (Alternatively, use `DOUBLE COMPLEX` or in Fortran90 `COMPLEX(KIND=2)` for the second line.)

By contrast, the C language does not natively have complex numbers, but both C99 and C++ have a `complex.h` header file⁷. This defines a complex number as in Fortran, as two real numbers.

Storing a complex number like this is easy, but sometimes it is computationally not the best solution. This becomes apparent when we look at arrays of complex numbers. If a computation often relies on access to the real (or imaginary) parts of complex numbers exclusively, striding through an array of complex numbers, has a stride two, which is disadvantageous (see section 1.3.4.5). In this case, it is better to allocate one array for the real parts, and another for the imaginary parts.

Exercise 3.11. Suppose arrays of complex numbers are stored the Fortran way. Analyze the memory access pattern of pairwise multiplying the arrays, that is, $\forall_i: c_i \leftarrow a_i \cdot b_i$, where `a()`, `b()`, `c()` are arrays of complex numbers.

7. These two header files are not identical, and in fact not compatible. Beware, if you compile C code with a C++ compiler [34].

Exercise 3.12. Show that an $n \times n$ linear system $Ax = b$ over the complex numbers can be written as a $2n \times 2n$ system over the real numbers. Hint: split the matrix and the vectors in their real and imaginary parts. Argue for the efficiency of storing arrays of complex numbers as separate arrays for the real and imaginary parts.

3.5 Conclusions

Computations done on a computer are invariably beset with numerical error. In a way, the reason for the error is the imperfection of computer arithmetic: if we could calculate with actual real numbers there would be no problem. (There would still be the matter of measurement error in data, and approximations made in numerical methods; see the next chapter.) However, if we accept roundoff as a fact of life, then various observations hold:

- Mathematically equivalent operations need not behave identically from a point of stability; see the ‘abc-formula’ example.
- Even rearrangements of the same computations do not behave identically; see the summing example.

Thus it becomes imperative to analyze computer algorithms with regard to their roundoff behaviour: does roundoff increase as a slowly growing function of problem parameters, such as the number of terms evaluated, or is worse behaviour possible? We will not address such questions in further detail in this book.

Chapter 4

Numerical treatment of differential equations

In this chapter we will look at the numerical solution of Ordinary Differential Equations (ODEs) and Partial Differential Equations (PDEs). These equations are commonly used in physics to describe phenomena such as the flow of air around an aircraft, or the bending of a bridge under various stresses. While these equations are often fairly simple, getting specific numbers out of them ('how much does this bridge sag if there are a hundred cars on it') is more complicated, often taking large computers to produce the desired results. Here we will describe the techniques that turn ODEs and PDEs into computable problems.

First of all, we will look at Initial Value Problems (IVPs), which describes processes that develop in time. Here we only consider ODEs: scalar functions that are only depend on time. The name derives from the fact that typically the function is specified at an initial time point.

Next, we will look at Boundary Value Problems (BVPs), describing processes in space. In realistic situations, this will concern multiple space variables, so we have a PDE. The name BVP is explained by the fact that the solution is specified on the boundary of the domain of definition.

Finally, we will consider the 'heat equation', an Initial Boundary Value Problem (IBVP) which has aspects of both IVPs and BVPs: it describes heat spreading through a physical object such as a rod. The initial value describes the initial temperature, and the boundary values give prescribed temperatures at the ends of the rod.

Our aim in this chapter is to show the origins of an important class of computational problems. Therefore we will not go into theoretical matters of existence, uniqueness, or conditioning of solutions. For this, see [66] or any book that is specifically dedicated to ODEs or PDEs. For ease of analysis we will also assume that all functions involved have sufficiently many higher derivatives, and that each derivative is sufficiently smooth.

4.1 Initial value problems

Many physical phenomena change over time, and typically the laws of physics give a description of the change, rather than of the quantity of interest itself. For instance, Newton's second law

$$F = ma$$

is a statement about the change in position of a point mass: expressed as

$$a = \frac{d^2}{dt^2}x = F/m$$

it states that acceleration depends linearly on the force exerted on the mass. A closed form description $x(t) = \dots$ for the location of the mass can sometimes be derived analytically, but in many cases some form of approximation or numerical computation is needed.

Newton's equation is an ODE since it describes a function of one variable, time. It is an IVP since it describes the development in time, starting with some initial conditions. As an ODE, it is 'of second order' since it involves a second derivative. We can reduce this to first order, involving only first derivatives, if we allow vector quantities. Defining $u(t) = (x(t), x'(t))^{t\text{1}}$, we find for u :

$$u' = Au + B, \quad A = \begin{pmatrix} 0 & 1 \\ 0 & 0 \end{pmatrix}, \quad B = \begin{pmatrix} 0 \\ F/a \end{pmatrix}$$

For simplicity, in this course we will only consider scalar equations; our reference equation is then

$$u'(t) = f(t, u(t)), \quad u(0) = u_0, \quad t > 0, \tag{4.1}$$

and in this section we will consider numerical methods for its solution.

Typically, the initial value in some starting point (often chosen as $t = 0$) is given: $u(0) = u_0$ for some value u_0 , and we are interested in the behaviour of u as $t \rightarrow \infty$. As an example, $f(x) = x$ gives the equation $u'(t) = u(t)$. This is a simple model for population growth: the equation states that the rate of growth is equal to the size of the population. The equation (4.1) can be solved analytically for some choices of f , but we will not consider this. Instead, we only consider the numerical solution and the accuracy of this process.

In a numerical method, we consider discrete size time steps to approximate the solution of the continuous time-dependent process. Since this introduces a certain amount of error, we will analyze the error introduced in each time step, and how this adds up to a global error. In some cases, the need to limit the global error will impose restrictions on the numerical scheme.

4.1.1 Error and stability

Since numerical computation will always involve the inaccuracies stemming from the use of machine arithmetic, we want to avoid the situation where a small perturbation in the initial value leads to large perturbations in the solution. Therefore, we will call a differential equation 'stable' if solutions corresponding to different initial values u_0 converge to one another as $t \rightarrow \infty$.

Let us limit ourselves to the so-called 'autonomous' ODE

$$u'(t) = f(u(t)) \tag{4.2}$$

1. We use the prime symbol to indicate differentiation in case of functions of a single variable.

in which the right hand side does not explicitly depend on t^2 . A sufficient criterium for stability is:

$$\frac{\partial}{\partial u} f(u) = \begin{cases} > 0 & \text{unstable} \\ = 0 & \text{neutrally stable} \\ < 0 & \text{stable} \end{cases}$$

Proof. If u^* is a zero of f , meaning $f(u^*) = 0$, then the constant function $u(t) \equiv u^*$ is a solution of $u' = f(u)$, a so-called ‘equilibrium’ solution. We will now consider how small perturbations from the equilibrium behave. Let u be a solution of the PDE, and write $u(t) = u^* + \eta(t)$, then we have

$$\begin{aligned} \eta' &= u' = f(u) = f(u^* + \eta) = f(u^*) + \eta f'(u^*) + O(\eta^2) \\ &= \eta f'(u^*) + O(\eta^2) \end{aligned}$$

Ignoring the second order terms, this has the solution

$$\eta(t) = e^{f'(x^*)t}$$

which means that the perturbation will damp out if $f'(x^*) < 0$.

We will often refer to the simple example $f(u) = -\lambda u$, with solution $u(t) = u_0 e^{-\lambda t}$. This problem is stable if $\lambda > 0$.

4.1.2 Finite difference approximation: Euler explicit method

In order to solve the problem numerically, we turn the continuous problem into a discrete one by looking at finite time/space steps. Assuming all functions are sufficiently smooth, a straightforward Taylor expansion³ gives:

$$u(t + \Delta t) = u(t) + u'(t)\Delta t + u''(t)\frac{\Delta t^2}{2!} + u'''(t)\frac{\Delta t^3}{3!} + \dots$$

This gives for u' :

$$\begin{aligned} u'(t) &= \frac{u(t+\Delta t) - u(t)}{\Delta t} + \frac{1}{\Delta t} \left(u''(t)\frac{\Delta t^2}{2!} + u'''(t)\frac{\Delta t^3}{3!} + \dots \right) \\ &= \frac{u(t+\Delta t) - u(t)}{\Delta t} + \frac{1}{\Delta t} O(\Delta t^2) \\ &= \frac{u(t+\Delta t) - u(t)}{\Delta t} + O(\Delta t) \end{aligned} \tag{4.3}$$

We can approximate the infinite sum of higher derivatives by a single $O(\Delta t^2)$ if all derivates are bounded; alternatively, appendix A.4 shows that this sum is equal to $\Delta t^2 u''(t + \alpha \Delta t)$ with $0 < \alpha < 1$.

We see that we can approximate a differential operator by a *finite difference*, with an error that is known in its order of magnitude as a function of the time step.

2. Non-autonomous ODEs can be transformed to autonomous ones, so this is no limitation. If $u = u(t)$ is a scalar function and $f = f(t, u)$, we define $u_2(t) = t$ and consider the equivalent autonomous system $\begin{pmatrix} u' \\ u'_2 \end{pmatrix} = \begin{pmatrix} f(u_2, u) \\ 1 \end{pmatrix}$

3. See appendix A.4 if you are unfamiliar with this.

Substituting this in $u' = f(t, u)$ gives⁴

$$\frac{u(t + \Delta t) - u(t)}{\Delta t} = f(t, u(t)) + O(\Delta t)$$

or

$$u(t + \Delta t) = u(t) + \Delta t f(t, u(t)) + O(\Delta t^2)$$

We use this equation to derive a numerical scheme: with $t_0 = 0, t_{k+1} = t_k + \Delta t = \dots = (k+1)\Delta t$, we get a difference equation

$$u_{k+1} = u_k + \Delta t f(t_k, u_k)$$

for u_k quantities, and we hope that u_k will be a good approximation to $u(t_k)$. This is known as the ‘Explicit Euler’ or ‘Euler forward’ method.

The process of going from a differential equation to a difference equation is often referred to as *discretization*, since we compute function values only in a discrete set of points. The values computed themselves are still real valued. Another way of phrasing this: the numerical solution is found in the finite dimensional space \mathbb{R}^k if we compute k time steps. The solution to the original problem is found in the space of functions $\mathbb{R} \rightarrow \mathbb{R}$.

In (4.3) we approximated one operator by another, and in doing so made a *truncation error* of order $O(\Delta t)$ as $\Delta t \downarrow 0$ (see appendix A.2 for a more formal introduction to this notation for orders of magnitude.). This does *not* immediately imply that the difference equation computes a solution that is close to the true solution. For that some more analysis is needed.

We start by analyzing the ‘local error’: if we assume the computed solution is exact at step k , that is, $u_k = u(t_k)$, how wrong will we be at step $k+1$? We have

$$\begin{aligned} u(t_{k+1}) &= u(t_k) + u'(t_k)\Delta t + u''(t_k)\frac{\Delta t^2}{2!} + \dots \\ &= u(t_k) + f(t_k, u(t_k))\Delta t + u''(t_k)\frac{\Delta t^2}{2!} + \dots \end{aligned}$$

and

$$u_{k+1} = u_k + f(t_k, u_k)\Delta t$$

So

$$\begin{aligned} L_{k+1} &= u_{k+1} - u(t_{k+1}) = u_k - u(t_k) + f(t_k, u_k) - f(t_k, u(t_k)) - u''(t_k)\frac{\Delta t^2}{2!} + \dots \\ &= -u''(t_k)\frac{\Delta t^2}{2!} + \dots \end{aligned}$$

This shows that in each step we make an error of $O(\Delta t^2)$. If we assume that these errors can be added, we find a global error of

$$E_k \approx \sum_k L_k = k\Delta t \frac{\Delta t^2}{2!} = O(\Delta t^3)$$

Since the global error is of first order in Δt , we call this a ‘first order method’. Note that this error, which measures the distance between the true and computed solutions, is of the same order $O(\Delta t)$ as the truncation error, which is the error in approximating the operator.

4. The following equation is a mathematical equality, and should not be interpreted as a way of computing u' for a given function u . Recalling the discussion in section 3.3.4 you can see that this formula would quickly lead to cancellation for small Δt . For a discussion of numerical differentiation, see a numerical analysis textbook.

4.1.2.1 Stability of the Euler explicit method

Consider the IVP $u' = f(t, u)$ for $t \geq 0$, where $f(t, u) = -\lambda u$ and an initial value $u(0) = u_0$ is given. This has an exact solution of $u(t) = u_0 e^{-\lambda t}$. From the above discussion, we conclude that this problem is stable, meaning that small perturbations in the solution ultimately damp out, if $\lambda > 0$. We will now investigate the question of whether the numerical solution behaves the same way as the exact solution, that is, whether numerical solutions also converge to zero.

The Euler forward, or explicit Euler, scheme for this problem is

$$u_{k+1} = u_k - \Delta t \lambda u_k = (1 - \lambda \Delta t) u_k \Rightarrow u_k = (1 - \lambda \Delta t)^k u_0.$$

For stability, we require that $u_k \rightarrow 0$ as $k \rightarrow \infty$. This is equivalent to

$$\begin{aligned} u_k \downarrow 0 &\Leftrightarrow |1 - \lambda \Delta t| < 1 \\ &\Leftrightarrow -1 < 1 - \lambda \Delta t < 1 \\ &\Leftrightarrow -2 < -\lambda \Delta t < 0 \\ &\Leftrightarrow 0 < \lambda \Delta t < 2 \\ &\Leftrightarrow \Delta t < 2/\lambda \end{aligned}$$

We see that the stability of the numerical solution scheme depends on the value of Δt : the scheme is only stable if Δt is small enough. For this reason, we call the explicit Euler method *conditionally stable*. Note that the stability of the differential equation and the stability of the numerical scheme are two different questions. The continuous problem is stable if $\lambda > 0$; the numerical problem has an additional condition that depends on the discretization scheme used.

Note that the stability analysis we just performed was specific to the differential equation $u' = -\lambda u$. If you are dealing with a different IVP you have to perform a separate analysis. However, you will find that explicit methods typically give conditional stability.

4.1.2.2 The Euler implicit method

The explicit method you just saw was easy to compute, but the conditional stability is a potential problem. For instance, it could imply that the number of time steps would be a limiting factor. There is an alternative to the explicit method that does not suffer from the same objection.

Instead of expanding $u(t + \Delta t)$, consider the following expansion of $u(t - \Delta t)$:

$$u(t - \Delta t) = u(t) - u'(t)\Delta t + u''(t)\frac{\Delta t^2}{2!} + \dots$$

which implies

$$u'(t) = \frac{u(t) - u(t - \Delta t)}{\Delta t} + u''(t)\Delta t/2 + \dots$$

As before, we take the equation $u'(t) = f(t, u(t))$ and approximate $u'(t)$ by a difference formula:

$$\frac{u(t) - u(t - \Delta t)}{\Delta t} = f(t, u(t)) + O(\Delta t) \Rightarrow u(t) = u(t - \Delta t) + \Delta t f(t, u(t)) + O(\Delta t^2)$$

Again we define fixed points $t_k = kt$, and we define a numerical scheme:

$$u_{k+1} = u_k + \Delta t f(t_{k+1}, u_{k+1})$$

where u_k is an approximation of $u(t_k)$.

An important difference with the explicit scheme is that u_{k+1} now also appears on the right hand side of the equation. That is, computation of u_{k+1} is now implicit. For example, let $f(t, u) = -u^3$, then $u_{k+1} = u_k - \Delta t u_{k+1}^3$. In other words, u_{k+1} is the solution for x of the equation $\Delta t x^3 + x = u_k$. This is a nonlinear equation, which typically can be solved using the Newton method.

4.1.2.3 Stability of the implicit Euler method

Let us take another look at the example $f(t, u) = -\lambda u$. Formulating the implicit method gives

$$u_{k+1} = u_k - \lambda \Delta t u_{k+1} \Leftrightarrow (1 + \lambda \Delta t) u_{k+1} = u_k$$

so

$$u_{k+1} = \left(\frac{1}{1 + \lambda \Delta t} \right) u_k \Rightarrow u_k = \left(\frac{1}{1 + \lambda \Delta t} \right)^k u_0.$$

If $\lambda > 0$, which is the condition for a stable equation, we find that $u_k \rightarrow 0$ for all values of λ and Δt . This method is called *unconditionally stable*. One advantage of an implicit method over an explicit one is clearly the stability: it is possible to take larger time steps without worrying about unphysical behaviour. Of course, large time steps can make convergence to the *steady state* (see Appendix A.3.4) slower, but at least there will be no divergence.

On the other hand, implicit methods are more complicated. As you saw above, they can involve nonlinear systems to be solved in every time step. In cases where u is vector-valued, such as in the heat equation, discussed below, you will see that the implicit method requires the solution of a system of equations.

Exercise 4.1. Analyse the accuracy and computational aspects of the following scheme for the

IVP $u'(x) = f(x)$:

$$u_{i+1} = u_i + h(f(x_i) + f(x_{i+1}))/2$$

which corresponds to adding the Euler explicit and implicit schemes together. You do not have to analyze the stability of this scheme.

Exercise 4.2. Consider the initial value problem $y'(t) = y(t)(1 - y(t))$. Observe that $y \equiv 0$ and $y \equiv 1$ are solutions. These are called ‘equilibrium solutions’.

1. A solution is stable, if perturbations ‘converge back to the solution’, meaning that for ϵ small enough,

if $y(t) = \epsilon$ for some t , then $\lim_{t \rightarrow \infty} y(t) = 0$

and

if $y(t) = 1 + \epsilon$ for some t , then $\lim_{t \rightarrow \infty} y(t) = 1$

This requires for instance that

$$y(t) = \epsilon \Rightarrow y'(t) < 0.$$

Investigate this behaviour. Is zero a stable solution? Is one?

2. Consider the explicit method

$$y_{k+1} = y_k + \Delta t y_k (1 - y_k)$$

for computing a numerical solution to the differential equation. Show that

$$y_k \in (0, 1) \Rightarrow y_{k+1} > y_k, \quad y_k > 1 \Rightarrow y_{k+1} < y_k$$

3. Write a small program to investigate the behaviour of the numerical solution under various choices for Δt . Include program listing and a couple of runs in your homework submission.
4. You see from running your program that the numerical solution can oscillate. Derive a condition on Δt that makes the numerical solution monotone. It is enough to show that $y_k < 1 \Rightarrow y_{k+1} < 1$, and $y_k > 1 \Rightarrow y_{k+1} > 1$.
5. Now consider the implicit method

$$y_{k+1} - \Delta t y_{k+1} (1 - y_{k+1}) = y_k$$

and show that y_{k+1} is easily computed from y_k . Write a program, and investigate the behaviour of the numerical solution under various choices for Δt .

6. Show that the numerical solution of the implicit scheme is monotone for all choices of Δt .

4.2 Boundary value problems

In the previous section you saw initial value problems, which model phenomena that evolve over time. We will now move on to ‘boundary value problems’, which are in general stationary in time, but which describe a phenomenon that is location dependent. Examples would be the shape of a bridge under a load, or the heat distribution in a window pane, as the temperature outside differs from the one inside.

The general form of a (second order, one-dimensional) BVP is⁵

$$u''(x) = f(x, u, u') \text{ for } x \in [a, b] \text{ where } u(a) = u_a, u(b) = u_b$$

but here we will only consider the simple form

$$-u''(x) = f(x) \text{ for } x \in [0, 1] \text{ with } u(0) = u_0, u(1) = u_1. \quad (4.4)$$

in one space dimension, or

$$-u_{xx}(\bar{x}) - u_{yy}(\bar{x}) = f(\bar{x}) \text{ for } \bar{x} \in \Omega = [0, 1]^2 \text{ with } u(\bar{x}) = u_0 \text{ on } \delta\Omega. \quad (4.5)$$

in two space dimensions. Here, $\delta\Omega$ is the boundary of the domain Ω . Since we prescribe the value of u on the boundary, such a problem is called a Boundary Value Problem (BVP).

5. Actually, the boundary conditions are can be more general, involving derivatives on the interval end points. Here we only look at *Dirichlet boundary conditions* which prescribe function values on the boundary of the domain.

4.2.1 General PDE theory

There are several types of PDE, each with distinct mathematical properties. The most important property is that of *region of influence*: if we tinker with the problem so that the solution changes in one point, what other points will be affected.

- *Hyperbolic PDEs* are of the form

$$Au_{xx} + Bu_{yy} + \text{lower order terms} = 0$$

with A, B of opposite sign. Such equations describe waves, or more general convective phenomena, that are conservative, and do not tend to a steady state.

Intuitively, changing the solution of a wave equation at any point will only change certain future points, since waves have a propagation speed that makes it impossible for a point to influence points in the near future that are too far away in space. This type of PDE will not be discussed in this book.

- *Parabolic PDEs* are of the form

$$Au_x + Bu_{yy} + \text{no higher order terms in } x = 0$$

and they describe diffusion-like phenomena; these often tend to a *steady state*. The best way to characterize them is to consider that the solution in each point in space and time is influenced by a certain finite region at each previous point in space⁶. The *heat equation* (section 4.3) is the standard example of this type.

- *Elliptic PDEs* have the form

$$Au_{xx} + Bu_{yy} + \text{lower order terms} = 0$$

where $A, B > 0$; they typically describe processes that have reached a *steady state*, for instance as $t \rightarrow \infty$ in a parabolic problem. They are characterized by the fact that all points influence each other. These equations often describe phenomena in structural mechanics, such as a beam or a membrane. It is intuitively clear that pressing down on any point of a membrane will change the elevation of every other point, no matter how little. The *Poisson equation* (section 4.2.2) is the standard example of this type.

4.2.2 The Poisson equation

We call the operator Δ , defined by

$$\Delta u = u_{xx} + u_{yy},$$

a second order *differential operator*, and equation (4.5) a second-order PDE. Specifically, the problem

$$-\Delta u = -u_{xx}(\bar{x}) - u_{yy}(\bar{x}) = f(\bar{x}) \text{ for } \bar{x} \in \Omega = [0, 1]^2 \text{ with } u(\bar{x}) = u_0 \text{ on } \delta\Omega. \quad (4.6)$$

is called the *Poisson equation*, in this case defined on the unit square. Second order PDEs are quite common, describing many phenomena in fluid and heat flow and structural mechanics.

6. This leads to a condition limiting the time step in *IBVP*, known as the *Courant-Friedrichs-Lowy condition* http://en.wikipedia.org/wiki/CourantFriedrichsLowy_condition. It describes the notion that in the exact problem $u(x, t)$ depends on a range of $u(x', t - \Delta t)$ values; the time step of the numerical method has to be small enough that the numerical solution takes all these points into account.

4.2.2.1 One-dimensional case

At first, for simplicity, we consider the one-dimensional Poisson equation

$$-u_{xx} = f(x).$$

In order to find a numerical scheme we use Taylor series as before, expressing $u(x+h)$ and $u(x-h)$ in terms of u and its derivatives at x . Let $h > 0$, then

$$u(x+h) = u(x) + u'(x)h + u''(x)\frac{h^2}{2!} + u'''(x)\frac{h^3}{3!} + u^{(4)}(x)\frac{h^4}{4!} + u^{(5)}(x)\frac{h^5}{5!} + \dots$$

and

$$u(x-h) = u(x) - u'(x)h + u''(x)\frac{h^2}{2!} - u'''(x)\frac{h^3}{3!} + u^{(4)}(x)\frac{h^4}{4!} - u^{(5)}(x)\frac{h^5}{5!} + \dots$$

Our aim is now to approximate $u''(x)$. We see that the u' terms in these equations would cancel out under addition, leaving $2u(x)$:

$$u(x+h) + u(x-h) = 2u(x) + u''(x)h^2 + u^{(4)}(x)\frac{h^4}{12} + \dots$$

so

$$-u''(x) = \frac{2u(x) - u(x+h) - u(x-h)}{h^2} + u^{(4)}(x)\frac{h^2}{12} + \dots \quad (4.7)$$

The basis for a numerical scheme for (4.4) is then the observation

$$\frac{2u(x) - u(x+h) - u(x-h)}{h^2} = f(x, u(x), u'(x)) + O(h^2),$$

which shows that we can approximate the differential operator by a difference operator, with an $O(h^2)$ truncation error as $h \downarrow 0$.

To derive a numerical method, we divide the interval $[0, 1]$ into equally spaced points: $x_k = kh$ where $h = 1/(n+1)$ and $k = 0 \dots n+1$. With these, the Finite Difference (FD) formula (4.7) leads to a numerical scheme that forms a system of equations:

$$-u_{k+1} + 2u_k - u_{k-1} = h^2 f(x_k) \quad \text{for } k = 1, \dots, n \quad (4.8)$$

This process of using the FD formula (4.7) for the approximate solution of a PDE is known as the *Finite Difference Method (FDM)*.

For most values of k this equation relates u_k unknown to the unknowns u_{k-1} and u_{k+1} . The exceptions are $k = 1$ and $k = n$. In that case we recall that u_0 and u_{n+1} are known boundary conditions, and we write the equations with unknowns on the left and known quantities on the right as

$$\begin{cases} 2u_1 - u_2 = h^2 f(x_1) + u_0 \\ 2u_n - u_{n-1} = h^2 f(x_n) + u_{n+1}. \end{cases}$$

We can now summarize these equations for u_k , $k = 1 \dots n - 1$ as a matrix equation:

$$\begin{pmatrix} 2 & -1 & & \\ -1 & 2 & -1 & \\ & \ddots & \ddots & \ddots \end{pmatrix} \begin{pmatrix} u_1 \\ u_2 \\ \vdots \end{pmatrix} = \begin{pmatrix} h^2 f_1 + u_0 \\ h^2 f_2 \\ \vdots \end{pmatrix} \quad (4.9)$$

This has the form $Au = f$ with A a fully known matrix, f a fully known vector, and u a vector of unknowns. Note that the right hand side vector has the boundary values of the problem in the first and last locations. This means that, if you want to solve the same differential equation with different boundary conditions, only the vector f changes.

Exercise 4.3. A condition of the type $u(0) = u_0$ is called a *Dirichlet boundary condition*.

Physically, this corresponds to knowing the temperature at the end point of a rod. Other boundary conditions exist. Specifying a value for the derivative, $u'(0) = u'_0$, rather than for the function value, would be appropriate if we are modeling fluid flow and the outflow rate at $x = 0$ is known. This is known as a *Neumann boundary condition*.

A Neumann boundary condition $u'(0) = u'_0$ can be modeled by stating

$$\frac{u_0 - u_1}{h} = u'_0.$$

Show that, unlike in the case of the Dirichlet boundary condition, this affects the matrix of the linear system.

Show that having a Neumann boundary condition at both ends gives a singular matrix, and therefore no unique solution to the linear system. (Hint: guess the vector that has eigenvalue zero.)

Physically this makes sense. For instance, in an elasticity problem, Dirichlet boundary conditions state that the rod is clamped at a certain height; a Neumann boundary condition only states its angle at the end points, which leaves its height undetermined.

Let us list some properties of A that you will see later are relevant for solving such systems of equations:

- The matrix is very *sparse*: the percentage of elements that is nonzero is low. The nonzero elements are not randomly distributed but located in a band around the main diagonal. We call this a *banded matrix* in general, and a *tridiagonal matrix* in this specific case.
- The matrix is symmetric. This property does not hold for all matrices that come from discretizing BVPs, but it is true if there are no odd order (meaning first, third, fifth, ...) derivatives, such as u_x, u_{xxx}, u_{xy} .
- Matrix elements are constant in each diagonal, that is, in each set of points $\{(i, j) : i - j = c\}$ for some c . This is only true for very simple problems. It is no longer true if the differential equation has location dependent terms such as $\frac{d}{dx}(a(x)\frac{du}{dx})$. It is also no longer true if we make h variable through the interval, for instance because we want to model behaviour around the left end point in more detail.
- Matrix elements conform to the following sign pattern: the diagonal elements are positive, and the off-diagonal elements are nonpositive. This property depends on the numerical scheme used, but it is often true. Together with the following property of definiteness, this is called an *M-matrix*. There is a whole mathematical theory of these matrices [8].

- The matrix is positive definite: $x^t Ax > 0$ for all nonzero vectors x . This property is inherited from the original continuous problem, if the numerical scheme is carefully chosen. While the use of this may not seem clear at the moment, later you will see methods for solving the linear system that depend on it.

Strictly speaking the solution of equation (4.9) is simple: $u = A^{-1}f$. However, computing A^{-1} is not the best way of finding u . As observed just now, the matrix A has only $3N$ nonzero elements to store. Its inverse, on the other hand, does not have a single nonzero. Although we will not prove it, this sort of statement holds for most sparse matrices. Therefore, we want to solve $Au = f$ in a way that does not require $O(n^2)$ storage.

4.2.2.2 Two-dimensional BVPs

The one-dimensional BVP above was atypical in a number of ways, especially related to the resulting linear algebra problem. In this section we will see a two-dimensional problem, which displays some new aspects.

The one-dimensional problem above had a function $u = u(x)$, which now becomes $u = u(x, y)$ in two dimensions. The two-dimensional problem we are interested in is then

$$-u_{xx} - u_{yy} = f, \quad (x, y) \in [0, 1]^2, \quad (4.10)$$

where the values on the boundaries are given. We get our discrete equation by applying equation (4.7) in x and y directions:

$$\begin{aligned} -u_{xx}(x, y) &= \frac{2u(x, y) - u(x+h, y) - u(x-h, y)}{h^2} + u^{(4)}(x, y) \frac{h^2}{12} + \dots \\ -u_{yy}(x, y) &= \frac{2u(x, y) - u(x, y+h) - u(x, y-h)}{h^2} + u^{(4)}(x, y) \frac{h^2}{12} + \dots \end{aligned}$$

or, taken together:

$$4u(x, y) - u(x+h, y) - u(x-h, y) - u(x, y+h) - u(x, y-h) = 1/h^2 f(x, y) + O(h^2) \quad (4.11)$$

Let again $h = 1/(n+1)$ and define $x_i = ih$ and $y_j = jh$; let u_{ij} be the approximation to $u(x_i, y_j)$, then our discrete equation becomes

$$4u_{ij} - u_{i+1,j} - u_{i-1,j} - u_{i,j+1} - u_{i,j-1} = h^{-2} f_{ij}. \quad (4.12)$$

We now have $n \times n$ unknowns u_{ij} . To render this in a linear system as before we need to put them in a linear ordering, which we do by defining $I = I_{ij} = j + i \times n$. This is called the *lexicographic ordering* since it sorts the coordinates (i, j) as if they are strings.

Using this ordering gives us $N = n^2$ equations

$$4u_I - u_{I+1} - u_{I-1} - u_{I+n} - u_{I-n} = h^{-2} f_I, \quad I = 1, \dots, N \quad (4.13)$$




Figure 4.1: A difference stencil applied to a two-dimensional square domain

and the linear system looks like

$$A = \left(\begin{array}{cc|cc|c} 4 & -1 & & \emptyset & -1 & \emptyset \\ -1 & 4 & -1 & & -1 & \\ \ddots & \ddots & \ddots & & \ddots & \\ & \ddots & \ddots & -1 & \ddots & \\ \emptyset & & -1 & 4 & \emptyset & -1 \\ \hline -1 & & & \emptyset & 4 & -1 \\ & -1 & & & -1 & 4 & -1 \\ & \uparrow & \ddots & & \uparrow & \uparrow & \uparrow \\ k-n & & & & k-1 & k & k+1 & -1 & 4 & k+n \\ \hline & & -1 & & \ddots & & & & \ddots & \end{array} \right) \quad (4.14)$$

However, it can be more insightful to render these equations in a way that makes clear the two-dimensional connections of the unknowns. For this, figure 4.1 pictures the variables in the domain, and how equation (4.12) relates them. From now on, when making such a picture of the domain, we will just use the indices of the variables, and omit the ‘ u ’ identifier.

The matrix of equation 4.14 is banded as in the one-dimensional case, but unlike in the one-dimensional case, there are zeros inside the band. (This has some important consequences when we try to solve the linear system; see section 5.4.3.) Because the matrix has five nonzero diagonals, it is said to be of *penta-diagonal* structure.

You can also put a block structure on the matrix, by grouping the unknowns together that are in one row of the domain. This is called a *block matrix*, and, on the block level, it has a *tridiagonal* structure, so we call




Figure 4.2: A triangular domain of definition for the Poisson equation

this a *block tridiagonal* matrix. Note that the diagonal blocks themselves are tridiagonal; the off-diagonal blocks are minus the identity matrix.

This matrix, like the one-dimensional example above, has constant diagonals, but this is again due to the simple nature of the problem. In practical problems it will not be true. That said, such ‘constant coefficient’ problems occur, and when they are on rectangular domains, there are very efficient methods for solving the linear system with $N \log N$ time complexity.

Exercise 4.4. The block structure of the matrix, with all diagonal blocks having the same size, is due to the fact that we defined our BVP on a square domain. Sketch the matrix structure that arises from discretizing equation (4.10), again with central differences, but this time defined on a triangular domain; see figure 4.2. Show that, again, there is a block tridiagonal matrix structure, but that the blocks are now of varying sizes. Hint: start by sketching a small example. For $n = 4$ you should get a 10×10 matrix with a 4×4 block structure.

For domains that are even more irregular, the matrix structure will also be irregular; see figure 4.3 for an example.

The regular block structure is also caused by our decision to order the unknowns by rows and columns. This known as the *natural ordering* or *lexicographic ordering*; various other orderings are possible. One common way of ordering the unknowns is the *red-black ordering* or *checkerboard ordering* which has advantages for parallel computation. This will be discussed in section 6.6.

There is more to say about analytical aspects of the BVP (for instance, how smooth is the solution and how does that depend on the boundary conditions?) but those questions are outside the scope of this course. Here we only focus on the numerical aspects of the matrices. In the chapter on linear algebra, we will come back to the BVP, since solving the linear system is mathematically interesting.




Figure 4.3: A matrix from an irregular problem

4.2.2.3 Difference stencils

The discretization (4.11) is often phrased as applying the *difference stencil*

$$\begin{array}{ccc} \cdot & -1 & \cdot \\ -1 & 4 & -1 \\ \cdot & -1 & \cdot \end{array}$$

to the function u . Given a physical domain, we apply the stencil to each point in that domain to derive the equation for that point. Figure 4.1 illustrates that for a square domain of $n \times n$ points. Connecting this figure with equation (4.14), you see that the connections in the same line give rise to the main diagonal and first upper and lower offdiagonal; the connections to the next and previous lines become the nonzeros in the off-diagonal blocks.

This particular stencil is often referred to as the ‘5-point star’. There are other difference stencils; the structure of some of them are depicted in figure 4.4. A stencil with only connections in horizontal or vertical




Figure 4.4: The structure of some difference stencils in two dimensions

direction is called a ‘star stencil’, while one that has cross connections (such as the second in figure 4.4) is called a ‘box stencil’.

Exercise 4.5. Consider the third stencil in figure 4.4, used for a BVP on a square domain.

What does the sparsity structure of the resulting matrix look like, if we again order the variables by rows and columns?

Other stencils than the 5-point star can be used to attain higher accuracy, for instance giving a truncation error of $O(h^4)$. They can also be used for other differential equations than the one discussed above. For instance, it is not hard to show that for the equation $u_{xxxx} + u_{yyyy} = f$ we need a stencil that contains both $x, y \pm h$ and $x, y \pm 2h$ connections, such as the third stencil in the figure. Conversely, using the 5-point stencil no values of the coefficients give a discretization of the fourth order problem with less than $O(1)$ truncation error.

While the discussion so far has been about two-dimensional problems, it is easily generalized to higher dimensions for such equations as $-u_{xx} - u_{yy} - u_{zz} = f$. The straightforward generalization of the 5-point stencil, for instance, becomes a 7-point stencil in three dimensions.

4.2.2.4 Other discretization techniques

In the above, we used the FDM to find a numerical solution to a differential equation. There are various other techniques, and in fact, in the case of boundary value problems, they are usually preferred over finite differences. The most popular methods are the *FEM* and the *finite volume method*. Especially the finite element method is attractive, since it can handle irregular shapes more easily, and it is more amenable to approximation error analysis. However, on the simple problems discussed here it gives similar or even the same linear systems as FD methods, so we limit the discussion to Finite Differences, since we are mostly concerned with the computational aspects of the linear systems.

There will be a brief discussion of finite element matrices in section 6.5.2.

4.3 Initial boundary value problem

We will now go on to discuss an Initial Boundary Value Problem (IBVP), which, as you may deduce from the name, combines aspects of IVPs and BVPs. Here we will limit ourselves to one space dimension.

The problem we are considering is that of heat conduction in a rod, where $T(x, t)$ describes the temperature in location x at time t , for $x \in [a, b]$, $t > 0$. The so-called *heat equation* (see Appendix A.3 for a quick introduction to PDEs in general and the heat equation in particular) is:

$$\frac{\partial}{\partial t} T(x, t) - \alpha \frac{\partial^2}{\partial x^2} T(x, t) = q(x, t)$$

where

- The initial condition $T(x, 0) = T_0(x)$ describes the initial temperature distribution.
- The boundary conditions $T(a, t) = T_a(t)$, $T(b, t) = T_b(t)$ describe the ends of the rod, which can for instance be fixed to an object of a known temperature.

- The material the rod is made of is modeled by a single parameter $\alpha > 0$, the thermal diffusivity, which describes how fast heat diffuses through the material.
- The forcing function $q(x, t)$ describes externally applied heating, as a function of both time and place.

There is a simple connection between the IBVP and the BVP: if the boundary functions T_a and T_b are constant, and q does not depend on time, only on location, then intuitively T will converge to a *steady state*. The equation for this is $-\alpha u''(x) = q$.

4.3.1 Discretization

We now discretize both space and time, by $x_{j+1} = x_j + \Delta x$ and $t_{k+1} = t_k + \Delta t$, with boundary conditions $x_0 = a$, $x_n = b$, and $t_0 = 0$. We write T_j^k for the numerical solution at $x = x_j, t = t_k$; with a little luck, this will approximate the exact solution $T(x_j, t_k)$.

For the space discretization we use the central difference formula (4.8):

$$\frac{\partial^2}{\partial x^2} T(x, t_k) \Big|_{x=x_j} \Rightarrow \frac{T_{j-1}^k - 2T_j^k + T_{j+1}^k}{\Delta x^2}.$$

For the time discretization we can use any of the schemes in section 4.1.2. We will investigate again the explicit and implicit schemes, with similar conclusions about the resulting stability.

4.3.1.1 Explicit scheme

With explicit time stepping we approximate the time derivative as

$$\frac{\partial}{\partial t} T(x_j, t) \Big|_{t=t_k} \Rightarrow \frac{T_j^{k+1} - T_j^k}{\Delta t}. \quad (4.15)$$

Taking this together with the central differences in space, we now have

$$\frac{T_j^{k+1} - T_j^k}{\Delta t} - \alpha \frac{T_{j-1}^k - 2T_j^k + T_{j+1}^k}{\Delta x^2} = q_j^k$$

which we rewrite as

$$T_j^{k+1} = T_j^k + \frac{\alpha \Delta t}{\Delta x^2} (T_{j-1}^k - 2T_j^k + T_{j+1}^k) + \Delta t q_j^k \quad (4.16)$$

Pictorially, we render this as a difference stencil in figure 4.5. This expresses that the function value in each point is determined by a combination of points on the previous time level.

It is convenient to summarize the set of equations (4.16) for a given k and all values of j in vector form as

$$T^{k+1} = \left(I - \frac{\alpha \Delta t}{\Delta x^2} K \right) T^k + \Delta t q^k \quad (4.17)$$




Figure 4.5: The difference stencil of the Euler forward method for the heat equation

where

$$K = \begin{pmatrix} 2 & -1 & & \\ -1 & 2 & -1 & \\ & \ddots & \ddots & \ddots \end{pmatrix}, \quad T^k = \begin{matrix} T_1^k \\ \vdots \\ T_n^k \end{matrix}$$

The important observation here is that the dominant computation for deriving the vector T^{k+1} from T^k is a simple matrix-vector multiplication:

$$T^{k+1} \leftarrow AT^k + \Delta t q^k$$

where $A = I - \frac{\alpha \Delta t}{\Delta x^2} K$. This is a first indication that the sparse matrix-vector product is an important operation; see sections 5.4 and 6.4. Actual computer programs using an explicit method often do not form the matrix, but evaluate the equation (4.16). However, the linear algebra formulation (4.17) is more insightful for purposes of analysis.

4.3.1.2 Implicit scheme

In equation (4.15) we let T^{k+1} be defined from T^k . We can turn this around by defining T^k from T^{k-1} , as we did for the IVP in section 4.1.2.2. For the time discretization this gives

$$\frac{\partial}{\partial t} T(x, t) \Big|_{t=t_k} \Rightarrow \frac{T_j^k - T_j^{k-1}}{\Delta t} \quad \text{or} \quad \frac{\partial}{\partial t} T(x, t) \Big|_{t=t_{k+1}} \Rightarrow \frac{T_j^{k+1} - T_j^k}{\Delta t}. \quad (4.18)$$

The implicit time step discretization of the whole heat equation, evaluated in t_{k+1} , now becomes:

$$\frac{T_j^{k+1} - T_j^k}{\Delta t} - \alpha \frac{T_{j-1}^{k+1} - 2T_j^{k+1} + T_{j+1}^{k+1}}{\Delta x^2} = q_j^{k+1}$$

or

$$T_j^{k+1} - \frac{\alpha \Delta t}{\Delta x^2} (T_{j-1}^{k+1} - 2T_j^{k+1} + T_{j+1}^{k+1}) = T_j^k + \Delta t q_j^{k+1} \quad (4.19)$$




Figure 4.6: The difference stencil of the Euler backward method for the heat equation

Figure 4.6 renders this as a stencil; this expresses that each point on the current time level influences a combination of points on the next level. Again we write this in vector form:

$$\left(I + \frac{\alpha \Delta t}{\Delta x^2} K \right) T^{k+1} = T^k + \Delta t q^{k+1} \quad (4.20)$$

As opposed to the explicit method, where a matrix-vector multiplication sufficed, the derivation of the vector T^{k+1} from T^k now involves solving a linear system

$$T^{k+1} \leftarrow A^{-1}(T^k + \Delta t q^{k+1})$$

where $A = I + \frac{\alpha \Delta t}{\Delta x^2} K$, a harder operation than the matrix-vector multiplication. In this case, it is not possible, as above, to evaluate the equation (4.19) directly. Codes using an implicit method actually form the coefficient matrix, and solve the system (4.20) as such. Solving linear systems will be the focus of much of chapters 5 and 6.

Exercise 4.6. Show that the flop count for a time step of the implicit method is of the same order as of a time step of the explicit method. (This only holds for a problem with one space dimension.) Give at least one argument why we consider the implicit method as computationally ‘harder’.

The numerical scheme that we used here is of first order in time and second order in space: the truncation error (section 4.1.2) is $O(\Delta t + \Delta x^2)$. It would be possible to use a scheme that is second order in time by using central differences in time too. Alternatively, see exercise 4.7.

4.3.2 Stability analysis

We now analyse the stability of the explicit and implicit schemes in a simple case. Let $q \equiv 0$, and assume $T_j^k = \beta^k e^{i\ell x_j}$ for some ℓ ⁷. This assumption is intuitively defensible: since the differential equation does not ‘mix’ the x and t coordinates, we surmise that the solution will be a product $T(x, t) = v(x) \cdot w(t)$ of the separate solutions of

$$\begin{cases} v_{xx} = c_1 v, & v(0) = 0, v(1) = 0 \\ w_t = c_2 w & w(0) = 1 \end{cases}$$

7. Actually, β is also dependent on ℓ , but we will save ourselves a bunch of subscripts, since different β values never appear together in one formula.

The only meaningful solution occurs with $c_1, c_2 < 0$, in which case we find:

$$v_{xx} = -c^2 v \Rightarrow v(x) = e^{-icx} = e^{-i\ell\pi x}$$

where we substitute $c = \ell\pi$ to take boundary conditions into account, and

$$w(t) = e^{-ct} = e^{-ck\Delta t} = \beta^k, \quad \beta = e^{-ck}.$$

If the assumption on this form of the solution holds up, we need $|\beta| < 1$ for stability.

Substituting the surmised form for T_j^k into the explicit scheme gives

$$\begin{aligned} T_j^{k+1} &= T_j^k + \frac{\alpha\Delta t}{\Delta x^2}(T_{j-1}^k - 2T_j^k + T_{j+1}^k) \\ \Rightarrow \beta^{k+1}e^{i\ell x_j} &= \beta^k e^{i\ell x_j} + \frac{\alpha\Delta t}{\Delta x^2}(\beta^k e^{i\ell x_{j-1}} - 2\beta^k e^{i\ell x_j} + \beta^k e^{i\ell x_{j+1}}) \\ &= \beta^k e^{i\ell x_j} \left[1 + \frac{\alpha\Delta t}{\Delta x^2} [e^{-i\ell\Delta x} - 2 + e^{i\ell\Delta x}] \right] \\ \Rightarrow \beta &= 1 + 2\frac{\alpha\Delta t}{\Delta x^2} \left[\frac{1}{2}(e^{i\ell\Delta x} + e^{-\ell\Delta x}) - 1 \right] \\ &= 1 + 2\frac{\alpha\Delta t}{\Delta x^2} (\cos(\ell\Delta x) - 1) \end{aligned}$$

For stability we need $|\beta| < 1$:

- $\beta < 1 \Leftrightarrow 2\frac{\alpha\Delta t}{\Delta x^2}(\cos(\ell\Delta x) - 1) < 0$: this is true for any ℓ and any choice of $\Delta x, \Delta t$.
- $\beta > -1 \Leftrightarrow 2\frac{\alpha\Delta t}{\Delta x^2}(\cos(\ell\Delta x) - 1) > -2$: this is true for all ℓ only if $2\frac{\alpha\Delta t}{\Delta x^2} < 1$, that is

$$\Delta t < \frac{\Delta x^2}{2\alpha}$$

The latter condition poses a big restriction on the allowable size of the time steps: time steps have to be small enough for the method to be stable. This is similar to the stability analysis of the explicit method for the IVP; however, now the time step is also related to the space discretization. This implies that, if we decide we need more accuracy in space and we halve the space discretization Δx , the number of time steps will be multiplied by four.

Let us now consider the stability of the implicit scheme. Substituting the form of the solution $T_j^k = \beta^k e^{i\ell x_j}$ into the numerical scheme gives

$$\begin{aligned} T_j^{k+1} - T_j^k &= \frac{\alpha\Delta t}{\Delta x^2}(T_{j+1}^{k+1} - 2T_j^{k+1} + T_{j-1}^{k+1}) \\ \Rightarrow \beta^{k+1}e^{i\ell\Delta x} - \beta^k e^{i\ell x_j} &= \frac{\alpha\Delta t}{\Delta x^2}(\beta^{k+1}e^{i\ell x_{j-1}} - 2\beta^{k+1}e^{i\ell x_j} + \beta^{k+1}e^{i\ell x_{j+1}}) \end{aligned}$$

Dividing out $e^{i\ell x_j} \beta^{k+1}$ gives

$$\begin{aligned} 1 &= \beta^{-1} + 2\alpha \frac{\Delta t}{\Delta x^2} (\cos \ell\Delta x - 1) \\ \beta &= \frac{1}{1 + 2\alpha \frac{\Delta t}{\Delta x^2} (1 - \cos \ell\Delta x)} \end{aligned}$$

Since $1 - \cos \ell \Delta x \in (0, 2)$, the denominator is strictly > 1 . Therefore the condition $|\beta| < 1$ is always satisfied, regardless the value of ℓ and the choices of Δx and Δt : the method is always stable.

Exercise 4.7. The schemes we considered here are of first order in time and second order in space: their discretization order are $O(\Delta t) + O(\Delta x^2)$. Derive the *Crank-Nicolson method* that is obtained by averaging the explicit and implicit schemes, show that it is unconditionally stable, and of second order in time.

Chapter 5

Numerical linear algebra

In chapter 4 you saw how the numerical solution of partial differential equations can lead to linear algebra problems. Sometimes this is a simple problem – a matrix-vector multiplication in the case of the Euler forward method – but sometimes it is more complicated, such as the solution of a system of linear equations in the case of Euler backward methods. Solving linear systems will be the focus of this chapter; in other applications, which we will not discuss here, eigenvalue problems need to be solved.

You may have learned a simple algorithm for solving system of linear equations: elimination of unknowns, also called Gaussian elimination. This method can still be used, but we need some careful discussion of its efficiency. There are also other algorithms, the so-called iterative solution methods, which proceed by gradually approximating the solution of the linear system. They warrant some discussion of their own.

Because of the PDE background, we only consider linear systems that are square and nonsingular. Rectangular, in particular overdetermined, systems have important applications too in a corner of numerical analysis known as optimization theory. However, we will not cover that in this book.

The standard work on numerical linear algebra is Golub and Van Loan's *Matrix Computations* [56]. It covers algorithms, error analysis, and computational details. Heath's *Scientific Computing* covers the most common types of computations that arise in scientific computing; this book has many excellent exercises and practical projects.

5.1 Elimination of unknowns

In this section we are going to take a closer look at Gaussian elimination, or elimination of unknowns. You may have seen this method before (and if not, it will be explained below), but we will be a bit more systematic here so that we can analyze various aspects of it.

One general thread of this chapter will be the discussion of the efficiency of the various algorithms. When you learned how to solve a system of unknowns by gradually eliminating unknowns, you most likely never applied that method to a matrix larger than 4×4 . The linear systems that occur in PDE solving can be thousands of times larger, and counting how many operations, as well as how much memory, they require becomes important.

Let us consider an example of the importance of efficiency in choosing the right algorithm. The solution of a linear system can be written with a fairly simple explicit formula, using determinants. This is called ‘Cramer’s rule’. It is mathematically elegant, but completely impractical for our purposes.

If a matrix A and a vector b are given, and a vector x satisfying $Ax = b$ is wanted, then, writing $|A|$ for the determinant,

$$x_i = \frac{\begin{vmatrix} a_{11} & a_{12} & \dots & a_{1i-1} & b_1 & a_{1i+1} & \dots & a_{1n} \\ a_{21} & & \dots & & b_2 & & \dots & a_{2n} \\ \vdots & & & & \vdots & & & \vdots \\ a_{n1} & & \dots & & b_n & & \dots & a_{nn} \end{vmatrix}}{|A|}$$

For any matrix M the determinant is defined recursively as

$$|M| = \sum_i (-1)^i m_{1i} |M^{[1,i]}|$$

where $M^{[1,i]}$ denotes the matrix obtained by deleting row 1 and column i from M . This means that computing the determinant of a matrix of dimension n means n times computing a size $n - 1$ determinant. Each of these requires $n - 1$ determinants of size $n - 2$, so you see that the number of operations required to compute the determinant is factorial in the matrix size. This quickly becomes prohibitive, even ignoring any issues of numerical stability. Later in this chapter you will see complexity estimates for other methods of solving systems of linear equations that are considerably more reasonable.

Let us now look at a simple example of solving linear equations with elimination of unknowns. Consider the system

$$\begin{aligned} 6x_1 &- 2x_2 & +2x_3 &= 16 \\ 12x_1 &- 8x_2 & +6x_3 &= 26 \\ 3x_1 &- 13x_2 & +3x_3 &= -19 \end{aligned} \tag{5.1}$$

We eliminate x_1 from the second and third equation by

- multiplying the first equation $\times 2$ and subtracting the result from the second equation, and
- multiplying the first equation $\times 1/2$ and subtracting the result from the third equation.

The linear system then becomes

$$\begin{aligned} 6x_1 &- 2x_2 & +2x_3 &= 16 \\ 0x_1 &- 4x_2 & +2x_3 &= -6 \\ 0x_1 &- 12x_2 & +2x_3 &= -27 \end{aligned}$$

Finally, we eliminate x_2 from the third equation by multiplying the second equation by 3, and subtracting the result from the third equation:

$$\begin{aligned} 6x_1 &- 2x_2 & +2x_3 &= 16 \\ 0x_1 &- 4x_2 & +2x_3 &= -6 \\ 0x_1 &+ 0x_2 & -4x_3 &= -9 \end{aligned}$$

We can now solve $x_3 = 9/4$ from the last equation. Substituting that in the second equation, we get $-4x_2 = -6 - 2x_2 = -21/2$ so $x_2 = 21/8$. Finally, from the first equation $6x_1 = 16 + 2x_2 - 2x_3 = 16 + 21/4 - 9/2 = 76/4$ so $x_1 = 19/6$.

We can write this more compactly by omitting the x_i coefficients. Write

$$\begin{pmatrix} 6 & -2 & 2 \\ 12 & -8 & 6 \\ 3 & -13 & 3 \end{pmatrix} \begin{pmatrix} x_1 \\ x_2 \\ x_3 \end{pmatrix} = \begin{pmatrix} 16 \\ 26 \\ -19 \end{pmatrix}$$

as

$$\left[\begin{array}{ccc|c} 6 & -2 & 2 & 16 \\ 12 & -8 & 6 & 26 \\ 3 & -13 & 3 & -19 \end{array} \right] \quad (5.2)$$

then the elimination process is

$$\left[\begin{array}{ccc|c} 6 & -2 & 2 & 16 \\ 12 & -8 & 6 & 26 \\ 3 & -13 & 3 & -19 \end{array} \right] \rightarrow \left[\begin{array}{ccc|c} 6 & -2 & 2 & 16 \\ 0 & -4 & 2 & -6 \\ 0 & -12 & 2 & -27 \end{array} \right] \rightarrow \left[\begin{array}{ccc|c} 6 & -2 & 2 & 16 \\ 0 & -4 & 2 & -6 \\ 0 & 0 & -4 & -9 \end{array} \right].$$

In the above example, the matrix coefficients could have been any real (or, for that matter, complex) coefficients, and you could follow the elimination procedure mechanically. There is the following exception. At some point in the computation, we divided by the numbers 6, -4 , -4 which are found on the diagonal of the matrix in the last elimination step. These quantities are called the *pivots*, and clearly they are required to be nonzero.

Exercise 5.1. The system

$$\begin{aligned} 6x_1 - 2x_2 + 2x_3 &= 16 \\ 12x_1 - 4x_2 + 6x_3 &= 26 \\ 3x_1 - 13x_2 + 3x_3 &= -19 \end{aligned}$$

is the same as the one we just investigated in equation (5.1), except for the (2, 2) element. Confirm that you get a zero pivot in the second step.

The first pivot is an element of the original matrix; as you saw in the preceding exercise, the other pivots can not easily be found without doing the actual elimination. In particular, there is no easy way of predicting zero pivots from looking at the system of equations.

If a pivot turns out to be zero, all is not lost for the computation: we can always exchange two matrix rows; this is known as *pivoting*. It is not hard to show¹ that with a nonsingular matrix there is always a row exchange possible that puts a nonzero element in the pivot location.

Exercise 5.2. Suppose you want to exchange matrix rows 2 and 3 of the system of equations in equation (5.2). What other adjustments would you have to make to make sure you still compute the correct solution? Continue the system solution of the previous exercise by exchanging rows 2 and 3, and check that you get the correct answer.

1. And you can find this in any elementary linear algebra textbook.

Exercise 5.3. Take another look at exercise 5.1. Instead of exchanging rows 2 and 3, exchange columns 2 and 3. What does this mean in terms of the linear system? Continue the process of solving the system; check that you get the same solution as before.

In general, with floating point numbers and round-off, it is very unlikely that a matrix element will become exactly zero during a computation. Also, in a PDE context, the diagonal is usually nonzero. Does that mean that pivoting is in practice almost never necessary? The answer is *no*: pivoting is desirable from a point of view of numerical stability. In the next section you will see an example that illustrates this fact.

5.2 Linear algebra in computer arithmetic

In most of this chapter, we will act as if all operations can be done in exact arithmetic. However, it is good to become aware of some of the potential problems due to our finite precision computer arithmetic. This allows us to design algorithms that minimize the effect of roundoff. A more rigorous approach to the topic of numerical linear algebra includes a full-fledged error analysis of the algorithms we discuss; however, that is beyond the scope of this course. Error analysis of computations in computer arithmetic is the focus of Wilkinson's classic *Rounding errors in Algebraic Processes* [134] and Higham's more recent *Accuracy and Stability of Numerical Algorithms* [70].

Here, we will only note a few paradigmatic examples of the sort of problems that can come up in computer arithmetic: we will show why pivoting during LU factorization is more than a theoretical device, and we will give two examples of problems in eigenvalue calculations due to the finite precision of computer arithmetic.

5.2.1 Roundoff control during elimination

Above, you saw that row interchanging ('pivoting') is necessary if a zero element appears on the diagonal during elimination of that row and column. Let us now look at what happens if the pivot element is not zero, but close to zero.

Consider the linear system

$$\begin{pmatrix} \epsilon & 1 \\ 1 & 1 \end{pmatrix} x = \begin{pmatrix} 1 + \epsilon \\ 2 \end{pmatrix}$$

which has the solution solution $x = (1, 1)^t$. Using the $(1, 1)$ element to clear the remainder of the first column gives:

$$\begin{pmatrix} \epsilon & 1 \\ 0 & 1 - \frac{1}{\epsilon} \end{pmatrix} x = \begin{pmatrix} 1 + \epsilon \\ 2 - \frac{1+\epsilon}{\epsilon} \end{pmatrix}.$$

We can now solve x_2 and from it x_1 .

If ϵ is small, say $\epsilon < \epsilon_{\text{mach}}$, the $1 + \epsilon$ term in the right hand side will be simply 1: our linear system will be

$$\begin{pmatrix} \epsilon & 1 \\ 1 & 1 \end{pmatrix} x = \begin{pmatrix} 1 \\ 2 \end{pmatrix}$$

but the solution $(1, 1)^t$ will still satisfy the system in machine arithmetic.

Next, $1/\epsilon$ will be very large, so the second component of the right hand side after elimination will be $2 - \frac{1}{\epsilon} = -1/\epsilon$. Also, the $(2, 2)$ element of the matrix is then $-1/\epsilon$ instead of $1 - 1/\epsilon$:

$$\begin{pmatrix} \epsilon & 1 \\ 0 & -1/\epsilon \end{pmatrix} x = \begin{pmatrix} 1 \\ -1/\epsilon \end{pmatrix}$$

We get the correct value $x_2 = 1$, but

$$\epsilon x_1 + x_2 = 1 \Rightarrow \epsilon x_1 = 0 \Rightarrow x_1 = 0,$$

which is 100% wrong.

What would have happened if we had pivoted as described above? We exchange the matrix rows, giving

$$\begin{pmatrix} 1 & 1 \\ \epsilon & 1 \end{pmatrix} x = \begin{pmatrix} 2 \\ 1 + \epsilon \end{pmatrix} \Rightarrow \begin{pmatrix} 1 & 1 \\ 0 & 1 - \epsilon \end{pmatrix} x = \begin{pmatrix} 2 \\ 1 - \epsilon \end{pmatrix}$$

Now we get, regardless the size of epsilon:

$$x_2 = \frac{1 - \epsilon}{1 - \epsilon} = 1, \quad x_1 = 2 - x_2 = 1$$

In this example we used a very small value of ϵ ; a much more refined analysis shows that even with ϵ greater than the machine precision pivoting still makes sense. The general rule of thumb is: *Always do row exchanges to get the largest remaining element in the current column into the pivot position*. In chapter 4 you saw matrices that arise in certain practical applications; it can be shown that for them pivoting is never necessary; see exercise 5.13.

The pivoting that was discussed above is also known as *partial pivoting*, since it is based on row exchanges only. Another option would be *full pivoting*, where row and column exchanges are combined to find the largest element in the remaining subblock, to be used as pivot. Finally, *diagonal pivoting* applies the same exchange to rows and columns. (This is equivalent to renumbering the unknowns of the problem, a strategy which we will consider in section 6.7 for increasing the parallelism of the problem.) This means that pivots are only searched on the diagonal. From now on we will only consider partial pivoting.

5.2.2 Influence of roundoff on eigenvalue computations

Consider the matrix

$$A = \begin{pmatrix} 1 & \epsilon \\ \epsilon & 1 \end{pmatrix}$$

where $\epsilon_{\text{mach}} < |\epsilon| < \sqrt{\epsilon_{\text{mach}}}$, which has eigenvalues $1 + \epsilon$ and $1 - \epsilon$. If we calculate its characteristic polynomial in computer arithmetic

$$\begin{vmatrix} 1 - \lambda & \epsilon \\ \epsilon & 1 - \lambda \end{vmatrix} = \lambda^2 - 2\lambda + (1 - \epsilon^2) = \lambda^2 - 2\lambda + 1.$$

we find a double eigenvalue 1. Note that the exact eigenvalues are expressible in working precision; it is the algorithm that causes the error. Clearly, using the characteristic polynomial is not the right way to compute eigenvalues, even in well-behaved, symmetric positive definite, matrices.

An unsymmetric example: let A be the matrix of size 20

$$A = \begin{pmatrix} 20 & 20 & & \emptyset \\ & 19 & 20 & \\ & & \ddots & \ddots \\ & & & 2 & 20 \\ \emptyset & & & & 1 \end{pmatrix}.$$

Since this is a triangular matrix, its eigenvalues are the diagonal elements. If we perturb this matrix by setting $A_{20,1} = 10^{-6}$ we find a perturbation in the eigenvalues that is much larger than in the elements:

$$\lambda = 20.6 \pm 1.9i, 20.0 \pm 3.8i, 21.2, 16.6 \pm 5.4i, \dots$$

Also, several of the computed eigenvalues have an imaginary component, which the exact eigenvalues do not have.

5.3 LU factorization

So far, we have looked at eliminating unknowns in the context of solving a single system of linear equations. Suppose you need to solve more than one system with the same matrix, but with different right hand sides. This happens for instance if you take multiple time steps in an implicit method. Can you use any of the work you did in the first system to make solving subsequent ones easier?

The answer is yes. You can split the solution process in a part that only concerns the matrix, and a part that is specific to the right hand side. If you have a series of systems to solve, you have to do the first part only once, and, luckily, that even turns out to be the larger part of the work.

Let us take a look at the same example of section 5.1 again.

$$A = \begin{pmatrix} 6 & -2 & 2 \\ 12 & -8 & 6 \\ 3 & -13 & 3 \end{pmatrix}$$

In the elimination process, we took the 2nd row minus $2 \times$ the first and the 3rd row minus $1/2 \times$ the first. Convince yourself that this combining of rows can be done by multiplying A from the left by

$$L_1 = \begin{pmatrix} 1 & 0 & 0 \\ -2 & 1 & 0 \\ -1/2 & 0 & 1 \end{pmatrix},$$

which is the identity with the elimination coefficients in the first column, below the diagonal. The first step in elimination of variables is equivalent to transforming the system $Ax = b$ to $L_1 Ax = L_1 b$.

In the next step, you subtracted $3 \times$ the second row from the third. Convince yourself that this corresponds to left-multiplying the current matrix $L_1 A$ by

$$L_2 = \begin{pmatrix} 1 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & -3 & 1 \end{pmatrix}$$

We have now transformed our system $Ax = b$ into $L_2 L_1 Ax = L_2 L_1 b$, and $L_2 L_1 A$ is of ‘upper triangular’ form. If we define $U = L_2 L_1 A$, then $A = L_1^{-1} L_2^{-1} U$. How hard is it to compute matrices such as L_2^{-1} ? Remarkably easy, it turns out to be.

We make the following observations:

$$L_1 = \begin{pmatrix} 1 & 0 & 0 \\ -2 & 1 & 0 \\ -1/2 & 0 & 1 \end{pmatrix} \quad L_1^{-1} = \begin{pmatrix} 1 & 0 & 0 \\ 2 & 1 & 0 \\ 1/2 & 0 & 1 \end{pmatrix}$$

and likewise

$$L_2 = \begin{pmatrix} 1 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & -3 & 1 \end{pmatrix} \quad L_2^{-1} = \begin{pmatrix} 1 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & 3 & 1 \end{pmatrix}$$

and even more remarkable:

$$L_1^{-1} L_2^{-1} = \begin{pmatrix} 1 & 0 & 0 \\ 2 & 1 & 0 \\ 1/2 & 3 & 1 \end{pmatrix},$$

that is, $L_1^{-1} L_2^{-1}$ contains the off-diagonal elements of L_1^{-1}, L_2^{-1} unchanged, and they in turn contain the elimination coefficients.

Exercise 5.4. Show that a similar statement holds, even if there are elements above the diagonal.

If we define $L = L_1^{-1} L_2^{-1}$, we now have $A = LU$; this is called an *LU factorization*. We see that the coefficients of L below the diagonal are the negative of the coefficients used during elimination. Even better, the first column of L can be written while the first column of A is being eliminated, so the computation of L and U can be done without extra storage, at least if we can afford to lose A .

5.3.1 The algorithm

Let us write out the *LU* factorization algorithm in more or less formal code.

```

⟨LU factorization⟩:
  for k = 1, n - 1:
    ⟨eliminate values in column k⟩
    ⟨eliminate values in column k⟩:
      for i = k + 1 to n:

```

```

⟨compute multiplier for row i⟩
⟨update row i⟩
⟨compute multiplier for row i⟩
   $a_{ik} \leftarrow a_{ik}/a_{kk}$ 
⟨update row i⟩:
  for  $j = k + 1$  to  $n$ :
     $a_{ij} \leftarrow a_{ij} - a_{ik} * a_{kj}$ 

```

Or, putting everything together:

```

⟨LU factorization⟩:
  for  $k = 1, n - 1$ :
    for  $i = k + 1$  to  $n$ :
       $a_{ik} \leftarrow a_{ik}/a_{kk}$ 
      for  $j = k + 1$  to  $n$ :
         $a_{ij} \leftarrow a_{ij} - a_{ik} * a_{kj}$ 

```

(5.3)

This is the most common way of presenting the LU factorization. However, other ways of computing the same result exist. Algorithms such as the LU factorization can be coded in several ways that are mathematically equivalent, but that have different computational behaviour. This issue, in the context of dense matrices, is the focus of van de Geijn and Quintana's *The Science of Programming Matrix Computations* [127].

5.3.2 The Cholesky factorization

The LU factorization of a symmetric matrix does not give an L and U that are each other's transpose: L has ones on the diagonal and U has the pivots. However it is possible to make a factorization of a symmetric matrix A of the form $A = LL^t$. This has the advantage that the factorization takes the same amount of space as the original matrix, namely $n(n + 1)/2$ elements. We a little luck we can, just as in the LU case, overwrite the matrix with the factorization.

We derive this algorithm by reasoning inductively. Let us write $A = LL^t$ on block form:

$$A = \begin{pmatrix} A_{11} & A_{21}^t \\ A_{21} & A_{22} \end{pmatrix} = LL^t = \begin{pmatrix} \ell_{11} & 0 \\ \ell_{21} & L_{22} \end{pmatrix} \begin{pmatrix} \ell_{11} & \ell_{21}^t \\ 0 & L_{22}^t \end{pmatrix}$$

then $\ell_{11}^2 = a_{11}$, from which we get ℓ_{11} . We also find $\ell_{11}(L^t)_{1j} = \ell_{j1} = a_{1j}$, so we can compute the whole first column of L . Finally, $A_{22} = L_{22}L_{22}^t + \ell_{12}\ell_{12}^t$, so

$$L_{22}L_{22}^t = A_{22} - \ell_{12}\ell_{12}^t,$$

which shows that L_{22} is the Cholesky factor of the updated A_{22} block. Recursively, the algorithm is now defined.

5.3.3 Uniqueness

It is always a good idea, when discussing numerical algorithms, to wonder if different ways of computing lead to the same result. This is referred to as the ‘uniqueness’ of the result, and it is of practical use: if

the computed result is unique, swapping one software library for another will not change anything in the computation.

Let us consider the uniqueness of LU factorization. The definition of an LU factorization algorithm (without pivoting) is that, given a nonsingular matrix A , it will give a lower triangular matrix L and upper triangular matrix U such that $A = LU$. The above algorithm for computing an LU factorization is deterministic (it does not contain instructions ‘take any row that satisfies...’), so given the same input, it will always compute the same output. However, other algorithms are possible, so we need worry whether they give the same result.

Let us then assume that $A = L_1 U_1 = L_2 U_2$ where L_1, L_2 are lower triangular and U_1, U_2 are upper triangular. Then, $L_2^{-1} L_1 = U_2 U_1^{-1}$. In that equation, the left hand side is the product of lower triangular matrices, while the right hand side contains only upper triangular matrices.

Exercise 5.5. Prove that the product of lower triangular matrices is lower triangular, and the product of upper triangular matrices upper triangular. Is a similar statement true for inverses of nonsingular triangular matrices?

The product $L_2^{-1} L_1$ is apparently both lower triangular and upper triangular, so it must be diagonal. Let us call it D , then $L_1 = L_2 D$ and $U_2 = DU_1$. The conclusion is that LU factorization is not unique, but it is unique ‘up to diagonal scaling’.

Exercise 5.6. The algorithm in section 5.3.1 resulted in a lower triangular factor L that had ones on the diagonal. Show that this extra condition makes the factorization unique.

Exercise 5.7. Show that an alternative condition of having ones on the diagonal of U is also sufficient for the uniqueness of the factorization.

Since we can demand a unit diagonal in L or in U , you may wonder if it is possible to have both. (Give a simple argument why this is not strictly possible.) We can do the following: suppose that $A = LU$ where L and U are nonsingular lower and upper triangular, but not normalized in any way. Write

$$L = (I + L')D_L, \quad U = D_U(I + U'), \quad D = D_L D_U.$$

After some renaming we now have a factorization

$$A = (I + L)D(I + U) \tag{5.4}$$

where D is a diagonal matrix containing the pivots.

Exercise 5.8. Show that you can also normalize the factorization on the form

$$A = (D + L)D^{-1}(D + U).$$

How does this D relate to the previous?

Exercise 5.9. Consider the factorization of a tridiagonal matrix this way. How do L and U relate to the triangular parts of A ? Derive a relation between D and D_A and show that this is the equation that generates the pivots.

5.3.4 Pivoting

Above, you saw examples where pivoting, that is, exchanging rows, was necessary during the factorization process, either to guarantee the existence of a nonzero pivot, or for numerical stability. We will now integrate pivoting into the LU factorization.

Let us first observe that row exchanges can be described by a matrix multiplication. Let

$$P^{(i,j)} = i \begin{pmatrix} & & i & j \\ & 0 & & \\ 0 & \ddots & \ddots & \\ & 0 & 1 & \\ & & I & \\ j & 1 & 0 & I \\ & & & \ddots \end{pmatrix}$$

then $P^{(i,j)} A$ is the matrix A with rows i and j exchanged. Since we may have to pivot in every iteration of the factorization process, we introduce a sequence $p(\cdot)$ where $p(i)$ is the j value of the row that row i is switched with. We write $P^{(i)} \equiv P^{(i,p(i))}$ for short.

Exercise 5.10. Show that $P^{(i)}$ is its own inverse.

The process of factoring with partial pivoting can now be described as:

- Let $A^{(i)}$ be the matrix with columns $1 \dots i - 1$ eliminated, and partial pivoting applied to get the desired element in the (i, i) location.
- Let $\ell^{(i)}$ be the vector of multipliers in the i -th elimination step. (That is, the elimination matrix L_i in this step is the identity plus $\ell^{(i)}$ in the i -th column.)
- Let $P^{(i+1)}$ (with $j \geq i + 1$) be the matrix that does the partial pivoting for the next elimination step as described above.
- Then $A^{(i+1)} = P^{(i+1)} L_i A^{(i)}$.

In this way we get a factorization of the form

$$L_{n-1} P^{(n-2)} L_{n-2} \cdots L_1 P^{(1)} A = U.$$

Suddenly it has become impossible to write $A = LU$: instead we write

$$A = P^{(1)} L_1^{-1} \cdots P^{(n-2)} L_{n-1}^{-1} U. \quad (5.5)$$

Exercise 5.11. Recall from sections 1.6.8 and 1.6.9 that blocked algorithms are often desirable from a performance point of view. Why is the ‘ LU factorization with interleaved pivoting matrices’ in equation (5.5) bad news for performance?

Fortunately, equation (5.5) can be simplified: the P and L matrices ‘almost commute’. We show this by looking at an example: $P^{(2)}L_1 = \tilde{L}_1P^{(2)}$ where \tilde{L}_1 is very close to L_1 .

$$\begin{pmatrix} 1 & & & \\ & 0 & 1 & \\ & & I & \\ & 1 & 0 & \\ \end{pmatrix} \begin{pmatrix} 1 & \emptyset & & \\ \vdots & 1 & & \\ & \ell^{(1)} & \ddots & \\ & & & 1 \end{pmatrix} = \begin{pmatrix} 1 & \emptyset & & \\ \vdots & 0 & 1 & \\ \tilde{\ell}^{(1)} & & & \\ \vdots & 1 & 0 & \\ \vdots & & & I \end{pmatrix} = \begin{pmatrix} 1 & \emptyset & & \\ \vdots & 1 & & \\ \tilde{\ell}^{(1)} & & \ddots & \\ \vdots & & & 1 \end{pmatrix} \begin{pmatrix} 1 & 0 & 1 & \\ & I & \\ 1 & 0 & I & \\ \end{pmatrix}$$

where $\tilde{\ell}^{(1)}$ is the same as $\ell^{(1)}$, except that elements i and $p(i)$ have been swapped. You can now easily convince yourself that similarly $P^{(2)}$ et cetera can be ‘pulled through’ L_1 .

As a result we get

$$P^{(n-2)} \cdots P^{(1)} A = \tilde{L}_1^{-1} \cdots L_{n-1}^{-1} U = \tilde{L} U. \quad (5.6)$$

This means that we can again form a matrix L just as before, except that every time we pivot, we need to update the columns of L that have already been computed.

Exercise 5.12. If we write equation (5.6) as $PA = LU$, we get $A = P^{-1}LU$. Can you come up with a simple formula for P^{-1} in terms of just P ? Hint: each $P^{(i)}$ is symmetric and its own inverse; see the exercise above.

Exercise 5.13. Earlier, you saw that 2D BVP (section 4.2.2.2) give rise to a certain kind of matrix. We stated, without proof, that for these matrices pivoting is not needed. We can now formally prove this, focusing on the crucial property of *diagonal dominance*:

$$\forall_i a_{ii} \geq \sum_{j \neq i} |a_{ij}|.$$

Assume that a matrix A satisfies $\forall_{j \neq i}: a_{ij} \leq 0$. Show that the matrix is diagonally dominant iff there are vectors $u, v \geq 0$ (meaning that each component is nonnegative) such that $Au = v$.

Show that, after eliminating a variable, for the remaining matrix \tilde{A} there are again vectors $\tilde{u}, \tilde{v} \geq 0$ such that $\tilde{A}\tilde{u} = \tilde{v}$.

Now finish the argument that (partial) pivoting is not necessary if A is symmetric and diagonally dominant. (One can actually prove that pivoting is not necessary for any *symmetric positive definite (SPD)* matrix, and diagonal dominance is a stronger condition than SPD-ness.)

5.3.5 Solving the system

Now that we have a factorization $A = LU$, we can use this to solve the linear system $Ax = b$. If we introduce a temporary vector $y = Ux$, then we see this takes two steps:

$$Ly = b, \quad Ux = z.$$

The first part, $Ly = b$ is called the ‘lower triangular solve’, since it involves the lower triangular matrix L .

$$\begin{pmatrix} 1 & & & \emptyset \\ \ell_{21} & 1 & & \\ \ell_{31} & \ell_{32} & 1 & \\ \vdots & & \ddots & \\ \ell_{n1} & \ell_{n2} & \dots & 1 \end{pmatrix} \begin{pmatrix} y_1 \\ y_2 \\ \vdots \\ y_n \end{pmatrix} = \begin{pmatrix} b_1 \\ b_2 \\ \vdots \\ b_n \end{pmatrix}$$

In the first row, you see that $y_1 = b_1$. Then, in the second row $\ell_{21}y_1 + y_2 = b_2$, so $y_2 = b_2 - \ell_{21}y_1$. You can imagine how this continues: in every i -th row you can compute y_i from the previous y -values:

$$y_i = b_i - \sum_{j < i} \ell_{ij}y_j.$$

Since we compute y_i in increasing order, this is also known as the forward substitution, forward solve, or forward sweep.

The second half of the solution process, the upper triangular solve, backward substitution, or backward sweep, computes x from $Ux = y$:

$$\begin{pmatrix} u_{11} & u_{12} & \dots & u_{1n} \\ u_{22} & \dots & u_{2n} \\ \ddots & & \vdots \\ \emptyset & & u_{nn} \end{pmatrix} \begin{pmatrix} x_1 \\ x_2 \\ \vdots \\ x_n \end{pmatrix} = \begin{pmatrix} y_1 \\ y_2 \\ \vdots \\ y_n \end{pmatrix}$$

Now we look at the last line, which immediately tells us that $x_n = u_{nn}^{-1}y_n$. From this, the line before the last states $u_{n-1n-1}x_{n-1} + u_{n-1n}x_n = y_{n-1}$, which gives $x_{n-1} = u_{n-1n-1}^{-1}(y_{n-1} - u_{n-1n}x_n)$. In general, we can compute

$$x_i = u_{ii}^{-1}(y_i - \sum_{j > i} u_{ij}y_j)$$

for decreasing values of i .

Exercise 5.14. In the backward sweep you had to divide by the numbers u_{ii} . That is not possible if any of them are zero. Relate this problem back to the above discussion.

5.3.6 Complexity

In the beginning of this chapter, we indicated that not every method for solving a linear system takes the same number of operations. Let us therefore take a closer look at the complexity², that is, the number of operations as function of the problem size, of the use of an LU factorization in solving the linear system.

The complexity of solving the linear system, given the LU factorization, is easy to compute. Looking at the lower and upper triangular part together, you see that you perform a multiplication with all off-diagonal elements (that is, elements ℓ_{ij} or u_{ij} with $i \neq j$). Furthermore, the upper triangular solve involves divisions by the u_{ii} elements. Now, division operations are in general much more expensive than multiplications, so in this case you would compute the values $1/u_{ii}$, and store them instead.

2. See appendix A.2 for an explanation of complexity.

Exercise 5.15. Take a look at the factorization algorithm, and argue that storing the reciprocals of the pivots does not add to the computational complexity.

Summing up, you see that, on a system of size $n \times n$, you perform n^2 multiplications and roughly the same number of additions. This is the same complexity as of a simple matrix-vector multiplication, that is, of computing Ax given A and x .

The complexity of computing the LU factorization is a bit more involved to compute. Refer to the algorithm in section 5.3.1. You see that in the k -th step two things happen: the computation of the multipliers, and the updating of the rows. There are $n - k$ multipliers to be computed, each of which involve a division. After that, the update takes $(n - k)^2$ additions and multiplications. If we ignore the divisions for now, because there are fewer of them, we find that the LU factorization takes $\sum_{k=1}^{n-1} 2(n - k)^2$ operations. If we number the terms in this sum in the reverse order, we find

$$\#ops = \sum_{k=1}^{n-1} 2k^2.$$

Since we can approximate a sum by an integral, we find that this is $2/3n^3$ plus some lower order terms. This is of a higher order than solving the linear system: as the system size grows, the cost of constructing the LU factorization completely dominates.

5.3.7 Block algorithms

Often, matrices have a natural block structure, such as in the case of two-dimensional BVPs; section 4.2.2.2. Many linear algebra operations can be formulated in terms of these blocks. This can have several advantages over the traditional scalar view of matrices. For instance, it improves *cache blocking* (section 1.6.7); it also facilitates scheduling linear algebra algorithms on *multicore* architectures (section 6.10).

For block algorithms we write a matrix as

$$A = \begin{pmatrix} A_{11} & \dots & A_{1N} \\ \vdots & & \vdots \\ A_{M1} & \dots & A_{MN} \end{pmatrix}$$

where M, N are the block dimensions, that is, the dimension expressed in terms of the subblocks. Usually, we choose the blocks such that $M = N$ and the diagonal blocks are square.

As a simple example, consider the matrix-vector product $y = Ax$, expressed in block terms.

$$\begin{pmatrix} Y_1 \\ \vdots \\ Y_M \end{pmatrix} = \begin{pmatrix} A_{11} & \dots & A_{1M} \\ \vdots & & \vdots \\ A_{M1} & \dots & A_{MM} \end{pmatrix} \begin{pmatrix} X_1 \\ \vdots \\ X_M \end{pmatrix}$$

To see that the block algorithm computes the same result as the old scalar algorithm, we look at a component Y_{ik} , that is the k -th scalar component of the i -th block. First,

$$Y_i = \sum_j A_{ij} X_j$$

so

$$Y_{i_k} = \left(\sum_j A_{ij} X_j \right)_k = \sum_j (A_{ij} X_j)_k = \sum_j \sum_\ell A_{ijk\ell} X_{j\ell}$$

which is the product of the k -th row of the i -th blockrow of A with the whole of X .

A more interesting algorithm is the block version of the LU factorization. The algorithm (5.3) then becomes

```
(LU factorization):
for k = 1, n - 1:
    for i = k + 1 to n:
         $A_{ik} \leftarrow A_{ik} A_{kk}^{-1}$ 
        for j = k + 1 to n:
             $A_{ij} \leftarrow A_{ij} - A_{ik} \cdot A_{kj}$ 
```

(5.7)

which mostly differs from the earlier algorithm in that the division by a_{kk} has been replaced by a multiplication by A_{kk}^{-1} . Also, the U factor will now have pivot blocks, rather than pivot elements, on the diagonal, so U is only ‘block upper triangular’, and not strictly upper triangular.

Exercise 5.16. We would like to show that the block algorithm here again computes the same result as the scalar one. Doing so by looking explicitly at the computed elements is cumbersome, so we take another approach. First, recall from section 5.3.3 that LU factorizations are unique: if $A = L_1 U_1 = L_2 U_2$ and L_1, L_2 have unit diagonal, then $L_1 = L_2, U_1 = U_2$.

Next, consider the computation of A_{kk}^{-1} . Show that this can be done easily by first computing an LU factorization of A_{kk} . Now use this to show that the block LU factorization can give L and U factors that are strictly triangular. The uniqueness of LU factorizations then proves that the block algorithm computes the scalar result.

5.4 Sparse matrices

In section 4.2.2.2 you saw that the discretization of BVPs (and IBVPs) may give rise to sparse matrices. Since such a matrix has N^2 elements but only $O(N)$ nonzeros, it would be a big waste of space to store this as a two-dimensional array. Additionally, we want to avoid operating on zero elements.

In this section we will explore efficient storage schemes for sparse matrices, and the form that familiar linear algebra operations take when using sparse storage.

5.4.1 Storage of sparse matrices

It is pointless to look for an exact definition of *sparse matrix*, but an operational definition is that a matrix is called ‘sparse’ if there are enough zeros to make specialized storage feasible. We will discuss here briefly the most popular storage schemes for sparse matrices. Since a matrix is no longer stored as a simple 2-dimensional array, algorithms using such storage schemes need to be rewritten too.

5.4.1.1 Diagonal storage

In section 4.2.2.1 you have seen examples of sparse matrices that were banded. In fact, their nonzero elements are located precisely on a number of subdiagonals. For such a matrix, a specialized storage scheme is possible.

Let us take as an example the matrix of the one-dimensional BVP (section 4.2.2.1). Its elements are located on three subdiagonals: the main diagonal and the first super and subdiagonal. The idea of *storage by diagonals* or *diagonal storage* is to store the diagonals consecutively in memory. The most economical storage scheme for such a matrix would store the $2n - 2$ elements consecutively. However, for various reasons it is more convenient to waste a few storage locations, as shown in figure 5.1.




Figure 5.1: Diagonal storage of a banded matrix

Thus, for a matrix with size $n \times n$ and a *bandwidth* p , we need a rectangular array of size $n \times p$ to store the matrix. The matrix of equation (4.9) would then be stored as

$$\begin{matrix} * & 2 & -1 \\ -1 & 2 & -1 \\ \vdots & \vdots & \vdots \\ -1 & 2 & * \end{matrix} \quad (5.8)$$

where the stars indicate array elements that do not correspond to matrix elements: they are the triangles in the top left and bottom right in figure 5.1.

Of course, now we have to wonder about the conversion between array elements $A(i, j)$ and matrix elements A_{ij} . This is easiest done in the Fortran language. If we allocate the array with

```
dimension A(n, -1:1)
```

then the main diagonal A_{ii} is stored in $A(*, 0)$. For instance, $A(1, 0) \sim A_{11}$. The next location in the same row of the matrix A , $A(1, 1) \sim A_{12}$. It is easy to see that together we have the conversion

$$A(i, j) \sim A_{i,i+j}. \quad (5.9)$$

Exercise 5.17. What is the reverse conversion, that is, what array location $A(?, ?)$ does the matrix element A_{ij} correspond to?

Exercise 5.18. If you are a C programmer, derive the conversion between matrix elements A_{ij} and array elements $A[i][j]$.

If we apply this scheme to the matrix of the two-dimensional BVP (section 4.2.2.2), it becomes wasteful, since we would be storing many zeros that exist inside the band. Therefore, we refine this scheme by storing only the nonzero diagonals: if the matrix has p nonzero diagonals, we need an $n \times p$ array. For the matrix of equation (4.14) this means:

*	*	4	-1	-1
:	:	4	-1	-1
:	-1	4	-1	-1
-1	-1	4	-1	-1
:	:	:	:	:
-1	-1	4	*	*

Of course, we need an additional integer array telling us the locations of these nonzero diagonals.

In the preceding examples, the matrices had an equal number of nonzero diagonals above and below the main diagonal. In general this need not be true. For this we introduce the concepts of

- *left halfbandwidth*: if A has a left halfbandwidth of p then $A_{ij} = 0$ for $i > j + p$, and
- *right halfbandwidth*: if A has a right halfbandwidth of p then $A_{ij} = 0$ for $j > i + p$.

5.4.1.2 Operations on diagonal storage

The most important operation on sparse matrices is the matrix-vector product. With a matrix stored by diagonals, as described above, it is still possible to perform the ordinary rowwise or columnwise product using the conversion formula (5.9)³. However, with a small bandwidth, this gives short vector lengths and relatively high loop overhead, so it will not be efficient. It is possible do to much better than that.

If we look at how the matrix elements are used in the matrix-vector product, we see that the main diagonal is used as

$$y_i \leftarrow y_i + A_{ii}x_i,$$

the first superdiagonal is used as

$$y_i \leftarrow y_i + A_{ii+1}x_{i+1} \quad \text{for } i < n,$$

and the first subdiagonal as

$$y_i \leftarrow y_i + A_{ii-1}x_{i-1} \quad \text{for } i > 1.$$

In other words, the whole matrix-vector product can be executed in just three vector operations of length n (or $n - 1$), instead of n inner products of length 3 (or 2).

3. In fact, this is how Lapack banded routines work.

```

for diag = -diag_left, diag_right
    for loc = max(1,1-diag), min(n,n-diag)
        y(loc) = y(loc) + val(loc,diag) * x(loc+diag)
    end
end

```

Exercise 5.19. Write a routine that computes $y \leftarrow A^t x$ by diagonals. Implement it in your favourite language and test it on a random matrix.

Exercise 5.20. The above code fragment is efficient if the matrix is dense inside the band.

This is not the case for, for instance, the matrix of two-dimensional BVPs; see section 4.2.2.2 and in particular equation (4.14). Write code for the matrix-vector product by diagonals that only uses the nonzero diagonals.

Exercise 5.21. Multiplying matrices is harder than multiplying a matrix times a vector. If matrix A has left and halfbandwidth p_A, q_Q , and matrix B has p_B, q_B , what are the left and right halfbandwidth of $C = AB$? Assuming that an array of sufficient size has been allocated for C , write a routine that computes $C \leftarrow AB$.

5.4.1.3 Compressed row storage

If we have a sparse matrix that does not have a simple band structure, or where the number of nonzero diagonals becomes impractically large, we use the more general Compressed Row Storage (CRS) scheme. As the name indicates, this scheme is based on compressing all rows, eliminating the zeros; see figure 5.2. Since this loses the information what columns the nonzeros originally came from, we have to store this




Figure 5.2: Compressing a row of a sparse matrix in the CRS format

explicitly. Consider an example of a sparse matrix:

$$A = \begin{pmatrix} 10 & 0 & 0 & 0 & -2 & 0 \\ 3 & 9 & 0 & 0 & 0 & 3 \\ 0 & 7 & 8 & 7 & 0 & 0 \\ 3 & 0 & 8 & 7 & 5 & 0 \\ 0 & 8 & 0 & 9 & 9 & 13 \\ 0 & 4 & 0 & 0 & 2 & -1 \end{pmatrix}. \quad (5.10)$$

After compressing all rows, we store all nonzeros in a single real array. The column indices are similarly stored in an integer array, and we store pointers to where the columns start. Using 0-based indexing this gives:

val	10	-2	3	9	3	7	8	7	3 ... 9	13	4	2	-1
col_ind	0	4	0	1	5	1	2	3	0 ... 4	5	1	4	5
row_ptr	0	2	5	8	12	16	19						.

A simple variant of CRS is *Compressed Column Storage (CCS)* where the elements in columns are stored contiguously. This is also known as the *Harwell-Boeing matrix format* [35]. Another storage scheme you may come across is *coordinate storage*, where the matrix is stored as a list of triplets $\langle i, j, a_{ij} \rangle$. The popular *Matrix Market* website [1] uses a variant of this scheme.

5.4.1.4 Algorithms on compressed row storage

In this section we will look at the form some algorithms take in CRS.

The most common operation is the matrix-vector product:

```
for (row=0; row<nrows; row++) {
    s = 0;
    for (icol=ptr[row]; icol<ptr[row+1]; icol++) {
        int col = ind[icol];
        s += a[icol] * x[col];
    }
    y[row] = s;
}
```

You recognize the standard matrix-vector product algorithm for $y = Ax$, where the inner product is taken of each row A_{i*} and the input vector x . However, note that the inner loop no longer has the column number as index, but rather the location where that number is to be found. This extra step is known as *indirect addressing*.

Now, how about if you wanted to compute the product $y = A^t x$? In that case you need rows of A^t , or, equivalently, columns of A . Finding arbitrary columns of A is hard, requiring lots of searching, so you may think that this algorithm is correspondingly hard to compute. Fortunately, that is not true.

If we exchange the i and j loop in the standard algorithm for $y = Ax$, we get

$$\begin{array}{ll} y \leftarrow 0 & y \leftarrow 0 \\ \text{for } i: & \Rightarrow \quad \text{for } j: \\ \quad \text{for } j: & \quad \text{for } i: \\ \quad \quad y_i \leftarrow y_i + a_{ij}x_j & \quad \quad y_i \leftarrow y_i + a_{ji}x_j \end{array}$$

We see that in the second variant, columns of A are accessed, rather than rows. This means that we can use the second algorithm for computing the $A^t x$ product by rows.

Exercise 5.22. Write out the code for the transpose product $y = A^t x$ where A is stored in CRS format. Write a simple test program and confirm that your code computes the right thing.

Exercise 5.23. What if you need access to both rows and columns at the same time? Implement an algorithm that tests whether a matrix stored in CRS format is symmetric. Hint: keep an array of pointers, one for each row, that keeps track of how far you have progressed in that row.

Exercise 5.24. The operations described so far are fairly simple, in that they never make changes to the sparsity structure of the matrix. The CRS format, as described above, does not allow you to add new nonzeros to the matrix, but it is not hard to make an extension that does allow it.

Let numbers $p_i, i = 1 \dots n$, describing the number of nonzeros in the i -th row, be given. Design an extension to CRS that gives each row space for q extra elements. Implement this scheme and test it: construct a matrix with p_i nonzeros in the i -th row, and check the correctness of the matrix-vector product before and after adding new elements, up to q elements per row.

Now assume that the matrix will never have more than a total of qn nonzeros. Alter your code so that it can deal with starting with an empty matrix, and gradually adding nonzeros in random places. Again, check the correctness.

We will revisit the transpose product algorithm in section 6.4.3 in the context of shared memory parallelism.

5.4.2 Sparse matrices and graph theory

Many arguments regarding sparse matrices can be formulated in terms of graph theory. To see why this can be done, consider a matrix A of size n and observe that we can define a graph $\langle E, V \rangle$ by $V = \{1, \dots, n\}$, $E = \{(i, j) : a_{ij} \neq 0\}$. This is called the *adjacency graph* of the matrix. For simplicity, we assume that A has a nonzero diagonal. If necessary, we can attach weights to this graph, defined by $w_{ij} = a_{ij}$. The graph is then denoted $\langle E, V, W \rangle$. (If you are not familiar with the basics of graph theory, see appendix A.5.)

Graph properties now correspond to matrix properties; for instance, the degree of the graph is the maximum number of nonzeros per row, not counting the diagonal element. As another example, if the graph of the matrix is an *undirected graph*, this means that $a_{ij} \neq 0 \Leftrightarrow a_{ji} \neq 0$. We call such a matrix *structurally symmetric*: it is not truly symmetric in the sense that $\forall_{ij} : a_{ij} = a_{ji}$, but every nonzero in the upper triangle corresponds to one in the lower triangle and vice versa.

One advantage of considering the graph of a matrix is that graph properties do not depend on how we order the nodes, that is, they are invariant under permutation of the matrix.

Exercise 5.25. Let us take a look at what happens with a matrix A when the nodes of its graph $G = \langle V, E, W \rangle$ are renumbered. As a simple example, we number the nodes backwards; that is, with n the number of nodes, we map node i to $n+1-i$. Correspondingly, we find a new graph $G' = \langle V, E', W' \rangle$ where

$$(i, j) \in E' \Leftrightarrow (n+1-i, n+1-j) \in E, \quad w'_{ij} = w_{n+1-i, n+1-j}.$$

What does this renumbering imply for the matrix A' that corresponds to G' ? If you exchange the labels i, j on two nodes, what is the effect on the matrix A ?

Some graph properties can be hard to see from the sparsity pattern of a matrix, but are easier deduced from the graph.

Exercise 5.26. Let A be the tridiagonal matrix of the one-dimensional BVP (see section 4.2.2.1) of size n with n odd. What does the graph of A look like? Consider the permutation that results from putting the nodes in the following sequence: $1, 3, 5, \dots, n, 2, 4, 6, \dots, n-1$. What does the sparsity pattern of the permuted matrix look like? Renumbering strategies such as this will be discussed in more detail in section 6.7.2.

Exercise 5.27. Take again the matrix from the previous exercise, and zero the offdiagonal elements closest to the ‘middle’ of the matrix: let $a_{(n+1)/2, (n+1)/2+1} = a_{(n+1)/2+1, (n+1)/2} = 0$. Describe what that does to the graph of A . Such a graph is called *reducible*. Now apply the permutation of the previous exercise and sketch the resulting sparsity pattern. Note that the reducibility of the graph is now harder to read from the sparsity pattern.

5.4.3 LU factorizations of sparse matrices

In section 4.2.2.1 the one-dimensional BVP led to a linear system with a tridiagonal coefficient matrix. If we do one step of Gaussian elimination, the only element that needs to be eliminated is in the second row:

$$\left(\begin{array}{cccccc} 2 & -1 & 0 & \dots & & \\ -1 & 2 & -1 & & & \\ 0 & -1 & 2 & -1 & & \\ \ddots & \ddots & \ddots & \ddots & & \end{array} \right) \Rightarrow \left(\begin{array}{c|cccc} 2 & -1 & 0 & \dots & \\ 0 & 2 - \frac{1}{2} & -1 & & \\ 0 & -1 & 2 & -1 & \\ \ddots & \ddots & \ddots & \ddots & \ddots \end{array} \right)$$

There are two important observations to be made: one is that this elimination step does not change any zero elements to nonzero. The other observation is that the part of the matrix that is left to be eliminated is again tridiagonal. Inductively, during the elimination no zero elements change to nonzero: the sparsity pattern of $L + U$ is the same as of A , and so the factorization takes the same amount of space to store as the matrix.

The case of tridiagonal matrices is unfortunately not typical, as we will shortly see in the case of two-dimensional problems. But first we will extend the discussion on graph theory of section 5.4.2 to factorizations.

5.4.3.1 Graph theory of sparse LU factorization

Graph theory is often useful when discussing the factorization of a sparse matrix. Let us investigate what eliminating the first unknown (or sweeping the first column) means in graph theoretic terms. We are assuming a structurally symmetric matrix.

We consider eliminating an unknown as a process that takes a graph $G = \langle V, E \rangle$ and turns it into a graph $G' = \langle V', E' \rangle$. The relation between these graphs is first that a vertex, say k , has been removed from the vertices: $k \notin V'$, $V' \cup \{k\} = V$.

The relationship between E and E' is more complicated. In the Gaussian elimination algorithm the result of eliminating variable k is that the statement

$$a_{ij} \leftarrow a_{ij} - a_{ik}a_{kk}^{-1}a_{kj}$$

is executed for all $i, j \neq k$. If $a_{ij} \neq 0$ originally, then its value is merely altered. In case $a_{ij} = 0$ in the original matrix, there will be a nonzero element, termed a *fill-in* element, after the k unknown is eliminated:




Figure 5.3: Eliminating a vertex introduces a new edge in the quotient graph

in E there was no edge (i, j) , and this edge is present in E' . This is illustrated in figure 5.3.

Summarizing, eliminating an unknown gives a graph that has one vertex less, and that has edges for all i, j such that there were edges between i or j and the eliminated variable k .

Exercise 5.28. Go back to exercise 5.26. Use a graph argument to determine the sparsity pattern after the odd variables have been eliminated.

Exercise 5.29. Prove the generalization of the above argument about eliminating a single vertex. Let $I \subset V$ be any set of vertices, and let J be the vertices connected to I :

$$J \cap I = \emptyset, \quad \forall_{i \in I} \exists_{j \in J}: (i, j) \in E.$$

Now show that eliminating the variables in I leads to a graph $\langle V', E' \rangle$ where all nodes in J are connected in the remaining graph, if there was a path between them through I :

$$\forall_{j_1, j_2 \in J}: \text{there is a path } j_1 \rightarrow j_2 \text{ through } I \text{ in } E \Rightarrow (j_1, j_2) \in E'.$$

5.4.3.2 Fill-in

We now return to the factorization of the matrix from two-dimensional problems. We write such matrices of size $N \times N$ as block matrices with block dimension n , each block being of size n . (Refresher question:




Figure 5.4: Creation of fill-in connection in the matrix graph

where do these blocks come from?) Now, in the first elimination step we need to zero two elements, a_{21} and $a_{n+1,1}$.

$$\left(\begin{array}{cccc|cc} 4 & -1 & 0 & \dots & -1 & -1 \\ -1 & 4 & -1 & 0 & \dots & 0 & -1 \\ \ddots & \ddots & \ddots & & \ddots & & \\ -1 & 0 & \dots & & 4 & -1 & -1 \\ 0 & -1 & 0 & \dots & -1 & 4 & -1 \end{array} \right) \Rightarrow \left(\begin{array}{c|ccccc|cc} 4 & -1 & 0 & \dots & -1 & & \\ \hline 4 & -1/4 & -1 & 0 & \dots & -1/4 & -1 \\ \ddots & \ddots & \ddots & & \ddots & & \\ -1/4 & -1 & 0 & & 4 & -1 & -1 \\ -1 & 0 & & & -1 & 4 & -1 \end{array} \right)$$

You see that eliminating a_{21} and $a_{n+1,1}$ causes two *fill* elements to appear: in the original matrix $a_{2,n+1}$ and $a_{n+1,2}$ are zero, but in the modified matrix these locations are nonzero. We define *fill locations* as locations (i, j) where $a_{ij} = 0$, but $(L + U)_{ij} \neq 0$.

Clearly the matrix fills in during factorization. With a little imagination you can also see that every element in the band outside the first diagonal block will fill in. However, using the graph approach of section 5.4.3.1 it becomes easy to visualize the fill-in connections that are created.

In figure 5.4 this is illustrated for the graph of the 2d BVP example. (The edges corresponding to diagonal elements have not been pictured here.) Each variable in the first row that is eliminated creates connections between the next variable and the second row, and between variables in the second row. Inductively you see that after the first row is eliminated the second row is fully connected. (Connect this to exercise 5.29.)

Exercise 5.30. Finish the argument. What does the fact that variables in the second row are fully connected imply for the matrix structure? Sketch in a figure what happens after the first variable in the second row is eliminated.

Exercise 5.31. The LAPACK software for dense linear algebra has an LU factorization routine that overwrites the input matrix with the factors. Above you saw that is possible since the columns of L are generated precisely as the columns of A are eliminated. Why is such an algorithm not possible if the matrix is stored in sparse format?

5.4.3.3 Fill-in estimates

In the above example you saw that the factorization of a sparse matrix can take much more space than the matrix itself, but still less than storing an entire square array of size the matrix dimension. We will now give some bounds for the *space complexity* of the factorization, that is, the amount of space needed to execute the factorization algorithm.

Exercise 5.32. Prove the following statements.

1. Assume that the matrix A has a *halfbandwidth* p , that is, $a_{ij} = 0$ if $|i - j| > p$. Show that, after a factorization without pivoting, $L + U$ has the same halfbandwidth.
2. Show that, after a factorization with partial pivoting, L has a left halfbandwidth of p , whereas U has a right halfbandwidth of $2p$.
3. Assuming no pivoting, show that the fill-in can be characterized as follows:
Consider row i . Let j_{\min} be the leftmost nonzero in row i , that is $a_{ij} \neq 0$ for $j < j_{\min}$. Then there will be no fill-in in row i to the left of column j_{\min} . Likewise, if i_{\min} is the topmost nonzero in column j , there will be no fill-in in column j above row i_{\min} .

As a result, L and U have a ‘skyline’ profile. Given a sparse matrix, it is now easy to allocate enough storage to fit a factorization without pivoting: this is known as *skyline storage*.

This exercise shows that we can allocate enough storage for the factorization of a banded matrix:

- for the factorization without pivoting of a matrix with bandwidth p , an array of size $N \times p$ suffices;
- the factorization with partial pivoting of a matrix left halfbandwidth p and right halfbandwidth q can be stored in $N \times (p + 2q + 1)$.
- A skyline profile, sufficient for storing the factorization, can be constructed based on the specific matrix.

We can apply this estimate to the matrix from the two-dimensional BVP, section 4.2.2.2.

Exercise 5.33. Show that in equation (4.14) the original matrix has $O(N) = O(n^2)$ nonzero elements, $O(N^2) = O(n^4)$ elements in total, and the factorization has $O(nN) = O(n^3) = O(N^{3/2})$ nonzeros.

These estimates show that the storage required for an *LU* factorization can be more than what is required for A , and the difference is not a constant factor, but related to the matrix size. Without proof we state that the inverses of the kind of sparse matrices you have seen so far are fully dense, so storing them takes even more. This is an important reason that solving linear systems $Ax = y$ is not done in practice by computing A^{-1} and multiplying $x = A^{-1}y$. (Numerical stability is another reason that this is not done.) The fact that even a factorization can take a lot of space is one reason for considering iterative methods, as we will do in section 5.5.

Above, you saw that the factorization of a dense matrix of size $n \times n$ takes $O(n^3)$ operations. How is this for a sparse matrix? Let us consider the case of a matrix with halfbandwidth p , and assume that the original matrix is dense in that band. The pivot element a_{11} is used to zero p elements in the first column, and for

each the first row is added to that row, involving p multiplications and additions. In sum, we find that the number of operations is roughly

$$\sum_{i=1}^n p^2 = p^2 \cdot n$$

plus or minus lower order terms.

Exercise 5.34. The assumption of a band that is initially dense is not true for the matrix of a two-dimensional BVP. Why does the above estimate still hold, up to some lower order terms?

In exercise 5.32 above you derived an estimate for the amount of fill-in that is easy to apply. However, it can be a considerable overestimate. It is desirable to compute or estimate the amount of fill-in with less work than doing the actual factorization. We will now sketch an algorithm for finding the exact number of nonzeros in $L + U$, with a cost that is linear in this number. We will do this in the (structurally) symmetric case. The crucial observation is the following. Suppose column i has more than one nonzero below the diagonal:

$$\begin{pmatrix} \ddots & & & \\ & a_{ii} & a_{ij} & a_{ik} \\ & & \ddots & \\ & a_{ji} & a_{jj} & \\ & & & \ddots \\ a_{ki} & ?a_{kj}? & & a_{kk} \end{pmatrix}$$

Eliminating a_{ki} in the i -th step causes an update of a_{kj} , or a fill-in element if originally $a_{kj} = 0$. However, we can infer the existence of this nonzero value: eliminating a_{ji} causes a fill-in element in location (j, k) , and we know that structural symmetry is preserved. In other words, if we are only counting nonzeros, it is enough to look at the effects of eliminating the (j, i) location, or in general the first nonzero below the pivot. Following this argument through, we only need to record the nonzeros in one row per pivot, and the entire process has a complexity linear in the number of nonzeros in the factorization.

5.4.3.4 Fill-in reduction

Graph properties of a matrix, such as degree and diameter, are invariant under renumbering the variables. Other properties, such as fill-in during a factorization, are affected by renumbering. In fact, it is worthwhile investigating whether it is possible to reduce the amount of fill-in by renumbering the nodes of the matrix graph, or equivalently, by applying a *permutation* to the linear system.

Exercise 5.35. Consider the ‘arrow’ matrix with nonzeros only in the first row and column and on the diagonal:

$$\begin{pmatrix} * & * & \cdots & * \\ * & * & & \emptyset \\ \vdots & & \ddots & \\ * & \emptyset & & * \end{pmatrix}$$

What is the number of nonzeros in the matrix, and in the factorization, assuming that no addition ever results in zero? Can you find a symmetric permutation of the variables of the problem such that the new matrix has no fill-in?

This example is not typical, but it is true that fill-in estimates can sometimes be improved upon by clever permuting of the matrix (see for instance section 6.7.1). Even with this, as a rule the statement holds that an *LU* factorization of a sparse matrix takes considerably more space than the matrix itself. This is one of the motivating factors for the iterative methods in the next section.

5.5 Iterative methods

Gaussian elimination, the use of an *LU* factorization, is a simple way to find the solution of a linear system, but as we saw above, in the sort of problems that come from discretized PDEs, it can create a lot of fill-in. In this section we will look at a completely different approach, where the solution of the system is found by a sequence of approximations.

The computational scheme looks, very roughly, like:

$$\begin{cases} \text{Choose any starting vector } x_0 \text{ and repeat for } i \geq 0: \\ x_{i+1} = Bx_i + c \\ \text{until some stopping test is satisfied.} \end{cases}$$

The important feature here is that no systems are solved with the original coefficient matrix; instead, every iteration involves a matrix-vector multiplication or a solution of a much simpler system. Thus we have replaced a complicated operation, constructing an *LU* factorization and solving a system with it, by a repeated simpler and cheaper operation. This makes iterative methods easier to code, and potentially more efficient.

Let us consider a simple example to motivate the precise definition of the iterative methods. Suppose we want to solve the system

$$\begin{pmatrix} 10 & 0 & 1 \\ 1/2 & 7 & 1 \\ 1 & 0 & 6 \end{pmatrix} \begin{pmatrix} x_1 \\ x_2 \\ x_3 \end{pmatrix} = \begin{pmatrix} 21 \\ 9 \\ 8 \end{pmatrix}$$

which has the solution $(2, 1, 1)$. Suppose you know (for example, from physical considerations) that solution components are roughly the same size. Observe the dominant size of the diagonal, then, to decide that

$$\begin{pmatrix} 10 & & \\ & 7 & \\ & & 6 \end{pmatrix} \begin{pmatrix} x_1 \\ x_2 \\ x_3 \end{pmatrix} = \begin{pmatrix} 21 \\ 9 \\ 8 \end{pmatrix}$$

might be a good approximation. This has the solution $(2.1, 9/7, 8/6)$. Clearly, solving a system that only involves the diagonal of the original system is both easy to do, and, at least in this case, fairly accurate.

Another approximation to the original system would be to use the lower triangle. The system

$$\begin{pmatrix} 10 & & \\ 1/2 & 7 & \\ 1 & 0 & 6 \end{pmatrix} \begin{pmatrix} x_1 \\ x_2 \\ x_3 \end{pmatrix} = \begin{pmatrix} 21 \\ 9 \\ 8 \end{pmatrix}$$

has the solution $(2.1, 7.95/7, 5.9/6)$. Solving triangular systems is a bit more work than diagonal systems, but still a lot easier than computing an LU factorization. Also, we have not generated any fill-in in the process of finding this approximate solution.

Thus we see that there are easy to compute ways of getting reasonably close to the solution. Can we somehow repeat this trick?

Formulated a bit more abstractly, what we did was instead of solving $Ax = b$ we solved $L\tilde{x} = b$. Now define Δx as the distance from the true solution: $\tilde{x} = x + \Delta x$. This gives $A\Delta x = A\tilde{x} - b \equiv r$, where r is the *residual*. Next we solve again $L\Delta x = r$ and update $\tilde{x} = \tilde{x} - \Delta x$.

iteration	1	2	3
x_1	2.1000	2.0017	2.000028
x_2	1.1357	1.0023	1.000038
x_3	0.9833	0.9997	0.999995

In this case we get two decimals per iteration, which is not typical.

It is now clear why iterative methods can be attractive. Solving a system by Gaussian elimination takes $O(n^3)$ operations, as shown above. A single iteration in a scheme as the above takes $O(n^2)$ operations if the matrix is dense, and possibly as low as $O(n)$ for a sparse matrix. If the number of iterations is low, this makes iterative methods competitive.

Exercise 5.36. When comparing iterative and direct methods, the flop count is not the only relevant measure. Outline some issues relating to the efficiency of the code in both cases. Also compare the cases of solving a single linear system and solving multiple.

5.5.1 Abstract presentation

It is time to do a formal presentation of the iterative scheme of the above example. Suppose we want to solve $Ax = b$, and a direct solution is too expensive, but multiplying by A is feasible. Suppose furthermore that we have a matrix $K \approx A$ such that solving $Kx = b$ can be done cheaply.

Instead of solving $Ax = b$ we solve $Kx = b$, and define x_0 as the solution: $Kx_0 = b$. This leaves us with an error $e_0 = x_0 - x$, for which we have the equation $A(x_0 - e_0) = b$ or $Ae_0 = Ax_0 - b$. We call $r_0 \equiv Ax_0 - b$ the *residual*; the error then satisfies $Ae_0 = r_0$.

If we could solve the error from the equation $Ae_0 = r_0$, we would be done: the true solution is then found as $x = x_0 - e_0$. However, since solving with A was too expensive the last time, we can not do so this time either, so we determine the error correction approximately. We solve $K\tilde{e}_0 = r_0$ and set $x_1 := x_0 - \tilde{e}_0$; the story can now continue with $e_1 = x_1 - x$, $r_1 = Ax_1 - b$, $K\tilde{e}_1 = r_1$, $x_2 = x_1 - \tilde{e}_1$, et cetera.

The iteration scheme is then:

Let x_0 be given

For $i \geq 0$:

- let $r_i = Ax_i - b$
- compute e_i from $Ke_i = r_i$
- update $x_{i+1} = x_i - e_i$

The scheme we have given here is called *stationary iteration*, where every update is performed the same way, without any dependence on the iteration number. It has a simple analysis, but unfortunately limited applicability.

There are several questions we need to answer about iterative schemes:

- Does this scheme always take us to the solution?
- If the scheme converges, how quickly?
- When do we stop iterating?
- How do we choose K ?

We will now devote some attention to these matters, though a full discussion is beyond the scope of this book.

5.5.2 Convergence and error analysis

We start with the question of whether the iterative scheme converges, and how quickly. Consider one iteration step:

$$\begin{aligned} r_1 &= Ax_1 - b = A(x_0 - \tilde{e}_0) - b \\ &= r_0 - AK^{-1}r_0 \\ &= (I - AK^{-1})r_0 \end{aligned} \tag{5.11}$$

Inductively we find $r_n = (I - AK^{-1})^n r_0$, so $r_n \downarrow 0$ if all eigenvalues satisfy $|\lambda(I - AK^{-1})| < 1$.

This last statement gives us both a condition for convergence, by relating K to A , and a geometric convergence rate, if K is close enough.

Exercise 5.37. Derive a similar inductive relation for e_n .

It is hard to determine if the condition $|\lambda(I - AK^{-1})| < 1$ is satisfied by computing the actual eigenvalues. However, sometimes the Gershgorin theorem (appendix A.1.5) gives us enough information.

Exercise 5.38. Consider the matrix A of equation (4.14) that we obtained from discretization of a two-dimensional BVP. Let K be matrix containing the diagonal of A , that is $k_{ii} = a_{ii}$ and $k_{ij} = 0$ for $i \neq j$. Use the Gershgorin theorem to show that $|\lambda(I - AK^{-1})| < 1$.

The argument in this exercise is hard to generalize for more complicated choices of K , such as you will see below. Here we only remark that for certain matrices A , these choices of K will always lead to convergence, with a speed that decreases as the matrix size increases. We will not go into the details beyond stating that for M -matrices (see section 4.2.2.1) these iterative methods converge. For more details on the convergence theory of stationary iterative methods, see [129].

5.5.3 Computational form

Above, in section 5.5.1, we derived stationary iteration as a process that involves multiplying by A and solving with K . However, in some cases a simpler implementation is possible. Consider the case where $A = K - N$, and we know both K and N . Then we write

$$Ax = b \Rightarrow Kx = Nx + b$$

and we observe that x is a fixed point of the iteration

$$Kx_{i+1} = Nx_i + b.$$

It is easy to see that this is a stationary iteration:

$$\begin{aligned} Kx_{i+1} &= Nx_i + b \\ &= Kx_i - Ax_i + b \\ &= Kx_i - r_i \\ \Rightarrow x_{i+1} &= x_i - K^{-1}r_i. \end{aligned}$$

The convergence criterium $|\lambda(I - AK^{-1})| < 1$ (see above) now simplifies to $|\lambda(NK^{-1})| < 1$.

Let us consider some cases. First of all, let $K = D_A$, that is, the matrix containing the diagonal part of A : $k_{ii} = a_{ii}$ and $k_{ij} = 0$ for all $i \neq j$. This is known as the *Jacobi method* method. The iteration scheme becomes

for $k = 1, \dots$ until convergence, do:

for $i = 1 \dots n$:

$$\begin{aligned} // a_{ii}x_i^{(k+1)} &= \sum_{j \neq i} a_{ij}x_j^{(k)} + b_i \text{ becomes:} \\ x_i^{(k+1)} &= a_{ii}^{-1}(\sum_{j \neq i} a_{ij}x_j^{(k)} + b_i) \end{aligned}$$

(Bearing in mind that divisions are relatively costly, section 1.2, we would actually store the a_{ii}^{-1} quantities explicitly, and replace the division by a multiplication.)

This requires us to have one vector x for the current iterate $x^{(k)}$, and one temporary t for the next vector $x^{(k+1)}$. The easiest way to write this is probably:

for $k = 1, \dots$ until convergence, do:

for $i = 1 \dots n$:

$$t_i = a_{ii}^{-1}(-\sum_{j \neq i} a_{ij}x_j + b_i)$$

copy $x \leftarrow t$

For the simple case of a one-dimensional problem this is illustrated in figure 5.5: in each x_i point the values of the two neighbours are combined with the current value to generate a new value. Since the computations in all the x_i points are independent, this can be done in parallel on a parallel computer.

But, you might think, in the sum $\sum_{j \neq i} a_{ij}x_j$ why not use the $x^{(k+1)}$ values for as far as already computed? In terms of the vectors $x^{(k)}$ this means




Figure 5.5: Data movement pattern in the Jacobi iteration on a one-dimensional problem

for $k = 1, \dots$ until convergence, do:

for $i = 1 \dots n$:

$$x_i^{(k+1)} = a_{ii}^{-1}(-\sum_{j < i} a_{ij}x_j^{(k+1)} - \sum_{j > i} a_{ij}x_j^{(k)} + b_i)$$

Surprisingly, the implementation is simpler than of the Jacobi method:

for $k = 1, \dots$ until convergence, do:

for $i = 1 \dots n$:

$$x_i = a_{ii}^{-1}(-\sum_{j \neq i} a_{ij}x_j + b_i)$$

If you write this out as a matrix equation, you see that the newly computed elements $x_i^{(k+1)}$ are multiplied with elements of $D_A + L_A$, and the old elements $x_j^{(k)}$ by U_A , giving

$$(D_A + L_A)x^{(k+1)} = -U_Ax^{(k)} + b$$

which is called the *Gauss-Seidel* method.

For the one-dimensional case, the Gauss-Seidel method is illustrated in figure 5.6; every x_i point still




Figure 5.6: Data movement pattern in the Gauss-Seidel iteration on a one-dimensional problem

combines its neighbours' values, but now the left value is actually from the next outer iteration. Since the computations in the x_i points are now dependent, this type of iteration is not simple to implement on a parallel computer. Some strategies for dealing with this are discussed in section 6.6.

Finally, we can insert a damping parameter into the Gauss-Seidel scheme, giving the *Successive Over-Relaxation (SOR)* method:

for $k = 1, \dots$ until convergence, do:

for $i = 1 \dots n$:

$$x_i^{(k+1)} = \omega a_{ii}^{-1}(-\sum_{j < i} a_{ij}x_j^{(k+1)} - \sum_{j > i} a_{ij}x_j^{(k)} + b_i) + (1 - \omega)x_i^{(k)}$$

Surprisingly for something that looks like an interpolation, the method actually works with value for ω in the range $\omega \in (0, 2)$, the optimal value being larger than 1 [64]. Computing the optimal ω is not simple.

5.5.4 Convergence of the method

We are interested in two questions: firstly whether the iterative method converges at all, and if so, with what speed. The theory behind these questions goes far beyond this book. Above we remarked that convergence can often be guaranteed for M -matrices; with regard to the convergence speed a full analysis is usually only possible in model cases. For the matrices from BVPs, as described in section 4.2.2.2, we state without proof that the smallest eigenvalue of the coefficient matrix is $O(h^2)$. The geometric convergence ratio $|\lambda(I - AK^{-1})|$ derived above can then be shown to be as follows:

- For the Jacobi method, the ratio is $1 - O(h^2)$;
- For the Gauss-Seidel iteration it also is $1 - O(h^2)$, but the method converges twice as fast;
- For the SOR method, the optimal omega can improve the convergence factor to $1 - O(h)$.

5.5.5 Choice of K

The convergence and error analysis above showed that the closer K is to A , the faster the convergence will be. In the initial examples we already saw the diagonal and lower triangular choice for K . We can describe these formally by letting $A = D_A + L_A + U_A$ be a splitting into diagonal, lower triangular, upper triangular part of A . Here are some methods with their traditional names:

- Richardson iteration: $K = \alpha I$.
- Jacobi method: $K = D_A$ (diagonal part),
- Gauss-Seidel method: $K = D_A + L_A$ (lower triangle, including diagonal)
- The SOR method: $K = \omega^{-1}D_A + L_A$
- Symmetric SOR (SSOR) method: $K = (D_A + L_A)D_A^{-1}(D_A + U_A)$.
- Iterative refinement: $K = LU$ where LU is a true factorization of A . In exact arithmetic, solving a system $LUx = y$ gives you the exact solution, so using $K = LU$ in an iterative method would give convergence after one step. In practice, roundoff error will make the solution be inexact, so people will sometimes iterate a few steps to get higher accuracy.

Exercise 5.39. What is the extra cost of a few steps of iterative refinement over a single system solution, assuming a dense system?

Exercise 5.40. The Jacobi iteration for the linear system $Ax = b$ is defined as

$$x_{i+1} = x_i - K^{-1}(Ax_i - b)$$

where K is the diagonal of A . Show that you can transform the linear system (that is, find a different coefficient matrix and right hand side vector that will still have the same solution) so that you can compute the same x_i vectors but with $K = I$, the identity matrix.

What are the implications of this strategy, in terms of storage and operation counts? Are there special implications if A is a sparse matrix?

Suppose A is symmetric. Give a simple example to show that $K^{-1}A$ does not have to be symmetric. Can you come up with a different transformation of the system so that symmetry of the coefficient matrix is preserved and that has the same advantages as the transformation above? You can assume that the matrix has positive diagonal elements.

Exercise 5.41. Show that the transformation of the previous exercise can also be done for the Gauss-Seidel method. Give several reasons why this is not a good idea.

There are many different ways of choosing the preconditioner matrix K . Some of them are defined algebraically, such as the incomplete factorization discussed below. Other choices are inspired by the differential equation. For instance, if the operator is

$$\frac{\delta}{\delta x}(a(x, y)\frac{\delta}{\delta x}u(x, y)) + \frac{\delta}{\delta y}(b(x, y)\frac{\delta}{\delta y}u(x, y)) = f(x, y)$$

then the matrix K could be derived from the operator

$$\frac{\delta}{\delta x}(\tilde{a}(x)\frac{\delta}{\delta x}u(x, y)) + \frac{\delta}{\delta y}(\tilde{b}(y)\frac{\delta}{\delta y}u(x, y)) = f(x, y)$$

for some choices of \tilde{a}, \tilde{b} . The second set of equations is called a *separable problem*, and there are *fast solvers* for them, meaning that they have $O(N \log N)$ time complexity; see [132].

5.5.5.1 Constructing K as an incomplete LU factorization

We briefly mention one other choice of K , which is inspired by Gaussian elimination. As in Gaussian elimination, we let $K = LU$, but now we use an *Incomplete LU (ILU)* factorization. Remember that a regular *LU* factorization is expensive because of the fill-in phenomenon. In an incomplete factorization, we limit the fill-in artificially.

If we write Gauss elimination as

```
for k, i, j:
    a[i, j] = a[i, j] - a[i, k] * a[k, j] / a[k, k]
```

we define an incomplete variant by

```
for k, i, j:
    if a[i, j] not zero:
        a[i, j] = a[i, j] - a[i, k] * a[k, j] / a[k, k]
```

- The resulting factorization is no longer exact: $LU \approx A$, so it is called an Incomplete LU (ILU) factorization.
- An ILU factorization takes much less space than a full factorization: the sparsity of $L + U$ is the same as of A .

The algorithm above is called ‘ILU(0)’, where the zero refers to the fact that absolutely no fill-in is allowed during the incomplete factorization. Other schemes that allow a limited amount of fill-in exist. Much more can be said about this method; we will only remark that for M -matrices this scheme typically gives a converging method [97].

Exercise 5.42. How do operation counts of the matrix-vector product and solving a system with an ILU factorization compare?

You have seen that a full factorization of sparse matrix can need a higher order storage ($N^{3/2}$ for the factorization versus N for the matrix), but that an incomplete factorization takes $O(N)$, just like the matrix. It may therefore come as a surprise that the error matrix $R = A - LU$ is not dense, but itself sparse.

Exercise 5.43. Let A be the matrix of the Poisson equation, LU an incomplete factorization, and $R = A - LU$. Show that R is a bi-diagonal matrix:

- Consider that R consists of those elements that are discarded during the factorization. Where are they located in the matrix?
- Alternatively, write out the sparsity pattern of the product LU and compare that to the sparsity pattern of A .

5.5.5.2 Cost of constructing a preconditioner

In the example of the heat equation (section 4.3) you saw that each time step involves solving a linear system. As an important practical consequence, any setup cost for solving the linear system, such as constructing the preconditioner, will be amortized over the sequence of systems that is to be solved. A similar argument holds in the context of nonlinear equations, a topic that we will not discuss as such. Nonlinear equations are solved by an iterative process such as the *Newton method*, which in its multidimensional form leads to a sequence of linear systems. Although these have different coefficient matrices, it is again possible to amortize setup costs by reusing the preconditioner for a number of Newton steps.

5.5.5.3 Parallel preconditioners

Constructing and using a preconditioner is a balancing act of many considerations: a more accurate preconditioner leads to convergence in fewer iterations, but these iterations can be more expensive; in addition, a more accurate preconditioner can be more costly to construct. In parallel, this story is even more complicated, because certain preconditioners are not very parallel to begin with. Therefore, we may accept a preconditioner that is parallel, but that has a worse iteration count than a serial preconditioner. For more discussion, see section 6.6.

5.5.6 Stopping tests

The next question we need to tackle is when to stop iterating. Above we saw that the error decreases geometrically, so clearly we will never reach the solution exactly, even if that were possible in computer arithmetic. Since we only have this relative convergence behaviour, how do we know when we are close enough?

We would like the error $e_i = x - x_i$ to be small, but measuring this is impossible. Above we observed that $Ae_i = r_i$, so

$$\|e_i\| \leq \|A^{-1}\| \|r_i\| \leq \lambda_{\max}(A^{-1}) \|r_i\|$$

If we know anything about the eigenvalues of A , this gives us a bound on the error. (The norm of A is only the largest eigenvalue for symmetric A . In general, we need singular values here.)

Another possibility is to monitor changes in the computed solution. If these are small:

$$\|x_{n+1} - x_n\| / \|x_n\| < \epsilon$$

we can also conclude that we are close to the solution.

Exercise 5.44. Prove an analytic relationship between the distance between iterates and the distance to the true solution. If your equation contains constants, can they be determined theoretically or in practice?

Exercise 5.45. Write a simple program to experiment with linear system solving. Take the matrix from the 1D BVP (use an efficient storage scheme) and program an iterative method using the choice $K = D_A$. Experiment with stopping tests on the residual and the distance between iterates. How does the number of iterations depend on the size of the matrix?

Change the matrix construction so that a certain quantity is added to the diagonal, that is, add αI to the original matrix. What happens when $\alpha > 0$? What happens when $\alpha < 0$? Can you find the value where the behaviour changes? Does that value depend on the matrix size?

5.5.7 Theory of general iterative methods

Above, you saw iterative methods of the form $x_{i+1} = x_i - K^{-1}r_i$, and we will now see iterative methods of the more general form

$$x_{i+1} = x_i + \sum_{j \leq i} K^{-1}r_j \alpha_{ji}, \quad (5.12)$$

that is, using all previous residuals to update the iterate. One might ask, ‘why not introduce an extra parameter and write $x_{i+1} = \alpha_i x_i + \dots$?’ Here we give a short argument that the former scheme describes a large class of methods. Indeed, the current author is not aware of methods that fall outside this scheme.

We defined the residual, given an approximate solution \tilde{x} , as $\tilde{r} = A\tilde{x} - b$. For this general discussion we precondition the system as $K^{-1}Ax = K^{-1}b$. (See section 5.5.5 where we discussed transforming the linear system.) The corresponding residual for the initial guess \tilde{x} is

$$\tilde{r} = K^{-1}A\tilde{x} - K^{-1}b.$$

We now find that

$$x = A^{-1}b = \tilde{x} - A^{-1}K\tilde{r} = \tilde{x} - (K^{-1}A)^{-1}\tilde{r}.$$

Now, the *Cayley-Hamilton theorem* states that for every A there exists a polynomial $\phi(x)$ (the *characteristic polynomial*) such that

$$\phi(A) = 0.$$

We observe that we can write this polynomial ϕ as

$$\phi(x) = 1 + x\pi(x)$$

where π is another polynomial. Applying this to $K^{-1}A$, we have

$$0 = \phi(K^{-1}A) = I + K^{-1}A\pi(K^{-1}A) \Rightarrow (K^{-1}A)^{-1} = -\pi(K^{-1}A)$$

so that $x = \tilde{x} + \pi(K^{-1}A)\tilde{r}$. Now, if we let $x_0 = \tilde{x}$, then $\tilde{r} = K^{-1}r_0$, giving the equation

$$x = x_0 + \pi(K^{-1}A)K^{-1}r_0.$$

This equation suggests an iterative scheme: if we can find a series of polynomials $\pi^{(i)}$ of degree i to approximate π , it will give us a sequence of iterates

$$x_{i+1} = x_0 + \pi^{(i)}(K^{-1}A)K^{-1}r_0 = x_0 + K^{-1}\pi^{(i)}(AK^{-1})r_0 \quad (5.13)$$

that ultimately reaches the true solution. Multiplying this equation by A and subtracting b on both sides gives

$$r_{i+1} = r_0 + \hat{\pi}^{(i)}(AK^{-1})r_0$$

where $\hat{\pi}^{(i)}(x) = x\pi^{(i)}(x)$. This immediately gives us

$$r_i = \hat{\pi}^{(i)}(AK^{-1})r_0 \quad (5.14)$$

where $\hat{\pi}^{(i)}$ is a polynomial of degree i with $\hat{\pi}^{(i)}(0) = 1$. This statement can be used as the basis of a convergence theory of iterative methods. However, this goes beyond the scope of this book.

Let us look at a couple of instances of equation (5.14). For $i = 1$ we have

$$r_1 = (\alpha_1 AK^{-1} + \alpha_2 I)r_0 \Rightarrow AK^{-1}r_0 = \beta_1 r_1 + \beta_0 r_0$$

for some values α_i, β_i . For $i = 2$

$$r_2 = (\alpha_2(AK^{-1})^2 + \alpha_1 AK^{-1} + \alpha_0)r_0$$

for different values α_i . But we had already established that AK_0^{-1} is a combination of r_1, r_0 , so now we have that

$$(AK^{-1})^2r_0 \in [r_2, r_1, r_0],$$

and it is clear how to show inductively that

$$(AK^{-1})^i r_0 \in [r_i, \dots, r_0]. \quad (5.15)$$

Substituting this in (5.13) we finally get

$$x_{i+1} = x_0 + \sum_{j \leq i} K^{-1} r_j \alpha_{ji}. \quad (5.16)$$

It is easy to see that the scheme (5.12) is of the form (5.16) and that the reverse implication also holds.

Summarizing, the basis of iterative methods is a scheme where iterates get updated by all residuals computed so far:

$$x_{i+1} = x_i + \sum_{j \leq i} K^{-1} r_j \alpha_{ji}. \quad (5.17)$$

Compare that to the stationary iteration (section 5.5.1) where the iterates get updated from just the last residual, and with a coefficient that stays constant.

We can say more about the α_{ij} coefficients. If we multiply equation (5.17) by A , and subtract b from both sides, we find

$$r_{i+1} = r_i + \sum_{j \leq i} A K^{-1} r_j \alpha_{ji}. \quad (5.18)$$

Let us consider this equation for a moment. If we have a starting residual r_0 , the next residual is computed as

$$r_1 = r_0 + A K^{-1} r_0 \alpha_{00}.$$

From this we get that $A K^{-1} r_0 = \alpha_{00}^{-1} (r_1 - r_0)$, so for the next residual,

$$\begin{aligned} r_2 &= r_1 + A K^{-1} r_1 \alpha_{11} + A K^{-1} r_0 \alpha_{01} \\ &= r_1 + A K^{-1} r_1 \alpha_{11} + \alpha_{00}^{-1} \alpha_{01} (r_1 - r_0) \\ \Rightarrow A K^{-1} r_1 &= \alpha_{11}^{-1} (r_2 - (1 + \alpha_{00}^{-1} \alpha_{01}) r_1 + \alpha_{00}^{-1} \alpha_{01} r_0) \end{aligned}$$

We see that we can express $A K^{-1} r_1$ as a sum $r_2 \beta_2 + r_1 \beta_1 + r_0 \beta_0$, and that $\sum_i \beta_i = 0$.

Generalizing this, we find (with different α_{ij} than above)

$$\begin{aligned} r_{i+1} &= r_i + A K^{-1} r_i \delta_i + \sum_{j \leq i+1} r_j \alpha_{ji} && \text{substituting } \alpha_{ii} := 1 + \alpha_{ii} \\ r_{i+1}(1 - \alpha_{i+1,i}) &= A K^{-1} r_i \delta_i + r_i(1 + \alpha_{ii}) + \sum_{j < i} r_j \alpha_{ji} && \alpha_{i+1,i} := 1 - \alpha_{i+1,i} \\ r_{i+1} \alpha_{i+1,i} &= A K^{-1} r_i \delta_i + \sum_{j \leq i} r_j \alpha_{ji} && \text{note that } \alpha_{i+1,i} = \sum_{j \leq i} \alpha_{ji} \\ r_{i+1} \alpha_{i+1,i} \delta_i^{-1} &= A K^{-1} r_i + \sum_{j \leq i} r_j \alpha_{ji} \delta_i^{-1} && \text{substituting } \gamma_{ij} = \alpha_{ij} \delta_j^{-1} \\ r_{i+1} \alpha_{i+1,i} \delta_i^{-1} &= A K^{-1} r_i + \sum_{j \leq i} r_j \alpha_{ji} \delta_i^{-1} \\ r_{i+1} \gamma_{i+1,i} &= A K^{-1} r_i + \sum_{j \leq i} r_j \gamma_{ji} \end{aligned}$$

and we have that $\gamma_{i+1,i} = \sum_{j \leq i} \gamma_{ji}$.

We can take this last equation and write it as $AK^{-1}R = RH$ where

$$H = \begin{pmatrix} -\gamma_{11} & -\gamma_{12} & \dots & & \\ \gamma_{21} & -\gamma_{22} & -\gamma_{23} & \dots & \\ 0 & \gamma_{32} & -\gamma_{33} & -\gamma_{34} & \\ \emptyset & \ddots & \ddots & \ddots & \ddots \end{pmatrix}$$

In this, H is a so-called *Hessenberg matrix*: it is upper triangular plus a single lower subdiagonal. Also we note that the elements of H in each column sum to zero.

Because of the identity $\gamma_{i+1,i} = \sum_{j \leq i} \gamma_{ji}$ we can subtract b from both sides of the equation for r_{i+1} and ‘divide out A ’, giving

$$x_{i+1}\gamma_{i+1,i} = K^{-1}r_i + \sum_{j \leq i} x_j\gamma_{ji}.$$

This gives us the general form for iterative methods:

$$\begin{cases} r_i = Ax_i - b \\ x_{i+1}\gamma_{i+1,i} = K^{-1}r_i + \sum_{j \leq i} x_j\gamma_{ji} \\ r_{i+1}\gamma_{i+1,i} = AK^{-1}r_i + \sum_{j \leq i} r_j\gamma_{ji} \end{cases} \quad \text{where } \gamma_{i+1,i} = \sum_{j \leq i} \gamma_{ji}. \quad (5.19)$$

This form holds for many iterative methods, including the stationary iterative methods you have seen above. In the next sections you will see how the γ_{ij} coefficients follow from orthogonality conditions on the residuals.

5.5.8 Iterating by orthogonalization

The stationary methods described above (section 5.5.1) have been around in some form or another for a long time: Gauss described some variant in a letter to a student. They were perfected in the thesis of Young [137] in 1950; the final reference is probably the book by Varga [129]. These methods are little used these days, except in the specialized context of *multigrid smoothers*, a topic not discussed in this course.

At almost the same time, the field of methods based on orthogonalization was kicked off by two papers [86, 69], though it took a few decades for them to find wide applicability. (For further history, see [55].)

The basic idea is as follows:

If you can make all your residuals orthogonal to each other, and the matrix is of dimension n , then after n iterations you have to have converged: it is not possible to have an $n+1$ -st residual that is orthogonal to all previous and nonzero. Since a zero residual means that the corresponding iterate is the solution, we conclude that after n iterations we have the true solution in hand.

With the size of matrices that contemporary applications generate this reasoning is no longer relevant: it is not computationally realistic to iterate for n iterations. Moreover, roundoff will probably destroy any accuracy of the solution. However, it was later realized [113] that such methods are a realistic option in the case of *symmetric positive definite (SPD)* matrices. The reasoning is then:

The sequence of residuals spans a series of subspaces of increasing dimension, and by orthogonalizing, the new residuals are projected on these spaces. This means that they will have decreasing sizes.




Figure 5.7: The optimal update u_m make the new residual orthogonal to the AK_m subspace

This is illustrated in figure 5.7.

In this section you will see the basic idea of iterating by orthogonalization. The method presented here is only of theoretical interest; next you will see the Conjugate Gradients (CG) and Generalized Minimum Residual (GMRES) methods that are the basis of many real-life applications.

Let us now take the basic scheme (5.19) and orthogonalize the residuals. Instead of the normal inner product we use the K^{-1} -inner product:

$$(x, y)_{K^{-1}} = x^t K^{-1} y$$

and we will force residuals to be K^{-1} -orthogonal:

$$\forall_{i \neq j}: r_i \perp_{K^{-1}} r_j \Leftrightarrow \forall_{i \neq j}: r_i K^{-1} r_j = 0$$

This is known as the *Full Orthogonalization Method (FOM)* scheme:

```

        Let  $r_0$  be given
        For  $i \geq 0$ :
            let  $s \leftarrow K^{-1} r_i$ 
            let  $t \leftarrow AK^{-1} r_i$ 
            for  $j \leq i$ :
                let  $\gamma_j$  be the coefficient so that  $t - \gamma_j r_j \perp r_j$ 
                for  $j \leq i$ :
                    form  $s \leftarrow s - \gamma_j x_j$ 
                    and  $t \leftarrow t - \gamma_j r_j$ 
            let  $x_{i+1} = (\sum_j \gamma_j)^{-1} s$ ,  $r_{i+1} = (\sum_j \gamma_j)^{-1} t$ .
    
```

You may recognize the *Gram-Schmidt* orthogonalization in this (see appendix A.1.2 for an explanation): in each iteration r_{i+1} is initially set to $AK^{-1} r_i$, and orthogonalized against r_j with $j \leq i$.

We can use *modified Gram-Schmidt* by rewriting the algorithm as:

Let r_0 be given
 For $i \geq 0$:
 let $s \leftarrow K^{-1}r_i$
 let $t \leftarrow AK^{-1}r_i$
 for $j \leq i$:
 let γ_j be the coefficient so that $t - \gamma_j r_j \perp r_j$
 form $s \leftarrow s - \gamma_j x_j$
 and $t \leftarrow t - \gamma_j r_j$
 let $x_{i+1} = (\sum_j \gamma_j)^{-1}s$, $r_{i+1} = (\sum_j \gamma_j)^{-1}t$.

These two versions of the FOM algorithm are equivalent in exact arithmetic, but differ in practical circumstances in two ways:

- The modified Gramm-Schmidt method is more numerically stable;
- The unmodified method allows you to compute all inner products simultaneously. We discuss this below in section 6.5.

Even though the FOM algorithm is not used in practice, these computational considerations carry over to the GMRES method below.

5.5.9 Coupled recurrences form of iterative methods

Above, you saw the general equation (5.19) for generating iterates and search directions. This equation is often split as

- An update of the x_i iterate from a single *search direction*:

$$x_{i+1} = x_i - \delta_i p_i,$$

and

- A construction of the search direction from the residuals known so far:

$$p_i = K^{-1}r_i + \sum_{j < i} \beta_{ij} K^{-1}r_j.$$

It is not hard to see inductively that we can also define

$$p_i = K^{-1}r_i + \sum_{j < i} \gamma_{ji} p_j,$$

and this last form is the one that is used in practice.

The iteration dependent coefficients are typically chosen to let the residuals satisfy various orthogonality conditions. For instance, one can choose to let the method be defined by letting the residuals be orthogonal ($r_i^t r_j = 0$ if $i \neq j$), or A -orthogonal ($r_i^t A r_j = 0$ if $i \neq j$). Many more schemes exist. Such methods can converge much faster than stationary iteration, or converge for a wider range of matrix and preconditioner types. Below we will see two such methods; their analysis, however, is beyond the scope of this course.

5.5.10 The method of Conjugate Gradients

In this section, we will derive the Conjugate Gradients (CG) method, which is a specific implementation of the FOM algorithm. In particular, it has pleasant computational properties in the case of an SPD matrix A .

The CG method takes as its basic form the coupled recurrences formulation described above, and the coefficients are defined by demanding that the sequence of residuals r_0, r_1, r_2, \dots satisfy

$$r_i^t K^{-1} r_j = 0 \quad \text{if } i \neq j.$$

We start by deriving the CG method for nonsymmetric systems, and then show how it simplifies in the symmetric case. (The approach here is taken from [37]).

The basic equations are

$$\begin{cases} x_{i+1} = x_i - \delta_i p_i \\ r_{i+1} = r_i - \delta_i A p_i \\ p_{i+1} = K^{-1} r_{i+1} + \sum_{j \leq i} \gamma_{ji+1} p_j, \end{cases} \quad (5.20)$$

where the first and third equation were introduced above, and the second can be found by multiplying the first by A (check this!).

We will now derive the coefficients in this method by induction. In essence, we assume that we have current residual r_{cur} , a residuals to be computed r_{new} , and a collection of known residuals R_{old} . Rather than using subscripts ‘old, cur, new’, we use the following convention:

- x_1, r_1, p_1 are the current iterate, residual, and search direction. Note that the subscript 1 does not denote the iteration number here.
- x_2, r_2, p_2 are the iterate, residual, and search direction that we are about to compute. Again, the subscript does not equal the iteration number.
- X_0, R_0, P_0 are all previous iterates, residuals, and search directions bundled together in a block of vectors.

In terms of these quantities, the update equations are then

$$\begin{cases} x_2 = x_1 - \delta_1 p_1 \\ r_2 = r_1 - \delta_1 A p_1 \\ p_2 = K^{-1} r_2 + v_{12} p_1 + P_0 u_{02} \end{cases} \quad (5.21)$$

where δ_1, v_{12} are scalars, and u_{02} is a vector with length the number of iterations before the current. We now derive δ_1, v_{12}, u_{02} from the orthogonality of the residuals. To be specific, the residuals have to be orthogonal under the K^{-1} inner product: we want to have

$$r_2^t K^{-1} r_1 = 0, \quad r_2^t K^{-1} R_0 = 0.$$

Combining these relations gives us, for instance,

$$\left. \begin{array}{l} r_1^t K^{-1} r_2 = 0 \\ r_2 = r_1 - \delta_1 A K^{-1} p_1 \end{array} \right\} \Rightarrow \delta_1 = \frac{r_1^t r_1}{r_1^t A K^{-1} p_1}.$$

Finding v_{12}, u_{02} is a little harder. For this, we start by summarizing the relations for the residuals and search directions in equation (5.20) in block form as

$$(R_0, r_1, r_2) \begin{pmatrix} 1 & & & \\ -1 & 1 & & \\ & \ddots & \ddots & \\ \hline & & -1 & 1 \\ \hline & & -1 & 1 \end{pmatrix} = A(P_0, p_1, p_2) \operatorname{diag}(D_0, d_1, d_2)$$

$$(P_0, p_1, p_2) \begin{pmatrix} I - U_{00} & -u_{01} & -u_{02} \\ & 1 & -v_{12} \\ & & 1 \end{pmatrix} = K^{-1}(R_0, r_1, r_2)$$

or abbreviated $RJ = APD$, $P(I-U) = R$ where J is the matrix with identity diagonal and minus identity subdiagonal. We then observe that

- $R^t K^{-1} R$ is diagonal, expressing the orthogonality of the residuals.
- Combining that $R^t K^{-1} R$ is diagonal and $P(I-U) = R$ gives that $R^t P = R^t K^{-1} R(I-U)^{-1}$. We now reason that $(I-U)^{-1}$ is upper diagonal, so $R^t P$ is upper triangular. This tells us quantities such as $r_2^t p_1$ are zero.
- Combining the relations for R and P , we get first that

$$R^t K^{-t} AP = R^t K^{-t} RJD^{-1}$$

which tells us that $R^t K^{-t} AP$ is lower bidiagonal. Expanding R in this equation gives

$$P^t AP = (I-U)^{-t} R^t RJD^{-1}.$$

Here D and $R^t K^{-1} R$ are diagonal, and $(I-U)^{-t}$ and J are lower triangular, so $P^t AP$ is lower triangular.

- This tells us that $P_0^t A p_2 = 0$ and $p_1^t A p_2 = 0$.
- Taking the product of $P_0^t A$, $p_1^t A$ with the definition of p_2 in equation (5.21) gives

$$u_{02} = -(P_0^t AP_0)^{-1} P_0^t AK^{-1} r_2, \quad v_{12} = -(p_1^t A p_1)^{-1} p_1^t AK^{-1} r_2.$$

- If A is symmetric, $P^t AP$ is lower triangular (see above) and symmetric, so it is in fact diagonal. Also, $R^t K^{-t} AP$ is lower bidiagonal, so, using $A = A^t$, $P^t AK^{-1} R$ is upper bidiagonal. Since $P^t AK^{-1} R = P^t AP(I-U)$, we conclude that $I-U$ is upper bidiagonal, so, only in the symmetric case, $u_{02} = 0$.

Some observations about this derivation.

- Strictly speaking we are only proving necessary relations here. It can be shown that these are sufficient too.
- There are different formulas that wind up computing the same vectors, in exact arithmetic. For instance, it is easy to derive that $p_1^t r_1 = r_1^t r_1$, so this can be substituted in the formulas just derived. The implementation of the CG method as it is typically implemented, is given in figure 5.8.

```

Compute  $r^{(0)} = b - Ax^{(0)}$  for some initial guess  $x^{(0)}$ 
for  $i = 1, 2, \dots$ 
    solve  $Mz^{(i-1)} = r^{(i-1)}$ 
     $\rho_{i-1} = r^{(i-1)T} z^{(i-1)}$ 
    if  $i = 1$ 
         $p^{(1)} = z^{(0)}$ 
    else
         $\beta_{i-1} = \rho_{i-1}/\rho_{i-2}$ 
         $p^{(i)} = z^{(i-1)} + \beta_{i-1}p^{(i-1)}$ 
    endif
     $q^{(i)} = Ap^{(i)}$ 
     $\alpha_i = \rho_{i-1}/p^{(i)T} q^{(i)}$ 
     $x^{(i)} = x^{(i-1)} + \alpha_i p^{(i)}$ 
     $r^{(i)} = r^{(i-1)} - \alpha_i q^{(i)}$ 
    check convergence; continue if necessary
end

```

Figure 5.8: The Preconditioned Conjugate Gradient Method

- In the k -th iteration, computing $P_0^t Ar_2$ (which is needed for u_{02}) takes k inner products. First of all, inner products are disadvantageous in a parallel context. Secondly, this requires us to store all search directions indefinitely. This second point implies that both work and storage go up with the number of iterations. Contrast this with the stationary iteration scheme, where storage was limited to the matrix and a few vectors, and work in each iteration was the same.
- The objections just raised disappear in the symmetric case. Since u_{02} is zero, the dependence on P_0 disappears, and only the dependence on p_1 remains. Thus, storage is constant, and the amount of work per iteration is constant. The number of inner products per iteration can be shown to be just two.

Exercise 5.46. Do a flop count of the various operations in one iteration of the CG method.

Assume that A is the matrix of a five-point stencil and that the preconditioner M is an incomplete factorization of A (section 5.5.1). Let N be the matrix size.

5.5.11 Derivation from minimization

The above derivation of the CG method is not often found in the literature. The typical derivation starts with a minimization problem with a *symmetric positive definite (SPD)* matrix A :

For which vector x with $\|x\| = 1$ is $f(x) = 1/2 x^t Ax - b^t x$ minimal? (5.22)

If we accept the fact that the function f has a minimum, which follows from the positive definiteness, we find the minimum by computing the derivative

$$f'(x) = Ax - b.$$

and asking where $f'(x) = 0$. And, presto, there we have the original linear system.

Exercise 5.47. Derive the derivative formula above. (Hint: write out the definition of derivative as $\lim_{h \downarrow 0} \dots$) Note that this requires A to be symmetric.

For the derivation of the iterative method, we state that the iterate x_i is updated with a certain stepsize δ_i along a *search direction* p_i :

$$x_{i+1} = x_i + p_i \delta_i$$

The optimal stepsize

$$\delta_i = \frac{r_i^t p_i}{p_i^t A p_i}$$

is then derived as the one that minimizes the function f along the line $x_i + \delta \delta p_i$:

$$\delta_i = \underset{\delta}{\operatorname{argmin}} \|f(x_i + p_i \delta)\|$$

The construction of the search direction from the residuals follows by induction proof from the requirement that the residuals be orthogonal. For a typical proof, see [3].

5.5.12 GMRES

In the discussion of the CG method above, it was pointed out that orthogonality of the residuals requires storage of all residuals, and k inner products in the k 'th iteration. Unfortunately, it can be proved that the work savings of the CG method can, for all practical purposes, not be found outside of *SPD* matrices [39].

The *GMRES* method is a popular implementation of such full orthogonalization schemes. In order to keep the computational costs within bounds, it is usually implemented as a *restarted* method. That is, only a certain number (say $k = 5$ or 20) of residuals is retained, and every k iterations the method is restarted. The code can be found in figure 5.9.

Other methods exist that do not have the storage demands of GMRES, for instance QMR [46] and BiCGstab [128]. Even though by the remark above these can not orthogonalize the residuals, they are still attractive in practice.

5.5.13 Complexity

The efficiency of Gaussian elimination was fairly easy to assess: factoring and solving a system takes, deterministically, $\frac{1}{3}n^3$ operations. For an iterative method, the operation count is the product of the number of operations per iteration times the number of iterations. While each individual iteration is easy to analyze, there is no good theory to predict the number of iterations. (In fact, an iterative method may not even converge to begin with.) Added to this is the fact that Gaussian elimination can be coded in such a way that there is considerable cache reuse, making the algorithm run at a fair percentage of the computer's peak speed. Iterative methods, on the other hand, are much slower on a flops per second basis.

All these considerations make the application of iterative methods to linear system solving somewhere in between a craft and a black art. In practice, people do considerable experimentation to decide whether an iterative method will pay off, and if so, which method is preferable.

```

 $x^{(0)}$  is an initial guess
for  $j = 1, 2, \dots$ 
    Solve  $r$  from  $Mr = b - Ax^{(0)}$ 
     $v^{(1)} = r/\|r\|_2$ 
     $s := \|r\|_2 e_1$ 
    for  $i = 1, 2, \dots, m$ 
        Solve  $w$  from  $Mw = Av^{(i)}$ 
        for  $k = 1, \dots, i$ 
             $h_{k,i} = (w, v^{(k)})$ 
             $w = w - h_{k,i}v^{(k)}$ 
        end
         $h_{i+1,i} = \|w\|_2$ 
         $v^{(i+1)} = w/h_{i+1,i}$ 
        apply  $J_1, \dots, J_{i-1}$  on  $(h_{1,i}, \dots, h_{i+1,i})$ 
        construct  $J_i$ , acting on  $i$ th and  $(i+1)$ st component
        of  $h_{.,i}$ , such that  $(i+1)$ st component of  $J_i h_{.,i}$  is 0
         $s := J_i s$ 
        if  $s(i+1)$  is small enough then (UPDATE( $\tilde{x}, i$ ) and quit)
    end
    UPDATE( $\tilde{x}, m$ )
end

```

In this scheme UPDATE(\tilde{x}, i)
replaces the following computations:

Compute y as the solution of $Hy = \tilde{s}$, in which
the upper $i \times i$ triangular part of H has $h_{i,j}$ as
its elements (in least squares sense if H is singular),
 \tilde{s} represents the first i components of s
 $\tilde{x} = x^{(0)} + y_1 v^{(1)} + y_2 v^{(2)} + \dots + y_i v^{(i)}$
 $s^{(i+1)} = \|b - A\tilde{x}\|_2$
if \tilde{x} is an accurate enough approximation then quit
else $x^{(0)} = \tilde{x}$

Figure 5.9: The Preconditioned GMRES(m) Method

5.6 Further Reading

Iterative methods is a very deep field. As a practical introduction to the issues involved, you can read the ‘Templates book’ [5], online at <http://netlib.org/templates/>. For a deeper treatment of the theory, see the book by Saad [114] of which the first edition can be downloaded at <http://www-users.cs.umn.edu/~saad/books.html>.

Chapter 6

High performance linear algebra

In this section we will discuss a number of issues pertaining to linear algebra on parallel computers. We will take a realistic view of this topic, assuming that the number of processors is finite, and that the problem data is always large, relative to the number of processors. We will also pay attention to the physical aspects of the communication network between the processors.

We will analyze various linear algebra operations, including iterative methods, and their behaviour in the presence of a network with finite bandwidth and finite connectivity. This chapter will conclude with various short remarks regarding complications in algorithms that arise due to parallel execution.

6.1 Parallel dense matrix-vector product

In designing a parallel version of an algorithm, one often proceeds by making a *data decomposition* of the objects involved. In the case of a matrix-vector operations such as the product $y = Ax$, we have the choice of starting with a vector decomposition, and exploring its ramifications on how the matrix can be decomposed, or rather to start with the matrix, and deriving the vector decomposition from it. In this case, it seems natural to start with decomposing the matrix rather than the vector, since it will be most likely of larger computational significance. We now have two choices:

1. We make a one-dimensional decomposition of the matrix, splitting it in block rows or block columns, and assigning each of these – or groups of them – to a processor.
2. Alternatively, we can make a two-dimensional decomposition, assigning to each processor one or more general submatrices.

We start by considering the decomposition in block rows. Consider a processor p and the set I_p of indices of rows that it owns¹, and let $i \in I_p$ be a row that is assigned to this processor. The elements in row i are used in the operation

$$y_i = \sum_j a_{ij}x_j$$

We now reason:

1. For ease of exposition we will let I_p be a contiguous range of indices, but any general subset is allowed.

- If processor p has all x_j values, the matrix-vector product can trivially be executed, and upon completion, the processor has the correct values y_j for $j \in I_p$.
- This means that every processor needs to have a copy of x , which is wasteful. Also it raises the question of data integrity: you need to make sure that each processor has the correct value of x .
- In certain practical applications (for instance iterative methods, as you have seen before), the output of the matrix-vector product is, directly or indirectly, the input for a next matrix-vector operation. This is certainly the case for the power method which computes x, Ax, A^2x, \dots . Since our operation started with each processor having the whole of x , but ended with it owning only the local part of Ax , we have a mismatch.
- Maybe it is better to assume that each processor, at the start of the operation, has only the local part of x , that is, those x_i where $i \in I_p$, so that the start state and end state of the algorithm are the same. This means we have to change the algorithm to include some communication that allows each processor to obtain those values x_i where $i \notin I_p$.

Exercise 6.1. Go through a similar reasoning for the case where the matrix is decomposed in block columns. Describe the parallel algorithm in detail, like above, but without giving pseudo code.

Let us now look at the communication in detail: we will consider a fixed processor p and consider the operations it performs and the communication that necessitates. According to the above analysis, in executing the statement $y_i = \sum_j a_{ij}x_j$ we have to be aware what processor the j values ‘belong to’. To acknowledge this, we write

$$y_i = \sum_{j \in I_p} a_{ij}x_j + \sum_{j \notin I_p} a_{ij}x_j \quad (6.1)$$

If $j \in I_p$, the instruction $y_i \leftarrow y_i + a_{ij}x_j$ involves only quantities that are already local to the processor. Let us therefore concentrate on the case $j \notin I_p$. It would be nice if we could just write the statement

$$y(i) = y(i) + a(i, j) * x(j)$$

and some lower layer would automatically transfer $x(j)$ from whatever processor it is stored on to a local register. (The PGAS languages of section 2.5.6 aim to do this, but their efficiency is far from guaranteed.) An implementation, based on this optimistic view of parallelism, is given in figure 6.1.

The immediate problem with such a ‘local’ approach is that too much communication will take place.

- If the matrix A is dense, the element x_j is necessary once for each row $i \in I_p$, and it will thus be fetched once for every row $i \in I_p$.
- For each processor $q \neq p$, there will be (large) number of elements x_j with $j \in I_q$ that need to be transferred from processor q to p . Doing this in separate messages, rather than one bulk transfer, is very wasteful.

With shared memory these issues are not much of a problem, but in the context of distributed memory it is better to take a *buffering* approach.

Instead of communicating individual elements of x , we use a local buffer B_{pq} for each processor $q \neq p$ where we collect the elements from q that are needed to perform the product on p . (See figure 6.2 for an illustration.) The parallel algorithm is given in figure 6.3.

Input: Processor number p ; the elements x_i with $i \in I_p$; matrix elements A_{ij} with $i \in I_p$.

Output: The elements y_i with $i \in I_p$

for $i \in I_p$ **do**

$s \leftarrow 0$;

for $j \in I_p$ **do**

$s \leftarrow s + a_{ij}x_j$

for $j \notin I_p$ **do**

send x_j from the processor that owns it to the current one, then;

$s \leftarrow s + a_{ij}x_j$

$y_i \leftarrow s$

Procedure Naive Parallel MVP($A, x_{local}, y_{local}, p$)

Figure 6.1: A naïvely coded parallel matrix-vector product




Figure 6.2: The parallel matrix-vector product with a blockrow distribution.

Input: Processor number p ; the elements x_i with $i \in I_p$; matrix elements A_{ij} with $i \in I_p$.

Output: The elements y_i with $i \in I_p$

for $q \neq p$ **do**

Send elements of x from processor q to p , receive in buffer B_{pq} .

$y_{local} \leftarrow Ax_{local}$

for $q \neq p$ **do**

$y_{local} \leftarrow y_{local} + A_{pq}B_q$

Procedure Parallel MVP($A, x_{local}, y_{local}, p$)

Figure 6.3: A buffered implementation of the parallel matrix-vector product

In addition to preventing an element from being fetched more than once, this also combines many small messages into one large message, which is usually more efficient; recall our discussion of bandwidth and latency in section 2.6.7.

Exercise 6.2. Give pseudocode for the matrix-vector product using nonblocking operations (section 2.5.3.6)

Above we said that having a copy of the whole of x on each processor was wasteful in space. The implicit argument here is that, in general, we do not want local storage to be function of the number of processors: ideally it should be only a function of the local data. (This is related to weak scaling; section 2.7.4.)

You see that, because of communication considerations, we have actually decided that it is unavoidable, or at least preferable, for each processor to store the whole input vector. Such trade-offs between space and time efficiency are fairly common in parallel programming. For the dense matrix-vector product we can actually defend this overhead, since the vector storage is of lower order than the matrix storage, so our over-allocation is small by ratio. Below (section 6.4), we will see that for the sparse matrix-vector product the overhead can be much less.

It is easy to see that the parallel dense matrix-vector product, as described above, has perfect speedup *if we are allowed to ignore the time for communication*. In the next section you will see that the block row implementation above is not optimal if we take communication into account. For scalability we need a two-dimensional decomposition.

6.2 Scalability of the dense matrix-vector product

In this section, we will give a full analysis of the parallel computation of $y \leftarrow Ax$, where $x, y \in \mathbb{R}^n$ and $A \in \mathbb{R}^{n \times n}$. We will assume that p nodes will be used, but we make no assumptions on their connectivity. We will see that the way the matrix is distributed makes a big difference for the scaling of the algorithm; for the original research see [?, ?, ?], and see section 2.7.4 for the definitions of the various forms of scaling.

An important part of this discussion is a thorough analysis of collective operations, so we start with this.

6.2.1 Collective operations

Collective operations play an important part in linear algebra operations. In fact, the scalability of the operations can depend on the cost of these collectives. (See [16] for details.)

In computing the cost of a collective operation, three architectural constants are enough to give lower bounds: α , the of sending a single message, β , the inverse of the for sending data (see section 1.3.2), and γ , the inverse of the , the time for performing an arithmetic operation. Sending n data items then takes time $\alpha + \beta n$. We further assume that a processor can only send one message at a time. We make no assumptions about the connectivity of the processors; thus, the lower bounds derived here will hold for a wide range of architectures.

The main implication of the architectural model above is that the number of active processors can only double in each step of an algorithm. For instance, to do a broadcast, first processor 0 sends to 1, then 0 and 1 can send to 2 and 3, then 0–3 send to 4–7, et cetera. This cascade of messages is called a *minimum*

spanning tree of the processor network, and it follows that any collective algorithm has at least $\alpha \log_2 p$ cost associated with the accumulated latencies.

6.2.1.1 Broadcast

In a *broadcast* operation, a single processor has n data elements that needs to send to all others: the other processors need a full copy of all n elements. By the above doubling argument, we conclude that a broadcast to p processors takes time at least $\lceil \log_2 p \rceil$ steps with a total latency of $\lceil \log_2 p \rceil \alpha$. Since n elements are sent, this adds at least a time $n\beta$ for all elements to leave the sending processor, giving a total cost lower bound of

$$\lceil \log_2 p \rceil \alpha + n\beta.$$

We can illustrate the spanning tree method as follows:

	$t = 0$	$t = 1$	$t = 2$	$t = 3$
p_0	x_0, x_1, x_2, x_3	$x_0 \downarrow, x_1 \downarrow, x_2 \downarrow, x_3 \downarrow$	$x_0 \downarrow, x_1 \downarrow, x_2 \downarrow, x_3 \downarrow$	x_0, x_1, x_2, x_3
p_1			$x_0 \downarrow, x_1 \downarrow, x_2 \downarrow, x_3 \downarrow$	x_0, x_1, x_2, x_3
p_2				x_0, x_1, x_2, x_3
p_3				x_0, x_1, x_2, x_3

On $t = 1$, p_0 sends to p_1 ; on $t = 2$ p_0, p_1 send to p_2, p_3 .

6.2.1.2 Reduction

In a *reduction* operation, each processor has n data elements, and one processor needs to combine them elementwise, for instance computing n sums or products.

By running the broadcast backwards in time, we see that a reduction operation has the same lower bound on the communication of $\lceil \log_2 p \rceil \alpha + n\beta$. A reduction operation also involves computation, which would take a total time of $(p - 1)\gamma n$ sequentially: each of n items gets reduced over p processors. Since these operations can potentially be parallelized, the lower bound on the computation is $\frac{p-1}{p}\gamma n$, giving a total of

$$\lceil \log_2 p \rceil \alpha + n\beta + \frac{p-1}{p}\gamma n.$$

We illustrate this again, using the notation $x_i^{(j)}$ for the data item i that was originally on processor j , and $x_i^{(j:k)}$ for the sum of the items i of processors $j \dots k$.

	$t = 1$	$t = 2$	$t = 3$
p_0	$x_0^{(0)}, x_1^{(0)}, x_2^{(0)}, x_3^{(0)}$	$x_0^{(0:1)}, x_1^{(0:1)}, x_2^{(0:1)}, x_3^{(0:1)}$	$x_0^{(0:3)}, x_1^{(0:3)}, x_2^{(0:3)}, x_3^{(0:3)}$
p_1	$x_0^{(1)} \uparrow, x_1^{(1)} \uparrow, x_2^{(1)} \uparrow, x_3^{(1)} \uparrow$		
p_2	$x_0^{(2)}, x_1^{(2)}, x_2^{(2)}, x_3^{(2)}$	$x_0^{(2:3)} \uparrow, x_1^{(2:3)} \uparrow, x_2^{(2:3)} \uparrow, x_3^{(2:3)} \uparrow$	
p_3	$x_0^{(3)} \uparrow, x_1^{(3)} \uparrow, x_2^{(3)} \uparrow, x_3^{(3)} \uparrow$		

On time $t = 1$ processors p_0, p_2 receive from p_1, p_3 , and on $t = 2$ p_0 receives from p_2 .

6.2.1.3 Allreduce

An *allreduce* operation computes the same elementwise reduction of n elements on each processor, but leaves the result on each processor, rather than just on the root of the spanning tree. This could be implemented as a reduction followed by a broadcast, but more clever algorithms exist.

The lower bound on the cost of an allreduce is, somewhat remarkably, almost the same as of a simple reduction: since in a reduction not all processors are active at the same time, we assume that the extra work can be spread out perfectly. This means that the lower bound on the latency and computation stays the same. For the bandwidth we reason as follows: in order for the communication to be perfectly parallelized, $\frac{p-1}{p}n$ items have to arrive at, and leave each processor. Thus we have a total time of

$$\lceil \log_2 p \rceil \alpha + 2 \frac{p-1}{p} n \beta + \frac{p-1}{p} n \gamma.$$

6.2.1.4 Allgather

In a *gather* operation on n elements, each processor has n/p elements, and one processor collects them all, without combining them as in a reduction. The *allgather* computes the same gather, but leaves the result on all processors.

Again we assume that gathers with multiple targets are active simultaneously. Since every processor originates a minimum spanning tree, we have $\log_2 p \alpha$ latency; since each processor receives n/p elements from $p-1$ processors, there is $\frac{p-1}{p} \beta$ bandwidth cost. The total cost for constructing a length n vector by allgather is then

$$\lceil \log_2 p \rceil \alpha + \frac{p-1}{p} n \beta.$$

	$t = 1$	$t = 2$	$t = 3$
p_0	$x_0 \downarrow$	$x_0x_1 \downarrow$	$x_0x_1x_2x_3$
p_1	$x_1 \uparrow$	$x_0x_1 \downarrow$	$x_0x_1x_2x_3$
p_2	$x_2 \downarrow$	$x_2x_3 \uparrow$	$x_0x_1x_2x_3$
p_3	$x_3 \uparrow$	$x_2x_3 \uparrow$	$x_0x_1x_2x_3$

At time $t = 1$, there is an exchange between neighbours p_0, p_1 and likewise p_2, p_3 ; at $t = 2$ there is an exchange over distance two between p_0, p_2 and likewise p_1, p_3 .

6.2.1.5 Reduce-scatter

In a *reduce-scatter* operation, each processor has n elements, and an n -way reduction is done on them. Unlike in the reduce or allreduce, the result is then broken up, and distributed as in a scatter operation.

Formally, processor i has an item $x_i^{(i)}$, and it needs $\sum_j x_i^{(j)}$. We could implement this by doing a size p reduction, collecting the vector $(\sum_i x_0^{(i)}, \sum_i x_1^{(i)}, \dots)$ on one processor, and scattering the results. However it is possible to combine these operations in a so-called *bidirectional exchange* algorithm:

	$t = 1$	$t = 2$	$t = 3$
p_0	$x_0^{(0)}, x_1^{(0)}, x_2^{(0)} \downarrow, x_3^{(0)} \downarrow$	$x_0^{(0:2:2)}, x_1^{(0:2:2)} \downarrow$	$x_0^{(0:3)}$
p_1	$x_0^{(1)}, x_1^{(1)}, x_2^{(1)} \downarrow, x_3^{(1)} \downarrow$	$x_0^{(1:3:2)} \uparrow, x_1^{(1:3:2)}$	$x_1^{(0:3)}$
p_2	$x_0^{(2)} \uparrow, x_1^{(2)} \uparrow, x_2^{(2)}, x_3^{(2)}$	$x_2^{(0:2:2)}, x_3^{(0:2:2)} \downarrow$	$x_2^{(0:3)}$
p_3	$x_0^{(3)} \uparrow, x_1^{(3)} \uparrow, x_2^{(3)}, x_3^{(3)}$	$x_0^{(1:3:2)} \uparrow, x_1^{(1:3:2)}$	$x_3^{(0:3)}$

The reduce-scatter can be considered as a allgather run in reverse, with arithmetic added, so the cost is

$$\lceil \log_2 p \rceil \alpha + \frac{p-1}{p} n(\beta + \gamma).$$

6.2.2 Matrix-vector product, partitioning by rows

Partition

$$A \rightarrow \begin{pmatrix} A_0 \\ A_1 \\ \vdots \\ A_{p-1} \end{pmatrix} \quad x \rightarrow \begin{pmatrix} x_0 \\ x_1 \\ \vdots \\ x_{p-1} \end{pmatrix}, \quad \text{and} \quad y \rightarrow \begin{pmatrix} y_0 \\ y_1 \\ \vdots \\ y_{p-1} \end{pmatrix},$$

where $A_i \in \mathbb{R}^{m_i \times n}$ and $x_i, y_i \in \mathbb{R}^{m_i}$ with $\sum_{i=0}^{p-1} m_i = n$ and $m_i \approx n/p$. We will start by assuming that A_i , x_i , and y_i are originally assigned to \mathcal{P}_i .

The computation is characterized by the fact that each processor needs the whole vector x , but owns only an n/p fraction of it. Thus, we execute an *allgather* of x . After this, the processor can execute the local product $y_i \leftarrow A_i x$; no further communication is needed after that.

An algorithm with cost computation for $y = Ax$ in parallel is then given by

Step	Cost (lower bound)
Allgather x_i so that x is available on all nodes	$\lceil \log_2(p) \rceil \alpha + \frac{p-1}{p} n\beta$ $\approx \log_2(p)\alpha + n\beta$
Locally compute $y_i = A_i x$	$\approx 2\frac{n^2}{p}\gamma$

Cost analysis The total cost of the algorithm is given by, approximately,

$$T_p(n) = T_p^{\text{1D-row}}(n) = 2\frac{n^2}{p}\gamma + \underbrace{\log_2(p)\alpha + n\beta}_{\text{Overhead}}$$

6. High performance linear algebra

Since the sequential cost is $T_1(n) = 2n^2\gamma$, the speedup is given by

$$S_p^{1D\text{-row}}(n) = \frac{T_1(n)}{T_p^{1D\text{-row}}(n)} = \frac{2n^2\gamma}{2\frac{n^2}{p}\gamma + \log_2(p)\alpha + n\beta} = \frac{p}{1 + \frac{p\log_2(p)\alpha}{2n^2}\frac{\gamma}{\gamma} + \frac{p\beta}{2n}\frac{\gamma}{\gamma}}$$

and the parallel efficiency by

$$E_p^{1D\text{-row}}(n) = \frac{S_p^{1D\text{-row}}(n)}{p} = \frac{1}{1 + \frac{p\log_2(p)\alpha}{2n^2}\frac{\gamma}{\gamma} + \frac{p\beta}{2n}\frac{\gamma}{\gamma}}.$$

An optimist's view Now, if one fixes p and lets n get large,

$$\lim_{n \rightarrow \infty} E_p(n) = \lim_{n \rightarrow \infty} \left[\frac{1}{1 + \frac{p\log_2(p)\alpha}{2n^2}\frac{\gamma}{\gamma} + \frac{p\beta}{2n}\frac{\gamma}{\gamma}} \right] = 1.$$

Thus, if one can make the problem large enough, eventually the parallel efficiency is nearly perfect. However, this assumes unlimited memory, so this analysis is not practical.

A pessimist's view In a *strong scalability* analysis, one fixes n and lets p get large, to get

$$\lim_{p \rightarrow \infty} E_p(n) = \lim_{p \rightarrow \infty} \left[\frac{1}{1 + \frac{p\log_2(p)\alpha}{2n^2}\frac{\gamma}{\gamma} + \frac{p\beta}{2n}\frac{\gamma}{\gamma}} \right] = 0.$$

Thus, eventually the parallel efficiency becomes nearly nonexistent.

A realist's view In a more realistic view we increase the number of processors with the amount of data. This is called *weak scalability*, and it makes the amount of memory that is available to store the problem scale linearly with p .

Let M equal the number of floating point numbers that can be stored in a single node's memory. Then the aggregate memory is given by Mp . Let $n_{\max}(p)$ equal the largest problem size that can be stored in the aggregate memory of p nodes. Then, if *all* memory can be used for the matrix,

$$(n_{\max}(p))^2 = Mp \quad \text{or} \quad n_{\max}(p) = \sqrt{Mp}.$$

The question now becomes what the parallel efficiency for the largest problem that can be stored on p nodes:

$$\begin{aligned} E_p^{1D\text{-row}}(n_{\max}(p)) &= \frac{1}{1 + \frac{p\log_2(p)\alpha}{2(n_{\max}(p))^2}\frac{\gamma}{\gamma} + \frac{p\beta}{2n_{\max}(p)}\frac{\gamma}{\gamma}} \\ &= \frac{1}{1 + \frac{\log_2(p)\alpha}{2M}\frac{\gamma}{\gamma} + \frac{\sqrt{p}\beta}{2\sqrt{M}}\frac{\gamma}{\gamma}}. \end{aligned}$$

Now, if one analyzes what happens when the number of nodes becomes large, one finds that

$$\lim_{p \rightarrow \infty} E_p(n_{\max}(p)) = \lim_{p \rightarrow \infty} \left[\frac{1}{1 + \frac{\log_2(p)}{2M} \frac{\alpha}{\gamma} + \frac{\sqrt{p}}{2\sqrt{M}} \frac{\beta}{\gamma}} \right] = 0.$$

Thus, this parallel algorithm for matrix-vector multiplication does not scale.

If you take a close look at this expression for efficiency, you'll see that the main problem is the $1/\sqrt{p}$ part of the expression. This term involves a factor β , and if you follow the derivation backward you see that it comes from the time to send data between the processors. Informally this can be described as saying that the message size is too large to make the problem scalable. In fact, the message size is constant n , regardless the number of processors.

Alternatively, a realist realizes that there is a limited amount of time, T_{\max} , to get a computation done. Under the best of circumstances, that is, with zero communication overhead, the largest problem that we can solve in time T_{\max} is given by

$$T_p(n_{\max}(p)) = 2 \frac{(n_{\max}(p))^2}{p} \gamma = T_{\max}.$$

Thus

$$(n_{\max}(p))^2 = \frac{T_{\max}p}{2\gamma} \quad \text{or} \quad n_{\max}(p) = \frac{\sqrt{T_{\max}}\sqrt{p}}{\sqrt{2\gamma}}.$$

Then the parallel efficiency that is attained by the algorithm for the largest problem that can be solved in time T_{\max} is given by

$$E_{p,n_{\max}} = \frac{1}{1 + \frac{\log_2 p}{T} \alpha + \sqrt{\frac{p}{T}} \frac{\beta}{\gamma}}$$

and the parallel efficiency as the number of nodes becomes large approaches

$$\lim_{p \rightarrow \infty} E_p = \sqrt{\frac{T\gamma}{p\beta}}.$$

Again, efficiency cannot be maintained as the number of processors increases and the execution time is capped.

6.2.3 Matrix-vector product, partitioning by columns

Partition

$$A \rightarrow (A_0, A_1, \dots, A_{p-1}) \quad x \rightarrow \begin{pmatrix} x_0 \\ x_1 \\ \vdots \\ x_{p-1} \end{pmatrix}, \quad \text{and} \quad y \rightarrow \begin{pmatrix} y_0 \\ y_1 \\ \vdots \\ y_{p-1} \end{pmatrix},$$

6. High performance linear algebra

where $A_j \in \mathbb{R}^{n \times n_j}$ and $x_j, y_j \in \mathbb{R}^{n_j}$ with $\sum_{j=0}^{p-1} n_j = n$ and $n_j \approx n/p$.

We will start by assuming that A_j , x_j , and y_j are originally assigned to \mathcal{P}_j (but now A_i is a block of columns). In this algorithm by columns, processor i can compute the length n vector $A_i x_i$ without prior communication. These partial results then have to be added together

$$y \leftarrow \sum_i A_i x_i$$

in a *reduce-scatter* operation: each processor i scatters a part $(A_i x_i)_j$ of its result to processor j . The receiving processors then perform a reduction, adding all these fragments:

$$y_j = \sum_i (A_i x_i)_j.$$

The algorithm with costs is then given by:

Step	Cost (lower bound)
Locally compute $y^{(j)} = A_j x_j$	$\approx 2 \frac{n^2}{p} \gamma$
Reduce-scatter the $y^{(j)}$ s so that $y_i = \sum_{j=0}^{p-1} y_i^{(j)}$ is on \mathcal{P}_i	$\lceil \log_2(p) \rceil \alpha + \frac{p-1}{p} n \beta + \frac{p-1}{p} n \gamma$ $\approx \log_2(p) \alpha + n(\beta + \gamma)$

Cost analysis The total cost of the algorithm is given by, approximately,

$$T_p^{\text{1D-col}}(n) = 2 \frac{n^2}{p} \gamma + \underbrace{\log_2(p) \alpha + n(\beta + \gamma)}_{\text{Overhead}}$$

Notice that this is identical to the cost $T_p^{\text{1D-row}}(n)$, except with β replaced by $(\beta + \gamma)$. It is not hard to see that the conclusions about scalability are the same.

6.2.4 Two-dimensional partitioning

Next, partition

$$A \rightarrow \begin{pmatrix} A_{00} & A_{01} & \dots & A_{0,p-1} \\ A_{10} & A_{11} & \dots & A_{1,p-1} \\ \vdots & \vdots & \ddots & \vdots \\ A_{p-1,0} & A_{p-1,1} & \dots & A_{p-1,p-1} \end{pmatrix} \quad x \rightarrow \begin{pmatrix} x_0 \\ x_1 \\ \vdots \\ x_{p-1} \end{pmatrix}, \quad \text{and} \quad y \rightarrow \begin{pmatrix} y_0 \\ y_1 \\ \vdots \\ y_{p-1} \end{pmatrix},$$

where $A_{ij} \in \mathbb{R}^{n_i \times n_j}$ and $x_i, y_i \in \mathbb{R}^{n_i}$ with $\sum_{i=0}^{p-1} n_i = N$ and $n_i \approx N/\sqrt{P}$.

We will view the nodes as an $r \times c$ mesh, with $P = rc$, and index them as p_{ij} , with $i = 0, \dots, r-1$ and $j = 0, \dots, c-1$. The following illustration for a 12×12 matrix on a 3×4 processor grid illustrates the assignment of data to nodes, where the i, j “cell” shows the matrix and vector elements owned by p_{ij} :

x_0	x_3	x_6	x_9
$a_{00} \quad a_{01} \quad a_{02} \quad y_0$	$a_{03} \quad a_{04} \quad a_{05}$	$a_{06} \quad a_{07} \quad a_{08}$	$a_{09} \quad a_{0,10} \quad a_{0,11}$
$a_{10} \quad a_{11} \quad a_{12}$	$a_{13} \quad a_{14} \quad a_{15} \quad y_1$	$a_{16} \quad a_{17} \quad a_{18}$	$a_{19} \quad a_{1,10} \quad a_{1,11}$
$a_{20} \quad a_{21} \quad a_{22}$	$a_{23} \quad a_{24} \quad a_{25}$	$a_{26} \quad a_{27} \quad a_{28} \quad y_2$	$a_{29} \quad a_{2,10} \quad a_{2,11}$
$a_{30} \quad a_{31} \quad a_{32}$	$a_{33} \quad a_{34} \quad a_{35}$	$a_{37} \quad a_{37} \quad a_{38}$	$a_{39} \quad a_{3,10} \quad a_{3,11} \quad y_3$
x_1	x_4	x_7	x_{10}
$a_{40} \quad a_{41} \quad a_{42} \quad y_4$	$a_{43} \quad a_{44} \quad a_{45}$	$a_{46} \quad a_{47} \quad a_{48}$	$a_{49} \quad a_{4,10} \quad a_{4,11}$
$a_{50} \quad a_{51} \quad a_{52}$	$a_{53} \quad a_{54} \quad a_{55} \quad y_5$	$a_{56} \quad a_{57} \quad a_{58}$	$a_{59} \quad a_{5,10} \quad a_{5,11}$
$a_{60} \quad a_{61} \quad a_{62}$	$a_{63} \quad a_{64} \quad a_{65}$	$a_{66} \quad a_{67} \quad a_{68} \quad y_6$	$a_{69} \quad a_{6,10} \quad a_{6,11}$
$a_{70} \quad a_{71} \quad a_{72}$	$a_{73} \quad a_{74} \quad a_{75}$	$a_{77} \quad a_{77} \quad a_{78}$	$a_{79} \quad a_{7,10} \quad a_{7,11} \quad y_7$
x_2	x_5	x_8	x_{11}
$a_{80} \quad a_{81} \quad a_{82} \quad y_8$	$a_{83} \quad a_{84} \quad a_{85}$	$a_{86} \quad a_{87} \quad a_{88}$	$a_{89} \quad a_{8,10} \quad a_{8,11}$
$a_{90} \quad a_{91} \quad a_{92}$	$a_{93} \quad a_{94} \quad a_{95} \quad y_9$	$a_{96} \quad a_{97} \quad a_{98}$	$a_{99} \quad a_{9,10} \quad a_{9,11}$
$a_{10,0} \quad a_{10,1} \quad a_{10,2}$	$a_{10,3} \quad a_{10,4} \quad a_{10,5}$	$a_{10,6} \quad a_{10,7} \quad a_{10,8} \quad y_{10}$	$a_{10,9} \quad a_{10,10} \quad a_{10,11}$
$a_{11,0} \quad a_{11,1} \quad a_{11,2}$	$a_{11,3} \quad a_{11,4} \quad a_{11,5}$	$a_{11,7} \quad a_{11,7} \quad a_{11,8}$	$a_{11,9} \quad a_{11,10} \quad a_{11,11} \quad y_{11}$

In other words, p_{ij} owns the matrix block A_{ij} and parts of x and y . This makes possible the following algorithm:

- Since x_j is distributed over the j th column, the algorithm starts by collecting x_j on each processor p_{ij} by an *allgather* inside the processor columns.
- Each processor p_{ij} then computes $y_{ij} = A_{ij}x_j$. This involves no further communication.
- The result y_i is then collected by gathering together the pieces y_{ij} in each processor row to form y_i , and this is then distributed over the processor row. These two operations are in fact combined to form a *reduce-scatter*.
- If $r = c$, we can transpose the y data over the processors, so that it can function as the input for a subsequent matrix-vector product. If, on the other hand, we are computing $A^t Ax$, then y is now correctly distributed for the A^t product.

Algorithm The algorithm with cost analysis is

Step	Cost (lower bound)
Allgather x_i 's within columns	$\lceil \log_2(r) \rceil \alpha + \frac{r-1}{p} n\beta$ $\approx \log_2(r)\alpha + \frac{n}{c}\beta$
Perform local matrix-vector multiply	$\approx 2\frac{n^2}{p}\gamma$
Reduce-scatter y_i 's within rows	$\lceil \log_2(c) \rceil \alpha + \frac{c-1}{p} n\beta + \frac{c-1}{p} n\gamma$ $\approx \log_2(c)\alpha + \frac{n}{c}\beta + \frac{n}{c}\gamma$

Cost analysis The total cost of the algorithm is given by, approximately,

$$T_p^{r \times c}(n) = T_p^{r \times c}(n) = 2\frac{n^2}{p}\gamma + \underbrace{\log_2(p)\alpha + \left(\frac{n}{c} + \frac{n}{r}\right)\beta + \frac{n}{r}\gamma}_{\text{Overhead}}$$

6. High performance linear algebra

We will now make the simplification that $r = c = \sqrt{p}$ so that

$$T_p^{\sqrt{p} \times \sqrt{p}}(n) = T_p^{\sqrt{p} \times \sqrt{p}}(n) = 2 \frac{n^2}{p} \gamma + \underbrace{\log_2(p)\alpha + \frac{n}{\sqrt{p}}(2\beta + \gamma)}_{\text{Overhead}}$$

Since the sequential cost is $T_1(n) = 2n^2\gamma$, the speedup is given by

$$S_p^{\sqrt{p} \times \sqrt{p}}(n) = \frac{T_1(n)}{T_p^{\sqrt{p} \times \sqrt{p}}(n)} = \frac{2n^2\gamma}{2 \frac{n^2}{p} \gamma + \frac{n}{\sqrt{p}}(2\beta + \gamma)} = \frac{p}{1 + \frac{p \log_2(p) \alpha}{2n^2} \frac{\gamma}{\gamma} + \frac{\sqrt{p}(2\beta + \gamma)}{2n} \frac{\gamma}{\gamma}}$$

and the parallel efficiency by

$$E_p^{\sqrt{p} \times \sqrt{p}}(n) = \frac{1}{1 + \frac{p \log_2(p) \alpha}{2n^2} \frac{\gamma}{\gamma} + \frac{\sqrt{p}(2\beta + \gamma)}{2n} \frac{\gamma}{\gamma}}$$

We again ask the question what the parallel efficiency for the largest problem that can be stored on p nodes is.

$$\begin{aligned} E_p^{\sqrt{p} \times \sqrt{p}}(n_{\max}(p)) &= \frac{1}{1 + \frac{p \log_2(p) \alpha}{2n^2} \frac{\gamma}{\gamma} + \frac{\sqrt{p}(2\beta + \gamma)}{2n} \frac{\gamma}{\gamma}} \\ &= \frac{1}{1 + \frac{\log_2(p) \alpha}{2M} \frac{\gamma}{\gamma} + \frac{1}{2\sqrt{M}} \frac{(2\beta + \gamma)}{\gamma}} \end{aligned}$$

so that still

$$\lim_{p \rightarrow \infty} E_p^{\sqrt{p} \times \sqrt{p}}(n_{\max}(p)) = \lim_{p \rightarrow \infty} \frac{1}{1 + \frac{\log_2(p) \alpha}{2M} \frac{\gamma}{\gamma} + \frac{1}{2\sqrt{M}} \frac{(2\beta + \gamma)}{\gamma}} = 0.$$

However, $\log_2 p$ grows very slowly with p and is therefore considered to act much like a constant. In this case $E_p^{\sqrt{p} \times \sqrt{p}}(n_{\max}(p))$ decreases very slowly and the algorithm is considered to be scalable for practical purposes.

Note that when $r = p$ the 2D algorithm becomes the "partitioned by rows" algorithm and when $c = p$ it becomes the "partitioned by columns" algorithm. It is not hard to show that the 2D algorithm is scalable in the sense of the above analysis when $r = c$, as long as r/c is kept constant.

6.3 Scalability of LU factorization

A full analysis of the scalability of dense LU factorization is quite involved, so we will state without further proof that again a two-dimensional distribution is needed. However, we can identify a further complication. Since factorizations of any type² progress through a matrix, processors will be inactive for part of the time.

2. Gaussian elimination can be performed in right-looking, left-looking and Crout variants; see [127].

Exercise 6.3. Consider the regular right-looking Gaussian elimination

```

for k=1..n
    p = 1/a(k,k)
    for i=k+1,n
        for j=k+1,n
            a(i,j) = a(i,j)-a(i,k)*p*a(k,j)
    
```

Analyze the running time, speedup, and efficiency as a function of N , if we assume a one-dimensional distribution, and enough processors to store one column per processor. Show that speedup is limited.

Also perform this analysis for a two-dimensional decomposition where each processor stores one element.

For this reason, an *overdecomposition* is used, where the matrix is divided in more blocks than there are processors, and each processor stores several, non-contiguous, sub-matrices. We illustrate this in figure 6.4




Figure 6.4: One-dimensional cyclic distribution: assignment of four matrix columns to two processors, and the resulting mapping of storage to matrixcolumns

where we divide four block columns of a matrix to two processors: each processor stores in a contiguous block of memory two non-contiguous matrix columns.

Next, we illustrate in figure 6.5 that a matrix-vector product with such a matrix can be performed without knowing that the processors store non-contiguous parts of the matrix. All that is needed is that the input vector is also cyclicly distributed.

Exercise 6.4. Now consider a 4×4 matrix and a 2×2 processor grid. Distribute the matrix cyclicly both by rows and columns. Show how the matrix-vector product can again be performed using the contiguous matrix storage, as long as the input is distributed correctly. How is the output distributed? Show that more communication is needed than the reduction of the one-dimensional example.

Specifically, with $P < N$ processors, and assuming for simplicity $N = cP$, we let processor 0 store rows




Figure 6.5: Matrix-vector multiplication with a cyclically distributed matrix

$0, c, 2c, 3c, \dots$; processor 1 stores rows $1, c+1, 2c+1, \dots$, et cetera. This scheme can be generalized to a two-dimensional distribution, if $N = c_1P_1 = c_2P_2$ and $P = P_1P_2$. This is called a *2D cyclic distribution*. This scheme can be further extended by considering block rows and columns (with a small block size), and assigning to processor 0 the *block* rows $0, c, 2c, \dots$.

Exercise 6.5. Consider a square $n \times n$ matrix, and a square $p \times p$ processor grid, where p divides n without remainder. Consider the overdecomposition outlined above, and make a sketch of matrix element assignment for the specific case $n = 6, p = 2$. That is, draw an $n \times n$ table where location (i, j) contains the processor number that stores the corresponding matrix element. Also make a table for each of the processors describing the local to global mapping, that is, giving the global (i, j) coordinates of the elements in the local matrix. (You will find this task facilitated by using zero-based numbering.) Now write functions P, Q, I, J of i, j that describe the global to local mapping, that is, matrix element a_{ij} is stored in location $(I(i, j), J(i, j))$ on processor $(P(i, j), Q(i, j))$.

6.4 Parallel sparse matrix-vector product

In section 5.4 you saw a first discussion of sparse matrices, limited to use on a single processor. We will now go into parallelism aspects.

The dense matrix-vector product, as you saw above, required each processor to communicate with every other, and to have a local buffer of essentially the size of the global vector. In the sparse case, considerably less buffer space, as well as less communication, is needed. Let us analyze this case. We will assume that the matrix is distributed by block rows, where processor p owns the matrix rows with indices in some set I_p .

The line $y_i = y_i + a_{ij}x_j$ now has to take into account that a_{ij} can be zero. In particular, we need to consider that, for some pairs $i \in I_p, j \notin I_p$ no communication will be needed. Declaring for each $i \in I_p$ a sparsity pattern set

$$S_{p;i} = \{j : j \notin I_p, a_{ij} \neq 0\}$$

our multiplication instruction becomes

$$y_i += a_{ij}x_j \quad \text{if } j \in S_{p;i}.$$




Figure 6.6: A difference stencil applied to a two-dimensional square domain, distributed over processors. A cross-processor connection is indicated.

If we want to avoid, as above, a flood of small messages, we combine all communication into a single message per processor. Defining

$$S_p = \bigcup_{i \in I_p} S_{p;i},$$

the algorithm now becomes:

- Collect all necessary off-processor elements x_j with $j \in S_p$ into one buffer;
- Perform the matrix-vector product, reading all elements of x from local storage.

This whole analysis of course also applies to dense matrices. This becomes different if we consider where sparse matrices come from. Let us start with a simple case.

Recall figure 4.1, which illustrated a discretized boundary value problem on the simplest domain, a square, and let us now parallelize it. We do this by partitioning the domain; each processor gets the matrix rows corresponding to its subdomain. Figure 6.6 shows how this gives rise to connections between processors: the elements a_{ij} with $i \in I_p, j \notin I_p$ are now the ‘legs’ of the stencil that reach beyond a processor boundary. The set of all such j , formally defined as

$$G = \{j \notin I_p : \exists_{i \in I_p} : a_{ij} \neq 0\}$$

is known as the *ghost region* of a processor; see figure 6.7.

Exercise 6.6. Show that a one-dimensional partitioning of the domain leads to a partitioning of the matrix into block rows, but a two-dimensional partitioning of the domain does not. You can do this in the abstract, or you can illustrate it: take a 4×4 domain (giving a matrix of size 16), and partition it over 4 processors. The one-dimensional domain




Figure 6.7: The ghost region of a processor, induced by a stencil

partitioning corresponds to giving each processor one line out of the domain, while the two-dimensional partitioning gives each processor a 2×2 subdomain. Draw the matrices for these two cases.

Our crucial observation is now that, for each processor, the number of other processors it is involved with is strictly limited. This has implications for the efficiency of the operation.

6.4.1 Parallel efficiency of the sparse matrix-vector product

In the case of the dense matrix-vector product (section 6.2), partitioning the matrix over the processors by (block) rows did not lead to a scalable algorithm. Part of the reason was the increase in the number of neighbours that each processor needs to communicate with. Figure 6.6 shows that, for the matrix of a 5-five point stencil, this number is limited to four.

Exercise 6.7. Take a square domain and a partitioning of the variables of the processors as in figure 6.6. What is the maximum number of neighbours a processor needs to communicate with for the box stencil in figure 4.4? In three space dimensions, what is the number of neighbours if a 7-point central difference stencil is used?

The observation that each processor communicates with just a few neighbours stays intact if we go beyond square domains to more complicated physical objects. If a processor receives a more or less contiguous subdomain, the number of its neighbours will be limited. This implies that even in complicated problems each processor will only communicate with a small number of other processors. Compare this to the dense case where each processor had to receive data from every other processor. It is obvious that the sparse case is far more friendly to the interconnection network. (The fact that it is also more common for large systems may influence the choice of network to install if you are about to buy a new parallel computer.)

For square domains, this argument can easily be made formal. Let the unit domain $[0, 1]^2$ be partitioned over P processors in a $\sqrt{P} \times \sqrt{P}$ grid. From figure 6.6 we see that every processor communicates with at most four neighbours. Let the amount of work per processor be w and the communication time with each neighbour c . Then the time to perform the total work on a single processor is $T_1 = Pw$, and the parallel

time is $T_P = w + 4c$, giving a speed up of

$$S_P = Pw/(w + 4c) = P/(1 + 4c/w) \approx P(1 - 4c/w).$$

Exercise 6.8. Express c and w as functions of N and P , and show that the speedup is asymptotically optimal, under weak scaling of the problem.

Exercise 6.9. In this exercise you will analyze the parallel sparse matrix-vector product for a hypothetical, but realistic, parallel machine. Let the machine parameters be characterized by (see section 1.3.2):

- *Latency:* $\alpha = 1\mu s = 10^{-6}s$.
- *Bandwidth:* $1Gb/s$ corresponds to $\beta = 10^{-9}$.
- *Computation rate:* A per-core flops rate of $1Gflops$ means $\gamma = 10^9$. This number may seem low, but note that the matrix-vector product has less reuse than the matrix-matrix product, which can achieve close to peak performance, and that the sparse matrix-vector product is even more bandwidth-bound.

We assume 10^4 processors, and a five-point stencil matrix of size $N = 25 \cdot 10^{10}$. This means each processor stores $5 \cdot 8 \cdot N/p = 10^9$ bytes. If the matrix comes from a problem on a square domain, this means the domain was size $n \times n$ where $n = \sqrt{N} = 5 \cdot 10^5$. Case 1. Rather than dividing the matrix, we divide the domain, and we do this first by horizontal slabs of size $n \times (n/p)$. Argue that the communication complexity is $2(\alpha + n\beta)$ and computation complexity is $10 \cdot n \cdot (n/p)$. Show that the resulting computation outweighs the communication by a factor 250.

Case 2. We divide the domain into patches of size $(n/\sqrt{p}) \times (n/\sqrt{p})$. The memory and computation time are the same as before. Derive the communication time and show that it is better by a factor of 50.

Argue that the first case does not weakly scale: under the assumption that N/p is constant the speedup will go down. Argue that the second case does scale weakly.

The argument that a processor will only connect with a few neighbours is based on the nature of the scientific computations. It is true for FDM and FEM methods. In the case of the *Boundary Element Method (BEM)*, any subdomain needs to communicate with everything in a radius r around it. As the number of processors goes up, the number of neighbours per processor will also go up.

Exercise 6.10. Give a formal analysis of the speedup and efficiency of the BEM algorithm.

Assume again a unit amount of work w per processor and a time of communication c per neighbour. Since the notion of neighbour is now based on physical distance, not on graph properties, the number of neighbours will go up. Give T_1, T_p, S_p, E_p for this case.

There are also cases where a sparse matrix needs to be handled similarly to a dense matrix. For instance, Google's *Pagerank* algorithm (see section 8.2.2) has at its heart the repeated operation $x \leftarrow Ax$ where A is a sparse matrix with $A_{ij} \neq 0$ if web page j links to page i ; see section 8.2.2. This makes A a very sparse matrix, with no obvious structure, so every processor will most likely communicate with almost every other.

6.4.2 Memory behaviour of the sparse matrix-vector product

In section 1.6.8 you saw an analysis of the sparse matrix-vector product in the dense case, on a single processor. Some of the analysis carries over immediately to the sparse case, such as the fact that each matrix element is used only once and that the performance is bound by the bandwidth between processor and memory.

Regarding reuse of the input and the output vector, if the matrix is stored by rows, such as in CRS format (section 5.4.1.3), access to the output vector will be limited to one write per matrix row. On the other hand, the loop unrolling trick for getting reuse of the input vector can not be applied here. Code that combines two iterations is as follows:

```
for (i=0; i<M; i+=2) {
    s1 = s2 = 0;
    for (j) {
        s1 = s1 + a[i][j] * x[j];
        s2 = s2 + a[i+1][j] * x[j];
    }
    y[i] = s1; y[i+1] = s2;
}
```

The problem here is that if a_{ij} is nonzero, it is not guaranteed that $a_{i+1,j}$ is nonzero. The irregularity of the sparsity pattern makes optimizing the matrix-vector product hard. Modest improvements are possible by identifying parts of the matrix that are small dense blocks [14, 25, 130].

On a *GPU* the sparse matrix-vector product is also limited by memory bandwidth. Programming is now harder because the GPU has to work in data parallel mode, with many active threads.

An interesting optimization becomes possible if we consider the context in which the sparse matrix-vector product typically appears. The most common use of this operation is in iterative solution methods for linear systems (section 5.5), where it is applied with the same matrix in possibly hundreds of iterations. Thus we could consider leaving the matrix stored on the GPU and only copying the input and output vectors for each product operation.

6.4.3 The transpose product

In section 5.4.1.3 you saw that the code for both the regular and the transpose matrix-vector product are limited to loop orderings where rows of the matrix are traversed. (In section 1.5.2 you saw a discussion of computational effects of changes in loop order; in this case we are limited to row traversal by the storage format.)

In this section we will briefly look at the parallel transpose product. Equivalently to partitioning the matrix by rows and performing the transpose product, we look at a matrix stored and partitioned by columns and perform the regular product.

The algorithm for the product by columns can be given as:

```

 $y \leftarrow 0$ 
for  $j$ :
    for  $i$ :
         $y_i \leftarrow y_i + a_{ij}x_j$ 
    
```

Both in shared and distributed memory we distribute outer iterations over processors. The problem is then that each outer iteration updates the whole output vector. This is a problem: with shared memory it leads to multiple writes to locations in the output and in distributed memory it requires communication that is as yet unclear.

One way to solve this would be to allocate a private output vector $y^{(p)}$ for each process:

```

 $y^{(p)} \leftarrow 0$ 
for  $j \in$  the rows of processor  $p$ 
    for all  $i$ :
         $y_i^{(p)} \leftarrow y_i^{(p)} + a_{ji}x_j$ 
    
```

after which we sum $y \leftarrow \sum_p y^{(p)}$.

6.4.4 Setup of the sparse matrix-vector product

While in the square domain case it was easy for a processor to decide which are its neighbours, in the sparse case this is not so simple. The straightforward way to proceed is to have a preprocessing stage:

- Each processor makes an inventory of what non-local indices it needs; assuming that each processor knows what range of indices each other processor owns, it then decides which indices to get from what neighbours.
- Each processor sends a list of indices to each of its neighbours; this list will be empty for most of the neighbours, but we can not omit sending it.
- Each processor then receives these lists from all others, and draws up lists of which indices to send.

You will note that, even though the communication during the matrix-vector product involves only a few neighbours for each processor, giving a cost that is $O(1)$ in the number of processors, the setup involves all-to-all communications, which is $O(P)$ in the number of processors. The setup can be reduced to $O(\log P)$ with some trickery [40].

Exercise 6.11. The above algorithm for determining the communication part of the sparse matrix-vector product can be made far more efficient if we assume a matrix that is *structurally symmetric*: $a_{ij} \neq 0 \Leftrightarrow a_{ji} \neq 0$. Show that in this case no communication is needed to determine the communication pattern.

6.5 Computational aspects of iterative methods

All iterative methods feature the following operations:

- A matrix-vector product; this was discussed for the sequential case in section 5.4 and for the parallel case in section 6.4. In the parallel case, construction of FEM matrices has a complication that we will discuss in section 6.5.2.

- The construction of the preconditioner matrix $K \approx A$, and the solution of systems $Kx = y$. This was discussed in the sequential case in section 5.5.5. Below we will go into parallelism aspects in section 6.6.
- Some vector operations (including inner products, in general). These will be discussed next.

6.5.1 Vector operations

There are two types of vector operations in a typical iterative method: vector additions and inner products.

Exercise 6.12. Consider the CG method of section 5.5.10, figure 5.8, applied to the matrix from a 2D BVP; equation (4.14), First consider the unpreconditioned case $M = I$. Show that there is a roughly equal number of floating point operations are performed in the matrix-vector product and in the vector operations. Express everything in the matrix size N and ignore lower order terms. How would this balance be if the matrix had 20 nonzeros per row?

Next, investigate this balance between vector and matrix operations for the FOM scheme in section 5.5.8. Since the number of vector operations depends on the iteration, consider the first 50 iterations and count how many floating point operations are done in the vector updates and inner product versus the matrix-vector product. How many nonzeros does the matrix need to have for these quantities to be equal?

Exercise 6.13. Flop counting is not the whole truth. What can you say about the efficiency of the vector and matrix operations in an iterative method, executed on a single processor?

6.5.1.1 Vector additions

The vector additions are typically of the form $x \leftarrow x + \alpha y$ or $x \leftarrow \alpha x + y$. If we assume that all vectors are distributed the same way, this operation is fully parallel.

6.5.1.2 Inner products

Inner products are vector operations, but they are computationally more interesting than updates, since they involve communication.

When we compute an inner product, most likely every processor needs to receive the computed value. We use the following algorithm:

```

for processor  $p$  do
    compute  $a_p \leftarrow x_p^t y_p$  where  $x_p, y_p$  are the part of  $x, y$  stored on processor  $p$ 
    do a global reduction to compute  $a = \sum_p a_p$ 
    broadcast the result
Algorithm 1: Compute  $a \leftarrow x^t y$  where  $x, y$  are distributed vectors

```

The reduction and broadcast (which can be joined into an `Allreduce`) combine data over all processors, so they have a communication time that increases with the number of processors. This makes the inner

product potentially an expensive operation, and people have suggested a number of ways to reducing their impact on the performance of iterative methods.

Exercise 6.14. Iterative methods are typically used for sparse matrices. In that context, you can argue that the communication involved in an inner product can have a larger influence on overall performance than the communication in the matrix-vector product. What is the complexity of the matrix-vector product and the inner product as a function of the number of processors?

Here are some of the approaches that have been taken.

- The CG method has two inner products per iteration that are inter-dependent. It is possible to rewrite the method so that it computes the same iterates (in exact arithmetic, at least) but so that the two inner products per iteration can be combined. See [20, 22, 98, 135].
- It may be possible to overlap the inner product calculation with other, parallel, calculations [24].
- In the GMRES method, use of the classical Gram-Schmidt (GS) method takes far fewer independent inner product than the modified GS method, but it is less stable. People have investigated strategies for deciding when it is allowed to use the classic GS method [88].

6.5.2 Finite element matrix construction

The *FEM* leads to an interesting issue in parallel computing. For this we need to sketch the basic outline of how this method works. The FEM derives its name from the fact that the physical objects modeled are divided into small two or three dimensional shapes, the elements, such as triangles and squares in 2D, or pyramids and bricks in 3D. On each of these, the function we are modeling is then assumed to polynomial, often of a low degree, such as linear or bilinear.




Figure 6.8: A finite element domain, parallelization of the matrix construction, and parallelization of matrix element storage

The crucial fact is that a matrix element a_{ij} is then the sum of computations, specifically certain integrals, over all elements that contain both variables i and j :

$$a_{ij} = \sum_{e: i,j \in e} a_{ij}^{(e)}.$$

The computations in each element share many common parts, so it is natural to assign each element e uniquely to a processor P_e , which then computes all contributions $a_{ij}^{(e)}$. In figure 6.8 element 2 is assigned to processor 0 and element 4 to processor 1.

Now consider variables i and j and the matrix element a_{ij} . It is constructed as the sum of computations over domain elements 2 and 4, which have been assigned to different processors. Therefore, no matter what processor row i is assigned to, at least one processor will have to communicate its contribution to matrix element a_{ij} .

Clearly it is not possibly to make assignments P_e of elements and P_i of variables such that P_e computes in full the coefficients a_{ij} for all $i \in e$. In other words, if we compute the contributions locally, there needs to be some amount of communication to assemble certain matrix elements. For this reason, modern linear algebra libraries such as PETSc (see tutorial section B.6) allow any processor to set any matrix element.

6.6 Parallel preconditioners

Above (sections 5.5.5 and 5.5.5.1) we saw a couple of different choices of K . In this section we will begin the discussion of parallelization strategies. The discussion is continued in detail in the next sections.

6.6.1 Jacobi preconditioning

The Jacobi method (section 5.5.3) uses the diagonal of A as preconditioner. Applying this is as parallel as is possible: the statement $y \leftarrow K^{-1}x$ scales every element of the input vector independently. Unfortunately the improvement in the number of iterations with a Jacobi preconditioner is rather limited. Therefore we need to consider more sophisticated methods such ILU. Unlike with the Jacobi preconditioner, parallelism is then not trivial.

6.6.2 The trouble with parallel ILU

Above we saw that, in a flop counting sense, applying an ILU preconditioner (section 5.5.5.1) is about as expensive as doing a matrix-vector product. This is no longer true if we run our iterative methods on a parallel computer.

At first glance the operations are similar. A matrix-vector product $y = Ax$ looks like

```
for i=1..n
    y[i] = sum over j=1..n a[i,j]*x[j]
```

In parallel this would look like

```
for i=myfirstrow..mylastrow
    y[i] = sum over j=1..n a[i,j]*x[j]
```

Suppose that a processor has local copies of all the elements of A and x that it will need, then this operation is fully parallel: each processor can immediately start working, and if the work load is roughly equal, they will all finish at the same time. The total time for the matrix-vector product is then divided by the number of processors, making the speedup more or less perfect.

Consider now the forward solve $Lx = y$, for instance in the context of an ILU preconditioner:

```
for i=1..n
    x[i] = (y[i] - sum over j=1..i-1 ell[i,j]*x[j]) / a[i,i]
```

We can simply write the parallel code:

```
for i=myfirstrow..mylastrow
    x[i] = (y[i] - sum over j=1..i-1 ell[i,j]*x[j]) / a[i,i]
```

but now there is a problem. We can no longer say ‘suppose a processor has local copies of everything in the right hand side’, since the vector x appears both in the left and right hand side. While the matrix-vector product is in principle fully parallel over the matrix rows, this triangular solve code is recursive, hence sequential.

In a parallel computing context this means that, for the second processor to start, it needs to wait for certain components of x that the first processor computes. Apparently, the second processor can not start until the first one is finished, the third processor has to wait for the second, and so on. The disappointing conclusion is that in parallel only one processor will be active at any time, and the total time is the same as for the sequential algorithm. This is actually not a big problem in the dense matrix case, since parallelism can be found in the operations for handling a single row (see section 6.10), but in the sparse case it means we can not use incomplete factorizations without some redesign.

In the next few subsections we will see different strategies for finding preconditioners that perform efficiently in parallel.

6.6.3 Block Jacobi methods

Various approaches have been suggested to remedy this sequentiality the triangular solve. For instance, we could simply let the processors ignore the components of x that should come from other processors:

```
for i=myfirstrow..mylastrow
    x[i] = (y[i] - sum over j=myfirstrow..i-1 ell[i,j]*x[j])
           / a[i,i]
```

This is not mathematically equivalent to the sequential algorithm (technically, it is called a *block Jacobi* method with ILU as the *local solve*), but since we’re only looking for an approximation $K \approx A$, this is simply a slightly cruder approximation.

Exercise 6.15. Take the Gauss-Seidel code you wrote above, and simulate a parallel run. What is the effect of increasing the (simulated) number of processors?




Figure 6.9: Sparsity pattern corresponding to a block Jacobi preconditioner

The idea behind block methods can easily be appreciated pictorially; see figure 6.9. In effect, we make an ILU of the matrix that we get by ignoring all connections between processors. Since in a BVP all points influence each other (see section 4.2.1), using a less connected preconditioner will increase the number of iterations if executed on a sequential computer. However, block methods are parallel and, as we observed above, a sequential preconditioner is very inefficient in a parallel context, so we put up with this increase in iterations.

6.6.4 Parallel ILU

The Block Jacobi preconditioner operates by decoupling domain parts. While this may give a method that is highly parallel, it may give a higher number of iterations than a true ILU preconditioner. (A theoretical argument can be made that this decoupling decreases the efficiency of the iterative method; see section 4.2.1.) Fortunately it is possible to have a parallel ILU method.

In section 6.7.2 you saw the combination of *graph colouring* and permutation. Let P be the permutation that groups like-coloured variables together, then $\tilde{A} = P^t AP$ is a matrix with the following structure:

- \tilde{A} has a block structure with the number of blocks equal to the number of colours in the adjacency graph of A ; and
- each diagonal block is a diagonal matrix.

Now, if you are performing an iterative system solution and you are looking for a parallel preconditioner you can use this permuted matrix. Consider solving $Ly = x$ with the permuted system. We write the usual algorithm (section 5.3.5) as

```

for c in the set of colours:
    for i in the variables of colour c:
         $y_i \leftarrow x_i - \sum_{j < i} \ell_{ij} y_j$ 

```

Exercise 6.16. Show that the flop count of solving a system $LUX = y$ remains the same (in the highest order term) when you from an ILU factorization in the natural ordering to one in the colour-permuted ordering.




Figure 6.10: A partitioned domain with coloured nodes




Figure 6.11: Solving a parallel multicolour ILU in four steps

Where does all this colouring get us? Solving is still sequential... Well, it is true that the outer loop over the colours is sequential, but all the points of one colour are independent of each other, so they can be solved at the same time. So if we use an ordinary domain partitioning and combine that with a multi-colouring (see figure 6.10), the processors are all active during all the colour stages; see figure 6.11. Ok, if you take a close look at that figure you'll see that one processor is not active in the last colour. With large numbers of nodes per processor this is unlikely to happen, but there may be some load imbalance.

6.7 Ordering strategies and parallelism

6.7.1 Nested dissection

Above, you have seen several examples of ordering the variables in the domain other than with the *lexicographic ordering*. In this section you will see the *nested dissection ordering*, which was initially designed as a way to reduce fill-in. However, it is also advantageous in a parallel computing context.

Nested dissection is a recursive process for determining a nontrivial ordering of the unknowns in a domain. In the first step, the computational domain is split in two parts, with a dividing strip between them; see

figure 6.12. To be precise, the separator is wide enough that there are no connections between the left and right subdomain.




Figure 6.12: Domain dissection into two unconnected subdomains and a separator

right *subdomain*. The resulting matrix A^{DD} has a 3×3 structure, corresponding to the three divisions of the domain. Since the subdomains Ω_1 and Ω_2 are not connected, the submatrices A_{12}^{DD} and A_{21}^{DD} are zero.

$$A^{\text{DD}} = \begin{pmatrix} A_{11} & \emptyset & A_{13} \\ \emptyset & A_{22} & A_{23} \\ A_{31} & A_{32} & A_{33} \end{pmatrix} = \left\{ \begin{array}{c|cc|c} * & * & & 0 \\ * & * & * & \vdots \\ \ddots & \ddots & \ddots & 0 \\ * & * & * & * \\ & * & * & 0 \\ \hline & & & 0 \\ & & & \vdots \\ \emptyset & & & 0 \\ & & & \vdots \\ & & & 0 \\ \hline 0 & \dots & \dots & 0 & * & 0 & \dots & \dots & 0 & * & * \end{array} \right\} \begin{array}{l} (n^2 - n)/2 \\ \\ \\ \\ \\ \\ \hline \end{array} \begin{array}{l} (n^2 - n)/2 \\ \\ \\ \\ \\ \\ \hline \\ \\ \\ \\ \\ \\ \hline \\ \\ \\ \\ \\ \\ \hline \end{array} n$$

This process of dividing the domain by a separator is also called *domain decomposition* or *substructuring*, although this name is also associated with the mathematical analysis of the resulting matrices [9]. In this example of a rectangular domain it is of course trivial to find a separator. However, for the type of equations we get from BVPs it is usually feasible to find a separator efficiently for any domain [92]; see also section A.5.5.1.

Let us now consider the *LU* factorization of this matrix. If we factor it in terms of the 3×3 block structure,

we get

$$A^{\text{DD}} = LU = \begin{pmatrix} I & & \\ \emptyset & I & \\ A_{31}A_{11}^{-1} & A_{32}A_{22}^{-1} & I \end{pmatrix} \begin{pmatrix} A_{11} & \emptyset & A_{13} \\ A_{22} & A_{23} & \\ S_{33} & & \end{pmatrix}$$

where

$$S_{33} = A_{33} - A_{31}A_{11}^{-1}A_{13} - A_{32}A_{22}^{-1}A_{23}.$$

The important fact here is that

- the contributions $A_{31}A_{11}^{-1}A_{13}$ and $A_{32}A_{22}^{-1}A_{23}$ can be computed simultaneously, so the factorization is largely parallel; and
- both in the forward and backward solve, components 1 and 2 of the solution can be computed simultaneously, so the solution process is also largely parallel.

The third block can not trivially be handled in parallel, so this introduces a sequential component in the algorithm. We also need to take a closer look at the structure of S_{33} .

Exercise 6.17. In section 5.4.3.1 you saw the connection between LU factorization and graph theory: eliminating a node leads to a graph with that node removed, but with certain new connections added. Show that, after eliminating the first two sets of variables, the graph of the remaining matrix on the separator will be fully connected.

The upshot is that after eliminating all the variables in blocks 1 and 2 we are left with a matrix S_{33} that is fully dense of size $n \times n$.

The introduction of a separator gave us a factorization that was two-way parallel. Now we iterate this process: we put a separator inside blocks 1 and 2 (see figure 6.13), which gives the following matrix structure:




Figure 6.13: A four-way domain decomposition

$$A^{\text{DD}} = \left(\begin{array}{cccc|ccc} A_{11} & & & A_{15} & A_{17} \\ & A_{22} & & A_{25} & A_{27} \\ & & A_{33} & & A_{36} & A_{37} \\ & & & A_{44} & A_{46} & A_{47} \\ \hline A_{51} & A_{52} & & A_{55} & & A_{57} \\ & A_{63} & A_{64} & & A_{66} & A_{67} \\ \hline A_{71} & A_{72} & A_{73} & A_{74} & A_{75} & A_{76} & A_{77} \end{array} \right)$$

(Note the similarities with the ‘arrow’ matrix in section 5.4.3.4, and recall the argument that this led to lower fill-in.) The LU factorization of this is:

$$\left(\begin{array}{cccc|ccc} I & & & & & & \\ & I & & & & & \\ & & I & & & & \\ & & & I & & & \\ \hline A_{51}A_{11}^{-1} & A_{52}A_{22}^{-1} & & & I & & \\ A_{63}A_{33}^{-1} & A_{64}A_{44}^{-1} & & & & I & \\ \hline A_{71}A_{11}^{-1} & A_{72}A_{22}^{-1} & A_{73}A_{33}^{-1} & A_{74}A_{44}^{-1} & A_{75}S_5^{-1} & A_{76}S_6^{-1} & I \end{array} \right) .$$

$$\left(\begin{array}{cccc|ccc} A_{11} & & & A_{15} & A_{17} \\ & A_{22} & & A_{25} & A_{27} \\ & & A_{33} & & A_{36} & A_{37} \\ & & & A_{44} & A_{46} & A_{47} \\ \hline & & & S_5 & & A_{57} \\ & & & S_6 & & A_{67} \\ \hline & & & & & S_7 \end{array} \right)$$

where

$$\begin{aligned} S_5 &= A_{55} - A_{51}A_{11}^{-1}A_{15} - A_{52}A_{22}^{-1}A_{25}, & S_6 &= A_{66} - A_{63}A_{33}^{-1}A_{36} - A_{64}A_{44}^{-1}A_{46} \\ S_7 &= A_{77} - \sum_{i=1,2,3,4} A_{7i}A_{ii}^{-1}A_{i7} - \sum_{i=5,6} A_{7i}S_i^{-1}A_{i7}. \end{aligned}$$

Constructing the factorization now goes as follows:

- Blocks A_{ii} are factored in parallel for $i = 1, 2, 3, 4$; similarly the contributions $A_{5i}A_{ii}^{-1}A_{i5}$ for $i = 1, 2$, $A_{6i}A_{ii}^{-1}A_{i6}$ for $i = 3, 4$, and $A_{7i}A_{ii}^{-1}A_{i7}$ for $i = 1, 2, 3, 4$ can be constructed in parallel.
- The Schur complement matrices S_5, S_6 are formed and subsequently factored in parallel, and the contributions $A_{7i}S_i^{-1}A_{i7}$ for $i = 5, 6$ are constructed in parallel.
- The Schur complement S_7 is formed and factored.

Analogous to the above reasoning, we conclude that after eliminating blocks 1,2,3,4 the updated matrices S_5, S_6 are dense of size $n/2$, and after eliminating blocks 5,6 the Schur complement S_7 is dense of size n .

Exercise 6.18. Show that solving a system with A^{DD} has a similar parallelism to constructing the factorization as described above.

For future reference, we will call the sets 1 and 2 each others’ siblings, and similarly for 3 and 4. The set 5 is the parent of 1 and 2, 6 is the parent of 3 and 4; 5 and 6 are siblings and 7 is the parent of 5 and 6.

6.7.1.1 Domain decomposition

In figure 6.13 we divided the domain four ways by a recursive process. This leads up to our discussion of nested dissection. It is also possible to immediately split a domain in any number of strips, or in a grid of subdomains. As long as the separators are wide enough, this will give a matrix structure with many independent subdomains. As in the above discussion, an LU factorization will be characterized by

- parallel processing of the subdomains, both in the factorization and L, U solves, and
- a system to be solved on the separator structure.




Figure 6.14: One-way domain decomposition

Exercise 6.19. The matrix from a two-dimensional BVP has a block tridiagonal structure. Divide the domain in four strips, that is, using three separators (see figure 6.14). Note that the separators are uncoupled in the original matrix.

Now sketch the sparsity structure of the resulting system on the separators are elimination of the subdomains. Show that the system is block tridiagonal.

6.7.1.2 Complexity

The nested dissection method repeats the above process until the subdomains are very small. For a theoretical analysis, we keep dividing until we have subdomains of size 1×1 , but in practice one could stop at sizes such as 32, and use an efficient dense solver to factor and invert the blocks.

To derive the complexity of the algorithm, we take another look at figure 6.13, and see that complexity argument, the total space a full recursive nested dissection factorization needs is the sum of

- one dense matrix on a separator of size n , plus
- two dense matrices on separators of size $n/2$,
- taking together $3/2 n^2$ space and $5/12 n^3$ time;
- the two terms above then get repeated on four subdomains of size $(n/2) \times (n/2)$.

With the observation that $n = \sqrt{N}$, this sums to

$$\begin{aligned} \text{space} &= 3/2n^2 + 4 \cdot 3/2(n/2)^2 + \dots \\ &= N(3/2 + 3/2 + \dots) \log n \text{ terms} \\ &= O(N \log N) \end{aligned}$$

$$\begin{aligned} \text{time} &= 5/12n^3/3 + 4 \cdot 5/12(n/2)^3/3 + \dots \\ &= 5/12N^{3/2}(1 + 1/4 + 1/16 + \dots) \\ &= O(N^{3/2}) \end{aligned}$$

Apparently, we now have a factorization that is parallel to a large extent, and that is done in $O(N \log N)$ space, rather than $O(N^{3/2})$ (see section 5.4.3.3). The factorization time has also gone down from $O(N^2)$ to $O(N^{3/2})$.

Unfortunately, this space savings only happens in two dimensions: in three dimensions we need

- one separator of size $n \times n$, taking $(n \times n)^2 = N^{4/3}$ space and $1/3 \cdot (n \times n)^3 = 1/3 \cdot N^2$ time,
- two separators of size $n \times n/2$, taking $N^{3/2}/2$ space and $1/3 \cdot N^2/4$ time,
- four separators of size $n/2 \times n/2$, taking $N^{3/2}/4$ space and $1/3 \cdot N^2/16$ time,
- adding up to $7/4N^{3/2}$ space and $21/16N^2/3$ time;
- on the next level there are 8 subdomains that contribute these terms with $n \rightarrow n/2$ and therefore $N \rightarrow N/8$.

This makes the total space

$$\frac{7}{4}N^{3/2}(1 + (1/8)^{4/3} + \dots) = O(N^{3/2})$$

and the total time

$$\frac{21}{16}N^2(1 + 1/16 + \dots)/3 = O(N^2).$$

We no longer have the tremendous savings of the 2D case. A much more complicated analysis shows that the order improvement holds for general problems in 2D, and that 3D in general has a higher complexity [91].

6.7.1.3 Parallelism

The nested dissection method clearly introduces a lot of parallelism, and we can characterize it as task parallelism (section 2.4.3): associated with each separator is a task of factoring its matrix, and later one of solving a linear system on its variables. However, the tasks are not independent: in figure 6.13 the factorization on domain 7 has to wait for 5 and 6, and they have to wait for 1,2,3,4. Thus, we have tasks

with dependencies in the form of a tree: each separator matrix can be factored only when its children have been factored.

Mapping these tasks to processors is not trivial. First of all, if we are dealing with shared memory we can use a simple task queue:

```

Queue ← {}

for all bottom level subdomains  $d$  do
    add  $d$  to the Queue

while Queue is not empty do
    if a processor is idle then
        assign a queued task to it

    if a task is finished AND its sibling is finished then
        add its parent to the queue

```

The main problem here is that at some point we will have more processors than tasks, thus causing load unbalance. This problem is made more severe by the fact that the last tasks are also the most substantial, since the separators double in size from level to level. (Recall that the work of factoring a dense matrix goes up with the third power of the size!) Thus, for the larger separators we have to switch from task parallelism to medium-grained parallelism, where processors collaborate on factoring a block.

With distributed memory, we can now solve the parallelism problem with a simple task queue, since it would involve moving large amounts of data. (But recall that work is a higher power of the matrix size, which this time works in our favour, making communication relatively cheap.) The solution is then to use some form of domain decomposition. In figure 6.13 we could have four processors, associated with block 1,2,3,4. Processors 1 and 2 would then negotiate which one factors block 5 (and similarly processors 3 and 4 and block 6), or they could both do it redundantly.

6.7.1.4 Preconditioning

As with all factorizations, it is possible to turn the nested dissection method into a preconditioner by making the factorization incomplete. (For the basic idea of incomplete factorizations, see section 5.5.1). However, here the factorization is formulated completely in terms of *block matrices*, and the division by the pivot element becomes an inversion or system solution with the pivot block matrix. We will not go into this further; for details see the literature [4, 36, 99].

6.7.2 Variable reordering and colouring: independent sets

Another permutation of the problem variables is based on graph colouring (section A.5.3). The direct goal here is to maximize available parallelism.



Figure 6.15: Red-black ordering of points on a line

Let us take a simple example, where A is a tridiagonal matrix. The equation $Ax = b$ looks like

$$\begin{pmatrix} a_{11} & a_{12} & & & \emptyset \\ a_{21} & a_{22} & a_{23} & & \\ & a_{32} & a_{33} & a_{34} & \\ \emptyset & \ddots & \ddots & \ddots & \end{pmatrix} \begin{pmatrix} x_1 \\ x_2 \\ x_3 \\ \vdots \end{pmatrix} = \begin{pmatrix} y_1 \\ y_2 \\ y_3 \\ \vdots \end{pmatrix}$$

We observe that x_i directly depends on x_{i-1} and x_{i+1} , but not x_{i-2} or x_{i+2} . Thus, let us see what happens if we permute the indices to group every other component together.

Pictorially, we take the points $1, \dots, n$ and colour them red and black (figure 6.15), then we permute them to first take all red points, and subsequently all black ones. The correspondingly permuted matrix looks as follows:

$$\begin{pmatrix} a_{11} & & a_{12} & & \\ & a_{33} & & a_{32} & a_{34} \\ & & a_{55} & & \ddots & \ddots \\ & & & \ddots & \ddots & \\ a_{21} & a_{23} & & a_{22} & & \\ a_{43} & a_{45} & & & a_{44} & \\ & \ddots & \ddots & & & \ddots \end{pmatrix} \begin{pmatrix} x_1 \\ x_3 \\ x_5 \\ \vdots \\ x_2 \\ x_4 \\ \vdots \end{pmatrix} = \begin{pmatrix} y_1 \\ y_3 \\ y_5 \\ \vdots \\ y_2 \\ y_4 \\ \vdots \end{pmatrix}$$

With this permuted A , the Gauss-Seidel matrix $D_A + L_A$ looks like

$$\begin{pmatrix} a_{11} & & \emptyset & & \\ & a_{33} & & & \\ & & a_{55} & & \\ & & & \ddots & \\ a_{21} & a_{23} & & a_{22} & & \\ a_{43} & a_{45} & & & a_{44} & \\ & \ddots & \ddots & & & \ddots \end{pmatrix}$$

What does this buy us? Well, let's spell out the solution of a system $Lx = y$.

```

for  $i = 1, 3, 5, \dots$  do
    solve  $x_i \leftarrow y_i/a_{ii}$ 

for  $i = 2, 4, 6, \dots$  do
    compute  $t = a_{ii-1}x_{i-1} + a_{ii+1}x_{i+1}$ 
    solve  $x_i \leftarrow (y_i - t)/a_{ii}$ 

```

Apparently the algorithm has three stages that are each parallel over half the domain points. This is illustrated in figure 6.16. Theoretically we could accomodate a number of processors that is half the number of




Figure 6.16: Red-black solution on a 1d domain

the domain points, but in practice each processor will have a subdomain. Now you can see in figure 6.17 how this causes a very modest amount of communication: each processor sends at most the data of two red points to its neighbours.




Figure 6.17: Parallel red-black solution on a 1d domain

Red-black ordering can be applied to two-dimensional problems too. Let us apply a red-black ordering to the points (i, j) where $1 \leq i, j \leq n$. Here we first apply a successive numbering to the odd points on the first line $(1, 1), (3, 1), (5, 1), \dots$, then the even points of the second line $(2, 2), (4, 2), (6, 2), \dots$, the odd points on the third line, et cetera. Having thus numbered half the points in the domain, we continue with the even points in the first line, the odd points in the second, et cetera. As you can see in figure 6.18, now the red points are only connected to black points, and the other way around. In graph theoretical terms, you have found a *colouring* (see appendix A.5 for the definition of this concept) of the matrix graph with two colours.




Figure 6.18: Red-black ordering of the variables of a two-dimensional domain

Exercise 6.20. Apply the red-black ordering to the 2D BVP (4.10). Sketch the resulting matrix structure.

The red-black ordering is a simple example of *graph colouring* (sometimes called *multi-colouring*). In simple cases, such as the unit square domain we considered in section 4.2.2.2 or its extension to 3D, the *colour number* of the adjacency graph is easily determined.

Exercise 6.21. You saw that a red-black ordering of unknowns coupled with the regular five-point star stencil give two subsets of variables that are not connected among themselves, that is, they form a two-colouring of the matrix graph. Can you find a colouring if nodes are connected by the second stencil in figure 4.4?

There is a simple bound for the number of colours needed for the graph of a sparse matrix: the number of colours is at most $d + 1$ where d is the degree of the graph. To see that we can colour a graph with degree d using $d + 1$ colours, consider a node with degree d . No matter how its neighbours are coloured, there is always an unused colour among the $d + 1$ available ones.

Exercise 6.22. Consider a sparse matrix, where the graph can be coloured with d colours. Permute the matrix by first enumerating the unknowns of the first colour, then the second colour, et cetera. What can you say about the sparsity pattern of the resulting permuted matrix?

If you are looking for a direct solution of the linear system you can repeat the process of colouring and permuting on the matrix that remains after you have eliminated one colour. In the case of a tridiagonal matrix you saw that this remaining matrix was again tridiagonal, so it is clear how to continue the process. This is called *recursive doubling*. If the matrix is not tridiagonal but *block tridiagonal*, this operation can be performed on blocks.

6.8 Operator splitting

In some contexts, it is necessary to perform implicit calculations through all directions of a two or three-dimensional array. For example, in section 4.3 you saw how the implicit solution of the heat equation gave

rise to repeated systems

$$(\alpha I + \frac{d^2}{dx^2} + \frac{d^2}{dy^2})u^{(t+1)} = u^{(t)} \quad (6.2)$$

Without proof, we state that the time-dependent problem can also be solved by

$$(\beta I + \frac{d^2}{dx^2})(\beta I + \frac{d^2}{dy^2})u^{(t+1)} = u^{(t)} \quad (6.3)$$

for suitable β . This scheme will not compute the same values on each individual time step, but it will converge to the same steady state. The scheme can also be used as a preconditioner in the BVP case.

This approach has considerable advantages, mostly in terms of operation counts: the original system has to be solved either making a factorization of the matrix, which incurs *fill-in*, or by solving it iteratively.

Exercise 6.23. Analyze the relative merits of these approaches, giving rough operation counts.

Consider both the case where α has dependence on t and where it does not. Also discuss the expected speed of various operations.

A further advantage appears when we consider the parallel solution of (6.3). Note that we have a two-dimensional set of variables u_{ij} , but the operator $I + d^2u/dx^2$ only connects $u_{ij}, u_{ij-1}, u_{ij+1}$. That is, each line corresponding to an i value can be processed independently. Thus, both operators can be solved fully parallel using a one-dimensional partition on the domain. The solution of a the system in (6.2), on the other hand, has limited parallelism.

Unfortunately, there is a serious complication: the operator in x direction needs a partitioning of the domain in on direction, and the operator in y in the other. The solution usually taken is to transpose the u_{ij} value matrix in between the two solves, so that the same processor decomposition can handle both. This transposition can take a substantial amount of the processing time of each time step.

Exercise 6.24. Discuss the merits of and problems with a two-dimensional decomposition of the domain, using a grid of $P = p \times p$ processors. Can you suggest a way to ameliorate the problems?

One way to speed up these calculations, is to replace the implicit solve, by an explicit operation; see section 6.9.3.

6.9 Parallelism and implicit operations

In the discussion of IBVPs (section 4.1.2.2) you saw that implicit operations can have great advantages from the point of numerical stability. However, you also saw that they make the difference between methods based on a simple operation such as the matrix-vector product, and ones based on the more complicated linear system solution. There are further problems with implicit methods when you start computing in parallel.

Exercise 6.25. Let A be the matrix

$$A = \begin{pmatrix} a_{11} & & \emptyset & \\ a_{21} & a_{22} & & \\ & \ddots & \ddots & \\ \emptyset & & a_{n,n-1} & a_{nn} \end{pmatrix}. \quad (6.4)$$

Show that the matrix vector product $y \leftarrow Ax$ and the system solution $x \leftarrow A^{-1}y$, obtained by solving the triangular system $Ax = y$, not by inverting A , have the same operation count.

Now consider parallelizing the product $y \leftarrow Ax$. Suppose we have n processors, and each processor i stores x_i and the i -th row of A . Show that the product Ax can be computed without idle time on any processor but the first.

Can the same be done for the solution of the triangular system $Ax = y$? Show that the straightforward implementation has every processor idle for an $(n - 1)/n$ fraction of the computation.

We will now see a number of ways of dealing with this inherently sequential component.

6.9.1 Wavefronts

Above, you saw that solving a lower triangular system of size N can have sequential time complexity of N steps. In practice, things are often not quite that bad. Implicit algorithms such as solving a triangular system are inherently sequential, but the number of steps can be less than is apparent at first.

Exercise 6.26. Take another look at the matrix from a two-dimensional BVP on the unit square, discretized with central differences. Derive the matrix structure if we order the unknowns by diagonals. What can you say about the sizes of the blocks and the structure of the blocks themselves?


Let us take another look at figure 4.1 that describes the difference stencil of a two-dimensional BVP. The corresponding picture for the lower triangular factor is in figure 6.19. This describes the sequentiality of the lower triangular solve process $x \leftarrow L^{-1}y$:

$$x_k = y_k - \ell_{k,k-1}x_{k-1} - \ell_{k,k-n}x_{k-n}$$

In other words, the value at point k can be found if its neighbours to the left (that is, variable $k - 1$) and below (variable $k - n$) are known.

Turning this around, we see that, if we know x_1 , we can not only find x_2 , but also x_{n+1} . In the next step we can determine x_3 , x_{n+2} , and x_{2n+1} . Continuing this way, we can solve x by wavefronts: the values of x on each wavefront are independent, so they can be solved in parallel in the same sequential step.

Exercise 6.27. Finish this argument. What is the maximum number of processors we can employ, and what is the number of sequential steps? What is the resulting efficiency?

Figure 6.19: The difference stencil of the L factor of the matrix of a two-dimensional BVP

6.9.2 Recursive doubling

One strategy for dealing with recurrences is *recursive doubling*, which you already saw in exercise 1.4. Here we will discuss it in a more systematic manner. First, take the matrix from (6.4) and scale it to be of the form

$$\begin{pmatrix} 1 & & \emptyset \\ b_{21} & 1 & \\ \ddots & \ddots & \\ \emptyset & b_{n,n-1} & 1 \end{pmatrix}$$

which we write as $A = I + B$.

Exercise 6.28. How does solving the system $(I + B)x = y$ help in solving $Ax = y$? What are the operation counts of solving the system in the two different ways?

Now we do something that looks like Gaussian elimination, except that we do not start with the first row, but the second. (What would happen if you did Gaussian elimination or LU decomposition on the matrix $I + B$?) We use the second row to eliminate b_{32} :

$$\begin{pmatrix} 1 & & \emptyset \\ & 1 & \\ -b_{32} & 1 & \\ \ddots & \ddots & \\ \emptyset & & 1 \end{pmatrix} \times \begin{pmatrix} 1 & & \emptyset \\ b_{21} & 1 & \\ b_{32} & 1 & \\ \ddots & \ddots & \\ \emptyset & b_{n,n-1} & 1 \end{pmatrix} = \begin{pmatrix} 1 & & \emptyset \\ b_{21} & 1 & \\ -b_{32}b_{21} & 0 & \\ \emptyset & b_{n,n-1} & 1 \end{pmatrix}$$

which we write as $L^{(2)}A = A^{(2)}$. We also compute $L^{(2)}y = y^{(2)}$ so that $A^{(2)}x = y^{(2)}$ has the same

solution as $Ax = y$. Solving the transformed system gains us a little: after we compute x_1 , x_2 and x_3 can be computed in parallel.

Now we repeat this elimination process by using the fourth row to eliminate b_{54} , the sixth row to eliminate b_{76} , et cetera. The final result is, summarizing all $L^{(i)}$ matrices:

$$\left(\begin{array}{cccccc|c} 1 & & & & & & \emptyset \\ 0 & 1 & & & & & \\ -b_{32} & 1 & 1 & & & & \\ & 0 & 1 & & & & \\ & & -b_{54} & 1 & & & \\ & & & 0 & 1 & & \\ & & & & -b_{76} & 1 & \\ & & & & \ddots & \ddots & \end{array} \right) \times (I+B) = \left(\begin{array}{cccccc|c} 1 & & & & & & \emptyset \\ b_{21} & 1 & & & & & \\ -b_{32}b_{21} & 0 & 1 & & & & \\ & & b_{43} & 1 & & & \\ & & & -b_{54}b_{43} & 0 & 1 & \\ & & & & b_{65} & 1 & \\ & & & & -b_{76}b_{65} & 0 & 1 \\ & & & & \ddots & \ddots & \ddots \end{array} \right)$$

which we write as $L(I + B) = C$, and solving $(I + B)x = y$ now becomes $Cx = L^{-1}y$.

This final result needs close investigation.

- First of all, computing $y' = L^{-1}y$ is simple. (Work out the details. How much parallelism is available?)
- Solving $Cx = y'$ is still sequential, but it no longer takes n steps: from x_1 we can get x_3 , from that we get x_5 , et cetera. In other words, there is only a sequential relationship between the odd numbered components of x .
- The even numbered components of x do not depend on each other, but only on the odd components: x_2 follows from x_1 , x_4 from x_3 , et cetera. Once the odd components have been computed, admittedly sequentially, this step is fully parallel.

We can describe the sequential solving of the odd components by itself:

$$\left(\begin{array}{ccc|c} 1 & & \emptyset & \\ c_{21} & 1 & & \\ \ddots & \ddots & & \\ \emptyset & c_{n,n-1} & 1 & \end{array} \right) \begin{pmatrix} x_1 \\ x_3 \\ \vdots \\ x_n \end{pmatrix} = \begin{pmatrix} y'_1 \\ y'_3 \\ \vdots \\ y'_n \end{pmatrix}$$

where $c_{i+1i} = -b_{2n+1,2n}b_{2n,2n-1}$. In other words, we have reduced a size n sequential problem to a sequential problem of the size kind and a parallel problem, both of size $n/2$. Now we can repeat this procedure recursively, reducing the original problem to a sequence of parallel operations, each half the size of the former.

The process of computing all partial sums through recursive doubling is also referred to as *parallel prefix*. In the abstract it can be applied to any associative operator.

6.9.3 Approximating implicit by explicit operations, series expansion

There are various reasons why it is sometimes allowed to replace an implicit operation, which, as you saw above, can be problematic in practice, by a different one that is practically more advantageous.

- Using an explicit method for the heat equation (section 4.3) instead of an implicit one is equally legitimate, as long as we observe step size restrictions on the explicit method.
- Tinkering with the preconditioner (section 5.5.7) in an iterative method is allowed, since it will only affect the speed of convergence, not the solution the method converges to. You already saw one example of this general idea in the *block Jacobi* method; section 6.6.3. In the rest of this section you will see how recurrences in the preconditioner, which are implicit operations, can be replaced by explicit operations, giving various computational advantages.

Solving a linear system is a good example of an implicit operation, and since this comes down to solving two triangular systems, let us look at ways of finding a computational alternative to solving a lower triangular system. If U is upper triangular and nonsingular, we let D be the diagonal of U , and we write $U = D(I - B)$ where B is an upper triangular matrix with a zero diagonal, also called a *strictly upper triangular matrix*; we say that $I - B$ is a *unit upper triangular matrix*.

Exercise 6.29. Let $A = LU$ be an LU factorization where L has ones on the diagonal. Show how solving a system $Ax = b$ can be done, involving only the solution of unit upper and lower triangular systems. Show that no divisions are needed during the system solution.

Our operation of interest is now solving the system $(I - B)x = y$. We observe that

$$(I - B)^{-1} = I + B + B^2 + \dots \quad (6.5)$$

and $B^n = 0$ where n is the matrix size (check this!), so we can solve $(I - B)x = y$ exactly by

$$x = \sum_{k=0}^{n-1} B^k y.$$

Of course, we want to avoid computing the powers B^k explicitly, so we observe that

$$\sum_{k=0}^1 B^k y = (I + B)y, \quad \sum_{k=0}^2 B^k y = (I + B(I + B))y, \quad \sum_{k=0}^3 B^k y = (I + B(I + B((I + B))))y, \quad (6.6)$$

et cetera. The resulting algorithm for evaluating $\sum_{k=0}^{n-1} B^k y$ is called *Horner's rule*, and you see that it avoids computing matrix powers B^k .

Exercise 6.30. Suppose that $I - B$ is bidiagonal. Show that the above calculation takes $n(n+1)$ operations. What is the operation count for computing $(I - B)x = y$ by triangular solution?

We have now turned an implicit operation into an explicit one, but unfortunately one with a high operation count. In practical circumstances, however, we can truncate the sum of matrix powers.

Exercise 6.31. Let A be the tridiagonal matrix

$$A = \begin{pmatrix} 2 & -1 & & & \emptyset \\ -1 & 2 & -1 & & \\ & \ddots & \ddots & \ddots & \\ & & & & -1 \\ \emptyset & & & -1 & 2 \end{pmatrix}$$

of the one-dimensional BVP from section 4.2.2.1.

1. Recall the definition of diagonal dominance in section 5.3.4. Is this matrix diagonally dominant?
2. Show that the pivots in an LU factorization of this matrix (without pivoting) satisfy a recurrence. Hint: show that after n elimination steps ($n \geq 0$) the remaining matrix looks like

$$A^{(n)} = \begin{pmatrix} d_n & -1 & & & \emptyset \\ -1 & 2 & -1 & & \\ & \ddots & \ddots & \ddots & \\ & & & -1 & 2 \\ \emptyset & & & & \end{pmatrix}$$

and show the relation between d_{n+1} and d_n .

3. Show that the sequence $n \mapsto d_n$ is descending, and derive the limit value.
4. Write out the L and U factors in terms of the d_n pivots.
5. Are the L and U factors diagonally dominant?

The above exercise implies (note that we did not actually prove it!) that for matrices from BVPs we find that $B^k \downarrow 0$, in element size and in norm. This means that we can approximate the solution of $(I - B)x = y$ by, for instance, $x = (I + B)y$ or $x = (I + B + B^2)y$. Doing this still has a higher operation count than the direct triangular solution, but it is computationally advantageous in at least two ways:

- The explicit algorithm has a better pipeline behaviour.
- The implicit algorithm has problems in parallel, as you have seen; the explicit algorithm is easily parallelized.

Of course, this approximation may have further implications for the stability of the overall numerical algorithm.

Exercise 6.32. Describe the parallelism aspects of Horner's rule; equation (6.6).

6.10 Block algorithms on multicore architectures

In section 5.3.7 you saw that certain linear algebra algorithms can be formulated in terms of submatrices. This point of view can be beneficial for the efficient execution of linear algebra operations on shared memory architectures such as current *multicore* processors.

As an example, let us consider the *Cholesky factorization*, which computes $A = LL^t$ for a symmetric positive definite matrix A ; see also section 5.3.2. Recursively, we can describe the algorithm as follows:

$$\text{Chol} \begin{pmatrix} A_{11} & A_{21}^t \\ A_{21} & A_{22} \end{pmatrix} = LL^t \quad \text{where} \quad L = \begin{pmatrix} L_{11} & 0 \\ \tilde{A}_{21} & \text{Chol}(A_{22} - \tilde{A}_{21}\tilde{A}_{21}^t) \end{pmatrix}$$

and where $\tilde{A}_{21} = A_{21}L_{11}^{-t}$, $A_{11} = L_{11}L_{11}^t$.

In practice, the block implementation is applied to a partitioning

$$\left(\begin{array}{c|cc} & \text{finished} \\ \hline A_{kk} & A_{k,>k} \\ \hline A_{>k,k} & A_{>k,>k} \end{array} \right)$$

where k is the index of the current block row, and the factorization is finished for all indices $< k$. The factorization is written as follows, using Blas names for the operations:

for $k = 1, \text{nblocks}$:

- Chol: factor $L_k L_k^t \leftarrow A_{kk}$
- Trsm: solve $\tilde{A}_{>k,k} \leftarrow A_{>k,k} L_k^{-t}$
- Gemm: form the product $\tilde{A}_{>k,k} \tilde{A}_{>k,k}^t$
- Syrk: symmetric rank- k update $A_{>k,>k} \leftarrow A_{>k,>k} - \tilde{A}_{>k,k} \tilde{A}_{>k,k}^t$

The key to parallel performance is to partition the indices $> k$ and write the algorithm in terms of these blocks:

$$\left(\begin{array}{c|ccc} & \text{finished} & & \\ \hline A_{kk} & A_{k,k+1} & A_{k,k+2} & \cdots \\ \hline A_{k+1,k} & A_{k+1,k+1} & A_{k+1,k+2} & \cdots \\ A_{k+2,k} & A_{k+2,k+2} & & \\ \vdots & \vdots & & \end{array} \right)$$

The algorithm now gets an extra level of inner loops:

for $k = 1, \text{nblocks}$:

- Chol: factor $L_k L_k^t \leftarrow A_{kk}$
- for $\ell > k$:
 - Trsm: solve $\tilde{A}_{\ell,k} \leftarrow A_{\ell,k} L_k^{-t}$
 - for $\ell_1, \ell_2 > k$:
 - Gemm: form the product $\tilde{A}_{\ell_1,k} \tilde{A}_{\ell_2,k}^t$
 - for $\ell_1, \ell_2 > k, \ell_1 \leq \ell_2$:
 - Syrk: symmetric rank- k update $A_{\ell_1,\ell_2} \leftarrow A_{\ell_1,\ell_2} - \tilde{A}_{\ell_1,k} \tilde{A}_{\ell_2,k}^t$

Now it is clear that the algorithm has a good deal of parallelism: the iterations in every ℓ -loop can be processed independently. However, these loops get shorter in every iteration of the outer k -loop, so it is not immediate how many processors we can accommodate. Moreover, it is not necessary to preserve the order of operations of the algorithm above. For instance, after

$$L_1 L_1^t = A_{11}, \quad A_{21} \leftarrow A_{21} L_1^{-t}, \quad A_{22} \leftarrow A_{22} - A_{21} A_{21}^t$$


the factorization $L_2 L_2^t = A_{22}$ can start, even if the rest of the $k = 1$ iteration is still unfinished. Instead of looking at the algorithm, it is a better idea to construct a *Directed Acyclic Graph (DAG)* (see section A.5 for a brief tutorial on graphs) of the tasks of all inner iterations. Figure 6.20 shows the DAG of all tasks of matrix of 4×4 blocks. This graph is constructed by simulating the Cholesky algorithm above, making a vertex for every task, adding an edge (i, j) if task j uses the output of task i .

Exercise 6.33. What is the diameter of this graph? Identify the tasks that lie on the path that determines the diameter. What is the meaning of these tasks in the context of the algorithm? This path is called the *critical path*. Its length determines the execution time of the computation in parallel, even if an infinite number of processors is available.

Exercise 6.34. Assume there are T tasks that all take a unit time to execute, and assume we have p processors. What is the theoretical minimum time to execute the algorithm? Now amend this formula to take into account the critical path; call its length C .

In the execution of the tasks a DAG, several observations can be made.

- If more than one update is made to a block, it is probably advantageous to have these updates be computed by the same process. This simplifies maintaining *cache coherence*.
- If data is used and later modified, the use must be finished before the modification can start. This can even be true if the two actions are on different processors, since the memory subsystem typically maintains cache coherence, so the modifications can affect the process that is reading the data. This case can be remedied by having a copy of the data in main memory, giving a reading process data that is reserved (see section 1.4.1).

Figure 6.20: Graph of task dependencies in a 4×4 Cholesky factorization

Chapter 7

Molecular dynamics

Molecular dynamics is a technique for simulating the atom-by-atom behavior of molecules and deriving macroscopic properties from these atomistic motions. It has application to biological molecules such as proteins and nucleic acids, as well as natural and synthetic molecules in materials science and nanotechnology. Molecular dynamics falls in the category of particle methods, which includes N-body problems in celestial mechanics and astrophysics, and many of the ideas presented here will carry over to these other fields. In addition, there are special cases of molecular dynamics including ab initio molecular dynamics where electrons are treated quantum mechanically and thus chemical reactions can be modeled. We will not treat these special cases, but will instead concentrate on *classical* molecular dynamics.

The idea behind molecular dynamics is very simple: a set of particles interact according to Newton's law of motion, $F = ma$. Given the initial particle positions and velocities, the particle masses and other parameters, as well as a model of the forces that act between particles, Newton's law of motion can be integrated numerically to give a trajectory for each of the particles for all future (and past) time. Commonly, the particles reside in a computational box with periodic boundary conditions.

A molecular dynamics time step is thus composed of two parts:

- 1: compute forces on all particles
- 2: update positions (integration).

The computation of the forces is the expensive part. State-of-the-art molecular dynamics simulations are performed on parallel computers because the force computation is costly and a vast number of time steps are required for reasonable simulation lengths. In many cases, molecular dynamics is applied to simulations on molecules with a very large number of atoms as well, e.g., up to a million for biological molecules and long time scales, and up to billions for other molecules and shorter time scales.

Numerical integration techniques are also of interest in molecular dynamics. For simulations that take a large number of time steps and for which the preservation of quantities such as energy is more important than order of accuracy, the solvers that must be used are different than the traditional ODE solvers presented in Chapter 4.

In the following, we will introduce force fields used for biomolecular simulations and discuss fast methods for computing these forces. Then we devote sections to the parallelization of molecular dynamics for short-range forces and the parallelization of the 3-D FFT used in fast computations of long-range forces. We

end with a section introducing the class of integration techniques that are suitable for molecular dynamics simulations. Our treatment of the subject of molecular dynamics in this chapter is meant to be introductory and practical; for more information, the text [45] is recommended.

7.1 Force Computation

7.1.1 Force Fields

In classical molecular dynamics, the model of potential energy and of the forces that act between atoms is called a *force field*. The force field is a tractable but approximate model of quantum mechanical effects which are computationally too expensive to determine for large molecules. Different force fields are used for different types of molecules, as well as for the same molecule by different researchers, and none are ideal.

In biochemical systems, commonly-used force fields model the potential energy function as the sum of bonded, van der Waals, and electrostatic (Coulomb) energy:

$$E = E_{\text{bonded}} + E_{\text{Coul}} + E_{\text{vdW}}$$

The potential is a function of the positions of all the atoms in the simulation. The force on an atom is the negative gradient of this potential at the position of the atom.

The bonded energy is due to covalent bonds in a molecule,

$$E_{\text{bonded}} = \sum_{\text{bonds}} k_i(r_i - r_{i,0})^2 + \sum_{\text{angles}} k_i(\theta_i - \theta_{i,0})^2 + \sum_{\text{torsions}} V_n(1 + \cos(n\omega - \gamma))$$

where the three terms are, respectively, sums over all covalent bonds, sums over all angles formed by two bonds, and sums over all dihedral angles formed by three bonds. The fixed parameters k_i , $r_{i,0}$, etc. depend on the types of atoms involved, and may differ for different force fields. Additional terms or terms with different functional forms are also commonly used.

The remaining two terms for the potential energy E are collectively called the nonbonded terms. Computationally, they form the bulk of the force calculation. The electrostatic energy is due to atomic charges and is modeled by the familiar

$$E_{\text{Coul}} = \sum_i \sum_{j>i} \frac{q_i q_j}{4\pi\epsilon_0 r_{ij}}$$

where the sum is over all pairs of atoms, q_i and q_j are the charges on atoms i and j , and r_{ij} is the distance between atoms i and j . Finally, the van der Waals energy approximates the remaining attractive and repulsive effects, and is commonly modeled by the Lennard-Jones function

$$E_{\text{vdW}} = \sum_i \sum_{j>i} 4\epsilon_{ij} \left[\left(\frac{\sigma_{ij}}{r_{ij}} \right)^{12} - \left(\frac{\sigma_{ij}}{r_{ij}} \right)^6 \right]$$

where ϵ_{ij} and σ_{ij} are force field parameters depending on atom types. At short distances, the repulsive (r^{12}) term is in effect, while at long distances, the dispersive (attractive, $-r^6$) term is in effect.

Parallelization of the molecular dynamics force calculation depends on parallelization each of these individual types of force calculations. The bonded forces are local computations in the sense that for a given atom, only nearby atom positions and data are needed. The van der Waals forces are also local and are termed short-range because they are negligible for large atom separations. The electrostatic forces are long-range, and various techniques have been developed to speed up these calculations. In the next two subsections, we separately discuss the computation of short-range and long-range nonbonded forces.

7.1.2 Computing Short-Range Nonbonded Forces

The computation of short-range nonbonded forces for a particle can be truncated beyond a cutoff radius, r_c , of that particle. The naive approach to perform this computation for a particle i is by examining all other particles and computing their distance to particle i . For n particles, the complexity of this approach is $O(n^2)$, which is equivalent to computing forces between all pairs of particles. There are two data structures, *cell lists* and *Verlet neighbor lists*, that can be used independently for speeding up this calculation, as well as an approach that combines the two.




Figure 7.1: Computing nonbonded forces within a cutoff, r_c . To compute forces involving the highlighted particle, only particles in the shaded regions are considered.

Cell Lists

The idea of cell lists appears often in problems where a set of points that are nearby a given point is sought. Referring to Fig. 7.1(a), where we illustrate the idea with a 2-D example, a grid is laid over the set of particles. If the grid spacing is no less than r_c , then to compute the forces on particle i , only the particles in the cell containing i and the 8 adjacent cells need to be considered. One sweep through all the particles is used to construct a list of particles for each cell. These cell lists are used to compute the forces for all particles. At the next time step, since the particles have moved, the cell lists must be regenerated or updated. The complexity of this approach is $O(n)$ for computing the data structure and $O(n \times n_c)$ for the

force computation, where n_c is the average number of particles in 9 cells (27 cells in 3-D). The storage required for the cell list data structure is $O(n)$.

Verlet Neighbor Lists

The cell list structure is somewhat inefficient because, for each particle i , n_c particles are considered, but this is much more than the number of particles within the cutoff r_c . A Verlet neighbor list is a list of particles within the cutoff for a particle i . Each particle has its own list, and thus the storage required is $O(n \times n_v)$ where n_v is the average number of particles within the cutoff. Once these lists are constructed, computing the forces is then very fast, requiring the minimal complexity $O(n \times n_v)$. Constructing the list is more expensive, requiring examining all the particles for each particle, i.e., no less than the original complexity of $O(n^2)$. The advantage, however, is that the neighbor lists can be reused for many time steps if an expanded cutoff, r_v is used. Referring to a 2-D example in Fig. 7.1(b), the neighbor list can be reused as long as no particle from outside the two circles moves inside the inner circle. If the maximum speed of the particles can be estimated or bounded, then one can determine a number of time steps for which it is safe to reuse the neighbor lists. (Alternatively, it may be possible to signal when any particle crosses to a position within the cutoff.) Technically, the Verlet neighbor list is the list of particles within the expanded cutoff, r_v .

Using Cell and Neighbor Lists Together

The hybrid approach is simply to use Verlet neighbor lists but to use cell lists to construct the neighbor lists. This reduces the high cost when neighbor lists need to be regenerated. This hybrid approach is very effective and is often the approach used in state-of-the-art molecular dynamics software.

Both cell lists and Verlet neighbor lists can be modified to exploit the fact that the force f_{ij} on particle i due to particle j is equal to $-f_{ji}$ (Newton's third law) and only needs to be computed once. For example, for cell lists, only 4 of the 8 cells (in 2-D) need to be considered.

7.1.3 Computing Long-Range Forces

Electrostatic forces are challenging to compute because they are long-range: each particle feels a non-negligible electrostatic force from all other particles in the simulation. An approximation that is sometimes used is to truncate the force calculation for a particle after a certain cutoff radius (as is done for short-range van der Waals forces). This generally produces unacceptable artifacts in the results, however.

There are several more accurate methods for speeding up the computation of electrostatic forces, avoiding the $O(n^2)$ sum over all pairs of n particles. We briefly outline some of these methods here.

Hierarchical N-body Methods

Hierarchical N-body methods, including the Barnes-Hut method and the fast multipole method, are popular for astrophysical particle simulations, but are typically too costly for the accuracy required in biomolecular simulations. In the Barnes-Hut method, space is recursively divided into 8 equal cells (in 3-D) until each cell contains zero or one particles. Forces between nearby particles are computed individually, as normal, but

for distant particles, forces are computed between one particle and a set of distant particles within a cell. An accuracy measure is used to determine if the force can be computed using a distant cell or must be computed by individually considering its children cells. The Barnes-Hut method has complexity $O(n \log n)$. The fast multipole method has complexity $O(n)$; this method calculates the potential and does not calculate forces directly.

Particle-Mesh Methods

In particle-mesh methods, we exploit the Poisson equation

$$\nabla^2 \phi = -\frac{1}{\epsilon} \rho$$

which relates the potential ϕ to the charge density ρ , where $1/\epsilon$ is a constant of proportionality. To utilize this equation, we discretize space using a mesh, assign charges to the mesh points, solve Poisson's equation on the mesh to arrive at the potential on the mesh. The force is the negative gradient of the potential (for conservative forces such as electrostatic forces). A number of techniques have been developed for distributing point charges in space to a set of mesh points and also for numerically interpolating the force on the point charges due to the potentials at the mesh points. Many fast methods are available for solving the Poisson equation, including multigrid methods and fast Fourier transforms. With respect to terminology, particle-mesh methods are in contrast to the naive *particle-particle* method where forces are computed between all pairs of particles.

It turns out that particle-mesh methods are not very accurate, and a more accurate alternative is to split each force into a short-range, rapidly-varying part and a long-range, slowly-varying part:

$$f_{ij} = f_{ij}^{sr} + f_{ij}^{lr}.$$

One way to accomplish this easily is to weigh f by a function $h(r)$, which emphasizes the short-range part (small r) and by $1 - h(r)$ which emphasizes the long-range part (large r). The short-range part is computed by computing the interaction of all pairs of particles within a cutoff (a particle-particle method) and the long-range part is computed using the particle-mesh method. The resulting method, called particle-particle-particle-mesh (PPPM, or P³M) is due to Hockney and Eastwood, in a series of papers beginning in 1973.

Ewald Method

The Ewald method is the most popular of the methods described so far for electrostatic forces in biomolecular simulations and was developed for the case of periodic boundary conditions. The structure of the method is similar to PPPM in that the force is split between short-range and long-range parts. Again, the short-range part is computed using particle-particle methods, and the long-range part is computed using Fourier transforms. Variants of the Ewald method are very similar to PPPM in that the long-range part uses a mesh, and fast Fourier transforms are used to solve the Poisson equation on the mesh. For additional details, see, for example [45]. In Section 7.3, we describe the parallelization of the 3-D FFT to solve the 3-D Poisson equation.

7.2 Parallel Decompositions

We now discuss the parallel computation of forces. Plimpton [109] created a very useful categorization of molecular dynamics parallelization methods, identifying *atom*, *force*, and *spatial* decomposition methods. Here, we closely follow his description of these methods. We also add a fourth category which has come to be recognized as differing from the earlier categories, called *neutral territory* methods, a name coined by Shaw [117]. Neutral territory methods are currently used by many state-of-the-art molecular dynamics codes. Spatial decompositions and neutral territory methods are particularly advantageous for parallelizing cutoff-based calculations.

7.2.1 Atom Decompositions

In an atom decomposition, each particle is assigned to one processor, and that processor is responsible for computing the particle's forces and updating its position for the entire simulation. For the computation to be roughly balanced, each processor is assigned approximately the same number of particles (a random distribution works well). An important point of atom decompositions is that each processor generally needs to communicate with all other processors to share updated particle positions.




Figure 7.2: Atom decomposition, showing a force matrix of 16 particles distributed among 8 processors. A dot represents a nonzero entry in the force matrix. On the left, the matrix is symmetric; on the right, only one element of a pair of skew-symmetric elements is computed, to take advantage of Newton's third law.

An atom decomposition is illustrated by the *force matrix* in Fig. 7.2(a). For n particles, the force matrix is an n -by- n matrix; the rows and columns are numbered by particle indices. A nonzero entry f_{ij} in the matrix denotes a nonzero force on particle i due to particle j which must be computed. This force may be a nonbonded and/or a bonded force. When cutoffs are used, the matrix is sparse, as in this example. The matrix is dense if forces are computed between all pairs of particles. The matrix is skew-symmetric because of Newton's third law, $f_{ij} = -f_{ji}$. The lines in Fig. 7.2(a) show how the particles are partitioned. In the figure, 16 particles are partitioned among 8 processors.

Algorithm 1 shows one time step from the point of view of one processor. At the beginning of the time step, each processor holds the positions of particles assigned to it.

Algorithm 1 Atom decomposition time step

- 1: send/receive particle positions to/from all other processors
 - 2: (if nonbonded cutoffs are used) determine which nonbonded forces need to be computed
 - 3: compute forces for particles assigned to this processor
 - 4: update positions (integration) for particles assigned to this processor
-

An optimization is to halve the amount of computation, which is possible because the force matrix is skew-symmetric. To do this, we choose exactly one of f_{ij} or f_{ji} for all skew-symmetric pairs such that each processor is responsible for computing approximately the same number of forces. Choosing the upper or lower triangular part of the force matrix is a bad choice because the computational load is unbalanced. A better choice is to compute f_{ij} if $i + j$ is even in the upper triangle, or if $i + j$ is odd in the lower triangle, as shown in Fig. 7.2(b). There are many other options.

When taking advantage of skew-symmetry in the force matrix, all the forces on a particle owned by a processor are no longer computed by that processor. For example, in Fig. 7.2(b), the forces on particle 1 are no longer computed only by the first processor. To complete the force calculation, processors must communicate to send forces that are needed by other processors and receive forces that are computed by other processors. The above algorithm must now be modified by adding a communication step (step 4) as shown in Algorithm 2.

Algorithm 2 Atom decomposition time step, without redundant calculations

- 1: send/receive particle positions to/from all other processors
 - 2: (if nonbonded cutoffs are used) determine which nonbonded forces need to be computed
 - 3: compute *partial* forces for particles assigned to this processor
 - 4: send particle forces needed by other processors and receive particle forces needed by this processor
 - 5: update positions (integration) for particles assigned to this processor
-

This algorithm is advantageous if the extra communication is outweighed by the savings in computation. Note that the amount of communication doubles in general.

7.2.2 Force Decompositions

In a force decomposition, the forces are distributed among the processors for computation. A straightforward way to do this is to partition the force matrix into blocks and to assign each block to a processor. Fig. 7.3(a) illustrates this for the case of 16 particles and 16 processors. Particles also need to be assigned to processors (as in atom decompositions) for the purpose of having processors assigned to update particle positions. In the example of the Figure, processor i is assigned to update the positions of particle i ; in practical problems, a processor would be assigned to update the positions of many particles. Note that, again, we first consider the case of a skew-symmetric force matrix.




Figure 7.3: Force decomposition, showing a force matrix of 16 particles and forces partitioned among 16 processors.

We now examine the communication required in a time step for a force decomposition. Consider processor 3, which computes partial forces for particles 0, 1, 2, 3, and needs positions from particles 0, 1, 2, 3, and also 12, 13, 14, 15. Thus processor 3 needs to perform communication with processors 0, 1, 2, 3, and processors 12, 13, 14, 15. After forces have been computed by all processors, processor 3 needs to collect forces on particle 3 computed by other processors. Thus processor 2 needs to perform communication again with processors 0, 1, 2, 3.

Algorithm 3 shows what is performed in one time step, from the point-of-view of one processor. At the beginning of the time step, each processor holds the positions of all the particles assigned to it.

Algorithm 3 Force decomposition time step

- 1: send positions of my assigned particles which are needed by other processors; receive row particle positions needed by my processor (this communication is between processors in the same processor row, e.g., processor 3 communicates with processors 0, 1, 2, 3)
 - 2: receive column particle positions needed by my processor (this communication is generally with processors in another processor row, e.g., processor 3 communicates with processors 12, 13, 14, 15)
 - 3: (if nonbonded cutoffs are used) determine which nonbonded forces need to be computed
 - 4: compute forces for my assigned particles
 - 5: send forces needed by other processors; receive forces needed for my assigned particles (this communication is between processors in the same processor row, e.g., processor 3 communicates with processors 0, 1, 2, 3)
 - 6: update positions (integration) for my assigned particles
-

In general, if there are p processors (and p is square, for simplicity), then the the force matrix is partitioned

into \sqrt{p} by \sqrt{p} blocks. The force decomposition just described requires a processor to communicate in three steps, with \sqrt{p} processors in each step. This is much more efficient than atom decompositions which require communications among all p processors.

We can also exploit Newton's third law in force decompositions. Like for atom decompositions, we first choose a modified force matrix where only one of f_{ij} and f_{ji} is computed. The forces on particle i are computed by a row of processors and now also by a column of processors. Thus an extra step of communication is needed by each processor to collect forces from a column of processors for particles assigned to it. Whereas there were three communication steps, there are now four communication steps when Newton's third law is exploited (the communication is not doubled in this case as in atom decompositions).

A modification to the force decomposition saves some communication. In Fig. 7.4, the columns are reordered using a *block-cyclic* ordering. Consider again processor 3, which computes partial forces for particles 0, 1, 2, 3. It needs positions from particles 0, 1, 2, 3, as before, but now also with processors 3, 7, 11, 15. The latter are processors in the same processor column as processor 3. Thus all communications are within the same processor row or processor column, which may be advantageous on mesh-based network architectures. The modified method is shown as Algorithm 4.




Figure 7.4: Force decomposition, with permuted columns in the force matrix. Note that columns 3, 7, 11, 15 are now in the block column corresponding to processors 3, 7, 11, 15 (the same indices), etc.

7.2.3 Spatial Decompositions

In a spatial decomposition, space is decomposed into cells. Each cell is assigned to a processor which is responsible for computing the forces on particles that lie inside the cell. Fig. 7.5(a) illustrates a spatial decomposition into 64 cells for the case of a 2-D simulation. (This is a decomposition of space and is not to be confused with a force matrix.) Typically, the number of cells is chosen to be equal to the number of processors. Since particles move during the simulation, the assignment of particles to cells changes as well. This is in contrast to atom and force decompositions.

Algorithm 4 Force decomposition time step, with permuted columns of force matrix

- 1: send positions of my assigned particles which are needed by other processors; receive row particle positions needed by my processor (this communication is between processors in the same processor row, e.g., processor 3 communicates with processors 0, 1, 2, 3)
- 2: receive column particle positions needed by my processor (this communication is generally with processors in the same processor column, e.g., processor 3 communicates with processors 3, 7, 11, 15)
- 3: (if nonbonded cutoffs are used) determine which nonbonded forces need to be computed
- 4: compute forces for my assigned particles
- 5: send forces needed by other processors; receive forces needed for my assigned particles (this communication is between processors in the same processor row, e.g., processor 3 communicates with processors 0, 1, 2, 3)
- 6: update positions (integration) for my assigned particles

Fig. 7.5(b) shows one cell (center square) and the region of space (shaded) that contains particles that are potentially within the cutoff radius, r_c , with particles in the given cell. The shaded region is often called the *import region*, since the given cell must import positions of particles lying in this region to perform its force calculation. Note that not all particles in the given cell must interact with all particles in the import region, especially if the import region is large compared to the cutoff radius.




Figure 7.5: Spatial decomposition, showing particles in a 2-D computational box, (a) partitioned into 64 cells, (b) import region for one cell.

Algorithm 5 shows what each processor performs in one time step. We assume that at the beginning of the time step, each processor holds the positions of the particles in its cell.

To exploit Newton's third law, the shape of the import region can be halved. Now each processor only computes a partial force on particles in its cell, and needs to receive forces from other processors to compute the total force on these particles. Thus an extra step of communication is involved. We leave it as an exercise to the reader to work out the details of the modified import region and the pseudocode for this case.

Algorithm 5 Spatial decomposition time step

- 1: send positions needed by other processors for particles in their import regions; receive positions for particles in my import region
 - 2: compute forces for my assigned particles
 - 3: update positions (integration) for my assigned particles
-

In the implementation of a spatial decomposition method, each cell is associated with a list of particles in its import region, similar to a Verlet neighbor list. Like a Verlet neighbor list, it is not necessary to update this list at every time step, if the import region is expanded slightly. This allows the import region list to be reused for several time steps, corresponding to the amount of time it takes a particle to traverse the width of the expanded region. This is exactly analogous to Verlet neighbor lists.

In summary, the main advantage of spatial decomposition methods is that they only require communication between processors corresponding to nearby particles. A disadvantage of spatial decomposition methods is that, for very large numbers of processors, the import region is large compared to the number of particles contained inside each cell.

7.2.4 Neutral Territory Methods

Our description of neutral territory methods follows closely that of Shaw [117]. A neutral territory method can be viewed as combining aspects of spatial decompositions and force decompositions. To parallelize the integration step, particles are assigned to processors according to a partitioning of space. To parallelize the force computation, each processor computes the forces between two sets of particles, but these particles may be unrelated to the particles that have been assigned to the processor for integration. As a result of this additional flexibility, neutral territory methods may require much less communication than spatial decomposition methods.

An example of a neutral territory method is shown in Fig. 7.6 for the case of a 2-D simulation. In the method shown in the Figure, the given processor is assigned the computation of forces between particles lying in the horizontal bar with particles lying in the vertical bar. These two regions thus form the import region for this method. By comparing to Fig. 7.6(b), the import region for this neutral territory method is much smaller than that for the corresponding spatial decomposition method. The advantage is greater when the size of the cells corresponding to each processor is small compared to the cutoff radius.

After the forces are computed, the given processor sends the forces it has computed to the processors that need these forces for integration. We thus have Algorithm 6.

Algorithm 6 Neutral territory method time step

- 1: send and receive particle positions corresponding to import regions
 - 2: compute forces assigned to this processor
 - 3: send and receive forces required for integration
 - 4: update positions (integration) for particles assigned to this processor
-

Like other methods, the import region of the neutral territory method can be modified to take advantage of




Figure 7.6: Neutral territory method, showing particles in a 2-D computational box and the import region (shaded) for one cell (center square). This Figure can be compared directly to the spatial decomposition case of Fig. 7.5(b). See Shaw [117] for additional details.

Newton's third law. We refer to Shaw [117] for additional details and for illustrations of neutral territory methods in 3-D simulations.

7.3 Parallel Fast Fourier Transform

A common component of many methods for computing long-range forces is the 3-D FFT for solving the Poisson equation on a 3-D mesh. The Fourier transform diagonalizes the Poisson operator (called the Laplacian) and one forward and one inverse FFT transformation are required in the solution. Consider the discrete Laplacian operator L (with periodic boundary conditions) and the solution of ϕ in $-L\phi = \rho$. Let F denote the Fourier transform. The original problem is equivalent to

$$\begin{aligned} -(FLF^{-1})F\phi &= F\rho \\ \phi &= -F^{-1}(FLF^{-1})^{-1}F\rho. \end{aligned}$$

The matrix FLF^{-1} is diagonal. The forward Fourier transform F is applied to ρ , then the Fourier-space components are scaled by the inverse of the diagonal matrix, and finally, the inverse Fourier transform F^{-1} is applied to obtain the solution ϕ .

For realistic protein sizes, a mesh spacing of approximately 1 Ångstrom is typically used, leading to a 3-D mesh that is quite small by many standards: $64 \times 64 \times 64$, or $128 \times 128 \times 128$. Parallel computation would often not be applied to a problem of this size, but parallel computation must be used because the data ρ is already distributed among the parallel processors (assuming a spatial decomposition is used).

A 3-D FFT is computed by computing 1-D FFTs in sequence along each of the three dimensions. For the $64 \times 64 \times 64$ mesh size, this is 4096 1-D FFTs of dimension 64. The parallel FFT calculation is typically bound by communication. The best parallelization of the FFT depends on the size of the transforms and

the architecture of the computer network. Below, we first describe some concepts for parallel 1-D FFTs and then describe some concepts for parallel 3-D FFTs. For current software and research dedicated to the parallelization and efficient computation (using SIMD operations) of large 1-D transforms, we refer to the SPIRAL and FFTW packages. These packages use autotuning to generate FFT codes that are efficient for the user's computer architecture.

7.3.1 Parallel 1-D FFT

1-D FFT without Transpose

Fig. 7.7 shows the data dependencies (data flow diagram) between the inputs (left) and outputs (right) for the 16-point radix-2 decimation-in-frequency FFT algorithm. (Not shown is a bit-reversal permutation that may be necessary in the computation.) The Figure also shows a partitioning of the computation among four processors. In this parallelization, the initial data is not moved among processors, but communication occurs during the computation. In the example shown in the Figure, communication occurs in the first two FFT stages; the final two stages do not involve communication. When communication does occur, every processor communicates with exactly one other processor.

1-D FFT with Transpose

Use of transposes is common to parallelize FFT computations. Fig. 7.8(a) shows the same data flow diagram as in Fig. 7.7, but horizontal lines have been removed and additional index labels have been added for clarity. As before, the first two FFT stages are performed without communication. The data is then transposed among the processors. With this transposed data layout, the last two FFT stages can be performed without communication. The final data is not in the original order; an additional transpose may be needed, or the data may be used in this transposed order. Fig. 7.8(b) shows how the indices are partitioned among four processors before and after the transpose. From these two Figures, notice that the first two stages have data dependencies that only involve indices in the same partition. The same is true for the second two stages for the partitioning after the transpose. Observe also that the structure of the computations before and after the transpose are identical.

7.3.2 Parallel 3-D FFT

3-D FFT with Block Decomposition

Fig. 7.9(a) shows a block decomposition of the FFT input data when a spatial decomposition is used for a mesh of size $8 \times 8 \times 8$ distributed across 64 processors arranged in a $4 \times 4 \times 4$ topology. The parallel 1-D FFT algorithms can be applied in each of the dimensions. For the example shown in the Figure, each 1-D FFT computation involves 4 processors. Each processor performs multiple 1-D FFTs simultaneously (four in this example). Within each processor, data is ordered contiguously if traversing one of the dimensions, and thus data access is strided for computation in the other two dimensions. Strided data access can be slow, and thus it may be worthwhile to reorder the data within each processor when computing the FFT for each of the dimensions.




Figure 7.7: Data flow diagram for 1-D FFT for 16 points. The shaded regions show a decomposition for 4 processors (one processor per region). In this parallelization, the first two FFT stages have no communication; the last two FFT stages do have communication.

3-D FFT with Slab Decomposition

The slab decomposition is shown in Fig. 7.9(b) for the case of 4 processors. Each processor holds one or more planes of the input data. This decomposition is used if the input data is already distributed in slabs, or if it can be easily redistributed this way. The two 1-D FFTs in the plane of the slabs require no communication. The remaining 1-D FFTs require communication and could use one of the two approaches for parallel 1-D FFTs described above. A disadvantage of the slab decomposition is that for large numbers of processors, the number of processors may exceed the number of points in the 3-D FFT along any one dimension. An alternative is the pencil decomposition below.

3-D FFT with Pencil Decomposition

The pencil decomposition is shown in Fig. 7.9(c) for the case of 16 processors. Each processor holds one or more pencils of the input data. If the original input data is distributed in blocks as in Fig. 7.9(a), then communication among a row of processors (in a 3-D processor mesh) can distribute the data into the pencil decomposition. The 1-D FFTs can then be performed with no communication. To perform the 1-D FFT in another dimension, the data needs to be redistributed into pencils in another dimension. In total, four communication stages are needed for the entire 3-D FFT computation.




Figure 7.8: 1-D FFT with transpose. The first two stages do not involve communication. The data is then transposed among the processors. As a result, the second two stages also do not involve communication.

7.4 Integration for Molecular Dynamics

To numerically integrate the system of ordinary differential equations in molecular dynamics, special methods are required, different than the traditional ODE solvers that were studied in Chapter 4. These special methods, called symplectic methods, are better than other methods at producing solutions that have constant energy, for example, for systems that are called Hamiltonian (which include systems from molecular dynamics). When Hamiltonian systems are integrated with many time steps over a long time interval, preservation of structure such as total energy is often more important than the order of accuracy of the method. In this section, we motivate some ideas and give some details of the Störmer-Verlet method, which is sufficient for simple molecular dynamics simulations.

Hamiltonian systems are a class of dynamical systems which conserve energy and which can be written in a form called Hamilton's equations. Consider, for simplicity, the *simple harmonic oscillator*

$$u'' = -u$$

where u is the displacement of a single particle from an equilibrium point. This equation could model a particle with unit mass on a spring with unit spring constant. The force on a particle at position u is $-u$. This system does not look like a molecular dynamics system but is useful for illustrating several ideas.

The above second order equation can be written as a system of first order equations

$$\begin{aligned} q' &= p \\ p' &= -q \end{aligned}$$




Figure 7.9: Three data decompositions for 3-D FFTs.

where $q = u$ and $p = u'$ which is common notation used in classical mechanics. The general solution is

$$\begin{pmatrix} q \\ p \end{pmatrix} = \begin{pmatrix} \cos t & \sin t \\ -\sin t & \cos t \end{pmatrix} \begin{pmatrix} q \\ p \end{pmatrix}.$$

The kinetic energy of the simple harmonic oscillator is $p^2/2$ and the potential energy is $q^2/2$ (the negative gradient of potential energy is the force, $-q$). Thus the total energy is proportional to $q^2 + p^2$.

Now consider the solution of the system of first order equations by three methods, explicit Euler, implicit Euler, and a method called the Störmer-Verlet method. The initial condition is $(q, p) = (1, 0)$. We use a time step of $h = 0.05$ and take 500 steps. We plot q and p on the horizontal and vertical axes, respectively (called a *phase plot*). The exact solution, as given above, is a unit circle centered at the origin.

Figure 7.10 shows the solutions. For explicit Euler, the solution spirals outward, meaning the displacement and momentum of the solution increases over time. The opposite is true for the implicit Euler method. A plot of the total energy would show the energy increasing and decreasing for the two cases, respectively. The solutions are better when smaller time steps are taken or when higher order methods are used, but these methods are not at all appropriate for integration of symplectic systems over long periods of time. Figure 7.10(c) shows the solution using a symplectic method called the Störmer-Verlet method. The solution shows that $q^2 + p^2$ is preserved much better than in the other two methods.

The Störmer-Verlet method is derived very easily. We derive it for the second order equation

$$u'' = f(t, u)$$

by simply replacing the left-hand side with a finite difference approximation

$$\frac{u_{k+1} - 2u_k + u_{k-1}}{h^2} = f(t_k, u_k)$$

which can be rearranged to obtain the method

$$u_{k+1} = 2u_k - u_{k-1} + h^2 f(t_k, u_k).$$

The formula can equivalently be derived from Taylor series. The method is similar to linear multistep methods in that some other technique is needed to supply the initial step of the method. The method is also




Figure 7.10: Phase plot of the solution of the simple harmonic oscillator for three methods with initial value $(1,0)$, time step 0.05 , and 500 steps. For explicit Euler, the solution spirals outward; for implicit Euler, the solution spirals inward; the total energy is best preserved with the Störmer-Verlet method.

time-reversible, because the formula is the same if $k+1$ and $k-1$ are swapped. To explain why this method is symplectic, unfortunately, is beyond the scope of this introduction.

The method as written above has a number of disadvantages, the most severe being that the addition of the small h^2 term is subject to catastrophic cancellation. Thus this formula should not be used in this form, and a number of mathematically equivalent formulas (which can be derived from the formula above) have been developed.

One alternative formula is the *leap-frog* method:

$$\begin{aligned} u_{k+1} &= u_k + hv_{k+1/2} \\ v_{k+1/2} &= v_{k-1/2} + hf(t_k, u_k) \end{aligned}$$

where v is the first derivative (velocity) which is offset from the displacement u by a half step. This formula does not suffer from the same roundoff problems and also makes available the velocities, although they need to be re-centered with displacements in order to calculate total energy at a given step. The second of this pair of equations is basically a finite difference formula.

A third form of the Störmer-Verlet method is the *velocity Verlet* variant:

$$\begin{aligned} u_{k+1} &= u_k + hv_k + \frac{h^2}{2} f(t_k, u_k) \\ v_{k+1} &= v_k + \frac{h^2}{2} (f(t_k, u_k) + f(t_{k+1}, u_{k+1})) \end{aligned}$$

where now the velocities are computed at the same points as the displacements. Each of these algorithms can be implemented such that only two sets of quantities need to be stored (two previous positions, or a position and a velocity). These variants of the Störmer-Verlet method are popular because of their simplicity, requiring only one costly force evaluation per step. Higher-order methods have generally not been practical.

The velocity Verlet scheme is also the basis of multiple time step algorithms for molecular dynamics. In these algorithms, the slowly-varying (typically long-range) forces are evaluated less frequently and update the positions less frequently than the quickly-varying (typically short-range) forces. Finally, many state-of-the-art molecular dynamics integrate a Hamiltonian system that has been modified in order to control the simulation temperature and pressure. Much more complicated symplectic methods have been developed for these systems.

Chapter 8

Combinatorics

Traditional scientific computing applications concern continuous data, often stemming from PDEs. In this chapter we will concern two applications areas, sorting and graph computations, that are not traditionally considered as scientific computing, but that are interesting from a point of high performance and large scale computing.

8.1 Sorting

Sorting is not a common operation in scientific computing: one expects it to be more important in databases, whether these be financial or biological (for instance in sequence alignment). However, it sometimes comes up, for instance in *Adaptive Mesh Refinement (AMR)* and other applications where significant manipulations of data structures occurs.

In this section we will briefly look at the QuickSort algorithm and how it can be done in parallel. For more details, see [83] and the references therein.

8.1.1 Brief introduction to sorting

There are many sorting algorithms. One way to distinguish them is by their computational complexity, that is, given an array of n elements, how many operations does it take to sort them, as a function of n . For some sorting algorithms, the answer to this question is not simple to give. While some algorithms work largely independent of the state of the input data, for others, the operation count does depend on it. One could imagine that a sorting algorithm would make a pass over the data to check if it was already sorted. In that case, the complexity is n operations for a sorted list, and something higher for an unsorted list.

The so-called *bubble sort* algorithm has a complexity independent of the data to be sorted. This algorithm is given by:

```
for t from n - 1 down to 1 do
    for e from 1 to t do
        if elements e and e + 1 are ordered the wrong way then
            exchange them
```

Algorithm 2: The bubble sort algorithm

It is easy to see that this algorithm has a complexity of $O(n^2)$: the inner loop does t comparisons and up to t exchanges. Summing this from 1 to $n - 1$ gives approximately $n^2/2$ comparisons and at most the same number of exchanges.

Theoretically one can show that a sorting algorithm has to have at least complexity $O(n \log n)$ ¹. There are indeed several algorithms that are guaranteed to attain this complexity, but a very popular algorithm, called *quicksort* has only an ‘expected’ complexity of $O(n \log n)$, and a worst case complexity of $O(n^2)$.

8.1.2 Quicksort

Quicksort is a recursive algorithm, that, unlike bubble sort, is not deterministic. It is a two step procedure, based on a reordering of the sequence²:

Algorithm: Dutch National Flag ordering of an array

Input : An array of elements, and a ‘pivot’ value

Output: The input array with elements ordered as red-white-blue, where red elements are larger than the pivot, white elements are equal to the pivot, and blue elements are less than the pivot

We state without proof that this can be done in $O(n)$ operations. With this, quicksort becomes:

Algorithm: Quicksort

Input : An array of elements

Output: The input array, sorted

while *The array is longer than one element do*

 pick an arbitrary value as pivot

 apply the Dutch National Flag reordering to this array

 Quicksort(the blue elements)

 Quicksort(the red elements)

The indeterminacy of this algorithm, and the variance in its complexity, stems from the pivot choice. In the worst case, the pivot is always the (unique) smallest element of the array. There will then be no blue elements, the only white element is the pivot, and the recursive call will be on the array of $n - 1$ red elements. It is easy to see that the running time will then be $O(n^2)$. On the other hand, if the pivot is always (close to) the median, that is, the element that is intermediate in size, then the recursive calls will have an

1. One can consider a sorting algorithm as a decision tree: a first comparison is made, depending on it two other comparisons are made, et cetera. Thus, an actual sorting becomes a path through this decision tree. If every path has running time h , the tree has 2^h nodes. Since a sequence of n elements can be ordered in $n!$ ways, the tree needs to have enough paths to accomodate all of these; in other words, $2^h \geq n!$. Using Stirling’s formula, this means that $n \geq O(n \log n)$

2. The name is explained by its origin with the Dutch computer scientist Edsger Dijkstra; see http://en.wikipedia.org/wiki/Dutch_national_flag_problem.

about equal running time, and we get a recursive formula for the running time:

$$T_n = 2T_{n/2} + O(n)$$

which is (again without proof) $O(n \log n)$.

We will now consider parallel implementations of quicksort.

8.1.3 Quicksort in shared memory

A simple parallelization of the quicksort algorithm can be achieved by executing the two recursive calls in parallel. This is easiest realized with a shared memory model, and threads (section 2.5.1) for the recursive calls. However, this implementation is not efficient.

On an array of length n , and with perfect pivot choice, there will be n threads active in the final stage of the algorithm. Optimally, we would want a parallel algorithm to run in $O(\log n)$ time, but here the time is dominated by the initial reordering of the array by the first thread.

Exercise 8.1. Make this argument precise. What is the total running time, the speedup, and the efficiency of parallelizing the quicksort algorithm this way?

Since shared memory is not the most interesting case, we will forego trying to make the thread implementation more efficient, and we will move on straight away to distributed memory parallelization.

8.1.4 Quicksort on a hypercube

As was apparent from the previous section, for an efficient parallelization of the quicksort algorithm, we need to make the Dutch National Flag reordering parallel too. Let us then assume that the array has been partitioned over the p processors of a hypercube of dimension d (meaning that $p = 2^d$).

In the first step of the parallel algorithm, we choose a pivot, and broadcast it to all processors. All processors will then apply the reordering independently on their local data.

In order to bring together the red and blue elements in this first level, every processor is now paired up with one that has a binary address that is the same in every bit but the most significant one. In each pair, the blue elements are sent to the processor that has a 1 value in that bit; the red elements go to the processor that has a 0 value in that bit.

After this exchange (which is local, and therefore fully parallel), the processors with an address $1xxxxx$ have all the red elements, and the processors with an address $0xxxxx$ have all the blue elements. The previous steps can now be repeated on the subcubes.

This algorithm keeps all processors working in every step; however, it is susceptible to load imbalance if the chosen pivots are far from the median. Moreover, this load imbalance is not lessened during the sort process.

8.1.5 Quicksort on a general parallel processor

Quicksort can also be done on any parallel machine that has a linear ordering of the processors. We assume at first that every processor holds exactly one array element, and, because of the flag reordering, sorting will always involve a consecutive set of processors.

Parallel quicksort of an array (or subarray in a recursive call) starts by constructing a binary tree on the processors storing the array. A pivot value is chosen and broadcast through the tree. The tree structure is then used to count on each processor how many elements in the left and right subtree are less than, equal to, or more than the pivot value.

With this information, the root processor can compute where the red/white/blue regions are going to be stored. This information is sent down the tree, and every subtree computes the target locations for the elements in its subtree.

If we ignore network contention, the reordering can now be done in unit time, since each processor sends at most one element. This means that each stage only takes time in summing the number of blue and red elements in the subtrees, which is $O(\log n)$ on the top level, $O(\log n/2)$ on the next, et cetera. This makes for almost perfect speedup.

8.2 Graph problems

Various problems in scientific computing can be formulated as graph problems (for an introduction to graph theory see Appendix A.5); for instance, you have encountered the problem of load balancing (section 2.10.1.2) and finding independent sets (section 6.7.2). Many traditional graph algorithms are not immediately, or at least not efficiently, applicable, since the graphs are often distributed, and traditional graph theory assume global knowledge of the whole graph.

Recently, new types of graph computations have arisen in scientific computing. Here the graph are no longer tools, but objects of study themselves. Examples are the *World Wide Web* or the *social graph* of *Facebook*, or the graph of all possible *protein interactions* in a living organism.

For this reason, combinatorial computational science is becoming a discipline in its own right. We will look at some specific graph problems in this chapter.

8.2.1 ‘Real world’ graphs

In discussions such as in section 4.2.2.2 you have seen how the discretization of PDEs leads to computational problems that have a graph aspect to them. Such graphs have properties that make them amenable to certain kinds of problems. For instance, using FDMs or FEMs to model two or three-dimensional objects leads to graphs where each node is connected to just a few neighbours. This makes it easy to find *separators*, which in turn allows such solution methods as *nested dissection*; see section 6.7.1.

There are however applications with computationally intensive graph problems that do not look like FEM graphs. We will briefly look at the example of the world-wide web, and algorithms such *Google’s PageRank* which try to find authoritative nodes.

For now, we will call such graphs *random graphs*, although this term has a technical meaning too [38].

8.2.1.1 Properties of random graphs

The graphs we have seen in most of this course have properties that stem from the fact that they model objects in our three-dimensional world. Thus, the typical distance between two nodes is typically $O(N^{1/3})$ where N is the number of nodes. Random graphs do not behave like this: they often have a *small world* property where the typical distance is $O(\log N)$. A famous example is the graph of film actors and their connection by having appeared in the same movie: according to ‘Six degrees of separation’, no two actors have a distance more than six in this graph. In graph terms this means that the diameter of the graph is six.

Small-world graphs have other properties, such as the existence of cliques (although these feature too in higher order FEM problems) and hubs: nodes of a high degree. This leads to implications such as the following: deleting a random node in such a graph does not have a large effect on shortest paths.

Exercise 8.2. Considering the graph of airports and the routes that exist between them. If there are only hubs and non-hubs, argue that deleting a non-hub has no effect on shortest paths between other airports. On the other hand, consider the nodes ordered in a two-dimensional grid, and delete an arbitrary node. How many shortest paths are affected?

8.2.1.2 Concepts

Two measures of centrality: eigenvector centrality and betweenness. Low EC and high betweenness indicates a ‘gatekeeper’ function.

Degree, diameter, distance are defined as usual.

Betweenness is defined as

$$C(v) = \frac{\sum_{s \neq t \neq v} \#\text{shortest paths between } s, t}{\sum_{s \neq t \neq v} \#\text{shortest paths between } s, t \text{ that go through } v}$$

Eigenvector centrality is the magnitude of a node’s component in the Perron vector; see section 8.2.2.

Closeness measures the average distance of a node to all others:

$$c(v) = \frac{1}{n-1} \sum_{t \neq v} d(t, v).$$

Clustering coefficient measures how much of a graph is organized in cliques. A global coefficient is

$$\frac{\#\text{closed triplets}}{\#\text{open triplets}}$$

where an open triplet is a triplet i, j, k so that

$$(i, j) \in E, \quad (i, k) \in E, \quad (j, k) \notin E$$

while for a closed triplet the last relation is an inclusion. A local definition is based on the fact that in a *clique* of k nodes there are $k(k-1)/2$ edges (in an undirected graph). Defining the *neighbourhood* of a node i as

$$N_i = \{j \neq i : (i, j) \in E\},$$

the local clustering coefficient can be defined as

$$\frac{|\{e_{jk}\}_{j,k \in N_i}|}{k(k-1)/2}.$$

8.2.2 Hypertext algorithms

There are several algorithms based on linear algebra for measuring the importance of web sites [?]. We will briefly define a few and discuss computational implications.

8.2.2.1 HITS

In the HITS (Hypertext-Induced Text Search) algorithm, sites have a *hub* score that measures how many other sites it points to, and an *authority* score that measures how many sites point to it. To calculate such scores we define an *incidence matrix* L , where

$$L_{ij} = \begin{cases} 1 & \text{document } i \text{ points to document } j \\ 0 & \text{otherwise} \end{cases}$$

The authority scores x_i are defined as the sum of the hub scores y_j of everything that points to i , and the other way around. Thus

$$\begin{aligned} x &= L^t y \\ y &= Lx \end{aligned}$$

or $x = LL^t x$ and $y = L^t Ly$, showing that this is an eigenvalue problem. The eigenvector we need has only nonnegative entries; this is known as the *Perron vector* for a *nonnegative matrix*, see appendix A.1.4. The Perron vector is computed by a *power method*; see next section.

A practical search strategy is:

- Find all documents that contain the search terms;
- Build the subgraph of these documents, and possible one or two levels of documents related to them;
- Compute authority and hub scores on these documents, and present them to the user as an ordered list.

8.2.2.2 Pagerank

The PageRank [105] basic idea is similar to HITS. Again we define a connectivity matrix

$$M_{ij} = \begin{cases} 1 & \text{if page } j \text{ links to } i \\ 0 & \text{otherwise} \end{cases}$$

With $e = (1, \dots, 1)$, the vector $d^t = e^t M$ counts how many links there are on a page: d_i is the number of links on page i . We construct a diagonal matrix $D = \text{diag}(d_1, \dots)$ we normalize M to $T = MD^{-1}$.

Now the columns sums (that is, the sum of the elements in any column) of T are all 1, which we can express as $e^t T e$. Such a matrix is called *stochastic matrix*. It has the following interpretation:

If p is a vector of probabilities, that is, p_i is the probability that the user is looking at page i , then Tp is the vector of probabilities after the user has clicked on a random link.

The PageRank algorithm introduces another element: sometimes the user will get bored from clicking, and will go to an arbitrary page (there are also provisions for pages with no outgoing links). If we call s the chance that the user will click on a link, then the chance of going to an arbitrary page is $1 - s$. Together, we now have the process

$$p' \leftarrow sTp + (1 - s)e,$$

that is, if p is a vector of probabilities then p' is a vector of probabilities that describes where the user is after making one page transition, either by clicking on a link or by ‘teleporting’.

The PageRank vector is the stationary point of this process; you can think of it as the probability distribution after the user has made infinitely many transitions. The PageRank vector satisfies

$$p = sTp + (1 - s)e \Leftrightarrow (I - sT)p = (1 - s)e.$$

Thus, we now have to wonder whether $I - sT$ has an inverse. If the inverse exists it satisfies

$$(I - sT)^{-1} = I + sT + s^2T^2 + \dots$$

It is not hard to see that the inverse exists: with the Gershgorin theorem (appendix A.1.5) you can see that the eigenvalues of T satisfy $|\lambda| \leq 1$. Now use that $s < 1$, so the series of partial sums converges.

The above formula for the inverse also indicates a way to compute the PageRank vector p by using a series of matrix-vector multiplications.

Exercise 8.3. Write pseudo-code for computing the PageRank vector, given the matrix T . Show that you never need to compute the powers of T explicitly. (This is an instance of *Horner’s rule*.)

In the case that $s = 1$, meaning that we rule out teleportation, the PageRank vector satisfies $p = Tp$, which is again the problem of finding the *Perron vector*; see appendix A.1.4.

We find the Perron vector by a power iteration (section A.1.3)

$$p^{(i+1)} = Tp^{(i)}.$$

This is a sparse matrix vector product, but unlike in the BVP case the sparsity is unlikely to have a structure such as bandedness. Computationally, one probably has to use the same parallelism arguments as for a dense matrix: the matrix has to be distributed two-dimensionally [102].

Chapter 9

Discrete systems

Interaction between discrete elements:

- external
- nearby
- far

External forces are simple and conveniently parallel.

Nearby forces are easy to handle if spatial domain decomposition is used: at best ghost regions needed.

Load imbalance because of particle migration.

Far-field forces are difficult because every particle interacts with every other: naive algorithms are $O(n^2)$.

Particle-mesh methods: move particles to nearby mesh points, use the fact that the far-field equation satisfies a PDE that is easy to solve, use FFT or multigrid (complexity $O(n \log n)$), calculate forces by interpolation.

Approximation by letting faraway particles act as group:

1. Barnes-Hut
2. Fast Multipole Methods (FMMs)

Also $n \log n$ complexity.

Chapter 10

Monte Carlo Methods

Monte Carlo simulation is a broad term for methods that use random numbers and statistical sampling to solve problems, rather than exact modeling. From the nature of this sampling, the result will have some uncertainty, but the statistical ‘law of large numbers’ will ensure that the uncertainty goes down as the number of samples grows. The statistical law that underlies this is as follows: if N independent observations are made of a quantity with standard deviation σ , then the standard deviation of the mean is σ/\sqrt{N} . This means that more observations will lead to more accuracy; what makes Monte Carlo methods interesting is that this gain in accuracy is not related to dimensionality of the original problem.

Monte Carlo techniques are of course natural candidates for simulating phenomena that are statistical in nature, such as radioactive decay, or Brownian motion. Other problems where Monte Carlo simulation is attractive are outside the realm of scientific computing. For instance, the Black-Scholes model for stock option pricing [?] uses Monte Carlo simulation.

Some problems that you have seen before, such as solving a linear system of equations, can be tackled with Monte Carlo techniques. However, this is not a typical application. Below we will discuss two applications where exact methods would take far too much time to compute and where statistical sampling can quickly give a reasonably accurate answer.

An important tool for statistical sampling is random number generator. We start by briefly discussing the problems in generating random numbers, especially in parallel.

10.1 Parallel Random Number Generation

Random numbers are often used in simulations as some examples below will show. True random numbers are very hard to obtain: they could be generated by measuring quantum processes such as radioactive particles, but this is very cumbersome. Instead, we use *pseudo-random numbers*. This means that we use a deterministic mathematical process, that is sufficiently irregular that for practical purposes no order can be found in it.

An easy way to generate random numbers (we leave off the ‘pseudo’ qualification) is to use linear congruential generators (for all you ever need to know about random numbers, see Knuth [?]), recurrences of the form

$$x_{k+1} = (ax_k + b) \mod m.$$

This sequence is periodic, since it consists of nonnegative integers at most $m - 1$, and with period m under certain conditions. A typical period is 2^{31} . The starting point x_0 of the series is known as the ‘seed’. Software for random numbers often lets you specify the seed. To get reproducible results you would run your program with the same seed multiple times; to get random behaviour over multiple runs of your program you could for instance derive the seed from clock and calendar functions.

Random number generation is problematic in parallel. To see this, consider a parallel process that uses a random number generator on each subprocess, and consider a single processor emulating the parallel process. Now this single process in effect has a random number generator that consists of interleaving the parallel generator results. This means that, if we use the same generator in all parallel processes, the effective generator over the whole process will produce stretches of identical values.

We can solve this problem by having a central task that supplies the random values for all processes, but this introduces a bottleneck. A better solution is to set up independent generators with parameter choices that guarantee statistical randomness. This is not simple. For instance, if two sequences $x_i^{(1)}, x_i^{(2)}$ have the same values of a, b, m , and their starting points are close together, the sequences will be strongly correlated. Less trivial examples of correlation exist.

Various techniques for random number generation exist, such as using two sequences, where one generates the starting points for the other sequence, which is the one actually used in the simulation. Software for parallel random number generator can be found at <http://sprng.cs.fsu.edu/> [?].

10.2 Examples

10.2.1 Integration by statistics

Let’s start with something simpler than integration: measuring an area. Suppose you have a pond of an irregular shape in your backyard, and that the yard itself is rectangular with known dimensions. If you would now throw pebbles into your yard so that they are equally likely to land at any given spot, then the ratio of pebbles falling in the pond to those falling outside equals the ratio of the areas.

Less fanciful and more mathematically, let $\Omega \in [0, 1]^2$, and let a function $f(\bar{x})$ describing the boundary of Ω , that is

$$\begin{cases} f(\bar{x}) < 0 & x \notin \Omega \\ f(\bar{x}) > 0 & x \in \Omega \end{cases}$$

Now take random points $\bar{x}_0, \bar{x}_1, \bar{x}_2 \in [0, 1]^2$, then we can estimate the area of Ω by counting how often $f(\bar{x}_i)$ is positive or negative.

We can extend this idea to integration. The average value of a function on an interval (a, b) is defined as

$$\langle f \rangle = \frac{1}{b-a} \int_a^b f(x) dx$$

On the other hand, we can also estimate the average as

$$\langle f \rangle \approx \frac{1}{N} \sum_{i=1}^n f(x_i)$$

if the points x_i are reasonably distributed and the function f is not too wild. This leads us to

$$\int_a^b f(x) dx \approx (b-a) \frac{1}{N} \sum_{i=1}^n f(x_i)$$

Statistical theory, that we will not go into, tells us that the uncertainty σ_I in the integral is related to the standard deviation σ_f by

$$\sigma_I \sim \frac{1}{\sqrt{N}} \sigma_f$$

for normal distributions.

So far, Monte Carlo integration does not look much different from classical integration. The difference appears when we go to higher dimensions. In that case, for classical integration we would need N points in each dimension, leading to N^d points in d dimensions. In the Monte Carlo method, on the other hand, the points are taken at random from the d -dimensional space, and a much lower number of points suffices.

Computationally, Monte Carlo methods are attractive since all function evaluations can be performed in parallel.

10.2.2 Monte Carlo simulation of the Ising model

The Ising model (for an introduction, see [?]) was originally proposed to model ferromagnetism. Magnetism is the result of atoms aligning their ‘spin’ direction: let’s say spin can only be ‘up’ or ‘down’, then a material has magnetism if more atoms have spin up than down, or the other way around. The atoms are said to be in a structure called a ‘lattice’.

Now imagine heating up a material, which loosens up the atoms. If an external field is applied to the material, the atoms will start aligning with the field, and if the field is removed the magnetism disappears again. However, below a certain critical temperature the material will retain its magnetism. We will use Monte Carlo simulation to find the stable configurations that remain.

Let’s say the lattice Λ has N atoms, and we denote a configuration of atoms as $\sigma = (\sigma_1, \dots, \sigma_N)$ where each $\sigma_i = \pm 1$. The energy of a lattice is modeled as

$$H = H(\sigma) = -J \sum_i \sigma_i - E \sum_{ij} \sigma_i \sigma_j.$$

The first term models the interaction of individual spins σ_i with an external field of strength J . The second term, which sums over nearest neighbour pairs, models alignment of atom pairs: the product $\sigma_i \sigma_j$ is positive if the atoms have identical spin, and negative if opposite.

In *statistical mechanics*, the probability of a configuration is

$$P(\sigma) = \exp(-H(\sigma))/Z$$

where the ‘partitioning function’ Z is defined as

$$Z = \sum_{\sigma} \exp(H(\sigma))$$

where the sum runs over all 2^N configurations.

A configuration is stable if its energy does not decrease under small perturbations. To explore this, we iterate over the lattice, exploring whether altering the spin of atoms lowers the energy. We introduce an element of chance to prevent artificial solutions. (This is the *Metropolis algorithm* [?].)

```
for fixed number of iterations do
    for each atom  $i$  do
        calculate the change  $\Delta E$  from changing the sign of  $\sigma_i$ 
        if  $\Delta E <$  or  $\exp(-\Delta E)$  greater than some random number then
            accept the change
```

This algorithm can be parallelized, if we notice the similarity with the structure of the sparse matrix-vector product. In that algorithm too we compute a local quantity by combining inputs from a few nearest neighbours. This means we can partitioning the lattice, and compute the local updates after each processor collects a *ghost region*.

Having each processor iterate over local points in the lattice corresponds to a particular global ordering of the lattice; to make the parallel computation equivalent to a sequential one we also need a parallel random generator (section 10.1).

Appendix A

Theoretical background

This course requires no great mathematical sophistication. Mostly it assumes that you know the basics of linear algebra: what are matrices and vectors, and the most common operations on them.

In the following appendices we will cover some less common bits of theory that have been moved out of the main storyline of the preceding chapters.

- In [A.1](#) we cover some linear algebra material that you may not, or probably will not, have seen before.
- Appendix [A.2](#) gives the basic definitions of complexity theory, which you need for analyzing algorithms.
- Much of scientific computing is about the treatment of Ordinary and Partial Differential Equations. In this book, they are discussed in chapters [4](#) and [6](#). Appendix [A.3](#) gives some background knowledge about PDEs, and appendix [A.4](#) discusses Taylor expansion, which is a basic mechanism for getting a computational form of ODEs and PDEs.
- In the discussion of computational methods and of parallel architectures, graph theory often comes up. The basic concepts are discussed in appendix [A.5](#).
- The FFT algorithm is used in chapter [7](#) on Molecular Dynamics; we derive and discuss it in appendix [A.6](#).
- Finally, [A.7](#) gives the definition and a short discussion of Finite State Automata (FSAs), which comes up in the definition of CPUs.

A.1 Linear algebra

In this course it is assumed that you know what a matrix and a vector are, simple algorithms such as how to multiply them, and some properties such as invertibility of a matrix. This appendix introduces some concepts and theorems that are not typically part of a first course in linear algebra.

A.1.1 Norms

A *norm* is a way to generalize the concept of absolute value to multi-dimensional objects such as vectors and matrices. There are many ways of defining a norm, and there is theory of how different norms relate. Here we only give the basic definitions; for more detail see any linear algebra textbook, for instance [?].

A.1.1.1 Vector norms

A norm is any function $n(\cdot)$ on a vector space V with the following properties:

- $n(x) \geq 0$ for all $x \in V$ and $n(x) = 0$ only for $x = 0$,
- $n(\lambda x) = |\lambda|n(x)$ for all $x \in V$ and $\lambda \in \mathbb{R}$.
- $n(x + y) \leq n(x) + n(y)$

For any $p \geq 1$, the following defines a vector norm:

$$\|x\|_p = \sqrt[p]{\sum_i |x_i|^p}.$$

Common norms are $\|\cdot\|_1$ ('sum of absolute values') and $\|\cdot\|_2$ ('square root of sum of squares'); the $\|\cdot\|_\infty$ norm is defined as $\lim_{p \rightarrow \infty} \|\cdot\|_p$, and it is not hard to see that this equals

$$\|x\|_\infty = \max_i |x_i|.$$

A.1.1.2 Matrix norms

By considering a matrix of size n as a vector of length n^2 , we can define the Frobenius matrix norm:

$$\|A\|_F = \sqrt{\sum_{i,j} |a_{ij}|^2}.$$

However, we will mostly look at *associated matrix norms*:

$$\|A\|_p = \sup_{\|x\|_p=1} \|Ax\|_p = \sup_x \frac{\|Ax\|_p}{\|x\|_p}.$$

From their definition, it easily follows that

$$\|Ax\| \leq \|A\| \|x\|$$

for associated norms.

The following are easy to derive:

- $\|A\|_1 = \max_j \sum_i |a_{ij}|,$
- $\|A\|_\infty = \max_i \sum_j |a_{ij}|.$

By observing that $\|A\|_2 = \sup_{\|x\|_2=1} x^t A^t Ax$, it is not hard to derive that $\|A\|_2$ is the maximal singular value of A , which is the root of the maximal eigenvalue of $A^t A$.

The matrix *condition number* is defined as

$$\kappa(A) = \|A\| \|A^{-1}\|.$$

In the symmetric case this is the ratio between the largest and smallest eigenvalue.

A.1.2 Gram-Schmidt orthogonalization

The Gram-Schmidt (GS) algorithm takes a series of vectors and inductively orthogonalizes them. This can be used to turn an arbitrary basis of a vector space into an orthogonal basis; it can also be viewed as transforming a matrix A into one with orthogonal columns. If Q has orthogonal columns, $Q^t Q$ is diagonal, which is often a convenient property to have.

The basic principle of the GS algorithm can be demonstrated with two vectors u, v . Suppose we want a vector v' so that u, v and u, v' span the same space, but $v' \perp u$. For this we let

$$v' \leftarrow v - \frac{u^t v}{u^t u} u.$$

It is easy to see that this satisfies the requirements.

Suppose we have an set of vectors u_1, \dots, u_n that we want to orthogonalize. We do this by successive applications of the above transformation:

```

For  $i = 1, \dots, n$ :
  For  $j = 1, \dots, i - 1$ :
    let  $c_{ji} = u_j^t u_i / u_j^t u_j$ 
  For  $i = 1, \dots, n$ :
    update  $u_i \leftarrow u_i - c_{ji} u_j$ 

```

Often the vector v in the algorithm above is normalized; this adds a line

$$u_i \leftarrow u_i / \|u_i\|$$

to the algorithm. GS orthogonalization with this normalization, applied to a matrix, is also known as the *QR factorization*.

Exercise A.1.1. Suppose that we apply the GS algorithm to the columns of a rectangular matrix A , giving a matrix Q . Prove that there is an upper triangular matrix R such that $A = QR$. (Hint: look at the c_{ji} coefficients above.) If we normalize the orthogonal vector in the algorithm above, Q has the additional property that $Q^t Q = I$. Prove this too.

The GS algorithm as given above computes the desired result, but only in exact arithmetic. A computer implementation can be quite inaccurate if the angle between v and one of the u_i is small. In that case, the Modified Gram-Schmidt (MGS) algorithm will perform better:

For $i = 1, \dots, n$:

let $c_i = u_i^t v / u_i^t u_i$
update $v \leftarrow v - c_i u_i$

To contrast it with MGS, the original GS algorithm is also known as Classical Gram-Schmidt (CGS).

As an illustration of the difference between the two methods, consider the matrix

$$A = \begin{pmatrix} 1 & 1 & 1 \\ \epsilon & 0 & 0 \\ 0 & \epsilon & 0 \\ 0 & 0 & \epsilon \end{pmatrix}$$

where ϵ is of the order of the machine precision, so that $1 + \epsilon^2 = 1$ in machine arithmetic. The CGS method proceeds as follows:

- The first column is of length 1 in machine arithmetic, so

$$q_1 = a_1 = \begin{pmatrix} 1 \\ \epsilon \\ 0 \\ 0 \end{pmatrix}.$$

- The second column gets orthogonalized as $v \leftarrow a_2 - 1 \cdot q_1$, giving

$$v = \begin{pmatrix} 0 \\ -\epsilon \\ \epsilon \\ 0 \end{pmatrix}, \quad \text{normalized: } q_2 = \begin{pmatrix} 0 \\ -\frac{\sqrt{2}}{2} \\ \frac{\sqrt{2}}{2} \\ 0 \end{pmatrix}$$

- The third column gets orthogonalized as $v \leftarrow a_3 - c_1 q_1 - c_2 q_2$, where

$$\begin{cases} c_1 = q_1^t a_3 = 1 \\ c_2 = q_2^t a_3 = 0 \end{cases} \Rightarrow v = \begin{pmatrix} 0 \\ -\epsilon \\ 0 \\ \epsilon \end{pmatrix}; \quad \text{normalized: } q_3 = \begin{pmatrix} 0 \\ \frac{\sqrt{2}}{2} \\ 0 \\ \frac{\sqrt{2}}{2} \end{pmatrix}$$

It is easy to see that q_2 and q_3 are not orthogonal at all. By contrast, the MGS method differs in the last step:

- As before, $q_1^t a_3 = 1$, so

$$v \leftarrow a_3 - q_1 = \begin{pmatrix} 0 \\ -\epsilon \\ \epsilon \\ 0 \end{pmatrix}.$$

Then, $q_2^t v = \frac{\sqrt{2}}{2} \epsilon$ (note that $q_2^t a_3 = 0$ before), so the second update gives

$$v \leftarrow v - \frac{\sqrt{2}}{2} \epsilon q_2 = \begin{pmatrix} 0 \\ \frac{\epsilon}{2} \\ -\frac{\epsilon}{2} \\ \epsilon \end{pmatrix}, \quad \text{normalized: } \begin{pmatrix} 0 \\ \frac{\sqrt{6}}{6} \\ -\frac{\sqrt{6}}{6} \\ 2\frac{\sqrt{6}}{6} \end{pmatrix}$$

Now all $q_i^t q_j$ are on the order of ϵ for $i \neq j$.

A.1.3 The power method

The vector sequence

$$x_i = Ax_{i-1},$$

where x_0 is some starting vector, is called the *power method* since it computes the product of subsequent matrix powers times a vector:

$$x_i = A^i x_0.$$

There are cases where the relation between the x_i vectors is simple. For instance, if x_0 is an eigenvector of A , we have for some scalar λ

$$Ax_0 = \lambda x_0 \quad \text{and} \quad x_i = \lambda^i x_0.$$

However, for an arbitrary vector x_0 , the sequence $\{x_i\}_i$ is likely to consist of independent vectors. Up to a point.

Exercise A.1.2. Let A and x be the $n \times n$ matrix and dimension n vector

$$A = \begin{pmatrix} 1 & 1 & & \\ & 1 & 1 & \\ & & \ddots & \ddots & \\ & & & 1 & 1 \\ & & & & 1 \end{pmatrix}, \quad x = (0, \dots, 0, 1)^t.$$

Show that the sequence $[x, Ax, \dots, A^i x]$ is an independent set for $i < n$. Why is this no longer true for $i \geq n$?

Now consider the matrix B :

$$B = \left(\begin{array}{cc|c} 1 & 1 & & \\ & \ddots & \ddots & \\ & & 1 & 1 \\ & & & 1 \hline & & 1 & 1 \\ & & & \ddots & \ddots \\ & & & & 1 & 1 \\ & & & & & 1 \end{array} \right), \quad y = (0, \dots, 0, 1)^t$$

Show that the set $[y, By, \dots, B^i y]$ is an independent set for $i < n/2$, but not for any larger values of i .

While in general the vectors x, Ax, A^2x, \dots can be expected to be independent, in computer arithmetic this story is no longer so clear.

Suppose the matrix has eigenvalues $\lambda_0 > \lambda_1 \geq \dots \lambda_{n-1}$ and corresponding eigenvectors u_i so that

$$Au_i = \lambda_i u_i.$$

Let the vector x be written as

$$x = c_0 u_0 + \dots + c_{n-1} u_{n-1},$$

then

$$A^i x = c_0 \lambda_0^i u_0 + \dots + c_{n-1} \lambda_{n-1}^i u_{n-1}.$$

If we write this as

$$A^i x = \lambda_0^i \left[c_0 u_0 + c_1 \left(\frac{\lambda_1}{\lambda_0} \right)^i + \dots + c_{n-1} \left(\frac{\lambda_{n-1}}{\lambda_0} \right)^i \right],$$

we see that, numerically, $A^i x$ will get progressively closer to a multiple of u_0 , the *dominant eigenvector*. Hence, any calculation that uses independence of the $A^i x$ vectors is likely to be inaccurate.

A.1.4 Nonnegative matrices; Perron vectors

If A is a nonnegative matrix, the maximal eigenvalue has the property that its eigenvector is nonnegative: this is the the *Perron-Frobenius theorem*.

Theorem 1 *If a nonnegative matrix A is irreducible, its eigenvalues satisfy*

- *The eigenvalue α_1 that is largest in magnitude is real and simple:*

$$\alpha_1 > |\alpha_2| \geq \dots .$$

- *The corresponding eigenvector is positive.*

A.1.5 The Gershgorin theorem

Finding the eigenvalues of a matrix is usually complicated. However, there are some tools to estimate eigenvalues. In this section you will see a theorem that, in some circumstances, can give useful information on eigenvalues.

Let A be a square matrix, and x, λ an eigenpair: $Ax = \lambda x$. Looking at one component, we have

$$a_{ii}x_i + \sum_{j \neq i} a_{ij}x_j = \lambda x_i.$$

A. Theoretical background

Taking norms:

$$(a_{ii} - \lambda) \leq \sum_{j \neq i} |a_{ij}| \left| \frac{x_j}{x_i} \right|$$

Taking the value of i for which $|x_i|$ is maximal, we find

$$(a_{ii} - \lambda) \leq \sum_{j \neq i} |a_{ij}|.$$

This statement can be interpreted as follows:

The eigenvalue λ is located in the circle around a_{ii} with radius $\sum_{j \neq i} |a_{ij}|$.

Since we do not know for which value of i $|x_i|$ is maximal, we can only say that there is some value of i such that λ lies in such a circle. This is the Gershgorin theorem.

Theorem 2 Let A be a square matrix, and let D_i be the circle with center a_{ii} and radius $\sum_{j \neq i} |a_{ij}|$, then the eigenvalues are contained in the union of circles $\cup_i D_i$.

We can conclude that the eigenvalues are in the interior of these discs, if the constant vector is not an eigenvector.

A.2 Complexity

At various places in this book we are interested in how many operations an algorithm takes. It depends on the context what these operations are, but often we count additions (or subtractions) and multiplications. This is called the *arithmetic* or *computational complexity* of an algorithm. For instance, summing n numbers takes $n - 1$ additions. Another quantity that we may want to describe is the amount of space (computer memory) that is needed. Sometimes the space to fit the input and output of an algorithm is all that is needed, but some algorithms need temporary space. The total required space is called the *space complexity* of an algorithm.

Both arithmetic and space complexity depend on some description of the input, for instance, for summing an array of numbers, the length n of the array is all that is needed. We express this dependency by saying ‘summing an array of numbers has time complexity $n - 1$ additions, where n is the length of the array’.

The time (or space) the summing algorithm takes is not dependent on other factors such as the values of the numbers. By contrast, some algorithms such as computing the greatest common divisor of an array of integers can be dependent on the actual values.

Exercise A.2.1. What is the time and space complexity of multiplying two square matrices of size $n \times n$? Assume that an addition and a multiplication take the same amount of time.

Often we aim to simplify the formulas that describe time or space complexity. For instance, if the complexity of an algorithm is $n^2 + 2n$, we see that for $n > 2$ the complexity is less than $2n^2$, and for $n > 4$ it is less than $(3/2)n^2$. On the other hand, for all values of n the complexity is at least n^2 . Clearly, the quadratic term n^2 is the most important, and the linear term n becomes less and less important by ratio. We express this informally by saying that the complexity is quadratic in n as $n \rightarrow \infty$: there are constants c, C so that for n large enough the complexity is at least cn^2 and at most Cn^2 .

This is expressed for short by saying that the complexity is of *order* n^2 , written as $O(n^2)$ as $n \rightarrow \infty$. In chapter 4 you will see phenomena that we want to describe as orders of a parameter that goes to zero. In that case we write for instance $f(h) = O(h^2)$ as $h \downarrow 0$, meaning that f is bounded by ch^2 and Ch^2 for certain constants c, C and h small enough.

A.3 Partial Differential Equations

Partial Differential Equations are the source of a large fraction of HPC problems. Here is a quick derivation of two of the most important ones.

A.3.1 Partial derivatives

Derivatives of a function $u(x)$ are a measure of the rate of change. Partial derivatives do the same, but for a function $u(x, y)$ of two variables. Notated u_x and u_y , these *partial derivatives* indicate the rate of change if only one variable changes and the other stays constant.

Formally, we define u_x, u_y by:

$$u_x(x, y) = \lim_{h \rightarrow 0} \frac{u(x + h, y) - u(x, y)}{h}, \quad u_y(x, y) = \lim_{h \rightarrow 0} \frac{u(x, y + h) - u(x, y)}{h}$$

A.3.2 Poisson or Laplace Equation

Let T be the temperature of a material, then its heat energy is proportional to it. A segment of length Δx has heat energy $Q = c\Delta x \cdot u$. If the heat energy in that segment is constant

$$\frac{\delta Q}{\delta t} = c\Delta x \frac{\delta u}{\delta t} = 0$$

but it is also the difference between inflow and outflow of the segment. Since flow is proportional to temperature differences, that is, to u_x , we see that also

$$0 = \left. \frac{\delta u}{\delta x} \right|_{x+\Delta x} - \left. \frac{\delta u}{\delta x} \right|_x$$

In the limit of $\Delta x \downarrow 0$ this gives $u_{xx} = 0$, which is called the *Laplace equation*. If we have a source term, for instance corresponding to externally applied heat, the equation becomes $u_{xx} = f$, which is called the *Poisson equation*.

A.3.3 Heat Equation

Let T be the temperature of a material, then its heat energy is proportional to it. A segment of length Δx has heat energy $Q = c\Delta x \cdot u$. The rate of change in heat energy in that segment is

$$\frac{\delta Q}{\delta t} = c\Delta x \frac{\delta u}{\delta t}$$

but it is also the difference between inflow and outflow of the segment. Since flow is proportional to temperature differences, that is, to u_x , we see that also

$$\frac{\delta Q}{\delta t} = \left. \frac{\delta u}{\delta x} \right|_{x+\Delta x} - \left. \frac{\delta u}{\delta x} \right|_x$$

In the limit of $\Delta x \downarrow 0$ this gives $u_t = \alpha u_{xx}$.

A.3.4 Steady state

The solution of an IBVP is a function $u(x, t)$. In cases where the forcing function and the boundary conditions do not depend on time, the solution will converge in time, to a function called the *steady state* solution:

$$\lim_{t \rightarrow \infty} u(x, t) = u_{\text{steadystate}}(x).$$

This solution satisfies a BVP, which can be found by setting $u_t \equiv 0$. For instance, for the heat equation

$$u_t = u_{xx} + q(x)$$

the steady state solution satisfies $-u_{xx} = q(x)$.

A.4 Taylor series

Taylor series expansion is a powerful mathematical tool. In this course it is used several times in proving properties of numerical methods.

The Taylor expansion theorem, in a sense, asks how well functions can be approximated by polynomials, that is, for a given function f , can we find coefficients c_i with $i = 1, \dots, n$ so that

$$f(x) \approx c_0 + c_1x + c_2x^2 + \dots + c_nx^n.$$

This question obviously needs to be refined. What do we mean by ‘approximately equal’? This approximation formula can not hold for all functions f and all x : the function $\sin x$ is bounded for all x , but any polynomial is unbounded for $x \rightarrow \pm\infty$, so any polynomial approximation to the $\sin x$ function is unbounded. Clearly we can only approximate on an interval.

We will show that a function f with sufficiently many derivatives can be approximated as follows: if the n -th derivative $f^{(n)}$ is continuous on an interval I , then there are coefficients c_0, \dots, c_{n-1} such that

$$\forall_{x \in I}: |f(x) - \sum_{i < n} c_i x^i| \leq cM_n \quad \text{where } M_n = \max_{x \in I} |f^{(n)}(x)|$$

It is easy to get inspiration for what these coefficients should be. Suppose

$$f(x) = c_0 + c_1x + c_2x^2 + \dots$$

(where we will not worry about matters of convergence and how long the dots go on) then filling in

$$x = 0 \text{ gives } c_0 = f(0).$$

Next, taking the first derivative

$$f'(x) = c_1 + 2c_2x + 3c_3x^2 + \dots$$

and filling in

$$x = 0 \text{ gives } c_1 = f'(0).$$

From the second derivative

$$f''(x) = 2c_2 + 6c_3x + \dots$$

so filling in $x = 0$ gives

$$c_2 = f''(0)/2.$$

Similarly, in the third derivative

$$\text{filling in } x = 0 \text{ gives } c_3 = \frac{1}{3!}f^{(3)}(0).$$

Now we need to be a bit more precise. Cauchy's form of Taylor's theorem says that

$$f(x) = f(a) + \frac{1}{1!}f'(a)(x-a) + \cdots + \frac{1}{n!}f^{(n)}(a)(x-a)^n + R_n(x)$$

where the 'rest term' R_n is

$$R_n(x) = \frac{1}{(n+1)!}f^{(n+1)}(\xi)(x-a)^{n+1} \quad \text{where } \xi \in (a, x) \text{ or } \xi \in (x, a) \text{ depending.}$$

If $f^{(n+1)}$ is bounded, and $x = a + h$, then the form in which we often use Taylor's theorem is

$$f(x) = \sum_{k=0}^n \frac{1}{k!}f^{(k)}(a)h^k + O(h^{n+1}).$$

We have now approximated the function f on a certain interval by a polynomial, with an error that decreases geometrically with the inverse of the degree of the polynomial.

For a proof of Taylor's theorem we use integration by parts. First we write

$$\int_a^x f'(t)dt = f(x) - f(a)$$

as

$$f(x) = f(a) + \int_a^x f'(t)dt$$

Integration by parts then gives

$$\begin{aligned} f(x) &= f(a) + [xf'(x) - af'(a)] - \int_a^x tf''(t)dt \\ &= f(a) + [xf'(x) - xf'(a) + xf'(a) - af'(a)] - \int_a^x tf''(t)dt \\ &= f(a) + x \int_a^x f''(t)dt + (x-a)f'(a) - \int_a^x tf''(t)dt \\ &= f(a) + (x-a)f'(a) + \int_a^x (x-t)f''(t)dt \end{aligned}$$

Another application of integration by parts gives

$$f(x) = f(a) + (x-a)f'(a) + \frac{1}{2}(x-a)^2f''(a) + \frac{1}{2} \int_a^x (x-t)^2 f'''(t)dt$$

Inductively, this gives us Taylor's theorem with

$$R_{n+1}(x) = \frac{1}{n!} \int_a^x (x-t)^n f^{(n+1)}(t)dt$$

By the mean value theorem this is

$$\begin{aligned} R_{n+1}(x) &= \frac{1}{(n+1)!}f^{(n+1)}(\xi) \int_a^x (x-t)^n f^{(n+1)}(t)dt \\ &= \frac{1}{(n+1)!}f^{(n+1)}(\xi)(x-a)^{n+1} \end{aligned}$$

A.5 Graph theory

Graph theory is the branch of mathematics that studies pairwise relations between objects. Graphs both appear as tools for analyzing issues in HPC, and as objects of study themselves. This appendix introduces the basic concepts and some relevant theory.

A.5.1 Definitions

A graph consists of a set of objects, and set of relations between them. The objects, called the *nodes* or *vertices* of the graph, usually form a finite set, so we usually identify them with consecutive integers $1 \dots n$ or $0 \dots n - 1$. The relation that holds between nodes is described by the *edges* of the graph: if i and j are related, we say that (i, j) is an edge of the graph. This relation does not need to be symmetric, take for instance the ‘less than’ relation.

Formally, then, a graph is a tuple $G = \langle V, E \rangle$ where $V = \{1, \dots, n\}$ for some n , and $E \subset \{(i, j) : 1 \leq i, j \leq n, i \neq j\}$.




Figure A.1: A simple graph

A graph is called an *undirected graph* if $(i, j) \in E \Leftrightarrow (j, i) \in E$. The alternative is a *directed graph*, where we indicate an edge (i, j) with an arrow from i to j .

Two concepts that often appear in graph theory are the degree and the diameter of a graph.

Definition 1 *The degree denotes the maximum number of nodes that are connected to any node:*

$$d(G) \equiv \max_i |\{j : j \neq i \wedge (i, j) \in E\}|.$$

Definition 2 *The diameter of a graph is the length of the longest shortest path in the graph, where a path is defined as a set of vertices v_1, \dots, v_{k+1} such that $v_i \neq v_j$ for all $i \neq j$ and*

$$\forall 1 \leq i \leq k : (v_i, v_{i+1}) \in E.$$

The length of this path is k .

The concept of diameter is illustrated in figure A.2.




Figure A.2: Shortest paths

A path where all nodes are disjoint except for $v_1 = v_{k+1}$ is called a *cycle*.

Sometimes we are only interested in the mere existence of an edge (i, j) , at other times we attach a value or ‘weight’ w_{ij} to that edge. A graph with weighted edges is called a *weighted graph*. Such a graph can be represented as a tuple $G = \langle V, E, W \rangle$ where E and W have the same cardinality.

A.5.2 Common types of graphs

A.5.2.1 Directed Acyclic Graphs

A graph that does not have cycles is called *acyclic*. A special case of this type of graph is the *Directed Acyclic Graph (DAG)*. This type of graph can for instance be used to model dependencies between tasks: if there is an edge between i, j , it means that task i has to be done before task j .

A.5.2.2 Trees

One special case of DAGs is the *tree graph*: here any node can have multiple incoming edges, but only one outgoing edge. Nodes with no incoming edges are *leaf nodes*; a node with no outgoing edges is called a *root* (can there be more than one root?), and all other nodes are called *interior nodes*.

A.5.3 Graph colouring and independent sets

We can assign labels to the nodes of a graph, which is equivalent to partitioning the set of nodes into disjoint subsets. One type of labeling that is of interest is *graph colouring*: here the labels (or ‘colours’) are chosen so that, if nodes i and j have the same colour, there is no edge connecting them: $(i, j) \notin E$.

There is a trivial colouring of a graph, where each node has its own colour. More interestingly, the minimum number of colours with which you can colour a graph is called the *colour number* of the graph.

Exercise A.5.1. Show that, if a graph has degree d , the colour number is at most $d + 1$.

A famous graph colouring problem is the ‘four colour theorem’: if a graph depicts countries on a two-dimensional map (a so-called ‘planar’ graph), then the colour number is at most four. In general, finding the colour number is hard (in fact, NP-hard).

The colour sets of a graph colouring are also called *independent sets*, since within each colour no node is connected to a node of the same colour.

There is a trivial way of finding independent sets: declare each node to have its own unique colour. On the other hand, finding the ‘best’ division in independent sets, for instance through finding the colour number of the graph, is difficult. However, often it is enough to find a reasonable partitioning of the nodes into independent sets, for instance in constructing parallel ILU preconditioners; section 6.6.4. The following algorithm does that [76, 94]:

- Give each node a unique random number.
- Now find the set of nodes that have a higher number than all of their neighbours; call this the first independent set.
- Remove this set from the graph, and find again the nodes with a higher number than all their neighbours; this will be the second set.
- Repeat this procedure until all nodes are in an independent set.

Exercise A.5.2. Convince yourself that the sets found this way are indeed independent.

A.5.4 Graphs and matrices

A graph can be rendered in a number of ways. You could of course just list nodes and edges, but little insight can be derived that way. Simple graphs can be visualized by drawing vertices and edges, but for large graphs this becomes unwieldy. Another option is to construct the *adjacency matrix* of the graph. For a graph $G = \langle V, E \rangle$, the adjacency matrix M (with a size n equal to the number of vertices $|V|$) is defined by

$$M_{ij} = \begin{cases} 1 & (i, j) \in E \\ 0 & \text{otherwise} \end{cases}$$

Conversely, if you have a matrix, especially a *sparse matrix*, you can construct its *adjacency graph*. This is illustrated in figure A.3 for both a dense and a sparse matrix. In this example, the matrices are structurally symmetric, so we use lines instead of arrows in the graphs. There is an edge on each vertex corresponding to the diagonal element; this edge will often be left out of illustrations.




Figure A.3: A dense and a sparse matrix, both with their adjacency graph

If a matrix has no zero elements, its adjacency graph has an edge between each pair of vertices. Such a graph is called a *clique*. If the graph is undirected, the adjacency matrix is symmetric, and conversely, if a matrix is *structurally symmetric*, its adjacency graph is undirected.

As an example of graph concepts that can easily be read from the adjacency matrix, consider reducibility.

Definition 3 A graph is called *irreducible* if for every pair i, j of nodes there is a path from i to j and from j to i . A graph is *reducible* if it is not irreducible.

Exercise A.5.3. Let A be a matrix

$$A = \begin{pmatrix} B & C \\ \emptyset & D \end{pmatrix}$$

where B and D are square matrices. Prove the reducibility of the graph of which this is the adjacency matrix.

For graphs with edge weights, we set the elements of the adjacency matrix to the weights:

$$M_{ij} = \begin{cases} w_{ij} & (i, j) \in E \\ 0 & \text{otherwise} \end{cases}$$

Here is another example of how adjacency matrices can simplify reasoning about graphs.

Exercise A.5.4. Let $G = \langle V, E \rangle$ be an undirected graph, and let $G' = \langle V, E' \rangle$ be the graph with the same vertices, but with vertices defined by

$$(i, j) \in E' \Leftrightarrow \exists k: (i, k) \in E \wedge (k, j) \in E.$$

If M is the adjacency matrix of G , show that M^2 is the adjacency matrix of G' , where we use boolean multiplication on the elements: $1 \cdot 1 = 1$, $1 + 1 = 1$.

A.5.5 Spectral graph theory

With a graph G and its adjacency matrix A_G , we can define a *stochastic matrix* or *Markov matrix* by scaling A_G to have unit column sums¹:

$$W_G = D_G^{-1} A_G \quad \text{where } (D_G)_{ii} = \deg(i).$$

1. A definition using unit row sums is possible too, in that case every product Ax appearing in algorithms is replaced by $x^t A$.

This matrix describes random walks through the graph. Interpret the vertices of the graph as locations or states, meaning you can be in exactly one of them at any time. Let a vector p be a description of the probabilities of being in the nodes of G , then $e^t p = 1$. Now we interpret the edge weights as the probabilities of making a transition to another node. Mathematically, $tW_G p$ describes the probabilities after a single transition. Note that normalizing the column sums means that these transition probabilities add up to 1.

Another matrix to associate with a graph is the *graph Laplacian*

$$L_G = D_G - A_G.$$

This matrix has zero rowsums and positive diagonal entries, so by the Gershgorin theorem (section A.1.5) all its eigenvalues are in the complex right half plane.

Exercise A.5.5. Show that the vector of all ones is an eigenvector with eigenvalue 1.

This Laplacian matrix gives us a quadratic form:

$$x^t L_G x = \sum_{(i,j) \in E} (x_i - x_j)^2.$$

A.5.5.1 Eigenvalue theorems for graph matrices

There are various interesting theorems connected with the graph adjacency and Laplacian matrix. We will not give any proofs; see [120].

First we give *Fiedler's theorem*.

Theorem 3 Let G be a weighted path graph on n vertices, let L_P have eigenvalues $0 = \lambda_1 < \lambda_2 \leq \dots \leq \lambda_n$, and let v_k be an eigenvector of λ_k . Then v_k changes sign $k - 1$ times.

Another theorem by Fiedler [41]:

Theorem 4 Let $G = (V, E, w)$ be a weighted connected graph, and let L_G be its Laplacian matrix. Let $0 = \lambda_1 < \lambda_2 \leq \dots \leq \lambda_n$ be the eigenvalues of L_G and let v_1, \dots, v_n be the corresponding eigenvectors. For any $k \geq 2$, let $W_k = \{i \in V : v_k(i) \geq 0\}$. Then, the graph induced by G on W_k has at most $k - 1$ connected components.

The important consequence of this is that the eigenvector to the first nontrivial eigenvalue can be used to partition the graph in two connected pieces: one of nodes where the eigenvector is positive, and one where the eigenvector is negative.

The adjacency matrix is nonnegative, and there is an extensive theory for this type of matrix [8]; see the Perron-Frobenius theorem in section A.1.4.

Lemma 1 The largest eigenvalue of the adjacency matrix can be bounded by the maximum node degree:

$$\alpha_1 \leq d_{\max}.$$

A.5.5.2 Cheeger's inequality

Above we remarked that the first non-trivial eigenvalue of the graph Laplacian has a relation to partitioning a graph in two parts. The *Cheeger's constant* and *Cheeger's inequality* relate this eigenvalue to a certain quality measure of partitionings.

Let V be the set of vertices and $S \subset V$, then Cheeger's constant of a graph is defined as

$$C = \min_S \frac{e(S, V - S)}{\min \text{vol}(S), \text{vol}(V - S)}$$

where $e(S, V - S)$ denotes the number of edges connecting S to $V - S$, and the volume of a set of nodes is defined as

$$\text{vol}(S) = \sum_{e \in S} d(e).$$

Cheeger's inequality then states

$$2C \geq \lambda \geq \frac{C^2}{2}$$

where λ is the first nontrivial eigenvalue of the graph Laplacian.

A.6 Fourier Transforms

Let $y(t)$ be a function defined on $(-\infty, \infty)$. If this function is built up out of sine and cosine functions

$$y(t) = \sum_{k=-\infty}^{\infty} \alpha_k \sin 2\pi kt + \beta_k \cos 2\pi kt$$

then we can recover the α_k, β_k coefficients from taking the inner product with sine and cosine functions:

$$(\sin 2\pi nt, \sin 2\pi mt) = 0 \quad \text{if } n \neq m$$

where the inner product is defined as

$$(f, g) = \int_{infty}^{\infty} f(t)g(t)dt$$

This inspires us to make a transform function $Y(\omega)$ that describes the frequency content in the function $y(t)$:

$$Y(\omega) = \frac{1}{\sqrt{2\pi}} \int_{-\infty}^{\infty} e^{-i\omega t} y(t) dt$$

If we limit $y(t)$ to a measurement interval $(0, T)$ (or we assume that the function is periodic on this interval) and we use a discrete interval $h = 1/N$, giving measurement point $t_k = kh$ and frequencies $\omega_n = 2\pi n/Nh$, we can approximate

$$\begin{aligned} Y(\omega) &= \frac{1}{\sqrt{2\pi}} \int_{-\infty}^{\infty} e^{-i\omega t} y(t) dt \\ &= \frac{1}{\sqrt{2\pi}} \int_0^T e^{-i\omega t} y(t) dt \\ &= \frac{1}{\sqrt{2\pi}} \sum_{k=1}^N e^{-i\omega_n t_k} y(t_k) h \\ &= \frac{1}{\sqrt{2\pi}} \sum_{k=1}^N e^{-2\pi i kn/N} y(t_k) h \end{aligned}$$

Dividing out h we define

$$Y_n = Y(\omega_n)/h = \frac{1}{\sqrt{2\pi}} \sum_{k=1}^N y_k e^{-2\pi i kn/N}$$

and the inverse transform

$$y(t) = \frac{1}{\sqrt{2\pi}} \int_{-\infty}^{\infty} e^{i\omega t} \approx \sum_{n=1}^N \frac{2\pi}{Nh} \frac{e^{i\omega_n t}}{\sqrt{2\pi}} Y(\omega_n).$$

With a complex variable $Z = e^{-2\pi i/N}$ this becomes

$$y_k = \frac{\sqrt{2\pi}}{N} \sum_{n=1}^N Z^{-nk} Y_n, \quad Y_n = \frac{1}{\sqrt{2\pi}} \sum_{k=1}^N Z^{nk} y_k.$$

To motivate the Fast Fourier Transform (FFT) algorithm let us consider a concrete example with $N = 8$. With $Z_n = e^{-2\pi n/8}$ we have that $Z_n = Z_{n+8k}$ and $Z_{n+4} = -Z_n$, so we only have to compute 4 Z_n values. The computation

$$\begin{aligned} Y_0 &= Z_0y_0 + Z_0y_1 + \dots \\ Y_1 &= Z_0y_0 + Z_1y_1 + Z_2y_2 + \dots \\ Y_2 &= Z_0y_0 + Z_2y_1 + Z_4y_2 + Z_6y_3 + \dots \\ Y_3 &= Z_0y_0 + Z_3y_1 + Z_6y_3 + \dots \\ &\dots \\ y_7 &= Z_0y_1 + Z_7y_1 + Z_{14}y_2 + \dots \end{aligned}$$

reduces to

$$\begin{aligned} Y_0 &= Z_0y_0 + Z_0y_1 + Z_0y_2 + Z_0y_3 + Z_0y_4 + Z_0y_5 + Z_0y_6 + Z_0y_7 \\ Y_1 &= Z_0y_0 + Z_1y_1 + Z_2y_2 + Z_3y_3 - Z_0y_4 - Z_1y_5 - Z_2y_6 - Z_3y_7 \\ Y_2 &= Z_0y_0 + Z_2y_2 - Z_0Y - 2 - Z_2y_3 + Z_0y_4 + Z_2y_5 - Z_0y_6 - Z_0y_7 \\ Y_3 &= Z_0y_0 + Z_3y_1 - Z_2y_2 + Z_1y_3 - Z_0y_4 - Z_3y_5 + Z_2y_6 - Z_1y_7 \\ Y_4 &= Z_0y_0 - Z_0y_1 + Z_0y_2 - Z_0y_3 + Z_0y_4 - Z_0y_5 + Z_0y_6 - Z_0y_7 \\ Y_5 &= Z_0y_0 - Z_1y_1 + Z_2y_2 - Z_3y_3 - Z_0y_4 + Z_1y_5 - Z_2y_6 + Z_3y_7 \\ Y_6 &= Z_0y_0 - Z_2y_2 - Z_0Y_2 + Z_2y_3 + Z_0y_4 - Z_2y_5 - Z_0y_6 + Z_0y_7 \\ Y_7 &= Z_0y_0 - Z_3y_1 - Z_2y_2 - Z_1y_3 - Z_0y_4 + Z_3y_5 + Z_2y_6 + Z_1y_7 \end{aligned}$$

There is a large number of common subexpressions and ‘almost subexpressions’. For instance, note that Y_0, Y_1 contain $Z_0y_0 \pm Z_0y_4$. Next, Y_0, Y_2 and Y_4, Y_6 contain $(Z_0y_0 \pm Z_2y_2) \pm (Z_0y_4 \pm Z_2y_6)$. Et cetera. Thus, the FFT algorithm can be built out of an elementary ‘butterfly’


$$\left. \begin{array}{c} x \\ y \end{array} \right\} \Rightarrow \left\{ \begin{array}{c} x + y \\ x - y \end{array} \right.$$

A.7 Finite State Automatons

Finite State Automatons (FSAs) are mathematical abstractions of simple machines. For example, take a vending machine that will dispense a candy bar when a quarter has been inserted. There are four actions possible with a vending machine: insert a quarter, press ‘coin return’ to ask for any inserted money back, open the window to take the candy bar, and close the window again. Whether an action is possible (especially the third) depends on the state the machine is in. There are three states: the begin state, the state where the quarter has been inserted and the window unlocked (let us call this ‘ready to dispense’), and the state where the window is open (which we will call ‘dispensing’).

In certain states, certain actions are not possible. For instance, in the beginning state the window can not be opened.

The mathematical description of this vending machine consists of 1. the list of states, 2. a table of how the possible actions make the machine go from one state to another. However, rather than writing down the table, a graphical representation is usually more insightful.



Appendix B

Practical tutorials

In the theory part of this book you learned mathematical models can be translated to algorithms that can be realized efficiently on modern hardware. You learned how data structures and coding decisions influence the performance of your code. In other words, you should now have all the tools to write programs that solve scientific problems.

This would be all you would need to know, if there was any guarantee that a correctly derived algorithm and well designed data structure could immediately be turned into a correct program. Unfortunately, there is more to programming than that. This collection of tutorials will give you the tools to be an effective scientific programmer.

The vast majority of scientific programming is done on the Unix platform so we start out with a tutorial on Unix in section B.1, followed by an explanation of the how your code is handled by compilers and linkers and such in section B.2.

Next you will learn about some tools that will increase your productivity and effectiveness:

- The *Make* utility is used for managing the building of projects; section B.3.
- Source control systems store your code in such a way that you can undo changes, or maintain multiple versions; in section B.4 you will see the *subversion* software.
- Storing and exchanging scientific data becomes an important matter once your program starts to produce results; in section B.5 you will learn the use of *HDF5*.
- A lot of functionality that you need has been coded already by other people; in section B.6 you will learn about some of the scientific libraries that are available to you.
- Visual output of program data is important, but too wide a topic to discuss here in great detail; section B.7 teaches you the basics of the *gnuplot* package, which is suitable for simple data plotting.

We also consider the activity of program development itself: section B.8 considers how to code to prevent errors, and section B.9 teaches you to debug code with *gdb*. Section B.10 discusses measuring the performance of code. Section B.11 contains some information on how to write a program that uses more than one programming language.

Finally, section B.12 teaches you about the L^AT_EX document system, so that you can report on your work in beautifully typeset articles.

Many of the tutorials are very hands-on. Do them while sitting at a computer!

B.1 Unix intro

Unix is an *Operating System (OS)*, that is, a layer of software between the user or a user program and the hardware. It takes care of files and screen output, and it makes sure that many processes can exist side by side on one system. However, it is not immediately visible to the user. Most of the time that you use Unix, you are typing commands which are executed by an interpreter called the *shell*. The shell makes the actual OS calls. There are a few possible Unix shells available, but in this tutorial we will assume that you are using the *sh* or *bash* shell, although many commands are common to the various shells in existence.

This short tutorial will get you going; if you want to learn more about Unix and shell scripting, see for instance <http://www.tldp.org/guides.html>.

B.1.1 Files and such

Purpose. In this section you will learn about the Unix file system, which consists of *directories* that store *files*. You will learn about *executable* files and commands for displaying data files.

B.1.1.1 Looking at files

Purpose. In this section you will learn commands for displaying file contents.

The `ls` command gives you a listing of files that are in your present location.

Exercise. Type `ls`. Does anything show up?

Expected outcome. If there are files in your directory, they will be listed; if there are none, no output will be given. This is standard Unix behaviour: no output does not mean that something went wrong, it only means that there is nothing to report.

The `cat` command is often used to display files, but it can also be used to create some simple content.

Exercise. Type `cat > newfilename` (where you can pick any filename) and type some text. Conclude with `Control-d` on a line by itself. Now use `cat` to view the contents of that file: `cat newfilename`.

Expected outcome. In the first use of `cat`, text was concatenated from the terminal to a file; in the second the file was cat'ed to the terminal output. You should see on your screen precisely what you typed into the file.

Caveats. Be sure to type `Control-d` as the first thing on the last line of input. If you really get stuck, `Control-c` will usually get you out. Try this: start creating a file with `cat > filename` and hit `Control-c` in the middle of a line. What are the contents of your file?

Above you used `ls` to get a directory listing. You can also use the `ls` command on specific files:

Exercise. Do `ls newfilename` with the file that you created above; also do `ls nosuchfile` with a file name that does not exist.

Expected outcome. For an existing file you get the file name on your screen; for a non-existing file you get an error message.

The `ls` command can give you all sorts of information.

Exercise. Read the man page of the `ls` command: `man ls`. Find out the size and creation date of some files, for instance the file you just created.

Expected outcome. Did you find the `ls -s` and `ls -l` options? The first one lists the size of each file, usually in kilobytes, the other gives all sorts of information about a file, including things you will learn about later.

Caveats. The `man` command puts you in a mode where you can view long text documents. This viewer is common on Unix systems (it is available as the `more` or `less` system command), so memorize the following ways of navigating: Use the space bar to go forward and the `u` key to go back up. Use `g` to go to the beginning of the text, and `G` for the end. Use `q` to exit the viewer. If you really get stuck, `Control-c` will get you out.

(If you already know what command you're looking for, you can use `man` to get online information about it. If you forget the name of a command, `man -k keyword` can help you find it.)

The `touch` command creates an empty file, updates the timestamp of a file if it already exists. Use `ls -l` to confirm this behaviour.

Three more useful commands for files are: `cp` for copying, `mv` (short for ‘move’) for renaming, and `rm` (‘remove’) for deleting. Experiment with them.

There are more commands for displaying a file, parts of a file, or information about a file.

Exercise. Do `ls /usr/share/words` or `ls /usr/share/dict/words` to confirm that a file with words exists on your system. Now experiment with the commands `head`, `tail`, `more`, and `wc` using that file.


Expected outcome. `head` displays the first couple of lines of a file, `tail` the last, and `more` uses the same viewer that is used for `man` pages. Read the `man` pages for these commands and experiment with increasing and decreasing the amount of output. The `wc` (‘word count’) command reports the number of words, characters, and lines in a file.

B.1.1.2 Directories

Purpose. Here you will learn about the Unix directory tree, how to manipulate it and how to move around in it.

B. Practical tutorials

A unix file system is a tree of directories, where a directory is a container for files or more directories. We will display directories as follows:




The root of the Unix directory tree is indicated with a slash. Do `ls /` to see what the files and directories there are in the root. Note that the root is not the location where you start when you reboot your personal machine, or when you log in to a server.

Exercise. The command to find out your current working directory is `pwd`. Your home directory is your working directory immediately when you log in. Find out your home directory.

Expected outcome. You will typically see something like `/home/yourname` or `/Users/yourname`. This is system dependent.

Do `ls` to see the contents of the working directory. In the displays in this section, directory names will be followed by a slash: `dir/` but this character is not part of their name. You can get this output by using `ls -F`, and you can tell your shell to use this output consistently by stating alias `ls=ls -F` at the start of your session. Example:



The command for making a new directory is `mkdir`.

Exercise. Make a new directory with `mkdir newdir` and view the current directory with `ls`

Expected outcome. You should see this structure:



The command for going into another directory, that is, making it your working directory, is `cd` ('change directory'). It can be used in the following ways:

- `cd` Without any arguments, `cd` takes you to your home directory.
- `cd <absolute path>` An absolute path starts at the root of the directory tree, that is, starts with `/`. The `cd` command takes you to that location.
- `cd <relative path>` A relative path is one that does not start at the root. This form of the `cd` command takes you to `<yourcurrentdir>/<relative path>`.

Exercise. Do `cd newdir` and find out where you are in the directory tree with `pwd`. Confirm with `ls` that the directory is empty. How would you get to this location using an absolute path?

Expected outcome. `pwd` should tell you `/home/you/newdir`, and `ls` then has no output, meaning there is nothing to list. The absolute path is `/home/you/newdir`.

Exercise. Let's quickly create a file in this directory: `touch onefile`, and another directory: `mkdir otherdir`. Do `ls` and confirm that there are a new file and directory.

Expected outcome. You should now have:

```
/home/you/
└── newdir/.....you are here
    ├── onefile
    └── otherdir/
```

The `ls` command has a very useful option: with `ls -a` you see your regular files and hidden files, which have a name that starts with a dot. Doing `ls -a` in your new directory should tell you that there are the following files:

```
/home/you/
└── newdir/.....you are here
    ├── .
    ├── ..
    ├── onefile
    └── otherdir/
```

The single dot is the current directory, and the double dot is the directory one level back.

Exercise. Predict where you will be after `cd ./otherdir/..` and check to see if you were right.

Expected outcome. The single dot sends you to the current directory, so that does not change anything. The `otherdir` part makes that subdirectory your current working directory. Finally, `..` goes one level back. In other words, this command puts you right back where you started.

Since your home directory is a special place, there are shortcuts for `cd`'ing to it: `cd` without arguments, `cd ~`, and `cd $HOME` all get you back to your home.

Go to your home directory, and from there do `ls newdir` to check the contents of the first directory you created, without having to go there.

Exercise. What does `ls ..` do?

Expected outcome. Recall that `..` denotes the directory one level up in the tree: you should see your own home directory, plus the directories of any other users.

Exercise. Can you use `ls` to see the contents of someone else's home directory? In the previous exercise you saw whether other users exist on your system. If so, do `ls ../thatotheruser`.

Expected outcome. If this is your private computer, you can probably view the contents of the other user's directory. If this is a university computer or so, the other directory may very well be protected – permissions are discussed in the next section – and you get `ls: ../otheruser: Permission denied`.

Make an attempt to move into someone else's home directory with `cd`. Does it work?

B. Practical tutorials

You can make copies of a directory with `cp`, but you need to add a flag to indicate that you recursively copy the contents: `cp -r`. Make another directory `somedir` in your home so that you have

```
/home/you/
└── newdir/.....you have been working in this one
    └── somedir/.....you just created this one
```

What is the difference between `cp -r newdir somedir` and `cp -r newdir thirddir` where `thirddir` is not an existing directory name?

B.1.1.3 Permissions

Purpose. In this section you will learn about how to give various users on your system permission to do (or not to do) various things with your files.

Unix files, including directories, have permissions, indicating ‘who can do what with this file’. Actions that can be performed on a file fall into three categories:

- reading `r`: any access to a file (displaying, getting information on it) that does not change the file;
- writing `w`: access to a file that changes its content, or even its metadata such as ‘date modified’;
- executing `x`: if the file is executable, to run it; if it is a directory, to enter it.

The people who can potentially access a file are divided into three classes too:

- the user `u`: the person owning the file;
- the group `g`: a group of users to which the owner belongs;
- other `o`: everyone else.

These nine permissions are rendered in sequence

<code>user</code>	<code>group</code>	<code>other</code>
<code>rwx</code>	<code>rwx</code>	<code>rwx</code>

For instance `rwx-r--r--` means that the owner can read and write a file, the owner’s group and everyone else can only read.

Permissions are also rendered numerically in groups of three bits, by letting `r = 4, w = 2, x = 1`:

<code>rwx</code>
421

Common codes are `7 = rwx` and `6 = rw`. You will find many files that have permissions `755` which stands for an executable that everyone can run, but only the owner can change, or `644` which stands for a data file that everyone can see but again only the owner can alter. You can set permissions by

```
chmod <permissions> file          # just one file
chmod -R <permissions> directory # directory, recursively
```

Examples:

```
chmod 766 file # set to rwxrw-rw-
chmod g+w file # give group write permission
chmod g=rx file # set group permissions
chmod o-w file # take away write permission from others
chmod o= file # take away all permissions from others.
chmod g+r,o-x file # give group read permission
                  # remove other execute permission
```

The man page gives all options.

Exercise. Make a file `foo` and do `chmod u-r foo`. Can you now inspect its contents? Make the file readable again, this time using a numeric code. Now make the file readable to your classmates. Check by having one of them read the contents.

Expected outcome. When you've made the file 'unreadable' by yourself, you can still `ls` it, but not `cat` it: that will give a 'permission denied' message.

Make a file `com` with the following contents:

```
#!/bin/sh
echo "Hello world!"
```

This is a legitimate shell script. What happens when you type `./com`? Can you make the script executable?

Adding or taking away permissions can be done with the following syntax:

B.1.1.4 Wildcards

You already saw that `ls filename` gives you information about that one file, and `ls` gives you all files in the current directory. To see files with certain conditions on their names, the *wildcard* mechanism exists. The following wildcards exist:

- * any number of characters.
- ? any character.

Example:

```
%% ls
      sk      ski      skiing    skill
%% ls ski*
ski      skiing    skill
```

The second option lists all files whose name start with `ski`, followed by any number of other characters'; below you will see that in different contexts `ski*` means 'sk followed by any number of i characters'. Confusing, but that's the way it is.

B.1.2 Text searching and regular expressions

Purpose. In this section you will learn how to search for text in files.

For this section you need at least one file that contains some amount of text. You can for instance get random text from <http://www.lipsum.com/feed/html>.

The `grep` command can be used to search for a text expression in a file.

Exercise. Search for the letter `q` in your text file with `grep q yourfile` and search for it in all files in your directory with `grep q *`. Try some other searches.

Expected outcome. In the first case, you get a listing of all lines that contain a `q`; in the second case, `grep` also reports what file name the match was found in: `qfile:this line has q in it`.

Caveats. If the string you are looking for does not occur, `grep` will simply not output anything. Remember that this is standard behaviour for Unix commands if there is nothing to report.

In addition to searching for literal strings, you can look for more general expressions.

<code>^</code>	the beginning of the line
<code>\$</code>	the end of the line
<code>.</code>	any character
<code>*</code>	any number of repetitions
<code>[xyz]</code>	any of the characters xyz

This looks like the wildcard mechanism you just saw (section B.1.1.4) but it's subtly different. Compare the example above with:

```
%% cat s
sk
ski
skill
skiing
%% grep "ski*" s
sk
ski
skill
skiing
```

In the second case you search for a string consisting of `sk` and any number of `i` characters, including zero of them.

Some more examples: you can find

- All lines that contain the letter ‘q’ with `grep q yourfile`;
- All lines that start with an ‘a’ with `grep "^a" yourfile` (if your search string contains special characters, it is a good idea to use quote marks to enclose it);

- All lines that end with a digit with `grep "[0-9]\$" yourfile`.

Exercise. Construct the search strings for finding

- lines that start with an uppercase character, and
- lines that contain exactly one character.

Expected outcome. For the first, use the range characters [], for the second use the period to match any character.

Exercise. Add a few lines `x = 1`, `x = 2`, `x = 3` (that is, have different numbers of spaces between `x` and the equals sign) to your test file, and make `grep` commands to search for all assignments to `x`.

The characters in the table above have special meanings. If you want to search that actual character, you have to *escape* it.

Exercise. Make a test file that has both `abc` and `a.c` in it, on separate lines. Try the commands `grep "a.c" file`, `grep a\..c file`, `grep "a\..c" file`.

Expected outcome. You will see that the period needs to be escaped, and the search string needs to be quoted. In the absence of either, you will see that `grep` also finds the `abc` string.

B.1.2.1 Stream editing with sed

Unix has various tools for processing text files on a line-by-line basis. The stream editor `sed` is one example. If you have used the `vi` editor, you are probably used to a syntax like `s/foo/bar/` for making changes. With `sed`, you can do this on the commandline. For instance

```
sed 's/foo/bar/' myfile > mynewfile
```

will apply the substitute command `s/foo/bar/` to every line of `myfile`. The output is shown on your screen so you should capture it in a new file; see section B.1.3.2 for more on output redirection.

B.1.2.2 Cutting up lines with cut

Another tool for editing lines is `cut`, which will cut up a line and display certain parts of it. For instance,

```
cut -c 2-5 myfile
```

will display the characters in position 2–5 of every line of `myfile`. Make a test file and verify this example.

Maybe more useful, you can give `cut` a delimiter character and have it split a line on occurrences of that delimiter. For instance, your system will mostly likely have a file `/etc/passwd` that contains user information¹, with every line consisting of fields separated by colons. For instance:

1. This is traditionally the case; on Mac OS information about users is kept elsewhere and this file only contains system services.

```
daemon:*:1:1:System Services:/var/root:/usr/bin/false
nobody:*:-2:-2:Unprivileged User:/var/empty:/usr/bin/false
root:*:0:0:System Administrator:/var/root:/bin/sh
```

The seventh and last field is the login shell of the user; `/bin/false` indicates that the user is unable to log in.

You can display users and their login shells with:

```
cut -d ":" -f 1,7 /etc/passwd
```

This tells `cut` to use the colon as delimiter, and to print fields 1 and 7.

B.1.3 Command execution

B.1.3.1 Search paths

Purpose. In this section you will learn how Unix determines what to do when you type a command name.

If you type a command such as `ls`, the shell does not just rely on a list of commands: it will actually go searching for a program by the name `ls`. This means that you can have multiple different commands with the same name, and which one gets executed depends on which one is found first.

Exercise. What you may think of as ‘Unix commands’ are often just executable files in a system directory. Do which `ls`, and do an `ls -l` on the result

Expected outcome. The location of `ls` is something like `/bin/ls`. If you `ls` that, you will see that it is probably owned by root. Its executable bits are probably set for all users.

The locations where unix searches for commands is the ‘search path’, which is stored in the *environment variable* (for more details see below) `PATH`.

Exercise. Do `echo $PATH`. Can you find the location of `cd`? Are there other commands in the same location? Is the current directory ‘.’ in the path? If not, do `export PATH=".:$PATH"`. Now create an executable file `cd` in the current director (see above for the basics), and do `cd`.

Expected outcome. The path will be a list of colon-separated directories, for instance `/usr/bin:/usr/local/bin:/usr/X11R6/bin`. If the working directory is in the path, it will probably be at the end: `/usr/X11R6/bin:.` but most likely it will not be there. If you put ‘.’ at the start of the path, unix will find the local `cd` command before the system one.

Some people consider having the working directory in the path a security risk. If your directory is writable, someone could put a malicious script named `cd` (or any other system command) in your directory, and you would execute it unwittingly.

It is possible to define your own commands as aliases of existing commands.

Exercise. Do `alias chdir=cd` and convince yourself that now `chdir` works just like `cd`. Do `alias rm='rm -i'`; look up the meaning of this in the man pages. Some people find this alias a good idea; can you see why?

Expected outcome. The `-i` ‘interactive’ option for `rm` makes the command ask for confirmation before each delete. Since unix does not have a trashcan that needs to be emptied explicitly (as on Windows or the Mac OS), this can be a good idea.

B.1.3.2 Redirection and Pipelines

Purpose. In this section you will learn how to feed one command into another, and how to connect commands to input and output files.

So far, the unix commands you have used have taken their input from your keyboard, or from a file named on the command line; their output went to your screen. There are other possibilities for providing input from a file, or for storing the output in a file.

B.1.3.2.1 Input redirection The `grep` command had two arguments, the second being a file name. You can also write `grep string < yourfile`, where the less-than sign means that the input will come from the named file, `yourfile`.

B.1.3.2.2 Output redirection More usefully, `grep string yourfile > outfile` will take what normally goes to the terminal, and send it to `outfile`. The output file is created if it didn’t already exist, otherwise it is overwritten. (To append, use `grep text yourfile >> outfile`.)

Exercise. Take one of the `grep` commands from the previous section, and send its output to a file. Check that the contents of the file are identical to what appeared on your screen before. Search for a string that does not appear in the file and send the output to a file. What does this mean for the output file?

Expected outcome. Searching for a string that does not occur in a file gives no terminal output. If you redirect the output of this `grep` to a file, it gives a zero size file. Check this with `ls` and `wc`.

B.1.3.2.3 Standard files Unix has three standard files that handle input and output:

`stdin` is the file that provides input for processes.

`stdout` is the file where the output of a process is written.

`stderr` is the file where error output is written.

In an interactive session, all three files are connected to the user terminal. Using input or output redirection then means that the input is taken or the output sent to a different file than the terminal.

B. Practical tutorials

B.1.3.2.4 Command redirection Instead of taking input from a file, or sending output to a file, it is possible to connect two commands together, so that the second takes the output of the first as input. The syntax for this is cmdone | cmdtwo; this is called a pipeline. For instance, grep a yourfile | grep b finds all lines that contains both an a and a b.

Exercise. Construct a pipeline that counts how many lines there are in your file that contain the string th. Use the wc command (see above) to do the counting.

There are a few more ways to combine commands. Suppose you want to present the result of wc a bit nicely. Type the following command

```
echo The line count is `wc -l foo`
```

where foo is the name of an existing file. The way to get the actual line count echoed is by the backquote:

```
echo The line count is `wc -l foo`
```

Anything in between backquotes is executed before the rest of the command line is evaluated. The way wc is used here, it prints the file name. Can you find a way to prevent that from happening?

B.1.3.3 Processes

The Unix operating system can run many programs at the same time, by rotating through the list and giving each only a fraction of a second to run each time. The command ps can tell you everything that is currently running.

Exercise. Type ps. How many programs are currently running? By default ps gives you only programs that you explicitly started. Do ps -u *wax* for a detailed list of everything that is running. How many programs are running? How many belong to the root user, how many to you?

Expected outcome. To count the programs belonging to a user, pipe the ps command through an appropriate grep, which can then be piped to wc.

In this long listing of ps, the second column contains the process numbers. Sometimes it is useful to have those. The cut command explained above can cut certain position from a line: type ps -u *wax* | cut -c 10-14.

To get dynamic information about all running processes, use the top command. Read the man page to find out how to sort the output by CPU usage.

When you type a command and hit return, that command becomes, for the duration of its run, the *foreground process*. Everything else that is running at the same time is a *background process*.

Make an executable file hello with the following contents:

```
#!/bin/sh
while [ 1 ] ; do
```

```
sleep 2
date
done
```

and type `./hello`.

Exercise. Type `Control-z`. This suspends the foreground process. It will give you a number like [1] or [2] indicating that it is the first or second program that has been suspended or put in the background. Now type `bg` to put this process in the background. Confirm that there is no foreground process by hitting return, and doing an `ls`.

Expected outcome. After you put a process in the background, the terminal is available again to accept foreground commands. If you hit return, you should see the command prompt. However, the background process still keeps generating output.

Exercise. Type `jobs` to see the processes in the current session. If the process you just put in the background was number 1, type `fg %1`. Confirm that it is a foreground process again.

Expected outcome. If a shell is executing a program in the foreground, it will not accept command input, so hitting return should only produce blank lines.

Exercise. When you have made the `hello` script a foreground process again, you can kill it with `Control-c`. Try this. Start the script up again, this time as `./hello &` which immediately puts it in the background. You should also get output along the lines of [1] 12345 which tells you that it is the first job you put in the background, and that 12345 is its process ID. Kill the script with `kill %1`. Start it up again, and kill it by using the process number.

Expected outcome. The command `kill 12345` using the process number is usually enough to kill a running program. Sometimes it is necessary to use `kill -9 12345`.

B.1.3.4 Shell customization

Above it was mentioned that `ls -F` is an easy way to see which files are regular, executable, or directories; by typing `alias ls='ls -F'` the `ls` command will automatically expanded to `ls -F` every time it is invoked. If you would like this behaviour in every login session, you can add the `alias` command to your `.profile` file. Other shells than sh/bash have other files for such customizations.

B.1.4 Scripting

The unix shells are also programming environments. You will learn more about this aspect of unix in this section.

B. Practical tutorials

B.1.4.1 Shell variables

Above you encountered PATH, which is an example of an shell, or environment, variable. These are variables that are known to the shell and that can be used by all programs run by the shell. You can see the full list of all variables known to the shell by typing env.

You can get the value of a shell variable by prefixing it with a dollar sign. Type the following two commands and compare the output:

```
echo PATH  
echo $PATH
```

Exercise. Check on the value of the HOME variable by typing echo \$HOME. Also find the value of HOME by piping env through grep.

B.1.4.2 Control structures

Like any good programming system, the shell has some control structures. Their syntax takes a bit of getting used to. (Different shells have different syntax; in this tutorial we only discuss the bash shell).

In the bash shell, control structures can be written over several lines:

```
if [ $PATH = "" ] ; then  
    echo "Error: path is empty"  
fi
```

or on a single line:

```
if [ `wc -l file` -gt 100 ] ; then echo "file too long" ; fi
```

There are a number of tests defined, for instance -f somefile tests for the existence of a file. Change your script so that it will report -1 if the file does not exist.

There are also loops. A for loop looks like

```
for var in listofitems ; do  
    something with $var  
done
```

This does the following:

- for each item in listofitems, the variable var is set to the item, and
- the loop body is executed.

As a simple example:

```
%% for x in a b c ; do echo $x ; done  
a  
b
```

c

In a more meaningful example, here is how you would make backups of all your .c files:

```
for cfile in *.c ; do  
    cp $myfile $myfile.bak  
done
```

Shell variables can be manipulated in a number of ways. Execute the following commands to see that you can remove trailing characters from a variable:

```
%% a=b.c  
%% echo ${a%.c}  
b
```

With this as a hint, write a loop that renames all your .c files to .x files.

B.1.4.3 Scripting

It is possible to write programs of unix shell commands. First you need to know how to put a program in a file and have it be executed. Make a file `script1` containing the following two lines:

```
#!/bin/bash  
echo "hello world"
```

and type `./script1` on the command line. Result? Make the file executable and try again.

You can give your script command line arguments. If you want to be able to call

```
./script1 foo bar
```

you can use variables `$1, $2` et cetera in the script:

```
#!/bin/bash  
  
echo "The first argument is $1"  
echo "There were $# arguments in all"
```

Write a script that takes as input a file name argument, and reports how many lines are in that file.

Edit your script to test whether the file has less than 10 lines (use the `foo -lt bar` test), and if it does, `cat` the file. Hint: you need to use backquotes inside the test.

The number of command line arguments is available as `$#`. Add a test to your script so that it will give a helpful message if you call it without any arguments.

B.1.5 Expansion

The shell performs various kinds of expansion on a command line, that is, replacing part of the command-line with different text.

Brace expansion:

```
%% echo a{b,cc,ddd}e  
abe acce addde
```

This can for instance be used to delete all extension of some base file name:

```
%% rm tmp.{c,s,o} # delete tmp.c tmp.s tmp.o
```

Tilde expansion gives your own, or someone else's home directory:

```
%% echo ~  
/share/home/00434/eijkhout  
%% echo ~eijkhout  
/share/home/00434/eijkhout
```

Parameter expansion gives the value of shell variables:

```
%% x=5  
%% echo $x  
5
```

Undefined variables do not give an error message:

```
%% echo $y
```

There are many variations on parameter expansion. Above you already saw that you can strip trailing characters:

```
%% a=b.c  
%% echo ${a%.c}  
b
```

Here is how you can deal with undefined variables:

```
%% echo ${y:-0}  
0
```

The backquote mechanism (section B.1.3.2 above) is known as command substitution:

```
%% echo 123 > w  
%% cat w  
123  
%% wc -c w
```

```
        4 w
%% if [ `cat w | wc -c` -eq 4 ] ; then echo four ; fi
four
```

Unix shell programming is very much oriented towards text manipulation, but it is possible to do arithmetic. Arithmetic substitution tells the shell to treat the expansion of a parameter as a number:

```
%% x=1
%% echo $((x*2))
2
```

Integer ranges can be used as follows:

```
%% for i in {1..10} ; do echo $i ; done
1
2
3
4
5
6
7
8
9
10
```

B.1.6 Shell interaction

Interactive use of Unix, in contrast to script writing (section B.1.4), is a complicated conversation between the user and the shell. You, the user, type a line, hit return, and the shell tries to interpret it. There are several cases.

- Your line contains one full command, such as `ls foo`: the shell will execute this command.
- You can put more than one command on a line, separated by semicolons: `mkdir foo; cd foo`. The shell will execute these commands in sequence.
- Your input line is not a full command, for instance `while [1]`. The shell will recognize that there is more to come, and use a different prompt to show you that it is waiting for the remainder of the command.
- Your input line would be a legitimate command, but you want to type more on a second line. In that case you can end your input line with a backslash character, and the shell will recognize that it needs to hold off on executing your command. In effect, the backslash will hide (*escape*) the return.

When the shell has collected a command line to execute, by using one or more of your input line or only part of one, as described just now, it will apply expansion to the command line (section B.1.5). It will then

interpret the commandline as a command and arguments, and proceed to invoke that command with the arguments as found.

There are some subtleties here. If you type `ls * .c`, then the shell will recognize the wildcard character and expand it to a command line, for instance `ls foo.c bar.c`. Then it will invoke the `ls` command with the argument list `foo.c bar.c`. Note that `ls` does not receive `* .c` as argument! In cases where you do want the unix command to receive an argument with a wildcard, you need to escape it so that the shell will not expand it. For instance, `find . -name *.c` will make the shell invoke `find` with arguments `. -name *.c`.

B.1.7 The system and other users

If you are on your personal machine, you may be the only user logged in. On university machines or other servers, there will often be other users. Here are some commands relating to them.

`whoami` show your login name
`who` show the other currently logged in users
`finger otherusername` get information about another user
`top` which processes are running on the system; use `top -u` to get this sorted the amount of cpu time they are currently taking. (On Linux, try also the `vmstat` command.)
`uptime` how long has your system been up?

B.1.8 Review questions

Exercise B.1.1. Write a shell script for making backups. When you call this script as `./backup somefile` it should test whether `somefile.bak` exists, and give a warning if it does. In either case, it should copy the original file to a backup.

B.2 Compilers and libraries

B.2.1 An introduction to binary files

Purpose. In this section you will be introduced to the different types of binary files that you encounter while programming.

One of the first things you become aware of when you start programming is the distinction between the readable source code, and the unreadable, but executable, program code. In this tutorial you will learn about a couple more file types:

- A source file can be compiled to an *object file*, which is a bit like a piece of an executable: by itself it does nothing, but it can be combined with other object files to form an executable.
- A *library* is a bundle of object files that can be used to form an executable. Often, libraries are written by an expert and contain code for specialized purposes such as linear algebra manipulations. Libraries are important enough that they can be commercial, to be bought if you need expert code for a certain purpose.

You will now learn how these types of files are created and used.

B.2.2 Simple compilation

Purpose. In this section you will learn about executables and object files.

Let's start with a simple program that has the whole source in one file.

One file: `hello.c` Compile this program with your favourite compiler; we will use `gcc` in this tutorial, but substitute your own as desired. As a result of the compilation, a file `a.out` is created, which is the executable.

```
%% gcc hello.c
%% ./a.out
hello world
```

You can get a more sensible program name with the `-o` option:

```
%% gcc -o helloprog hello.c
%% ./helloprog
hello world
```

Now we move on to a program that is in more than one source file.

Main program: `fooprog.c`

Subprogram: `fooprog.c` As before, you can make the program with one command.

```
%% gcc -o foo fooprog.c foosub.c
%% ./foo
hello world
```

However, you can also do it in steps, compiling each file separately and then linking them together.

```
%% gcc -c fooprog.c
%% gcc -c foosub.c
%% gcc -o foo fooprog.o foosub.o
%% ./foo
hello world
```

The `-c` option tells the compiler to compile the source file, giving an *object file*. The third command then acts as the *linker*, tying together the object files into an executable. (With programs that are spread over several files there is always the danger of editing a subroutine definition and then forgetting to update all the places it is used. See the ‘make’ tutorial, section B.3, for a way of dealing with this.)

B.2.3 Libraries

Purpose. In this section you will learn about libraries.

If you have written some subprograms, and you want to share them with other people (perhaps by selling them), then handing over individual object files is inconvenient. Instead, the solution is to combine them into a library. First we look at *static libraries*, for which the *archive utility* `ar` is used. A static library is linked into your executable, becoming part of it. This may lead to large executables; you will learn about shared libraries next, which do not suffer from this problem.

Create a directory to contain your library (depending on what your library is for this can be a system directory such as `/usr/bin`), and create the library file there.

```
%% mkdir .. /lib
%% ar cr .. /lib/libfoo.a foosub.o
```

The `nm` command tells you what’s in the library:

```
%% nm .. /lib/libfoo.a

.. /lib/libfoo.a (foosub.o) :
00000000 T _bar
U _printf
```

Line with `T` indicate functions defined in the library file; a `U` indicates a function that is used.

The library can be linked into your executable by explicitly giving its name, or by specifying a library path:

```
%% gcc -o foo fooprog.o .. /lib/libfoo.a
# or
%% gcc -o foo fooprog.o -L .. /lib -lfoo
%% ./foo
hello world
```

A third possibility is to use the `LD_LIBRARY_PATH` shell variable. Read the man page of your compiler for its use, and give the commandlines that create the `foo` executable, linking the library through this path.

Although they are somewhat more complicated to use, *shared libraries* have several advantages. For instance, since they are not linked into the executable but only loaded at runtime, they lead to (much) smaller executables. They are not created with `ar`, but through the compiler. For instance:

```
%% gcc -dynamiclib -o ../lib/libfoo.so foosub.o
%% nm ../lib/libfoo.so

../lib/libfoo.so(single module):
00000fc4 t __dyld_func_lookup
00000000 t __mh_dylib_header
00000fd2 T _bar
    U _printf
00001000 d dyld_mach_header
00000fb0 t dyld_stub_binding_helper
```

Shared libraries are not actually linked into the executable; instead, the executable will contain the information where the library is to be found at execution time:

```
%% gcc -o foo fooprog.o -L../lib -Wl,-rpath,'pwd'../lib -lfoo
%% ./foo
hello world
```

The link line now contains the library path twice:

1. once with the `-L` directive so that the linker can resolve all references, and
2. once with the linker directive `-Wl,-rpath,'pwd'../lib` which stores the path into the executable so that it can be found at runtime.

Build the executable again, but without the `-Wl` directive. Where do things go wrong and why? You can also fix this problem by using `LD_LIBRARY_PATH`. Explore this.

Use the command `ldd` to get information about what shared libraries your executable uses. (On Mac OS X, use `otool -L` instead.)

B.3 Managing projects with Make

The *Make* utility helps you manage the building of projects: its main task is to facilitate rebuilding only those parts of a multi-file project that need to be recompiled or rebuilt. This can save lots of time, since it can replace a minutes-long full installation by a single file compilation. *Make* can also help maintaining multiple installations of a program on a single machine, for instance compiling a library with more than one compiler, or compiling a program in debug and optimized mode.

Make is a Unix utility with a long history, and traditionally there are variants with slightly different behaviour, for instance on the various flavours of Unix such as HP-UX, AIX, IRIX. These days, it is advisable, no matter the platform, to use the GNU version of *Make* which has some very powerful extensions; it is available on all Unix platforms (on Linux it is the only available variant), and it is a *de facto* standard. The manual is available at <http://www.gnu.org/software/make/manual/make.html>, or you can read the book [96].

There are other build systems, most notably *Scons* and *Bjam*. We will not discuss those here. The examples in this tutorial will be for the C and Fortran languages, but *Make* can work with any language, and in fact with things like *TeX* that are not really a language at all; see section B.3.6.

B.3.1 A simple example

Purpose. In this section you will see a simple example, just to give the flavour of *Make*.

The files for this section can be downloaded from <http://tinyurl.com/ISTC-make-tutorial>.

B.3.1.1 C

Make the following files:

foo.c

bar.c

bar.h and a makefile:

Makefile

The makefile has a number of rules like

```
foo.o : foo.c  
<TAB>cc -c foo.c
```

which have the general form

```
target : prerequisite(s)  
<TAB>rule(s)
```

where the rule lines are indented by a TAB character.

A rule, such as above, states that a ‘target’ file `foo.o` is made from a ‘prerequisite’ `foo.c`, namely by executing the command `cc -c foo.c`. The precise definition of the rule is:

- if the target `foo.o` does not exist or is older than the prerequisite `foo.c`,
- then the command part of the rule is executed: `cc -c foo.c`
- If the prerequisite is itself the target of another rule, than that rule is executed first.

Probably the best way to interpret a rule is:

- if any prerequisite has changed,
- then the target needs to be remade,
- and that is done by executing the commands of the rule;
- checking the prerequisite requires a recursive application of make:
 - if the prerequisite does not exist, find a rule to create it;
 - if the prerequisite already exists, check applicable rules to see if it needs to be remade.

If you call `make` without any arguments, the first rule in the makefile is evaluated. You can execute other rules by explicitly invoking them, for instance `make foo.o` to compile a single file.

Exercise. Call `make`.

Expected outcome. The above rules are applied: `make` without arguments tries to build the first target, `fooprog`. In order to build this, it needs the prerequisites `foo.o` and `bar.o`, which do not exist. However, there are rules for making them, which `make` recursively invokes. Hence you see two compilations, for `foo.o` and `bar.o`, and a link command for `fooprog`.

Caveats. Typos in the makefile or in file names can cause various errors. In particular, make sure you use tabs and not spaces for the rule lines. Unfortunately, debugging a makefile is not simple. `Make`’s error message will usually give you the line number in the make file where the error was detected.

Exercise. Do `make clean`, followed by `mv foo.c boo.c` and `make` again. Explain the error message. Restore the original file name.

Expected outcome. `Make` will complain that there is no rule to make `foo.c`. This error was caused when `foo.c` was a prerequisite for making `foo.o`, and was found not to exist. `Make` then went looking for a rule to make it and no rule for creating `.c` files exists.

Now add a second argument to the function `bar`. This requires you to edit `bar.c` and `bar.h`: go ahead and make these edits. However, it also requires you to edit `foo.c`, but let us for now ‘forget’ to do that. We will see how `Make` can help you find the resulting error.

Exercise. Call `make` to recompile your program. Did it recompile `foo.c`?

Expected outcome. Even though conceptually `foo.c` would need to be recompiled since it uses the `bar` function, `Make` did not do so because the makefile had no rule that forced it.

In the makefile, change the line

B. Practical tutorials

```
foo.o : foo.c
```

to

```
foo.o : foo.c bar.h
```

which adds `bar.h` as a prerequisite for `foo.o`. This means that, in this case where `foo.o` already exists, `Make` will check that `foo.o` is not older than any of its prerequisites. Since `bar.h` has been edited, it is younger than `foo.o`, so `foo.o` needs to be reconstructed.

Exercise. Confirm that the new makefile indeed causes `foo.o` to be recompiled if `bar.h` is changed. This compilation will now give an error, since you ‘forgot’ to edit the use of the `bar` function.

B.3.1.2 Fortran

Make the following files:

`foomain.F`

`foomod.F` and a makefile:

`Makefile` If you call `make`, the first rule in the makefile is executed. Do this, and explain what happens.

Exercise. Call `make`.

Expected outcome. The above rules are applied: `make` without arguments tries to build the first target, `foomain`. In order to build this, it needs the prerequisites `foomain.o` and `foomod.o`, which do not exist. However, there are rules for making them, which `make` recursively invokes. Hence you see two compilations, for `foomain.o` and `foomod.o`, and a link command for `fooprog`.

Caveats. Typos in the makefile or in file names can cause various errors. Unfortunately, debugging a makefile is not simple. You will just have to understand the errors, and make the corrections.

Exercise. Do `make clean`, followed by `mv foomod.c boomod.c` and `make again`. Explain the error message. Restore the original file name.

Expected outcome. `Make` will complain that there is no rule to make `foomod.c`. This error was caused when `foomod.c` was a prerequisite for `foomod.o`, and was found not to exist. `Make` then went looking for a rule to make it, and no rule for making `.F` files exists.

Now add an extra parameter to `func` in `foomod.F` and recompile.

Exercise. Call `make` to recompile your program. Did it recompile `foomain.F`?

Expected outcome. Even though conceptually `foomain.F` would need to be recompiled, *Make* did not do so because the makefile had no rule that forced it.

Change the line

```
foomain.o : foomain.F
```

to

```
foomain.o : foomain.F foomod.o
```

which adds `foomod.o` as a prerequisite for `foomain.o`. This means that, in this case where `foomain.o` already exists, *Make* will check that `foomain.o` is not older than any of its prerequisites. Recursively, *Make* will then check if `foomode.o` needs to be updated, which is indeed the case. After recompiling `foomode.F`, `foomode.o` is younger than `foomain.o`, so `foomain.o` will be reconstructed.

Exercise. Confirm that the corrected makefile indeed causes `foomain.F` to be recompiled.

B.3.1.3 About the make file

The make file needs to be called `makefile` or `Makefile`; it is not a good idea to have files with both names in the same directory. If you want *Make* to use a different file as make file, use the syntax `make -f My_Makefile`.

B.3.2 Variables and template rules

Purpose. In this section you will learn various work-saving mechanisms in *Make*, such as the use of variables and of template rules.

B.3.2.1 Makefile variables

It is convenient to introduce variables in your makefile. For instance, instead of spelling out the compiler explicitly every time, introduce a variable in the makefile:

```
CC = gcc  
FC = gfortran
```

and use `$(CC)` or `$(FC)` on the compile lines:

```
foo.o : foo.c  
        $(CC) -c foo.c  
foomain.o : foomain.F  
        $(FC) -c foomain.F
```

B. Practical tutorials

Exercise. Edit your makefile as indicated. First do `make clean`, then `make foo` (C) or `make fooprog` (Fortran).

Expected outcome. You should see the exact same compile and link lines as before.

Caveats. Unlike in the shell, where braces are optional, variable names in a makefile have to be in braces or parentheses. Experiment with what happens if you forget the braces around a variable name.

One advantage of using variables is that you can now change the compiler from the commandline:

```
make CC="icc -O2"  
make FC="gfortran -g"
```

Exercise. Invoke `Make` as suggested (after `make clean`). Do you see the difference in your screen output?

Expected outcome. The compile lines now show the added compiler option `-O2` or `-g`.

`Make` also has built-in variables:

- `$@` The target. Use this in the link line for the main program.
- `$^` The list of prerequisites. Use this also in the link line for the program.
- `$<` The first prerequisite. Use this in the compile commands for the individual object files.

Using these variables, the rule for `fooprog` becomes

```
fooprog : foo.o bar.o  
          ${CC} -o $@ $^
```

and a typical compile line becomes

```
foo.o : foo.c bar.h  
        ${CC} -c $<
```

You can also declare a variable

```
THEPROGRAM = fooprog
```

and use this variable instead of the program name in your makefile. This makes it easier to change your mind about the name of the executable later.

Exercise. Construct a commandline so that your makefile will build the executable `fooprog_v2`.

Expected outcome. `make THEPROGRAM=fooprog_v2`

B.3.2.2 Template rules

In your makefile, the rules for the object files are practically identical:

- the rule header (`foo.o : foo.c`) states that a source file is a prerequisite for the object file with the same base name;
- and the instructions for compiling (`$(CC) -c $<`) are even character-for-character the same, now that you are using *Make*'s built-in variables;
- the only rule with a difference is

```
foo.o : foo.c bar.h  
        $(CC) -c $<
```

where the object file depends on the source file and another file.

We can take the commonalities and summarize them in one rule²:

```
%.o : %.c  
      $(CC) -c $<  
%.o : %.F  
      $(FC) -c $<
```

This states that any object file depends on the C or Fortran file with the same base name. To regenerate the object file, invoke the C or Fortran compiler with the `-c` flag. These template rules can function as a replacement for the multiple specific targets in the makefiles above, except for the rule for `foo.o`.

The dependence of `foo.o` on `bar.h`, or `foomain.o` on `foomod.o`, can be handled by adding a rule

```
# C  
foo.o : bar.h  
# Fortran  
foomain.o : foomod.o
```

with no further instructions. This rule states, ‘if file `bar.h` or `foomod.o` changed, file `foo.o` or `foomain.o` needs updating’ too. *Make* will then search the makefile for a different rule that states how this updating is done, and it will find the template rule.

Exercise. Change your makefile to incorporate these ideas, and test.

B.3.3 Wildcards

Your makefile now uses one general rule for compiling all your source files. Often, these source files will be all the `.c` or `.F` files in your directory, so is there a way to state ‘compile everything in this directory’? Indeed there is. Add the following lines to your makefile, and use the variable `COBJECTS` or `FOBJECTS` wherever appropriate.

2. This mechanism is the first instance you’ll see that only exists in GNU make, though in this particular case there is a similar mechanism in standard make. That will not be the case for the wildcard mechanism in the next section.

```
# wildcard: find all files that match a pattern
CSOURCES := ${wildcard *.c}
# pattern substitution: replace one pattern string by another
COBJECTS := ${patsubst %.c,%.o,${SRC} }

FSOURCES := ${wildcard *.F}
FOBJECTS := ${patsubst %.F,%.o,${SRC} }
```

B.3.4 Miscellania

B.3.4.1 What does this makefile do?

Above you learned that issuing the `make` command will automatically execute the first rule in the makefile. This is convenient in one sense³, and inconvenient in another: the only way to find out what possible actions a makefile allows is to read the makefile itself, or the – usually insufficient – documentation.

A better idea is to start the makefile with a target

```
info :
    @echo "The following are possible:"
    @echo "  make"
    @echo "  make clean"
```

Now `make` without explicit targets informs you of the capabilities of the makefile.

B.3.4.2 Phony targets

The example makefile contained a target `clean`. This uses the *Make* mechanisms to accomplish some actions that are not related to file creation: calling `make clean` causes *Make* to reason ‘there is no file called `clean`, so the following instructions need to be performed’. However, this does not actually cause a file `clean` to spring into being, so calling `make clean` again will make the same instructions being executed.

To indicate that this rule does not actually make the target, declare

```
.PHONY : clean
```

One benefit of declaring a target to be phony, is that the *Make* rule will still work, even if you have a file named `clean`.

3. There is a convention among software developers that a package can be installed by the sequence `./configure ; make ; make install`, meaning: Configure the build process for this computer, Do the actual build, Copy files to some system directory such as `/usr/bin`.

B.3.4.3 Predefined variables and rules

Calling `make -p yourtarget` causes make to print out all its actions, as well as the values of all variables and rules, both in your makefile and ones that are predefined. If you do this in a directory where there is no makefile, you'll see that make actually already knows how to compile `.c` or `.F` files. Find this rule and find the definition of the variables in it.

You see that you can customize make by setting such variables as `CFLAGS` or `FFLAGS`. Confirm this with some experimentation. If you want to make a second makefile for the same sources, you can call `make -f othermakefile` to use this instead of the default `Makefile`.

Note, by the way, that both `makefile` and `Makefile` are legitimate names for the default makefile. It is not a good idea to have both `makefile` and `Makefile` in your directory.

B.3.4.4 Using the target as prerequisite

Suppose you have two different targets that are treated largely the same. You would want to write:

```
PROGS = myfoo other
${PROGS} : ${@.o}
${CC} -o ${@} ${@.o} ${list of libraries goes here}
```

and saying `make myfoo` would cause

```
cc -c myfoo.c
cc -o myfoo myfoo.o ${list of libraries}
```

and likewise for `make other`. What goes wrong here is the use of `${@.o}` as prerequisite. In Gnu Make, you can repair this as follows⁴:

```
.SECONDEXPANSION:
${PROGS} : $$@.o
```

Exercise. Write a second main program `foosecond.c` or `foosecond.F`, and change your makefile so that the calls `make foo` and `make foosecond` both use the same rule.

B.3.5 Shell scripting in a Makefile

Purpose. In this section you will see an example of a longer shell script appearing in a makefile rule.

In the makefiles you have seen so far, the command part was a single line. You can actually have as many lines there as you want. For example, let us make a rule for making backups of the program you are building.

Add a backup rule to your makefile. The first thing it needs to do is make a backup directory:

4. Technical explanation: Make will now look at lines twice: the first time `$$` gets converted to a single `$`, and in the second pass `$$` becomes the name of the target.

```
.PHONY : backup
backup :
    if [ ! -d backup ] ; then
        mkdir backup
    fi
```

Did you type this? Unfortunately it does not work: every line in the command part of a makefile rule gets executed as a single program. Therefore, you need to write the whole command on one line:

```
backup :
    if [ ! -d backup ] ; then mkdir backup ; fi
```

or if the line gets too long:

```
backup :
    if [ ! -d backup ] ; then \
        mkdir backup ; \
    fi
```

Next we do the actual copy:

```
backup :
    if [ ! -d backup ] ; then mkdir backup ; fi
    cp myprog backup/myprog
```

But this backup scheme only saves one version. Let us make a version that has the date in the name of the saved program.

The Unix `date` command can customize its output by accepting a format string. Type the following:
`date` This can be used in the makefile.

Exercise. Edit the `cp` command line so that the name of the backup file includes the current date.

Expected outcome. Hint: you need the backquote. Consult the Unix tutorial if you do not remember what backquotes do.

If you are defining shell variables in the command section of a makefile rule, you need to be aware of the following. Extend your `backup` rule with a loop to copy the object files:

```
backup :
    if [ ! -d backup ] ; then mkdir backup ; fi
    cp myprog backup/myprog
    for f in ${OBJS} ; do \
        cp $f backup ; \
    done
```

(This is not the best way to copy, but we use it for the purpose of demonstration.) This leads to an error message, caused by the fact that *Make* interprets `$f` as an environment variable of the outer process. What works is:

```
backup :  
    if [ ! -d backup ] ; then mkdir backup ; fi  
    cp myprog backup/myprog  
    for f in ${OBJS} ; do \  
        cp $$f backup ; \  
    done
```

(In this case *Make* replaces the double dollar by a single one when it scans the commandline. During the execution of the commandline, `$f` then expands to the proper filename.)

B.3.6 A Makefile for L^AT_EX

The *Make* utility is typically used for compiling programs, but other uses are possible too. In this section, we will discuss a makefile for L^AT_EX documents.

We start with a very basic makefile: The command `make myfile.pdf` will invoke `pdflatex myfile.tex`, if needed, once. Next we repeat invoking `pdflatex` until the log file no longer reports that further runs are needed: We use the `$(basename fn)` macro to extract the base name without extension from the target name.

In case the document has a bibliography or index, we run `bibtex` and `makeindex`. The minus sign at the start of the line means that *Make* should not abort if these commands fail.

Finally, we would like to use *Make*'s facility for taking dependencies into account. We could write a makefile that has the usual rules

```
mainfile.pdf : mainfile.tex includefile.tex
```

but we can also discover the include files explicitly. The following makefile is invoked with

```
make pdf TEXTFILE=mainfile
```

The `pdf` rule then uses some shell scripting to discover the include files (but not recursively), and it calls `emphMake` again, invoking another rule, and passing the dependencies explicitly. This shell scripting can also be done outside the makefile, generating the makefile dynamically.

B.4 Source control

Source code control systems, also called *revision control* systems, are a way of storing software, where not only the current version is stored, but also all previous versions. This is done by maintaining a *repository* for all versions, while one or more users work on a ‘checked out’ copy of the latest version. Those of the users that are developers can then commit their changes to the repository. Other users then update their local copy. The repository typically resides on a remote machine that is reliably backup up.

There are various reasons for keeping your source in a repository.

- If you work in a team, it is the best way to synchronize your work with your colleagues. It is also a way to document what changes were made, by whom, and why.
- It will allow you to roll back a defective code to a version that worked.
- It allows you to have branches, for instance for customizations that need to be kept out of the main development line. If you are working in a team, a branch is a way to develop a major feature, stay up to date with changes your colleagues make, and only add your feature to the main development when it is sufficiently tested.
- If you work alone, it is a way to synchronize between more than one machine. (You could even imagine traveling without all your files, and installing them from the repository onto a borrowed machine as the need arises.)
- Having a source code repository is one way to backup your work.

There are various source code control systems; in this tutorial you will learn the basics of *Subversion*, also called *svn*.

B.4.1 How to do this tutorial

This lab should be done two people, to simulate a group of programmers working on a joint project. You can also do this on your own by using two copies of the repository.

B.4.2 Create and populate a repository

Purpose. In this section you will create a repository and make a local copy to work on.

First we need to have a repository. In practice, you will often use one that has been set up by a sysadmin, but there are several ways to set up a repository yourself.

- There are commercial and free hosting services such as <http://code.google.com/projecthosting> (open source only) or <http://unfuddle.com/about/tour/plans>. Once you create a repository there, you can make a local copy on your computer:

```
%% svn co http://yourname.unfuddle.com/svn/yourname_yourproject/ pro
```

Checked out revision 0.
where `co` is short for ‘check out’.
- Alternatively, you can create a repository in the local file system:

```
%% svnadmin create ./repository --fs-type=fsfs
```

To make it accessible do

```
%% chmod -R g+rwx ./repository  
%% chmod g+rX ~
```

To make a copy of the repository you specify a file URL:

```
%% svn co file://`pwd`/repository project
```

You now have an empty directory `project`.

Exercise. Go into the project directory and see if it is really empty.

Expected outcome. There is a hidden directory `.svn`

The project directory knows where the master copy of the repository is stored.

Exercise. Do `svn info`

Expected outcome. You will see the URL of the repository and the revision number

Caveats. Make sure you are in the right directory. In the outer directories, you will get `svn: warning: '.' is not a working copy`

B.4.3 New files

Purpose. In this section you will make some simple changes: editing an existing file and creating a new file.

One student now makes a file to add to the repository⁵.

```
%% cat > firstfile  
a  
b  
c  
d  
e  
f  
^D
```

This file is unknown to `svn`:

```
%% svn status  
? firstfile
```

5. It is also possible to use `svn import` to create a whole repository from an existing directory tree.

B. Practical tutorials

We need to declare the file as belonging to the repository; a subsequent `svn commit` command then copies it into the master repository.

```
%% svn add firstfile
A          firstfile
%% svn status
A          firstfile
%% svn commit -m "made a first file"
Adding      firstfile
Transmitting file data .
Committed revision 1.
```

Exercise. The second student can now do `svn update` to update their copy of the repository

Expected outcome. `svn` should report A `firstfile` and Updated to revision 1.. Check that the contents of the file are correct.

Caveats. In order to do the update command, you have to be in a checked-out copy of the repository. Do `svn info` to make sure that you are in the right place.

Exercise. Let both students create a new directory with a few files. Declare the directory and commit it. Do `svn update` to obtain the changes the other mde.

Expected outcome. You can do `svn add` on the directory, this will also add the files contained in it.

Caveats. Do not forget the `commit`.

In order for `svn` to keep track of your files, you should never do `cp` or `mv` on files that are in the repository. Instead, do `svn cp` or `svn mv`. Likewise, there are commands `svn rm` and `svn mkdir`.

B.4.4 Conflicts

Purpose. In this section you will learn about how do deal with conflicting edits by two users of the same repository.

Now let's see what happens when two people edit the same file. Let both students make an edit to `firstfile`, but one to the top, the other to the bottom. After one student commits the edit, the other will see

```
%% emacs firstfile # make some change
%% svn commit -m "another edit to the first file"
Sending      firstfile
svn: Commit failed (details follow):
svn: Out of date: 'firstfile' in transaction '5-1'
```

The solution is to get the other edit, and commit again. After the update, `svn` reports that it has resolved a conflict successfully.

```
%% svn update
G firstfile
Updated to revision 5.
%% svn commit -m "another edit to the first file"
Sending      firstfile
Transmitting file data .
Committed revision 6.
```

The G at the start of the line indicates that svn has resolved a conflicting edit.

If both students make edits on the same part of the file, svn can no longer resolve the conflicts. For instance, let one student insert a line between the first and the second, and let the second student edit the second line. Whoever tries to commit second, will get messages like this:

```
%% svn commit -m "another edit to the first file"
svn: Commit failed (details follow):
svn: Aborting commit: '/share/home/12345/yourname/myproject/firstfile'
remains in conflict
%% svn update
C firstfile
Updated to revision 7.
```

Subversion will give you several options. For instance, you can type e to open the file in an editor. You can also type p for ‘postpone’ and edit it later. Opening the file in an editor, it will look like

```
aa
<<<<< .mine
bb
=====
123
b
>>>>> .r7
cc
```

indicating the difference between the local version (‘mine’) and the remote. You need to edit the file to resolve the conflict.

After this, you tell svn that the conflict was resolved, and you can commit:

```
%% svn resolved firstfile
Resolved conflicted state of 'firstfile'
%% svn commit -m "another edit to the first file"
Sending      firstfile
Transmitting file data .
Committed revision 8.
```

The other student then needs to do another update to get the correction.

B.4.5 Inspecting the history

Purpose. In this section, you will learn how to get information about the repository.

You've already seen `svn info` as a way of getting information about the repository. To get the history, do `svn log` to get all log messages, or `svn log 2:5` to get a range.

To see differences in various revisions of individual files, use `svn diff`. First do `svn commit` and `svn update` to make sure you are up to date. Now do `svn diff firstfile`. No output, right? Now make an edit in `firstfile` and do `svn diff firstfile` again. This gives you the difference between the last committed version and the working copy.

You can also ask for differences between committed versions with `svn diff -r 4:6 firstfile`.

The output of this `diff` command is a bit cryptic, but you can understand it without too much trouble. There are also fancy GUI implementations of `svn` for every platform that show you differences in a much nicer way.

If you simply want to see what a file used to look like, do `svn cat -r 2 firstfile`. To get a copy of a certain revision of the repository, do `svn export -r 3 . . ./rev3`, which exports the repository at the current directory ('dot') to the directory `./rev3`.

If you save the output of `svn diff`, it is possible to apply it with the Unix `patch` command. This is a quick way to send patches to someone without them needing to check out the repository.

B.4.6 Shuffling files around

We now realize that we really wanted all these files in a subdirectory in the repository. First we create the directory, putting it under `svn` control:

```
%% svn mkdir trunk  
A trunk
```

Then we move all files there, again prefixing all commands with `svn`:

```
%% for f in firstfile otherfile myfile mysecondfile ; do \  
    svn mv $f trunk/ ; done  
A trunk/firstfile  
D firstfile  
A trunk/otherfile  
D otherfile  
A trunk/myfile  
D myfile  
A trunk/mysecondfile  
D mysecondfile
```

Finally, we commit these changes:

```
%% svn commit -m "trunk created"
Deleting      firstfile
Adding        trunk/firstfile
Deleting      myfile
Deleting      mysecondfile
Deleting      otherfile
Adding        trunk
Adding        trunk/myfile
Adding        trunk/mysecondfile
Adding        trunk/otherfile
```

You probably now have picked up on the message that you always use `svn` to do file manipulations. Let's pretend this has slipped your mind.

Exercise. Create a file `somefile` and commit it to the repository. Then do `rm somefile`, thereby deleting a file without `svn` knowing about it. What is the output of `svn status`?

Expected outcome. `svn` indicates with an exclamation point that the file has disappeared.

You can fix this situation in a number of ways:

- `svn revert` restores the file to the state in which it was last restored. For a deleted file, this means that it is brought back into existence from the repository. This command is also useful to undo any local edits, if you change your mind about something.
- `svn rm firstfile` is the official way to delete a file. You can do this even if you have already deleted the file outside `svn`.
- Sometimes `svn` will get confused about your attempts to delete a file. You can then do `svn --force rm yourfile`.

B.4.7 Branching and merging

Suppose you want to tinker with the repository, while still staying up to date with changes that other people make.

```
%% svn copy \
<the URL of your repository>/trunk \
<the URL of your repository>/onebranch \
-m "create a branch"
```

```
Committed revision 11.
```

You can check this out as before:

B. Practical tutorials

```
%% svn co <the URL of your repository>/onebranch \
    projectbranch
A  projectbranch/mysecondfile
A  projectbranch/otherfile
A  projectbranch/myfile
A  projectbranch/firstfile
Checked out revision 11.
```

Now, if you make edits in this branch, they will not be visible in the trunk:

```
%% emacs firstfile # do some edits here
%% svn commit -m "a change in the branch"
Sending      firstfile
Transmitting file data .
Committed revision 13.
%% (cd ../myproject/trunk/ ; svn update )
At revision 13.
```

On the other hand, edits in the main trunk can be pulled into this branch:

```
%% svn merge ^/trunk
--- Merging r13 through r15 into '.':
U      secondfile
```

When you are done editing, the branch edits can be added back to the trunk. For this, it is best to have a clean checkout of the branch:

```
%% svn co file://`pwd`/repository/trunk mycleanproject
A      # all the current files
```

and then do a special merge:

```
%% cd mycleanproject
%% svn merge --reintegrate ^/branch
--- Merging differences between repository URLs into '.':
U      firstfile
U      .
%% svn info
Path: .
URL: <the URL of your repository>/trunk
Repository Root: <the URL of your repository>
Repository UUID: dc38b821-b9c6-4ala-a194-a894fbald7e7
Revision: 16
Node Kind: directory
Schedule: normal
Last Changed Author: build
```

```
Last Changed Rev: 14
Last Changed Date: 2009-05-18 13:34:55 -0500 (Mon, 18 May 2009)
%% svn commit -m "trunk updates from the branch"
Sending .
Sending      firstfile
Transmitting file data .
Committed revision 17.
```

B.4.8 Repository browsers

The `svn` command can give you some amount of information about a repository, but there are graphical tools that are easier to use and that give a better overview of a repository. For the common platforms, several such tools exist, free or commercial. Here is a browser based tool: <http://www.websvn.info>.

B.4.9 Other source control systems

Lately, there has been considerable interest in ‘distributed source code control’ system, such as *git* or *mercurial*. In these systems, each user has a local repository against which commits can be made. This has some advantages over systems like `svn`.

Consider the case where a developer is working on a patch that takes some time to code and test. During this time, development on the project goes on, and by the time the patch can be committed, too many changes have been made for `svn` to be able to merge the patch. As a result, branching and merging is often a frustrating experience with traditional system. In distributed systems, the developer can do commits against the local repository, and roll back versions as needed. Additionally, when the patch is ready to merge back, it is not a single massive change, but a sequence of small changes, which the source control system should be better able to handle.

A good introduction to Mercurial can be found at <http://www.hginit.com/>.

B.5 Scientific Data Storage

There are many ways of storing data, in particular data that comes in arrays. A surprising number of people stores data in spreadsheets, then exports them to ascii files with comma or tab delimiters, and expects other people (or other programs written by themselves) to read that in again. Such a process is wasteful in several respects:

- The ascii representation of a number takes up much more space than the internal binary representation. Ideally, you would want a file to be as compact as the representation in memory.
- Conversion to and from ascii is slow; it may also lead to loss of precision.

For such reasons, it is desirable to have a file format that is based on binary storage. There are a few more requirements on a useful file format:

- Since binary storage can differ between platforms, a good file format is platform-independent. This will, for instance, prevent the confusion between *big-endian* and *little-endian* storage, as well as conventions of 32 versus 64 bit floating point numbers.
- Application data can be heterogeneous, comprising integer, character, and floating point data. Ideally, all this data should be stored together.
- Application data is also structured. This structure should be reflected in the stored form.
- It is desirable for a file format to be *self-documenting*. If you store a matrix and a right-hand side vector in a file, wouldn't it be nice if the file itself told you which of the stored numbers are the matrix, which the vector, and what the sizes of the objects are?

This tutorial will introduce the HDF5 library, which fulfills these requirements. HDF5 is a large and complicated library, so this tutorial will only touch on the basics. For further information, consult <http://www.hdfgroup.org/HDF5/>. While you do this tutorial, keep your browser open on <http://www.hdfgroup.org/HDF5/doc/> or http://www.hdfgroup.org/HDF5/RM/RM_H5Front.html for the exact syntax of the routines.

B.5.1 Introduction to HDF5

As described above, HDF5 is a file format that is machine-independent and self-documenting. Each HDF5 file is set up like a directory tree, with subdirectories, and leaf nodes which contain the actual data. This means that data can be found in a file by referring to its name, rather than its location in the file. In this section you will learn to write programs that write to and read from HDF5 files. In order to check that the files are as you intend, you can use the `h5dump` utility on the command line.⁶

Just a word about compatibility. The HDF5 format is not compatible with the older version HDF4, which is no longer under development. You can still come across people using hdf4 for historic reasons. This tutorial is based on HDF5 version 1.6. Some interfaces changed in the current version 1.8; in order to use 1.6 APIs with 1.8 software, add a flag `-DH5_USE_16_API` to your compile line.

Many HDF5 routines are about creating objects: file handles, members in a dataset, et cetera. The general syntax for that is

6. In order to do the examples, the `h5dump` utility needs to be in your path, and you need to know the location of the `hdf5.h` and `libhdf5.a` and related library files.

```
hid_t h_id;
h_id = H5Xsomething(...);
```

Failure to create the object is indicated by a negative return parameter, so it would be a good idea to create a file `myh5defs.h` containing:

```
#include "hdf5.h"
#define H5REPORT(e) \
    {if (e<0) {printf("\nHDF5 error on line %d\n\n", __LINE__); return e;}}
```

and use this as:

```
#include "myh5defs.h"

hid_t h_id;
h_id = H5Xsomething(...); H5REPORT(h_id);
```

B.5.2 Creating a file

First of all, we need to create an HDF5 file.

```
hid_t file_id;
herr_t status;

file_id = H5Fcreate( filename, ... );
...
status = H5Fclose(file_id);
```

This file will be the container for a number of data items, organized like a directory tree.

Exercise. Create an HDF5 file by compiling and running the `create.c` example below.

Expected outcome. A file `file.h5` should be created.

Caveats. Be sure to add HDF5 include and library directories:

```
cc -c create.c -I. -I/opt/local/include
```

and

```
cc -o create create.o -L/opt/local/lib -lhdf5. The include and lib directories will be
system dependent.
```

You can display the created file on the commandline:

```
%% h5dump file.h5
HDF5 "file.h5" {
GROUP "/" {
}
```

```
}
```

Note that an empty file corresponds to just the root of the directory tree that will hold the data.

B.5.3 Datasets

Next we create a dataset, in this example a 2D grid. To describe this, we first need to construct a dataspace:

```
dims[0] = 4; dims[1] = 6;
dataspace_id = H5Screate_simple(2, dims, NULL);
dataset_id = H5Dcreate(file_id, "/dset", dataspace_id, .... );
.....
status = H5Dclose(dataset_id);
status = H5Sclose(dataspace_id);
```

Note that datasets and dataspaces need to be closed, just like files.

Exercise. Create a dataset by compiling and running the `dataset.c` code below

Expected outcome. This creates a file `dset.h5` that can be displayed with `h5dump`.

We again view the created file online:

```
%% h5dump dset.h5
HDF5 "dset.h5" {
GROUP "/" {
    DATASET "dset" {
        DATATYPE H5T_STD_I32BE
        DATASPACE SIMPLE { ( 4, 6 ) / ( 4, 6 ) }
        DATA {
            (0,0): 0, 0, 0, 0, 0, 0,
            (1,0): 0, 0, 0, 0, 0, 0,
            (2,0): 0, 0, 0, 0, 0, 0,
            (3,0): 0, 0, 0, 0, 0, 0
        }
    }
}
}
```

The datafile contains such information as the size of the arrays you store. Still, you may want to add related scalar information. For instance, if the array is output of a program, you could record with what input parameter was it generated.

```
parmspace = H5Screate(H5S_SCALAR);
parm_id = H5Dcreate
    (file_id, "/parm", H5T_NATIVE_INT, parmspace, H5P_DEFAULT);
```

Exercise. Add a scalar dataspace to the HDF5 file, by compiling and running the `parmwrite.c` code below.

Expected outcome. A new file `wdset.h5` is created.

```
%% h5dump wdset.h5
HDF5 "wdset.h5" {
GROUP "/" {
    DATASET "dset" {
        DATATYPE H5T_IEEE_F64LE
        DATASPACE SIMPLE { ( 4, 6 ) / ( 4, 6 ) }
        DATA {
            (0,0): 0.5, 1.5, 2.5, 3.5, 4.5, 5.5,
            (1,0): 6.5, 7.5, 8.5, 9.5, 10.5, 11.5,
            (2,0): 12.5, 13.5, 14.5, 15.5, 16.5, 17.5,
            (3,0): 18.5, 19.5, 20.5, 21.5, 22.5, 23.5
        }
    }
    DATASET "parm" {
        DATATYPE H5T_STD_I32LE
        DATASPACE SCALAR
        DATA {
            (0): 37
        }
    }
}
}
```

B.5.4 Writing the data

The datasets you created allocate the space in the hdf5 file. Now you need to put actual data in it. This is done with the `H5Dwrite` call.

```
/* Write floating point data */
for (i=0; i<24; i++) data[i] = i+.5;
status = H5Dwrite
    (dataset,H5T_NATIVE_DOUBLE,H5S_ALL,H5S_ALL,H5P_DEFAULT,
     data);
/* write parameter value */
parm = 37;
status = H5Dwrite
    (parmset,H5T_NATIVE_INT,H5S_ALL,H5S_ALL,H5P_DEFAULT,
     &parm);
```

```

%% h5dump wdset.h5
HDF5 "wdset.h5" {
GROUP "/" {
    DATASET "dset" {
        DATATYPE H5T_IEEE_F64LE
        DATASPACE SIMPLE { ( 4, 6 ) / ( 4, 6 ) }
        DATA {
            (0,0): 0.5, 1.5, 2.5, 3.5, 4.5, 5.5,
            (1,0): 6.5, 7.5, 8.5, 9.5, 10.5, 11.5,
            (2,0): 12.5, 13.5, 14.5, 15.5, 16.5, 17.5,
            (3,0): 18.5, 19.5, 20.5, 21.5, 22.5, 23.5
        }
    }
    DATASET "parm" {
        DATATYPE H5T_STD_I32LE
        DATASPACE SCALAR
        DATA {
            (0): 37
        }
    }
}
}

```

If you look closely at the source and the dump, you see that the data types are declared as ‘native’, but rendered as `LE`. The ‘native’ declaration makes the datatypes behave like the built-in C or Fortran data types. Alternatively, you can explicitly indicate whether data is *little-endian* or *big-endian*. These terms describe how the bytes of a data item are ordered in memory. Most architectures use little endian, as you can see in the dump output, but, notably, IBM uses big endian.

B.5.5 Reading

Now that we have a file with some data, we can do the mirror part of the story: reading from that file. The essential commands are

```

h5file = H5Fopen( .... )
....
H5Dread( dataset, .... data .... )

```

where the `H5Dread` command has the same arguments as the corresponding `H5Dwrite`.

Exercise. Read data from the `wdset.h5` file that you create in the previous exercise, by compiling and running the `allread.c` example below.

Expected outcome. Running the `allread` executable will print the value 37 of the parameter, and the value 8.5 of the (1, 2) data point of the array.

Caveats. Make sure that you run `parmwrite` to create the input file.

```
%% ./allread
parameter value: 37
arbitrary data point [1,2]: 8.500000e+00
```

B.6 Scientific Libraries

applications,approximation,discrete,namd,performance,programming.tex

There are many libraries for scientific computing. Some are specialized to certain application areas, others are quite general. In this section we will take a brief look at the PETSc library for sparse matrix computations, and the BLAS/Lapack libraries for dense computations.

B.6.1 The Portable Extendable Toolkit for Scientific Computing

PETSc, the Portable Extendable Toolkit for Scientific Computation [], is a large powerful library, mostly concerned with linear and nonlinear system of equations that arise from discretized PDEs. Since it has many hundreds of routines (and a good manual already exists) we limit this tutorial to going through a few simple, yet representative, PETSc programs.

B.6.1.1 What is in PETSc?

PETSc can be used as a library in the traditional sense, where you use some high level functionality, such as solving a nonlinear system of equations, in your program. However, it can also be used as a toolbox, to compose your own numerical applications using low-level tools.

- Linear system solvers (sparse/dense, iterative/direct)
- Nonlinear system solvers
- Tools for distributed matrices
- Support for profiling, debugging, graphical output

The basic functionality of PETSc can be extended through external packages:

- Dense linear algebra: Scalapack, Plapack
- Grid partitioning software: ParMetis, Jostle, Chaco, Party
- ODE solvers: PVODE
- Eigenvalue solvers (including SVD): SLEPC
- Optimization: TAO

B.6.1.2 Design of PETSc

PETSc has an object-oriented design, even though it is implemented in C, a not object oriented language. PETSc is also parallel: all objects in Petsc are defined on an MPI communicator (section 2.5.3.3). For an object such as a matrix this means that it is stored distributed over the processors in the communicator; for objects such as solvers it means that their operation is distributed over the communicator. PETSc objects can only interact if they are based on the same communicator. Most of the time objects will be defined on the MPI_COMM_WORLD communicator, but subcommunicators can be used too. This way, you can define a matrix or a linear system on all your available processors, or on a subset.

Parallelism is handled through MPI. You may need to have occasional MPI calls in a PETSc code, but the vast bulk of communication is done behind the scenes inside PETSc calls. Shared memory parallel (such as through OpenMP; section 2.5.2) is not used explicitly, but the user can incorporate it without problems.

The object-oriented design means that a call such as matrix-vector multiplication

```
MATMult (A, x, y); // y <- A x
```

looks the same, regardless whether A is sparse or dense, sequential or parallel.

One implication of this is that the actual data are usually hidden from the user. Data can be accessed through routines such as

```
double *array;
VecGetArray (myvector, &array);
```

but most of the time the application does not explicitly maintain the data, only the PETSc objects containing the data. As the ultimate consequence of this, the user usually does not allocate data; rather, matrix and vector arrays get created through the PETSc create calls, and subsequent values are inserted through PETSc calls:

```
MatSetValue (A, i, j, v, INSERT_VALUES); // A[i, j] <- v
```

This may feel like the user is giving up control, but it actually makes programming a lot easier, since the user does not have to worry about details of storage schemes, especially in parallel.

B.6.1.3 Small examples

In this section we will go through a number of successively more complicated examples of the use of PETSc. The files can be downloaded from

<http://tinyurl.com/ISTC-petsc-tutorial>. While doing these examples it is a good idea to keep the manual page open:

<http://tinyurl.com/PETSc-man-page>. You can also download a manual in pdf form from <http://tinyurl.com/PETSc-pdf-manual>.

When you do these examples, make sure to use a version of PETSc that has debug mode enabled!

B.6.1.3.1 Program structure The first example (we only list C sources in this book; the download includes their Fortran equivalents) illustrates the basic structure of a PETSc program: the include file at the top and the calls to `PetscInitialize`, `PetscFinalize`. Further more it uses two routines:

- `PetscOptionsGetInt` is used to check if the program was invoked with a `-n` option and a numerical value: if you ran your program as `./init -n 45`, the variable `n` should have the value 45.
- `PetscPrintf` functions like the `printf` function, except that only one processor executes the print command. If you ran your program as `mpieexec -np 4 init` and you used `printf`, you would get four copies of the output.

`init.c`

Just about the only lines of MPI that you need to know when programming PETSc are:

```
C:  
ierr = MPI_Comm_size(comm, &ntids);  
ierr = MPI_Comm_rank(comm, &mytid);  
F:  
call MPI_Comm_size(comm, &ntids, ierr);  
call MPI_Comm_rank(comm, &mytid, ierr);
```

The first line gives the size of the communicator, meaning how many processes there are; the second one gives the rank of the current process as a number from zero to the number of processes minus one.

Exercise B.6.1. Add these two lines to your program. Look up the routine `PetscSynchronizedPrintf` in the documentation and use it to let each process print out a line like `Process 3 out of 7`. You may also need to use `PetscSynchronizedFlush`.

B.6.1.3.2 Vectors

Next we start making PETSc objects, first a vector.

vec.c Note how it takes several calls to fully create the vector object:

- The type `VECMPI` means that the vector will be distributed.
- The routine setting the size has two size parameters; the second specifies that the global size is `n`, and the first one says that you leave the distribution for PETSc to decide.

At the end of the program there is a `VecDestroy`, which deallocates the memory for the vector. While this is strictly speaking not necessary for the functioning of the program, it is a good idea to issue `Destroy` calls for each `Create` call, since it can prevent potential *memory leaks*.

Exercise B.6.2. Comment out the `VecDestroy` call, and run the program with the option `-malloc_dump`. PETSc will now report on all memory that had not been freed at the time of the `PetscFinalize` call.

If you run the program in parallel the vector will be created distributed over the processors. The program contains a call to `VecGetOwnershipRange` to discover what part of the vector lives on what processor. You see that the `VecView` calls display for each processor precisely that part of the vector.

Exercise B.6.3. The listing has a call to `VecSet` to set the vector elements to a constant value. Remove this line. Use the `myfirst`, `mylast` variables and the PETSc routine `VecSetValue` to let every process set its local vector elements to the processor number. (The last argument of `VecSetValue` should be `INSERT_VALUES`.) That is, if the vector is six elements long and there are three processors, the resulting vector should be $(0, 0, 1, 1, 2, 2)$.

Exercise B.6.4. Change the code from the previous exercise. Now every vector element should be the sum of the processor number and the previous processor numbers; in the above example the result should be $(0, 0, 1, 1, 3, 3)$. Read the man page for `VecSetValue`!

Run the code from the previous two exercises again, adding a commandline argument `-log_summary`. Observe that the first code has no messages in the `VecAssemblyBegin/End` calls, but the second one does.

B.6.1.3.3 Matrices Let's move up to matrices. Creating a matrix is similar to creating a vector. In this case the type is `MPIAIJ` which stands for a distributed sparse matrix.

mat.c In this example a diagonal matrix is constructed, with each processor setting only its locally stored elements.

Exercise B.6.5. In addition to setting the diagonal, also set the first subdiagonal and the first superdiagonal, that is, the elements $(i, i - 1)$ and $(i, i + 1)$. To set all three elements in a row with one call you can do this:

```
vm = 1.*mytid;
for (i=myfirst; i<mylast; i++) {
    PetscInt j[3]; PetscReal v[3];
    j[0] = i-1; j[1] = i; j[2] = i+1;
    v[0] = --vm-1; v[1] = 2*vm; v[2] = -vm+1;
    ierr = MatSetValues(A, 1, &i, 3, j, v, INSERT_VALUES); CHKERRQ(ierr);
}
```

However, this code is not entirely correct. Edit the program using this fragment and run it. Diagnose the problem and fix it.

B.6.1.3.4 Matrix-vector operations Next we will create a file `mul.c` based on `mat.c` and multiply the matrix and the vector. Make sure that the size declarations of the matrix and the vector are compatible. You also need a second vector to store the result of the multiplication. This is easiest done by

```
ierr = VecDuplicate(x, &y); CHKERRQ(ierr);
```

Exercise B.6.6. Look up the `MatMult` routine in the documentation and use it in your program.

Use `VecView` to inspect the result. Note that no size parameters or anything pertaining to parallelism appears in the calling sequence.

B.6.1.3.5 Solvers Copy your `mat.c` file to `sys.c`: we are going to explore linear system solving. First you need to create a solver object and give it the matrix as operator:

```
ierr = KSPCreate(comm, &solver); CHKERRQ(ierr);
ierr = KSPSetOperators(solver, A, A, 0); CHKERRQ(ierr);
ierr = KSPSolve(solver, x, y); CHKERRQ(ierr);
ierr = VecView(y, 0); CHKERRQ(ierr);
```

Exercise B.6.7. Add these lines to your code. Make sure you know what the correct solution is by using `MatMult` to obtain the right hand side.

You have just used the default linear system solver. Run the program again, but with the option `-ksp_view`. This will tell you all the details of what solver was used.

Solving the linear system is a one line call to `KSPSolve`. The story would end there if it weren't for some complications:

- Iterative methods can fail, and the solve call does not tell us whether that happened.
- If the system was solved successfully, we would like to know in how many iterations.
- There can be other reason for the iterative method to halt, such as reaching its maximum number of iterations without converging.

Exercise B.6.8. Use the routine `KSPGetConvergedReason` to inspect the status of the solution vector. Use `KSPGetIterationNumber` to see how many iterations it took.

Exercise B.6.9. Add code to your program to compute the residual and its norm. For the residual, look up the routines `VecDuplicate` and `VecAXPY`; for computing its norm look up `VecNorm`.

Exercise B.6.10. Add a call to `KSPSetFromOptions` to your code. Use the option `-ksp_monitor` to observe the convergence behaviour.

The workings of a PETSc program can be customized to a great degree through the use of commandline options. This includes setting the type of the solver. In order for such options to be obeyed, you first need to put a command `KSPSetFromOptions` before the `KSPSolve` call.

Exercise B.6.11. The `-ksp_view` option told you what solver and preconditioner were used. Look up the routines `KSPSetType` and `PCSetType` and use those to change the iterative method to CG and the preconditioner to Jacobi. Do this first by using commandline options, and then by editing the code.

B.6.1.4 A realistic program

This section will give you some further help towards solving a realistic PDE problem.

B.6.1.4.1 Construction of the coefficient matrix In the examples above you used a commandline argument to determine the matrix size directly. Here we construct the matrix of 5-point stencil for the Poisson operator (see section 4.2.2.2 and in particular figure 4.1). Determining its size takes two steps: you need to read the domain size $n = 1/h - 1$ and compute the matrix size from it.

C:

```
int domain_size,matrix_size;
PetscOptionsGetInt
    (PETSC_NULL,"-n",&domain_size,&flag);
matrix_size = domain_size*domain_size;
```

Fortran:

```
integer :: domain_size,matrix_size
call PetscOptionsGetInt(PETSC_NULL_CHARACTER,
>      "-n",domain_size,flag)
matrix_size = domain_size*domain_size;
```

Now you use the `matrix_size` parameter for constructing the matrix.

B.6.1.4.2 Filling in matrix elements Just like in the examples above, you want each processor to set only its local rows. The easiest way to iterate over those is to iterate over all variables / matrix rows and select only the local ones.

We will now set matrix elements (refer to the full domain, but only inserting those elements that are in its matrix block row).

C:

```
MatGetOwnershipRange(A, &myfirst, &mylast);
for ( i=0; i<domain_size; i++ ) {
    for ( j=0; j<domain_size; j++ ) {
        I = j + matrix_size*i;
        if (I>=myfirst && I<mylast) {
            J = I; // for the diagonal element
            MatSetValues
                (A, 1, &I, 1, &J, &v, INSERT_VALUES);
            J = .... // for the other points
            J = ....
        }
    }
}
MatAssemblyBegin(A, MAT_FINAL_ASSEMBLY);
MatAssemblyEnd(A, MAT_FINAL_ASSEMBLY);
```

Fortran:

```
call MatGetOwnershipRange(A, myfirst, mylast)
do i=0,matrix_size-1
    do j=0,domain_size-1
        ii = j + domain_size*i
        if (ii>=myfirst .and. ii<mylast) then
            jj = ii ; for the diagonal element
            call MatSetValues
                >          (A, 1, ii, 1, jj, v, INSERT_VALUES)
            jj = ii... ; for the other elements
            jj = ii...
        end if
    end do
end do
call MatAssemblyBegin(A, MAT_FINAL_ASSEMBLY)
call MatAssemblyEnd(A, MAT_FINAL_ASSEMBLY)
```

Exercise B.6.12. Construct the matrix from equation (4.14) in section 4.2.2.2. Compute and output the product with the identity vector (meaning that all elements are 1), and check that the result is correct. Make sure to test your program in parallel.

B.6.1.4.3 Finite Element Matrix assembly PETSc's versatility in dealing with Finite Element matrices (see sections 4.2.2.4 and 6.5.2), where elements are constructed by adding together contributions, sometimes from different processors. This is no problem in PETSc: any processor can set (or add to) any matrix element. The assembly calls will move data to their eventual location on the correct processors.

```

for (e=myfirstelement; e<mylastelement; e++) {
    for (i=0; i<nlocalnodes; i++) {
        I = localtoglobal(e,i);
        for (j=0; j<nlocalnodes; j++) {
            J = localtoglobal(e,j);
            v = integration(e,i,j);
            MatSetValues
                (mat, 1, &I, 1, &J, &v, ADD_VALUES);
            ....
        }
    }
}
MatAssemblyBegin (mat, MAT_FINAL_ASSEMBLY);
MatAssemblyEnd (mat, MAT_FINAL_ASSEMBLY);

```

B.6.1.4.4 Linear system solver We have covered the basics of setting up the solver and solving the system above.

As an illustration of the toolbox nature of PETSc, you can now use routines you have already seen to compute the residual and its norm.

Exercise B.6.13. Create a new vector z (use `VecDuplicate`) and store the product of A and the computed solution y (use `MatMult`) in it. If you solved the system accurately, z should now be equal to x . To see how close it is, use

```

PetscReal norm;
VecAXPY (z, -1, x);
VecNorm (z, NORM_2, &norm);

```

to subtract x from z and compute the norm of the result.

B.6.1.5 Quick experimentation

Reading a parameter from the commandline above is actually a special case of a general mechanism for influencing PETSc's workings through commandline options.

Here is an example of setting the iterative solver and preconditioner from the commandline:

```

yourprog -ksp_type gmres -ksp_gmres_restart 25
          -pc_type ilu -pc_factor_levels 3

```

In order for this to work, your code needs to call

```
KSPSetFromOptions(solver);
```

before the system solution. This mechanism is very powerful, and it obviates the need for much code recompilation.

B.6.2 Libraries for dense linear algebra: Lapack and Scalapack

Dense linear algebra, that is linear algebra on matrices that are stored as two-dimensional arrays (as opposed to sparse linear algebra; see section 5.4, as well as the tutorial on PETSc B.6) has been standardized for a considerable time. The basic operations are defined by the three levels of *Basic Linear Algebra Subprograms (BLAS)*:

- Level 1 defines vector operations that are characterized by a single loop [89].
- Level 2 defines matrix vector operations, both explicit such as the matrix-vector product, and implicit such as the solution of triangular systems [33].
- Level 3 defines matrix-matrix operations, most notably the matrix-matrix product [32].

The name ‘BLAS’ suggests a certain amount of generality, but the original authors were clear [89] that these subprograms only covered dense linear algebra. Attempts to standardize sparse operations have never met with equal success.

Based on these building blocks libraries have been built that tackle the more sophisticated problems such as solving linear systems, or computing eigenvalues or singular values. *Linpack*⁷ and *Eispack* were the first to formalize these operations involved, using Blas Level 1 and Blas Level 2 respectively. A later development, *Lapack* uses the blocked operations of Blas Level 3. As you saw in section 1.5.1, this is needed to get high performance on cache-based CPUs. (Note: the reference implementation of the BLAS [10] will not give good performance with any compiler; most platforms have vendor-optimized implementations, such as the *MKL* library from Intel.)

With the advent of parallel computers, several projects arose that extended the Lapack functionality to distributed computing, most notably *Scalapack* [19] and *PLapack* [126, 125]. These packages are considerably harder to use than Lapack⁸ because of the need for the two-dimensional block cyclic distribution; sections 6.2 and 6.3. We will not go into the details here.

B.6.2.1 BLAS matrix storage

There are a few points to bear in mind about the way matrices are stored in the BLAS and LAPACK⁹:

B.6.2.1.1 Array indexing Since these libraries originated in a Fortran environment, they use 1-based indexing. Users of languages such as C/C++ are only affected by this when routines use index arrays, such as the location of pivots in LU factorizations.

7. The linear system solver from this package later became the *Linpack benchmark*; see section 2.10.6.

8. PLapack is probably the easier to use of the two.

9. We are not going into band storage here.




Figure B.1: Column-major storage of an array in Fortran

B.6.2.1.2 Fortran column-major ordering Since computer memory is one-dimensional, some conversion is needed from two-dimensional matrix coordinates to memory locations. The *Fortran* language uses *column-major* storage, that is, elements in a column are stored consecutively; see figure B.1. This is also described informally as ‘the leftmost index varies quickest’.

B.6.2.1.3 Submatrices and the LDA parameter Using the storage scheme described above, it is clear how to store an $m \times n$ matrix in mn memory locations. However, there are many cases where software needs access to a matrix that is a subblock of another, larger, matrix. As you see in figure B.2 such a




Figure B.2: A subblock out of a larger matrix




Figure B.3: A subblock out of a larger matrix, using LDA

subblock is no longer contiguous in memory. The way to describe this is by introducing a third parameter in addition to M , N : we let LDA be the ‘leading dimension of A ’, that is, the allocated first dimension of the surrounding array. This is illustrated in figure B.3.

B.6.2.2 Organisation of routines

Lapack is organized with three levels of routines:

- Drivers. These are powerful top level routine for problems such as solving linear systems or computing an SVD. There are simple and expert drivers; the expert ones have more numerical sophistication.
- Computational routines. These are the routines that drivers are built up out of¹⁰. A user may have occasion to call them by themselves.
- Auxiliary routines.

Routines conform to a general naming scheme: XYYZZZ where

X precision: S, D, C, Z stand for single and double, single complex and double complex, respectively.

YY storage scheme: general rectangular, triangular, banded.

ZZZ operation. See the manual for a list.

Expert driver names end on ’X’.

B.6.2.2.1 Lapack data formats

Lapack and Blas use a number of data formats, including

GE General matrix: stored two-dimensionally as $A(LDA, *)$

SY/HE Symmetric/Hermitian: general storage; **UPLO** parameter to indicate upper or lower (e.g. **SPOTRF**)

10. Ha! Take that, Winston.

GB/SB/HB General/symmetric/Hermitian band; these formats use column-major storage; in SGBTRF over-allocation needed because of pivoting

PB Symmetric or Hermitian positive definite band; no overallocation in SPDTRF

B.6.2.2.2 Lapack operations

- Linear system solving. Simple drivers: -SV (e.g., DGESV) Solve $AX = B$, overwrite A with LU (with pivoting), overwrite B with X.
Expert driver: -SVX Also transpose solve, condition estimation, refinement, equilibration
- Least squares problems. Drivers:
 - xGELS using QR or LQ under full-rank assumption
 - xGELSY "complete orthogonal factorisation"
 - xGELSS using SVD
 - xGELSD using divide-conquer SVD (faster, but more workspace than xGELSS)Also: LSE & GLM linear equality constraint & general linear model
- Eigenvalue routines. Symmetric/Hermitian: xSY or xHE (also SP, SB, ST) simple driver -EV expert driver -EVX divide and conquer -EVD relative robust representation -EVR General (only xGE) Schur decomposition -ES and -ESX eigenvalues -EV and -EVX SVD (only xGE) simple driver -SVD divide and conquer SDD Generalized symmetric (SY and HE; SP, SB) simple driver GV expert GVX divide-conquer GVD Nonsymmetric Schur: simple GGES, expert GGESX eigen: simple GGEV, expert GGEVX svd: GGSVD

B.7 Plotting with GNUpot

applications,approximation,discrete,namd,performance,programming.tex
The *gnuplot* utility is a simple program for plotting sets of points or curves. This very short tutorial will show you some of the basics. For more commands and options, see the manual <http://www.gnuplot.info/docs/gnuplot.html>.

B.7.1 Usage modes

The two modes for running *gnuplot* are *interactive* and *from file*. In interactive mode, you call *gnuplot* from the command line, type commands, and watch output appear; you terminate an interactive session with *quit*. If you want to save the results of an interactive session, do *save "name.plt"*. This file can be edited, and loaded with *load "name.plt"*.

Plotting non-interactively, you call *gnuplot <your file>*.

The output of *gnuplot* can be a picture on your screen, or drawing instructions in a file. Where the output goes depends on the setting of the *terminal*. By default, *gnuplot* will try to draw a picture. This is equivalent to declaring

```
set terminal x11
```

or aqua, windows, or any choice of graphics hardware.

For output to file, declare

```
set terminal pdf
```

or fig, latex, pbm, et cetera. Note that this will only cause the pdf commands to be written to your screen: you need to direct them to file with

```
set output "myplot.pdf"
```

or capture them with

```
gnuplot my.plt > myplot.pdf
```

B.7.2 Plotting

The basic plot commands are *plot* for 2D, and *splot* ('surface plot') for 3D plotting.

B.7.2.1 Plotting curves

By specifying

```
plot x**2
```

you get a plot of $f(x) = x^2$; *gnuplot* will decide on the range for x . With

```
set xrange [0:1]
plot 1-x title "down", x**2 title "up"
```

you get two graphs in one plot, with the x range limited to $[0, 1]$, and the appropriate legends for the graphs. The variable x is the default for plotting functions.

Plotting one function against another – or equivalently, plotting a parametric curve – goes like this:

```
set parametric
plot [t=0:1.57] cos(t), sin(t)
```

which gives a quarter circle.

To get more than one graph in a plot, use the command `set multiplot`.

B.7.2.2 Plotting data points

It is also possible to plot curves based on data points. The basic syntax is `plot 'datafile'`, which takes two columns from the data file and interprets them as (x, y) coordinates. Since data files can often have multiple columns of data, the common syntax is `plot 'datafile' using 3:6` for columns 3 and 6. Further qualifiers like `with lines` indicate how points are to be connected.

Similarly, `splot "datafile3d.dat" 2:5:7` will interpret three columns as specifying (x, y, z) coordinates for a 3D plot.

If a data file is to be interpreted as level or height values on a rectangular grid, do `splot "matrix.dat" matrix` for data points; connect them with

```
split "matrix.dat" matrix with lines
```

B.7.2.3 Customization

Plots can be customized in many ways. Some of these customizations use the `set` command. For instance,

```
set xlabel "time"
set ylabel "output"
set title "Power curve"
```

You can also change the default drawing style with

```
set style function dots
```

(`dots`, `lines`, `dots,points`, *et cetera*), or change on a single plot with

```
plot f(x) with points
```

B.7.3 Workflow

Imagine that your code produces a dataset that you want to plot, and you run your code for a number of inputs. It would be nice if the plotting can be automated. Gnuplot itself does not have the facilities for this, but with a little help from shell programming this is not hard to do.

Suppose you have data files

```
data1.dat data2.dat data3.dat
```

and you want to plot them with the same gnuplot commands. You could make a file `plot.template`:

```
set term pdf
set output "FILENAME.pdf"
plot "FILENAME.dat"
```

The string `FILENAME` can be replaced by the actual file names using, for instance `sed`:

```
for d in data1 data2 data3 ; do
    cat plot.template | sed s/FILENAME/$d/ > plot.cmd
    gnuplot plot.cmd
done
```

Variations on this basic idea are many.

B.8 Good coding practices

Sooner or later, and probably sooner than later, every programmer is confronted with code not behaving as intended. In this section you will learn some techniques of dealing with this problem. At first we will see a number of techniques for *preventing* errors; after that we will discuss debugging, the process of finding the, inevitable, errors in a program once they have occurred.

B.8.1 Defensive programming

In this section we will discuss a number of techniques that are aimed at preventing the likelihood of programming errors, or increasing the likelihood of them being found at runtime. We call this *defensive programming*.

Scientific codes are often large and involved, so it is a good practice to code knowing that you are going to make mistakes and prepare for them. Another good coding practice is the use of tools: there is no point in reinventing the wheel if someone has already done it for you. Some of these tools are described in other sections:

- Build systems, such as Make, Scons, Bjam; see section [B.3](#).
- Source code management with SVN, Git; see section [B.4](#).
- Regression testing and designing with testing in mind (unit testing)

First we will have a look at runtime sanity checks, where you test for things that can not or should not happen.

Example 1: if a subprogram has an array argument, it is a good idea to test whether the actual argument is a null pointer.

Example 2: if you calculate a numerical result for which certain mathematical properties hold, for instance you are writing a sine function, for which the result has to be in $[-1, 1]$, you should test whether this property indeed holds for the result.

There are various ways to handle the case where the impossible happens.

B.8.1.1 The assert macro

The C standard library has a file `assert.h` which provides an `assert()` macro. Inserting `assert(foo)` has the following effect: if `foo` is zero (false), a diagnostic message is printed on standard error:

```
Assertion failed: foo, file filename, line line-number
```

which includes the literal text of the expression, the file name, and line number; and the program is subsequently aborted. Here is an example:

```
#include<assert.h>

void open_record(char *record_name)
{
    assert(record_name!=NULL);
```

```
    /* Rest of code */
}

int main(void)
{
    open_record(NULL);
}
```

The `assert` macro can be disabled by defining the `NDEBUG` macro.

B.8.1.1.1 An assert macro for Fortran (Thanks to Robert McLay for this code.)

```
#if (defined( GFORTRAN ) || defined( G95 ) || defined ( PGI) )
#define MKSTR(x) "x"
#else
#define MKSTR(x) #x
#endif
#ifndef NDEBUG
#define ASSERT(x, msg) if (.not. (x) ) \
    call assert( FILE , LINE ,MKSTR(x),msg)
#else
#define ASSERT(x, msg)
#endif
subroutine assert(file, ln, testStr, msgIn)
implicit none
character(*) :: file, testStr, msgIn
integer :: ln
print *, "Assert: ",trim(testStr)," Failed at ",trim(file),":",ln
print *, "Msg:", trim(msgIn)
stop
end subroutine assert
```

which is used as

```
ASSERT(nItemsSet.gt.arraySize,"Too many elements set")
```

B.8.1.2 Try-catch in C++

B.8.1.3 Use of error codes

In some software libraries (for instance MPI or PETSc) every subprogram returns a result, either the function value or a parameter, to indicate success or failure of the routine. It is good programming practice to check these error parameters, even if you think that nothing can possibly go wrong.

B. Practical tutorials

It is also a good idea to write your own subprograms in such a way that they always have an error parameter. Let us consider the case of a function that performs some numerical computation.

```
float compute(float val)
{
    float result;
    result = ... /* some computation */
    return result;
}

float value,result;
result = compute(value);
```

Looks good? What if the computation can fail, for instance:

```
result = ... sqrt(val) ... /* some computation */
```

How do we handle the case where the user passes a negative number?

```
float compute(float val)
{
    float result;
    if (val<0) { /* then what? */
    } else
        result = ... sqrt(val) ... /* some computation */
    return result;
}
```

We could print an error message and deliver some result, but the message may go unnoticed, and the calling environment does not really receive any notification that something has gone wrong.

The following approach is more flexible:

```
int compute(float val,float *result)
{
    float result;
    if (val<0) {
        return -1;
    } else {
        *result = ... sqrt(val) ... /* some computation */
    }
    return 0;
}

float value,result; int ierr;
ierr = compute(value,&result);
```

```
if (ierr!=0) { /* take appropriate action */
}
```

You can save yourself a lot of typing by writing

```
#define CHECK_FOR_ERROR(ierr) \
    if (ierr!=0) { \
        printf("Error %d detected\n", ierr); \
        return -1; \
    } \
    ... \
ierr = compute(value, &result); CHECK_FOR_ERROR(ierr);
```

Using some cpp macros you can even define

```
#define CHECK_FOR_ERROR(ierr) \
    if (ierr!=0) { \
        printf("Error %d detected in line %d of file %s\n", \
            ierr, __LINE__, __FILE__); \
        return -1; \
    }
```

Note that this macro not only prints an error message, but also does a further return. This means that, if you adopt this use of error codes systematically, you will get a full backtrace of the calling tree if an error occurs. (In the Python language this is precisely the wrong approach since the backtrace is built-in.)

B.8.2 Guarding against memory errors

In scientific computing it goes pretty much without saying that you will be working with large amounts of data. Some programming languages make managing data easy, others, one might say, make making errors with data easy.

The following are some examples of *memory violations*.

- Writing outside array bounds. If the address is outside the user memory, your code may abort with an error such as *segmentation violation*, and the error is reasonably easy to find. If the address is just outside an array, it will corrupt data but not crash the program; such an error may go undetected for a long time, as it can have no effect, or only introduce subtly wrong values in your computation.
- Reading outside array bounds can be harder to find than errors in writing, as it will often not abort your code, but only introduce wrong values.
- The use of uninitialized memory is similar to reading outside array bounds, and can go undetected for a long time. One variant of this is through attaching memory to an unallocated pointer. This particular kind of error can manifest itself in interesting behaviour. Let's say you notice that your program misbehaves, you recompile it with debug mode to find the error, and now the error no longer occurs. This is probably due to the effect that, with low optimization levels, all allocated arrays are filled with zeros. Therefore, your code was originally reading a random value, but is now getting a zero.

This section contains some techniques to prevent errors in dealing with memory that you have reserved for your data.

B.8.2.1 Array bound checking and other memory techniques

In parallel codes, memory errors will often show up by a crash in an MPI routine. This is hardly ever an MPI problem or a problem with your cluster.

Compilers for Fortran often have support for array bound checking. Since this makes your code much slower, you would only enable it during the development phase of your code.

B.8.2.2 Memory leaks

We say that a program has a *memory leak*, if it allocates memory, and subsequently loses track of that memory. The operating system then thinks the memory is in use, while it is not, and as a result the computer memory can get filled up with allocated memory that serves no useful purpose.

In this example data is allocated inside a lexical scope:

```
for (i=....) {
    real *block = malloc( /* large number of bytes */ )
    /* do something with that block of memory */
    /* and forget to call "free" on that block */
}
```

The block of memory is allocated in each iteration, but the allocation of one iteration is no longer available in the next. A similar example can be made with allocating inside a conditional.

It should be noted that this problem is far less serious in Fortran, where memory is deallocated automatically as a variable goes out of scope.

There are various tools for detecting memory errors: Valgrind, DMALLOC, Electric Fence. For valgrind, see section [B.9.3](#).

B.8.2.3 Roll-your-own malloc

Many programming errors arise from improper use of dynamically allocated memory: the program writes beyond the bounds, or writes to memory that has not been allocated yet, or has already been freed. While some compilers can do bound checking at runtime, this slows down your program. A better strategy is to write your own memory management. Some libraries such as PETSc already supply an enhanced malloc; if this is available you should certainly make use of it.

If you write in C, you will probably know the `malloc` and `free` calls:

```
int *ip;
ip = (int*) malloc(500*sizeof(int));
if (ip==0) {/* could not allocate memory */}
```

```
..... do stuff with ip .....
free(ip);
```

You can save yourself some typing by

```
#define MYMALLOC(a,b,c) \
    a = (c*)malloc(b*sizeof(c)); \
    if (a==0) /* error message and appropriate action */ \
        \
    int *ip;
    MYMALLOC(ip,500,int);
```

Runtime checks on memory usage (either by compiler-generated bounds checking, or through tools like valgrind or Rational Purify) are expensive, but you can catch many problems by adding some functionality to your malloc. What we will do here is to detect memory corruption after the fact.

We allocate a few integers to the left and right of the allocated object (line 1 in the code below), and put a recognizable value in them (line 2 and 3), as well as the size of the object (line 2). We then return the pointer to the actually requested memory area (line 4).

```
#define MEMCOOKIE 137
#define MYMALLOC(a,b,c) { \
    char *aa; int *ii; \
    aa = malloc(b*sizeof(c)+3*sizeof(int)); /* 1 */ \
    ii = (int*)aa; ii[0] = b*sizeof(c); \
    ii[1] = MEMCOOKIE; /* 2 */ \
    aa = (char*)(ii+2); a = (c*)aa; /* 4 */ \
    aa = aa+b*sizeof(c); ii = (int*)aa; \
    ii[0] = MEMCOOKIE; /* 3 */ \
}
```

Now you can write your own `free`, which tests whether the bounds of the object have not been written over.

```
#define MYFREE(a) { \
    char *aa; int *ii;, ii = (int*)a; \
    if (*(--ii)!=MEMCOOKIE) printf("object corrupted\n"); \
    n = *(--ii); aa = a+n; ii = (int*)aa; \
    if (*ii!=MEMCOOKIE) printf("object corrupted\n"); \
}
```

You can extend this idea: in every allocated object, also store two pointers, so that the allocated memory areas become a doubly linked list. You can then write a macro `CHECKMEMORY` which tests all your allocated objects for corruption.

Such solutions to the memory corruption problem are fairly easy to write, and they carry little overhead. There is a memory overhead of at most 5 integers per object, and there is practically no performance penalty.

(Instead of writing a wrapper for `malloc`, on some systems you can influence the behaviour of the system routine. On linux, `malloc` calls hooks that can be replaced with your own routines; see http://www.gnu.org/s/libc/manual/html_node/Hooks-for-Malloc.html.)

B.8.2.4 Specific techniques: Fortran

Use `Implicit none`.

Put all subprograms in modules so that the compiler can check for missing arguments and type mismatches. It also allows for automatic dependency building with `fdepend`.

Use the C preprocessor for conditional compilation and such.

B.8.3 Testing

There are various philosophies for testing the correctness of a code.

- Correctness proving: the programmer draws up predicates that describe the intended behaviour of code fragments and proves by mathematical techniques that these predicates hold [72, 29].
- Unit testing: each routine is tested separately for correctness. This approach is often hard to do for numerical codes, since with floating point numbers there is essentially an infinity of possible inputs, and it is not easy to decide what would constitute a sufficient set of inputs.
- Integration testing: test subsystems
- System testing: test the whole code. This is often appropriate for numerical codes, since we often have model problems with known solutions, or there are properties such as bounds that need to hold on the global solution.
- Test-driven design: the program development process is driven by the requirement that testing is possible at all times.

With parallel codes we run into a new category of difficulties with testing. Many algorithms, when executed in parallel, will execute operations in a slightly different order, leading to different roundoff behaviour. For instance, the parallel computation of a vector sum will use partial sums. Some algorithms have an inherent damping of numerical errors, for instance stationary iterative methods (section 5.5.1), but others have no such built-in error correction (nonstationary methods; section 5.5.7). As a result, the same iterative process can take different numbers of iterations depending on how many processors are used.

B.8.3.1 Test-driven design and development

In test-driven design there is a strong emphasis on the code always being testable. The basic ideas are as follows.

- Both the whole code and its parts should always be testable.
- When extending the code, make only the smallest change that allows for testing.
- With every change, test before and after.
- Assure correctness before adding new features.

B.9 Debugging

When a program misbehaves, *debugging* is the process of finding out *why*. There are various strategies of finding errors in a program. The crudest one is debugging by print statements. If you have a notion of where in your code the error arises, you can edit your code to insert print statements, recompile, rerun, and see if the output gives you any suggestions. There are several problems with this:

- The edit/compile/run cycle is time consuming, especially since
- often the error will be caused by an earlier section of code, requiring you to edit, compile, and rerun repeatedly. Furthermore,
- the amount of data produced by your program can be too large to display and inspect effectively, and
- if your program is parallel, you probably need to print out data from all processors, making the inspection process very tedious.

For these reasons, the best way to debug is by the use of an interactive *debugger*, a program that allows you to monitor and control the behaviour of a running program. In this section you will familiarize yourself with *gdb*, which is the open source debugger of the *GNU* project. Other debuggers are proprietary, and typically come with a compiler suite. Another distinction is that *gdb* is a commandline debugger; there are graphical debuggers such as *ddd* (a frontend to *gdb*) or *DDT* and *TotalView* (debuggers for parallel codes). We limit ourselves to *gdb*, since it incorporates the basic concepts common to all debuggers.

In this tutorial you will debug a number of simple programs with *gdb* and *valgrind*. The files can be downloaded from <http://tinyurl.com/ISTC-debug-tutorial>.

B.9.1 Invoking *gdb*

There are three ways of using *gdb*: using it to start a program, attaching it to an already running program, or using it to inspect a *core dump*. We will only consider the first possibility.

Here is an example of how to start *gdb* with program that has no arguments (Fortran users, use *hello.F*):

tutorials-public/gdb/c/hello.c

```
%% cc -g -o hello hello.c
# regular invocation:
%% ./hello
hello world
# invocation from gdb:
%% gdb hello
GNU gdb 6.3.50-20050815 # ..... version info
Copyright 2004 Free Software Foundation, Inc. .... copyright info ....
(gdb) run
Starting program: /home/eijkhout/tutorials-public/gdb/hello
Reading symbols for shared libraries +. done
hello world

Program exited normally.
```

B. Practical tutorials

```
(gdb) quit  
%%
```

Important note: the program was compiled with the *debug flag* `-g`. This causes the *symbol table* (that is, the translation from machine address to program variables) and other debug information to be included in the binary. This will make your binary larger than strictly necessary, but it will also make it slower, for instance because the compiler will not perform certain optimizations¹¹.

To illustrate the presence of the symbol table do

```
%% cc -g -o hello hello.c  
%% gdb hello  
GNU gdb 6.3.50-20050815 # ..... version info  
(gdb) list
```

and compare it with leaving out the `-g` flag:

```
%% cc -o hello hello.c  
%% gdb hello  
GNU gdb 6.3.50-20050815 # ..... version info  
(gdb) list
```

For a program with commandline input we give the arguments to the `run` command (Fortran users use `say.F`):

tutorials-public/gdb/c/say.c

```
%% cc -o say -g say.c  
%% ./say 2  
hello world  
hello world  
%% gdb say  
.... the usual messages ...  
(gdb) run 2  
Starting program: /home/eijkhout/tutorials-public/gdb/c/say 2  
Reading symbols for shared libraries +. done  
hello world  
hello world  
  
Program exited normally.
```

11. Compiler optimizations are not supposed to change the semantics of a program, but sometimes do. This can lead to the nightmare scenario where a program crashes or gives incorrect results, but magically works correctly with compiled with debug and run in a debugger.

B.9.2 Finding errors

Let us now consider some programs with errors.

B.9.2.1 C programs

tutorials-public/gdb/c/square.c

```
%% cc -g -o square square.c
%% ./square
5000
Segmentation fault
```

The *segmentation fault* (other messages are possible too) indicates that we are accessing memory that we are not allowed to, making the program abort. A debugger will quickly tell us where this happens:

```
%% gdb square
(gdb) run
50000

Program received signal EXC_BAD_ACCESS, Could not access memory.
Reason: KERN_INVALID_ADDRESS at address: 0x000000000000eb4a
0x00007fff824295ca in __svfscanf_l ()
```

Apparently the error occurred in a function `__svfscanf_l`, which is not one of ours, but a system function. Using the backtrace (or bt, also where or w) command we quickly find out how this came to be called:

```
(gdb) backtrace
#0 0x00007fff824295ca in __svfscanf_l ()
#1 0x00007fff8244011b in fscanf ()
#2 0x0000000100000e89 in main (argc=1, argv=0x7fff5fbfc7c0) at square.c:7
```

We take a close look at line 7, and see that we need to change `nmax` to `&nmax`.

There is still an error in our program:

```
(gdb) run
50000

Program received signal EXC_BAD_ACCESS, Could not access memory.
Reason: KERN_PROTECTION_FAILURE at address: 0x000000010000f000
0x0000000100000ebe in main (argc=2, argv=0x7fff5fbfc7a8) at square1.c:9
9           squares[i] = 1. / (i * i); sum += squares[i];
```

We investigate further:

B. Practical tutorials

```
(gdb) print i  
$1 = 11237  
(gdb) print squares[i]  
Cannot access memory at address 0x10000f000
```

and we quickly see that we forgot to allocate `squares`.

By the way, we were lucky here: this sort of memory errors is not always detected. Starting our programm with a smaller input does not lead to an error:

```
(gdb) run  
50  
Sum: 1.625133e+00  
  
Program exited normally.
```

B.9.2.2 Fortran programs

Compile and run the following program:

`tutorials-public/gdb/f/square.F` It should abort with a message such as ‘Illegal instruction’. Running the program in `gdb` quickly tells you where the problem lies:

```
(gdb) run  
Starting program: tutorials-public/gdb//fsquare  
Reading symbols for shared libraries ++++. done  
  
Program received signal EXC_BAD_INSTRUCTION, Illegal instruction/operand.  
0x0000000100000da3 in square () at square.F:7  
7 sum = sum + squares(i)
```

We take a close look at the code and see that we did not allocate `squares` properly.

B.9.3 Memory debugging with Valgrind

Insert the following allocation of `squares` in your program:

```
squares = (float *) malloc( nmax*sizeof(float) );
```

Compile and run your program. The output will likely be correct, although the program is not. Can you see the problem?

To find such subtle memory errors you need a different tool: a memory debugging tool. A popular (because open source) one is *valgrind*; a common commercial tool is *purify*.

`tutorials-public/gdb/c/square1.c` Compile this program with `cc -o square1 square1.c` and run it with `valgrind square1` (you need to type the input value). You will lots of output, starting with:

```

%% valgrind square1
==53695== Memcheck, a memory error detector
==53695== Copyright (C) 2002-2010, and GNU GPL'd, by Julian Seward et al.
==53695== Using Valgrind-3.6.1 and LibVEX; rerun with -h for copyright info
==53695== Command: a.out
==53695==
10
==53695== Invalid write of size 4
==53695==   at 0x100000EB0: main (square1.c:10)
==53695==     Address 0x10027e148 is 0 bytes after a block of size 40 alloc'd
==53695==       at 0x1000101EF: malloc (vg_replace_malloc.c:236)
==53695==     by 0x100000E77: main (square1.c:8)
==53695==
==53695== Invalid read of size 4
==53695==   at 0x100000EC1: main (square1.c:11)
==53695==     Address 0x10027e148 is 0 bytes after a block of size 40 alloc'd
==53695==       at 0x1000101EF: malloc (vg_replace_malloc.c:236)
==53695==     by 0x100000E77: main (square1.c:8)

```

Valgrind is informative but cryptic, since it works on the bare memory, not on variables. Thus, these error messages take some exegesis. They state that a line 10 writes a 4-byte object immediately after a block of 40 bytes that was allocated. In other words: the code is writing outside the bounds of an allocated array. Do you see what the problem in the code is?

Note that valgrind also reports at the end of the program run how much memory is still in use, meaning not properly freed.

If you fix the array bounds and recompile and rerun the program, valgrind still complains:

```

==53785== Conditional jump or move depends on uninitialised value(s)
==53785==   at 0x10006FC68: __ dtoa (in /usr/lib/libSystem.B.dylib)
==53785==   by 0x10003199F: __ vfprintf (in /usr/lib/libSystem.B.dylib)
==53785==     by 0x1000738AA: vfprintf_l (in /usr/lib/libSystem.B.dylib)
==53785==     by 0x1000A1006: printf (in /usr/lib/libSystem.B.dylib)
==53785==     by 0x100000EF3: main (in ./square2)

```

Although no line number is given, the mention of `printf` gives an indication where the problem lies. The reference to an ‘uninitialized value’ is again cryptic: the only value being output is `sum`, and that is not uninitialized: it has been added to several times. Do you see why valgrind calls `is uninitialized` all the same?

B.9.4 Stepping through a program

Often the error in a program is sufficiently obscure that you need to investigate the program run in detail. Compile the following program

tutorials-public/gdb/c/roots.c	and run it:
--------------------------------	-------------

```
%% ./roots
```

B. Practical tutorials

```
sum: nan
```

Start it in gdb as follows:

```
%% gdb roots
GNU gdb 6.3.50-20050815 (Apple version gdb-1469) (Wed May 5 04:36:56 UTC 2005)
Copyright 2004 Free Software Foundation, Inc.

...
(gdb) break main
Breakpoint 1 at 0x100000ea6: file root.c, line 14.
(gdb) run
Starting program: tutorials-public/gdb/c/roots
Reading symbols for shared libraries +. done

Breakpoint 1, main () at roots.c:14
14      float x=0;
```

Here you have done the following:

- Before calling `run` you set a *breakpoint* at the main program, meaning that the execution will stop when it reaches the main program.
- You then call `run` and the program execution starts;
- The execution stops at the first instruction in `main`.

If execution is stopped at a breakpoint, you can do various things, such as issuing the `step` command:

```
Breakpoint 1, main () at roots.c:14
14      float x=0;
(gdb) step
15      for (i=100; i>-100; i--)
(gdb)
16      x += root(i);
(gdb)
```

(if you just hit return, the previously issued command is repeated). Do a number of `steps` in a row by hitting return. What do you notice about the function and the loop?

Switch from doing `step` to doing `next`. Now what do you notice about the loop and the function?

Set another breakpoint: `break 17` and do `cont`. What happens?

Rerun the program after you set a breakpoint on the line with the `sqrt` call. When the execution stops there do `where` and `list`.

- If you set many breakpoints, you can find out what they are with `info breakpoints`.
- You can remove breakpoints with `delete n` where `n` is the number of the breakpoint.
- If you restart your program with `run` without leaving `gdb`, the breakpoints stay in effect.
- If you leave `gdb`, the breakpoints are cleared but you can save them: `save breakpoints <file>`. Use `source <file>` to read them in on the next `gdb` run.

B.9.5 Inspecting values

Run the previous program again in gdb: set a breakpoint at the line that does the `sqrt` call before you actually call `run`. When the program gets to line 8 you can do `print n`. Do `cont`. Where does the program stop?

If you want to repair a variable, you can do `set var=value`. Change the variable `n` and confirm that the square root of the new value is computed. Which commands do you do?

If a problem occurs in a loop, it can be tedious keep typing `cont` and inspecting the variable with `print`. Instead you can add a condition to an existing breakpoint: the following:

```
condition 1 if (n<0)
```

or set the condition when you define the breakpoint:

```
break 8 if (n<0)
```

Another possibility is to use `ignore 1 50`, which will not stop at breakpoint 1 the next 50 times.

Remove the existing breakpoint, redefine it with the condition `n<0` and rerun your program. When the program breaks, find for what value of the loop variable it happened. What is the sequence of commands you use?

B.9.6 Further reading

A good tutorial: <http://www.dirac.org/linux/gdb/>.

Reference manual: http://www.ofb.net-gnu/gdb/gdb_toc.html.

B.10 Performance measurement

Much of the teaching in this book is geared towards enabling you to write fast code, whether this is through the choice of the right method, or through optimal coding of a method. Consequently, you sometimes want to measure just *how fast* your code is. If you have a simulation that runs for many hours, you'd think just looking on the clock would be enough measurement. However, as you wonder whether your code could be faster than it is, you need more detailed measurements. This tutorial will teach you some ways to measure the behaviour of your code in more or less detail.

Here we will discuss

- timers: ways of measuring the execution time (and sometimes other measurements) of a particular piece of code, and
- profiling tools: ways of measuring how much time each piece of code, typically a subroutine, takes during a specific run.

B.10.1 Timers

There are various ways of timing your code, but mostly they come down to calling a routine twice that tells you the clock values:

```
tstart = clockticks()  
....  
tend = clockticks()  
runtime = (tend-tstart)/ticks_per_sec
```

For instance, in Fortran there is the `system_clock` routine: with output

```
Clock frequency: 10000  
1.000000 813802544 813826097 2.000000
```

In C there is the `clock` function: with output

```
clock resolution: 1000000  
res: 1.000000e+00  
start/stop: 0.000000e+00, 2.310000e+00  
Time: 2.310000e+00
```

Do you see a difference between the Fortran and C approaches? Hint: what happens in both cases when the execution time becomes long? At what point do you run into trouble?

B.10.1.1 System utilities

There are unix system calls that can be used for timing: `getrusage` and `gettimeofday`. These timers have the advantage that they can distinguish between user time and system time, that is, exclusively timing program execution or giving *wallclock time* including all system activities.

B.10.2 Accurate counters

The timers in the previous section had a resolution of at best a millisecond, which corresponds to several thousand cycles on a modern CPU. For more accurate counting it is typically necessary to use assembly language, such as the Intel RDTSC (ReaD Time Stamp Counter) instruction <http://developer.intel.com/drg/pentiumII/appnotes/RDTSCPM1.HTM>. However, this approach of using processor-specific timers is not portable. For this reason, the PAPI package (<http://icl.cs.utk.edu/papi/>) provides a uniform interface to timers and other performance counters. You can see this package in action in the codes in appendix D.

B.10.3 Profiling tools

Profiling tools will give you the time spent in various events in the program, typically functions and subroutines, or parts of the code that you have declared as such. The tool will then report how many time the event occurred, total and average time spent, et cetera.

The only tool we mention here is *gprof*, the profiler of the *GNU* compiler. There are other tools, such as *TAU*, which have great sophistication, but go beyond this tutorial. Finally, we mention that the *PETSc* library allows you to define your own timers and events.

```
% gcc -g -pg ./srcFile.  
% gprof ./exeFile gmon.out > profile.txt  
% gprof -l ./exeFile gmon.out > profile_line.txt  
% gprof -A ./exeFile gmon.out > profile_annotated.tx
```

B.10.3.1 MPI profiling

The MPI library has been designed to make it easy to profile. Each function such as `MPI_Send` does no more than calling `PMPI_Send`. This means that a profiling library can redefine `MPI_Send` to

- initialize a profiling stage,
- call `PMPI_Send`,
- finish the profiling stage.

B.10.4 Tracing

In profiling we are only concerned with aggregate information: how many times a routine was called, and with what total/average/min/max runtime. However sometimes we want to know about the exact timing of events. This is especially relevant in a parallel context when we care about *load unbalance* and *idle time*.

Tools such as Vampyr can collect trace information about events and in particular messages, and render them in displays such as figure B.4.



Figure B.4: A Vampyr timeline diagram of a parallel process.

B.11 C/Fortran interoperability

applications,approximation,discrete,namd,performance,programming.tex
Most of the time, a program is written in a single language, but in some circumstances it is necessary or desirable to mix sources in more than one language for a single executable. One such case is when a library is written in one language, but used by a program in another. In such a case, the library writer will probably have made it easy for you to use the library; this section is for the case that you find yourself in the place of the library writer. We will focus on the common case of interfacing between C/C++ and Fortran.

B.11.1 Arrays

C and Fortran have different conventions for storing multi-dimensional arrays. You need to be aware of this when you pass an array between routines written in different languages.

Fortran stores multi-dimensional arrays in *column-major* order. For two dimensional arrays ($A(i, j)$) this means that the elements in each column are stored contiguously: a 2×2 array is stored as $A(1, 1)$, $A(2, 1)$, $A(1, 2)$, $A(2, 2)$. Three and higher dimensional arrays are an obvious extension: it is sometimes said that ‘the left index varies quickest’.

C arrays are stored in *row-major* order: elements in each row are stored contiguous, and columns are then placed sequentially in memory. A 2×2 array $A[2][2]$ is then stored as $A[1][1]$, $A[1][2]$, $A[2][1]$, $A[2][2]$.

A number of remarks about arrays in C.

- C (before the C99 standard) has multi-dimensional arrays only in a limited sense. You can declare them, but if you pass them to another C function, they no longer look multi-dimensional: they have become plain `float*` (or whatever type) arrays. That brings us to the next point.

- Multi-dimensional arrays in C look as if they have type `float**`, that is, an array of pointers that point to (separately allocated) arrays for the rows. While you could certainly implement this:

```
float **A;
A = (float**)malloc(m*sizeof(float*));
for (i=0; i<n; i++)
    A[i] = (float*)malloc(n*sizeof(float));
```

careful reading of the standard reveals that a multi-dimensional array is in fact a single block of memory, no further pointers involved.

Given the above limitation on passing multi-dimensional arrays, and the fact that a C routine can not tell whether it's called from Fortran or C, it is best not to bother with multi-dimensional arrays in C, and to emulate them:

```
float *A;
A = (float*)malloc(m*n*sizeof(float));
#define SUB(i,j,m,n) i+j*m
for (i=0; i<m; i++)
    for (j=0; j<n; j++)
        .... A[SUB(i,j,m,n)] ....
```

where for interoperability we store the elements in column-major fashion.

B.11.2 Strings

Programming languages differ widely in how they handle strings.

- In C, a string is an array of characters; the end of the string is indicated by a null character, that is the ascii character zero, which has an all zero bit pattern. This is called *null termination*.
- In Fortran, a string is an array of characters. The length is maintained in a internal variable, which is passed as a hidden parameter to subroutines.
- In Pascal, a string is an array with an integer denoting the length in the first position. Since only one byte is used for this, strings can not be longer than 255 characters in Pascal.

As you can see, passing strings between different languages is fraught with peril. This situation is made even worse by the fact that passing strings as subroutine arguments is not standard.

Unless you are writing a text processor, it is therefore best not to use strings in your program. The next best solution is to use null-terminated strings throughout; some compilers support extensions to facilitate this, for instance writing

```
DATA forstring /'This is a null-terminated string.'C/
```

Recently, the ‘C/Fortran interoperability standard’ has provided a systematic solution to this.

B.11.3 Subprogram arguments

In C, you pass a `float` argument to a function if the function needs its value, and `float*` if the function has to modify the value of the variable in the calling environment. Fortran has no such distinction: every

variable is passed *by reference*. This has some strange consequences: if you pass a literal value (37.5) to a subroutine, the compiler will allocate a nameless variable with that value, and pass the address of it, rather than the value¹².

For interfacing Fortran and C routines, this means that a Fortran routine looks to a C program like all its argument are ‘star’ arguments. Conversely, if you want a C subprogram to be callable from Fortran, all its arguments have to be star-this or that. This means on the one hand that you will sometimes pass a variable by reference that you would like to pass by value.

Worse, it means that C subprograms like

```
void mysub(int **iarray) {
    *iarray = (int*)malloc(8*sizeof(int));
    return;
}
```

can not be called from Fortran. There is a hack to get around this (check out the Fortran77 interface to the Petsc routine `VecGetValues`) and with more cleverness you can use `POINTER` variables for this.

B.11.4 Linker conventions

As explained above, a compiler turns a source file into a binary, which no longer has any trace of the source language: it contains in effect functions in machine language. The linker will then match up calls and definitions, which can be in different files. The problem with using multiple languages is then that compilers have different notions of how to translate function names from the source file to the binary file.

The most common case of language interoperability is between C and Fortran. The problems are platform dependent, but commonly

- The Fortran compiler attaches a trailing underscore to function names in the object file.
- The C compiler takes the function name as it is in the source.

Since C is a popular language to write libraries in, this means we can solve the problem by either

- Appending an underscore to all C function names; or
- Include a simple wrapper call:

```
int SomeCFunction(int i, float f)
{
    .....
}
int SomeCFunction_(int i, float f)
{
    return SomeCFunction(i, f);
}
```

With the latest Fortran standard it is possible to declare the external name of variables and routines:

12. With a bit of cleverness and the right compiler, you can have a program that says `print *, 7` and prints 8 because of this.

```

%% cat t.f
module operator
  real, bind(C) :: x
contains
  subroutine s(), bind(C, name='_s')
    return
  end subroutine
  ...
end module
%% ifort -c t.f
%% nm t.o
.... T _s
.... C _x

```

It is also possible to declare data types to be C-compatible:

```

type, bind(C) :: c_comp
  real (c_float) :: data
  integer (c_int) :: i
  type (c_ptr) :: ptr
end type

```

B.11.5 Input/output

Both languages have their own system for handling input/output, and it is not really possible to meet in the middle. Basically, if Fortran routines do I/O, the main program has to be in Fortran. Consequently, it is best to isolate I/O as much as possible, and use C for I/O in mixed language programming.

B.11.6 Fortran/C interoperability in Fortran2003

The latest version of Fortran, unsupported by many compilers at this time, has mechanisms for interfacing to C.

- There is a module that contains named kinds, so that one can declare


```
INTEGER, KIND (C_SHORT) :: i
```
- Fortran pointers are more complicated objects, so passing them to C is hard; Fortran2003 has a mechanism to deal with C pointers, which are just addresses.
- Fortran derived types can be made compatible with C structures.

B.12 L^AT_EX for scientific documentation

B.12.1 The idea behind L^AT_EX, some history

T_EX is a typesetting system that dates back to the late 1970s. In those days, graphics terminals were you could design a document layout and immediately view it, the way you can with Microsoft Word, were rare. Instead, T_EX uses a two-step workflow, where you first type in your document with formatting instructions in an ascii document, using your favourite text editor. Next, you would invoke the `latex` program, as a sort of compiler, to translate this document to a form that can be printed or viewed.

```
%% edit mydocument.tex  
%% latex mydocument  
%% # print or view the resulting output
```

The process is comparable to making web pages by typing HTML commands.

This way of working may seem clumsy, but it has some advantages. For instance, the T_EX input files are plain ascii, so they can easily be generated automatically, for instance from a database. Also, you can edit them with whatever your favourite editor happens to be.

Another point in favour of T_EX is the fact that the layout is specified by commands that are written in a sort of programming language. This has some important consequences:

- Separation of concerns: when you are writing your document, you do not have to think about layout. You give the ‘chapter’ command, and the implementation of that command will be decided independently, for instance by you choosing a document style.
- Changing the layout of a finished document is easily done by choosing a different realization of the layout commands in the input file: the same ‘chapter’ command is used, but by choosing a different style the resulting layout is different. This sort of change can be as simple as a one-line change to the document style declaration.
- If you have unusual typesetting needs, it is possible to write new T_EX commands for this. For many needs such extensions have in fact already been written; see section B.12.4.

The commands in T_EX are fairly low level. For this reason, a number of people have written systems on top of T_EX that offer powerful features, such as automatic cross-referencing, or generation of a table of contents. The most popular of these systems is L^AT_EX. Since T_EX is an interpreted system, all of its mechanisms are still available to the user, even though L^AT_EX is loaded on top of it.

B.12.1.1 Installing L^AT_EX

The easiest way to install L^AT_EX on your system is by downloading the T_EXlive distribution from <http://tug.org/texlive>. Apple users can also use fink or macports. Various front-ends to T_EX exist, such as T_EXshop on the Mac.

B.12.1.2 Running L^AT_EX

Purpose. In this section you will run the L^AT_EX compiler

Originally, the `latex` compiler would output a device independent file format, named `dvi`, which could then be translated to PostScript or PDF, or directly printed. These days, many people use the `pdflatex` program which directly translates `.tex` files to `.pdf` files. This has the big advantage that the generated PDF files have automatic cross linking and a side panel with table of contents. An illustration is found below.

Let us do a simple example.

```
\documentclass{article}
\begin{document}
Hello world!
\end{document}
```

Figure B.5: A minimal L^AT_EX document

Exercise. Create a text file `minimal.tex` with the content as in figure B.5. Try the command `pdflatex minimal` or `latex minimal`. Did you get a file `minimal.pdf` in the first case or `minimal.dvi` in the second case? Use a pdf viewer, such as Adobe Reader, or `dvips` respectively to view the output.

Caveats. If you make a typo, T_EX can be somewhat unfriendly. If you get an error message and T_EX is asking for input, typing `x` usually gets you out, or `Ctrl-C`. Some systems allow you to type `e` to go directly into the editor to correct the typo.

B.12.2 A gentle introduction to L^AT_EX

Here you will get a very brief run-through of L^AT_EX features. There are various more in-depth tutorials available, such as the one by Oetiker [101].

B.12.2.1 Document structure

Each L^AT_EX document needs the following lines:

```
\documentclass{ ... } % the dots will be replaced
\begin{document}
\end{document}
```

The ‘`documentclass`’ line needs a class name in between the braces; typical values are ‘`article`’ or ‘`book`’. Some organizations have their own styles, for instance ‘`ieeeproc`’ is for proceedings of the IEEE.

All document text goes between the `\begin{document}` and `\end{document}` lines. (Matched ‘`begin`’ and ‘`end`’ lines are said to denote an ‘environment’, in this case the document environment.)

The part before `\begin{document}` is called the ‘preamble’. It contains customizations for this particular document. For instance, a command to make the whole document double spaced would go in the preamble. If you are using `pdflatex` to format your document, you want a line

```
\usepackage{hyperref}
```

here.

Have you noticed the following?

- The backslash character is special: it starts a `LATEX` command.
- The braces are also special: they have various functions, such as indicating the argument of a command.
- The percent character indicates that everything to the end of the line is a comment.

B.12.2.2 Some simple text

Purpose. In this section you will learn some basics of text formatting.

Exercise. Create a file `first.tex` with the content of figure B.5 in it. Type some text in the preamble, that is, before the `\begin{document}` line and run `pdflatex` on your file.

Expected outcome. You should get an error message because you are not allowed to have text in the preamble. Only commands are allowed there; all text has to go after `\begin{document}`.

Exercise. Edit your document: put some text in between the `\begin{document}` and `\end{document}` lines. Let your text have both some long lines that go on for a while, and some short ones. Put superfluous spaces between words, and at the beginning or end of lines. Run `pdflatex` on your document and view the output.

Expected outcome. You notice that the white space in your input has been collapsed in the output. `TeX` has its own notions about what space should look like, and you do not have to concern yourself with this matter.

Exercise. Edit your document again, cutting and pasting the paragraph, but leaving a blank line between the two copies. Paste it a third time, leaving several blank lines. Format, and view the output.

Expected outcome. `TeX` interprets one or more blank lines as the separation between paragraphs.

Exercise. Add `\usepackage{pslatae}` to the preamble and rerun `pdflatex` on your document. What changed in the output?

Expected outcome. This should have the effect of changing the typeface from the default to Times Roman.

Caveats. Typefaces are notoriously unstandardized. Attempts to use different typefaces may or may not work. Little can be said about this in general.

Add the following line before the first paragraph:

```
\section{This is a section}
```

and a similar line before the second. Format. You see that L^AT_EX automatically numbers the sections, and that it handles indentation different for the first paragraph after a heading.

Exercise. Replace `article` by `artikel3` in the documentclass declaration line and reformat your document. What changed?

Expected outcome. There are many documentclasses that implement the same commands as `article` (or another standard style), but that have their own layout. Your document should format without any problem, but get a better looking layout.

Caveats. The `artikel3` class is part of most distributions these days, but you can get an error message about an unknown documentclass if it is missing or if your environment is not set up correctly. This depends on your installation. If the file seems missing, download the files from <http://tug.org/texmf-dist/tex/latex/ntgclass/> and put them in your current directory; see also section B.12.2.8.

B.12.2.3 Math

Purpose. In this section you will learn the basics of math typesetting

One of the goals of the original T_EX system was to facilitate the setting of mathematics. There are two ways to have math in your document:

- Inline math is part of a paragraph, and is delimited by dollar signs.
- Display math is, as the name implies, displayed by itself.

Exercise. Put $x+y$ somewhere in a paragraph and format your document. Put $\begin{array}{c} x+y \\ \end{array}$ somewhere in a paragraph and format.

Expected outcome. Formulas between single dollars are included in the paragraph where you declare them. Formulas between $\begin{array}{c} \dots \\ \end{array}$ are typeset in a display.

For display equations with a number, use an `equation` environment. Try this.

Here are some common things to do in math. Make sure to try them out.

- Subscripts and superscripts: x_i^2 . If the sub or superscript is more than a single symbol, it needs to be grouped: x_{i+1}^{2n} . If you need a brace in a formula, use $\{\}$.
- Greek letters and other symbols: $\alpha\otimes\beta_i$.
- Combinations of all these $\int_{t=0}^{\infty} dt$.

Exercise. Take the last example and typeset it as display math. Do you see a difference with inline math?

Expected outcome. T_EX tries not to include the distance between text lines, even if there is math in a paragraph. For this reason it typesets the bounds on an integral sign differently from display math.

B.12.2.4 Referencing

Purpose. In this section you will see \TeX 's cross referencing mechanism in action.

So far you have not seen \LaTeX do much that would save you any work. The cross referencing mechanism of \LaTeX will definitely save you work: any counter that \LaTeX inserts (such as section numbers) can be referenced by a label. As a result, the reference will always be correct.

Start with an example document that has at least two section headings. After your first section heading, put the command `\label{sec:first}`, and put `\label{sec:other}` after the second section heading. These label commands can go on the same line as the `section` command, or on the next. Now put

As we will see in section~\ref{sec:other}.

in the paragraph before the second section. (The tilde character denotes a non-breaking space.)

Exercise. Make these edits and format the document. Do you see the warning about an undefined reference? Take a look at the output file. Format the document again, and check the output again. Do you have any new files in your directory?

Expected outcome. On a first pass through a document, the \TeX compiler will gather all labels with their values in a `.aux` file. The document will display a double question mark for any references that are unknown. In the second pass the correct values will be filled in.

Caveats. If after the second pass there are still undefined references, you probably made a typo. If you use the `bibtex` utility for literature references, you will regularly need three passes to get all references resolved correctly.

Above you saw that the `equation` environment gives displayed math with an equation number. You can add a label to this environment to refer to the equation number.

Exercise. Write a formula in an `equation` environment, and add a label. Refer to this label anywhere in the text. Format (twice) and check the output.

Expected outcome. The `\label` and `\ref` command are used in the same way for formulas as for section numbers. Note that you must use `\begin/end{equation}` rather than `\[. . . \]` for the formula.

B.12.2.5 Lists

Purpose. In this section you will see the basics of lists.

Bulleted and numbered lists are provided through an environment.

```
\begin{itemize}
\item This is an item;
\item this is one too.
```

```
\end{itemize}
\begin{enumerate}
\item This item is numbered;
\item this one is two.
\end{enumerate}
```

Exercise. Add some lists to your document, including nested lists. Inspect the output.

Expected outcome. Nested lists will be indented further and the labeling and numbering style changes with the list depth.

Exercise. Add a label to an item in an `enumerate` list and refer to it.

Expected outcome. Again, the `\label` and `\ref` commands work as before.

B.12.2.6 Graphics

Since you can not immediately see the output of what you are typing, sometimes the output may come as a surprise. That is especially so with graphics. L^AT_EX has no standard way of dealing with graphics, but the following is a common set of commands:

```
\usepackage{graphicx} % this line in the preamble
\includegraphics{myfigure} % in the body of the document
```

The figure can be in any of a number of formats, except that PostScript figures (with extension `.ps` or `.eps`) can not be used if you use `pdflatex`.

Since your figure is often not the right size, the `include` line will usually have something like:

```
\includegraphics[scale=.5]{myfigure}
```

A bigger problem is that figures can be too big to fit on the page if they are placed where you declare them. For this reason, they are usually treated as ‘floating material’. Here is a typical declaration of a figure:

```
\begin{figure}[ht]
\includegraphics{myfigure}
\caption{This is a figure}
\label{fig:first}
\end{figure}
```

It contains the following elements:

- The `figure` environment is for ‘floating’ figures; they can be placed right at the location where they are declared, at the top or bottom of the next page, at the end of the chapter, et cetera.

B. Practical tutorials

- The [ht] argument of the `\begin{figure}` line states that your figure should be attempted to be placed here; if that does not work, it should go top of the next page. The remaining possible specifications are b for placement at the bottom of a page, or p for placement on a page by itself. For example

```
\begin{figure}[hbp]
```

declares that the figure has to be placed here if possible, at the bottom of the page if that's not possible, and on a page of its own if it is too big to fit on a page with text.

- A caption to be put under the figure, including a figure number;
- A label so that you can refer to the figure number by its label: `figure~\ref{fig:first}`.
- And of course the figure material. There are various ways to fine-tune the figure placement. For instance

```
\begin{center}
  \includegraphics{myfigure}
\end{center}
```

gives a centered figure.

B.12.2.7 Bibliography references

The mechanism for citing papers and books in your document is a bit like that for cross referencing. There are labels involved, and there is a `\cite{thatbook}` command that inserts a reference, usually numeric. However, since you are likely to refer to a paper or book in more than one document you write, L^AT_EX allows you to have a database of literature references in a file by itself, rather than somewhere in your document.

Make a file `mybibliography.bib` with the following content:

```
@article{JoeDoe1985,
  author = {Joe Doe},
  title = {A framework for bibliography references},
  journal = {American Library Assoc. Mag.},
  year = {1985}
}
```

In your document `mydocument.tex`, put

```
For details, refer to Doe~\cite{JoeDoe1985} % somewhere in the text

\bibliography{mybibliography} % at the end of the document
\bibliographystyle{plain}
```

Format your document, then type on the commandline

```
bibtex mydocument
```

and format your document two more times. There should now be a bibliography in it, and a correct citation. You will also see that files `mydocument.bbl` and `mydocument.blg` have been created.

B.12.2.8 Styles and other customizations

On Unix systems, T_EX investigates the TEXINPUTS environment variable when it tries to find an include file. Consequently, you can create a directory for your styles and other downloaded include files, and set this variable to the location of that directory.

B.12.3 A worked out example

The following example `demo.tex` contains many of the elements discussed above.

```
\documentclass{artikel3}

\usepackage{pslatex,graphicx,amsmath,amssymb}
\usepackage{pdflatex}

\newtheorem{theorem}{Theorem}

\newcounter{excounter}
\newenvironment{exercise}
{\refstepcounter{excounter}}
{\begin{quotation}\textbf{Exercise} \arabic{excounter}. \end{quotation} }

\begin{document}
\title{SSC 335: demo}
\author{Victor Eijkhout}
\date{today}
\maketitle
```

```
\section{This is a section}
\label{sec:intro}
```

This is a test document, used in `\cite{latextdemo}`. It contains a discussion in section `\ref{sec:discussion}`.

```
\begin{exercise}\label{easy-ex}
Left to the reader.
\end{exercise}
\begin{exercise}
Also left to the reader, just like in exercise \ref{easy-ex}
\end{exercise}

\begin{theorem}
This is cool.
\end{theorem}
This is a formula: $a \Leftarrow b$.
\begin{equation}
\label{eq:one}
x_i \leftarrow y_{ij} \cdot x^{(k)}_j
\end{equation}
```

```

Text: $\int_0^1 \sqrt{x}, dx$  

\[
  \int_0^1 \sqrt{x}, dx
\]
\section{This is another section}
\label{sec:discussion}

\begin{table}[ht]
  \centering
  \begin{tabular}{|rl|} \hline one&value \\ \hline another&values \\ \hline
  \end{tabular}
\caption{This is the only table in my demo}
\label{tab:thetable}
\end{table}
\begin{figure}[ht]
  \centering
  \includegraphics{graphics/caches}
\caption{this is the only figure}
\label{fig:thefigure}
\end{figure}
As I showed in the introductory section~\ref{sec:intro}, in the  

paper~\cite{AdJo:colorblind}, it was shown that  

equation~\eqref{eq:one}
\begin{itemize}
\item There is an item.
\item There is another item
  \begin{itemize}
    \item sub one
    \item sub two
  \end{itemize}
\end{itemize}
\begin{enumerate}
\item item one
\item item two
  \begin{enumerate}
    \item sub one
    \item sub two
  \end{enumerate}
\end{enumerate}
\end{document}

\tableofcontents
\listoffigures

\bibliography{math}
\bibliographystyle{plain}

\end{document}

```

You also need the file `math.bib`:

```
@article{AdJo:colorblind,
author = {Loyce M. Adams and Harry F. Jordan},
title = {Is {SOR} color-blind?},
journal = {SIAM J. Sci. Stat. Comput.},
year = {1986},
volume = {7},
pages = {490--506},
abstract = {For what stencils do ordinary and multi-colour SOR have
the same eigenvalues.},
keywords = {SOR, colouring}
}

@misc{latexdemo,
author = {Victor Eijkhout},
title = {Short {\LaTeX}\ demo},
note = {SSC 335, oct 1, 2008}
}
```

The following sequence of commands

```
pdflatex demo
bibtex demo
pdflatex demo
pdflatex demo
```

gives

SSC 335: demo

Victor Eijkhout

today

1 This is a section

This is a test document, used in [2]. It contains a discussion in section 2.

Exercise 1. Left to the reader.

Exercise 2. Also left to the reader, just like in exercise 1

Theorem 1 *This is cool.*

This is a formula: $a \Leftarrow b$.

$$x_i \leftarrow y_{ij} \cdot x_j^{(k)} \quad (1)$$

Text: $\int_0^1 \sqrt{x} dx$

$$\int_0^1 \sqrt{x} dx$$

2 This is another section

one	value
another	values

Table 1: This is the only table in my demo




Figure 1: this is the only figure

As I showed in the introductory section 1, in the paper [1], it was shown that equation (1)

- There is an item.

- There is another item
 - sub one
 - sub two
- 1. item one
- 2. item two
 - (a) sub one
 - (b) sub two

Contents

- 1 This is a section 1
- 2 This is another section 1

List of Figures

- 1 this is the only figure 1

References

- [1] Loyce M. Adams and Harry F. Jordan. Is SOR color-blind? *SIAM J. Sci. Stat. Comput.*, 7:490–506, 1986.
- [2] Victor Eijkhout. Short L^AT_EX demo. SSC 335, oct 1, 2008.

B.12.4 Where to take it from here

This tutorial touched only briefly on some essentials of T_EX and L_AT_EX. You can find longer intros online [101], or read a book [85, 81, 100]. Macro packages and other software can be found on the Comprehensive T_EX Archive <http://www.ctan.org>. For questions you can go to the newsgroup `comp.text.tex`, but the most common ones can often already be found on web sites [122].

Appendix C

Class projects

C.1 Cache simulation and analysis

In this project you will build a cache simulator and analyze the cache hit/miss behaviour of code, either real or simulated.

C.1.1 Cache simulation

A simulated cache is a simple data structure that records for each cache address what memory address it contains, and how long the data has been present. Design this data structure and write the access routines. (Use of an object oriented language is recommended.)

Write your code so that your cache can have various levels of associativity, and different replacement policies.

For simplicity, do not distinguish between read and write access. Therefore, the execution of a program becomes a stream of

```
cache.access_address( 123456 );
cache.access_address( 70543 );
cache.access_address( 12338383 );
....
```

calls where the argument is the memory address. Your code will record whether the request can be satisfied from cache, or whether the data needs to be loaded from memory.

C.1.2 Code simulation

Find some example codes, for instance from a scientific project you are involved in, and translate the code to a sequence of memory address.

You can also simulate codes by generating a stream of access instructions as above:

- Some access will be to random locations, corresponding to use of scalar variables;
- At other times access will be to regularly space addresses, corresponding to the use of an array;

- Array operations with indirect addressing will cause prolonged episodes of random address access.

Try out various mixes of the above instruction types. For the array operations, try smaller and larger arrays with various degrees of reuse.

Does your simulated code behave like a real code?

C.1.3 Investigation

First implement a single cache level and investigate the behaviour of cache hits and misses. Explore different associativity amounts and different replacement policies.

C.1.4 Analysis

Do a statistical analysis of the cache hit/miss behaviour. You can start with [112]¹. Hartstein [65] found a power law behaviour. Are you finding the same?

1. Strictly speaking that paper is about page swapping out of virtual memory (section 1.3.8), but everything translates to cacheline swapping out of main memory.

C.2 Evaluation of Bulk Synchronous Programming

In this project you're asked to analyze the Bulk Synchronous Parallel (BSP) model, both abstractly and by simulation.

C.2.1 Discussion

For your assignment you need to investigate Bulk Synchronous Programming. Read the wikipedia article http://en.wikipedia.org/wiki/Bulk_synchronous_parallel and section 2.5.9 in the book.

Consider the following questions.

1. Discuss the relation between the complexity model of BSP and the α, β, γ model you learned in section 6.2.1.
2. BSP uses barrier synchronisations. Are these necessary in practice? Consider separately two different classes of algorithms, namely PDE solving, and large scale graph computations.

C.2.2 Simulation

In the defining paper on BSP, Valiant [124] advocates making more tasks than processors, and distributing them randomly. Program a simulation and test if this strategy solves the load balance problem. Discuss the random placement strategy in the context of various algorithms.

C.3 Heat equation

In this project you will combine some of the theory and practical skills you learned in class to solve a real world problem. In addition to writing code that solves the program, you will use the following software practices:

- use source code control,
- give the program checkpoint/restart capability, and
- use basic profiling and visualization of the results.

The Heat Equation (see section 4.3) is given by

$$\frac{\partial T(x, t)}{\partial t} = \begin{cases} \alpha \frac{\partial^2 T(x, y)}{\partial x^2} + q(x, t) & 1D \\ \alpha \frac{\partial^2 T(x, y)}{\partial x^2} + \alpha \frac{\partial^2 T(x, y)}{\partial y^2} + q(x, t) & 2D \\ \dots & 3D \end{cases}$$

where $t \geq 0$ and $x \in [0, 1]$, subject to boundary conditions

$$T(x, 0) = T_0(x), \quad \text{for } x \in [0, 1],$$

and similar in higher dimensions, and

$$T(0, t) = T_a(t), \quad T(1, t) = T_b(t), \quad \text{for } t > 0.$$

You will solve this problem using the explicit and implicit Euler methods.

C.3.1 Software

Write your software using the PETSc library (see tutorial B.6. In particular, use the `MatMult` routine for matrix-vector multiplication and `KSPSolve` for linear system solution. Exception: code the Euler methods yourself.

Be sure to use a Makefile for building your project (tutorial B.3).

Add your source files, Makefile, and job scripts to an svn repository (tutorial B.4); do not add binaries or output files. Make sure that there is a README file with instructions on how to build and run your code.

Implement a checkpoint/restart facility by writing vector data, size of the time step, and other necessary items, to an `hdf5` file (tutorial B.5). Your program should be able to read this file and resume execution.

C.3.2 Tests

Do the following tests on a single core.

Method stability

Run your program for the 1D case with

$$\begin{cases} q = \sin \ell \pi x \\ T_0(x) = e^x \\ T_a(t) = T_b(t) = 0 \\ \alpha = 1 \end{cases}$$

Take a space discretization at least $h = 10^{-2}$ but especially in parallel do not be afraid to try large problem sizes. Try various time steps and show that the explicit method can diverge. What is the maximum time step for which it is stable?

For the implicit method, at first use a direct method to solve the system. This corresponds to PETSc options `KSPPREONLY` and `PCLU` (see section 5.5.10 and the PETSc tutorial, B.6).

Now use an iterative method (for instance `KSPCG` and `PCJACOBI`); is the method still stable? Explore using a low convergence tolerance and large time steps.

Since the forcing function q and the boundary conditions have no time dependence, the solution $u(\cdot, t)$ will converge to a *steady state* solution $u_\infty(x)$ as $t \rightarrow \infty$. What is the influence of the time step on the speed with which implicit method converges to this steady state?

Hint: the steady state is described by $u_t \equiv 0$. Substitute this in the PDE. Can you find explicitly what the steady state is?

Run these tests with various values for ℓ .

Timing

If you run your code with the commandline option `-log_summary`, you will get a table of timings of the various PETSc routines. Use that to do the following timing experiments. Make sure you use a version of PETSc that was *not* compiled with debug mode.

Construct your coefficient matrix as a dense matrix, rather than sparse. Report on the difference in total memory, and the runtime and flop rate of doing one time step. Do this for both the explicit and implicit method and explain the results.

With a sparse coefficient matrix, report on the timing of a single time step. Discuss the respective flop counts and the resulting performance.

Restart

Implement a restart facility: every 10 iterations write out the values of the current iterate, together with values of Δx , Δt , and ℓ . Add a flag `-restart` to your program that causes it to read the restart file and resume execution, reading all parameters from the restart file.

Run your program for 25 iterations, and restart, causing it to run again from iteration 20. Check that the values in iterations 20 . . . 25 match.

C.3.3 Parallelism

Do the following tests to determine the parallel scaling of your code.

At first test the explicit method, which should be perfectly parallel. Report on actual speedup attained. Try larger and smaller problem sizes and report on the influence of the problem size.

The above settings for the implicit method (`KSPPREONLY` and `PCLU`) lead to a runtime error. One way out is to let the system be solved by an iterative method. Read the PETSc manual and web pages to find out some choices of iterative method and preconditioner and try them. Report on their efficacy.

C.3.4 Comparison of solvers

In the implicit timestepping method you need to solve linear systems. In the 2D (or 3D) case it can make a big difference whether you use a direct solver or an iterative one.

Set up your code to run with $q \equiv 0$ and zero boundary conditions everywhere; start with a nonzero initial solution. You should now get convergence to a zero steady state, thus the norm of the current solution is the norm of the iterate.

Now do the following comparison; take several values for the time step.

Direct solver

If your PETSc installation includes direct solvers such as `MUMPS`, you can invoke them with

```
myprog -pc_type lu -ksp_type preonly \
        -pc_factor_mat_solver_package mumps
```

Run your code with a direct solver, both sequentially and in parallel, and record how long it takes for the error to get down to 10^{-6} .

Iterative Solver

Use an iterative solver, for instance `KSPCG` and `KSPBCGS`. Experiment with the convergence tolerance: how many timesteps does it take to get a 10^{-6} error if you set the iterative method tolerance to 10^{-12} , how much if you take a lesser tolerance?

Compare timings between direct and iterative method.

C.3.5 Reporting

Write your report using L^AT_EX (tutorial B.12). Use both tables and graphs to report numerical results. Use gnuplot (tutorial B.7) or a related utility for graphs.

Appendix D

Codes

This section contains several simple codes that illustrate various issues relating to the performance of a single CPU. The explanations can be found in section 1.6.

D.1 Hardware event counting

The codes in this chapter make calls to a library named PAPI for ‘Performance Application Programming Interface’ [13, 107]. This is a portable set of calls to query the hardware counters that are built into most processors. Since these counters are part of the processor hardware, they can measure detailed events such as cache misses without this measurement process disturbing the phenomenon it is supposed to observe.

While using hardware counters is fairly straightforward, the question of whether what they are reporting is what you actually meant to measure is another matter altogether. For instance, the presence of hardware prefetch streams (section 1.3.5) implies that data can be loaded into cache without this load being triggered by a cache miss. Thus, the counters may report numbers that seem off, or even impossible, under a naive interpretation.

D.2 Cache size

This code demonstrates the fact that operations are more efficient if data is found in L1 cache, than in L2, L3, or main memory. To make sure we do not measure any unintended data movement, we perform one iteration to bring data in the cache before we start the timers.

D.3 Cachelines

This code illustrates the need for small strides in vector code. The main loop operates on a vector, progressing by a constant stride. As the stride increases, runtime will increase, since the number of cachelines transferred increases, and the bandwidth is the dominant cost of the computation.

There are some subtleties to this code: in order to prevent accidental reuse of data in cache, the computation is preceded by a loop that accesses at least twice as much data as will fit in cache. As a result, the array is guaranteed not to be in cache.

Note that figure 1.10 in section 1.6.4 only plots up to stride 8, while the code computes to 16. In fact, at stride 12 the prefetch behaviour of the Opteron changes, leading to peculiarities in the timing, as shown in figure D.1.




Figure D.1: Run time in kcycles and L1 reuse as a function of stride

D.4 Cache associativity

This code illustrates the effects of cache associativity; see sections 1.3.4.8 and 1.6.6 for a detailed explanation. A number of vectors (dependent on the inner loop variable i) is traversed simultaneously. Their lengths are chosen to induce cache conflicts. If the number of vectors is low enough, cache associativity will resolve these conflicts; for higher values of m the runtime will quickly increase. By allocating the vectors with a larger size, the cache conflicts go away.

D.5 TLB

This code illustrates the behaviour of a *TLB*; see sections 1.3.8 and 1.6.5 for a thorough explanation. A two-dimensional array is declared in column-major ordering (Fortran style). This means that striding through the data by varying the i coordinate will have a high likelihood of TLB hits, since all elements on a page are accessed consecutively. The number of TLB entries accessed equals the number of elements divided by the page size. Striding through the array by the j coordinate will have each next element hitting a new page, so TLB misses will ensue when the number of columns is larger than the number of TLB entries.

Bibliography

- [1] Matrix market. <http://math.nist.gov/MatrixMarket>.
- [2] G. Amdahl. The validity of the single processor approach to achieving large scale computing capabilities. In *Proceedings of the AFIPS Computing Conference*, volume 30, pages 483–485, 1967.
- [3] O. Axelsson and A.V. Barker. *Finite element solution of boundary value problems. Theory and computation*. Academic Press, Orlando, Fl., 1984.
- [4] Owe Axelsson and Ben Polman. Block preconditioning and domain decomposition methods II. *J. Comp. Appl. Math.*, 24:55–72, 1988.
- [5] Richard Barrett, Michael Berry, Tony F. Chan, James Demmel, June Donato, Jack Dongarra, Victor Eijkhout, Roldan Pozo, Charles Romine, and Henk van der Vorst. *Templates for the Solution of Linear Systems: Building Blocks for Iterative Methods*. SIAM, Philadelphia PA, 1994. <http://www.netlib.org/templates/>.
- [6] K.E. Batcher. MPP: A high speed image processor. In *Algorithmically Specialized Parallel Computers*. Academic Press, New York, 1985.
- [7] Gordon Bell. The outlook for scalable parallel processing. Decision Resources, Inc, 1994.
- [8] Abraham Berman and Robert J. Plemmons. *Nonnegative Matrices in the Mathematical Sciences*. SIAM, 1994. originally published by Academic Press, 1979, New York.
- [9] Petter E. Bjorstad, William Gropp, and Barry Smith. *Domain decomposition : parallel multilevel methods for elliptic partial differential equations*. Cambridge University Press, 1996.
- [10] Netlib.org BLAS reference implementation. <http://www.netlib.orgblas>.
- [11] Mark Bohr. A 30 year retrospective on Dennard’s MOSFET scaling paper. *Solid-State Circuits Newsletter, IEEE*, 12(1):11 –13, winter 2007.
- [12] BOOST interval arithmetic library. <http://www.boost.org/libs/numeric/interval/doc/interval.htm>.
- [13] S. Browne, J Dongarra, N. Garner, G. Ho, and P. Mucci. A portable programming interface for performance evaluation on modern processors. *International Journal of High Performance Computing Applications*, 14:189–204, Fall 2000.
- [14] Alfredo Buttari, Victor Eijkhout, Julien Langou, and Salvatore Filippone. Performance optimization and modeling of blocked sparse kernels. 21:467–484, 2007.
- [15] P. M. Campbell, K. D. Devine, J. E. Flaherty, L. G. Gervasio, and J. D. Teresco. Dynamic octree load balancing using space-filling curves, 2003.
- [16] Ernie Chan, Marcel Heimlich, Avi Purkayastha, and Robert van de Geijn. Collective communication: theory, practice, and experience. *Concurrency and Computation: Practice and Experience*, 19:1749–1783, 2007.
- [17] Chapel programming language homepage. <http://chapel.cray.com/>.

- [18] Barbara Chapman, Gabriele Jost, and Ruud van der Pas. *Using OpenMP: Portable Shared Memory Parallel Programming*, volume 10 of *Scientific Computation Series*. MIT Press, ISBN 0262533022, 9780262533027, 2008.
- [19] Yaeyoung Choi, Jack J. Dongarra, Roldan Pozo, and David W. Walker. Scalapack: a scalable linear algebra library for distributed memory concurrent computers. In *Proceedings of the fourth symposium on the frontiers of massively parallel computation (Frontiers '92), McLean, Virginia, Oct 19–21, 1992*, pages 120–127, 1992.
- [20] A. Chronopoulos and C.W. Gear. s -step iterative methods for symmetric linear systems. *Journal of Computational and Applied Mathematics*, 25:153–168, 1989.
- [21] Charles Clos. A study of non-blocking switching networks. *Bell System Technical Journal*, 32:406–242, 1953.
- [22] E.F. D'Azevedo, V.L. Eijkhout, and C.H. Romine. A matrix framework for conjugate gradient methods and some variants of cg with less synchronization overhead. In *Proceedings of the Sixth SIAM Conference on Parallel Processing for Scientific Computing*, pages 644–646, Philadelphia, 1993. SIAM.
- [23] Jeffrey Dean and Sanjay Ghemawat. MapReduce: Simplified data processing on large clusters. In *OSDI'04: Sixth Symposium on Operating System Design and Implementation*, 2004.
- [24] J. Demmel, M. Heath, and H. Van der Vorst. Parallel numerical linear algebra. In *Acta Numerica 1993*. Cambridge University Press, Cambridge, 1993.
- [25] Jim Demmel, Jack Dongarra, Victor Eijkhout, Erika Fuentes, Antoine Petitet, Rich Vuduc, R. Clint Whaley, and Katherine Yellick. Self adapting linear algebra algorithms and software. *Proceedings of the IEEE*, 93:293–312, February 2005.
- [26] R.H. Dennard, F.H. Gaensslen, V.L. Rideout, E. Bassous, and A.R. LeBlanc. Design of ion-implanted mosfet's with very small physical dimensions. *Solid-State Circuits, IEEE Journal of*, 9(5):256 – 268, oct 1974.
- [27] Ashish Deshpande and Martin Schultz. Efficient parallel programming with linda. In *In Supercomputing '92 Proceedings*, pages 238–244, 1992.
- [28] E. W. Dijkstra. Cooperating sequential processes. <http://www.cs.utexas.edu/users/EWD/transcriptions/EWD01xx/EWD123.html>. Technological University, Eindhoven, The Netherlands, September 1965.
- [29] Edsger W. Dijkstra. Programming as a discipline of mathematical nature. *Am. Math. Monthly*, 81:608–612, 1974.
- [30] J. Dongarra, A. Geist, R. Manchek, and V. Sunderam. Integrated PVM Framework Supports Heterogeneous Network Computing. *Computers in Physics*, 7(2):166–75, April 1993.
- [31] J. J. Dongarra. *The LINPACK benchmark: An explanation*, volume 297, chapter Supercomputing 1987, pages 456–474. Springer-Verlag, Berlin, 1988.
- [32] Jack J. Dongarra, Jeremy Du Croz, Sven Hammarling, and Iain Duff. A set of level 3 basic linear algebra subprograms. *ACM Transactions on Mathematical Software*, 16(1):1–17, March 1990.
- [33] Jack J. Dongarra, Jeremy Du Croz, Sven Hammarling, and Richard J. Hanson. An extended set of FORTRAN basic linear algebra subprograms. *ACM Transactions on Mathematical Software*, 14(1):1–17, March 1988.
- [34] Dr. Dobbs. Complex arithmetic: in the intersection of C and C++. <http://www.ddj.com/cpp/184401628>.

- [35] I. S. Duff, R. G. Grimes, and J. G. Lewis. Users' guide for the Harwell-Boeing sparse matrix collection (release I). Technical Report RAL 92-086, Rutherford Appleton Laboratory, 1992.
- [36] Victor Eijkhout. A general formulation for incomplete blockwise factorizations. *Comm. Appl. Numer. Meth.*, 4:161–164, 1988.
- [37] Victor Eijkhout, Paolo Bientinesi, and Robert van de Geijn. Towards mechanical derivation of krylov solver libraries. *Procedia Computer Science*, 1(1):1805–1813, 2010. proceedings of ICCS 2010, <http://www.sciencedirect.com/science/publication?issn=18770509&volume=1&issue=1>.
- [38] Paul Erdős and A. Rnyi. On the evolution of random graphs. *Publications of the Mathematical Institute of the Hungarian Academy of Sciences*, 5:17?–61, 1960.
- [39] V. Faber and T. A. Manteuffel. Necessary and sufficient conditions for the existence of a conjugate gradient method. 21(2):352–362, 1984.
- [40] R.D. Falgout, J.E. Jones, and U.M. Yang. Pursuing scalability for hypre's conceptual interfaces. Technical Report UCRL-JRNL-205407, Lawrence Livermore National Lab, 2004. submitted to ACM Transactions on Mathematical Software.
- [41] M. Fiedler. A property of eigenvectors of nonnegative symmetric matrices and its applications to graph theory. *Czechoslovak Mathematical Journal*, 25:618–633, 1975.
- [42] D. C. Fisher. Your favorite parallel algorithms might not be as fast as you think. *IEEE Trans. Computers*, 37:211–213, 1988.
- [43] M. Flynn. Some computer organizations and their effectiveness. *IEEE Trans. Comput.*, C-21:948, 1972.
- [44] Project fortress homepage. <http://projectfortress.sun.com/Projects/Community>.
- [45] D. Frenkel and B. Smit. Understanding molecular simulations: From algorithms to applications, 2nd edition. 2002.
- [46] Roland W. Freund and Noël M. Nachtigal. QMR: a quasi-minimal residual method for non-Hermitian linear systems. *Numer. Math.*, 60:315–339, 1991.
- [47] M. Frigo, Charles E. Leiserson, H. Prokop, and S. Ramachandran. Cache oblivious algorithms. In *Proc. 40th Annual Symposium on Foundations of Computer Science*, 1999.
- [48] A. Geist, A. Beguelin, J. Dongarra, W. Jiang, R. Manchek, and V. Sunderam. *PVM: A Users' Guide and Tutorial for Networked Parallel Computing*. MIT Press, 1994. The book is available electronically, the url is <ftp://www.netlib.org/pvm3/book/pvm-book.ps>.
- [49] David Gelernter. Generative communication in linda. *ACM Transactions on Programming Languages and Systems*, 7:80–112, 1985.
- [50] David Gelernter and Nicholas Carriero. Coordination languages and their significance. *Commun. ACM*, 35(2):97–107, 1992.
- [51] GNU multiple precision library. <http://gmplib.org/>.
- [52] Stefan Goedecker and Adolfy Hoisie. *Performance Optimization of Numerically Intensive Codes*. SIAM, 2001.
- [53] D. Goldberg. Compuer arithmetic. Appendix in [68].
- [54] David Goldberg. What every computer scientist should know about floating-point arithmetic. *Computing Surveys*, March 1991.

BIBLIOGRAPHY

- [55] G. H. Golub and D. P. O’Leary. Some history of the conjugate gradient and Lanczos algorithms: 1948-1976. 31:50–102, 1989.
- [56] Gene H. Golub and Charles F. Van Loan. *Matrix Computations*. The Johns Hopkins University Press, Baltimore, second edition edition, 1989.
- [57] Kazushige Goto and Robert A. van de Geijn. Anatomy of high-performance matrix multiplication. *ACM Trans. Math. Softw.*, 34(3):1–25, 2008.
- [58] F. Gray. Pulse code communication. U.S. Patent 2,632,058, March 17, 1953 (filed Nov. 1947).
- [59] Ronald I. Greenberg and Charles E. Leiserson. Randomized routing on fat-trees. In *Advances in Computing Research*, pages 345–374. JAI Press, 1989.
- [60] W. Gropp, E. Lusk, and A. Skjellum. *Using MPI*. The MIT Press, 1994.
- [61] William Gropp, Steven Huss-Lederman, Andrew Lumsdaine, Ewing Lusk, Bill Nitzberg, William Saphir, and Marc Snir. *MPI: The Complete Reference, Volume 2 - The MPI-2 Extensions*. MIT Press, 1998.
- [62] William Gropp, Thomas Sterling, and Ewing Lusk. *Beowulf Cluster Computing with Linux, 2nd Edition*. MIT Press, 2003.
- [63] Hadoop wiki. <http://wiki.apache.org/hadoop/FrontPage>.
- [64] Louis A. Hageman and David M. Young. *Applied Iterative Methods*. Academic Press, New York, 1981.
- [65] A. Hartstein, V. Srinivasan, T. R. Puzak, and P. G. Emma. Cache miss behavior: is it √2? In *Proceedings of the 3rd conference on Computing frontiers*, CF ’06, pages 313–320, New York, NY, USA, 2006. ACM.
- [66] Michael T. Heath. *Scientific Computing: an introductory survey; second edition*. McGraw Hill, 2002.
- [67] Don Heller. A survey of parallel algorithms in numerical linear algebra. *SIAM Review*, 20:740–777, 1978.
- [68] John L. Hennessy and David A. Patterson. *Computer Architecture, A Quantitative Approach*. Morgan Kaufman Publishers, 3rd edition edition, 1990, 3rd edition 2003.
- [69] M.R. Hestenes and E. Stiefel. Methods of conjugate gradients for solving linear systems. *Nat. Bur. Stand. J. Res.*, 49:409–436, 1952.
- [70] Nicholas J. Higham. *Accuracy and Stability of Numerical Algorithms*. Society for Industrial and Applied Mathematics, Philadelphia, PA, USA, second edition, 2002.
- [71] Jonathan. Hill, Bill Mccoll, Dan C. Stefanescu, Mark W. Goudreau, Kevin Lang, Satish B. Rao, Torsten Suel, Thanasis Tsantilas, and Rob H. Bisseling. BSplib: The BSP programming library. *Parallel Computing*, 24(14):1947–1980, 1998.
- [72] C. A. R. Hoare. An axiomatic basis for computer programming. *Communications of the ACM*, 12:576–580, 1969.
- [73] IEEE 754: Standard for binary floating-point arithmetic. <http://grouper.ieee.org/groups/754>.
- [74] Interval arithmetic. [http://en.wikipedia.org/wiki/Interval_\(mathematics\)](http://en.wikipedia.org/wiki/Interval_(mathematics)).
- [75] C.R. Jesshope and R.W. Hockney editors. The DAP approach, volume 2. pages 311–329. Infotech Intl. Ltd., Maidenhead, 1979.
- [76] M. T. Jones and P. E. Plassmann. The efficient parallel iterative solution of large sparse linear

- systems. In A. George, J.R. Gilbert, and J.W.H. Liu, editors, *Graph Theory and Sparse Matrix Computations*, IMA Vol 56. Springer Verlag, Berlin, 1994.
- [77] L. V. Kale and S. Krishnan. Charm++: Parallel programming with message-driven objects. In *Parallel Programming using C++*, G. V. Wilson and P. Lu, editors, pages 175–213. MIT Press, 1996.
- [78] Michael Karbo. PC architecture. <http://www.karbosguide.com/books/pcarchitecture/chapter00.htm>.
- [79] R.M. Karp and Y. Zhang. A randomized parallel branch-and-bound procedure. In *Proceedings of the Twentieth Annual ACM Symposium on Theory of Computing, Chicago, IL, USA, 2-4 May 1988*, pages .290–300. ACM Press, 1988.
- [80] Kendall Square Research. http://en.wikipedia.org/wiki/Kendall_Square_Research.
- [81] Helmut Kopka and Patrick W. Daly. *A Guide to L^AT_EX*. Addison-Wesley, first published 1992.
- [82] Milind Kulkarni, Martin Burtscher, Rajasekhar Inkulu, Keshav Pingali, and Calin Cascaval. How much parallelism is there in irregular applications? In *Principles and Practices of Parallel Programming (PPoPP)*, 2009.
- [83] Vipin Kumar, Ananth Grama, Anshul Gupta, and George Karypis. *Introduction to Parallel Computing*. Benjamin Cummings, 1994.
- [84] L. Lamport. How to make a multiprocessor computer that correctly executes multiprocess programs. *IEEE Transactions on Computers*, C-28:690?–691, 1979.
- [85] L. Lamport. *L^AT_EX, a Document Preparation System*. Addison-Wesley, 1986.
- [86] C. Lanczos. Solution of systems of linear equations by minimized iterations. *Journal of Research, Nat. Bu. Stand.*, 49:33–53, 1952.
- [87] Rubin H Landau, Manual José Páez, and Cristian C. Bordeianu. *A Survey of Computational Physics*. Princeton University Press, 2008.
- [88] J. Langou. *Iterative methods for solving linear systems with multiple right-hand sides*. Ph.D. dissertation, INSA Toulouse, June 2003. CERFACS TH/PA/03/24.
- [89] C. L. Lawson, R. J. Hanson, D. Kincaid, and F. T. Krogh. Basic Linear Algebra Subprograms for FORTRAN usage. *ACM Trans. Math. Software*, 5:308–323, 1979. (Algorithm 539).
- [90] Charles E. Leiserson. Fat-Trees: Universal networks for hardware-efficient supercomputing. *IEEE Trans. Comput.*, C-34:892–901, 1985.
- [91] Richard J. Lipton, Donald J. Rose, and Robert Endre Tarjan. Generalized nested dissection. *SIAM J. Numer. Anal.*, 16:346–358, 1979.
- [92] Richard J. Lipton and Robert Endre Tarjan. A separator theorem for planar graphs. *SIAM J. Appl. Math.*, 36:177–189, 1979.
- [93] J.D.C. Little. A proof of the queueing formula $L = \lambda W$. *Ope. Res.*, pages 383–387, 1961.
- [94] M. Luby. A simple parallel algorithm for the maximal independent set problem. *SIAM Journal on Computing*, 4, 1986.
- [95] Grzegorz Malewicz, Matthew H. Austern, Aart J.C. Bik, James C. Dehnert, Ilan Horn, Naty Leiser, and Grzegorz Czajkowski. Pregel: a system for large-scale graph processing - "abstract". In *Proceedings of the 28th ACM symposium on Principles of distributed computing*, PODC '09, pages 6–6, New York, NY, USA, 2009. ACM.
- [96] Robert Mecklenburg. *Managing Projects with GNU Make*. O'Reilly Media, 3rd edition edition,

BIBLIOGRAPHY

2004. Print ISBN:978-0-596-00610-5 ISBN 10:0-596-00610-1 Ebook ISBN:978-0-596-10445-0 ISBN 10:0-596-10445-6.
- [97] J.A. Meijerink and H.A. van der Vorst. An iterative solution method for linear systems of which the coefficient matrix is a symmetric M-matrix. *Math Comp*, 31:148–162, 1977.
- [98] Gerard Meurant. Multitasking the conjugate gradient method on the CRAY X-MP/48. *Parallel Computing*, 5:267–280, 1987.
- [99] Gérard Meurant. Domain decomposition methods for partial differential equations on parallel computers. *Int. J. Supercomputing Appl.*, 2:5–12, 1988.
- [100] Frank Mittelbach, Michel Goossens, Johannes Braams, David Carlisle, and Chris Rowley. *The L^AT_EX Companion, 2nd edition*. Addison-Wesley, 2004.
- [101] Tobi Oetiker. The not so short introductino to L^AT_EX. <http://tobi.oetiker.ch/lshort/>.
- [102] Andrew T. Ogielski and William Aiello. Sparse matrix computations on parallel processor arrays. *SIAM J. Sci. Stat. Comput.* in press.
- [103] S. Otto, J. Dongarra, S. Hess-Lederman, M. Snir, and D. Walker. *Message Passing Interface: The Complete Reference*. The MIT Press, 1995.
- [104] Michael L. Overton. *Numerical Computing with IEEE Floating Point Arithmetic*. SIAM, Philadelphia PA, 2001.
- [105] Larry Page, Sergey Brin, R. Motwani, and T. Winograd. The pagerank citation ranking: Bringing order to the web, 1998.
- [106] V. Ya. Pan. New combination sof methods for the acceleration of matrix multiplication. *Comp. & Maths. with Apppls.*, 7:73–125, 1981.
- [107] Performance application programming interface. <http://icl.cs.utk.edu/papi/>.
- [108] David A. Patterson. Technical perspective: the data center is the computer. *Commun. ACM*, 51(1):105–105, 2008.
- [109] S. Plimpton. Fast parallel algorithms for short-range molecular dynamics. *J. Comput. Phys.*, 117:1–19, 1995.
- [110] M. Püschel, B. Singer, J. Xiong, J. M. F. Moura, J. Johnson, D. Padua, M. Veloso, and R. W. Johnson. SPIRAL: A generator for platform-adapted libraries of signal processing algorithms. *Int'l Journal of High Performance Computing Applications*, 18(1):21–45, 2004.
- [111] Texas Advanced Computing Center: Sun Constellation Cluster: Ranger. <http://www.tacc.utexas.edu/resources/hpc/constellation>.
- [112] Gururaj S. Rao. Performance analysis of cache memories. *J. ACM*, 25:378–395, July 1978.
- [113] J.K. Reid. On the method of conjugate gradients for the solution of large sparse systems of linear equations. In J.K. Reid, editor, *Large sparse sets of linear equations*, pages 231–254. Academic Press, London, 1971.
- [114] Y. Saad. *Iterative methods for sparse linear systems*. PWS Publishing Company, Boston, 1996.
- [115] Tetsuya Sato. The earth simulator: Roles and impacts. *Nuclear Physics B - Proceedings Supplements*, 129-130:102 – 108, 2004. Lattice 2003.
- [116] David Schade. Canfar: Integrating cyberinfrastructure for astronomy. <https://wiki.bc.net/atl-conf/display/BCNETPUBLIC/CANFAR+-+Integrating+Cyberinfrastructure+for+Astronomy>.
- [117] D. E. Shaw. A fast, scalable method for the parallel evaluation of distance-limited pairwise particle interactions. *J. Comput. Chem.*, 26:1318–1328, 2005.

- [118] D. B. Skillicorn, Jonathan M. D. Hill, and W. F. Mccoll. Questions and answers about bsp, 1996.
- [119] Marc Snir, Steve Otto, Steven Huss-Lederman, David Walker, and Jack Dongarra. *MPI: The Complete Reference, Volume 1, The MPI-1 Core*. MIT Press, second edition edition, 1998.
- [120] Dan Spielman. Spectral graph theory, fall 2009. <http://www.cs.yale.edu/homes/spielman/561/>.
- [121] V. Strassen. Gaussian elimination is not optimal. *Numer. Math.*, 13:354–356, 1969.
- [122] TeX frequently asked questions.
- [123] Universal Parallel C at George Washington University. <http://upc.gwu.edu/>.
- [124] Leslie G. Valiant. A bridging model for parallel computation. *Commun. ACM*, 33:103–111, August 1990.
- [125] R. van de Geijn, Philip Alpatov, Greg Baker, Almadena Chtchelkanova, Joe Eaton, Carter Edwards, Murthy Guddati, John Gunnels, Sam Guyer, Ken Klimkowski, Calvin Lin, Greg Morrow, Peter Nagel, James Overfelt, and Michelle Pal. Parallel linear algebra package (PLAPACK): Release r0.1 (beta) users' guide. 1996.
- [126] Robert A. van de Geijn. *Using PLAPACK: Parallel Linear Algebra Package*. The MIT Press, 1997.
- [127] Robert A. van de Geijn and Enrique S. Quintana-Ortí. *The Science of Programming Matrix Computations*. www.lulu.com, 2008.
- [128] Henk van der Vorst. Bi-CGSTAB: a fast and smoothly converging variant of Bi-CG for the solution of nonsymmetric linear systems. *SIAM J. Sci. Stat. Comput.*, 13:631–644, 1992.
- [129] Richard S. Varga. *Matrix Iterative Analysis*. Prentice-Hall, Englewood Cliffs, NJ, 1962.
- [130] R. Vuduc, J. Demmel, and K. Yelikk. Oski: A library of automatically tuned sparse matrix kernels. In *(Proceedings of SciDAC 2005, Journal of Physics: Conference Series, to appear.*, 2005.
- [131] R. Clint Whaley, Antoine Petitet, and Jack J. Dongarra. Automated empirical optimization of software and the ATLAS project. *Parallel Computing*, 27(1–2):3–35, 2001. Also available as University of Tennessee LAPACK Working Note #147, UT-CS-00-448, 2000 (www.netlib.org/lapack/lawns/lawn147.ps).
- [132] O. Widlund. On the use of fast methods for separable finite difference equations for the solution of general elliptic problems. In D.J. Rose and R.A. Willoughby, editors, *Sparse matrices and their applications*, pages 121–134. Plenum Press, New York, 1972.
- [133] Barry Wilkinson and Michael Allen. *Parallel Programming*. Prentice Hall, New Jersey, 1999.
- [134] J.H. Wilkinson. *Rounding Errors in Algebraic Processes*. Prentice-Hall, Englewood Cliffs, N.J., 1963.
- [135] L. T. Yand and R. Brent. The improved bicgstab method for large and sparse unsymmetric linear systems on parallel distributed memory architectures. In *Proceedings of the Fifth International Conference on Algorithms and Architectures for Parallel Processing*. IEEE, 2002.
- [136] Randy Yates. Fixed point: an introduction. <http://www.digitalsignallabs.com/fp.pdf>, 2007.
- [137] David M. Young. *Iterative method for solving partial differential equations of elliptic type*. PhD thesis, Harvard Univ., Cambridge, MA, 1950.

Appendix E

Index and list of acronyms

AMR Adaptive Mesh Refinement	ILU Incomplete LU
AVX Advanced Vector Extensions	IVP Initial Value Problem
BEM Boundary Element Method	LAN Local Area Network
BSP Bulk Synchronous Parallel	LRU Least Recently Used
BLAS Basic Linear Algebra Subprograms	MGS Modified Gram-Schmidt
BVP Boundary Value Problem	MIC Many Integrated Cores
CAF Co-array Fortran	MIMD Multiple Instruction Multiple Data
CCS Compressed Column Storage	MPI Message Passing Interface
CG Conjugate Gradients	MTA Multi-Threaded Architecture
CGS Classical Gram-Schmidt	NUMA Non-Uniform Memory Access
COO Coordinate Storage	ODE Ordinary Differential Equation
CRS Compressed Row Storage	OS Operating System
DAG Directed Acyclic Graph	PGAS Partitioned Global Address Space
DSP Digital Signal Processing	PDE Partial Differential Equation
FD Finite Difference	PRAM Parallel Random Access Machine
FDM Finite Difference Method	RDMA Remote Direct Memory Access
FEM Finite Element Method	SAN Storage Area Network
FFT Fast Fourier Transform	SaaS Software as-a Service
FMM Fast Multipole Method	SFC Space-Filling Curve
FOM Full Orthogonalization Method	SIMD Single Instruction Multiple Data
FPGA Field-Programmable Gate Array	SIMT Single Instruction Multiple Thread
FPU Floating Point Unit	SM Streaming Multiprocessor
FSA Finite State Automaton	SMP Symmetric Multi Processor
FSB Front-Side Bus	SOR Successive Over-Relaxation
GMRES Generalized Minimum Residual	SP Streaming Processor
GPGPU General Purpose Graphics Processing Unit	SPMD Single Program Multiple Data
GPU Graphics Processing Unit	SPD symmetric positive definite
GS Gram-Schmidt	SSE SIMD Streaming Extensions
HPC High Performance Computing	TLB Translation Look-aside Buffer
HPF High Performance Fortran	UMA Uniform Memory Access
IBVP Initial Boundary Value Problem	UPC Unified Parallel C
ILP Instruction Level Parallelism	WAN Wide Area Network

Index

- 2's complement, 124
- α , see latency
- β , see bandwidth
- γ , see computation rate
- active messages, 87
- acyclic graph, 288
- Adaptive Mesh Refinement (AMR), 263
- address space, 57
shared, 57
- adjacency graph, 177, 289
- adjacency matrix, 289
- Advanced Vector Extensions (AVX), 55
- affinity, 67–68
- allgather, 207–208, 212
- Alliant FX/8, 29
- allreduce, 207
- AMD, 55, 119
Barcelona, 24, 26
Opteron, 19, 27, 35, 39, 41
- Amdahl's law, 103–105
- AMR, see Adaptive Mesh Refinement
- Apple
iCloud, 116
- archive utility, 315
- array processors, 54
- array syntax, 82
- asynchronous communication, 60
- atomic operation, 29, 66–67
- atomicity, see atomic operation
- autotuning, 46
- AVX, see Advanced Vector Extensions
- axpy, 30
- background process, 307
- backwards stability, 135
- banded matrix, 148
storage, 173–174
- bandwidth, 15, 100, 108, 205
aggregate, 91
of a matrix, see halfbandwidth
of a matrix, 173
- bandwidth bound algorithm, 119
- barrier, 88
- base, 125
- bash, 297
- Basic Linear Algebra Subprograms (BLAS), 348
- BBN
Butterfly, 96
- BEM, see Boundary Element Method
- benchmarking, 20, 31
- bidirectional exchange, 207
- big-endian, 335, 339
- binary-coded-decimal, 126
- bisection bandwidth, 91
- bisection width, 90
- bits, 123
- Bjam, 317
- BLAS, see Basic Linear Algebra Subprograms
- block Jacobi, 224, 240
- block matrix, 150, 232
- block tridiagonal, 151, 235
- blocking communication, 72, 78
- blocking for cache reuse, 38
- Boundary Element Method (BEM), 218
- Boundary Value Problem (BVP), 145–153
- branch misprediction, 13
- branch penalty, 13
- breakpoint, 367
- broadcast, 74, 206
- BSP, see Bulk Synchronous Parallel
- bubble sort, 263

- buffering, 203
Bulk Synchronous Parallel (BSP), 88
bus, 14
 speed, 16
 width, 16
butterfly exchange, 95
BVP, see Boundary Value Problem
by reference, 373
bytes, 123
- cache, 14, 18–24
 associative, 23
 block, 21
 blocking, 38, 43, 171
 coherence, 19, 27, 29–30, 34, 58, 243
 hierarchy, 19, 47
 hit, 19
 line, 21–22, 32
 mapping, 22
 miss, 19, 24
 oblivious programming, 47
 replacement policies, 20
 shared, 57
- cacheline
 boundary alignment, 22
- CAF, see Co-array Fortran
- capability computing, 116–117
- capacity computing, 116–117
- cartesian mesh, 92
- cartesian product, 81
- Cayley-Hamilton theorem, 191
- ccNUMA, 58
- CCS, see Compressed Column Storage
- CDC
 Cyber205, 56
- Cell processor, 99
- CG, see Conjugate Gradients
- CGS, see Classical Gram-Schmidt
- channel rate, 100
- channel width, 100
- Chapel, 82, 85–86
- characteristic polynomial, 191
- Charm++, 87
- checkerboard ordering, 151
- Cheeger’s
 constant, 292
 inequality, 292
- chess, 63
- Cholesky factorization, 166, 241
- Cilk, 69
- cleanup code, 36
- clique, 267, 290
- clock speed, 12
- Clos network, 99
- cloud computing, 114–116
- clusters, 56
- Co-array Fortran (CAF), 84–85
- co-processor, 99, 120
- coherence
 cache, 80
- collective communication, 74, 77–78, 205–208
- collective operation, 75, 100, 205–208
- colour number, 235, 289
- colouring, 234
- Columbia, 59
- column-major, 349, 371
- communication
 blocking, 77
 overlapping computation with, 59
- communication overhead, 104
- Compiler
 directives, 84
 compiler, 46, 61, 83
 flags, 136
 optimization, 17
 optimization levels, 129
 parallelizing, 64
- complexity, 282
 computational, 170–171, 282
 of iterative methods, 200
 space, 181–182, 282
- Compressed Column Storage (CCS), 176
- Compressed Row Storage (CRS), 175–177, 219
- computation rate, 100, 205
- computational finance, 117
- concurrency, 68
- condition number, 135, 277

conditionally stable, 143
congestion, 90
Conjugate Gradients (CG), 198
Connection Machine, 119
contention, 90
context switch, 106, 108
conveniently parallel, 63
COO, see Coordinate Storage
coordinate storage, 176
coordination language, 87
core, 27
 vs processor, 27
core dump, 362
correct rounding, 130, 131
Courant-Friedrichs-Lowy condition, 146
cpu-bound, 9
CPU-bound algorithm, 119
Cramer's rule, 160
Crank-Nicolson method, 158
Cray
 Cray-1, 56
 Cray-2, 56
 T3E, 80
 X/MP, 56
 XE6, 58
 XMT, 106
 Y/MP, 56
Cray Inc., 106
Cray Research, 106
critical path, 242
critical section, 67
crossbar, 57, 95
CRS, see Compressed Row Storage
CUDA, 54, 99, 107, 121
cycle (in graph), 288
cyclic distribution, 215

DAG, see Directed Acyclic Graph
data decomposition, 202
data parallel, 106, 107, 109
data parallelism, 106
data reuse, 14, 30
ddd, 362
DDT, 362

deadlock, 69, 73, 78
debug flag, 363
debugger, 362
debugging, 362–368
DEC
 Alpha, 56
defensive programming, 355
degree, 90, 287
Delauney mesh refinement, 62
Dennard scaling, 48
Dense linear algebra, 202–215
dependency, 12
diagonal dominance, 169
diagonal storage, 173–174, 175
diameter, 90, 287
die, 18
difference stencil, 152
differential operator, 146
direct mapping, 22
Directed Acyclic Graph (DAG), 242, 288
directories, 297
Dirichlet boundary condition, 145, 148
discretization, 142
distributed computing, 114–116
divide-and-conquer, 47
domain decomposition, 227
double precision, 108
DSP, see Digital Signal Processing

Earth Simulator, 119
ebook, 116
edges, 287
efficiency, 101
eigenvector
 dominant, 280
Eispack, 348
Elliptic PDEs, 146
embarrassingly parallel, 63, 101
embedding, 92
environment variable, 305
escape, 304, 312
ETA-10, 56
Euler
 explicit, 141–143

- implicit, 143–145
excess, 126
executable, 297
exponent, 125
- Facebook, 266
false sharing, 30, 80
Fast Fourier Transform (FFT), 41
fast solvers, 189
fat tree, 95
fault tolerance, 118
FD, see Finite Difference
FDM, see Finite Difference Method
FEM, see Finite Element Method
FFT, see Fast Fourier Transform
Fiedler’s theorem, 291
field scaling, 48
Field-Programmable Gate Array (FPGA), 117
files, 297
fill locations, 180
fill-in, 179–183, 236
 estimates, 181–182, 183
 reduction, 182
finite difference, 141
Finite Difference Method (FDM), 147
Finite Element Method (FEM), 153, 222
Finite State Automaton (FSA), 29, 295
finite volume method, 153
floating point pipeline, 35
flops, 13
flushed, 20
- FMM, see Fast Multipole Method
FOM, see Full Orthogonalization Method
foreground process, 307
Fortran, 349
 declarations in, 136
Fortress, 86
Fourier Transform, 293–294
FPGA, see Field-Programmable Gate Array
FPU, see Floating Point Unit
Front-Side Bus (FSB), 14
FSA, see Finite State Automaton
FSB, see Front-Side Bus
Full Orthogonalization Method (FOM), 195
- fully associative, 23
fully connected, 89
functional programming, 117–118
- gather, 74, 207
Gauss-Seidel, 187
GCC, 69
gdb, 362–368
General Purpose Graphics Processing Unit (GPGPU), 106
Generalized Minimum Residual (GMRES), 200
ghost region, 87, 216, 274
git, 334
Global Arrays, 81
GMRES, see Generalized Minimum Residual
GNU, 362, 370
 gdb, see gdb
 gnuplot, see gnuplot
 Make, see Make
gnuplot, 352
Google, 89, 218, 266
 Google Docs, 114–116
GPGPU, see General Purpose Graphics Processing Unit
gprof, 370
GPU, see Graphics Processing Unit
gradual underflow, 127
Gram-Schmidt, 195, 277–279
 modified, 195, 277
Grape computer, 99
graph
 seadjacency graph, 289
 colouring, 225, 235, 289
 directed, 287
 Laplacian, 111, 291
 random, 266
 social, 266
 theory, 287–292
 undirected, 90, 177, 287
Graphics Processing Unit (GPU), 56, 106–109, 119, 130, 219
Gray code, 94
grid (CUDA), 107
grid computing, 114

- GS, see Gram-Schmidt
guard digit, 131
Gustafson's law, 104
- halfbandwidth, 181
 left, 174
 right, 174
- hardware prefetch, 24
- Harwell-Boeing matrix format, 176
- heat equation, 146, 153
- Hessenberg matrix, 194
- heterogeneous computing, 120–121
- High Performance Fortran (HPF), 82, 84
- High-Performance Computing (HPC), 87, 114
- Horner's rule, 240, 269
- host processor, 120
- HPC, see High Performance Computing
- HPF, see High Performance Fortran
- hybrid computing, 79–80
- hyper-threading, 64
- Hyperbolic PDEs, 146
- hypercube, 93
- Hyperthreading, 27
- IBM, 86, 89, 126, 127, 339
 BlueGene, 59, 119
 BlueGene Q, 24
 Power series, 56
 Power6, 126
 Roadrunner, 49, 99
- IBVP, see Initial Boundary Value Problem
- idle, 109
- idle time, 78, 370
- ILP, see Instruction Level Parallelism
- ILU, see Incomplete LU
- incidence matrix, 268
- Incomplete LU (ILU), 189
- Incomplete LU (ILU)
 parallel, 224–226
- independent sets, 289
- indirect addressing, 176
- Initial Boundary Value Problem (IBVP), 146, 153–158
- Initial Value Problem (IVP), 139–145
- inner products, 221–222
- instruction issue, 54
- Instruction Level Parallelism (ILP), 9, 13, 48, 61
- instruction pipeline, 13
- Intel, 14, 27, 55, 119
 i860, 56, 99
 Itanium, 17, 119
 MIC, 121
 Paragon, 99
 Woodcrest, 23
 Xeon Phi, 54
- inter-node communication, 79
- interior nodes, 288
- intra-node communication, 79
- irreducible, 290
- Ising model, 273–274
- iterative methods, 183–200
- iterative refinement, 188
- IVP, see Initial Value Problem
- Jacobi method, 186
- kernel
 CUDA, 107
- Krylov methods, 183–200
- LAN, see Local Area Network
- Lapack, 119, 348, 350–351
- Laplace equation, 283
- latency, 15, 100, 205
- latency hiding, 15, 59
- leaf nodes, 288
- lexicographic ordering, 149, 151, 226
- libraries
 creating and using, 315–316
 numerical, 341–351, see Lapack, see PETSc
- Linda, 87
- linear algebra, 276–281
 software
 dense, 348–351
 sparse, 341–348
- linear array, 91
- linker, 315
- LINPACK

- benchmark, 31
Linpack, 119, 348
 benchmark, 35, 119, 348
Lisp, 118
Little's law, 25
little-endian, 335, 339
load
 balancing, 109–113
 balancing, dynamic, 110
 balancing, static, 110
 rebalancing, 111
 redistributing, 111, 113
 unbalance, 56, 71, 101, 109, 370
Local Area Network (LAN), 114
local solve, 224
locality, 9
 core, 34
 spatial, 31, 32
 temporal, 31
lock, 67
loop unrolling, 35, 45
LRU, see Least Recently Used
LU factorization, 165

M-matrix, 148, 189
machine epsilon, see machine precision
machine precision, 128
Make, 317–326
Mandelbrot set, 63, 110
mantissa, 126–129, 131, 132
manycore, 107
MapReduce, 117–118
Markov matrix, 290
matrix
 see adjacency matrix, 289
 nonnegative, 268
 norms, 276–277
 associated, 276
 stochastic, 268
 storage, dense, 214–215
 storage, sparse, 172–177
 strictly upper triangular, 240
 unit upper triangular, 240
Matrix Market, 176
matrix format, 176
memory
 access pattern, 20
 banks, 26
 distributed, 57
 hierarchy, 14
 leak, 343, 359
 pages, 26
 shared, 57
 stall, 15
 violations, 358
 wall, 14
memory-bound, 9
mercurial, 334
Message Passing Interface (MPI), 74–79
Metropolis algorithm, 274
MIMD, see Multiple Instruction Multiple Data
minimum spanning tree, 206
MIPS, 56
MKL, 348
Moore's law, 48
MPI, see Message Passing Interface
 MPI 3.0 draft, 78
MTA, see Multi-Threaded Architecture
multi-colouring, 235
Multi-Threaded Architecture (MTA), 106
multi-threading, 106
multicore, 13, 27–30, 48, 57, 171, 241
multigrid, 194
Multiple Instruction Multiple Data (MIMD), 56
MUMPS, 393

 $n_{1/2}$, 11
natural ordering, 151
nearest neighbour, 92
neighbourhood, 267
nested dissection, 226–232, 266
Neumann boundary condition, 148
Newton method, 190
node, 79
nodes, 287
non-blocking communication, 60, 74, 77, 78
non-local operation, 78
Non-Uniform Memory Access (NUMA), 58

- norm, 276
normalized floating point numbers, 127
null termination, 372
NUMA, see Non-Uniform Memory Access
NVidia, 99
- object file, 315
ODE, see Ordinary Differential Equation
one-sided communication, 80–81, 87
OpenMP, 68–71
Operating System (OS), 297
order, 282
Ordinary Differential Equation (ODE), 139–145
OS, see Operating System
overdecomposition, 89, 110, 214
overflow, 125, 127
overflow bit, 125
overlays, 26
- page table, 26
PageRank, 266, 268–269
Pagerank, 218
pages
 memory, see memory, pages
Parabolic PDEs, 146
parallel fraction, 103
parallel prefix, 239
Parallel Random Access Machine (PRAM), 102
parallelism
 data, 54, 60, 83
 dynamic, 70
 fine-grained, 60
 instruction-level, 50
 irregular, 63
parameter sweep, 63
partial derivates, 283
Partial Differential Equation (PDE), 145–158
partial differential equations, 283–284
partial pivoting, 163
Partitioned Global Address Space (PGAS), 58, 81–87
path (graph theory), 287
PCI-X bus, 108
PDE, see Partial Differential Equation
- peak performance, 12, 31, 35
penta-diagonal, 150
permutation, 182
Perron vector, 268, 269
Perron-Frobenius theorem, 280
PETSc, 341–348, 370
PGAS, see Partitioned Global Address Space
pipeline, 10–12, 35–36
 depth, 13, 48
 instruction, 13
 length, 13
 processor, 54
 pivoting, 161–163, 168–169
 diagonal, 163
 full, 163
 partial, 163
 pivots, 161
PLapack, 348
point-to-point communication, 74
Poisson equation, 146, 283
power
 consumption, 48–49
 efficiency, 54
 wall, 48
power method, 268, 279
PowerPC, 55
PRAM, see Parallel Random Access Machine
preconditioner, 188–190
prefetch data stream, 24
Pregel, 89
process
 affinity, see affinity
program counter, 8
protein interactions, 266
pseudo-random numbers, see random numbers
pthreads, 65
purify, 365
PVM, 79
- QR factorization, 277
quicksort, 264–266
- radix point, 125
random numbers, 271–272

- random placement, 89, 111
RDMA, see Remote Direct Memory Access
real numbers
 representation of, 123
recursive doubling, 12, 21, 235, 238–239
red-black ordering, 151, 232–235
reduce-scatter, 207–208, 211, 212
reducible, 178
reduction, 206
reduction operations, 70
redundancy, 91
refinement
 adaptive, 112
region of influence, 146
register, 8, 14, 16–17
 file, 16
 resident in, 17, 18
 spill, 17, 36
Remote Direct Memory Access (RDMA), 80
remote method invocation, 87
remote procedure call, 114
repository, 327
representation error
 absolute, 128
 relative, 128
residual, 184
resource contention, 69
revision control systems, see source code control
ring network, 91
round-off error analysis, 130–135
round-robin
 storage assignment, 83
 task scheduling, 71
rounding, 128
row-major, 371
- SaaS, see Software as-a Service
SAN, see Storage Area Network
scalability, 105
 strong, 105, 209
 weak, 105, 209
Scalapack, 119, 348
scaling, 105
scheduling
 dynamic, 71
 static, 71
Scons, 317
search direction, 196, 199
segmentation fault, 364
segmentation violation, 358
semaphore, 67
separable problem, 189
separator, 226, 266
Sequent Symmetry, 29
sequential consistency, 68, 69
sequential fraction, 103
serialized execution, 72
SFC, see Space-Filling Curve
SGI, 106
 UV, 58
sh, 297
shared libraries, 316
shell, 297
side effects, 118
sign bit, 124, 126
significant, 125, 126
significant digits, 132
SIMD, see Single Instruction Multiple Data
SIMD Streaming Extensions (SSE), 55, 99
SIMT, see Single Instruction Multiple Thread
Single Instruction Multiple Thread (SIMT), 107
single precision, 108
Single Program Multiple Data (SPMD), 56
skyline storage, 181
SM, see Streaming Multiprocessor
small world, 267
smoothers, 194
SMP, see Symmetric Multi Processor
socket, 27, 79, 120
Software as-a Service (SaaS), 115
SOR, see Successive Over-Relaxation
sorting, 263–266
source code control, 327
source-to-source transformations, 36
SP, see Streaming Processor
space-filling curve, 111–113
sparse

- linear algebra, 172–183, 215–220
matrix, 148, 172, 289
spatial locality, see locality, spatial
SPD, see symmetric positive definite
speculative execution, 13
speedup, 56, 101
SPMD, see Single Program Multiple Data
SSE, see SIMD Streaming Extensions
stall, 24
static libraries, 315
stationary iteration, 185
statistical mechanics, 274
steady state, 144, 146, 154, 284, 392
stochastic matrix, 290
Storage Area Network (SAN), 114
storage by diagonals, 173
stride, 21, 32, 38
strip mining, 45
structurally symmetric, 110, 177, 220, 290
subdomain, 226
substructuring, 227
Subversion, 327–334
Successive Over-Relaxation (SOR), 187
Sun
 Ray, 115
superlinear speedup, 101
superscalar, 9, 61
superstep, 52
supersteps, 81, 88
svn, see Subversion
swapped, 26
switch, 95
symbol table, 363
Symmetric Multi Processing (SMP), 57
symmetric positive definite (SPD), 169, 194, 199,
 200
system_clock, 369

task
 parallelism, 61–63
 queue, 63, 68
TAU, 370
Taylor series, 285–286
temporal locality, see locality, temporal

Tera Computer
 MTA, 106
ternary arithmetic, 127
thin client, 115
thread, 64–69, 109
 affinity, see affinity
 blocks, 107
 safe, 70
throughput computing, 107
Tianhe-1A, 99
Titanium, 84
TLB, see Translation Look-aside Buffer
 miss, 26
top 500, 119–120
torus, 92
TotalView, 362
transactional memory, 67
Translation Look-aside Buffer (TLB), 26, 395
tree graph, 288
tridiagonal, 150
tridiagonal matrix, 148
truncation, 128
truncation error, 142, 147
tuple space, 87

UMA, see Uniform Memory Access
unconditionally stable, 144
underflow, 127
Unified Parallel C (UPC), 82–84
Uniform Memory Access (UMA), 57, 96
unnormalized floating point numbers, 127
unsigned, 124
UPC, see Unified Parallel C
utility computing, 114
valgrind, 365–366
vector
 norms, 276
vector processor, 54
vertices, 287
Virtual memory, 26
virtualization, 114
von Neumann architectures, 7
wallclock time, 369

INDEX

WAN, see Wide Area Network
wavefront, 237
weak scaling, 103
weighted graph, 288
Wide Area Network (WAN), 114
wildcard, 302
work pool, 110
World Wide Web, 266

X10, 86
x86, 119