# Project 13: Using Kernel Debugging Commands with WinDbg (15 pts.)

# What You Need

• A Windows 10 machine with Livekd working, as prepared in the previous project. This project should work on Win 7 or any later version, but I only tested it on Windows 10.

# **Purpose**

Practice using simple WinDbg commands.

# **Starting Configuration**

You should have Livekd running, which launched WinDbg, as you did at the end of the previous project.

# Listing Modules with Im

At the bottom of the Command window, in the command bar, execute this command:

1m

A long list of loaded modules scrolls by.

Scroll back to see the **lm** command you entered, and the first few loaded kernel modules, as shown below.

```
Command - Dump C:\Windows\livekd.dmp - WinDbg:10.0.10586.567 X86
kd> lm
start
                       <u>module name</u>
          end
00230000 002c1000
                       windbg
                                    (deferred)
58490000 584d7000
                       symsru
                                    (deferred)
584e0000 58513000
                       sqmapi
                                    (deferred)
58520000 58590000
                       <u>dbgmodel</u>
                                    (deferred)
58590000 58a0c000
                       dbgeng
                                    (deferred)
58a10000 58b4e000
                       dbghelp
                                    (deferred)
                       MSFTEDIT
5fd90000 60023000
                                    (deferred)
63450000 634b8000
                       webio
                                    (deferred)
                       <u>dataexchange</u>
649b0000 649f1000
                                        (deferred)
678d0000 678e6000
                                    (deferred)
682e0000 682f2000
                                                     (deferred)
                       <u>ondemandconnroutehelper</u>
693F0000 693F8000
                       <u>rasadhlp</u>
                                    (deferred)
6d280000 6d288000
                       <u>version</u>
                                    (deferred)
                       COMCTL32
6d2b0000 6d4bf000
                                    (deferred)
6e250000 6e264000
                       dhcpcsvc
                                    (deferred)
                       dhcpcsvc6
6e270000 6e283000
                                     (deferred)
                       <u> Windows_Globalization</u>
                                                  (deferred)
6e300000 6e432000
                       <u>fwpuclnt</u>
6e680000 6e6c7000
                                    (deferred)
                       WINNSI
6e750000 6e758000
                                    (deferred)
70ae0000 70aea000
                       Secur32
                                    (deferred)
70af0000 70b8b000
                       WINHTIP
                                    (deferred)
                       <u>IPHLPAPI</u>
70ca0000 70ccf000
                                    (deferred)
71440000 7146d000
                       <u>XmlLite</u>
                                    (deferred)
72250000 72273000
                       qlobinputhost
                                         (deferred)
723e0000 72553000
                       windowscodecs
                                         (deferred)
                                    (deferred)
72780000 72803000
                       <u>dxgi</u>
72810000 72862000
                       Bcp47Langs
                                      (deferred)
72870000 72a8a000
                       <u>d3d11</u>
                                    (deferred)
72ae0000 72afd000
                       <u>dwmapi</u>
                                    (deferred)
72d60000 72e14000
                       <u>dcomp</u>
                                    (deferred)
73250000 732d4000
                       DNSAPI
                                    (deferred)
                                    (deferred)
73320000 73399000
                       <u>uxtheme</u>
733a0000 7346d000
                       <u>twinapi_appcore</u>
                                           (deferred)
73f40000 73f90000
                       mswsock
                                    (deferred)
                       SSPICLI
74230000 74254000
                                    (deferred)
744a0000 744bd000
                                    (deferred)
                       bcrypt
                                          (deferred)
74530000 7453c000
                       kernel_appcore
                       powrprof
74550000 74594000
                                    (deferred)
745a0000 745af000
                       profapi
                                    (deferred)
745b0000 745e7000
                       cfgmgr32
                                    (deferred)
kd>
```

Scroll down to find the module named **nt**, as shown below. It's easy to spot because it'e one of the few modules that shows a Symbols path.

This is Ntoskrnl, the main kernel module.

```
Command - Dump C:\Windows\livekd.dmp - WinDbg:10.0.10586.567 X86
                      MSCTF
                                  (deferred)
761a0000 762bf000
762c0000 776be000
                      SHELL32
                                  (deferred)
776c0000 77704000
                      sechost
                                  (deferred)
77710000 77794000
                      shcore
                                  (deferred)
                      <u>ntdll</u>
777c0000 7793b000
                                  (pdb symbols)
                                                           c:\symbols\ntdll.pdb\1D800FA4B5D64C84B7E9AA03C5E8A7121\ntdll.pdb
                                  (deferred)
80a00000 80a4a000
                      CLFS
80a50000 80a6b000
                      tm
                                  (deferred)
80a70000 80a83000
                                  (deferred)
                      PSHED
80a90000 80a9a000
                      BOOTUID
                                  (deferred)
80aa0000 80aaa000
                      <u>cmimcext</u>
                                  (deferred)
80ab0000 80ab9000
                      ntosext
                                  (deferred)
80ac0000 80b4b000
                      CI
                                  (deferred)
                                                (deferred)
80b50000 80bdd000
                      mcupdate_GenuineIntel
80be0000 80bec000
                      <u>werkernel</u>
                                   (deferred)
810ee000 810f6000
                      kd
                                  (deferred)
                      wfplwfs
                                  (deferred)
81c00000 81c18000
81c20000 81df2000
                      tcpip
                                  (deferred)
82002000 825f5000
                      nt
                                  (pdb symbols)
                                                           c:\symbols\ntkrpamp.pdb\F87A1D466E474BEB96AE200E68D9671E1\ntkrpamp.pdb
825f5000 82654000
                                  (aeterrea)
                      пат
82800000 8286b000
                                   (deferred)
                      <u>spaceport</u>
```

# **Viewing Memory**

82870000 82883000

In WinDbg, execute this command:

#### dd nt

You see the first several bytes of Ntoskrnl.exe, as shown below.

<u>volmgr</u>

(deferred)

This may be more familiar in ASCII.

In WinDbg, execute this command:

da nt

You see the characters "MZ" -- they are at the start of every EXE file.

```
kd> dd nt
804d7000   00905a4d 00000003 00000004 0000ffff
804d7010
          000000Ь8 00000000 00000040 00000000
804d7020
          00000000 00000000 00000000 00000000
804d7030
          00000000 00000000 00000000 000000e0
804d7040
          Oeba1f0e cd09b400 4c01b821 685421cd
          70207369 72676f72 63206d61 6f6e6e61
804d7050
804d7060
          65622074 6e757220 206e6920 20534f44
804d7070
          65646f6d 0a0d0d2e 00000024 00000000
kd> da nt
          "MZ."
804d7000
```

In WinDbg, execute this command:

#### da nt+4c

You see the message "This program cannot be run in DOS mode", as shown below:

```
kd> dd nt
82002000
          00905a4d 00000003 00000004 0000ffff
82002010
          000000b8 00000000 00000040 00000000
82002020
          0000000 00000000 0000000 00000000
82002030
          00000000 00000000 00000000 00000280
          Oeba1f0e cd09b400 4c01b821 685421cd
82002040
82002050
          70207369 72676F72 63206d61 6F6e6e61
82002060
          65622074 6e757220 206e6920 20534f44
82002070
          65646f6d 0a0d0d2e 00000024 00000000
kd> da nt
          "MZ."
82002000
kd> da nt+4c
          ".!This program cannot be run in "
8200204c
          "DOS mode....$"
8200206c
kd>
```

# Saving a Screen Image

Make sure you can see the message "This program cannot be run in DOS mode", as shown above.

On your keyboard, press the PrntScrn key.

Open Paint and paste the image in.

### YOU MUST SUBMIT WHOLE-DESKTOP IMAGES TO GET FULL CREDIT.

Save the image with a filename of "Proj 13a from YOUR NAME".

# **Searching for Functions**

In WinDbg, execute this command:

#### x nt!\*

This finds all the functions in Ntoskrnl.

There are a lot of them, as shown below:

```
kd> x nt!*
8203f570
                  nt!KiQuantumEnd (<no parameter info>)
                  nt!SmcCacheAdd (<no parameter info>)
8249a555
82003268
                  nt!GUID_CONSOLE_LOCKED = <no type information>
                  nt!CmpInitializeHive (<no parameter info>)
8225c556
                  nt!PopDripsWatchdoqAction = <no type information>
8222b644
                  nt!FsRtlpOplockKeysEqual (<no parameter info>)
820e7cda
823359da
                  nt!ObReleaseDuplicateInfo (<no parameter info>)
                  nt!MiInsertClone (<no parameter info>)
821af20a
                  nt!VfZwOpenEnlistment (<no parameter info>)
82506f46
                  nt!MiQueuePageFileExtension (<no parameter info>)
821a54df
8212efea
                  nt! ?? ::FNODOBFM::`string' (<no parameter info>)
                  nt!pXdvDriverStartIo = <no type information>
82545d94
                  nt!CmpLockTablePresent = <no type information>
8221d3d9
                  nt!PoAddThermalTriageData (<no parameter info>)
821b783e
                  nt!PopValidateExistingHiberFile (<no parameter info>)
8236b290
                  nt!ViGenericVerifyIrpStackUpward (<no parameter info>)
824f16b1
                  nt!_imp__WerLiveKernelCancelReport = <no type information>
82228390
                  nt! ?? ::NNGAKEGL::`string' (<no parameter info>)
8239f79a
                  nt!ExSaFree (<no parameter info>)
821da46e
                  nt!SepMatchCapability (<no parameter info>)
820e4f8c
                  nt!CmpGetIndexElementSize (<no parameter info>)
82331366
                  nt!ExAllocatePoolWithQuota (<no parameter info>)
821d6f7a
kd>
```

In WinDbg, execute this command:

#### x nt!\*Create\*

This finds all the functions in Ntoskrnl that contain the word "Create".

There are a lot of them, too.

kd> x nt!\*CreateFile\*

In WinDbg, execute this command:

#### x nt!\*CreateFile\*

This finds all the functions in Ntoskrnl that contain the word "CreateFile".

There are only about ten of those, including "nt!NtCreateFile", as shown below:

```
822cb2f0
                  nt!IopCreateFile (<no parameter info>)
8253e6e8
                  nt!pXdvIoCreateFile = <no type information>
8253eaf4
                  nt!pXdvZwCreateFile = <no type information>
                  nt!IoCreateFileEx (<no parameter info>)
822cb1da
825068a8
                  nt!UfZwCreateFile (<no parameter info>)
                  nt!BiCreateFileDeviceElement (<no parameter info>)
824ca86b
8253ebe0
                  nt!pXdvNtCreateFile = <no type information>
8233808e
                  nt!IoCreateFile (<no parameter info>)
825 Ø5df6
                  nt!VerifierNtCreateFile (<no parameter info>)
                  nt!IoCreateFileSpecifyDeviceObjectHint (<no parameter info>)
82344560
821198b0
                  nt!ZwCreateFile (<no parameter info>)
                  nt!NtCreateFile (<no parameter info>)
822cb2b0
824F8665
                  nt!ver1+1er1ocreateFile (<no parameter info>)
kd>
```

# **Unassembling a Function**

In WinDbg, execute this command:

#### u nt!NtCreateFile

This shows the first few bytes of the function, disassembled, as shown below:

```
kd> u nt!NtCreateFile
nt!NtCreateFile:
822cb2b0 8bff
                           MOV
                                   edi,edi
822cb2b2 55
                           push
                                   ebp
822cb2b3 8bec
                                   ebp,esp
                           MOV
822cb2b5 51
                                   ecx
                           push
822cb2b6 6a00
                           push
822cb2b8 6a20
                           push
                                   2 Øh
822cb2ba 6a00
                           push
                                   8
822cb2bc 6a00
                           push
|kd>
```

To see more of this function, it helps to use the WinDbg Disassembly window.


If the Command window is maximized, make it smaller.

From the WinDbg menu bar, click View, Disassembly.

In the Offset bar at the top, enter

#### nt!NtCreateFile

This shows the assembly code before and after the start of the NtCreateFile function, as shown below:



In the Offset bar at the top, enter

# nt!NtCreateFile+16

Resize this window to make the entire function visible. Drag the mouse through it to highlight the entire function, as shown below.

Offset: nt!NtCreateFile+16		
822cb2a6 cc	int	3
822cb2a7 cc	int	3
822cb2a8 cc	int	3
322cb2a9 cc	int	3
822cb2aa cc	int	3
822cb2ab cc	int	3
322cb2ac cc	int	3
322cb2ad cc	int	3
322cb2ae cc	int	3
322cb2af cc	int	3
nt!NtCreateFile:		
822cb2b0 8bff	mov	edi,edi
322cb2b2 55	push	ebp
822cb2b3 8bec	MOV	ebp,esp
822cb2b5 51	push	ecx
822cb2b6 6a00	push	0
322cb2b8 6a20	push	20h
322cb2ba 6a00	push	0
322cb2bc 6a00	push	9
822cb2be 6a00	push	0
322cb2c0 ff7530	push	dword ptr [ebp+30h]
322cb2c3 8b550c	MOV	edx,dword ptr [ebp+0Ch]
322cb2c6 ff752c	push	dword ptr [ebp+2Ch]
822cb2c9 8b4d <b>0</b> 8	mov	ecx,dword ptr [ebp+8]
322cb2cc ff7528	push	dword ptr [ebp+28h]
322cb2cf ff7524	push	dword ptr [ebp+24h]
322cb2d2 ff7520	push	dword ptr [ebp+20h]
322cb2d5 ff751c	push	dword ptr [ebp+1Ch]
822cb2d8 ff7518	push	dword ptr [ebp+18h]
822cb2db ff7514	push	dword ptr [ebp+14h]
822cb2de ff7510	push	dword ptr [ebp+10h]
822cb2e1 e80a000000	call	nt!lopCreateFile (822cb2f0)
322cb2e6 59	pop	ecx
822cb2e7 5d	pop	ebp
322cb2e8 c22c00	ret	2Ch
322cb2eb cc	int	3
822cb2ec cc	int	3
822cb2ed cc	int	3

# **Saving a Screen Image**

Make sure you have highlighted the entire function, as shown above.

On your keyboard, press the PrntScrn key.

Open Paint and paste the image in.

### YOU MUST SUBMIT WHOLE-DESKTOP IMAGES TO GET FULL CREDIT.

Save the image with a filename of "Proj 13b from YOUR NAME".

# **Online Help**

Close the Disassembly window.

In WinDbg, execute this command:

)

You see the first page of the online help, as shown below:

```
Open debugger.chm for complete debugger documentation
B[C|D|E][<bps>] - clear/disable/enable breakpoint(s)
BL - list breakpoints
BA <access> <size> <addr> - set processor breakpoint
BP <address> - set soft breakpoint
D[type][<range>] - dump memory
DT [-n|y] [[mod!]name] [[-n|y]fields]
   [address] [-1 list] [-a[]|c|i|o|r[#]|v] - dump using type information
|DV [<name>] - dump local variables
DX [-r[#]] <expr> - display C++ expression using extension model (e.g.: NatVis)
E[type] <address> [<values>] - enter memory values
G[H|N] [=<address> [<address>...]] - go
K <count> - stacktrace
KP <count> - stacktrace with source arguments
LM[k|1|u|v] - list modules
LN <expr> - list nearest symbols
|P [=<addr>] [<value>] - step over
Q - quit
R [[<reg> [= <expr>]]] - view or set registers
S[<opts>] <range> <values> - search memory
SX [{e|d|i|n} [-c "Cmd1"] [-c2 "Cmd2"] [-h] {Exception|Event|*}] - event filter
T [=<address>] [<expr>] - trace into
|V [<range>] - unassemble
version - show debuggee and debugger version
|X [<*|module>!]<*|symbol> - view symbols
? <expr> - display expression
|?? <expr> - display C++ expression
|$< <filename> - take input from a command file
Hit Enter...
Input>
```

Press Enter to see the other page.

kd> ?

# Viewing Type Information for a Structure

In WinDbg, execute this command:

#### dt nt!\_DRIVER\_OBJECT

This shows the first few lines of a driver object structure, which stores information about a kernel driver, as shown below. Notice the **DriverStart** pointer--this contains the location of the driver in memory.

```
kd> dt nt!_DRIVER_OBJECT
   +0x000 Type
                            : Int2B
   +0x002 Size
                            : Int2B
   +0x004 DeviceObject
                            : Ptr32 _DEVICE_OBJECT
                            : Uint4B
   +0x008 Flags
   +0x00c DriverStart
                            : Ptr32 Void
   +0x010 DriverSize
                            : Uint4B
   +0x014 DriverSection
                           : Ptr32 Void
   +0x018 DriverExtension
                            : Ptr32 _DRIVER_EXTENSION
                             UNICODE STRING
   +0x01c DriverName
   +0x024 HardwareDatabase : Ptr32 _UNICODE_STRING
   +0x028 FastIoDispatch
                            : Ptr32 _FAST_IO_DISPATCH
   +0x02c DriverInit
                             Ptr32
                                        long
   +0x030 DriverStartIo
                            : Ptr32
                                        void
   +0x034 DriverUnload
                            : Ptr32
                                        void
                            : [28] Ptr32
   +0x038 MajorFunction
                                             long
kd>
```

# Saving a Screen Image

Make sure the **DriverStart** pointer is visible, as shown above.

On your keyboard, press the PrntScrn key.

Open Paint and paste the image in.

#### YOU MUST SUBMIT WHOLE-DESKTOP IMAGES TO GET FULL CREDIT.

Save the image with a filename of "Proj 13c from YOUR NAME".

# **Turning in Your Project**

Email the images to: **cnit.126sam@gmail.com** with a subject line of **Proj 13 From Your Name**, replacing Your Name with your own first and last name. Send a Cc to yourself.

Posted 4-4-16 by Sam Bowne