# McMaster University

CAS 4ZP6

TEAM 9

CAPSTONE PROJECT 2013/2014

PORTER SIMULATION

# **Design Revision 0**

Authors:

Vitaliy Kondratiev - 0945220 Nathan Johrendt - 0950519 Tyler Lyn - 0948978 Mark Gammie - 0964156

Supervisor: Dr. Douglas Down

January 14, 2014

# **CONTENTS**

1	Revision History	3
2	Executive Summary 2.1 Introduction	3
3	Implementation Material       3.1 Language of Implementation	
4	Process Diagram	4
5	Dependency Diagram	6
6	Decomposition Description  6.1 Core - Simulation Core .  6.2 Core - Simulation State .  6.3 Core - Task .  6.4 Core - Task List Builder .  6.5 Core - Porter .  6.6 Core - Dispatcher .  6.7 Import - Simulation Setting .  6.8 Import - Hospital Layout Graph .  6.9 Import - Statistical Data Import .  6.10 Export - Statistical Data Export .  6.11 Logging .  6.12 GUI - Basic Settings .	7 8 9 10 11 12 12 13 14
7	Anticipated Changes	17

# 1 REVISION HISTORY

Revision #	Author	Date	Comment
	Vitaliy Kondratiev,		
	Nathan Johrendt,		
	Tyler Lyn,		
1	Mark Gammie	January 11, 2014	Revision 0 Added to repository

# **2** EXECUTIVE SUMMARY

# 2.1 Introduction

This document outlines the design decisions, style and methodology for the project of Porter Simulation to be complete for Hamilton Health Sciences.

#### 2.2 Purpose

The purpose of this document is to outline the design of each component and how they interface between each other. This document will aid the developers in the development process as well as any future maintenance required.

# 2.3 DESIGN OVERVIEW

# 3 IMPLEMENTATION MATERIAL

#### 3.1 Language of Implementation

Visual Basic in Excel will be used to interface GUI to Simulation Core module. Python Version 2.7.5 will be used for Simulation Core module and all other modules.

# 3.2 SUPPORTING TECHNOLOGY AND FRAMEWORKS

Simulation will be built on the SimPy 3.0.2 library  $\underline{\texttt{https://simpy.readthedocs.org/en/latest/}}$ . GUI will be built in Excel 2010.

# 4 PROCESS DIAGRAM




Figure 4.1: Process Diagram

# 5 DEPENDENCY DIAGRAM




Figure 5.1: Dependency Diagram

### 6 DECOMPOSITION DESCRIPTION

#### 6.1 Core - Simulation Core

Type: Module

**Purpose:** This module calls the required functions to fetch the import data, initializes the simulation and initializes processes.

**Function:** This module calls the required import modules (Simulation Settings, Hospital Layout Graph, Statistical Data Import), passes their data so that the Simulation State, Event List Builder and Dispatcher can be initialized.

#### **Interface:**

The interface for the Simulation core is the command line used to called it, defined as follows:

SimCore settings\_filename graph\_filename data\_filename

settings\_filename: the name of the file containing the simulation settings

graph\_filename: the name of the file containing the hospital layout graph

data\_filename: the name of the file containing the statistical data

**Process Steps:** This module first uses the Simulation Settings, Hospital Layout Graph and Statistical data to read in the external data. This data is used to configure other core modules in the simulation.

Once the external data is imported and the core modules are configured, the Simulation Core will begin the simulation and manage the core modules.

Data: None

**Error Handling:** Catch all on the simulation loop to report pertinent errors and to prevent unexpected termination.

**Requirement Reference:** 11.5

Critical Revision 0 Component: True

#### 6.2 Core - Simulation State

Type: Module

**Purpose:** This module's purpose is to be an interface between the simulation and its simulation state data structure.

**Function:** This module will contain functions that will be used by the simulation to perform queries on the system state data structure.

# **Interface:**

initSimulateState():

- Instantiating the simulation state with null values
- getSimulationTime():
  - Returns the current simulation time

getPorterList():

- Returns a list of the porter objects
- **Process Steps:**

Data:

**Error Handling:** 

**Requirement Reference:** 

Critical Revision 0 Component: True

6.3 CORE - TASK

Type: Module

Purpose: Provide information about a job to the porter.

**Function:** The task is declared with an origin, destination, required equipment and a priority. This information is necessary to allowing a porter to complete a job.

#### **Interface:**

getOriginLocation():

- · Returns the origin of a job
- getDestinationLocation():
  - Returns the destination of a job

getEquipment():

- Returns the equipment required for a job
- getPriority():
  - · Returns the priority of a job

getTime():

· Returns the time that the task will be requested

updatePriority():

· A process that will set the job to a higher priority after a specified amount of time has passed.

Process Steps: Tasks will be initialized once the Simulation Core shares the import modules with the Event List Builder. An initialized task will be able to provide the Dispatcher all the required information to organize a list of tasks. Also, once a task is given to a porter, the porter will then be able to start and complete a transport job.

**Data:** Transport Job Information

Error Handling: Catch any null values returned by the task's properties

Requirement Reference: None

Critical Revision 0 Component: True

#### 6.4 Core - Task List Builder

**Type:** Module

Purpose: Produces the list of tasks for the Simulation Core and Dispatcher modules to process

Function: This module populates a series of tasks following either a distribution or statistical data.

#### Interface:

addTask(origin, destination, equipment, priority, time):

• Input the origin, destination, equipment and priority of a job. Also include the time the task will be added to the Dispatcher

setTaskBuilderStats(data)

· Input the statistical or distribution data as it is required for creating meaningful data

**Process Steps:** The Task List Builder will first receive the data from the Simulation Core. This data will allow the Task List Builder to create jobs based on user specified parameters. Secondly, the Task List Builder will generate tasks and append them to the BinTree data structure, to allow for ordering, inserting and retrieval of tasks. Once a task reaches its "time" it will be added to the Dispatcher where it can be given to an available porter.

Data: Task List BinTree

Error Handling: Catch any null tasks

Requirement Reference: 8.1 (d)

Critical Revision 0 Component: True

# 6.5 Core - Porter

Type: Module

Purpose: To complete jobs provided by the dispatcher

**Function:** Completes the transport jobs assigned by the dispatcher. Unless a job is cancelled the porter will traverse through four states ('pending', 'dispatched', 'inprogress', 'complete')

#### Interface:

setStatePending(state):

- · Input the pending state
- Sets the porter's state to pending and waits to be assigned a job

#### setStateDispatched(state):

- · Input the dispatched state
- Sets the porter's state to dispatched and calculates the time between the porter's location and the job's origin

#### setStateInprogress(state):

- Input the inprogress state
- Sets the porter's state to inprogress and calculates the time between the job's origin and destination

#### setStateComplete(state):

- · Input the complete state
- Sets the porter's state to complete, records the completion time and sets the porter back to the pending state

# getAutoLocation():

- Returns the estimated location of a pending porter
- Estimates the current location of a porter based on how many minutes they have been in
- · Output the estimated location of a pending porter
- Estimates the current location of a porter based on how many minutes they have been in the pending state.

**Process Steps:** The module listens for state changes provided by the dispatcher and updates its' internal components as necessary.

Data: Stores internal data relating to its' current state.

Error Handling: Not Available

Requirement Reference: Not Available Critical Revision 0 Component: True

#### 6.6 CORE - DISPATCHER

Type: Module

Purpose: To organize pending jobs based on a weighted-value and assign them to porters

**Function:** This module orders pending jobs based off of a Dispatch Value which is computed using several parameters (Proximity Match Value, Weighted Job Priority and Appointment Factor). The pending job with the greatest Dispatch Value will be assigned to the closest available porter. Once the job is assigned to the porter the job will be considered as a dispatched job.

#### **Interface:**

assignJob(Task):

- Assigns the job with the greatest Dispatch Value to the closest available porter. getProxmityMatchValue(TaskOrigin):
  - Input the origin of a pending job
- Output a value based on how close an available porter is to a job's origin getWeightedJobPriority(TaskOrigin, TaskDestination):
  - Input the origin and destination of a pending job
  - Output a value based on the priority of the pending job

getAppointmentFactor(Task):

- Input a pending job
- Update the value for a job depending on if it was pre-scheduled or on-demand.

getDispatchValue(Task):

- · Input a pending job
- Compute the DispatchValue for a job: (ProxmityMatchValue + WeightedJobPriority \* AppointmentFactor)

**Process Steps:** All pending jobs are assessed and given a dispatch value (DV) based on the weighting and values of specified dispatch parameters.

These weights and values are determined using either the location of an available porter or the priority of a pending job.

All of the pending jobs are then ordered from greatest dispatch value to the least. When there is an available porter the pending job with the greatest dispatch value is given to the closest porter.

#### Data:

· Pending jobs

Error Handling: Not Available

Requirement Reference: Not Available

Critical Revision 0 Component: True

#### 6.7 IMPORT - SIMULATION SETTING

Type: Module

Purpose: Receives the settings data from the GUI and translates them for use by the simula-

tion core

Function: Receives data in the form of a csv and converts it to a readable format

#### **Interface:**

receiveSettings(Settings):

· Load and store setting into module

translateSettings():

• Outputs translated setting from the current loaded setting in the module

**Process Steps:** the module is called by the GUI from which it receives the settings as a csv file and stores them. Simulation Core calls the module to receive the current setting in the translated format.

**Data:** Settings

Error Handling: return NUll on incorrect settings received

Requirement Reference: Not Available

Critical Revision 0 Component: True

# 6.8 IMPORT - HOSPITAL LAYOUT GRAPH

Type: Module

**Purpose:** Receives layout data for the hospital from a .csv file and translates it for use by the simulation core.

**Function:** Interprets the data from the .csv file into a graph representing a HHS hospital transportation layout for porter movement.

#### **Interface:**

receiveLayout(Layout):

· Load and store layout into module

translateLayout():

• Outputs translated layout from the currently loaded .csv file to the module

**Process Steps:** Simulation core calls the module to receive the translated layout.

Data: Layout Graph

Error Handling: Returns NULL on incorrect settings.

Requirement Reference: Not Available
Critical Revision 0 Component: True

# 6.9 IMPORT - STATISTICAL DATA IMPORT

**Type:** Module

**Purpose:** Receives statistical data for the hospital from a .csv file and translates it for use by the simulation core.

**Function:** Interprets the data from the .csv file into statistical data and places them into variables for use by the Simulation Core.

#### **Interface:**

receiveStatistics(Statistics):

· Load and store statistics into module

translateStatistics():

• Outputs translated statistics from the currently loaded .csv file to the module

**Process Steps:** Simulation core calls the module to receive the translated statistical data variables.

Data: Statistic data variables

Error Handling: Returns NULL on incorrect settings.

Requirement Reference: Not Available

Critical Revision 0 Component: True

# 6.10 Export - Statistical Data Export

Type: Module

Purpose:

Function:
Interface:

Process Steps:

Data:

Error Handling:

Requirement Reference:

Critical Revision 0 Component: True

# 6.11 LOGGING

Type: Module

**Purpose:** 

**Function:** 

**Interface:** 

**Process Steps:** 

Data:

**Error Handling:** 

**Requirement Reference:** 

Critical Revision 0 Component: True

# 6.12 GUI - BASIC SETTINGS

Type: User Interface

Purpose: Allows the user to change the basic setting of the simulation and run the simulation

**Function:** 

Number of Porters: specify the number of porters for the simulation to run

Start Date: specify the day the simulation will run from

**Start Time:** specific time the simulation runs from **End Date:** specific time day the simulation will end

**End Time:** specific time the simulation ends

Job Distribution: users can choose from predefined distributions or base it on existing

statistical data

Job Intensity: specify the frequency of job distribution

**Correct Equipment Usage:** specify the percentage of correct equipment events **Patient Readiness:** specify the percentage of ready patients on porter arrival

Porter Wait Time: specify the time a porter waits for patient to be ready before abandoning

job

#### Interface:

Advanced Setting: proceed to Advanced Setting GUI

**Simulate:** push settings to Simulation Core **Default Settings:** reset to default values

Process Steps: Not Available

Data: Not Available

**Error Handling:** If any of the below values violates its restriction, excel will not allow the information to be sent to the simulation core.

Number of Porters: restricts the number of porters to a positive integer

**Start Date:** restricts the start date to day/month/year format

Start Time: restricts the start time to 12 or 24 hour time

**End Date:** restricts the end date to day/month/year format and checks that the date is on the same date or a later date than the start date

**End Time:** restricts the end time to 12 or 24 hour time and checks that the end time is further in the future than the start time

**Job Distribution:** user is restricted to a set series of options **Job Intensity:** user is restricted to a set series of options

Correct Equipment Usage: restricts the value between 0 and 100 percent

Patient Readiness: restricts the value between 0 and 100 percent

**Porter Wait Time:** restricts the value to a minimum of 0 **Requirement Reference:** 10.1.1, 10.1.2, 10.1.3, 10.1.4

Critical Revision 0 Component: True




Figure 6.1: Basic GUI

# 7 ANTICIPATED CHANGES

1 Change 1