

CSØ61: Machine Organization & Assembly Language Lab 6

Agenda

- 1. Presentation:
 - a. Sub-routine Review
 - b. Stacks
 - c. backing Up / Restoring Registers
 - d. Reverse Polish Notation
 - e. If Statements
 - f. Lab Descriptions
- 1. Work Time / Questions / Demos


Review Q

- Which of the following transfers the content in R2 to R1? (Multiple Correct)
 - o a) LD R1, R2
 - o b) ADD R1, R2, x0
 - o c) LDR R1, R2, #0
 - o d) AND R1, R2, R2

- Answer:
 - o b) R1 <- R2 + 0
 - o d) R1 <- R2 & R2

Stack'd


- A stack is an abstract data type with LIFO ordering!
 - Can only read/write to top of stack!
- Push Operation:
 - Push (add) a value onto the top of the stack!
 - Top of stack increases!
- Pop Operation:
 - Pop (take) a value from the top of the stack!
 - Top of stack decreases!



https://fullyunderstood.com/stack/


Stack Terms


- Top of Stack Address:
 - A memory address that refers to the element at the top of the stack!
- Base of Stack Address:
 - Pointer to the bottom of the stack!
 - Think of this like the floor!
 - Bottom of the stack is not an element.
 - Top of stack address can't be than the base address!
- Max of Stack Address:
 - o Pointer to the maximum of the stack!
 - Think of this like the ceiling!
 - Max of stack is not an element.
 - Top of stack address can't be greater than the max address!



Constrained Stack


- Our stack is constrained by some bounds!
- Overflow Error: Trying to push elements past the max address of the stack!
- Underflow Error: Trying to pop elements below the base address of the stack!






Implementing Push

- 1. Verify that the TOS (top of stack) address < MAX address!
 - a. If it is above/equal to the MAX address, print out a Stack Overflow error message and exit!
- 2. Increment the TOS address!
- 3. Write the element to the TOS address!



POP!

- Verify that the TOS address > BASE address!
 - a. If it's not, print out an underflow error message and exit!
- 2. Copy the value at the top of the stack to some destination register.
- 3. Decrement the TOS address.





- Back up registers at the start of the subroutine!
- Backing up registers means storing the register values in memory!
 - Backup registers that are used in your sub-routine logic.
 - Always always backup R7!
 - Don't backup registers that are being used as return values!

How to back up? Using a register STACK

Creating a Subroutine

- 1. Define sub-routine at remote location (e.g. x3200, x3400, etc)!
- 2. Backup registers!
 - Always backup R7!
 - Use R6 to store your register stack
 - Backup registers changed in the sub-routine!
 - Don't backup registers that are return values.
- 3. Put in your sub-routine logic code.
 - b. Code that does some task.
 - c. E.g. Store input into an array, compute a value, etc
- 4. Restore registers!
 - Restore registers in the reverse order there were backed up!
- 5. Exit out of the sub-routine (RET)!

```
.ORIG x3200
; Backup Registers
ADD R6, R6, #-1
STR R7, R6, #0
ADD R6, R6, #-1
STR R1, R6, #0
: Sub-routine logic
LD R1, UNIVERSE
ADD RO, R1, #1
: Restore registers
LDR R1, R6, #0
ADD R6, R6, #1
LDR R7, R6, #0
ADD R6. R6. #1
: Exit the sub-routine
RET
: Sub-routine Data
UNIVERSE .FILL
. END
```

Back onto a Stack

- Top of stack address will always be in R6 (e.g. xFE00)
- Subtract top of stack by 1!
- Store register value at current top of stack address!

```
ADD R6, R6, #-1
STR Rn, R6, #0 ; rn is the modified register r0 - r7
```


ADD R6, R6, #-1 STR R7, R6, #0 ADD R6, R6, #-1 STR R7, R6, #0 ADD R6, R6, #-1 STR R1, R6, #0

Restoring Registers

- After your sub-routine logic!
- Before the RET statement!
- Pop off values in the stack in the reverse order you pushed them on!

```
LDR R1, R6, #0; rn is the modified register r0 - r7 ADD R6, R6, #1
```

```
LDR R1, R6, #0
ADD R6, R6, #1
LDR R7, R6, #0
ADD R6, R6, #1
```



Routine so Far

Stack pointer decrements first!

Always store R7!

Stack pointer increments!

Reverse order!

Only need to set R6 once

```
.orig x3200
; Backup Registers
ADD R6, R6, #-1
STR R7, R6, #0
ADD R6, R6, #-1
STR R1, R6, #0
; Sub-routine logic
LDR R1, R6, #0
ADD R6, R6, #1
LDR R7, R6, #0
ADD R6, R6, #1
RET
; Sub-routine Data
.end
```

```
.ORIG x3200
AND R3, R3, x0
; Use R4 as the counter
AND R4, R4, x0
ADD R4, R4, #3
LOOP 3200
    ADD R3, R3, #15
    ADD R4, R4, #-1
    BRp LOOP 3200
END LOOP 3200
ADD R3, R3, #3
ADD R2, R1, R3
RET
. END
```

Back Up Q

Given the subroutine (on the left) with the following header, what registers should be backed up and restored?


```
; Subroutine: SUB_CONVERT_ASCII_3200
; Parameter (R1): Decimal number (0-9) to convert to ASCII
; Postcondition: Convert R1 from decimal to ASCII
; Return Value (R2): Result of conversion.
```


Answer: R7, R3 and R4

- Always backup R7!
- R3 and R4 have been modified in the subroutine.
- R2 is return value, so shouldn't be backed up.

Reverse Polish Notation

- Reverse Polish Notation (Post-fix)
 - Method of representing expressions!
 - Operator goes after numeric operands!





 $\label{lem:https://upload.wikimedia.org/wikipedia/commons/thumb/5/53/CPT-RPN-example 1.svg/600px-CPT-RPN-example 1.svg/600px-000px-CPT-RPN-example 1.svg/600px-000px-CPT-RPN-example 1.svg/600px-000px-000px-CPT-RPN-example 1.s$

If Statement

Goal: Execute IF statement if R0 is positive!
 If R0 is positive, jump to IF_START — BRP IF_START
 Otherwise, jump to IF_END — BR IF_END IF_START
 Code only executes if R0 is positive.
 Code inside if-statement IF END

If-Else

- Goal: Execute IF statement if R0 is positive, otherwise execute ELSE statement!
- If R0 is positive, jump to IF_START
- Otherwise, jump to ELSE_START
- Skip the else statement

• Why no BR over here?

```
ADD R0, R1, R2
BRp IF START
BR ELSE START
IF START
  ; Code inside if-stmt
  BR ELSE END
IF END
ELSE START
  ; Code inside else-stmt
ELSE END
```

Starter Code

- Separate stack used for backing up / restoring registers.
- Base of Stack Address
- Max of Stack Address
- Top of Stack Address
 - Starts out = BASE

```
.ORIG x3000
; Load register-backup stack
LD R6, REG STACK
: Load value stack
LD R3, STACK BASE
LD R4, STACK MAX
LD R5, STACK BASE; TOS
HALT
; Local Data
REG STACK .FILL
                  xFE00
STACK BASE .FILL xA000
STACK MAX .FILL
                  xA005
 ENID
```

Exercise 1

- Implement the stack push sub-routine!
- Test Harness: Push values (e.g. hard-coded, user-input, etc) to stack!
 - Demonstrate overflow error!

```
; Subroutine: SUB_STACK_PUSH
; Parameter (R1): The value to push onto the stack
; Parameter (R3): BASE: A pointer to the base (one less than the lowest available address) of the stack
; Parameter (R4): MAX: The "highest" available address in the stack
; Parameter (R5): TOS (Top of Stack): A pointer to the current top of the stack
; Postcondition: The subroutine has pushed (R1) onto the stack (i.e to address TOS+1).
; If the stack was already full (TOS = MAX), the subroutine has printed an overflow error message and terminated.
; Return Value: R5 ← updated TOS
```

Exercise 2

- Implement stack pop sub-routine!
 - Make sure to put the value popped into R0!
- Test Harness: Pop values (e.g. hard-coded or from user-input)
 - Demonstrate underflow error!

```
; Subroutine: SUB_STACK_POP
; Parameter (R3): BASE: A pointer to the base (<u>one less than</u> the lowest available address) of the stack
; Parameter (R4): MAX: The "highest" available address in the stack
; Parameter (R5): TOS (Top of Stack): A pointer to the <u>current</u> top of the stack
; Postcondition: The subroutine has popped MEM[TOS] off of the stack and copied it to R0.

If the stack was already empty (TOS = BASE), the subroutine has printed
an underflow error message and terminated.
; Return Values: R0 ← value popped off the stack
; R5 ← updated TOS
```

Exercise 3

- 1. Copy your push and pop sub-routine to the exercise 3 file!
- Implement a sub-routine SUB_RPN_ADDITION
 - a. Pop two values off the stack.
 - b. Add the values together.
 - c. Push result onto the stack.
- 1. Main Program:
 - b. Prompt user to enter a single-digit number.
 - Convert ASCII character to number.
 - ii. Push it onto stack (via the PUSH sub-routine)
 - c. Repeat the step above to get the second number.
 - d. Prompt user for an operator (the "+")
 - i. Can discard this input!
 - e. Call your new sub-routine SUB_RPN_ADDITION .
 - f. Pop result off from stack (via POP sub-routine)
 - g. Print out result to console (via a helper sub-routine PRINT_DIGIT)

Demo Info

- Lab Grade Breakdown:
 - 3 points for attendance.
 - 7 points for demoing (+1 bonus point demo'd before/during Friday).
 - o 3 point penalty if lab is demo'd during the next lab session.

- Tips before you demo:
 - Understand your code! (Know what each line does & the input/output)
 - Test your code! (Check for correct output and that there are no errors)