

Chapter 9: Subnetting IP Networks



Introduction to Networks

Cisco Networking Academy® Mind Wide Open™



- 9.0 Introduction
- 9.1 Subnetting an IPv4 Network
- 9.2 Addressing Schemes
- 9.3 Design Considerations for IPv6
- 9.4 Summary

Chapter 9: Objectives

Upon completion of this chapter, you will be able to:

- Explain why routing is necessary for hosts on different networks to communicate.
- Describe IP as a communication protocol used to identify a single device on a network.
- Given a network and a subnet mask, calculate the number of host addresses available.
- Calculate the necessary subnet mask in order to accommodate the requirements of a network.
- Describe the benefits of variable length subnet masking (VLSM).
- Explain how IPv6 address assignments are implemented in a business network.

Presentation_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential



9.1 Subnetting an IPv4 Network



Cisco Networking Academy® Mind Wide Open®

Network Segmentation

Reasons for Subnetting

Subnetting is the process of segmenting a network into multiple smaller network spaces called subnetworks or subnets.

- Large networks must be segmented into smaller subnetworks, creating smaller groups of devices and services to:
 - Control traffic by containing broadcast traffic within each subnetwork.
 - Reduce overall network traffic and improve network performance.


Communication Between Subnets


- A router is necessary for devices on different networks and subnets to communicate.
- Each router interface must have an IPv4 host address that belongs to the network or subnet that the router interface is connected.
- Devices on a network and subnet use the router interface attached to their LAN as their default gateway.




Planning the Network










Planning requires decisions on each subnet in terms of size, the number of hosts per subnet, and how host addresses will be assigned.



Subnetting an IPv4 Network

Basic Subnetting

- Borrowing Bits to Create Subnets
- Borrowing 1 bit $2^1 = 2$ subnets




Subnetting an IPv4 Network Subnets in Use

Subnets in Use

Subnet 0

Network 192.168.1.0-127/25

192.168.1.0/25



192.168.1.128/25

Subnet 1

Network 192.168.1.128-255/25

Address Range for 192.168.1.0/25 Subnet

Network Address

192. 168. 1. 0 000 0000 = 192.168.1.0

First Host Address

192. 168. 1. 0 000 0001 = 192.168.1.1

Last Host Address

192. 168. 1. 0 111 1110 = 192.168.1.126

Broadcast Address

192. 168. 1. 0 111 1111 = 192.168.1.127

Address Range for 192.168.1.128/25 Subnet

Network Address

192. 168. 1. 1 000 0000 = 192.168.1.128

First Host Address

192. 168. 1. 1 000 0001 = 192.168.1.129

Last Host Address


192. 168. 1. 1 111 1110 = 192.168.1.254

Broadcast Address

192. 168. 1. 1 111 1111 = 192.168.1.255

Subnetting an IPv4 Network


Subnetting Formulas



Subnetting an IPv4 Network

Creating 4 Subnets

Borrowing 2 bits to create 4 subnets. $2^2 = 4$ subnets



Presentation_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential



Creating Eight Subnets

Borrowing 3 bits to Create 8 Subnets. $2^3 = 8$ subnets

	Network	192.	168.	1.	000	0 0000	192.168.1.1
Net 0	Fist	192.	168.	1.	000	0 0001	192.168.1.1
	Last	192.	168.	1.	000	1 1110	192.168.1.30
	Broadcast	192.	168.	1.	000	1 1111	192.168.1.31
	Network	192.	168.	1.	001	0 0000	192.168.1.32
Net 1	Fist	192.	168.	1.	001	0 0001	192.168.1.33
	Last	192.	168.	1.	001	1 1110	192.168.1.62
	Broadcast	192.	168.	1.	001	1 1111	192.168.1.63
	Network	192.	168.	1.	010	0 0000	192.168.1.64
Net 2	Fist	192.	168.	1.	010	0 0001	192.168.1.65
	Last	192.	168.	1.	010	1 1110	192.168.1.94
	Broadcast	192.	168.	1.	010	1 1111	192.168.1.95
	Network	192.	168.	1.	010	0 0000	192.168.1.96
				-	010	0 0001	192.168.1.97
Net 3	Fist	192.	168.	1.	010	0 0001	132. 100. 1.37
Net 3	Fist Last	192.	168.	1.	010	1 1110	192.168.1.126
Net 3							




Creating Eight Subnets (Cont.)

Net 4 Net work Fist 192. 168. 1. 100 0 0000 192.168.1.1 Last 192. 168. 1. 100 1 1110 192.168.1.1 Broadcast 192. 168. 1. 100 1 1111 192.168.1.1 Network 192. 168. 1. 101 0 0000 192.168.1.1 Net 5 Fist 192. 168. 1. 101 0 0001 192.168.1.1 Last 192. 168. 1. 101 0 0001 192.168.1.1	129 158 159
Net 4 Fist 192. 168. 1. 100 0 0001 192.168.1.1 Last 192. 168. 1. 100 1 1110 192.168.1.1 Broadcast 192. 168. 1. 100 1 1111 192.168.1.1 Network 192. 168. 1. 101 0 0000 192.168.1.1 Net 5 Fist 192. 168. 1. 101 0 00001 192.168.1.1 Last 192. 168. 1. 101 1 1110 192.168.1.1	129 158 159
Net 4 Last 192. 168. 1. 100 1 1110 192.168.1.1 Broadcast 192. 168. 1. 100 1 1111 192.168.1.1 Network 192. 168. 1. 101 0 0000 192.168.1.1 Net 5 Fist 192. 168. 1. 101 0 0001 192.168.1.1 Last 192. 168. 1. 101 1 1110 192.168.1.1	158 159
Broadcast 192. 168. 1. 100 1 1111 192.168.1.1 Network 192. 168. 1. 101 0 0000 192.168.1.1 Net 5 Fist 192. 168. 1. 101 0 0001 192.168.1.1 Last 192. 168. 1. 101 1 1110 192.168.1.1	159
Network 192. 168. 1. 101 0 0000 192.168.1.1 Net 5 Fist 192. 168. 1. 101 0 0001 192.168.1.1 Last 192. 168. 1. 101 1 1110 192.168.1.1	
Net 5 Fist 192. 168. 1. 101 0 0001 192.168.1.1 Last 192. 168. 1. 101 1 1110 192.168.1.1	160
Last 192. 168. 1. 101 1 1110 192.168.1.1	
Last 192. 168. 1. 101 1 1110 192.168.1.1	161
D I 1 100 150 1 101 1 100 100 100 1	190
Broadcast 192. 168. 1. 101 1 1111 192.168.1.1	191
Network 192. 168. 1. 110 0 0000 192.168.1.1	192
Net 6 Fist 192. 168. 1. 110 0 0001 192.168.1.1	193
Last 192. 168. 1. 110 1 1110 192.168.1.2	222
Broadcast 192. 168. 1. 110 1 1111 192.168.1.2	223
Network 192. 168. 1. 111 0 0000 192.168.1.2	224
Net 7 Fist 192. 168. 1. 111 0 0001 192.168.1.2	225
Last 192. 168. 1. 111 1 1110 192.168.1.2	254
Broadcast 192. 168. 1. 111 1 1111 192.168.1.2	255

Subnetting an IPv4 Network

Creating Eight Subnets (Cont.)





Subnetting Based on Host Requirements

Two considerations when planning subnets:

- Number of subnets required
- Number of host addresses required

Formula to determine number of usable hosts: 2^n-2


- 2ⁿ (where n is the number of remaining host bits) is used to calculate the number of hosts.
- -2 (The subnetwork ID and broadcast address cannot be used on each subnet.)

resentation_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential

Subnetting Network-Based Requirements

Calculate the number of subnets:


- 2ⁿ (where n is the number of bits borrowed)
- Subnet needed for each department.



Determining the Subnet Mask

Subnetting To Meet Network Requirements

- Balance the required number of subnets and hosts for the largest subnet.
- Design the addressing scheme to accommodate the maximum number of hosts for each subnet.
- Allow for growth in each subnet.



Determining the Subnet Mask

Subnetting To Meet Network Requirements

Subnets and Addresses

```
10101100.00010000.000000 00.0000000 172.16.0.0/22

0 10101100.00010000.000000 00.0000000 172.16.0.0/26
1 10101100.00010000.000000 00.10000000 172.16.0.64/26
2 10101100.00010000.000000 00.110000000 172.16.0.128/26
3 10101100.00010000.000000 01.10000000 172.16.0.192/26
4 10101100.00010000.000000 01.00000000 172.16.1.0/26
5 10101100.00010000.000000 01.01000000 172.16.1.64/26
6 10101100.00010000.000000 01.10000000 172.16.1.128/26

Nets 7 - 14 not shown


15 10101100.00010000.000000 11.10000000 172.16.3.128/26
16 10101100.00010000.000000 11.110000000 172.16.3.128/26
```



Benefits of Variable Length Subnet Masking

Traditional Subnetting Wastes Addresses


- Traditional subnetting Uses the same number of addresses is allocated for each subnet.
- Subnets that require fewer addresses have unused (wasted) addresses; for example, WAN links only need two addresses.






Variable Length Subnet Masks (VLSM)

- The variable-length subnet mask (VLSM) or subnetting a subnet provides more efficient use of addresses.
- VLSM allows a network space to be divided in unequal parts.
- Subnet mask varies, depending on how many bits have been borrowed for a particular subnet.
- Network is first subnetted, and then the subnets are resubnetted.




Benefits of Variable Length Subnet Masking Basic VLSM



Benefits of Variable Length Subnet Masking VLSM in Practice

- Using VLSM subnets, the LAN and WAN segments in example below can be addressed with minimum waste.
- Each LANs will be assigned a subnet with /27 mask.
- Each WAN link will be assigned a subnet with /30 mask.





VLSM Subnetting of 192.168.20.0 /24

	/27 Network	Hosts
Blda A	.0	.130
Bldg B	.32	.3362
Bldg C	.64	.6594
Bldg D	.96	.97126
Unused	.128	.129158
Unused	.160	.161190
Unused	.192	.193222
	.224	.225254

	/30 Network	Hosts
WAN R1-R2	.224	.225226
WAN R2-R3	.228	.229230
WAN R3-R4	.232	.233234
Unused	.236	.237238
Unused	.240	.241242
Unused	.244	.245246
Unused	.248	.249250
Unused	.252	.253254



9.2 Addressing Schemes



Cisco Networking Academy® Mind Wide Open®

Structured Design

Planning to Address the Network

Allocation of network addresses should be planned and documented for the purposes of:

- Preventing duplication of addresses
- Providing and controlling access
- Monitoring security and performance

Client addresses – Usually dynamically assigned using the Dynamic Host Configuration Protocol (DHCP).

Sample Network Addressing Plan

Network: 192.168.1.0/24				
Use	First	Last		
Host Devices	.1	.229		
Servers	.230	.239		
Printers	.240	.249		
Intermediary Devices	.250	.253		
Gateway (router LAN interface)	.254			



9.3 Design Considerations for IPv6




Cisco Networking Academy® Mind Wide Open®


Subnetting an IPv6 Network

Subnetting Using the Subnet ID

An IPv6 Network Space is subnetted to support hierarchical, logical design of the network








Subnetting an IPv6 Network

Subnetting into the Interface ID

IPv6 bits can be borrowed from the interface ID to create additional IPv6 subnets.





9.3 Summary



Cisco Networking Academy® Mind Wide Open®

Chapter 9: Summary

In this chapter, you learned that:

- Subnetting is the process of segmenting a network, by dividing it into multiple smaller network spaces.
- Subnetting a subnet, or using VLSM, was designed to avoid wasting addresses.
- IPv6 address space is subnetted to support the hierarchical, logical design of the network.
- Size, location, use, and access requirements are all considerations in the address planning process.
- IP networks must be tested to verify connectivity and operational performance.

resentation_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential

Cisco | Networking Academy® | Mind Wide Open™