

Composed by Vladimir Ulogov

BUND standard library reference

This book serves as a reference guide for the BUND functions (or "words") defined in standard library.

Referencing 82 functions.



Introduction

I will introduce a new concatenative programming language called BUND in this work. What is a concatenative language, and how does it differ from the programming languages you're likely familiar with? You're likely acquainted with applicative programming languages like Python, C, or Java. Alternatively, you may have discovered functional programming languages such as Lisp, Haskell, or ML, other examples of applicative programming languages. This category is defined by the way functions are viewed and handled. In applicative languages, a function is treated as a mathematical primitive that computes based on passed arguments and returns a value. In contrast, concatenative programming languages pass a data context from one function to another, external to the function itself. While the stack is the most common method for passing such context, there are concatenative languages that don't utilize a stack. Passing data context enables the concatenation of data processing. Concatenative languages are less known in the software development communities, but you might have heard of languages such as Forth, PostScript, and Factor.

The stack is utilized in many but not all concatenative languages, while applicative languages often use stack structures internally to aid computation. Stacks are indispensable for recursive computation, passing return values computed by functions and storing references to an execution context. What distinguishes concatenative stack-based languages from applicative counterparts is the use of the stack for input data, computational context, and result storage. In essence, everything in concatenative stack-based languages is stored in the stack. In some cases, computational instructions are also stored alongside data on the stack. Since everything, including the context for functions, is stored on

BUND standard Library reference

the stack, functions in concatenative stack-based languages do not have conventional arguments. Although they function as such, they are often referred to as "words," as was defined in one of the first concatenative languages to gain popularity - Forth. Another characteristic of concatenative stack-based languages is their reliance on the stack's Last In, First Out (LIFO) nature. They often employ Reverse Polish Notation (RPN).

So, what will might surprise you in concatenative stack-based language?


- We already mentioned that the functions do not have arguments and no dedicated return value. All input and output data passed to and from the function are passed through the stack.
- You are responsible for ensuring the correct order of the values passed in the data context to the function, as this context is on the stack.
- You are also responsible for interpreting return data placed on the stack. Unlike in the functional language paradigm, there could be more than one return value, depending on your function (or "word").
- There are no variables. All data are stored on the stack.
- There are no global constants, variables, or values. Everything is on the stack.
- Due to the LIFO nature of the stack, you will deal with RPN, although BUND offers you an ability to creae a stack with FIFO policy.

What exactly is a Bund?

The BUND programming language is a member of the concatenative language family. A notable characteristic of concatenative languages is the presence of a computational context external to the code itself. All computations carried out by the functions, referred to as "words" in concatenative language terminology, are performed over this external context. This differs from the concepts commonly encountered in applicative languages, where function parameters are part of the function context. The computational context is typically structured as a Last In, First Out (LIFO) stack in concatenative languages. However, BUND distinguishes itself from most concatenative languages by having a more sophisticated concept of the computational context.


Circular data stack

Instead of using simple LIFO stacks, BUND stores data in multiple named circular buffers, also known as stacks. When you push data to the stack, the circular buffer expands, and when you pull or consume data from the stack, the buffer contracts. While the data buffer is circular, there is always a pointer that refers to the value located on top of the stack. Although you can rotate the buffer in the left or right direction, data is consumed in a single direction only.



Stack-of-stacks references

The next level of abstraction is a circular stack that refers to named data stacks while functioning just like a standard data stack in all other aspects. The stack referred to by the "top of the stack" reference is considered the "current stack," and all operations are by default performed within this data context. When creating a new stack, the reference moves to the top of the stack. When positioning a named stack to become the current stack, the buffer rotates to bring the required stack to the proper position at the "top of the stack."



BUND standard Library reference

Workbench

The workbench, an integral component of the BUND virtual machine, is a circular stack that temporarily holds and transfers values between computations conducted in various data contexts. Despite its functional significance, this circular stack does not carry a specific name.

What does the word "bund" mean?

The term "Bund" comes from German or Yiddish and can be translated as "association," "bundle," or "bunch." Throughout history, this word has been utilized in various contexts. In the context of the multi-stack concatenative programming language, "Bund" refers to the ability of the BUND language to integrate distinct, originally separate data and computation contexts into a unified computational process aimed at achieving a common goal.

¹singular Bundes, plural Bunde

BUND standard Library reference

How to use the reference?

denerally, the reference does not require details on now you present
information about your topic, but I still feel obligated to explain the
structure of the function reference page.
☐ At the top of the page, you will find an optional warning indicating
that using this function requires additional caution from the devel
oper.
☐ Next, a list will provide details about where the function is imple-
mented.
\square Following that, there is a description of the operations performed by
the function.
☐ Afterward, you will see a concise outline of the function's algorithm
highlighting how it interacts with the stack or workbench, including
its inputs and outputs.
☐ Finally, a code snippet will demonstrate how to utilize the function
effectively.




Figure 1: Here is your guide to the common Standard Library reference page.

BUND Standard library reference

Although language design is often simple, elegant, and thoughtfully executed, there is room for greater practicality. A language's core becomes truly functional and valuable to developers only when accompanied by a standard library of useful functions. These functions provide essential tools for performing operations and manipulating data effectively. Moreover, BUND shares several characteristics with other concatenative languages.

Memorize

All run-time functionality of the BUND implemented in standard library.

When I say "all," I mean that every aspect of the functionality extends beyond just implementing the BUND parser and core logic. The BUND standard library is situated across multiple locations. Although this may initially be a design flaw, I had deliberate reasons for structuring the standard library this way.

Info The Rust crate rust_multistack encompasses all the logic associated with stack operations. Additionally, it incorporates elements of the standard library that pertain specifically to these operations. Features include data swapping on the stack, data duplication, removal of data, stack rotation, creation of stacks, and other related functionalities. ☐ The Rust crate *rust_multistackvm* is a foundational implementation of the BUND virtual machine. Although different tools and interpreters may facilitate access to BUND, the core logic of the BUND language remains intact within this crate. This encompasses data manipulation and conversion, application logic, mathematical operations, lambda function processing, and all other essential features. The Bund runtime serves as the interpreter for the Bund programming language. It encompasses implementing all standard library functions and facilitating user-related features and controls.

Execute code snippet in the BUND debugger - debug

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime Execute code snippet inside BUND debugger

```
    function Debug_Shell()
    ⇒ Bund debugger
    Snippet ← current stack
    if Snippet = None then
    return Error("Stack is too shallow")
    Bund_Debugger(Snippet)
```

```
//
"2 2 + println" debug
```

Arguments passed via CLI for script and shell subcommands - args

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

Users can pass arguments to the script and shell subcommands after --. For example, to pass arguments to the shell subcommand, you would use:

```
bund shell -- "Argument1" 2 3
```

The "word" args will return to the top of the stack list containing the passed arguments.

```
    function function-name()
    Return passed arguments (if any)
    current stack ← ARGS
```

```
//
// Printing passed arguments
// bund sctipt --stdin -- 1 2 3
//
args println
// Will output [1:: 2:: 3]
```

Load and execute scripts stored as bootstrap scripts in the WORLD file - bootstrap



Scripts executed from the external file will alter current VM state

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

With the help of the *save* function, users can store the current state of the BUND VM into an external file. This file, called the "WORLD" file, contains a frozen version of the scripts that could be executed during bootstrap phase or by calling a *bootstrap* function. The *bootstrap* function, which can be used as "WORLD_file" bootstrap, will load content from this file and execute stored bootstrap scripts.

```
    function BUND-BOOTSTRAP()
    Load and execute bootstrap scripts from the WORLD file
    Filename ← current stack
    if Value = None then
    return Error("Stack is too shallow")
    BUND_BOOTSTRAP(Filename)
```

```
// Load and execute scripts from file _state.world_
    "state" bootstrap
```

Evaluate BUND code snippet taken as string from stack - bund.eval

Defined in
□ rust_multistack□ rust_multistackvm☑ bund runtime

This function is tasked with the evaluation of a code snippet that is retrieved from a string stored in the stack. The process involves standard error-handling mechanisms to manage any issues that may arise during execution. It is crucial to highlight that this function does not instantiate a new virtual machine."

```
    function Bund-Eval()
    Evaluate bund code snippet
    Snippet ← current stack
    if Snippet = None then
    return Error("Stack is too shallow")
    Bund_Eval(Snippet)
```

```
//
// Evaluate code snippet from the sting stored in the
stack
//
"2 2 +" bund.eval
// Leaves 42 on the stack
1
2
5
```

Evaluate BUND code snippet taken from the file. The name of the file is taken as string from stack - bund.eval-file

Defined in
□ rust_multistack□ rust_multistackvm☑ bund runtime

This function is responsible for the evaluation of a code snippet that is extracted from a string loaded from a specified file. The name of this file is derived from a string that is stored in the stack . All errors encountered during the execution of this function are managed using standard error-handling procedures. It is important to note that this function does not instantiate a new virtual machine.

```
    function BUND-EVAL-FILE()
    Evaluate bund code snippet
    Snippet ← Call("Read", [current stack])
    if Snippet = None then
    return Error("Stack is too shallow")
    BUND_EVAL(Snippet)
```

```
//
// Evaluate code snippet stored in the file
2
//
"helloworld.bund" bund.eval-file
// Prints "Hello World!"
5
```

Evaluate BUND code snippet taken from the file. The name of the file is taken as string from workbench - bund.eval-file.

Defined in
□ rust_multistack□ rust_multistackvm☑ bund runtime

This function is responsible for the evaluation of a code snippet that is extracted from a string loaded from a specified file. The name of this file is derived from a string that is stored within the workbench environment. All errors encountered during the execution of this function are managed using standard error-handling procedures. It is important to note that this function does not instantiate a new virtual machine.

```
    function BUND-EVAL-FILE-DOT()
    Evaluate bund code snippet
    Snippet ← Call("Read", [workbench])
    if Snippet = None then
    return Error("Workbench is too shallow")
    BUND_EVAL(Snippet)
```

```
//
// Evaluate code snippet stored in the file
2
//
"helloworld.bund" . bund.eval-file.
// Prints "Hello World!"
5
```

Evaluate BUND code snippet taken as string from workbench - bund.eval.

Defined in
□ rust_multistack□ rust_multistackvm☑ bund runtime

This function is tasked with the evaluation of a code snippet that is retrieved from a string stored in the workbench. The process involves standard error-handling mechanisms to manage any issues that may arise during execution. It is crucial to highlight that this function does not instantiate a new virtual machine."

```
    function Bund-Eval-from-Workbench()
    Evaluate bund code snippet
    Snippet ← workbench
    if Snippet = None then
    return Error("Workbench is too shallow")
    Bund_Eval(Snippet)
```

```
//
// Evaluate code snippet from the sting
// dynamically created and stored in the workbench
//
"2 " "2 +" + . bund.eval.
// Leaves 42 on the stack
```

Clear current stack - clear



```
Defined in

✓ rust_multistack

□ rust_multistackvm
□ bund runtime
```

This function clears out all data from the current stack

Clear named stack - clear_in

Danger

This is destructive operation with stack.

Defined in ✓ rust_multistack ☐ rust_multistackvm ☐ bund runtime

This function clears out all data from the named stack, taking the name of the stack from current stack

```
    function CLEAR_IN()
    Clearing named stack
    Name ← current stack
    if Name = None then
    return Error("Stack is too shallow")
    CLEAR_STACK(Name)
```

```
//
// Remove all data from named stack
//
@main
@StackName
1 2 3
@main
    :StackName clear_in
// After calling clear_in, stack with name "StackName"
// will have no data
12 3
10
```

Taking value from stack and convert it to boolean - convert.to_bool

Defined in □ rust_multistack ☑ rust_multistackvm □ bund runtime

Taking value from the stack, converting to the BOOL and pushing result to the stack

```
    function Convert_To_Bool()
    Converting Value to Boolean
    Value ← current stack
    if Value = None then
    return Error("Stack is too shallow")
    current stack ← Value::conv(BOOL)
```

```
//
// Converting data in stack to string
//
:TRUE convert.to_bool

TRUE == {
    "Conversion is succesful"
    println
} if
1
2
2
3
3
4
5
6
7
8
```

Taking value from workbench and convert it to boolean - convert.to_bool.

Defined in □ rust_multistack ☑ rust_multistackvm □ bund runtime

Taking value from the workbench, converting to the BOOLEAN and pushing result to the workbench

```
    function Convert_To_Bool_In_Workbench()
    Converting Value to Boolean
    Value ← workbench
    if Value = None then
    return Error("Workbench is too shallow")
    workbench ← Value::conv(BOOL)
```

```
1 . convert.to_bool. take
TRUE == {
    "Conversion is succesful"
    println
} if
1
2
2
5
```

Taking value from stack and convert it to float - convert.to_float

Defined in □ rust_multistack ✓ rust_multistackvm □ bund runtime

Taking value from the stack, converting to the FLOAT and pushing result to the stack

```
    function Convert_To_Float()
    Converting Value to Float
    Value ← current stack
    if Value = None then
    return Error("Stack is too shallow")
    current stack ← Value::conv(FLOAT)
```

```
//
// Converting data in stack to string
//
42 convert.to_float
42.0 == {
    "Conversion is succesful"
    println
} if

1
1
2
4
6
7
8
```

Taking value from workbench and convert it to float - convert.to float.

Defined in □ rust_multistack ☑ rust_multistackvm □ bund runtime

Taking value from the workbench, converting to the FLOAT and pushing result to the workbench

```
    function Convert_To_Float_In_Workbench()
    Converting Value to String
    Value ← workbench
    if Value = None then
    return Error("Workbench is too shallow")
    workbench ← Value::conv(FLOAT)
```

```
42 . convert.to_string. take
42.0 == {
    "Conversion is succesful"
    println
} if
1
2
2
5
```

Taking value from stack and convert it to int - convert.to_int

Defined in □ rust_multistack ✓ rust_multistackvm □ bund runtime

Taking value from the stack, converting to the INT and pushing result to the stack

```
    function Convert_To_Integer()
    Converting Value to Integer
    Value ← current stack
    if Value = None then
    return Error("Stack is too shallow")
    current stack ← Value::conv(INT)
```

```
//
// Converting data in stack to int
//
TRUE convert.to_int
1 == {
    "Conversion is succesful"
    println
} if
```

Taking value from workbench and convert it to int - convert.to_int.



Taking value from the workbench, converting to the INT and pushing result to the workbench

```
    function Convert_To_Integer_In_Workbench()
    Converting Value to Integer
    Value ← workbench
    if Value = None then
    return Error("Workbench is too shallow")
    workbench ← Value::conv(INT)
```

```
42.0 . convert.to_int. take
42 == {
    "Conversion is succesful"
    println
} if
2
```

Taking value from stack and convert it to list - convert.to_list

Defined in □ rust_multistack ✓ rust_multistackvm □ bund runtime

Taking value from the stack, converting to the LIST and pushing result to the stack

```
    function Convert_To_List()
    Converting Value to List
    Value ← current stack
    if Value = None then
    return Error("Stack is too shallow")
    current stack ← Value::conv(LIST)
```

```
//
// Converting data in stack to list
//
pair :
    41 42
; convert.to_list
[ 41 42 ] == {
    "Conversion is succesful"
    println
} if
1
1
2
2
3
3
6
6
6
7
7
10
```

Taking value from workbench and convert it to list - convert.to_list.

Defined in □ rust_multistack ☑ rust_multistackvm □ bund runtime

Taking value from the workbench, converting to the LIST and pushing result to the workbench

```
    function Convert_To_List_In_Workbench()
    Converting Value to List
    Value ← workbench
    if Value = None then
    return Error("Workbench is too shallow")
    workbench ← Value::conv(STRING)
```

```
pair :
    41 42
; . convert.to_list.
[ 41 42 ] ==. {
    "Conversion is succesful"
    println
} if
1
4
7
```

Taking value from stack and convert it to matrix - convert.to_matrix

Defined in □ rust_multistack ✓ rust_multistackvm □ bund runtime

Taking value from the stack, converting to the MATRIX and pushing result to the stack

```
    function Convert_To_Matrix()
    Converting Value to Matrix
    Value ← current stack
    if Value = None then
    return Error("Stack is too shallow")
    current stack ← Value::conv(MATRIX)
```

```
//
// Converting data in stack to matrix
//
[
  [ 1 2 3 ]
  [ 4 5 6 ]
] convert.to_matrix dup
"Size of matrix " print len println
1
1
2
3
6
7
8
```

Taking value from workbench and convert it to matrix - convert.to matrix.

Defined in □ rust_multistack ☑ rust_multistackvm □ bund runtime

Taking value from the workbench, converting to the MATRIX and pushing result to the workbench

```
    function Convert_To_Matrix_In_Workbench()
    Converting Value to Matrix
    Value ← workbench
    if Value = None then
    return Error("Workbench is too shallow")
    workbench ← Value::conv(MATRIX)
```

Taking value from stack and convert it to string - convert.to_string

Defined in □ rust_multistack ☑ rust_multistackvm □ bund runtime

Taking value from the stack, converting to the STRING and pushing result to the stack

```
    function Convert_To_String()
    Converting Value to String
    Value ← current stack
    if Value = None then
    return Error("Stack is too shallow")
    current stack ← Value::conv(STRING)
```

```
//
// Converting data in stack to string
//
42 convert.to_string
"42" == {
    "Conversion is succesful"
    println
} if
1
2
3
4
6
7
8
```

Taking value from workbench and convert it to string - convert.to_string.

Defined in □ rust_multistack ✓ rust_multistackvm □ bund runtime

Taking value from the workbench, converting to the STRING and pushing result to the workbench

```
    function Convert_To_String_In_Workbench()
    Converting Value to String
    Value ← workbench
    if Value = None then
    return Error("Workbench is too shallow")
    workbench ← Value::conv(STRING)
```

```
42 . convert.to_string.
  "42" ==. {
    "Conversion is succesful"
    println
} if
1
2
2
5
```

Taking value from stack and convert it to textbuffer - convert.to textbuffer

Defined in □ rust_multistack ✓ rust_multistackvm □ bund runtime

Taking value from the stack, converting to the TEXTBUFFER and pushing result to the stack

```
    function Convert_To_Textbuffer()
    Converting Value to Textbuffer
    Value ← current stack
    if Value = None then
    return Error("Stack is too shallow")
    current stack ← Value::conv(TEXTBUFFER)
```

```
//
// Converting data in stack to textbuffer
//
"Hello"
convert.to_textbuffer
"WSorld",
"!",
println
// And printing Hello World!
```

Taking value from workbench and convert it to textbuffer - convert.to_textbuffer.

Defined in □ rust_multistack ✓ rust_multistackvm □ bund runtime

Taking value from the workbench, converting to the TEXTBUFFER and pushing result to the workbench

```
    function Convert_To_Textbuffer_In_Workbench()
    Converting Value to Textbuffer
    Value ← workbench
    if Value = None then
    return Error("Workbench is too shallow")
    workbench ← Value::conv(TEXTBUFFER)
```

```
// Creating message in TEXTBUFFER

"Hello" .
   convert.to_textbuffer.
    "World" +.
   take println
// And printing Hello World!
1
2
3
4
5
```

Return name of current stack to current stack - current

Defined in ✓ rust_multistack □ rust_multistackvm □ bund runtime Returns the name of current stack to current stack

```
1: function CURRENT()
2: ▷ Returns the name of current stack to stack
3: Name ← VM::current_stack_name()
4: if Name = None then
5: return Error("Can not detect current stack name")
6: current stack ← Name

///
// Prints the name of current stack
2
//
current println
4
```

Display information about host - debug.display_hostinfo

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

Display information aout current host on which you are executing BUND code

- 1: **function** Debug_Display_Hostinfo()
- 2: Display current Host information
- 3: DEBUG_DISPLAY_HOSTINFO()

```
//
debug.display_hostinfo
```

Display data stored in current stack - debug.display_stack

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

Display the data stored into the current stack to the standard output. This debug command doesn't change stack state and stored values.

- 1: **function** Debug_Display_Stack()
- 2: ▷ Display stack state
- 3: Debug_Display_Stack()

```
//
debug.display_stack 1
2
```

Display data stored in workbench - debug.display_workbench


Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

Display the data stored into the workbench to the standard output. This debug command doesn't change workbench state and stored values.

- 1: **function** Debug_Display_Workbench()
- 2: ▷ Display Workbench State
- 3: Debug_Display_Workbench()

```
//
debug.display_workbench 1
2
```

Drop into a debug shell - debug.shell



// You can exit from debug.shell by pressing Ctrl-D

Decoding string from stack from BASE64 - decode.base64

Defined in □ rust_multistack □ rust_multistackvm □ bund runtime

Taking data in BASE64 from the stack and decoding it. Return decoded data to the stack.

```
1: function DECODE-BASE64()
2: ▷ Decoding from BASE64
3: Data ← current stack
4: if Data = None then
5: return Error("Stack is too shallow")
6: current stack ← Call("Decode_Base64", [Data])
```

```
//
// Encode and Decode data in BASE64
//
"Hello world!" encode.base64 decode.base64 println
// Prints "Hello world!"
5
```

Decoding string from workbench from BASE64 - decode.base64.


Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

Taking data in BASE64 from workbench and decoding it. Return decoded data to the workbench.

```
    function DECODE-BASE64-WORKBENCH()
    Decoding from BASE64
    Data ← workbench
    if Data = None then
    return Error("Workbench is too shallow")
    workbench ← Call("Decode_Base64", [Data])
```

```
//
// Encode and Decode data in BASE64
//
"Hello world!" . encode.base64. decode.base64. take
println
// Prints "Hello world!"
5
```

Drop element from the stack - drop




Defined in ✓ rust_multistack □ rust_multistackvm □ bund runtime

This function takes a single value from the top of current stack and discards it.

Drop the last value in the named stack - drop_in





Remove stack with all data - drop_stack



```
Defined in

✓ rust_multistack


☐ rust_multistackvm
☐ bund runtime

Drop named stack.
```

```
1: function DROP_STACK()
2: ▷ Drop the stack
3: Name ← current stack
4: if Value = None then
5: return Error("Stack is too shallow")
6: DROPSTACK(Name)


//
// Drop stack "TheStack"
//
:TheStack drop_stack
// Now stack _TheStack_ doesn't exists
```

Duplicate multiple values in the current stack - dup_many



```
1: function Dup_Many()
        ▷ Duplicate multiple values
2:
        N \leftarrow current stack
3:
       Name ← VM::current_stack_name()
4:
      while N >= 0 do
5:
             Value \leftarrow current stack
6:
             current stack ← Call("Dup", [N, Name, Value])
7:
            N \leftarrow N - 1
8:
//
// Duplicate data in stack
                                                                 3
42 41 2 dup many
// Now we have 42, 42, 41, 41 in stack
                                                                 5
```


Duplicate multiple values in the named stack - dup_many_in



```
1: function Dup_Many_In()
        ▷ Duplicate multiple items in the named stack
2:
        Name \leftarrow current stack
3:
        Name \leftarrow current stack
4:
5:
        if Name = None then
              return Error("Stack is too shallow")
6:
        if N = None then
7:
              return Error("Stack is too shallow")
8:
        while N >= 0 do
9:
10:
              Value \leftarrow Name stack
              Name\ stack \leftarrow Call("Dup", [N, Name, Value])
11:
              N \leftarrow N - 1
12:
```

```
@main
@StackName
    1 2 3
@main
    :StackName 3 dup_many_in
    // Duplicate all three values in
    // stack "StackName"
    7
```

Duplicate single value in the current stack - dup_one



```
1: function DUP_ONE()
2: ▷ Duplicate value
3: Value ← current stack
4: Name ← VM::current_stack_name()
5: current stack ← Call("Dup", [1, Name, Value])

// Duplicate data in stack
// dup_one
// Now we have 42, 42 in stack
```

Duplicate single value in the named stack - dup_one_in

Defined in rust_multistack rust_multistackvm bund runtime

Description of function

Duplicate single value in the named stack, when name of the stack is reading from current stack

```
1: function Dup One in()
        ▷ Duplicate value
2:
       Name \leftarrow current stack
3:
        Value \leftarrow current stack
4:
        stack Name ← Call("Dup", [1, Name, Value])
5:
//
// Duplicating single value from stack "A"
//
@A 42
@main
  :A dup one in
// Now in stack A we have 42, 42
                                                                7
```

Encoding string from stack into BASE64 - encode.base64

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime Taking data from the stack and encode it into BASE64

```
    function ENCODE-BASE64()
    Encoding to BASE64
    Data ← current stack
    if Data = None then
    return Error("Stack is too shallow")
    current stack ← Call("Encode_Base64", [Data])
```

```
//
// Encoding string "Hello world!" to BASE64

//
"Hello world!" encode.base64

// Returns to stack "FQAAAAAAABJRy1UdDF1YXV1RUxUcjF50VA5V1QA0Dn6XT950
```

Encoding string from workbench into BASE64 - encode.base64.

Defined in □ rust_multistack □ rust_multistackvm ✓ bund runtime

Taking data from workbench and encode it into BASE64. Put result to workbench

```
1: function ENCODE-BASE64()
2: ▷ Encoding to BASE64
3: Data ← workbench
4: if Data = None then
5: return Error("Stack is too shallow")
6: workbench ← Call("Encode_Base64", [Data])
```

```
//
// Encoding string "Hello world!" to BASE64

//
"Hello world!" . encode.base64. take
// Returns to stack "FQAAAAAAABJRy1UdDF1YXV1RUxUcjF50VA5V1QA0Dn6XT950
```

Make named stack current, create if stack doesn't exists - ensure_stack

Defined in	
✓ rust_multistack☐ rust_multistackvm☐ bund runtime	
Make named stack current, create if stack does not exists	

```
1: function ENSURE_STACK()
2: ▷ Make stack current, create if not exists
3: Name ← current stack
4: if Name = None then
5: return Error("Stack is too shallow")
6: if Not Call(Stack_Exists, [Name]) then
7: CREATE_STACK(Name)
8: To_STACK(Name)
```

```
//
// Set stack "StackName" current
//
"StackName" ensure_stack
4
```

Make named stack with set capacity current, create if stack doesn't exists. - ensure_stack_with_capacity

Defined in ✓ rust_multistack □ rust_multistackvm □ bund runtime

Make named stack current, create if stack does not exists with defined capacity

```
1: function Ensure_Stack_With_Capacity()

    Make stack current, create if not exists

2:
3:
        Name \leftarrow current stack
4:
        N \leftarrow current stack
5:
        if Name = None then
             return Error("Stack is too shallow")
6:
        if Not Call(Stack_Exists, [Name]) then
7:
             CREATE STACK WITH CAPACITY(Name, N)
8:
9:
        To STACK(Name)
```

```
//
// Set stack "StackName" current
// and set stack capacity to not more than
// 128 values
//
128 "StackName" ensure_stack
6
```

Writing string value of the data loaded from the stack into file - file.write



```
Defined in

□ rust_multistack
□ rust_multistackvm
☑ bund runtime
```

Writing value representation converted to string to the external file.

```
1: function FUNCTION-NAME()
        ▶ Writing string representation of the data to the file
2:
3:
        Filename \leftarrow current stack
        if Filename = None then
4:
             return Error("Stack is too shallow")
5:
        Data \leftarrow current stack
6:
        if Data = None then
7:
             return Error("Stack is too shallow")
8:
        FILE_WRITE(Filename, Call("To_String", [Data]))
9:
```

```
//
// Write "42" to the file fourtytwo.txt
2
//
42 convert.to_string
:fourtytwo.txt
file.write
6
```

Folding all values in the current stack - fold

Defined in ✓ rust_multistack □ rust_multistackvm □ bund runtime

The *fold* function is designed to extract either all values stored in the stack or just the values that precede the *nodata* entry in the current stack. These extracted values will be compiled into a list and added back to the current stack.

```
1: function Fold()
2:
         ▶ Folding data in the current stack
3:
        Result \leftarrow []
        for Current Stack not Empty do
4:
              Value \leftarrow current stack
5:
              if Value = NODATA then
6:
7:
                   Break()
              Result ← Value
8:
9:
         current \ stack \leftarrow Result
```

```
//
// Folding stack values into list
//
1 2 3 none 4 5 6 fold
// Calling fold will leave
// 1 2 3 and [ 4 5 6 ]
// in the current stack
7
```

Folding all values in the named stack - fold_stack

Defined in
✓ rust_multistack☐ rust_multistackvm☐ bund runtime

The *fold_stack* function is designed to extract either all values stored in the named stack or just the values that precede the *nodata* entry again, in the named stack. These extracted values will be compiled into a list and added back to the named stack.

```
1: function Fold()
2:
         ▶ Folding data in the named stack
3:
        Result \leftarrow []
4:
        Name \leftarrow current stack
        for Name not Empty do
5:
              Value \leftarrow Name stack
6:
7:
              if Value = NODATA then
8:
                   Break()
9:
              Result ← Value
        Name stack \leftarrow Result
10:
```


Returning path of current work directory - fs.cwd

Aliases □ cwd 1: function FS-CWD() 2: ▷ Return CWD 3: current stack ← Call("Fs_Cwd", []) // // Prints current work directory //	Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime	
<pre>1: function FS-CWD() 2: ▷ Return CWD 3: current stack ← Call("Fs_Cwd", [])</pre>	Return current work directory to the stack	
1: function FS-CWD() 2: ▷ Return CWD 3: current stack ← Call("Fs_Cwd", [])	Aliases	
2:	□ cwd	
2:		
3: current stack ← Call("Fs_Cwd", []) // // Prints current work directory //	V	
// // Prints current work directory //		
// Prints current work directory 2 //	3: $current \ stack \leftarrow Call("Fs_Cwd", [])$	
// Prints current work directory 2 //		1
//		2
1 ' 1 7	// cwd println	3

Generate random v4 UUID - id.uuid

Defined in □ rust_multistack □ rust_multistackvm ✓ bund runtime	
Generate random v4 uuid. Result is stored into stack	
1 C 1.	
1: function ID.UUID()	
2:	
3: $current_stack \leftarrow Call("Uuid.new_v4", [])$	
//	1
// Generating and printing UUID V4	2
//	3
id.uuid println	4

Loading VM state from the WORLD file - load



Defined in
 □ rust_multistack □ rust_multistackvm ☑ bund runtime

With the help of the *save* function, users can store the current state of the BUND VM into an external file. This file, called the "WORLD" file, contains a frozen version of the registered lambda functions, user functions, aliases, and the content of the stacks. The *load* function, which can be used as "WORLD_file" load, will load content from this file and add it to the existing BUND state.

```
1: function BUND-LOAD()
2: ▷ Restore VM state from WORLD file
3: Filename ← current stack
4: if Value = None then
5: return Error("Stack is too shallow")
6: BUND_LOAD(Filename)
```

```
//
// Load VM state from file _state.world_
//
"state" load
1
2
3
4
```

Loading function aliases from the WORLD file - load.aliases




Content from the external file will alter current list of aliases

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

With the help of the *save* function, users can store the current state of the BUND VM into an external file. This file, called the "WORLD" file, contains a frozen version of the registered lambda functions, user functions, aliases, and the content of the stacks. The *load.aliases* function, which can be used as "WORLD_file" load.aliases, will load VM aliases from this file and add it to the list of existing aliases.

```
    function BUND-LOAD-ALIASES()
    Restore VM function aliases from WORLD file
    Filename ← current stack
    if Value = None then
    return Error("Stack is too shallow")
    BUND_LOAD_ALIASES(Filename)
```

Loading lambda functions from the WORLD file - load.lambdas




Defined in □ rust_multistack □ rust_multistackvm ✓ bund runtime

With the help of the *save* function, users can store the current state of the BUND VM into an external file. This file, called the "WORLD" file, contains a frozen version of the registered lambda functions, user functions, aliases, and the content of the stacks. The *load.lambdas* function, which can be used as "WORLD_file" load.lambdas, will load lambda functions from this file and add it to the list of existing lambdas.

```
    function BUND-LOAD-LAMBDAS()
    Restore lambda functions from WORLD file
    Filename ← current stack
    if Value = None then
    return Error("Stack is too shallow")
    BUND_LOAD_LAMBDAS(Filename)
```

```
// Load lambda functions from file _state.world_
"state" load.lambdas
```

Loading for the stacks from the WORLD file - load.stacks



Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

With the help of the *save* function, users can store the current state of the BUND VM into an external file. This file, called the "WORLD" file, contains a frozen version of the registered lambda functions, user functions, aliases, and the content of the stacks. The *load.stacks* function, which can be used as "WORLD_file" load.stacks, will load stacks content from this file and add it to the existing data contexts.

```
    function BUND-LOAD-STACKS()
    Restore VM state from WORLD file
    Filename ← current stack
    if Value = None then
    return Error("Stack is too shallow")
    BUND_LOAD_STACKS(Filename)
```

E to the power of the value taken from stack - math.exp

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

Raise mathematical constant e to the power of the value that is taken from stack

```
    function MATH.EXP()
    E to the power of X
    X ← current stack
    if X = None then
    return Error("Stack is too shallow")
    current stack ← Call("Math_Exp", [X])
```

```
// e^1 is 2.718281828459045
// 1.0 math.exp println 4
```


Calculate factorial of the value taken from stack - math.factorial

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime Compute factorial of the numeric value taken from stack

```
    function MATH.FACTORIAL()
    ⇒ factorial of X
    X ← current stack
    if X = None then
    return Error("Stack is too shallow")
    current stack ← Call("Math_Factorial", [X])
```

```
//
// 1! is 1
//
1 math.factorial println
4
```

Calculate natural logarithm of the value taken from stack - math.ln



```
    function MATH.LN()
    Natural logarithm of X
    X ← current stack
    if X = None then
    return Error("Stack is too shallow")
    current stack ← Call("Math_Ln", [X])
```

```
//
// ln(1.0) is 0.0
//
1.0 math.ln println
4
```

Calculate n-th root of the value taken from stack - math.nroot

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

Compute N-th root of X, where N and X are taken from stack. Result is stored to the stack.

```
1: function MATH.NROOT()
2:
         \triangleright n-th root of X
         N \leftarrow current stack
3:
4:
        if N = None then
              return Error("Stack is too shallow")
5:
6:
         X \leftarrow current stack
         if X = None then
7:
              return Error("Stack is too shallow")
8:
         current \ stack \leftarrow Call("Math_NRoot", [X, N])
9:
```

```
// nroot(1.0, 1.0) is 1.0
//
1.0 1.0 math.nroot println
```

Calculate perimeter of rectangle where X and Y are taken from stack - math.perimeter


Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

The math perimeter function calculates the total length of a rectangle's boundaries, given its width and height, returning the result as a floating-point number.

```
1: function MATH.PERIMETER()
       2:
       X \leftarrow current stack
3:
       if N = None then
4:
            return Error("Stack is too shallow")
5:
6:
       Y \leftarrow current stack
       if X = None then
7:
            return Error("Stack is too shallow")
8:
       current \ stack \leftarrow Call("Math\_Perimeter", [X, Y])
9:
```

```
//
// perimeter of X=1.0 and Y=1.0 is 4.0
//
1.0 1.0 math.perimeter println
4
```

Calculate Y power of X where X and Y are taken from stack - math.power



```
1: function MATH.POWER()
2:
         \triangleright n-th root of X
3:
         N \leftarrow current stack
         if N = None then
4:
              return Error("Stack is too shallow")
5:
6:
        X \leftarrow current stack
         if X = None then
7:
              return Error("Stack is too shallow")
8:
         current \ stack \leftarrow Call("Math Power", [X, N])
9:
```

```
//
// 1.0 in the power of 0.0 is 1.0
//
0.0 1.0 math.perimeter println
4
```

Perform Simple Moving Average smoothing for list of numbers - math.smoothing

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

Performing SMA (simple moving average) smoothing of numeric sample that is loaded from the stack. Result value is returned to the stack.

```
    function MATH.SMOOTHING()
    SMA smoothing
    Sample ← current stack
    if Sample = None then
    return Error("Stack is too shallow")
    current stack ← Call("Math_Smoothing", [Sample])
```

```
//
// SMA smoothing
//
[1.22 3.004 5.0 4 2 88 3] math.smoothing println
4
```

Perform Simple Moving Average smoothing for list of numbers. Source is workbench - *math.smoothing*.

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

Performing SMA (simple moving average) smoothing of numeric sample that is loaded from the workbench. Result value is returned to the workbench.

```
    function MATH.SMOOTHING.()
    SMA smoothing
    Sample ← workbench
    if Sample = None then
    return Error("Workbench is too shallow")
    workbench ← Call("Math_Smoothing", [Sample])
```

```
//
// SMA smoothing
//
[1.22 3.004 5.0 4 2 88 3] . math.smoothing. take println 4
```

Perform Simple Moving Average smoothing for list of numbers preserving original value in the workbench. Source is workbench - math.smoothing._comma

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

Performing SMA (simple moving average) smoothing of numeric sample that is loaded from the workbench. Original value is preserved in the workbench. Result value is returned to the workbench.

```
    function MATH.SMOOTHING.,()
    SMA smoothing
    Sample ← workbench
    if Sample = None then
    return Error("Stack is too shallow")
    workbench ← Sample
    workbench ← Call("Math_Smoothing", [Sample])
```

```
//
// SMA smoothing
//
[1 2 3] . math.smoothing., debug.display_workbench
// Prints result and original value stored in the workbench
```

Perform Simple Moving Average smoothing for list of numbers preserving original value in the stack - math.smoothing_comma


Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

Performing SMA (simple moving average) smoothing of numeric sample that is loaded from the stack. Original value is preserved in the stack. Result value is returned to the stack.

```
    function MATH.SMOOTHING,()
    SMA smoothing
    Sample ← current stack
    if Sample = None then
    return Error("Stack is too shallow")
    current stack ← Sample
    current stack ← Call("Math_Smoothing", [Sample])
```

```
//
// SMA smoothing
//
[1 2 3] math.smoothing, debug.display_stack
// Prints result and original value stored in the stack
5
```

Moving value from current stack to named stack - move



```
1: function FUNCTION-NAME()
       2:
3:
       Name \leftarrow current stack
       if Name = None then
4:
            return Error("Stack is too shallow")
5:
       Value \leftarrow current stack
6:
       if Value = None then
7:
            return Error("Stack is too shallow")
8:
       Name stack \leftarrow Value
9:
```

Moving value between named stacks - move_from

```
Defined in

✓ rust_multistack

□ rust_multistackvm

□ bund runtime


Moving value between two named stacks
```

```
1: function FUNCTION-NAME()
       2:
       Name From \leftarrow current stack
3:
       if Name From = None then
4:
            return Error("Stack is too shallow")
5:
6:
       Name To \leftarrow current stack
7:
       if Name To = None then
            return Error("Stack is too shallow")
8:
9:
       Value \leftarrow Name\ From\ stack
10:
       if Value = None then
            return Error("Stack is too shallow")
11:
       Name To stack \leftarrow Value
12:
```

Rotate current stack to the left - rotate_current_left

Defined in ✓ rust_multistack □ rust_multistackvm □ bund runtime Rotate current stack as a circular buffer to the left 1: function Rotate_Current_Left() 2: ▷ Rotate current stack 3: Name ← VM::current_stack_name() 4: ROTATE_STACK_LEFT(1, Name)

Rotate current stack to the right - rotate_current_right



```
//
// Rotate current stack to the right
//
1 2 3 rotate_current_right
// The state of stack is 3 1 2
1
```

Rotate named stack left - rotate_stack_left

Defined in ✓ rust_multistack □ rust_multistackvm □ bund runtime Rotate named stack as a circular buffer to the left

```
    function ROTATE_CURRENT_LEFT()
    Rotate named stack
    Name ← current stack
    ROTATE_STACK_LEFT(1, Name)
```

```
//
// Rotate stack :A to the right and do the math
//
@main
@A
1 2 41
@main
:A rotate_stack_left + println
// Printing result of + operation = 42
```

Rotate named stack right - rotate_stack_right

Defined in ✓ rust_multistack □ rust_multistackvm □ bund runtime Rotate named stack as a circular buffer to the right

```
    function ROTATE_CURRENT_LEFT()
    Rotate named stack
    Name ← current stack
    ROTATE_STACK_RIGHT(1, Name)
```

```
//
// Rotate stack :A to the right and do the math
//
@main
@A
    1 41 3
@main
:A rotate_stack_right + println
// Printing result of + operation = 42
```

Saving state of the VM into a WORLD file - save

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

With the help of the *save* function, users can store the current state of the BUND VM into an external file. This file, called the "WORLD" file, contains a frozen version of the registered lambda functions, user functions, aliases, and the content of the stacks.

```
    function BUND-SAVE()
    Restore VM state from WORLD file
    Filename ← current stack
    if Value = None then
    return Error("Stack is too shallow")
    BUND_SAVE(Filename)
```

```
//
// Save VM state to the WORLD file _state.world_
2
//
"state" save
4
```

Saving function aliases into a WORLD file - save.aliases



With the help of the *save* function, users can store the current state of the BUND VM into an external file. This file, called the "WORLD" file, contains a frozen version of the registered lambda functions, user functions, aliases, and the content of the stacks. Function *save.aliases* performs the storing of current aliases into the WORLD file.

```
1: function BUND-SAVE-ALIASES()
2: ▷ Restore VM state from WORLD file
3: Filename ← current stack
4: if Value = None then
5: return Error("Stack is too shallow")
6: BUND_SAVE_ALIASES(Filename)
```

```
//
// Save BUND function aliases to the WORLD file
_state.world_
//
"state" save.aliases
```

Saving lambda functions into a WORLD file - save.lambdas

Defined in
□ rust_multistack□ rust_multistackvm☑ bund runtime

With the help of the *save* function, users can store the current state of the BUND VM into an external file. This file, called the "WORLD" file, contains a frozen version of the registered lambda functions, user functions, aliases, and the content of the stacks.

```
    function BUND-SAVE()
    Restore VM state from WORLD file
    Filename ← current stack
    if Value = None then
    return Error("Stack is too shallow")
    BUND_SAVE(Filename)
```

```
//
// Save lambdas to the WORLD file _state.world_
//
"state" save.lambdas
4
```

Store script from the stack into bootstrap scripts repository of the WORLD file - save.script

→ Danger

This function will change the state of the bootstrap scripts which may change the state of the VM

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

Adding script stored in the stack to the bootstrap scripts stored in the WORLD file.

```
1: function BUND-SAVE-SCRIPT()
        ▷ Saving bootstrap script into the WORLD file
2:
3:
        Filename \leftarrow current stack
        if Filename = None then
4:
             return Error("Stack is too shallow")
5:
6:
        Snippet \leftarrow current stack
7:
        if Snippet = None then
             return Error("Stack is too shallow")
8:
9:
        Name \leftarrow current stack
10:
        if Name = None then
             return Error("Stack is too shallow")
11:
        Bund_Save_Script(Filename, Snippet, Name)
12:
```

BUND standard Library reference

```
//
// Adding Plus42 script to bootstrap scripts
//
:Plus42 "42 +" "sample" save.script
4
```

Saving stacks data into a WORLD file - save.stacks



With the help of the *save* function, users can store the current state of the BUND VM into an external file. This file, called the "WORLD" file, contains a frozen version of the registered lambda functions, user functions, aliases, and the content of the stacks. Function *save.stacks* performs the save stacks data into the WORLD file.

```
    function BUND-SAVE-STACKS()
    ⇒ Restore VM state from WORLD file
    Filename ← current stack
    if Value = None then
    return Error("Stack is too shallow")
    BUND_SAVE_STACKS(Filename)
```

```
//
// Save stacks data into the WORLD file _state.world_
//
"state" save.stacks
```

Generate a list of the sequence of floating point numbers, according to sample configuration stored in the stack - seq

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime Create list filled with sequence of numbers according to configuration stored in the stack. Currently supposered types of the sequence is: □ seq.ascending and this is the default. Parameters are: X, Step, N □ seq.descending. Parameters are: X, Step, N

```
    function SEQ()
    Creating sequence of float numbers
    Conf ← current stack
    if Conf = None then
    return Error("Stack is too shallow")
    current stack ← Call("Seq", [Conf])
```

```
//
// Generate descending sequence
//
config
   "type" "seq.descending" set
   "X"   100.0    set
   "Step"   3.0    set
   "N"   3    set
   "Generated sequence is: " print seq println
```

Generate a list of the sequence of floating point numbers sorted in ascending - seq.asc

Defined in □ rust_multistack □ rust_multistackvm ☑ bund runtime

Create list filled with sequence of numbers started from X with defined step and size. Ordered in ascending. Result is stored in stack.


```
1: function SEQ.ASC()
         ▷ Creating sequence of float numbers
2:
        X \leftarrow current stack
3:
        if X = None then
4:
5:
              return Error("Stack is too shallow")
6:
        Step \leftarrow current stack
7:
        if Step = None then
              return Error("Stack is too shallow")
8:
9:
        N \leftarrow current stack
        if N = None then
10:
              return Error("Stack is too shallow")
11:
         current \ stack \leftarrow Call("Seq_Asc", [X, Step, N])
12:
```

```
//
// Create list containing [ 1.0 :: 1.1 :: 1.2 :: ]

//
3 0.1 1.0 seq.asc

4
```

Rotate circular list of stacks to left - stacks_left




@C

stacks right

// Now stacks are in order C A B

Rotate circular list of stacks to right - stacks_right



7

Check if stack exists - stack_exists

Defined in ✓ rust_multistack □ rust_multistackvm □ bund runtime

Returning TRUE to the stack if named stack exists, FALSE - otherwise


```
1: function STACK_EXISTS()
         ▷ Check if stack exists
2:
3:
         Name \leftarrow current stack
        if Name = None then
4:
              return Error("Stack is too shallow")
5:
6:
        if Not Call(Stack Exists, [Name]) then
              current \ stack \leftarrow FALSE
7:
         else
8:
9:
              current \ stack \leftarrow TRUE
```

```
// This snippet will check if stack with name "A"
// exists and prints the message
//
@A
: A
  stack exists
    { "Stack A existing" } ?
// And yes, it ddoes exists, as @A will make sure that
it does
: B
  stack exists
                                                            11
  not { "There is no stack with name B" } ?
                                                            12
// And stack B doesn't exists
                                                            13
```

Convert string stored on stack to the list of tokens - string.tokenize

→ Danger	
Remove if there is no danger	
Defined in	
☐ rust_multistack	
☐ rust_multistackvm	
☐ bund runtime	
Description of function	
Aliases	
☐ this is an alias	
1: function FUNCTION-NAME() 2: ▷ Comment	
3: Value ← current stack	
4: if Value = None then	
5: return Error("Stack is too shallow")	
	_
// //	1 2
//	3

Swap two vallues in current stack - swap_one



```
1: function SWAP_ONE()
2:
         > Swapping data in stack
         Value1 \leftarrow current stack
3:
         if Value1 = None then
4:
              return Error("Stack is too shallow")
5:
        Value2 \leftarrow current stack
6:
7:
         if Value2 = None then
              return Error("Stack is too shallow")
8:
9:
         current \ stack \leftarrow Value 2
         current\ stack \leftarrow Value1
10:
```

```
//
// Swapping values
//
1 2 swap_one
// As the result, we will have following state in the stack 2 1
```

Make existing stack with name - current - to_current

Defined in
✓ rust_multistack☐ rust_multistackvm☐ bund runtime

Taking name of the stack from the stack and makes this stack a current stack. If stack doesn't exists raise an error

```
1: function TO_CURRENT()
       ▶ Make already existing stack a current stack
2:
       Value \leftarrow current stack
3:
       if Value = None then
4:
            return Error("Stack is too shallow")
5:
       To Current(Name)
6:
//
// Make stack with name "A" - current
// stack must already exists
                                                              4
"A" to_current
                                                              5
```

Make stack with name - current - to_stack

Defined in ✓ rust_multistack □ rust_multistackvm □ bund runtime

Taking name of the stack from the stack and makes this stack a current stack. If stack doesn't exists VM creates it.

```
1: function TO_CURRENT()
2:
       ▶ Make stack a current stack. Create if not existing.
3:
       Name \leftarrow current stack
       if Name = None then
4:
            return Error("Stack is too shallow")
5:
       if not VM::stack exists(Name) then
6:
            Ensure Stack(Name)
7:
       To Current(Name)
8:
//
// Make stack with name "A" - current
                                                               3
"A" to_stack
```

Load and execute bund scripts from external file. - use

Danger

Function *use* may change the state of the VM as it executes functions from an external file.

Defined in rust_multistack rust_multistackvm bund runtime

Function *use* loads and executes BUND script. The file name is passed through the stack.

```
    function BUND-USE-FROM-STACK()
    Load and execute external scripts
    Filename ← current stack
    if Value = None then
    return Error("Stack is too shallow")
    BUND_USE(Filename)
```

```
//
// Load and execute script from "sample.bund"
2
//
"sample.bund" use
4
```

Load and execute bund scripts from external file. - use.

→ Danger

Function *use* may change the state of the VM as it executes functions from an external file.

Defined in rust_multistack rust_multistackvm bund runtime

Function $\it use.$ loads and executes BUND script. The file name is passed through the wirkbench.

```
    function BUND-USE-FROM-WORKBENCH()
    Load and execute external scripts
    Filename ← workbench
    if Value = None then
    return Error("Stack is too shallow")
    BUND_USE(Filename)
```

```
//
// Load and execute script from "sample.bund"
2
//
"sample" ".bund" + . use.
```

 $BU\!N\!D\ standard\ Library\ reference$

Conclusion

BUND is a very new language. It is currently in its early stages of development, and the language's runtime has many limitations. The standard library requires improvement, and the author or contributor must address several potential bugs. However, the *bundcore* crate and its dependencies have successfully passed all their test cases, which is a promising sign. Although the language is simple and its underlying dependencies are generally stable, there are no guarantees against critical bugs. The license is attached for reference. While concatenative, stack-based programming languages are not widely used in general programming practices, they have stood the test of time and deserve more attention from the software development community. BUND aims to address design gaps in this concept, and the author hopes to spark interest with his ideas and inspirations that brought BUND into existence.

You can get in touch with my via in my LinkedIn profile.

The BUND project is hosted on my GitHub page vulogov



 $BU\!N\!D\ standard\ Library\ reference$

License

Apache License Version 2.0, January 2004 http://www.apache.org/licenses/

TERMS AND CONDITIONS FOR USE, REPRODUCTION, AND DISTRIBUTION

1. Definitions.

"License" shall mean the terms and conditions for use, reproduction, and distribution as defined by Sections 1 through 9 of this document.

"Licensor" shall mean the copyright owner or entity authorized by the copyright owner that is granting the License.

"Legal Entity" shall mean the union of the acting entity and all other entities that control, are controlled by, or are under common control with that entity. For the purposes of this definition, "control" means (i) the power, direct or indirect, to cause the direction or management of such entity, whether by contract or otherwise, or (ii) ownership of fifty percent (50%) or more of the outstanding shares, or (iii) beneficial ownership of such entity.

"You" (or "Your") shall mean an individual or Legal Entity exercising permissions granted by this License.

"Source" form shall mean the preferred form for making modifications, including but not limited to software source code, documentation source, and configuration files.

"Object" form shall mean any form resulting from mechanical transformation or translation of a Source form, including but not limited to compiled object code, generated documentation, and conversions to other media types.

"Work" shall mean the work of authorship, whether in Source or Object form, made available under the License, as indicated by a copyright notice that is included in or attached to the work (an example is provided in the Appendix below).

"Derivative Works" shall mean any work, whether in Source or Object form, that is based on (or derived from) the Work and for which the editorial revisions, annotations, elaborations, or other modifications represent, as a whole, an original work of authorship. For the purposes of this License, Derivative Works shall not include works that remain separable from, or merely link (or bind by name) to the interfaces of, the Work and Derivative Works thereof.

"Contribution" shall mean any work of authorship, including the original version of the Work and any modifications or additions to that Work or Derivative Works thereof, that is intentionally submitted to Licensor for inclusion in the Work by the copyright owner or by an individual or Legal Entity authorized to submit on behalf of the copyright owner. For the purposes of this definition, "submitted" means any form of electronic, verbal, or written communication sent to the Licensor or its representatives, including but not limited to communication on electronic mailing lists, source code control systems, and issue tracking systems that are managed by, or on behalf of, the Licensor for the purpose of discussing and improving the Work, but excluding communication that is conspicuously marked or otherwise designated in writing by the copyright owner as "Not a Contribution."

"Contributor" shall mean Licensor and any individual or Legal Entity on behalf of whom a Contribution has been received by Licensor and subsequently incorporated within the Work.

2. Grant of Copyright License. Subject to the terms and conditions of

this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable copyright license to reproduce, prepare Derivative Works of, publicly display, publicly perform, sublicense, and distribute the Work and such Derivative Works in Source or Object form.

3. Grant of Patent License. Subject to the terms and conditions of

this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable (except as stated in this section) patent license to make, have made, use, offer to sell, sell, import, and otherwise transfer the Work, where such license applies only to those patent claims licensable by such Contributor that are necessarily infringed by their Contribution(s) alone or by combination of their Contribution(s) with the Work to which such Contribution(s) was submitted. If You institute patent litigation against any entity (including a cross-claim or counterclaim in a lawsuit) alleging that the Work or a Contribution incorporated within the Work constitutes direct or contributory patent infringement, then any patent licenses granted to You under this License for that Work shall terminate as of the date such litigation is filed.

4. Redistribution. You may reproduce and distribute copies of the

Work or Derivative Works thereof in any medium, with or without modifications, and in Source or Object form, provided that You meet the following conditions:

- (a) You must give any other recipients of the Work or Derivative Works a copy of this License; and
- (b) You must cause any modified files to carry prominent notices stating that You changed the files; and
- (c) You must retain, in the Source form of any Derivative Works that You distribute, all copyright, patent, trademark, and attribution notices from the Source form of the Work, excluding those notices that do not pertain to any part of the Derivative Works; and
- (d) If the Work includes a "NOTICE" text file as part of its distribution, then any Derivative Works that You distribute must include a readable copy of the attribution notices contained within such NOTICE file, excluding those notices that do not pertain to any part of the Derivative Works, in at least one of the following places: within a NOTICE text file distributed as part of the Derivative Works; within the Source form or

documentation, if provided along with the Derivative Works; or, within a display generated by the Derivative Works, if and wherever such third-party notices normally appear. The contents of the NOTICE file are for informational purposes only and do not modify the License. You may add Your own attribution notices within Derivative Works that You distribute, alongside or as an addendum to the NOTICE text from the Work, provided that such additional attribution notices cannot be construed as modifying the License.

You may add Your own copyright statement to Your modifications and may provide additional or different license terms and conditions for use, reproduction, or distribution of Your modifications, or for any such Derivative Works as a whole, provided Your use, reproduction, and distribution of the Work otherwise complies with the conditions stated in this License.

- 5. Submission of Contributions. Unless You explicitly state otherwise, any Contribution intentionally submitted for inclusion in the Work by You to the Licensor shall be under the terms and conditions of this License, without any additional terms or conditions. Notwithstanding the above, nothing herein shall supersede or modify the terms of any separate license agreement you may have executed with Licensor regarding such Contributions.
- 6. Trademarks. This License does not grant permission to use the trade names, trademarks, service marks, or product names of the Licensor, except as required for reasonable and customary use in describing the origin of the Work and reproducing the content of the NOTICE file.
- 7. Disclaimer of Warranty. Unless required by applicable law or agreed to in writing, Licensor provides the Work (and each Contributor provides its Contributions) on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied, including, without limitation, any warranties or conditions of TITLE, NON-INFRINGEMENT, MERCHANTABILITY, or FITNESS FOR

A PARTICULAR PURPOSE. You are solely responsible for determining

BUND standard Library reference

the appropriateness of using or redistributing the Work and assume any risks associated with Your exercise of permissions under this License.

8. Limitation of Liability. In no event and under no legal theory,

whether in tort (including negligence), contract, or otherwise, unless required by applicable law (such as deliberate and grossly negligent acts) or agreed to in writing, shall any Contributor be liable to You for damages, including any direct, indirect, special, incidental, or consequential damages of any character arising as a result of this License or out of the use or inability to use the Work (including but not limited to damages for loss of goodwill, work stoppage, computer failure or malfunction, or any and all other commercial damages or losses), even if such Contributor has been advised of the possibility of such damages.

9. Accepting Warranty or Additional Liability. While redistributing

the Work or Derivative Works thereof, You may choose to offer, and charge a fee for, acceptance of support, warranty, indemnity, or other liability obligations and/or rights consistent with this License. However, in accepting such obligations, You may act only on Your own behalf and on Your sole responsibility, not on behalf of any other Contributor, and only if You agree to indemnify, defend, and hold each Contributor harmless for any liability incurred by, or claims asserted against, such Contributor by reason of your accepting any such warranty or additional liability.

END OF TERMS AND CONDITIONS

APPENDIX: How to apply the Apache License to your work.

To apply the Apache License to your work, attach the following boiler-plate notice, with the fields enclosed by brackets "[]" replaced with your own identifying information. (Don't include the brackets!) The text should be enclosed in the appropriate comment syntax for the file format. We also recommend that a file or class name and description of purpose be included on the same "printed page" as the copyright notice for easier identification within third-party archives.

Copyright [yyyy] [name of copyright owner]

BUND standard Library reference

Licensed under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at

http://www.apache.org/licenses/LICENSE-2.0

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITH-OUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

 $BU\!N\!D\ standard\ Library\ reference$

 $BU\!N\!D\ standard\ Library\ reference$

Content

Introduction
What exactly is a Bund?
Circular data stack
Stack-of-stacks references
Workbench
What does the word "bund" mean?
How to use the reference?
BUND Standard library reference
Execute code snippet in the BUND debugger - debug 15
Arguments passed via CLI for script and shell subcommands - arg.
16
Load and execute scripts stored as bootstrap scripts in the WORLD
file - bootstrap
Evaluate BUND code snippet taken as string from stack - bund.eva
18
Evaluate BUND code snippet taken from the file. The name of the
file is taken as string from stack - bund.eval-file
Evaluate BUND code snippet taken from the file. The name of the
file is taken as string from workbench - bund.eval-file
Evaluate BUND code snippet taken as string from workbench
bund.eval 22
Clear current stack - <i>clear</i>
Clear named stack - clear_in
Taking value from stack and convert it to boolean - convert.to_boo
24
Taking value from workbench and convert it to boolean
convert.to_bool 25
Taking value from stack and convert it to float - convert.to_float 20
Taking value from workbench and convert it to float

$BU\!N\!D\ standard\ Library\ reference$

convert.to_float	. 27
Taking value from stack and convert it to int - convert.to_int	
Taking value from workbench and convert it to int - <i>convert.to</i> _	
29	
Taking value from stack and convert it to list - convert.to_list	. 30
Taking value from workbench and convert it to list - convert.to_	list.
31	
Taking value from stack and convert it to matrix - convert.to_ma	trix
32	
Taking value from workbench and convert it to matri	x -
convert.to_matrix	
Taking value from stack and convert it to string - convert.to_str	ing.
34	
Taking value from workbench and convert it to strin	g -
convert.to_string.	. 35
Taking value from stack and convert it to textbuffe	
convert.to_textbuffer	. 36
Taking value from workbench and convert it to textbuffe	er -
convert.to_textbuffer	. 37
Return name of current stack to current stack - current	. 38
Display information about host - debug.display_hostinfo	. 39
Display data stored in current stack - debug.display_stack	. 40
Display data stored in workbench - debug.display_workbench	. 41
Drop into a debug shell - debug.shell	. 42
Decoding string from stack from BASE64 - decode.base64	. 43
Decoding string from workbench from BASE64 - decode.base64.	44
Drop element from the stack - <i>drop</i>	. 45
Drop the last value in the named stack - drop_in	. 46
Remove stack with all data - drop_stack	. 47
Duplicate multiple values in the current stack - <i>dup_many</i>	. 48
Duplicate multiple values in the named stack - <code>dup_many_in</code>	. 49
Duplicate single value in the current stack - <i>dup_one</i>	. 50
Duplicate single value in the named stack - <code>dup_one_in</code>	. 51
Encoding string from stack into BASE64 - encode.base64	. 52
Encoding string from workbench into BASE64 - encode.base64.	53

$BU\!N\!D\ standard\ Library\ reference$

Make named stack current, create if stack doesn't exists
ensure_stack 5
Make named stack with set capacity current, create if stack doesn't
exists ensure_stack_with_capacity 5
Writing string value of the data loaded from the stack into file
file.write5
Folding all values in the current stack - fold 5
Folding all values in the named stack - fold_stack 5
Returning path of current work directory - fs.cwd 5
Generate random v4 UUID - id.uuid 6
Loading VM state from the WORLD file - load 6
Loading function aliases from the WORLD file - load.aliases 6
Loading lambda functions from the WORLD file - load.lambdas . 6
Loading for the stacks from the WORLD file - load.stacks 6
E to the power of the value taken from stack - <i>math.exp</i> 6
Calculate factorial of the value taken from stack - math.factorial 6
Calculate natural logarithm of the value taken from stack - math.l
67
Calculate n-th root of the value taken from stack - <i>math.nroot</i> 6
Calculate perimeter of rectangle where X and Y are taken from stack
- math.perimeter 6
Calculate Y power of X where X and Y are taken from stack
math.power
Perform Simple Moving Average smoothing for list of numbers
math.smoothing
Perform Simple Moving Average smoothing for list of number
Source is workbench - <i>math.smoothing</i>
Perform Simple Moving Average smoothing for list of number
preserving original value in the workbench. Source is workbench
math.smoothingcomma
Perform Simple Moving Average smoothing for list of number
preserving original value in the stack - $math.smoothing_comma$ 7
Moving value from current stack to named stack - move
Moving value between named stacks - move_from 7
Rotate current stack to the left - rotate_current_left

BUND standard Library reference

Rotate current stack to the right - rotate_current_right	78
Rotate named stack left - rotate_stack_left	79
Rotate named stack right - rotate_stack_right	80
Saving state of the VM into a WORLD file - save	81
Saving function aliases into a WORLD file - save.aliases	82
Saving lambda functions into a WORLD file - save.lambdas	83
Store script from the stack into bootstrap scripts repository	of the
WORLD file - save.script	84
Saving stacks data into a WORLD file - save.stacks	86
Generate a list of the sequence of floating point numbers, acco	ording
to sample configuration stored in the stack - seq	87
Generate a list of the sequence of floating point numbers so	rted in
ascending - seq.asc	
Rotate circular list of stacks to left - stacks_left	89
Rotate circular list of stacks to right - stacks_right	90
Check if stack exists - stack_exists	91
Convert string stored on stack to the list of tokens - string.to	kenize
92	
Swap two vallues in current stack - swap_one	93
Make existing stack with name - current - to_current	94
Make stack with name - current - to_stack	95
Load and execute bund scripts from external file use	96
Load and execute bund scripts from external file use	97
Conclusion	99
License	101

BUND standard Library reference