User Platform Client usage

Software Quality Team

ABSTRACT

This usage guide document will briefly introduce the usage of TMP Client for software verification, this document will include following areas:

- a) Client preparations
- b) Client installs
- c) Client initial setting
- d) Client run and result check

REVISION HISTORY

REVISION	RELEASE DATE	COMMENTS			
V1.0	9/10/2016	Initial draft			
V1.1	4/11/2017	Jason Wang			
V1.2	5/10/2019	Jason Wang			
V1.3	03/05/2020	Update based on Client version 2.09.xx			
V1.4	07/12/2022	Install software update			
V1.5	08/21/2024	Software path update			

CONTENTS

1 Preparation for TMP Client	5
1.1 What is TMP Client	5
1.2 System requirements	5
1.2.1 Operation System requirements	5
1.2.2 Hard Ware suggestion	5
1.3 System setting (Linux only)	5
1.3 Dependent software and version	5
1.3.1 Python	5
1.3.2 Subversion	6
2 Install TMP Client	6
2.1 Export TMP Client build	6
2.2 Install TMP Client build	7
2.2.1 Install with wizard	
2.2.2 Manually install	g
3 Launch TMP Client	g
3.1 TMP Client initial setting (console mode)	g
3.1.1 Software setting section	g
3.1.2 Machine setting section	10
3.1.3 Preference setting section	10
3.2 launch from Start Menu (Windows)	10
3.3 launch from command line	11
3.4 TMP Client initial setting (GUI mode)	11
3.4.1 Welcome setting	11
3.4.2 Client setting	12
3.4.3 Software setting	12
3.4.4 Preference setting	13
4 TMP Client usage	13
4.1 Main window introduction	13
4.1.1 Overview	13
4.1.2 Menu bar	14
4.1.3 Rejected queue panel	16
4.1.4 Captured queue panel	16
4 1 5 Watching task nanel	17

4.1.6 Status bar	18
4.2 Launch a local test suite	18
4.2.1 import a standard suite file	18
4.2.2 import a suite path	19
4.3 Launch remote test suite	19
4.4 Report output	19
4.5 Client info and update	20
5 Appendix	20

1 Preparation for TMP Client

1.1 What is TMP Client

TMP (Test Management Platform) Client is used to receive and run test case from TMP server, on the meanwhile client also support test suite run locally.

1.2 System requirements

1.2.1 Operation System requirements

The following are tested OS and we don't guarantee OS not list here

Window:

Win 7 or later.

Linux:

RedHat 6 or later CentOS 7 or later OpenSUSE 42 or later Ubuntu 16 or later

1.2.2 Hardware suggestion

CPU core number: 4 Physical memory: 16G

1.3 System setting (Linux only)

TMP Client will launch many test cases concurrently (Depends on user setting in Menu \rightarrow Setting \rightarrow Preference \rightarrow Max Threads) which will exceed the default user open files limitation (1024). To avoid this limitation, we need to add following two lines into file /etc/security/limits.conf.

* soft nofile 32768 * hard nofile 65536

To verify this modification, you can type: ulimit -a

1.3 Dependent software and version

1.3.1 Python

TMP Client will invoke core script to launch every detail test case. Core script was built by Python software, so we need Python ready on your machine.

And some Python packages were required for some specific tasks.

Source:

\\lsh-smb04\sw\ga\ga store\TMP tools\depend software\python and packages

Install Python:

- 1. Double click: python-3.8.7-amd64.exe (Windows) or unzip Python-3.8.7.tar.xz(Linux)
- 2. Put Python install path into environment 'PATH' variable

Install Python packages:

- 1. Copy 'offline' folder to your local machine
- 2. Go into 'offline' folder
- 3. Run following commands in console:
 - a. python -m pip install --no-index --find-links . psutil==5.8.0

- b. python -m pip install --no-index --find-links . JIRA==2.0.0
- c. python -m pip install --no-index --find-links . openpyxl==3.0.7
- d. python -m pip install --no-index --find-links . pymysgl==1.0.2

Check:

Run following commands in console:

- 1. python -- Python should be run with a correct version
- import psutil
 Python package imported, no crash
 import jira
 Python package imported, no crash
- 4. import openpyxl -- Python package imported, no crash
 5. import pymysql -- Python package imported, no crash

1.3.2 Subversion

In most case our core script and user case were stored in subversion. So TMP client need subversion ready on your machine.

Subversion version large than 1.6 is required.

Source:

\\lsh-smb04\sw\qa\qa_store\TMP_tools\depend_software

Install:

- 1. Double click: Setup-Subversion-1.6.6.msi (Windows)
- 2. Put SVN install path into environment 'PATH' variable

Check:

Run following commands in console:

1. svn –version --SVN should report correct version

2 Install TMP Client

2.1 Export TMP Client build

TMP Client build will follow the name rules as:

Tmp_client_a.bb_installer_ccc_ddd.dd

a: Public release version

b: Internal release version

ccc: bin/src, binary package or source package

ddd.dd: install platform which can be:

- 1) linux.run: package for Linux with install wizard.
- 2) windows.exe: package for windows with install wizard.
- 3) all.tar.gz: package for all platform with manually install.

For example:

- 1) tmp_client_216xx_installer_bin_linux.run:
 - Build for Linux (RedHat, Ubuntu, SUSE) install with wizard available.
- 2) tmp_client_216xx _installer_bin_windows.exe:
 - Build for Windows (win7 or later) install with wizard available.
- 3) tmp_client_216xx _installer_src_all.tar.gz:
 Build for all platforms install without install wizard (manually install).

Please export the build according to your requirements:

2.2 Install TMP Client build

Source:

\\lsh-smb04\sw\qa\qa store\TMP tools\client software

2.2.1 Install with wizard

TMP Client package offer general GUI setups, so you can simply follow with the wizard to install it.

Step 1: Double clicks install package.

Step 2: Confirm install build and click "Next"




Figure1: Confirm install build

Step 3: Select install type




Figure 2: Select install type

Step 4: Select install folder

The default install path will be <User home>/TestRail_Client. You can select another path with "Browse" button.




Figure3: Select install folder

Step 5: Select install components

Please select install components, the core component "TMP core component" is the must item to install.




Figure 4: Install components select

Step 6 License agreement

Please accept the license before next step.



Figure5: Accept the license

Step 7 Create Start Menu shortcuts (Windows)

On Windows platform, setup wizard will create shortcuts in "Start Menu" for your future launch.




Figure6: Start Menu shortcut create

Step 8 install

Click "install" button to install software.




Figure7: Install software

2.2.2 Manually install

If you download a source package like: tmp_client_216xx_installer_src_all.tar.gz You can use 7zip extract the source code on windows or tar command line (tar -xv -f tmp_client_216xx_installer_src_all.tar.gz) on Linux.

Place the source folder as you want.

3 Launch TMP Client

3.1 TMP Client initial setting (console mode)

This section is for TMP Client run in console mode only. For GUI mode initial setting will be launched after GUI start.

We can find the initial setting file from:

- 1. First launch: <cli>ent_install_path>/conf/default.ini
- 2. Future launch:<user_home_path>/client_conf/<machine_name>.ini

The xxx.ini file contains two kinds of sections:

- a) Section without "tmp_": Client software setting section
- b) Section with "tmp_": Client setting section.

3.1.1 Software setting section

Please use software name as the section name.

max_insts: used to define the maximum instances number for this software (launched number).

scan dir: Client will automatically scan this path to add new software builds.

version and path pairs: user specify the software version and the path manually.

You can specify as much version path pair as you like.

3.1.2 Machine setting section

Group: setting the Client group name.

Private: value can be "0" or "1", the default name is "1" if not present.

"0": public Client will run assigned and matched task.

"1": private Client will run assigned task only.

Terminal: Client name setting, client will scan machine name if not present.

Unattended: The value can be "0" or "1". The default value is "0" if option not present.

"0": Attended Mode. SW will do some special work (i.e. SW update) under user's operation.

"1": Unattended Mode. SW will do some special work (i.e. SW update) automatically.

Debug: Client run in debug mode or not.

"0": Client will run in normal mode.

"1": Client will run in debug mode.

3.1.3 Preference setting section

Link_mode: value can be "both", "remote" and "local". Client linked server select.

Max_threads: Maximum threads (test case) can be launched.

Thread mode: value can be "auto" and "manual"

Task_mode: auto, serial and parallel.

Auto: Client will take top priority level tasks and run parallel these tasks.

Serial: Client will run task one by one according to the task priority

Parallel: Client will run tasks in parallel mode

Work space: Client workspace, client will download and run case in this folder.

Save_space: Client result save space. If not, present client will skip copy case runtime results.

3.2 launch from Start Menu (Windows)

On Windows platform we can launch TMP Client from start menu.

Please click "Start Menu" → "All Programs" → "TestRail Client" → "Client"




Figure8: Launch from start menu

3.3 launch from command line

Please use following command lines to launch client:

- 1) <cli>client_install_path>/bin/clientc.exe -c (console mode)
- 2) <cli>client_install_path>/bin/client.exe (GUI mode)
- 3) Java –jar <client_install_path>/bin/client.jar –c (console mode)
- 4) Java –jar <client_install_path>/bin/client.jar (GUI mode)

3.4 TMP Client initial setting (GUI mode)

3.4.1 Welcome setting

You will be prompted a welcome setting dialog like following:




Figure9: Welcome setting

You can specify 'work space' and 'save space' and click 'Apply' button to finish the setting. Also, you can click the "Don't show welcome setting next time" check box to disable this dialog prompted next time.

3.4.2 Client setting

Click "Setting" → "Client..."

Run client setting in GUI way. Please refer 3.1.2 for details option descriptions.



Figure 10: Client Setting

3.4.3 Software setting

Click "Setting" → "Software..."

Run software setting in GUI way. Please refer 3.1.1 for details option descriptions.




Figure 11: Software Setting

3.4.4 Preference setting

Click "Setting" → "Preference..."

Run Preference setting in GUI way. Please refer 3.1.3 for details




Figure 12: Preference Setting

4 TMP Client usage

4.1 Main window introduction

4.1.1 Overview

Client main view constructed by 5 sections:

- 1) Menu bar
- 2) Rejected queue panel
- 3) Captured queue panel
- 4) Watching task panel

5) Status bar




Figure 13: Client main view

4.1.2 Menu bar

4.1.2.1 File menu

"Import...": Allow you import and run a standard test suite (suite Excel file, suite path)

"Exit": Exit/Close software. (If you just click close button on the main view, client will just close the window and hide. You can re-open the client window from system tray.)

4.1.2.2 View menu

Actions for "watching task panel (4)":

"All": Show all task cases in this task.

"Waiting": Show waiting task cases in this task.

"Processing": Show processing task cases in this task.

"Failed": Show failed task cases in this task.

"Passed": Show passed task cases in this task.

"TBD": Show TBD task cases in this task.

"Timeout": Show timeout task cases in this task.

[&]quot;Export...": Export test report.

4.1.2.3 Run menu

Actions for "Captured queue panel (3)" and "watching task panel (4)"

"Play": action for "Captured queue panel (3)", when there is a captured task selected, "Play" will restart this task.

"Pause": action for "Captured queue panel (3)", when there is a captured task selected, "Pause" will pause this task.

"Stop": action for "Captured queue panel (3)", when there is a captured task selected, "Stop" will stop this task.

"Retest" action for "watching task panel (4)". Retest the test case in watching task according with the condition selected.

4.1.2.4 Tools menu

4.1.2.4.1 Upload

Integrated tool, allow you to update standard test suite to TMP server.




Figure 14: Suite upload dialog

Please input your user name and pass word given by TMP admin.

Use "Select" button to select test suite you want to upload to server.

Click "Upload" button to start upload.

All output lines will be shown in "Upload Console Outputs" window.

4.1.2.4.2 Keygen

Integrated tool, allow you generate encryption code for your account and password which will be show on TMP website (auth_key = xxx)



Figure 15: Key generate

4.1.2.5 Setting menu

Client setting, refer to 3.4 section

4.1.2.6 Control menu

Client control, we shutdown/restart client or host machine.

4.1.2.7 Help menu

"Usage": show this help document and some demo usage.

"Contact": create email and send to Client developer.

"About": show client version information

4.1.3 Rejected queue panel

All rejected tasks will be shown here with queue name and rejected reason.

You can select one queue and make a right click to popup a "popup menu", click "Details" to show details information:




Figure 16: Detail rejects view

You will be shown request values and current client value.

4.1.4 Captured queue panel

All captured tasks will be shown here with queue name and current status.

You can select one queue and make a right click to popup a "popup menu" like following:

Captured	Queue	2		Status
110@run	1723	1	T+ an	Running
110@run	1356	1	T+ sil	Finished
110@run	1220	1	silicon	Finished
110@run	1219	1	T+ an	Finished
110@run	1212	1	T+ sil	Finished
110@run	1757	1	T+ sil	
110@run	1757		Show	inished
110@run	1757			inished
110@run	1757		Sort	inished
110@run	1757		Soft	inished
110@run	1757		Run	D1
110@run	1757		Run	Play
110@run	1757			Pause
110@run	1757		Details	Stop
110@run	1757		Results	
110@run	1757		0.1.5	inished
110@run	1757		Submit	inished
110@run	1757			inished
110@run	1757		Delete	inished
110@run	1757	1	1 mm	Finished
110@run	1757	1	T+ an	
110@run	1757	1	T+ an	
110@run	1757	1	T+ sil	Finished

Figure 17: Captured panel popup menu

"Show": click this button will show detail run case info in "watching task panel (4)"

"Sort → Priority": Sorting captured queue according queue priority

"Sort → RunID": Sorting captured queue according to queue run ID

"Sort → Time": Sorting captured queue according queue time

"Sort → Status": Sorting captured queue according queue status

"Run → Play": same function as 4.1.2.3 Run menu, make the select captured queue re-start

"Run → Pause": same function as 4.1.2.3 Run menu, make the select captured queue pause

"Run \rightarrow Stop": same function as 4.1.2.3 Run menu, make the select captured queue stop

"Details": Show detail information about this queue

"Results": Open the run location for this queue

"Submit": Generate the submit code (used for code check-in)

"Delete": Delete this queue and it's run results

4.1.5 Watching task panel

Watching task panel will show task queue data.

You can select one task case and make a right click to popup a "popup menu" like following:

ID Suite	Design	Status	Reason	Elapsed Time
	SDC cases/02 create generated c		ERROR	0h 0m 12s
	SDC cases/02 create generated c		ERROR	0h 0m 12s
	SDC cases/03 set clock latency/n.		ERROR	0h 0m 12s
	SDC cases/03 set clock latency/r		ERROR	0h 0m 12s
			ERROR	
m0 1 T+ analy m0 1 T+ analy			NA	0h 0m 12s 0h 0m 22s
	SDC cases/03 set clock latency/s		ERROR	0h 0m 12s
			ERROR	0h 0m 12s
			NA	0h 0m 12s 0h 0m 21s
	SDC cases/09 set min delay/fall			
	SDC cases/09 set min delay/fro		NA	0h 0m 21s
m0 1 T+ analy		Passed	NA	0h 0m 21s
	SDC cases/02 create generated c		NA	0h 0m 21s
	SDC cases/09 set min delay/fro	Passed	NA	0h 0m 21s
	SDC cases/09 set min delay/fro	Passed	NA	0h 0m 21s
	SDC cases/09 set min delay/fro		NA	0h 0m 21s
	SDC cases/09 set min delay/fro	Passed	NA	0h 0m 21s
	SDC cases/09 set min delay/thro		NA	0h 0m 21s
	SDC cases/09 set min delay/to c	. Passed	NA	0h 0m 21s
m0 1 T+ analy	SDC cases 107 lelay/a	Passed	NA	0h 0m 21s
m0 1 T+ analy		Passed	NA	0h 0m 21s
m0 1 T+ analy	SDC cases Terminate lelay/cl	. Passed	NA	0h 0m 21s
m0 1 T+ analy	SDC cases lelay/cl	. Passed	NA	0h 0m 21s
m0 1 T+ analy		1	NA	0h 0m 21s
m0 1 T+ analy	SDC cases View All	1	NA	0h 0m 21s
m0 1 T+ analy	SDC cases Wait	ing 1	ERROR	0h 0m 11s
m0 1 T+ analy	CD C Defails	essing 1	NA	0h 0m 21s
m0 1 T+ analy	SDC cases Results	- 1	NA	0h 0m 21s
m0 1 T+ analy		d i	NA	0h 0m 21s
	SDC cases/14 new featur Passe	d i	NA	0h 0m 20s
	SDC cases/14 new featur	1	NA	0h 0m 31s
m0 1 T+ analy		i	NA	0h 0m 41s
	SDC cases/15 wildcard v Time		NA	0h 0m 40s
	SDC cases/15 wildcard v	Out 1	NA	0h 0m 40s
		d i	ERROR	0h 0m 10s
	SDC cases/04 set clock (SDC cases/13 DRC/01 create cl		ERROR	
				0h 0m 15s
	SDC cases/13 DRC/01 create cl		ERROR	0h 0m 15s
	SDC cases/13 DRC/01 create cl		ERROR	0h 0m 15s
	SDC cases/13 DRC/01 create cl		NA	0h 0m 20s
	SDC cases/00 jedi/create clock	Passed	NA	0h 0m 36s
	SDC cases/00 jedi/create generat		NA	0h 0m 31s
	SDC cases/00 jedi/set clock gro		NA	0h 0m 36s
m0 1 T+ analy	SDC cases/00 jedi/set clock late	Passed	NA	0h 0m 31s

Figure 18: Task panel popup menu

4.1.6 Status bar

Status bar will show you current running threads number and current system info like MEM and CPU.

4.2 Launch a local test suite

Step 1: make sure your client not running in remote mode (Setting \rightarrow Preference \rightarrow link server) Step 2: click File \rightarrow import...

4.2.1 import a standard suite file

[&]quot;Retest": will retest this case.

[&]quot;Terminate": will terminate the running case. "View": same function as <u>4.1.2.2</u> view menu. "Details": Show test case detail information. "Results": open the task case result folder.




Figure 19: Import suite file

Here we have 'User suite files inputs' and 'Unit suite files inputs' the only difference is: When you click 'Select' in 'User suite files inputs' Client will go to '<User home>' directory. When you click 'Select' in 'Unit suite files inputs' Client will go to '<cli>client_install_path>/doc/TMP_EIT_suites' directory.

- 1. click 'Select' to find the suite file (Excel file)
- 2. if you have special environment to set, please put it in 'Extra environ'
- 3. 'Case Sort' used to select test case, demo: 'option1=value1, value2;option2=value1' here option1 and option2 are titles in suite file
- 4. Click 'Apply' to start testing

4.2.2 import a suite path




Figure 20: Import suite path

Client also supports a suite path import. Client use 'Key Pattern' for test case identification and 'Execute File' for test script.

4.3 Launch remote test suite

Make sure your client not running in local mode (Setting \rightarrow Preference \rightarrow link server).

4.4 Report output

click File → Export....




Figure 21: Export dialog

Select test queue and the titles for export and generate test report according to the wizard.

4.5 Client info and update

Click 'Help' → 'About' you will see following picture.



Figure 22: About dialog

In this dialog we can see the detail Client version and build date. Click 'Check Update' for developing new Client update.

5 Appendix

Software address: \\lsh-smb04\sw\qa\qa_store\TMP_tools\depend_software

TMP client build: Software QA SVN: /release/tmp_client/