1 Methods

$$\int_{S} \rho \overline{u} \phi \cdot \overline{n} dS = \int_{S} \Gamma \frac{\partial \phi}{\partial x} \cdot \overline{n} dS + \int_{V} q_{\phi} dV \tag{1}$$

We can approximate the two surface integrals as follows:

$$\int\limits_{S} \rho \overline{u} \phi \cdot \overline{n} dS = \left(\rho \underline{(u)} S \phi \right)_{i+1} - \left(\rho \underline{(u)} S \phi \right)_{i-1} \,,$$

and

$$\int\limits_{S} \Gamma \frac{\partial \phi}{\partial x} \cdot \overline{n} dS = \left(\Gamma S \frac{\partial \phi}{\partial x} \right)_{i+1} - \left(\Gamma S \frac{\partial \phi}{\partial x} \right)_{i-1} \,.$$

We can approximate the volume integral as follows:

$$\int\limits_{V} q_{\phi} dV = \overline{q}V \ .$$

If we assume S is constant our transport equation becomes:

$$\left(\rho_{\underline{-}}(u)\phi\right)_{i+1} - \left(\rho_{\underline{-}}(u)\phi\right)_{i-1} = \left(\Gamma\frac{\partial\phi}{\partial x}\right)_{i+1} - \left(\Gamma\frac{\partial\phi}{\partial x}\right)_{i-1} + \overline{q}V.$$

We can apply the Central Differencing Scheme approximations:

$$\phi_{i+1} = \frac{\phi_{I+1} + \phi_I}{2} \qquad \qquad \phi_{i-1} = \frac{\phi_{I-1} + \phi_I}{2}$$

$$\left(\frac{\partial \phi}{\partial x}\right)_{i+1} = \frac{\phi_{I+1} - \phi_I}{\delta x} \qquad \qquad \left(\frac{\partial \phi}{\partial x}\right)_{i-1} = \frac{\phi_I - \phi_{I-1}}{\delta x}$$

The transport equation now looks like:

$$\left(\frac{\rho \overline{u}}{2}\right)_{i+1} (\phi_{I+1} + \phi_I) - \left(\frac{\rho \overline{u}}{2}\right)_{i-1} (\phi_{I-1} + \phi_I) = \frac{\Gamma}{\Delta x} (\phi_{I+1} - \phi_I) - \frac{\Gamma}{\Delta x} (\phi_I - \phi_{I-1}) + \overline{q}_I \Delta x.$$

For this problem, the density and velocity are constant throughout the geometry. We can group terms and get the transport equation in a useful form to sovle.

$$\left[-\frac{\rho \overline{u}}{2} - \frac{\Gamma}{\Delta x} \right] \phi_{I-1} + \left[\frac{2\Gamma}{\Delta x} \right] \phi_I + \left[\frac{\rho \overline{u}}{2} - \frac{\Gamma}{\Delta x} \right] \phi_{I+1} = \overline{q}_I \, \Delta x \tag{2}$$

We can rewrite this equation as:

$$a_I \phi_{I-1} + b_I \phi_I + c_I \phi_{I+1} = Q_I . (3)$$

This equation works for middle nodes, but the edge nodes do not have enough neighbor nodes.

2 Results

Figure 1 shows the two solutions for Case 1: 5 control volumes and $\overline{u} = 0.1 \,\mathrm{m\,s^{-1}}$. Figure 2 shows the two solutions for Case 2: 5 control volumes and $\overline{u} = 2.5 \,\mathrm{m\,s^{-1}}$. Figure 3 shows the two solutions for Case 3: 20 control volumes and $\overline{u} = 2.5 \,\mathrm{m\,s^{-1}}$.




Figure 1: Central Difference Scheme and Analytical Solutions for Case 1.




Figure 2: Central Difference Scheme and Analytical Solutions for Case 2.




Figure 3: Central Difference Scheme and Analytical Solutions for Case 3.

Table 1 lists the error values calculated for each case.

Table 1: Error values for each case.

Case	Error
1	3.213926974817029
2	35.33997019002361
3	2.1977755170786173

3 Discussion