
RTI CORBA Compatibility Kit

CORBA-DDS Example Using Java

Instructions

Version 5.2.3





© 2007-2016 Real-Time Innovations, Inc. All rights reserved. Printed in U.S.A. First printing. April 2016.

Trademarks

Real-Time Innovations, RTI, NDDS, RTI Data Distribution Service, DataBus, Connext, Micro DDS, the RTI logo, 1RTI and the phrase, "Your Systems. Working as one," are registered trademarks, trademarks or service marks of Real-Time Innovations, Inc. All other trademarks belong to their respective owners.

Copy and Use Restrictions

No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form (including electronic, mechanical, photocopy, and facsimile) without the prior written permission of Real-Time Innovations, Inc. The software described in this document is furnished under and subject to the RTI software license agreement. The software may be used or copied only under the terms of the license agreement.

Technical Support

Real-Time Innovations, Inc. 232 E. Java Drive Sunnyvale, CA 94089

Phone: (408) 990-7444 Email: support@rti.com

Website: https://support.rti.com/

CORBA-DDS Example Using JAVA

This document will guide you through the steps required to create a CORBA-DDS publisher and a CORBA-DDS subscriber based on an IDL file. Then it will show you how to adapt those steps to create your own application (the provided example).

The example illustrates how to use the CORBA compatibility kit for *RTI*[®] *Connext DDS* (formerly *RTI Data Distribution Service*) to create applications that use CORBA and DDS and share a common set of types for both APIs.

The example includes:

L	A CORBA server application.
	A Connext DDS subscriber application.
	A combined CORBA client-DDS publisher application. This application uses CORBA
	and DDS to send text messages to the CORBA server and the Connext DDS subscriber.
	Both receiving applications print the messages to the console.

For more information, please see the RTI CORBA Compatibility Kit Installation Guide (<NDDSHOME>/doc/manuals/corba/ RTI_CORBA_Compatibility_Kit_InstallationGuide.pdf).

Paths Mentioned in Documentation

The documentation refers to:

1

□ <NDDSHOME>

This refers to the installation directory for *Connext DDS*.

The default installation paths are:

• UNIX-based systems, non-root user:

/home/your user name/rti_connext_dds-version

• UNIX-based systems, root user:

/opt/rti_connext_dds-version

• Windows systems, user without Administrator privileges:

<your home directory>\rti_connext_dds-version

• Windows systems, user with Administrator privileges:

C:\Program Files\rti_connext_dds-version

(You can specify a different location for the **rti_workspace** directory. See the *RTI Connext DDS Core Libraries Getting Started Guide.*)

You may also see \$NDDSHOME or %NDDSHOME%, which refers to an environment variable set to the installation path.

Wherever you see <NDDSHOME> used in a path, replace it with your installation path.

Note for Windows Users: When using a command prompt to enter a command that includes the path **C:\Program Files** (or any directory name that has a space), enclose the path in quotation marks. For example:

"C:\Program Files\rti_connext_dds-version\bin\rtiddsgen"

or if you have defined the NDDSHOME environment variable:

"%NDDSHOME%\bin\rtiddsgen"

 \Box <path to examples>

Examples are copied into your home directory the first time you run *RTI Launcher* or any script in **<NDDSHOME>/bin**. This document refers to the location of these examples as **<path to examples>.**

Wherever you see <path to examples>, replace it with the appropriate path.

By default, the examples are copied here:

• UNIX-based systems:

/home/your user name/rti_workspace/version/examples

• Windows systems:

<your home directory>\rti_workspace\version\examples

(You can specify that you do not want the examples copied to the workspace. See the *RTI Connext DDS Core Libraries Getting Started Guide.*)

2 Building the Example

The example is in **<path to examples>/connext_dds/java/corba_dds**, where **<path to examples> is:**

For UNIX-based systems:

/home/your user name/rti_workspace/version/examples/

For Windows systems:

C:\Users\your user name\Documents\rti_workspace\version\examples\

It includes the following:

Message.idl: The data types for the example.
MessageApp.java: Messaging application class, which contains the main method Depending on the parameters passed at the command line, the executable will run the <i>Connext DDS</i> subscriber, the CORBA server, or the sender/publisher.
MessageDDSPublisher.java: Class used by the sender to publish messages over DDS.
MessageDDSSubscriber.java: <i>Connext DDS</i> subscriber receiving the sender messages and prints them on the screen.

- ☐ MessageReceiverImpl.java: Class implementing the CORBA server interface based on the IDL interface MessageReceiver. When the method sendMessage is invoked the CORBA server will print the input message on the screen.
- ☐ **IDL Generated files:** These files are generated automatically by the JacORB IDL compiler and by *rtiddsgen*.

Follow these steps to compile the example application:

- **1.** Set Up Your Environment (Section 2.1)
- **2.** Generate the Source Code (Section 2.2)
- **3.** Modify the Publisher Data (Section 2.3)
- **4.** Compile the Publisher and Subscriber (Section 2.4)
- 5. Run the Example Publisher and Subscriber (Section 2.5)
- **6.** Use the Generated Files to Build the CORBA Example Application (Section 2.6)

2.1 Set Up Your Environment

Define the following environment variables:

- ☐ JAVA_HOME=<path to your JDK installation directory>
- ☐ **JAC_ORB**=<path to your JAC-ORB installation directory>
- □ **NDDSHOME**=<path to your Connext DDS installation directory>

Examples:

```
setenv JAVA_HOME /local/Java/jdk1.7
setenv JAC_ORB /local/JacORB-2.2.4
setenv NDDSHOME /home/your user name/rti connext dds-5.x.y
```

2.2 Generate the Source Code

To generate the source code, use JacORB's IDL code generator and *rtiddsgen* (*Connext DDS*'s IDL code generator):

- 1. Copy the example's IDL file (Message.idl) into a new directory of your choice.
- 2. Generate the CORBA support files by entering the following in a command shell:

```
$JAVA_HOME/bin/java -classpath \
$JAC_ORB/lib/idl.jar:$JAC_ORB/lib/logkit-1.2.jar \
org.jacorb.idl.parser -d . Message.idl
```

The above command will generate the following CORBA support files:

- DateTime.java, DateTimeHelper.java, DateTimeHolder.java
- Message.java, MessageHelper.java, MessageHolder.java
- MessageReceiver.java, MessageReceiverHelper.java
- MessageReceiverHolder.java
- MessageReceiverPOA.java, MessageReceiverPOATie.java
- MessageReceiverOperations.java, _MessageReceiverStub.java
- MSG_MAX_LENGTH.java
- USER_QOS_PROFILES.XML

3. Generate the *Connext DDS* support files:

```
$NDDSHOME/bin/rtiddsgen -typecode -language Java \
  -example <arch> -corba Message.idl
```

In the above commands, replace <arch> with your target architecture name. To recall your target architecture name, look in your \${NDDSHOME}/lib directory; an example is i86Linux2.6gcc4.1.2.

The above command will generate the following *Connext DDS* support files:

- DateTimeSeq.java, DateTimeTypeCode.java, DateTimeTypeSupport.java
- MessageSeq.java, MessageDataReader.java, MessageDataWriter.java
- MessageTypeSupport.java, MessageTypeCode.java
- MesssagePublisher.java, MessageSubscriber.java
- makefile_Message_<arch>

2.3 Modify the Publisher Data

You will need to modify the data sent by the DDS Publisher before compiling and running the Publisher and Subscriber. You can do so by editing **MessagePublisher.java** (in the same directory you created in Step 1 on Page 3) as follows:

```
for (int count = 0;
    (sampleCount == 0) || (count < sampleCount);
    ++count) {
    System.out.println("Writing Message, count " + count);

    /* Modify the instance to be written here */
    instance.time = new DateTime();
    instance.msg = "Hello World! (" + count + ")";

    /* Write data */
    writer.write(instance, instance_handle);
    try {
        Thread.sleep(sendPeriodMillis);
    } catch (InterruptedException ix) {
        System.err.println("INTERRUPTED");
        break;
    }
}</pre>
```

2.4 Compile the Publisher and Subscriber

In the same directory that you created in Step 1 on Page 3, enter the following:

```
gmake -f makefile_Message_<arch>
```

This will create the .class files in the same directory.

Note: gmake will fail if you do not have **javac** on your path.

See the RTI Connext DDS Core Libraries Getting Started Guide for more on how to compile rtidds-gen-generated code.

2.5 Run the Example Publisher and Subscriber

You have now successfully created a publisher and a subscriber for the CORBA data types included in the IDL file, **Message.idl**.

Run the applications in two separate terminals:

```
    gmake ARGS="<Domain_ID> <Number_of_Samples>" \
        -f makefile_Message_<arch> MessagePublisher
    gmake ARGS="<Domain_ID> <Number_of_Samples>" \
            -f makefile_Message_<arch> MessageSubscriber
```

Note that your environment will need to be set up according to Section 2.1 in each terminal.

Please refer to the RTI Connext DDS Core Libraries Getting Started Guide for more on how to run rtiddsgen-generated Publisher and Subscriber applications.

Example output from Message_publisher:

```
Writing Message, count 0
Writing Message, count 1
Writing Message, count 2
```

Example output from Message_subscriber:

```
Received:
    time :
        year: 0
        month: 0
        day: 0
        hour: 0
        minute: 0
        second: 0
    msg: Hello World! (0)
```

2.6 Use the Generated Files to Build the CORBA Example Application

This section describes how to use the code generated by JacORB's IDL generator and *rtiddsgen* to build a custom application:

- The custom application code has already been provided for you in <path to examples¹>/
 corba/java in the following files:
 - MessageDDSPublisher.java
 - MessageDDSSubscriber.java
 - MessageReceiverImpl.java
 - MessageApp.java

Copy these files into the directory that contains the files you generated in Section 2.2.

- **2.** Edit **makefile_Message_<arch>** as follows:
 - a. Add the new java files to JAVA_SOURCES.
 - **b.** Add the following rule to run **MessageApp**:

Note: You must <u>use a TAB before \$(JAVA_PATH)</u>, not spaces.

On UNIX-based systems:

```
MessageApp: ./MessageApp.class
$(JAVA_PATH) -classpath ".:$(RTI_CLASSPATH)" \
-Dorg.omg.CORBA.ORBClass=org.jacorb.orb.ORB \
-Dorg.omg.CORBA.ORBSingletonClass=org.jacorb.orb.ORBSingleton \
MessageApp $(ARGS)
```

^{1.} See Building the Example (Section 2)

On Windows systems:

```
MessageApp: ./MessageApp.class
$(JAVA_PATH) -classpath ".;$(RTI_CLASSPATH)" \
-Dorg.omg.CORBA.ORBClass=org.jacorb.orb.ORB \
-Dorg.omg.CORBA.ORBSingletonClass=org.jacorb.orb.ORBSingleton \
MessageApp $(ARGS)
```

- **c.** Save the new makefile as **makefile_MessageApp**.
- 3. Compile your application:

```
gmake -f makefile_MessageApp
```

3 Running the Example

You will need three separate command shells.

1. In the first command shell, run the CORBA server:

```
> gmake -f makefile MessageApp MessageApp ARGS="-cr Message.ior"
```

Message.ior is the name for a file that will be created by the CORBA server within the application to store its IOR (Interoperable Object Reference). The client will use this file in Step 3.

2. In the second terminal, run the *Connext DDS* subscriber:

```
> gmake -f makefile_MessageApp MessageApp ARGS="-nr <domainId>"
```

The domain ID is required. Only applications using the same domain ID will communicate with each other.

3. In the third terminal, run the client (sender) application:

```
> gmake -f makefile_MessageApp MessageApp \
    ARGS="-s Message.ior <domainId>"
```

The domain ID is required. Use the same value that you used for the subscriber.

The application will output a prompt as follows:

```
sender>
```

4. Type some messages at the prompt; they will be sent to the CORBA server and to the *Connext DDS* subscriber applications.