Estimating Model Parameters

Least Squares

Estimating σ^2

The Coefficient of Determination

A Linear Probabilistic Model

There are parameters β_0 , β_1 and σ^2 , such that for any fixed value of the independent variable x, the dependent variable is a random variable related to x through the **model equation**

$$Y = \beta_0 + \beta_1 x + \epsilon \tag{1}$$

The quantity ϵ in the model equation is a random variable, assumed to be normally distributed with

$$E(\epsilon) = 0$$
, $Var(\epsilon) = \sigma^2$.

Parameter Estimation


- ▶ Sample data consists of n pairs $(x_1, y_1), \dots, (x_n, y_n)$
- These observations are assumed to have been obtained independently of one another.


That is, y_i is the observed value of Y_i , where $Y_i = \beta_0 + \beta_1 x_i + \epsilon_i$ and the n deviations $\epsilon_1, \epsilon_2, \epsilon_n$ are independent rv's.

▶ The values of β_0, β_1 , and σ^2 remain to be estimated.

Least Squares

- A good estimate for regression line should be the one that observed points are scattered rather closely about this line.
- ► A measure of closeness is the vertical distances (deviations) from the observed points to the line.
- ► The best-fit line is then the one having the smallest possible sum of squared deviations.





Principle of Least Squares (Ordinary Least Squares or OLS)

The vertical deviation of the point (x_i, y_i) from the line $y = b_0 + b_1 x$ is

height of point – height of line =
$$y_i - (b_0 + b_1 x_i)$$

► The sum of squared vertical deviations from the points $(x_1, y_1), \dots, (x_n, y_n)$ to the line is then

$$f(b_0, b_1) = \sum_{i=1}^{n} (y_i - (b_0 + b_1 x_i))^2$$

- ▶ The point estimates of β_0 and β_1 , denoted by $\hat{\beta}_0$ and $\hat{\beta}_1$ and called the **least squares estimates**, are those values that minimize $f(b_0, b_1)$.
- ► The estimated regression line or least squares line is then the line whose equation is $y = \hat{\beta}_0 + \hat{\beta}_1 x$.

The minimizing values of b_0 and b_1 are found by taking partial derivatives of $f(b_0, b_1)$ with respect to both b_0 and b_1 , equating them both to zero [analogously to f'(b) = 0 in univariate calculus], and solving the equations

$$\frac{\partial f(b_0, b_1)}{\partial b_0} = \sum 2(y_i - b_0 - b_1 x_i)(-1) = 0$$

$$\frac{\partial f(b_0, b_1)}{\partial b_1} = \sum 2(y_i - b_0 - b_1 x_i)(-x_i) = 0$$

Least Square Estimator

▶ The least squares estimate of the slope coefficient β_1 of the true regression line is

$$b_1 = \hat{\beta}_1 = \frac{\sum (x_i - \bar{x})(y_i - \bar{y})}{\sum (x_i - \bar{x})^2} = \frac{S_{xy}}{S_{xx}}$$

Computing formulas for the numerator and denominator of \hat{eta}_1 are

$$S_{xy} = \sum x_i y_i - \left(\sum x_i\right) \left(\sum y_i\right) / n$$
 $S_{xx} = \sum x_i^2 - \left(\sum x_i\right)^2 / n$

▶ The least squares estimate of the intercept β_0 of the true regression line is

$$b_0 = \hat{\beta}_0 = \frac{\sum y_i - \hat{\beta}_1 \sum x_i}{n} = \bar{y} - \hat{\beta}_1 \bar{x}$$

► The computational formulas for S_{xy} and S_{xx} require only the summary statistics $\sum x_i, \sum y_i, \sum x_i^2$ and $\sum x_i y_i$.

Standard Error of $\hat{\beta}_1$

$$Var\left(\hat{\beta}_{1}\right) = Var\left(\frac{\sum (x_{i} - \bar{x})(Y_{i} - \bar{Y})}{\sum (x_{i} - \bar{x})^{2}}\right)$$

$$= Var\left(\frac{\sum (x_{i} - \bar{x})Y_{i}}{S_{xx}}\right) = Var\left(\sum \frac{x_{i} - \bar{x}}{S_{xx}}Y_{i}\right)$$

$$= \sum \frac{(x_{i} - \bar{x})^{2}}{S_{xx}^{2}}Var(Y_{i}) = \frac{S_{xx}}{S_{xx}^{2}}\sigma^{2} = \frac{\sigma^{2}}{S_{xx}}$$

So the standard error of $\hat{\beta}_1$ is

$$s_{\hat{eta}_1} = rac{\sigma}{\sqrt{S_{\sf xx}}}$$

Example

Following data are on x= iodine value (g) and y= cetane number for a sample of 14 biofuels

Calculating the summary statistics

$$\sum x_i = 1307.5, \quad \sum y_i = 779.2,$$

$$\sum x_i^2 = 128913.93, \quad \sum x_i y_i = 71347.30, \quad \sum y_i^2 = 43745.22$$

from which

$$S_{xx} = 128913.93 - (1307.5)^2/14 = 6802.7693$$

 $S_{xy} = 71347.30 - (1307.5)(799.2)/14 = -1424.41429$

Example Cont'd

The estimated slope of the true regression line (i.e., the slope of the least squares line) is

$$\hat{\beta}_1 = \frac{S_{xy}}{S_{xx}} = \frac{-1424.41429}{6802.7693} = -0.209$$

We estimate that the expected change in true average cetane number associated with a 1g increase in iodine value is -0.209, i.e., a decrease of 0.209.

Since $\bar{x}=93.392857$ and $\bar{y}=55.657143$, the estimated intercept of the true regression line is

$$\hat{\beta}_0 = \bar{y} - \hat{\beta}_1 \bar{x} = 55.658 - (-0.209)(93.393) = 75.21$$

The equation of the estimated regression line (least squares line) is y = 75.21 - 0.209x.



Example Cont'd




Figure: Scatter plot for data with least square line superimposed.

Remarks

- Be sure that the scatter plot shows a linear pattern with relatively homogenous variation before fitting the simple linear regression model.
- ► The least squares line should not be used make a prediction for an x value much beyond the range of observed data. The danger of extrapolation is that the fitted relationship may not be valid for such x values.

Estimating σ^2

The parameter σ^2 determines the amount of variability inherent in the regression model. A large value of σ^2 will lead to observed (x_i, y_i) 's that are quite spread out about the true regression line, whereas when σ^2 is small the observed points will tend to fall very close to the true line.




Figure: Typical sample for σ^2 : (a)small; (b)large.

Estimating σ^2

An estimate of σ^2 will be used in confidence interval (CI) formulas and hypothesis-testing procedures.

Many large deviations (residuals) suggest a large value of σ^2 , whereas deviations all of which are small in magnitude suggest that σ^2 is small.

Definition


▶ The **fitted values** (or predicted values) $\hat{y}_1, \dots, \hat{y}_n$ are obtained by successively substituting x_1, \dots, x_n into the equation of the estimated regression line:

$$\hat{y}_1 = \hat{\beta}_0 + \hat{\beta}_1 x_1, \cdot, \hat{y}_n = \hat{\beta}_0 + \hat{\beta}_1 x_n$$

▶ The **residuals** are the differences $y_1 - \hat{y}_1, y_2 - \hat{y}_2, \dots, y_n - \hat{y}_n$ between the observed and fitted y values.



After fitting a regression line to the data, the residuals are identified by the vertical line segments from the observed points to the line.



Estimating σ^2

► The error sum of squares (equivalently, residual sum of squares), denoted by SSE, is

$$SSE = \sum (y_i - \hat{y}_i)^2 = \sum (y_i - (\hat{\beta}_0 - \hat{\beta}_1 x_i))^2$$

▶ The estimate of σ^2 is

$$\hat{\sigma}^2 = s^2 = \frac{SSE}{n-2} = \frac{\sum (y_i - \hat{y}_i)^2}{n-2}$$

The n-2 df comes from the fact that when obtaining s^2 , the two parameters β_0 and β_1 must first be estimated, which results in a loss of 2 df.

A Shortcut Formula to Calculate SSE

Computation of SSE from the defining formula involves much tedious arithmetic, because both the predicted values and residuals must first be calculated.

Use of the following computational formula does not require these quantities.

$$SSE = \sum y_i^2 - \hat{\beta}_0 \sum y_i - \hat{\beta}_1 \sum x_i y_i$$