This is a collection of steps that I used, with a few alterations and changes for my specific needs, in order to set up my Plex server using Ubuntu 16.04.

In all the commands that are listed you can substitute the user "plex" for your specific user, be sure to also replace "plex" in all of the paths that are listed.

The guides should show the most recent version of the programs, you will want to check the provided sites to ensure that you have the most up to date version of the program. All of the instruction should still be the same.

How To Setup A Headless Media Server Using Ubuntu 16.04 and Plex Software

Pre-Install:

Power on your machine and set your BIOS settings to boot from CD/DVD.

After doing so, insert your Ubuntu DVD installer and boot from it. When your machine successfully booted up, you'll be prompted with a menu, similar to the image shown below


Step 1: Select Installer Language

Language			
Amharic	Français	Македонски	Tamil
Arabic	Gaeilge	Malayalam	ජිවාහා
Asturianu	Galego	Marathi	Thai
Беларуская	Gujarati	Burmese	Tagalog
Български	עברית	Nepali	Türkçe
Bengali	Hindi	Nederlands	Uyghur
Tibetan	Hrvatski	Norsk bokmål	Українська
Bosanski	Magyar	Norsk nynorsk	Tiếng Việt
Català	Bahasa Indonesia	Punjabi (Gurmukhi)	中文(简体)
Čeština	Íslenska	Polski	中文(繁體)
Dansk	Italiano	Português do Brasil	
Deutsch	日本語	Português	
Dzongkha	ქართული	Română	
Ελληνικά	Қазақ	Русский	
English	Khmer	Sámegillii	
Esperanto	ಕನ್ನಡ	ສິ∘ຑ⊚	
Español	한국어	Slovenčina	
Eesti	Kurdî	Slovenščina	
Euskara	Lao	Shqip	
ىسراف	Lietuviškai	Српски	
Suomi	Latviski	Svenska	


Step 2: Select Install Ubuntu Server 16.04



Step 3: Select the Operating System Language



Step 4: Select the Server Location




Step 5: Keyboard Detection

Select no unless you have a custom keyboard configuration you need to select separately.



Select the Country Origin for your keyboard



Select the layout for the keyboard.

```
[!] Configure the keyboard
Please select the layout matching the keyboard for this machine.
Keyboard layout:
English (US) – Cherokee
English (US) - English (Colemak)
English (US) – English (Dvorak alternative international no dead keys)
English (US) – English (Dvorak)
English (US) – English (Dvorak, international with dead keys)
English (US) - English (Macintosh)
English (US) – English (Programmer Dvorak)
English (US) - English (US, alternative international)
English (US) – English (US, international with dead keys)
English (US) - English (US, with euro on 5)
English (US) - English (Workman)
English (US) – English (Workman, international with dead keys)
English (US) – English (classic Dvorak)
English (US) – English (international AltGr dead keys)
English (US) – English (left handed Dvorak)
English (US) – English (right handed Dvorak)
English (US) – English (the divide/multiply keys toggle the layout)
English (US) - Russian (US, phonetic)
English (US) - Serbo-Croatian (US)
    <Go Back>
```


Step 6: Network configuration

The installer will auto detect the network settings. If you are using wireless, you may need to set this up manually.



Step 7: Choose a Hostname

Select a "nickname" for your server.




Step 8: Server User Fullname

Provide a Fullname for the primary account. This is not the root (administrator) user. This user can temporarily gain admin privileges using <code>sudo</code>. You will select the username in the next step.




Step 9: Server Username

Then provide the login username for the primary account.



Step 10: Server Password


Select a password for the user created above. You will have to re-enter the password to confirm.



If you are using a weak password there will be 1 more prompt that will ask if you would like to use a stronger password.


Step 11: Home Directory Encryption

Generally speaking, you do not have to encrypt your home directory. This is up to you whether you would like to or not. I selected No.




Step 12: Confirm Timezone

Confirm that the correct timezone is selected.




Step 13: Ubuntu Server Drive Partitioning

I selected "Guided - use entire disk. I have a 1TB SSD dedicated for the OS, and will create a volume of other HDD for the storage that I combined later once everything else was set up.




Step 14: Write the Partitions to Disk

Because partitioning is critical, you will be asked one more time to confirm before partitions will be written to the hard disk.




Step 15: Base Ubuntu 16.04 Server Installation

After partitioning, the installer continue to install Ubuntu Server 16.04 base system. Nothing to do here than wait for it to complete.




Step 16: Setup HTTP Proxy

In typical Ubuntu Home Server setup, this is generally not needed. So, leave it blank and continue to install Ubuntu 16.04 Server.



Step 17: Setup Automatic Updates


Ubuntu Server can automatically install updates when they are available. While this can break things sometimes installing just the security updates shouldn't. So I recommend installing security updates automatically on your Ubuntu home server.



When non-security updates are available, you will see a notification upon login and you can force an update using sudo apt-get upgrade command.

Step 18: Ubuntu Server Tasksel


After partitioning, this is the step that requires most user intervention. You will have to select what services you want to install on your Ubuntu 16.04 Server. "Standard System Utilities" should already be selected. In addition, for a typical Ubuntu homeserver setup, I recommend Sambe file server and OpenSSH server as well.



Samba will allow you to use shared drives to connect with other computers to add/remove files on and off of the server where OpenSSH Server will allow you to remote into the box rather than requiring you to have a monitor and keyboard always connected.


Step 19: GRUB Notification

GRUB is the boot menu that is shown immediately after your Ubuntu Server powers on. It shows a list of all OS installed on the system. It is installed to the hard drive containing the OS. In most cases this is /dev/sda. Select Yes to continue and the installation will continue and finish up.



Step 20: Reboot Ubuntu Server

And the Installation is complete! Hit Enter to reboot and you will then be prompted to log in with the information we set up in steps 9 and 10..



Step 21: Update Ubuntu and Security settings

Run sudo apt-get update
sudo apt-get upgrade -y
sudo apt dist-upgrade -y

Step 22: Reboot!

Type in sudo reboot

Setup and Install SSH

If you did not install OpenSSH Server from the above you can also install the same way here. If you did install as part of the installation package, go ahead and skip to Step 2.

Step 1: Install Open-SSH

Inside your Ubuntu Terminal type in sudo apt-get install openssh-server

Step 2: Modify the SSH Configuration

Type in sudo nano /etc/ssh/sshd_config and modify the configuration to what yours needs are for the ssh. I have highlighted the 2 items that I personally changed for security of my own server. Port so that I am not using the default port and which users are allowed to use SSH.

```
# Package generated configuration file
```

See the sshd config(5) manpage for details

What ports, IPs and protocols we listen for

Port 3333

Use these options to restrict which interfaces/protocols sshd will bind to

#ListenAddress ::

#ListenAddress 0.0.0.0

Protocol 2

HostKeys for protocol version 2

HostKey /etc/ssh/ssh host rsa key

HostKey /etc/ssh/ssh host dsa key

HostKey /etc/ssh/ssh host ecdsa key

HostKey /etc/ssh/ssh host ed25519 key

#Privilege Separation is turned on for security

UsePrivilegeSeparation yes

AllowUsers plex

Step 3: Restart the SSH Service

Type in sudo service ssh restart

Set Static IP Address for the Server

Step 1: Find the interface you need to use.

Type in ifconfig -a

```
plexQubuntu:~$ ifconfig -a
ens33
          Link encap:Ethernet HWaddr 00:0c:29:04:7b:16
          inet addr:192.168.80.131 Bcast:192.168.80.255 Mask:255.255.255.0
          inet6 addr: fe80::20c:29ff:fe04:7b16/64 Scope:Link
          UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
          RX packets:8 errors:0 dropped:0 overruns:0 frame:0
          TX packets:13 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:1000
          RX bytes:1048 (1.0 KB) TX bytes:1542 (1.5 KB)
lo
          Link encap:Local Loopback
          inet addr:127.0.0.1 Mask:255.0.0.0
          inet6 addr: ::1/128 Scope:Host
          UP LOOPBACK RUNNING MTU:65536 Metric:1
          RX packets:160 errors:0 dropped:0 overruns:0 frame:0
          TX packets:160 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:1
          RX bytes:11840 (11.8 KB) TX bytes:11840 (11.8 KB)
```

For this we will use ens33 as the interface that we will set the IP for.

Step 2: Edit the Interfaces file

Type in sudo nano /etc/network/interfaces

```
iface <interface> inet static
address 192.168.0.100
netmask 255.255.255.0
gateway 192.168.0.1
dns-nameservers 8.8.8.8 8.8.4.4
```

For the <interface> we will set that to the ens33. For the dns-nameservers, the above is the google dns, however, if you do know your own information from your provider, you will want to use that information.

Step 3: Restart the service or the Server


Type in sudo /etc/init.d/networking restart to restart the service or sudo reboot to restart the entire server

At this point you will be able to use that Static IP for the SSH. For example if this was your server you could use Putty.exe and use the IP 192.168.0.100:3333 to SSH in as long as you are on your local network. You can obtain Putty from http://www.putty.org

Plex Installation

Step 1: Obtain the Download File

Go to https://www.plex.tv/media-server-downloads/ and select the platform as Linux, then click on 'Choose Distribution'



Right click on Ubuntu 64-bit (14.04 or newer) and click on 'copy link address'

Step 2: Download the Install File

Type in sudo wget <paste the link you copied from Step 1> (You can see the full command how it looks in the image below.

```
plexQubuntu: $\times$ sudo wget https://downloads.plex.tv/plex-media-server/1.13.9.5439-7303bc002/plexmedia server_1.13.9.5439-7303bc002_amd64.deb
[sudo] password for plex:
--2018-10-18 09:24:51-- https://downloads.plex.tv/plex-media-server/1.13.9.5439-7303bc002/plexmedia server_1.13.9.5439-7303bc002_amd64.deb
Resolving downloads.plex.tv (downloads.plex.tv)... 104.18.156.41, 104.18.157.41, 2400:cb00:2048:1::6
812:9c29, ...
Connecting to downloads.plex.tv (downloads.plex.tv)|104.18.156.41|:443... connected.
HTTP request sent, awaiting response... 200 OK
Length: 103298298 (99M) [application/octet-stream]
Saving to: 'plexmediaserver_1.13.9.5439-7303bc002_amd64.deb'

plexmediaserver_1.13.9.5 100%[============================]] 98.51M 40.0MB/s in 2.5s
2018-10-18 09:24:54 (40.0 MB/s) - 'plexmediaserver_1.13.9.5439-7303bc002_amd64.deb' saved [103298298/103298298]
```

Step 3: Install the Package

Type in sudo dpkg -i <ple>plexmediaserver
package</pr>
just downloaded in Step 2> You can
also type plex then <tab> and it will auto fill the package ending in .deb. Make sure that you are in
the same directory that you downloaded the file into when you run this command.

```
plex@ubuntu:~$ ls
plexmediaserver_1.13.9.5439-7303bc002_amd64.deb
plex@ubuntu:~$ sudo dpkg -i plexmediaserver_1.13.9.5439-7303bc002_amd64.deb
```

Step 4: Log into Plex

You should be able to open up your browser and then navigate to http://192.168.0.100:32400/manage we use that IP because that is the one that we set the server up as the static ip. You will want to input whatever IP you set as your Static. You will then be able to claim and set up your Plex Server from that point.

Additional Installation Information

Docker Installation (These steps are the same as listed in the site below)

https://docs.docker.com/install/linux/docker-ce/ubuntu/#install-using-the-repository

Step 1: Install needed packages for Docker

```
Type in $ sudo apt-get install \
    apt-transport-https \
    ca-certificates \
    curl \
    software-properties-common
```

Step 2: Add the GPG Key for git

Type in the following,

```
$ curl -fsSL https://download.docker.com/linux/ubuntu/gpg | sudo apt-key add -
```

Step 3: Add the Repo that you will obtain Docker-ce from

```
Type in,
sudo add-apt-repository "deb [arch=amd64]
https://download.docker.com/linux/ubuntu $(lsb release -cs) stable"
```

Step 4: Update the apt package

```
Type sudo apt-get update
```

Step: Install Docker

```
Type sudo apt-get install docker-ce -y
```

This will then install the docker for being able to install containers for use.

Sonarr Docker Container Installation

https://hub.docker.com/r/linuxserver/sonarr/

Step 1: Pull the Container

```
Type in sudo docker pull linuxserver/sonarr
plex@ubuntuplexserver:"$ sudo docker pull linuxserver/sonarr
[sudo] password for plex:
Using default tag: latest
latest: Pulling from linuxserver/sonarr
18d680d61657: Pull complete
666fafd8621d: Pull complete
312810db6a55: Pull complete
6948fdd5a5f1: Pull complete
Oda8b00e0eb0: Pull complete
8251d7835870: Pull complete
a2b93e3b9369: Pull complete
68a629294fb5: Pull complete
37dace1a4e7b: Pull complete
9671bb8016a9: Pull complete
b292b13b1a04: Pull complete
Digest: sha256:31e46b4c984d58baefd5812eb70f133944ec62eba628d8429cf5eb8af017ace8
Status: Downloaded newer image for linuxserver/sonarr:latest
```

```
sudo docker create \
    --name sonarr \
    --restart=always \
    -p 8989:8989 \
    -e PUID=<user pid> -e PGID=<group id>\
    -v /etc/localtime:/etc/localtime:ro \
    -v <path you would like the config file in>:/config \
    -v <path to where tv library>:/tv \
    -v <path to where downloads are stored>>:/downloads \
    linuxserver/sonarr
```

```
plexQubuntuplexserver: $\(^\$\) sudo docker create \\
> --name sonarr \\
> --restart=always \\
> -p 8989:8989 \\
> -e PUID=1000 -e PGID=1000 \\
> -v /etc/localtime:/etc/localtime:ro \\
> -v /docker/sonarr:/config \\
> -v /plex/tv:/tv \\
> -v /downloads:/downloads \\
> linuxserver/sonarr
50d8474601666ece2b6c7052d9b7fa419013d73b0a782d95184d7817a88f70b1
```

The image above is an example of what mine looks like fully filled out with the locations that I am using on my server. You will need to create the directories that you are using for the config, tv and downloads.

```
You can find the PUID by typing in id -u <username>
plex@ubuntuplexserver: $ id -u plex
1000

That is the PUID you will need to enter.
You can find the GID by typing in id -g <group>
plex@ubuntuplexserver: $ id -g plex
1000
```

Step 3: Start the Container

```
Type in sudo docker start sonarr
plex@ubuntuplexserver: $\times \text{sudo docker start sonarr}
sonarr
```

Step 4: Access the Container

You can reach the container by opening your browser and going to http://localhost:8989. Or because we have assigned this server an IP address we could go to another computer and go to the site http://192.168.0.100:8989.

Radarr Docker Container Installation

https://hub.docker.com/r/linuxserver/radarr/

Step 1: Pull the Container

Type in sudo docker pull linuxserver/radarr

```
plex@ubuntuplexserver:~$ sudo docker pull linuxserver/radarr
Using default tag: latest
latest: Pulling from linuxserver/radarr
18d680d61657: Already exists
666fafd8621d: Already exists
312810db6a55: Already exists
6948fdd5a5f1: Already exists
Oda8b00e0eb0: Already exists
B251d7835870: Already exists
a2b93e3b9369: Already exists
68a629294fb5: Already exists
37dace1a4e7b: Already exists
01cf511a23be: Pull complete
c22f4af0c9b6: Pull complete
Digest: sha256:83b5efe101870af0634097fed9c1e20c1a01e8ff0753dd88cf49b735b6821d92
Status: Downloaded newer image for linuxserver/radarr:latest
```

Step 2: Type or copy/paste in

```
sudo docker create \
    --name radarr \
    --restart=always \
    -p 7878:7878 \
    -e PUID=<user pid> -e PGID=<group id>\
    -v /etc/localtime:/etc/localtime:ro \
    -v <path you would like the config file in>:/config \
    -v <path to where tv library>:/movies \
    -v <path to where downloads are stored>>:/downloads \
    linuxserver/radarr
```

```
plexQubuntuplexserver: $\(^\$\) sudo docker create \\
> --name=radarr \\
> --restart=always \\
> -v /docker/radarr:/config \\
> -v /downloads:/downloads \\
> -v /plex/movies:/movies \\
> -v /etc/localtime:/etc/localtime:ro \\
> -e PGID=1000 -e PUID=1000 \\
> -p 7878:7878 \\
> linuxserver/radarr
8d714a1c69631c6e98c245e621c544f997f723b1b9326a1468fd3695a808717b
```

The image above is an example of what mine looks like fully filled out with the locations that I am using on my server. You will need to create the directories that you are using for the config, tv and downloads.

Step 3: Start the Container

Type in sudo docker start radarr

plex@ubuntuplexserver:~\$ sudo docker start radarr radarr

Step 4: Access the Container

You can reach the container by opening your browser and going to http://localhost:7878. Or because we have assigned this server an IP address we could go to another computer and go to the site http://192.168.0.100:7878.

Jackett Docker Container Installation

https://hub.docker.com/r/linuxserver/jackett/

Step 1: Pull the Container

Type in sudo docker pull linuxserver/jackett

```
plex@ubuntuplexserver:/$ sudo docker pull linuxserver/jackett
Using default tag: latest
latest: Pulling from linuxserver/jackett
18d680d61657: Already exists
666fafd8621d: Already exists
312810db6a55: Already exists
6948fdd5a5f1: Already exists
Oda8b00e0eb0: Already exists
8251d7835870: Already exists
a2b93e3b9369: Already exists
68a629294fb5: Already exists
37dace1a4e7b: Already exists
dadec91689fe: Pull complete
6901d99e0120: Pull complete
Digest: sha256:bba96386714d1ce3c680378f391fd09c7ac232363f3264d612f09213d5c03b02
Status: Downloaded newer image for linuxserver/jackett:latest
```

```
sudo docker create \
    --name=jackett \
    --restart=always \
    -p 9117:9117 \
    -e PUID=<user pid> -e PGID=<group id>\
    -v <path you would like the config file in>:/config \
    -v <path to where downloads are stored>>:/downloads \
    linuxserver/jackett
```

```
plexQubuntuplexserver:/$ sudo docker create \
> --name=jackett \
> --restart=always \
> -p 9117:9117 \
> -e PUID=1000 -e PGID=1000 \
> -v /docker/jackett:/config \
> -v /downloads:/downloads \
> linuxserver/jackett
e5108adf72a8081934d82762517b471eb4f996eec4df37c8c35398d9430e298f
```

The image above is an example of what mine looks like fully filled out with the locations that I am using on my server. You will need to create the directories that you are using for the config, tv and downloads.

Step 3: Start the Container

```
Type in sudo docker start jackett plex@ubuntuplexserver:/$ sudo docker start jackett jackett
```

Step 4: Access the Container

You can reach the container by opening your browser and going to http://localhost:9117. Or because we have assigned this server an IP address we could go to another computer and go to the site http://192.168.0.100:9117.

Tautulli Docker Container Installation

https://hub.docker.com/r/linuxserver/tautulli/

Step 1: Pull the Container

```
Type in sudo docker pull linuxserver/tautulli
plex@ubuntuplexserver:/$ sudo docker pull linuxserver/tautulli
Using default tag: latest
latest: Pulling from linuxserver/tautulli
b52c7bb6cc92: Pull complete
9721e0283028: Pull complete
5419e3b18744: Pull complete
e05e2ab2836b: Pull complete
2d6d9f974953: Pull complete
02a43dd245b9: Pull complete
Digest: sha256:56c5a9efd45972b036a6d75d4397854079f2cb7dc867e68c6e0020b4918b32ec
Status: Downloaded newer image for linuxserver/tautulli:latest
```

Step 2: Type or copy/paste in

```
sudo docker create \
    --name=tautulli \
    --restart=always \
    -p 8181:8181 \
    -e PUID=<user pid> -e PGID=<group id>\
    -v <path you would like the config file in>:/config \
    -v <path to the plex logs>:/logs:ro \
    linuxserver/tautulli
```

```
plex@ubuntuplexserver:/$ sudo docker create \
> --name=tautulli \
> --restart=always \
> -v /docker/tautulli:/config \
> -v "/var/lib/plexmediaserver/Library/Application Support/Plex Media Server/":/logs:ro \
> -e PGID=1000 -e PUID=1000 \
> -p 8181:8181 \
> linuxserver/tautulli
a0df265ddb1f8795ec8d323e95654dd82d0372d4168e8bdefafec4d323ab7d86
```

The image above is an example of what mine looks like fully filled out with the locations that I am using on my server. You will need to create the directories that you are using for the config, ty and downloads

Step 3: Start the Container

```
Type in sudo docker start jackett

plex@ubuntuplexserver:/$ sudo docker start tautulli
tautulli
```

Step 4: Access the Container

You can reach the container by opening your browser and going to http://localhost:8181. Or because we have assigned this server an IP address we could go to another computer and go to the site http://192.168.0.100:8181.

Ombi Docker Container Installation

https://hub.docker.com/r/linuxserver/ombi/

Step 1: Pull the Container

Type in sudo docker pull linuxserver/ombi

```
plexQubuntuplexserver:/$ sudo docker pull linuxserver/ombi
Using default tag: latest
latest: Pulling from linuxserver/ombi
18d680d61657: Already exists
666fafd8621d: Already exists
312810db6a55: Already exists
6948fdd5a5f1: Already exists
04a8b00e0eb0: Already exists
8251d7835870: Already exists
8251d7835870: Already exists
a2b93e3b9369: Already exists
68a629294fb5: Already exists
53e2b790294f: Pull complete
3b2ae1e1ae8b: Pull complete
Digest: sha256:6079d69acc643fc27019390a24956378702006405c64f4c136d98589236e81a4
Status: Downloaded newer image for linuxserver/ombi:latest
```

Step 2: Type or copy/paste in

```
sudo docker create \
      --name=ombi \
      --restart=always \
      -p 3579:3579 \
      -e PUID=<user pid> -e PGID=<group id>\
      -v <path you would like the config file in>:/config \
      -v /etc/localtime:/etc/localtime:ro \
      linuxserver/ombi
plex@ubuntuplexserver:/$ sudo docker create 📏
 --name=ombi \
 --restart=always \
 -v /docker/ombi:/config \
 -е PGID=1000 -е PUID=1000 \
 -u/etc/localtime:/etc/localtime:ro \
 -p 3579:3579 \
> linuxserver/ombi
```

The image above is an example of what mine looks like fully filled out with the locations that I am using on my server. You will need to create the directories that you are using for the config, tv and downloads.

Step 3: Start the Container

```
Type in sudo docker start ombi
plex@ubuntuplexserver:/$ sudo docker start ombi
ombi
```

Step 4: Access the Container

You can reach the container by opening your browser and going to http://localhost:3579. Or because we have assigned this server an IP address we could go to another computer and go to the site http://192.168.0.100:3579.

NZBGET Docker Container Installation

https://hub.docker.com/r/linuxserver/nzbget/

Step 1: Pull the Container

Type in sudo docker pull linuxserver/nzbget

```
plexQubuntuplexserver:/$ sudo docker pull linuxserver/nzbget
Using default tag: latest
latest: Pulling from linuxserver/nzbget
b52c7bb6cc92: Already exists
9721e0283028: Already exists
5419e3b18744: Already exists
724048a2a72e: Pull complete
e23eb6243289: Pull complete
Digest: sha256:fcb7c1f568437697a0dc6086d1fdfcf8618696ae6c48727a71bba3e1e1f57846
Status: Downloaded newer image for linuxserver/nzbget:latest
```

```
sudo docker create \
    --name=nzbget \
    --restart=always \
    -p 6789:6789 \
    -e PUID=<user pid> -e PGID=<group id>\
    -v <path you would like the config file in>:/config \
    -v /etc/localtime:/etc/localtime:ro \
    -v /downloads:/downloads \
    linuxserver/nzbget
```

```
plexQubuntuplexserver:/$ sudo docker create \
> --name=nzbget \
> --restart=always \
> -p 6789:6789 \
> -e PUID=1000 -e PGID=1000 \
> -v /etc/localtime:/etc/localtime:ro \
> -v /docker/nzbget:/config \
> -v /downloads:/downloads \
> linuxserver/nzbget
e14269f5b805f9fb42c1d172091e34ee6d2dc71f164de81b4049882e2e653019
```

The image above is an example of what mine looks like fully filled out with the locations that I am using on my server. You will need to create the directories that you are using for the config, tv and downloads.

Step 3: Start the Container

```
Type in sudo docker start nzbget plex@ubuntuplexserver:/$ sudo docker start nzbget nzbget
```

Step 4: Access the Container

You can reach the container by opening your browser and going to http://localhost:6789. Or because we have assigned this server an IP address we could go to another computer and go to the site http://192.168.0.100:6789.

Deluge Docker Container Installation

https://hub.docker.com/r/linuxserver/deluge/

Step 1: Pull the Container

Type in sudo docker pull linuxserver/deluge

```
plexQubuntuplexserver:/$ sudo docker pull linuxserver/deluge
Using default tag: latest
latest: Pulling from linuxserver/deluge
284c9840697a: Pull complete
8eb91565a376: Pull complete
b5a35c665b46: Pull complete
77b976dee6f8: Pull complete
1863122e451c: Pull complete
Digest: sha256:95adcbe287b1236a207e68904cda47bdbd4c526279c7a3053c4cda4b2f663974
Status: Downloaded newer image for linuxserver/deluge:latest
```

```
sudo docker create \
    --name=deluge \
    --restart=always \
    --net=host \
    -e UMASK_SET=022 \
    -e PUID=<user pid> -e PGID=<group id>\
    -v <path you would like the config file in>:/config \
    -v <path to downloads directory>:/downloads \
    linuxserver/deluge
```

```
plex@ubuntuplexserver:/$ sudo docker create \
> --name=deluge \
> --restart=always \
> --net=host \
> -e UMASK_SET=022 \
> -e PUID=1000 -e PGID=1000 \
> -v /docker/deluge:/config \
> -v /downloads:/downloads \
> linuxserver/deluge
e7853dc1349d5bbb4a0e41cfa730d34d7b6c56fd73c2225db946c8753fc7afda
```

The image above is an example of what mine looks like fully filled out with the locations that I am using on my server. You will need to create the directories that you are using for the config, tv and downloads.

Step 3: Start the Container

```
Type in sudo docker start deluge plex@ubuntuplexserver:/$ sudo docker start deluge deluge
```

Step 4: Access the Container

You can reach the container by opening your browser and going to http://localhost:8080. Or because we have assigned this server an IP address we could go to another computer and go to the site http://192.168.0.100:8080.

Watchtower Docker Container Installation

https://github.com/v2tec/watchtower

Step 1: Pull the Container

Type in sudo docker pull v2tec/watchtower

```
plexQubuntuplexserver:/$ sudo docker pull v2tec/watchtower
Using default tag: latest
latest: Pulling from v2tec/watchtower
a5415f98d52c: Pull complete
c3f7208ad77c: Pull complete
169c1e589d74: Pull complete
Digest: sha256:4cb6299fe87dcbfe0f13dcc5a11bf44bd9628a4dae0035fecb8cc2b88ff0fc79
Status: Downloaded newer image for v2tec/watchtower:latest
```

```
Type in sudo docker run -d --name watchtower --restart=always -v /var/run/docker.sock:/var/run/docker.sock v2tec/watchtower --cleanup
```

plex@ubuntuplexserver:/\$ sudo docker run -d --name watchtower --restart=always -v /var/run/docker.so ck:/var/run/docker.sock v2tec/watchtower --cleanup 605d2b1c0b92b2ca65fac284408450432f45cec39917a5bb447db80d15a071f8

Step 3: Start the Container

plex@ubuntuplexserver:/\$ sudo docker start watchtower watchtower

Portainer Docker Container Installation

https://portainer.io/

Step 1: Create a Volume

Type in sudo docker volume create portainer data

plex@ubuntuplexserver:/\$ sudo docker volume create portainer_data portainer_data

Step 2: Pull the Container

```
Type in sudo docker pull portainer/portainer
```

```
plex@ubuntuplexserver:/$ sudo docker pull portainer/portainer
```

Using default tag: latest

latest: Pulling from portainer/portainer

Digest: sha256:07c0e19e28e18414dd02c313c36b293758acf197d5af45077e3dd69c630e25cc

Status: Image is up to date for portainer/portainer:latest

Step 3: Run the Container

```
Type in sudo docker run -d -p 9000:9000 -v /var/run/docker.sock:/var/run/docker.sock -v portainer_data:data portainer/portainer
```

plex@ubuntuplexserver:/\$ sudo docker run -d -p 9000:9000 -v /var/run/docker.sock:/var/run/docker.soc k -v portainer_data:data portainer/portainer

Step 4: Access the Container

You can reach the container by opening your browser and going to http://localhost:9000. Or because we have assigned this server an IP address we could go to another computer and go to the site http://192.168.0.100:9000.