
HoloLens AR Interaction Tasks Manual



Contents

- Setup
- Usage Instructions
- Make Changes
- Resources

Set Up

This guide assumes starting from scratch (no toolkits or editors installed) and walks through the steps to get the tasks running in Unity and deployed on the HoloLens.

Set up is separated into three stages.

- 1. Download and install necessary editors and toolkits
 - Windows 10 update and settings (you need to be running Windows 10)
 - Unity
 - Microsoft Visual Studio 2017
 - Mixed Reality Toolkit (Unity asset package)
- 2. Create Unity projects for each task
 - Get scene preview running
 - Build project solution
- 3. Deploy project solutions to HoloLens
 - Set up HoloLens
 - Deploy app using Visual Studio
 - Windows Device Portal

Download and Install Necessary Editors and Toolkits

This section is summarized by the following links.


- https://docs.microsoft.com/en-us/windows/mixed-reality/install-the-tools
- https://github.com/Microsoft/MixedRealityToolkit-Unity/blob/master/GettingStarted.md

Windows 10 update and settings (PC)


- Install the Windows 10 April 2018 Update by running Windows Update
 - o If Windows is up-to-date the Update installed
- Enable Developer mode
 - Go to Settings > Update & Security > For developers
 - You may need to reboot

Unity


- Download latest Long Term Support (LTS) Release of Unity Editor Download Assistant (Windows)
 - Projects tested on LTS Release 2017.4.10f1 (installer is provided)
 - Note a newer release may be out. A list can be found here:
 https://unity3d.com/unity/qa/lts-releases?ga=2.10765437.818138280.1527115303-289721018.1521153098
 - When installing, make sure to select Windows Store .NET Scripting Backend (you may install the docs as well)



Specify install folder




Create an account if you are a new Unity user



Microsoft Visual Studio

- Download and install Microsoft Visual Studio Community 2017 (installer included)
 - o Select Universal Windows Platform development workload
 - o Select Game Development with Unity workload
 - Deselect the Unity Editor optional component (we've already downloaded the latest release)



Mixed Reality Toolkit – Unity

- No action needed
- HoloToolkit 2017.4.10 packages are included in each project

Create Unity Projects for Each Task


This section walks through setting up the tasks in Unity.

- Cube task
- Cube random plane task
- Pointing task


The goal is to run scene preview for each task. When scene preview runs, the task is ready to be loaded onto the HoloLens.


Cube task

Open Unity and create a new project




 Title the project according to task and choose a location for the project folder then select Create Project






o An empty project will open in the editor (you may keep the editor open till the end)

Navigate to the project folder at your specified location




- Open a new file explorer and navigate to the provided corresponding task folder
 - o Copy the ProjectSettings and Assets folders into the newly created project folder


- o Opt to overwrite all files when copying
 - These are the ProjectSettings files




- Return to the open Unity project and wait for the project to load
- Open the main scene
 - File > Open Scene > scenes > main.unity




- Apply mixed reality project settings
 - Mixed Reality Toolkit > Configure > Apply Mixed Reality Project Settings



Click the play button to run the scene preview








Cube random plane task

- Follow the cube task steps above to run scene preview
 - o The initial scene preview view is the same

Pointing task

• Follow the cube task steps above to run scene preview



Pointing random plane task

Follow the cube task steps above to run scene preview

Deploy Project Solutions to HoloLens

This section outlines how to export a project from Unity to the HoloLens.

- Set up HoloLens
 - https://docs.microsoft.com/en-us/hololens/hololens-setup
- Build and export the solution from Unity
 - https://docs.microsoft.com/en-us/windows/mixed-reality/exporting-and-building-aunity-visual-studio-solution
- Use Visual Studio to deploy the task to the HoloLens
 - o https://docs.microsoft.com/en-us/windows/mixed-reality/using-visual-studio
 - I have only deployed over USB
 - Wi Fi is an option
- To configure and manage the HoloLens (e.g. record or take screenshots) use the Windows
 Device Portal
 - o https://docs.microsoft.com/en-us/windows/mixed-reality/using-the-windows-device-portal

Usage Instructions

These sections describe each task and their features. Screenshots are included at the end.

Each task can be *played* within the Unity Editor using scene preview (see Setup). Scene preview controls are as follows. These controls translate into gesture controls on the HoloLens.

- Hold right-click to look around
 - Locate the cursor in the center of the view
- WASD to move around
- Hold shift+right-click to ready the tap gesture
 - Cursor will slightly enlarge
 - One of the hands will turn blue
- In the ready tap gesture state orient cursor on an interactive object
 - o Tap or hold left-click to interact with the object

Cube Task

Objective

Tap and hold select white cubes to drag them into randomly spawned trigger points (white spheres). A cube is rendered transparent and colored red when it collides with a trigger point. A trial consists of 27 cubes populating a 3x3x3 array of trigger points. After a trial is completed a new one automatically begins, and the trial counter is updated. The task is complete after three trials. Interactive position sliders change the height and distance of the task.

Points are colored to indicate plane:

Front – yellow

- Middle green
- Back light blue

Timing

The trial timer starts when the first point of a new trial is triggered and stops when the last point of the trial is triggered. A text file with the 3 trial times is saved to a unique file path on the system. This is the application persistent data path.

On the HoloLens access the Device Portal/File Explorer, it is mapped to LocalAppData/YourApp/LocalState.

On the PC using Unity it is mapped to %userprofile%\AppData\Local\Packages\<productname>\LocalState. For example C:/Users/JaneDoe/AppData/LocalLow/DefaultCompany/some task.

Below is an example results file.

Trial 1 : 00:01:06.2945133 Trial 2 : 00:01:00.6964136 Trial 3 : 00:01:21.1255193

Usage

- Orient cursor on a white cube near its center
- Hold shift+right-click to ready the tap gesture
- With the cursor on or near the center of the cube hold left-click to drag
 - You should be holding shift+left-click+right-click
 - Both look around and use WASD to move the cube while dragging
- Drag the cube into a trigger point
- Adjust sliders as you would drag a cube

Cube Random Plane Task

Objective

Nearly identical to cube task. This task randomly spawns trigger points by frontal plane. A frontal plane is one of the 3x3 front facing trigger spawn arrays. There are three frontal planes front, middle, and back. For each trial, the plane spawn order is randomized, and trigger points are randomly spawned within the planes. An entire plane's trigger points must be triggered for the next plane (if any) to begin spawning points. Interactive position sliders change the height and distance of the task.

Points are colored to indicate plane:

- Front yellow
- Middle green
- Back light blue

Timing

The trial timer starts when the first point of a new trial is triggered and stops when the last point of the trial is triggered. The plane timer starts and stops when the first and last point of a plane is triggered,

respectively. A text file with the 3 trial times and 9 plane times is saved to a unique file path on the system. This is the application persistent data path.

On the HoloLens access the Device Portal/File Explorer, it is mapped to LocalAppData/YourApp/LocalState.

On the PC using Unity it is mapped to

%userprofile%\AppData\Local\Packages\<productname>\LocalState. For example C:/Users/JaneDoe/AppData/LocalLow/DefaultCompany/some task.

Below is an example results file.

```
Plane 1: 00:00:15.2287043 middle
Plane 2: 00:00:18.1968041 front
Plane 3: 00:00:20.9610970 back
Trial 1: 00:00:58.9365757
```

Plane 1 : 00:00:21.2238745 middle Plane 2 : 00:00:20.1131311 front Plane 3 : 00:00:22.2740597 back

Trial 2: 00:01:27.3456086

Plane 1 : 00:00:20.4123726 middle Plane 2 : 00:00:16.0041588 front Plane 3 : 00:00:17.5173976 back Trial 3 : 00:00:58.8113890

Usage

- Orient cursor on a white cube near its center
- Hold shift+right-click to ready the tap gesture
- With the cursor on or near the center of the cube hold left-click to drag
 - You should be holding shift+left-click+right-click
 - o Both look around and use WASD to move the cube while dragging
- Drag the cube into a trigger point
- Adjust sliders as you would drag a cube (see Cube Task)

Pointing Task

Objective

Tap select trigger points (red spheres) from a circular array of static points (white spheres). Trigger points will spawn indefinitely. Interactive sliders change the height, distance, and size of the circular static point array and the point sizes.

Usage

- Orient the cursor on a trigger point
- Hold shift+right-click to ready the tap gesture
- With the cursor on the trigger point left-click to tap select
- Adjust sliders as you would drag a cube (see Cube Task)

Timing

The timer starts when the first point is triggered and stops when the last point is triggered. A text file with the 3 trial times is saved to a unique file path on the system. This is the application persistent data path.

On the HoloLens access the Device Portal/File Explorer, it is mapped to LocalAppData/YourApp/LocalState.

On the PC using Unity it is mapped to %userprofile%\AppData\Local\Packages\<productname>\LocalState. For example C:/Users/JaneDoe/AppData/LocalLow/DefaultCompany/some task.

Below is an example results file.

00:00:16.8006315

Pointing Random Plane Task

Objective

Nearly identical to pointing task. This task consists of three frontal planes. There are 18 trigger point spawn locations for each plane. A new plane is spawned when all the trigger points have been selected in the current plane. The trigger points are white spheres and the static points are colored by plane:

- Front yellow
- Middle green
- Back light blue

The trigger points are white instead of red to avoid difficulty for colorblind users.

Timing

The trial timer starts when the first point of a new trial is triggered and stops when the last point of the trial is triggered. The plane timer starts and stops when the first and last point of a plane is triggered, respectively. A text file with the 3 trial times and 9 plane times is saved to a unique file path on the system. This is the application persistent data path.

On the HoloLens access the Device Portal/File Explorer, it is mapped to LocalAppData/YourApp/LocalState.

On the PC using Unity it is mapped to %userprofile%\AppData\Local\Packages\<productname>\LocalState. For example C:/Users/JaneDoe/AppData/LocalLow/DefaultCompany/some task.

Below is an example results file.

Plane 1 : 00:00:18.5338914 back Plane 2 : 00:00:16.2768163 front Plane 3 : 00:00:14.9830597 middle

Trial 1: 00:00:52.2205804

Plane 1 : 00:00:17.2352886 middle Plane 2 : 00:00:16.7567298 back Plane 3 : 00:00:16.7089160 front

Trial 2 : 00:00:53.2333645

Plane 1 : 00:00:15.7367118 front Plane 2 : 00:00:21.1945203 back Plane 3 : 00:00:15.8584202 middle

Trial 3: 00:00:54.8160205

Usage

- Orient the cursor on a trigger point
- Hold shift+right-click to ready the tap gesture
- With the cursor on the trigger point left-click to tap select
- Adjust sliders as you would drag a cube (see Cube Task)

Points are colored to indicate plane:

- Front yellow
- Middle green
- Back light blue

Web Browsing Task


Objective

Simulate web browsing. All keyboard input has been disabled.


Usage

- Navigate to https://web-browsing-task.appspot.com/ using the HoloLen's web browser
- To move the app (browser window)
 - Gaze at the app bar and tap and hold to select it. Move your hand to position the app, then raise your finger to place it.
- To resize the app (browser window)
 - Gaze at a corner or edge of the app window, and tap and hold. Move your hand to change the app window's size, and raise your finger when you're done.


Screenshots




Cube task before third trial completion.




Cube task after third trial completion.




Cube random plane task on back plane.




Cube random plane task on front plane with back plane filled.




Pointing task initially set.




Pointing task after slider adjustments.



Pointing random plane task initially set on back plane.



 $Pointing\ random\ plane\ task\ after\ slider\ adjustments\ on\ middle\ plane.$



A web browsing task page.


Make Changes

This section describes how to make changes to the tasks. Save the scene and project for changes to persist.

Camera distance

The camera parent position can be changed to adjust the initial view of a task. The process is the same for each Unity task.

- Open the task in Unity and select the MixedRealityCameraParent game object in the scene hierarchy
- Switch to the Inspector tab
- Adjust the Transform component's Position property then scene preview to see your changes




Sliders (pointing task)

The slider effects can be adjusted.

• Open the pointing task in Unity and select a slider from the scene hierarchy

- Switch to the Inspector tab
- Expand the Slider Gesture Control (Script) component
- Adjust the Min and Max Slider Values then scene preview to test your changes



Resources

Majority of the links in previous sections stem from these.

- https://docs.microsoft.com/en-us/windows/mixed-reality/
- https://docs.microsoft.com/en-us/hololens/
- https://support.microsoft.com/en-us/help/12644/hololens-use-gestures
- https://github.com/Microsoft/MixedRealityToolkit-Unity

To aid with troubleshooting, specifically script functionality, development commit history can be viewed on GitHub. However, latest developments may not be pushed yet.

- https://github.com/wilsjame/OEBL-cube
- https://github.com/wilsjame/OEBL-cube-random-plane
- https://github.com/wilsjame/OEBL-pointing
- https://github.com/wilsjame/OEBL-pointing-random-plane
- https://github.com/wilsjame/OEBL-web-browsing

Please email James jgwilson1214@gmail.com if something is not working as expected or with questions.

Manual updates

- 14 September 2018 initial commit
- 30 October 2018 add pointing random plane task, color depth indicators, and position sliders for all tasks
- 28 December 2018 add timers, show float values above position sliders