Project 1--CDA 3101 (Spring 2014)

Worth: 100 points (10% of course grade)
Assigned: Friday, Jan 24, 2014
Due: 1:25 pm, Monday, Feb 24, 2014

1. Purpose

This project is intended to help you understand the instructions of a very

simple assembly language and how to assemble programs into machine language.

2. Problem

This project has three parts. In the first part, you will write a program to

take an assembly-language program and produce the corresponding machine language. In the second part, you will write a behavioral simulator for the

resulting machine code. In the third part, you will write a short assembly-language program to multiply two numbers.

3. LC3101 Instruction-Set Architecture

For this project, you will be developing a simulator and assembler for the

 ${\tt LC3101}$ (Little Computer, used in CDA 3101). The ${\tt LC3101}$ is very simple, but

it is general enough to solve complex problems. For this project, you will

only need to know the instruction set and instruction format of the ${\tt LC3101}$.

The LC3101 is an 8-register, 32-bit computer. All addresses are word-addresses (unline MIPS which is byte-addressed). The LC3101 has 65536

words of memory. By assembly-language convention, register 0 will always contain 0 (i.e. the machine will not enforce this, but no assembly-language

program should ever change register 0 from its initial value of 0).

There are 3 instruction formats (bit 0 is the least-significant bit). Bits

31-25 are unused for all instructions, and should always be 0.

R-type instructions (add, nand):

bits 24-22: opcode bits 21-19: reg A bits 18-16: reg B

bits 15-3: unused (should all be 0)

bits 2-0: destReq

I-type instructions (lw, sw, beq):

bits 24-22: opcode bits 21-19: reg A

bits 18-16: reg B

bits 15-0: offsetField (16-bit, range of -32768 to 32767)

O-type instructions (halt, noop):

bits 24-22: opcode

bits 21-0: unused (should all be 0)

Table 1: Description of Machine Instructions

Assembly language Opcode in binary Action name for instruction (bits 24, 23, 22) ______

add (R-type format) 000 add contents of regA with contents of regB, store results in destReg.

nand (R-type format) 001 nand contents of regA with contents of regB, store results in destReg.

lw (I-type format) 010 load regB from memory. Memory address is formed by adding offsetField with the contents of regA.

sw (I-type format) 011 store regB into memory. Memory address is formed by adding offsetField with the contents of regA.

beq (I-type format) 100 if the contents of regA and regB are the same, then branch to the address PC+1+offsetField, where PC is the address of the beg instruction.

101 copy the value regA into destReg cmov (R-type) if the contents of regB != 0

halt (O-type format) 110 increment the PC (as with all instructions), then halt the machine (let the simulator notice that the machine halted).

noop (O-type format) 111 do nothing except increment PC. -----

4. LC3101 Assembly Language and Assembler (40%)

The first part of this project is to write a program to take an assembly-language program and translate it into machine language. You will

translate assembly-language names for instructions, such as beq, into their

numeric equivalent (e.g. 100), and you will translate symbolic names for addresses into numeric values. The final output will be a series of 32-bit

instructions (instruction bits 31-25 are always 0).

The format for a line of assembly code is:

label instruction field0 field1 field2 comments

The leftmost field on a line is the label field. Valid labels contain a maximum of 6 chjeacters and can consist of letters and numbers (but must start

with a letter). The label is optional (the white space following the label

field is require

Symbolic addresses refer to labels. For lw or sw instructions, the assembler

should compute offsetField to be equal to the address of the label. This could

be used with a zero base register to refer to the label, or could be used with

a non-zero base register to index into an array starting at the label. For beg

instructions, the assembler should translate the label into the numeric offsetField needed to branch to that label.

After the last used field comes more white space, then any comments. The comment field ends at the end of a line. Comments are vital to creating understandable assembly-language programs, because the instructions themselves

are rather cryptic.

In addition to LC3101 instructions, an assembly-language program may contain

directions for the assembler. The only assembler directive we will use is .fill

(note the leading period). .fill tells the assembler to put a number into the

place where the instruction would normally be stored. .fill instructions use

one field, which can be either a numeric value or a symbolic address.

example, ".fill 32" puts the value 32 where the instruction would normally be

stored. .fill with a symbolic address will store the address of the label.

In the example below, ".fill start" will store the value 2, because the label

"start" is at address 2.

The assembler should make two passes over the assembly-language program. In the

first pass, it will calculate the address for every symbolic label. Assume

that the first instruction is at address 0. In the second pass, it will generate a machine-language instruction (in decimal) for each line of assembly

language. For example, here is an assembly-language program (that counts down

from 5, stopping when it hits 0).

```
lw
                 1
                       five load reg1 with 5 (uses symbolic address)
      lw
           1
                 2
                       3
                             load reg2 with -1 (uses numeric address)
                 2
start add
           1
                       1
                             decrement reg1
                 1
                             goto end of program when reg1==0
      beq
           0
                       2
      beq
                       start go back to the beginning of the loop
     noop
done halt
                            end of program
five .fill 5
```

```
neg1 .fill -1
stAddr
           .fill start will contain the address of start (2)
And here is the corresponding machine language:
(address 0): 8454151 (hex 0x810007)
(address 1): 9043971 (hex 0x8a0003)
(address 2): 655361 (hex 0xa0001)
(address 3): 16842754 (hex 0x1010002)
(address 4): 16842749 (hex 0x100fffd)
(address 5): 29360128 (hex 0x1c00000)
(address 6): 25165824 (hex 0x1800000)
(address 7): 5 (hex 0x5)
(address 8): -1 (hex 0xffffffff)
(address 9): 2 (hex 0x2)
Be sure you understand how the above assembly-language program got
translated
to machine language.
Since your programs will always start at address 0, your program should
output the contents, not the addresses.
8454151
9043971
655361
16842754
16842749
29360128
25165824
-1
4.1. Running Your Assembler
Write your program to take two command-line arguments. The first
argument is
the file name where the assembly-language program is stored, and the
second
argument is the file name where the output (the machine-code) is written.
For example, with a program name of "assemble", an assembly-language
in "program.as", the following would generate a machine-code file
"program.mc":
    assemble program.as program.mc
Note that the format for running the command must use command-line
arguments
for the file names (rather than standard input and standard output).
program should store only the list of decimal numbers in the machine-code
```

file, one instruction per line. Any deviation from this format (e.g. extra

spaces or empty lines) will render your machine-code file ungradable. Any

other output that you want the program to generate (e.g. debugging output) can

be printed to standard output.

4.2. Error Checking

Your assembler should catch the following errors in the assembly-language program: use of undefined labels, duplicate labels, offsetFields that don't fit

in 16 bits, and unrecognized opcodes. Your assembler should exit(1) if it

detects an error and exit(0) if it finishes without detecting any errors. Your

assembler should NOT catch simulation-time errors, i.e. errors that would occur

at the time the assembly-language program executes (e.g. branching to address

-1, infinite loops, etc.).

4.3. Test Cases

An integral (and graded) part of writing your assembler will be to write a

suite of test cases to validate any LC3101 assembler. This is common practice

in the real world--software companies maintain a suite of test cases for their

programs and use this suite to check the program's correctness after a change.

Writing a comprehensive suite of test cases will deepen your understanding of

the project specification and your program, and it will help you a lot as you

debug your program.

The test cases for the assembler part of this project will be short assembly-language programs that serve as input to an assembler. You will submit your suite of test cases together with your assembler, and we will grade

your test suite according to how thoroughly it exercises an assembler.

test case may be at most 50 lines long, and your test suite may contain up to

20 test cases. These limits are much larger than needed for full credit

solution test suite is composed of 5 test cases, each < 10 lines long). See

Section 7 for how your test suite will be graded.

Hints: the example assembly-language program above is a good case to include

in your test suite, though you'll need to write more test cases to get full

credit. Remember to create some test cases that test the ability of an

As with the assembler, you will write a suite of test cases to validate the ${\tt LC3101}$ simulator.

The test cases for the simulator part of this project will be short assembly-language programs that, after being assembled into machine code, serve

as input to a simulator. You will submit your suite of test cases together

with your simulator, and we will grade your test suite according to how thoroughly it exercises an LC3101 simulator. Each test case may execute at

most 200 instructions on a correct simulator, and your test suite may contain

up to 20 test cases. These limits are much larger than needed for full credit

(the solution test suite is composed of a couple test cases, each executing

less than 40 instructions). See Section 7 for how your test suite will be graded.

5.2. Simulator Hints

Be careful how you handle offsetField for lw, sw, and beq. Remember that it's

a 2's complement 16-bit number, so you need to convert a negative offsetField

to a negative 32-bit integer on the Sun workstations (by sign extending it).

To do this, use the following function.

```
int
convertNum(int num)
{
   /* convert a 16-bit number into a 32-bit Sun integer */
   if (num & (1<<15) ) {
       num -= (1<<16);
   }
   return(num);
}</pre>
```

An example run of the simulator (not for the specified task of $\operatorname{multiplication}$)

is included at the end of this posting.

6. Assembly-Language Multiplication (20%)

The third part of this assignment is to write an assembly-language program to

multiply two numbers. Input the numbers by reading memory locations called

"mcand" and "mplier". The result should be stored in register 1 when the

program halts. You may assume that the two input numbers are at most 15 bits

and are positive; this ensures that the (positive) result fits in an ${\tt LC3101}$

word. See the algorithm on page 252 of the textbook for how to multiply. Remember that shifting left by one bit is the samey asdding the number to

itself. Given the LC3101 instruction set, it assest to modify the algorithm so that you avoid the right shift. Submit a version of the program $\,$

that computes (32766 * 10383).

Your multiplication program must be re as-4(o)9(na)7(bl)7(y)7(ef)7(fi)7(ci)7(en)7(t)

this

is several times longer and slower than the solution). To achieve this, you

must use a loop andshift algorithm to perform the multiplication; algorithms

suchy asuccesase addition (e.g. multiplying 5 * 6 by adding 5 six timeas

will take too long.

7. Grading and Formatting

the

test suites.

The best way to dsug your program i s to generate your own test cases, figure

The student suite of test cases for the asasbler andd simulator parts of this

proje will be graded according to how thoroughly they test an LC3101 (as-4(s)9(em)7(bl)7(er)7(o)7(r)7(si)7(mu)7(la)7(to)-4(r)9(.)7(W)7(e)7(wi)7(ll)7(b)

well it e oses potentially bugs in an as-4(s)9(se)7(mb)7(le)7(r)7(or)7(s)7(im)7(ul)

bler test suite, we will use e chy st case as input to a

of buggy assemblers. Ay st case exposes a buggy asasbler by causing it to generate a different answer from a corre asasbler. They st suite is graded basedsn how many of the buggy ass emblers were exposed by at leastsne test case. This is known asmutationy sting" in the research literature on automatedy sting.

For the simulator test suite, we will correctly assemble each test case, then use it as input to a set of buggy simulators. A test case exposes a buggy simulator by causing it to generate a different answer from a correct simulator. The test suite is graded based on how many of the buggy

simulators were exposed by at least one test case.

8. Turning in the Project

Submit you files through blackboard. Each part should be archived in a .tar or .zip file to help with grading.

Here are the files you should submit for each project part:

- 1) assembler (part 1a)
 - a. C/C++ program for your assembler
- b. suite of test cases (each test case is an assembly-language program

in a separate file)

- 2) simulator (part 1s)
 - a. C/C++ program for your simulator
- b. suite of test cases (each test case is an assembly-language program

in a separate file)

- 3) multiplication (part 1m)
 - a. assembly program for multiplication

Your assembler and simulator must each be in a single ${\tt C}$ or ${\tt C++}$ file. We will compile

your program on linprog using "gcc program.c -lm" (or g++), so your program

should not require additional compiler flags or liT87((p)7(ar)-4(t)9(1)7(P <</M 1t.8

```
You may also choose to not use this fragment.
/* Assembler code fragment for LC3101 */
#include <stdlib.h>
#include <stdio.h>
#include <string.h>
#define MAXLINELENGTH 1000
int readAndParse(FILE *, char *, char *, char *, char *, char *);
int isNumber(char *);
int
main(int argc, char *argv[])
    char *inFileString, *outFileString;
    FILE *inFilePtr, *outFilePtr;
    char label[MAXLINELENGTH], opcode[MAXLINELENGTH],
arq0[MAXLINELENGTH],
            arg1[MAXLINELENGTH], arg2[MAXLINELENGTH];
    if (argc != 3) {
        printf("error: usage: %s <assembly-code-file> <machine-code-</pre>
file>\n",
            argv[0]);
        exit(1);
    }
    inFileString = argv[1];
    outFileString = argv[2];
    inFilePtr = fopen(inFileString, "r");
    if (inFilePtr == NULL) {
        printf("error in opening %s\n", inFileString);
        exit(1);
    outFilePtr = fopen(outFileString, "w");
    if (outFilePtr == NULL) {
        printf("error in opening %s\n", outFileString);
        exit(1);
    /* here is an example for how to use readAndParse to read a line from
        inFilePtr */
    if (! readAndParse(inFilePtr, label, opcode, arg0, arg1, arg2) ) {
        /* reached end of file */
    }
    /* this is how to rewind the file ptr so that you start reading from
the
        beginning of the file */
    rewind(inFilePtr);
```

```
/* after doing a readAndParse, you may want to do the following to
test the
        opcode */
    if (!strcmp(opcode, "add")) {
        /* do whatever you need to do for opcode "add" */
   return(0);
}
 * Read and parse a line of the assembly-language file. Fields are
 * in label, opcode, arg0, arg1, arg2 (these strings must have memory
already
 * allocated to them).
 * Return values:
       0 if reached end of file
       1 if all went well
 * exit(1) if line is too long.
*/
int
readAndParse(FILE *inFilePtr, char *label, char *opcode, char *arg0,
    char *arg1, char *arg2)
    char line[MAXLINELENGTH];
    char *ptr = line;
    /* delete prior values */
    label[0] = opcode[0] = arg0[0] = arg1[0] = arg2[0] = '\0';
    /* read the line from the assembly-language file */
    if (fgets(line, MAXLINELENGTH, inFilePtr) == NULL) {
     /* reached end of file */
        return(0);
    /* check for line too long (by looking for a \n) */
    if (strchr(line, '\n') == NULL) {
        /* line too long */
     printf("error: line too long\n");
     exit(1);
    /* is there a label? */
    ptr = line;
    if (sscanf(ptr, "%[^\t\n ]", label)) {
     /* successfully read label; advance pointer over the label */
       ptr += strlen(label);
    }
    /*
```

```
* Parse the rest of the line. Would be nice to have real regular
              * expressions, but scanf will suffice.
           sscanf(ptr, "%*[\t\n ]%[^\t\n ]%[^\t\
]%*[\t\n ]%[^\t\n ]",
                      opcode, arg0, arg1, arg2);
           return(1);
}
int
isNumber(char *string)
           /* return 1 if string is a number */
           int i;
           return( (sscanf(string, "%d", &i)) == 1);
}
10. Code Fragment for Simulator
Here is some C code that may help you write the simulator. Again, you
should
take this merely as a hint. You may have to re-code this to make it do
exactly
what you want, but this should help you get started. Remember not to
change stateStruct or printState.
/* instruction-level simulator for LC3101 */
#include <stdio.h>
#include <string.h>
#define NUMMEMORY 65536 /* maximum number of words in memory */
#define NUMREGS 8 /* number of machine registers */
#define MAXLINELENGTH 1000
typedef struct stateStruct {
           int pc;
           int mem[NUMMEMORY];
           int reg[NUMREGS];
           int numMemory;
} stateType;
void printState(stateType *);
int
main(int argc, char *argv[])
           char line[MAXLINELENGTH];
           stateType state;
           FILE *filePtr;
           if (argc != 2) {
```

```
printf("error: usage: %s <machine-code file>\n", argv[0]);
     exit(1);
    filePtr = fopen(argv[1], "r");
    if (filePtr == NULL) {
     printf("error: can't open file %s", argv[1]);
     perror("fopen");
     exit(1);
    /* read in the entire machine-code file into memory */
    for (state.numMemory = 0; fgets(line, MAXLINELENGTH, filePtr) !=
NULL;
     state.numMemory++) {
     if (sscanf(line, "%d", state.mem+state.numMemory) != 1) {
          printf("error in reading address %d\n", state.numMemory);
          exit(1);
     printf("memory[%d]=%d\n", state.numMemory,
state.mem[state.numMemory]);
    return(0);
}
void
printState(stateType *statePtr)
    int i;
    printf("\n@@@\nstate:\n");
    printf("\tpc %d\n", statePtr->pc);
    printf("\tmemory:\n");
     for (i=0; i<statePtr->numMemory; i++) {
          printf("\t\tmem[ %d ] %d\n", i, statePtr->mem[i]);
    printf("\tregisters:\n");
     for (i=0; i<NUMREGS; i++) {</pre>
         printf("\t\treq[ %d ] %d\n", i, statePtr->req[i]);
    printf("end state\n");
}
11. Programming Tips
Here are a few programming tips for writing C/C++ programs to manipulate
bits:
```

2) The value of the expression (a >> b) is the number "a" shifted right

example, 27 decimal is 0x1b in hexadecimal.

1) To indicate a hexadecimal constant in, precede the number by 0x. For

by "b"

bits. Neither a nor b are changed. E.g. (25 >> 2) is 6. Note that 25 is 11001 in

binary, and 6 is 110 in binary.

3) The value of the expression (a << b) is the number "a" shifted left by "b"

bits. Neither a nor b are changed. E.g. (25 << 2) is 100. Note that 25 is 11001

in binary, and 100 is 1100100 in binary.

4) To find the value of the expression (a & b), perform a logical AND on each

bit of a and b (i.e. bit 31 of a ANDED with bit 31 of b, bit 30 of a ANDED with $\,$

bit 30 of b, etc.). E.g. (25 & 11) is 9, since:

```
11001 (binary) & 01011 (binary)
```

- = 01001 (binary), which is 9 decimal.
- 5) To find the value of the expression (a \mid b), perform a logical OR on each bit

of a and b (i.e. bit 31 of a ORED with bit 31 of b, bit 30 of a ORED with bit 30 $\,$

of b, etc.). E.g. (25 | 11) is 27, since:

```
11001 (binary)
& 01011 (binary)
```

= 11011 (binary), which is 27 decimal.

6) ~a is the bit-wise complement of a (a is not changed).

Use these operations to create and manipulate machine-code. E.g. to look at bit

- 3 of the variable a, you might do: (a>>3) & 0x1. To look at bits (bits 15-12) of
- a 16-bit word, you could do: (a>>12) & 0xF. To put a 6 into bits 5-3 and a 3 $\,$

into bits 2-1, you could do: (6<<3) | (3<<1). If you're not sure what an operation is doing, print some intermediate results to help you debug.

12. Example Run of Simulator

```
memory[0]=8454151
memory[1]=9043971
memory[2]=655361
memory[3]=16842754
memory[4]=16842749
memory[5]=29360128
memory[6]=25165824
```

```
memory[7]=5
memory[8]=-1
memory[9]=2
@@@
state:
     pc 0
     memory:
            mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[ 8 ] -1
           mem[ 9 ] 2
     registers:
           reg[ 0 ] 0
           reg[ 1 ] 0
           reg[ 2 ] 0
           reg[ 3 ] 0
            reg[ 4 ] 0
            reg[ 5 ] 0
            reg[ 6 ] 0
           reg[ 7 ] 0
end state
@@@
state:
     pc 1
     memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[8]-1
           mem[ 9 ] 2
      registers:
           reg[ 0 ] 0
            reg[ 1 ] 5
           reg[ 2 ] 0
            reg[ 3 ] 0
           reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
```

```
@@@
state:
     pc 2
     memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[8]-1
           mem[ 9 ] 2
     registers:
           reg[ 0 ] 0
           reg[ 1 ] 5
           reg[ 2 ] -1
           reg[ 3 ] 0
           reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
@@@
state:
     pc 3
     memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[8]-1
           mem[ 9 ] 2
     registers:
           reg[ 0 ] 0
           reg[ 1 ] 4
           reg[ 2 ] -1
           req[ 3 ] 0
           reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
@@@
state:
     pc 4
```

```
memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[ 8 ] -1
           mem[ 9 ] 2
     registers:
           reg[ 0 ] 0
           reg[ 1 ] 4
           reg[ 2 ] -1
           reg[ 3 ] 0
           reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
@@@
state:
     pc 2
     memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[8]-1
           mem[ 9 ] 2
     registers:
           reg[ 0 ] 0
           reg[ 1 ] 4
           reg[ 2 ] -1
           reg[ 3 ] 0
           reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
@@@
state:
     pc 3
     memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
```

```
mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[8]-1
           mem[ 9 ] 2
     registers:
           reg[ 0 ] 0
           reg[ 1 ] 3
           reg[ 2 ] -1
           reg[ 3 ] 0
           reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
@@@
state:
     pc 4
     memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[8]-1
           mem[ 9 ] 2
     registers:
           reg[ 0 ] 0
           reg[ 1 ] 3
           reg[ 2 ] -1
           reg[ 3 ] 0
           reg[ 4 ] 0
           req[5]0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
@@@
state:
     pc 2
     memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
```

```
mem[7]5
           mem[ 8 ] -1
           mem[ 9 ] 2
     registers:
           reg[ 0 ] 0
           reg[ 1 ] 3
           reg[ 2 ] -1
           reg[ 3 ] 0
           reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
@@@
state:
     pc 3
     memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[8]-1
           mem[ 9 ] 2
     registers:
           reg[ 0 ] 0
           reg[ 1 ] 2
           reg[ 2 ] -1
           reg[ 3 ] 0
           reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
@@@
state:
     pc 4
     memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[8]-1
           mem[ 9 ] 2
     registers:
```

```
reg[ 0 ] 0
           reg[ 1 ] 2
           reg[ 2 ] -1
           reg[ 3 ] 0
           reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
@@@
state:
     pc 2
     memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[8]-1
           mem[ 9 ] 2
     registers:
           reg[ 0 ] 0
           reg[ 1 ] 2
           reg[ 2 ] -1
           reg[ 3 ] 0
           reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
@@@
state:
     pc 3
     memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[8]-1
           mem[ 9 ] 2
     registers:
           reg[ 0 ] 0
           reg[ 1 ] 1
           reg[ 2 ] -1
           reg[ 3 ] 0
```

```
reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
@@@
state:
     pc 4
     memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[8]-1
           mem[ 9 ] 2
     registers:
           reg[ 0 ] 0
           reg[ 1 ] 1
           reg[ 2 ] -1
           reg[ 3 ] 0
           reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
@@@
state:
     pc 2
      memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[8]-1
           mem[ 9 ] 2
     registers:
           reg[ 0 ] 0
           reg[ 1 ] 1
           reg[ 2 ] -1
           reg[ 3 ] 0
           reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
```

```
end state
@@@
state:
     pc 3
     memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[8]-1
           mem[ 9 ] 2
      registers:
           reg[ 0 ] 0
           reg[ 1 ] 0
           reg[ 2 ] -1
           reg[ 3 ] 0
           reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
@@@
state:
     рс б
     memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[8]-1
           mem[ 9 ] 2
     registers:
           reg[ 0 ] 0
           reg[ 1 ] 0
           reg[ 2 ] -1
           reg[ 3 ] 0
           reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
machine halted
total of 17 instructions executed
final state of machine:
```

```
@@@
state:
     pc 7
     memory:
           mem[ 0 ] 8454151
           mem[ 1 ] 9043971
           mem[ 2 ] 655361
           mem[ 3 ] 16842754
           mem[ 4 ] 16842749
           mem[ 5 ] 29360128
           mem[ 6 ] 25165824
           mem[ 7 ] 5
           mem[8]-1
           mem[ 9 ] 2
     registers:
           reg[ 0 ] 0
           reg[ 1 ] 0
           reg[ 2 ] -1
           reg[ 3 ] 0
           reg[ 4 ] 0
           reg[ 5 ] 0
           reg[ 6 ] 0
           reg[ 7 ] 0
end state
```