

EMC® Avamar® Management Console Command Line Interface (MCCLI)

Version 7.2

Programmer Guide

302-001-930 REV 02 Copyright © 2001-2015 EMC Corporation. All rights reserved. Published in USA.

Published August, 2015

EMC believes the information in this publication is accurate as of its publication date. The information is subject to change without notice.

The information in this publication is provided as is. EMC Corporation makes no representations or warranties of any kind with respect to the information in this publication, and specifically disclaims implied warranties of merchantability or fitness for a particular purpose. Use, copying, and distribution of any EMC software described in this publication requires an applicable software license.

EMC², EMC, and the EMC logo are registered trademarks or trademarks of EMC Corporation in the United States and other countries. All other trademarks used herein are the property of their respective owners.

For the most up-to-date regulatory document for your product line, go to EMC Online Support (https://support.emc.com).

EMC Corporation Hopkinton, Massachusetts 01748-9103 1-508-435-1000 In North America 1-866-464-7381 www.EMC.com

CONTENTS

Tables		7
Preface		9
Chapter 1	Introduction	13
	System requirements	14
	Capabilities and limitations	14
Chapter 2	Installation and Configuration	17
	Installing the Java Runtime Environment	18
	Installing and configuring the MCCLI software	
Chapter 3	Command Reference	21
	General programming notes	22
	Data types	22
	Default values	22
	Optional and required arguments	22
	Pattern matching	
	Output description	23
	Command line syntax	
	Enumerating valid object IDs	
	Global event codes	
	Deprecated resources and commands	
	activity	
	activity cancel	
	activity get-log	
	activity show	
	agent show	
	backupbackupdalata	
	backup delete	
	backup edit	
	backup restorebackup show	
	backup sliowbackup validate	
	checkpoint	
	checkpoint cancel-validate	
	checkpoint cancer-validate	
	checkpoint delete	
	checkpoint show	
	checkpoint validate	
	client	
	client add	
	client add-datastore	
	client backup-group-dataset	
	client backup-target	
	client delete	

	client edit	55
	client import-clients-from-file	.60
	client invite	.60
	client move	. 61
	client remove-datastore	. 62
	client retire	63
	client show	. 63
	client show-datastore	66
	client show-plugins	.67
	client validate-clients-from-file	67
dataset		. 68
	dataset add	68
	dataset add-exclude	. 69
	dataset add-include	.70
	dataset add-option	. 71
	dataset add-target	. 72
	dataset copy	. 73
	dataset delete	73
	dataset delete-exclude	74
	dataset delete-include	. 75
	dataset delete-option	76
	dataset delete-target	77
	dataset edit-option	. 78
	dataset replace	
	dataset show	
dd		.82
	dd add	.82
	dd delete	. 83
	dd edit	.84
	dd show-prop	85
	dd show-util	87
domain		. 88
	domain add	. 88
	domain delete	88
	domain edit	. 89
	domain show	. 90
dump		. 90
	dump clientcache	. 91
	dump domaincache	. 91
	dump jobcache	.91
event		91
	event ack	
	event clear-data-integrity-alerts	93
	event get-info	.93
	event show	. 94
group		. 96
	group add	. 96
	group add-client	97
	group add-proxy	98
	group backup	
	group copy	100
	group delete	
	group edit	101
	group export	102
	group move-client	103
	group remove-client	104

	group replicate	106
	group show	
	group show-members	
	help	
	mcs	
	mcs import	
	mcs list	
	mcs reboot-proxy	
	mcs resume-scheduler	
	mcs scheduler-status	
	mcs stop	
	mcs suspend-scheduler	
	mcs waitforflushcomplete	
	plugin	
	plugin show	
	plugin update	
	retention	
	Advanced retention descriptors	
	retention add	
	retention copy	
	retention delete	115
	retention edit	116
	retention show	
	schedule	118
	schedule add	118
	schedule copy	120
	schedule delete	120
	schedule edit	121
	schedule show	123
	schedule show-timezones	124
	server	124
	server show-prop	124
	server show-services	126
	server show-util	127
	server start-service	127
	server stop-service	127
	user	128
	user add	128
	user authenticate	130
	user delete	131
	user edit	132
	user show	133
	user show-auth	134
	vcenter browse	
	version show	137
	vmcache	
	vmcache show	
	vmcache sync	
Appendix A	Utilities and Configuration Files	139
• •	avsetup_mccli	140
	mccli.xml	
	mcclimcs.xml	
	mccames.Am	141

group remove-proxy......105

Glossary 145

TABLES

1	Revision history	9
2	Minimum system requirements for MCCLI software	
3	Data types for mccli commands	
4	Pattern matching operator capabilities and limitations	
5	Returned values in default and normalized formats	
6	Enumerating valid object IDs	
7	Deprecated resources	
8	Deprecated commands	28
9	Advanced retention descriptors	
10	MCCLI essential files	
11	MCCLI default paths	
12	Parameters in mccli.xml	

TABLES

PREFACE

As part of an effort to improve its product lines, EMC periodically releases revisions of its software and hardware. Therefore, some functions described in this document might not be supported by all versions of the software or hardware currently in use. The product release notes provide the most up-to-date information on product features.

Contact your EMC technical support professional if a product does not function properly or does not function as described in this document.

Note

This document was accurate at publication time. Go to EMC Online Support (https://support.emc.com) to ensure that you are using the latest version of this document.

Purpose

This document describes how to install, configure, and use the Avamar Management Console Command Line Interface (MCCLI) Java client software application.

Audience

This document is intended for system administrators who are responsible for installing software and maintaining servers and clients on a network. This document assumes that the reader is familiar with the Avamar Administrator graphical management console as documented in the EMC Avamar Administration Guide, and does not generally repeat information in that document.

Revision history

The following table presents the revision history of this document.

Table 1 Revision history

Revision	Date	Description
01	June 2015	Initial release of Avamar 7.2.
02	August 2015	GA release of Avamar 7.2. Changed JRE requirement to 1.7 and added the section Requirements for accounts running MCCLI scripts on page 15.

Related documentation

The following EMC publications provide additional information:

- EMC Avamar Release Notes
- EMC Avamar Administration Guide
- EMC Avamar Operational Best Practices
- EMC Avamar and EMC Data Domain System Integration Guide

Special notice conventions used in this document

EMC uses the following conventions for special notices:

NOTICE

Addresses practices not related to personal injury.

Note

Presents information that is important, but not hazard-related.

Typographical conventions

EMC uses the following type style conventions in this document:

•	- 11
Bold	Use for names of interface elements, such as names of windows, dialog boxes, buttons, fields, tab names, key names, and menu paths (what the user specifically selects or clicks)
Italic	Use for full titles of publications referenced in text
Monospace	Use for:
	System code
	 System output, such as an error message or script
	 Pathnames, file names, prompts, and syntax
	Commands and options
Monospace italic	Use for variables
Monospace bold	Use for user input
[]	Square brackets enclose optional values
	Vertical bar indicates alternate selections - the bar means "or"
{}	Braces enclose content that the user must specify, such as x or y or z

Ellipses indicate nonessential information omitted from the example

Where to get help

The Avamar support page provides access to licensing information, product documentation, advisories, and downloads, as well as how-to and troubleshooting information. This information may enable you to resolve a product issue before you contact EMC Customer Support.

To access the Avamar support page:

- 1. Go to https://support.EMC.com/products.
- 2. Type a product name in the Find a Product box.
- 3. Select the product from the list that appears.
- 4. Click the arrow next to the **Find a Product** box.
- 5. (Optional) Add the product to the **My Products** list by clicking **Add to my products** in the top right corner of the **Support by Product** page.

Documentation

The Avamar product documentation provides a comprehensive set of feature overview, operational task, and technical reference information. Review the following documents in addition to product administration and user guides:

- Release notes provide an overview of new features and known limitations for a release.
- Technical notes provide technical details about specific product features, including step-by-step tasks, where necessary.
- White papers provide an in-depth technical perspective of a product or products as applied to critical business issues or requirements.

Knowledgebase

The EMC Knowledgebase contains applicable solutions that you can search for either by solution number (for example, esgxxxxxx) or by keyword.

To search the EMC Knowledgebase:

- 1. Click the **Search** link at the top of the page.
- 2. Type either the solution number or keywords in the search box.
- 3. (Optional) Limit the search to specific products by typing a product name in the **Scope by product** box and then selecting the product from the list that appears.
- 4. Select Knowledgebase from the Scope by resource list.
- 5. (Optional) Specify advanced options by clicking **Advanced options** and specifying values in the available fields.
- 6. Click the search button.

Online communities

Visit EMC Community Network at http://community.EMC.com for peer contacts, conversations, and content on product support and solutions. Interactively engage online with customers, partners and certified professionals for all EMC products.

Live chat

To engage EMC Customer Support by using live interactive chat, click **Join Live Chat** on the **Service Center** panel of the Avamar support page.

Service Requests

For in-depth help from EMC Customer Support, submit a service request by clicking **Create Service Requests** on the **Service Center** panel of the Avamar support page.

Note

To open a service request, you must have a valid support agreement. Contact your EMC sales representative for details about obtaining a valid support agreement or with questions about your account.

To review an open service request, click the **Service Center** link on the **Service Center** panel, and then click **View and manage service requests**.

Facilitating support

EMC recommends that you enable ConnectEMC and Email Home on all Avamar systems:

- ConnectEMC automatically generates service requests for high priority events.
- Email Home emails configuration, capacity, and general system information to EMC Customer Support.

Your comments

Your suggestions will help us continue to improve the accuracy, organization, and overall quality of the user publications. Send your opinions of this document to DPAD.Doc.Feedback@emc.com.

Please include the following information:

- Product name and version
- Document name, part number, and revision (for example, 01)
- Page numbers

• Other details that will help us address the documentation issue

CHAPTER 1

Introduction

This chapter includes the following topics:

•	System requirements	. 1	. 4
•	Capabilities and limitations	.1	. 4

System requirements

To connect to the Avamar server using MCCLI, you must have:

- A valid Avamar Administrator ID and password
- Network access to an operational Avamar server

Additionally, the computer running MCCLI software must meet the minimum requirements listed in the following table.

Table 2 Minimum system requirements for MCCLI software

Requirement	Minimum
Operating system	Red Hat Enterprise Linux Release 4 (64-bit)
	SUSE Linux Enterprise Server 11 (64-bit)
RAM	256 MB
Hard drive space	60 MB permanent hard drive space
Network interface	10BaseT or higher, configured with the latest drivers for the platform
Java Runtime Environment	JRE 1.7

Capabilities and limitations

These are the known capabilities and limitations of the MCCLI.

Version compatibility

The MCCLI software must be the same version as the MCS.

Hierarchical management

Hierarchical management is not supported. The root domain is assumed for all user IDs included on the command line. This means that a user must have an account in the root domain to use the MCCLI, and domain administrators cannot log on.

Relative path filenames

The use of filenames containing relative paths is not supported. Filenames are specified as part of the client bulk validate and load commands.

Client bulk validate/load file format

The client import-clients-from-file and client validate-clients-from-file commands currently only support clients definition input files in XML format. You cannot use a CSV file with these commands.

Delayed updates for MCCLI scheduler changes

When you use the MCCLI to suspend or resume the scheduler, the change takes effect immediately. However, the change may not appear in Avamar Administrator for approximately 15 seconds.

Deleting clients with backups pending

As with the Avamar Administrator, you cannot delete a client until it is idle without any backups in progress or it is in the wait queue.

Performance

MCCLI commands typically require approximately 8 seconds to complete. This elapsed time is primarily because the Java Virtual Machine (JVM) must be started to run any MCCLI command, and because decryption framework initialization adds approximately 6 seconds.

If you provide the option directly with each command, you can bypass the decryption framework initialization, which will improve performance.

Maximum number of clients

As with Avamar Administrator, the MCCLI is suitable for systems with a maximum of 5,000 clients.

Java stack trace

Any mccli command might display a Java stack trace if the command fails. This is due to unhandled exceptions.

Generic mccli command failed message

Some errors and failure conditions are not associated with specific event codes. Therefore, when these errors and failure conditions occur, the generic event code for a failed mccli command appears. For example, missing arguments or failed connection from the MCCLI to the MCS generates the same 23998 event (mccli command failed).

Remote clients must run mccli commands as root

If you have installed MCCLI on a remote client, all mccli commands invoked using the operating system root privileges.

Furthermore, if additional security is required, users should remove any passwords stored in mcclimes.xml and instead supply an --mcspasswd option with each mccli command.

Requirements for accounts running MCCLI scripts

The following requirements apply to scripting with the MCCLI:

- MCCLI scripts must be run using a local service-type account.
- Use of the MCUser account is not supported.
- The service account should only be used for scripts, and not as a regular user.

The EMC Avamar Administration Guide contains information about creating a new Avamar server account. After creating a new account, you must add the account profile to the mcclimcs.xml file as show in Add a new service account profile to the mcclimcs.xml file and encrypt the account password on page 142.

Introduction

CHAPTER 2

Installation and Configuration

This chapter includes the following topics:

•	Installing the Java Runtime Environment	.18
•	Installing and configuring the MCCLI software	18

Installing the Java Runtime Environment

The MCCLI requires Java Runtime Environment (JRE) 1.6 Update 12 or later. You can download a current JRE directly from the Avamar server.

Procedure

1. On the computer where MCCLI will be installed, open a web browser and type the following URL:

http://Avamar-server

where Avamar-server is the Avamar server network hostname or IP address.

The EMC Avamar Web Restore web page appears.

- 2. Click Downloads.
- 3. Expand the Linux for x86 (64 bit) folder.
- 4. Expand the correct Linux operating system folder for your computer.
- 5. Locate the JRE RPM install package (it is typically the last entry in the folder).
- 6. If the JRE on the client computer is older than the JRE hosted on the Avamar server, download the <code>jre-version-platform.rpm</code> install package to a temporary install folder such as <code>/tmp.</code>

where:

- *version* is the IRE version.
- *platform* is the computing platform.
- 7. Open a command shell and log in as root.
- 8. Change directory to the temporary install folder. For example:

cd /tmp

9. Follow the onscreen instructions to complete the JRE installation.

Installing and configuring the MCCLI software

Before you begin

The MCCLI sotware requires Java Runtime Environment (JRE) 1.6 Update 12 or later.

Procedure

1. On the computer where MCCLI will be installed, open a web browser and type the following URL:

http://Avamar-server

where Avamar-server is the Avamar server network hostname or IP address.

The EMC Avamar Web Restore web page appears.

- 2. Click Downloads.
- 3. Expand the Linux for x86 (64 bit) folder.
- 4. Do one of the following:
 - If installing on SUSE Linux Enterprise Server 11, expand the **SUSE Linux Enterprise Server 11** folder.

- If installing on Red Hat Enterprise Linux Release 4, expand the **Red Hat Enterprise** Linux 4 folder.
- 5. Download the dpnmccli-version.platform.x86_64.rpm install package to a temporary install folder such as /tmp.

where:

- version is the MCCLI software.
- platform is either sles11 64 or rhel4 64.
- 6. Open a command shell and log in as root.
- 7. Change directory to the temporary install folder. For example:

cd /tmp

8. Install the MCCLI RPM by typing:

rpm -ivh dpnmccli-version.platform.x86 64.rpm

Note

If installing the MCCLI software on the same Linux client that already has Avamar Administrator installed, you must include the --force option.

- 9. Follow the onscreen instructions to complete the MCCLI software installation.
- 10.Configure the MCCLI software by typing avsetup mccli.
- 11. When prompted, type the following information, and then press **Enter** to complete each entry.
 - Full path to the JRE installation folder. The default location is /usr/java/jre1.6.0 12.
 - Full path to Avamar software installation folder. The default location is /usr/local/avamar.
 - Full path to the folder where user data is stored. The default location is ~/.avamardata/var.
 - Avamar server IP address or hostname as defined in corporate DNS.
 - MCS data port number. The default data port is 7778.
 - Avamar administrative user account name.
 - · Avamar administrative user account password.

Installation and Configuration

CHAPTER 3

Command Reference

This chapter includes the following topics:

•	General programming notes	22
•	activity	
•	agent show	31
•	backup	31
•	checkpoint	43
•	client	45
•	dataset	68
•	dd	82
•	domain	88
•	dump	90
•	event	91
•	group	96
•	help	109
•	mcs	109
•	plugin	112
•	retention	112
•	schedule	118
•	server	124
•	user	128
•	vcenter browse	134
•	version show	137
•	vmcache	137

General programming notes

The mccli is a shell script wrapper that invokes the MCCLI Java application. It automatically sets various environment arguments that are required to invoke a Java application, thereby simplifying use of the MCCLI java application.

Data types

The following table lists the data types used by mccli commands and discusses how to correctly specify each data type on the mccli command line.

Table 3 Data types for mccli commands

Data type	Description
Boolean	Boolean values are the case-insensitive words true or false.
Integer	Integer values are always whole numbers.
String	String values contain plain text.
	If a string value contains spaces, it must be enclosed in either single or double quotes.
	Some mccli <i>String</i> values accept regular expression (regex) pattern matching operators, also known as wildcards.

Default values

If a command line argument has a default value, it is shown in parentheses. For example, the following *Boolean* value defaults to the false condition:

```
--verbose=Boolean(false)
```

Similarly, the following string value defaults to the root domain denoted by the slash character (/):

```
--domain=String(/)
```

Optional and required arguments

Command synopses use the following convention to convey whether a particular argument is required for that command:

- Optional arguments are enclosed by square brackets
- Required arguments are not

For example, consider the following example:

```
[--domain=String(/)] --name=String
```

The presence of square brackets indicates that --domain= is an optional argument, while the absence of square brackets indicates that --name= is a required argument.

Pattern matching

Some mccli string values accept regular expression (regex) pattern matching operators, also known as wildcards. mccli pattern matching operators are subject to certain capabilities and limitations described in the following table.

Table 4 Pattern matching operator capabilities and limitations

Operator	Description
Asterisk (*)	Matches zero or more occurrences of any character until the first folder delimiter character (for example, slash on UNIX platforms and backslash on Windows platforms) is encountered. This effectively limits the pattern matching to a single client folder.
	For example, /usr/* matches the contents of /usr but not the contents of /usr/bin or /usr/local.
Double asterisk (**)	Matches zero or more occurrences of any character. This correlates to conventional single asterisk regex behavior.
	For example, /usr/** matches the entire /usr folder structure, no matter how many subfolder levels are encountered.
Question mark (?)	Matches one occurrence of any character. Conventional regex behavior.
Plus sign (+)	Unlike conventional regex, the plus sign is not processed as a glob operator; the plus sign only matches a single occurrence of the plus sign.
Forward slash (/)	Patterns beginning with forward slash (/) are assumed to be absolute path designations for a single folder. Recursive processing of subfolders is disabled, and that folder name is not matched anywhere else.
[range of values]	Characters enclosed in square brackets and separated by a single hyphen (-) are interpreted as a range of values. This is conventional regex behavior. For example:
	• [0-9] matches any single numeric character
	• [a-z] matches any single lowercase alpha character
Pound sign (#)	In most cases, you can define multiple matching patterns in a text file and pass that file into the utility. This is generally easier than specifying multiple matches directly on the command line.
	However, when using a text file to pass in pattern matches, the pound sign (#) is interpreted as a comment if it appears at the beginning of a matching pattern. This causes that entire pattern matching entry to be ignored.

Output description

Specific messages are returned when an mccli command completes either successfully or unsuccessfully.

When an mccli command completes successfully, the following message is returned:

0,23000,CLI command completed successfully.

The message comprises three separate comma-delimited elements:

- The first element is the numeric return code, which is zero (0) because the command successfully completed.
- The second element is the numeric event code, 23000.
- The third element is the event code short description, CLI command completed successfully.

When an mccli command does not complete successfully, the output message is in the same format, but the return code is one (1) and the event code describes the error condition. For example:

1,22288, Dataset does not exist.

Command line syntax

This is the proper format and syntax for all mccli commands.

Syntax

```
mccli resource-class command command-options
global-options display-options
```

Resource classes

Each mccli command line must specify one and only one of the resource classes.

activity

Cancel or show backup, restore, or validation activities.

agent

Shows summary properties for all client agents.

backup

Restore folders and files to backup clients, and manage backups stored on the Avamar server.

checkpoint

Manage Avamar server checkpoints.

client

Manage backup client accounts on the Avamar server.

dataset

Manage backup datasets on the Avamar server.

dd

Manage Data Domain systems for use as Avamar backup targets.

domain

Manage Avamar server domains and subdomains.

dump

Dumps various DPNProxyService caches for troubleshooting purposes. Strictly reserved for EMC internal use only.

event

Access and manage Avamar server event code information.

group

Manage groups and group policy.

help

Show online help on a resource-by-resource basis.

mcs

Control various Management Console Server (MCS) functions.

plugin

Manage client plug-ins on the Avamar server.

retention

Manage backup retention policies.

schedule

Manage Avamar server schedules.

server

Monitor various Avamar server functions.

user

Manage backup user accounts.

vcenter

Browses a vCenter to locate virtual machines.

version

Shows the version of mccli currently installed.

vmcache

Assists with debugging possible vCenter data cache synchronization issues. Strictly reserved for EMC internal use only.

Commands

The list of possible commands is specific to each resource class. Individual resource class listings provide a list of commands available for each resource class.

Command options

The list of possible command options is specific to each combination of resource class and command. The individual command listings provide a list of command options available for each command.

Global options

Each mccli command line can contain one or more of the following options, which are global in nature, meaning that they can be used with any resource class or command.

```
--mcsprofile=String
```

Specifies the MCS profile name. If you supply this option, then settings stored in this profile are used, and other global options that you supply on the command line are ignored.

--mcsaddr*String*

Specifies the MCS network name or IP address.

- --mcsuserid*String*
- --mcspasswd*String*

Specifies an Avamar user account and password that is used to run mccli commands.

--mcsport*Integer*

Specifies the data port used to contact the MCS.

Typically, global options are persistently stored and read from the mccli.xml preferences file. You only supply the global options on an mccli command line in cases where the persistent settings must be temporarily overridden.

Display options

Each mccli command line can contain either of the following options, which control how command output is displayed.

--xml

Formats output as XML. This is useful for parsing output as part of a script.

--normalize

Produces output in a format that better supports parsing and comparison. This option affects any command that returns a date or time, or file system information such as capacity or file sizes.

The following table shows examples of returned values expressed in both default and normalized formats.

Table 5 Returned values in default and normalized formats

Value	Default format	Normalized format
Absolute time	Expressed as a conventional date and timestamp with the local timezone. For example: 2011-09-12 11:00:17 PDT	Expressed as an integer representing the UNIX precision time format numerical (UTC milliseconds from the epoch). For example: 1189620017000
Elapsed time	Expressed as the number of days, hours, minutes, and seconds that have elapsed. For example: 12 days 17h:30m	Expressed as an integer representing the total number of milliseconds that have elapsed. For example: 1099814000
Capacity	Expressed in bytes, MB, GB, or TB, whichever is most correct. For example: 1.3 TB	Expressed as an integer representing the total number of bytes. For example: 1464957140992

Enumerating valid object IDs

Several mccli command options require precise case-sensitive string or numeric object IDs for input values.

The following table lists mccli commands that return lists of valid object IDs.

Table 6 Enumerating valid object IDs

Object ID	Data type	Command
Activity ID	String	mccli activity show
Backup label	Integer	mccli backup show
Checkpoint ID	String	mccli checkpoint show
Client name	String	mccli client show
Dataset name	String	mccli dataset show
Domain name	String	mccli domain show

Table 6 Enumerating valid object IDs (continued)

Object ID	Data type	Command
Event ID	Integer	mccli event show
Group name	String	mccli group show
Plug-in ID	Integer	mccli plugin show
Retention policy name	String	mccli retention show
Schedule name	String	mccli schedule show
Time zone name	String	mccli schedule show-timezones
Service name	String	mccli server show-services
User account names	String	mccli user show
Authentication system name	String	mccli user show-auth

Global event codes

These events codes are global, which means that they can be returned for any mccli command. However, in the event of an error, many mccli commands return other event codes that more fully describe the specific error condition encountered. Those event codes are listed with each mccli command.

22601	Server inactive.
23000	CLI command successfully completed.
23001	Arguments required by CLI command are either missing or empty.
23993	Attempt to read or write a file has failed.
23995	Invalid option specified on the CLI.
23996	Failed to connect to the administrator server.
23997	Conflicting arguments specified on the command line.
23998	CLI command failed.
23999	Unexpected command failure.

Deprecated resources and commands

Deprecated resources and commands will continue to work, but should not be used for new integrations. If documentation for these deprecated resources and commands is required, refer to previous versions of this publication.

The following tables list deprecated resources and commands.

Table 7 Deprecated resources

Deprecated resource	Use instead
snapup	backup

Table 8 Deprecated commands

Deprecated command	Use instead
client activate	client invite
client load-bulk	client import-clients-from-file
client snapup-dataset	client backup-dataset
client snapup-group-dataset	client backup-group-dataset
client snapup-target	client backup-target
client validate-bulk	client validate-clients-from-file
group show-client-members	group show-members
group snapup	group backup

activity

The mccli activity resource is used to cancel or show backup, restore, and validation activities.

activity cancel

The mccli activity cancel command cancels a backup, restore, or validation activity. If the activity has already completed, then the command returns an event code indicating that the activity ID is invalid, along with information indicating that the job has already completed.

Syntax

mccli activity cancel --id=String --wait[=min]

Options

--id=String

Cancels the specified activity ID. *String* must be a valid activity ID. This argument is required.

Use mccli activity show to return a list of valid activity IDs.

--wait[=*min*]

Specifies a time period in minutes (min) that this command waits for the initiated operation to complete. If the operation completes before then, status is shown sooner. This option also shows more detailed status. If --wait=0 or --wait (no value) is supplied, the command waits indefinitely for the activity to complete.

Event codes

22205	Backup cancelled via console.
23010	Invalid ID specified on the CLI.
23023	Activity already completed.

activity get-log

The mccli activity get-log command displays the contents of the session log file for an activity. Use the --xml display option to show escaped log file content.

Syntax

```
mccli activity get-log --id=String
```

Options

```
--id=String
```

Gets log files for this activity ID. *String* must be a valid activity ID. This argument is required.

Use mccli activity show to return a list of valid activity IDs.

Event codes

23010 Invalid ID specified on the CLI.

activity show

The mccli activity show command lists backup, restore, and validation activities with summary information, or detailed information for a specific activity. If you are viewing summary information for multiple activities, you can filter the information on a domain or client basis.

Syntax

```
mccli activity show
{--domain=String(/) | --name=String [--domain=String(/)]}
[--active=Boolean(false)] [--completed=Boolean(false)]
[--contained-vm-activities=Boolean(false)] [--id=String]
[--name=String] [--queued=Boolean(false)]
[--source={avamar | dd}] [--verbose=Boolean(false)]
```

Options

```
--active=Boolean(false)
```

If true, then only currently running activities are shown.

```
--completed=Boolean(false)
```

If true, then only completed activities are shown.

```
--contained-vm-activities=Boolean(false)
```

If true, shows activities for virtual machine clients within VMware containers or vApps. This option is only valid if the client specified by --name is a VMware container or vApp.

```
--domain=String(/)
```

If supplied without --name, shows all activities for that domain.

If supplied with --name, specifies the Avamar server domain where that client resides.

```
--id=String
```

Specifies which activities to show. *String* must be a valid activity ID. Multiple --id options can be specified on the same command line.

Use mccli activity show to return a list of valid activity IDs.

```
--name=String
```

Shows activities for the specified client.

If *String* is a fully qualified client name (for example, /clients/MyClient), then the --domain option is ignored.

Use mccli client show to return a list of valid client names.

```
--queued=Boolean(false)
```

If true, then only queued activities are shown.

```
--source={avamar | dd}
```

If avamar is specified, then the command shows activities for the Avamar server.

Ifdd is specified, then the command shows activities for all configured Data Domain systems.

```
--verbose=Boolean(false)
```

If true, then detailed activity information is returned.

If false or not supplied, then summary information is returned.

Examples

This command returns activities for all virtual machine clients in the 10.31.183.55/FO2 container, with output formatted as XML:

```
mccli activity show --name=/10.31.183.55/FO2
--contained-vm-activities=true --verbose=true --xml
```

```
<CLIOutput>
 <Results>
  <ReturnCode>0</ReturnCode>
  <EventCode>23000</EventCode>
  <EventSummary>CLI command completed successfully.</EventSummary>
 </Results>
 <Data>
   <ID>9134224603666509</ID>
   <Status>Completed</Status>
    <ErrorCode>0</ErrorCode>
   <StartTime>2013-07-14 06:07 UTC</StartTime>
   <Elapsed>00h:00m:46s</Elapsed>
   <EndTime>2013-07-14 06:08 UTC</EndTime>
   <Type>On-Demand Backup</Type>
    <ProgressBytes>4,200,757
   <NewBytes>0.1%</NewBytes>
    <Client>TEST1</Client>
   <Domain>/10.31.183.55/HleDynamicClients/Domain>
    <OS>windows7Server64Guest</OS>
    <ClientRelease>7.1.100-333</ClientRelease>
   <Sched.StartTime>2013-07-14 06:07 UTC</Sched.StartTime>
    <Sched.EndTime>2013-07-15 06:07 UTC</Sched.EndTime>
   <ElapsedWait>00h:00m:29s</ElapsedWait>
   <Group>Admin On-Demand Group</Group>
    <Plug-In>Windows VMware Image</Plug-In>
   <RetentionPolicy>Default Retention/RetentionPolicy>
    <Retention>N</Retention>
    <Schedule>Admin On-Demand Schedule</Schedule>
    <Dataset>/Client On-Demand Data/Dataset>
    <WID>MOD-1342246036652 42992503ce8f11c007c26d73711fac08f5d5e331
    </WID>
```

```
<Server>Avamar</Server>
  <Container>F02</Container>
  </Row>
  </Data>
</CLIOutput>
```

agent show

The mccli agent show command shows summary properties for all client agents.

Syntax

mccli agent show

backup

The mccli backup resource is restore folders and files to backup clients, and manage backups stored on the Avamar server.

backup delete

The mccli backup delete command permanently deletes a backup from the server.

Syntax

```
mccli backup delete --name=String --created=String
--labelNum=Integer [--contained-vm-name=String]
[--domain=String(/)] [--force=Boolean(false)]
```

Options

--contained-vm-name=String

Specifies a virtual machine client within a VMware container or vApp. This option is only valid if the client specified by --name is a VMware container or vApp.

```
--created=String
```

Specifies the date the backup was created. *String* must be in the format of YYYY-MM-DD. This argument is required.

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the client specified by --name.

```
--force=Boolean(false)
```

By default, if you attempt to delete a backup that has more than one retention type assigned to it, then a warning is issued and the backup is not deleted. This is intended to prevent inadvertent deletion of a single backup that could remove more than one level of historical backups (daily, weekly, monthly, or yearly) from the server.

If true, then the checking is disabled and the backup is deleted regardless of the number of retention types assigned to it.

--labelNum=*Integer*

Specifies the label number of the backup to delete. This argument is required.

Use ${\tt backup}\ {\tt show}\ without\ supplying\ --labelNum\ to\ return\ a\ list\ of\ backups\ with\ integer\ label\ numbers.$

```
--name=String
```

Specifies the client from which the backup was originally taken. This argument is required.

If you supply a fully qualified client name (for example, /clients/MyClient), then --domain is ignored.

Use mccli client show to return a list of valid client names.

Event codes

22236	Client does not exist.
22552	Backup does not exist.
22553	Backup deleted.
22556	Changed backup retention.
22558	Multiple retention tags exist.

Examples

This command deletes the first backup (--labelNum=1) created on 2014-07-14 for virtual machine client TEST1 in the 10.31.183.55/FO2 container:

mccli backup delete --name=/10.31.183.55/FO2 --contained-vm-name=TEST1
--created="2014-07-14" --labelNum=1

backup edit

The mccli backup edit command enables you to change the backup expiration date.

You can change the backup expiration date by any of the following methods:

- Directly specifying a new expiration date, or that the backup should never expire
- Extending the existing expiration date
- Assigning an extended retention type to a backup

Syntax

```
mccli backup edit --name=String
--created=String --labelNum=Integer
{--expiration={YYYY-MM-DD | NO_EXPIRATION}
| --extend-expiration=+nn{D | W | M | Y}
| --retention={{D | daily} | {W | weekly}
| {M | monthly} | {Y | yearly} | none}}
[--contained-vm-name=String] [--domain=String(/)]
[--force=Boolean(false)]
```

Options

```
--contained-vm-name=String
```

Specifies a virtual machine client within a VMware container or vApp. This option is only valid if the client specified by --name is a VMware container or vApp.

--created=String

Specifies the date the backup was created. *String* must be in the format of YYYY-MM-DD. This argument is required.

--domain=String(/)

Specifies the Avamar server domain that contains the client specified by --name.

Use mccli domain show to return a list of valid domain names.

--expiration={YYYY-MM-DD|NO EXPIRATION}

Specifies a new expiration date.

- A specific calendar date, in the format of YYYY-MM-DD
- NO EXPIRATION specifies that the backup should never expire

The --expiration, --extend-expiration, and --retention options are mutually exclusive.

--extend-expiration=+nn{D | W | M | Y}

Extends the existing expiration date. Where *nn* is an integer, valid values are:

- +nnD—number of additional days added to the existing backup expiration date
- \bullet + nnW—number of additional weeks added to the existing backup expiration date
- +nnM—number of additional months added to the existing backup expiration date
- +nnY—number of additional years added to the existing backup expiration date

The --expiration, --extend-expiration, and --retention options are mutually exclusive.

--force=Boolean(false)

By default, if you attempt to delete a backup that has more than one retention type assigned to it, then a warning is issued and the backup is not deleted. This is intended to prevent inadvertent deletion of a single backup that could remove more than one level of historical backups (daily, weekly, monthly, or yearly) from the server.

If true, then the checking is disabled and the backup is deleted regardless of the number of retention types assigned to it.

--labelNum=*Integer*

Specifies the label number of the backup to delete. This argument is required.

Use backup show without supplying --labelNum to return a list of backups with integer label numbers.

--name=String

Specifies the client from which the backup was originally taken. This argument is required.

If you supply a fully qualified client name (for example, /clients/MyClient), then --domain is ignored.

Use mccli client show to return a list of valid client names.

Specifies the extended retention types to assign to this backup.

--retention={{D | daily} | {W | weekly} | {M | monthly} | {Y | yearly} | none}

Both short form and long formnone retention type values are allowed and can be mixed. For example, all of the following are valid:

- --retention=D, weekly
- --retention=Daily, W, monthly

The --expiration, --extend-expiration, and --retention options are mutually exclusive.

Event codes

22236	Client does not exist.
22552	Backup does not exist.
22556	Changed backup retention.
22557	$\label{eq:Failed} \textbf{Failed to modify retention of a backup.}$
22558	Multiple retention tags exist.

Examples

This command changes backup retention to daily for the second backup (--labelNum=2) created on 2014-07-14 for virtual machine client TEST1 in the 10.31.183.55/FO2 container:

```
mccli backup edit --name=/10.31.183.55/FO2
--contained-vm-name=TEST1 --labelNum=2 --created=2014-07-14
--retention=D
```

backup restore

The mccli backup restore command restores data to a client.

This command returns an activity ID, which can be passed to meeli activity show to get status for the restore activity.

This command supports any of the following restore scenarios:

- If restoring from a normal (non-virtual) filesystem or application backup:
 - Restore entire backup to the same (non-virtual) client
 - Restore selected folders or files to the same (non-virtual) client
 - Redirected restore of selected folders or files to a different (non-virtual) client
- If restoring from a VMware image backup:
 - Restore an entire VMware image backup to the same virtual machine
 - Redirected restore an entire VMware image backup to a different existing virtual machine
 - Redirected restore an entire VMware image backup to the new virtual machine
 - Restore selected folders or files to the same virtual machine
 - Redirected restore of selected folders or files to a different virtual machine

Syntax

```
mccli backup restore --name=String --labelNum=Integer
[--cmd=String [--cmd=String ...]]
[--contained-vm-name=String] [--data={all | vmdk-filename}]
[--datacenter=String] [--datastore-name=String]
[--dest-client-domain=String] [--dest-client-name=String]
[--dest-client-username=String --dest-client-password=String]
[--dest-dir=String] [--domain=String(/)]
[--esx-host-name=String] [--esx-host=String] [--folder=String]
[--network-old=String --network-new=String]
[--plugin=Integer] [--resource-pool=String]
[--restore-vm-to={original | existing | new | flr}
[--virtual-center-name=String] [--vm-configuration=Boolean(false)]
[--wait[=min]]
```

Options

```
--cmd=String
```

Specifies one ore more optional plug-in commands. You can supply multiple ——cmd arguments, but each argument can only specify one plug-in command.

For example, this is valid --cmd syntax:

```
--cmd="verbose=5" --cmd="throttle=5"
```

However, this is not valid --cmd syntax:

```
--cmd="verbose=5 throttle=5"
```

```
--contained-vm-name=String
```

Specifies a virtual machine client within a VMware container or vApp. This option is only valid if the client specified by --name is a VMware container or vApp.

```
--data={all | vmdk-filename}
```

Specifies a single optional target folder or file to restore.

When restoring from a VMWare image backup:

- all—restores all virtual disks
- *vmdk-filename*—restores only the virtual disk defined by *vmdk-filename*

Each --data= option can only specify one target folder or file to restore. Use multiple --data options to restore multiple targets.

```
--datacenter=String
```

When restoring a virtual machine or vApp, specifies a fully qualified datacenter name in vCenter.

This argument is required when restoring an entire image or selected disks to the same, different existing, or new virtual machine. It is not valid when restoring individual folders or files.

```
--datastore-name=String
```

When restoring a virtual machine or vApp to a new virtual machine, specifies the datastore name to be removed from the Avamar proxy. This argument is required.

```
--dest-client-domain=String
```

Specifies the Avamar server domain that contains the alternative client specified by the --dest-client-name argument.

Use mccli domain show to return a list of valid domain names.

```
--dest-client-name=String
```

When performing any redirected restore, specifies the destination client.

When performing a redirected restore of specific folders or files, you must also supply --dest-dir.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --dest-client-domain option is ignored.

Use mccli client show to return a list of valid client names.

- --dest-client-username=String
- --dest-client-password=String

When restoring folders or files from a VMware image backup, specifies the destination client username and password.

--dest-dir=*String*

When performing a redirected restore of specific folders or files, specifies the destination folder for the restored folders or files.

This argument is required when performing any redirected restore of specific folders or files, and optional for all other operations.

--domain=String(/)

Specifies the Avamar server domain that contains the client specified by --name.

Use mccli domain show to return a list of valid domain names.

--esx-host-name=*String*

When restoring a VMware image backup to a new virtual machine, specifies a fully qualified ESX server hostname in a datacenter.

--esx-host=String

When restoring a VMware image backup to a new a vApp, specifies the path to a host or cluster inside the datacenter.

--folder=String

When restoring a virtual machine or vApp to an existing or new virtual machine, specifies the folder path for the destination virtual machine in the datacenter.

--labelNum=*Integer*

Specifies the label number of the backup to delete. This argument is required.

Use backup show without supplying --labelNum to return a list of backups with integer label numbers.

--name=*String*

Specifies the client from which the backup was originally taken. This argument is required.

If you supply a fully qualified client name (for example, /clients/MyClient), then --domain is ignored.

Use mccli client show to return a list of valid client names.

- --network-old=*String*
- --network-new=*String*

When restoring a VMware image backup to a new a vApp, these options map old network setting to a new network setting. Both --network-old and --network-new options must be supplied.

36

Multiple --network-old and --network-new pairs are allowed. Multiple comma-separated mapping values are allowed for each option.

Example one-to-one mapping:

```
--network-old=vlan1 --network-new=vlan241
```

Example multiple one-to-one mappings:

```
--network-old=vlan1 --network-new=vlan241
--network-old=vlan2 --network-new=vlan242
--network-old=vlan3 --network-new=vlan243
```

Example many-to-one mapping:

```
--network-old=vlan1,vlan2,vlan3 --network-new=vlan241
```

Example combined many-to-one with one-to-one mapping:

```
--network-old=vlan1,vlan2 --network-new=vlan241 --network-old=vlan3 --network-new=vlan242
```

--plugin=*Integer*

Specifies the plug-in ID for the restore. This argument is required for all restores except vApps.

When performing a redirected restore, this argument should specify a plug-in that is compatible with the alternative destination client, not the plug-in that was originally used to perform the backup.

Use mccli plugin show to return a list of valid numeric plug-in IDs.

When restoring vApps, multiple --plugin and --cmd arguments are allowed. For example:

```
--plugin=3016 --cmd=--test=true --cmd=--test1=false --plugin=1016 --cmd=--test3=true
```

In this example, --test and --test1 are processed by plug-in 3016; --test3 is processed by plug-in 1016.

```
--resource-pool=String
```

When restoring a VMware image backup to a new a vApp, specifies a resource pool on the ESX host.

```
--restore-vm-to={original | existing | new | flr}
```

When restoring a VMware image backup, specifies the type of restore operation. String must be one of the following:

- original—restores the entire backup image to the original virtual machine or vApp
- existing—restores the entire backup image to a different existing virtual machine
- new—restores the entire backup image to a new virtual machine or vApp
- flr—restores folders or files

```
--virtual-center-name=String
```

When restoring a VMware image backup to an existing or new virtual machine or vApp, specifies the vCenter name.

```
--vm-configuration=Boolean(false)
```

When restoring a VMware image backup to an existing virtual machine or vApp, and this argument is true, VMware configuration files are restored.

```
--wait[=min]
```

Specifies a time period in minutes (min) that this command waits for the initiated operation to complete. If the operation completes before then, status is shown sooner. This option also shows more detailed status. If --wait=0 or --wait (no value) is supplied, the command waits indefinitely for the activity to complete.

Event codes

22236	Client does not exist.
22297	Request to restore is rejected.
22312	Client restore scheduled.
23009	Invalid plugin specified on the CLI.

Examples

This command restores an entire VMware image backup to the original virtual machine:

mccli backup restore --name=/Test/Test1 --labelNum=1 --plugin=3016
--restore-vm-to=original

This command restores an entire VMware image backup to a different existing virtual machine:

mccli backup restore --name=/Test/Test1 --labelNum=1 --plugin=3016 --restore-vm-to=existing --datacenter=Test/ESX40 --virtual-center=Test --dest-client-name=abcdef

This command restores virtual disk from a VMware image backup to a new virtual machine:

```
mccli backup restore --name=/Test/Test1/ --labelNum=2 --plugin=3016
--restore-vm-to=new --datacenter=VAAYU-DEV-WIN
--virtual-center-name=vcenter-1.example.com --datastore-name=Storage1
--esx-host-name=10.31.183.7 --dest-client-name=Test12345
--folder=Discovered virtual machine
--data=[Storage1] Disk-1/Disk-1.vmdk
```

This command restores selected folders and files to a different existing virtual machine:

```
mccli backup restore --name=/Test/Test1 --labelNum=1 --plugin=3019
--restore-vm-to=flr --dest-client-name=Test5
```

```
--dest-client-domain=/Test/Test --dest-client-username=Administrator
--data=C:\\1.log --dest-dir=C:\\ --dest-client-password=abcdefgh
```

This command restores a vApp to the original vApp:

```
mccli backup restore --name=/10.31.183.55/ABCD1
--contained-vm-name=YYY --labelNum=1
--restore-vm-to=original --vm-configuration=true
```

This command restores a vApp to the original vApp with plug-in command line options:

```
mccli backup restore --name=/10.31.183.55/ABCD1
--contained-vm-name=YYY --labelNum=1
--restore-vm-to=original --plugin=3016
--cmd=--allnodes=false --cmd=--test=true
--plugin=1016 --cmd=--allnodes=true
```

This command restores a vApp to a new vApp:

```
mccli backup restore --name=/10.31.183.55/ABCD1
--contained-vm-name=YYY --labelNum=1
--restore-vm-to=new --datacenter=DCF1/DCF2
--virtual-center-name=10.31.183.55 --datastore-name=datastore1
--esx-host=HOF1/HOF2/10.31.183.17 --dest-clientname=MyRestorevApp
--folder=FO1/FO2 --resource-pool=RP1/RP2
--network-old=VM Network --network-new=VM Network
```

backup show

The mccli backup show command returns all backups currently stored on the Avamar server or a Data Domain system for a client.

Syntax

```
mccli backup show --name=String --labelNum=Integer
[--after=String] [--before=String]
[--contained-vm-name=String] [--dir=String]
[--domain=String(/)] [--recursive=Boolean(false)]
```

```
[--retention={{D | daily} | {W | weekly}
| {M | monthly} | {Y | yearly} | none}]
[--verbose=Boolean(false)]
```

Options

--after=String

Only show backups created after this date. *String* must be in the format of YYYY-MM-DD.

--before=String

Only show backups created before this date. *String* must be in the format of YYYY-MM-DD.

--contained-vm-name=String

Specifies a virtual machine client within a VMware container or vApp. This option is only valid if the client specified by --name is a VMware container or vApp.

--dir=String

Specifies a top-level parent folder of the backup from which to begin listing folders and files.

--domain=String(/)

Specifies the Avamar server domain that contains the client specified by --name.

Use mccli domain show to return a list of valid domain names.

--labelNum=*Integer*

Specifies the label number of the backup. This argument is required.

Use backup show without supplying --labelNum to return a list of backups with integer label numbers.

--name=*String*

Specifies the client for which to show backups. This argument is required.

If you supply a fully qualified client name (for example, /clients/MyClient), then --domain is ignored.

Use mccli client show to return a list of valid client names.

--recursive=Boolean(false)

If true, then backup folders and files are recursively shown.

```
--retention=\{\{D \mid daily\} \mid \{W \mid weekly\} \mid \{M \mid monthly\} \mid \{Y \mid yearly\} \mid none\}
```

Specifies the extended retention types to show.

Both short form and long formnone retention type values are allowed and can be mixed. For example, all of the following are valid:

- --retention=D, weekly
- --retention=Daily, W, monthly

The --expiration, --extend-expiration, and --retention options are mutually exclusive.

--verbose=Boolean(false)

If true, then detailed information is returned.

Event codes

22236 Client does not exist.

Failed to retrieve the backups for a client.

Examples

This command returns a list of backups for MyClient:

mccli backup show --name=clients/MyClient

This command returns backups for virtual machine TEST1, which resides inside VMware container 10.31.183.55/FO2:

mccli backup show --name=/10.31.183.55/FO2 --verbose=true --contained-vm-name=TEST1 --xml

```
<CLIOutput>
 <Results>
  <ReturnCode>0</ReturnCode>
  <EventCode>23000</EventCode>
  <EventSummary>CLI command completed successfully.</EventSummary>
 </Results>
 <Data>
  <Row>
   <Created>2014-07-14 06:08:21 UTC</Created>
   <LabelNum>1</LabelNum>
   <Size>4200757</Size>
   <Retention>N</Retention>
   <Label>MOD-134224603642992503ce8f11c007c26d73711fac</Label>
   <Plugin>Windows VMware Image</Plugin>
   <Expires>2014-09-12 06:14:35 UTC</Expires>
   <Files />
   <Server>Avamar</Server>
  </Row>
 </Data>
</CLIOutput>
```

This command returns backups for vApp 10.31.183.55/APP1:

mccli backup show --name=/10.31.183.55/APP1 --verbose=true --xml

```
<CLIOutput>
<Results>
 <ReturnCode>0</ReturnCode>
 <EventCode>23000</EventCode>
 <EventSummary>CLI command completed successfully.</EventSummary>
</Results>
<Data>
  <Row>
  <Created>2014-07-14 06:42:46 UTC</Created>
  <LabelNum>1</LabelNum>
  <Size>4204699</Size>
  <Retention>N</Retention>
  <Label>MOD-134224603642992503ce8f11c007c26d73711fac</Label>
  <Plugin />
  <Expires>2014-09-12 06:49:40 UTC</Expires>
  <Files />
  <Server>Avamar
  <Networks>VM Network, Test2
 </Row>
```

```
</Data>
</CLIOutput>
```

backup validate

The mccli backup validate command initiates a validation of a backup.

Syntax

```
mccli backup validate --name=String
--labelNum=Integer --plugin=Integer
[--cmd=String [--cmd=String ...]
[--dest-client-domain=String] [--dest-client-name=String]
[--wait[=min]]
```

Options

```
--cmd=String
```

Specifies one ore more optional plug-in commands. You can supply multiple --cmd arguments, but each argument can only specify one plug-in command.

For example, this is valid --cmd syntax:

```
--cmd="verbose=5" --cmd="throttle=5"
```

However, this is not valid --cmd syntax:

```
--cmd="verbose=5 throttle=5"
```

```
--dest-client-domain=String
```

Used with --dest-client-name to validate a replicated backup (that is, a backup for a client in the REPLICATE domain) on an alternate client.

Specifies the Avamar server domain that contains the alternative client specified by the --dest-client-name argument.

Use mccli domain show to return a list of valid domain names.

```
--dest-client-name=String
```

When performing any redirected restore, specifies the destination client.

When performing a redirected restore of specific folders or files, you must also supply --dest-dir.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --dest-client-domain option is ignored.

Use mccli client show to return a list of valid client names.

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the client specified by --name.

Use mccli domain show to return a list of valid domain names.

```
--labelNum=Integer
```

Specifies the label number of the backup. This argument is required.

Use backup show without supplying ——labelNum to return a list of backups with integer label numbers.

```
--name=String
```

Specifies the client from which the backup was originally taken. This argument is required.

If you supply a fully qualified client name (for example, /clients/MyClient), then --domain is ignored.

Use mccli client show to return a list of valid client names.

--plugin=*Integer*

Specifies the plug-in ID for the restore. This argument is required.

Use mccli plugin show to return a list of valid plug-in IDs.

--wait[=*min*]

Specifies a time period in minutes (min) that this command waits for the initiated operation to complete. If the operation completes before then, status is shown sooner. This option also shows more detailed status. If --wait=0 or --wait (no value) is supplied, the command waits indefinitely for the activity to complete.

Event codes

22236	Client does not exist.
22298	Request to validate is rejected.
22315	Client validate scheduled.
23009	Invalid plugin specified on the CLI.

checkpoint

The mccli checkpoint resource is used to manage Avamar server checkpoints.

checkpoint cancel-validate

The mccli checkpoint cancel-validate command cancels an active (currently running) checkpoint validation

Syntax

mccli checkpoint cancel-validate

Event codes

A checkpoint validation was cancelled.No checkpoint validation is running.

checkpoint create

The mccli checkpoint create command creates a checkpoint. An MCS flush occurs as part of the checkpoint.

Syntax

mccli checkpoint create [--wait[=min]]

Options

--wait[=*min*]

Specifies a time period in minutes (min) that this command waits for the initiated operation to complete. If the operation completes before then, status is shown

sooner. This option also shows more detailed status. If --wait=0 or --wait (no value) is supplied, the command waits indefinitely for the activity to complete.

Event codes

22608	An Avamar server checkpoint was successfully created.
22609	An error occurred creating an Avamar server checknoint

checkpoint delete

The mccli checkpoint delete command permanently deletes a checkpoint from the Avamar server.

Syntax

mccli checkpoint delete --cptag=String

Options

--cptag=String

Specifies which checkpoint to delete. *String* must be a valid checkpoint ID. This argument is required.

Use mccli checkpoint show to return a list of valid checkpoint IDs.

Event codes

22611 An Avamar server checkpoint was not successfully deleted.

22617 The specified checkpoint was not found.

checkpoint show

The mccli checkpoint show command lists all checkpoints with summary or detailed information.

Syntax

mccli checkpoint show [--verbose=Boolean(false)]

Options

--verbose=Boolean(false)

If true, then detailed checkpoint information is returned.

If false, then summary information is returned.

Event codes

22531 Unexpected exception occurred.

checkpoint validate

The mccli checkpoint validate command validates (performs an HFS check on) a checkpoint.

Syntax

```
mccli checkpoint validate --cptag=String
[--checktype={full | rolling}] [--wait[=min]]
```

Options

--checktype={full|rolling}

Constrains checkpoint validation to one or more of the following checkpoint types:

- full—Perform all HFS checks
- rolling—Perform rolling HFS check

```
--cptag=String
```

Specifies which checkpoint to validate. *String* must be a valid checkpoint ID. This argument is required.

Use mccli checkpoint show to return a list of valid checkpoint IDs.

```
--wait[=min]
```

Specifies a time period in minutes (min) that this command waits for the initiated operation to complete. If the operation completes before then, status is shown sooner. This option also shows more detailed status. If --wait=0 or --wait (no value) is supplied, the command waits indefinitely for the activity to complete.

Event codes

- 22612 Starting to validate an Avamar server checkpoint.
- The specified checkpoint was not found.

client

The mocli client resource is used to manage backup client accounts on the Avamar server.

client add

The mccli client add command registers a new client with the MCS and adds it to the default group. The client need not be connected to the network. Registering a client allows you to subsequently define policies for that client, even if the client has not yet been activated.

Note

The ${\tt mccli}$ client add command cannot be used to add clients to the ${\tt REPLICATE}$ domain.

Syntax

```
mccli client add --name=String
[--changed-block-tracking=Boolean(false)] [--contact=String]
```

```
[--container-path=String] [--datacenter=String]
[--dataset-domain=String(/)] [--dataset=String]
[--domain=String(/)] [--email=String]
[--encryption={High | Medium | None}] [--folder=String]
[--host=String] [--location=String]
[--override-encryption=Boolean(false)]
[--override-retention=Boolean(false)]
[--overtime-option={ALWAYS | NEVER | NEXT | NEXT_SUCCESS}]
[--overtime=Boolean(false)] [--pageable=Boolean(false)]
[--pageaddr=String] [--pageport=String] [--phone=String] []
[--retention-domain=String(/)] [--retention=String]
[--type={normal | vcenter | proxy | vmachine | vcontainer | vapp}]
[--view-type={datastore | host-cluster | vm-template}]
[--virtual-center-name=String] [--virtual-center-password=String]
```

Options

--changed-block-tracking=Boolean(false)

If true, when adding a virtual machine, VMware container, or vApp client, changed block tracking is enabled.

--contact=String

Specifies responsible party contact information.

--container-path=String

When adding a VMware container or vApp, specifies the inventory path to that container.

--datacenter=String

When adding a virtual machine client, VMware container or vApp, specifies a fully qualified datacenter name in vCenter. This argument is required.

```
--dataset-domain=String(/)
```

Specifies the Avamar server domain that contains the dataset specified by the —— dataset argument.

Use mccli domain show to return a list of valid domain names.

--dataset=String

Specifies an alternative dataset this client will use for on-demand backups, or when the group dataset is overridden. *String* must be a valid dataset name.

Use mccli dataset show to return a list of valid dataset names.

--domain=String(/)

Specifies the domain for the new client.

--email=String

Specifies responsible party email address.

--encryption={High | Medium | None}

Specifies the encryption method that the client should use when performing ondemand backups and restores, or when the group encryption method is overridden.

46

Note

The exact encryption technology and bit strength used for any given client/server connection depends on a number of factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides additional information.

--folder=String

When adding a virtual machine client, specifies the folder path for virtual machines in the datacenter.

--host=String

If adding a VMware container or vApp, and --view-type=host-cluster, this option specifies the host path inside the datacenter.

--location=*String*

Specifies location information.

--name=String

Specifies the new client name. This argument is required.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --domain argument is ignored.

--override-encryption=Boolean(false)

If true, then use the encryption method specified by --encryption instead of the group encryption method for scheduled backups.

--override-retention=Boolean(false)

If true, then use the retention policy specified by --retention instead of the group retention policy for scheduled backups.

--overtime-option={ALWAYS | NEVER | NEXT | NEXT_SUCCESS}

Specifies scheduled group backup overtime behavior:

- ALWAYS—scheduled group backups can always run past the schedule duration setting.
- NEVER—scheduled group backups can never run past the schedule duration setting.
- NEXT—only the next scheduled group backup can run past the schedule duration setting.
- NEXT_SUCCESS—scheduled group backups can run past the schedule duration setting until a successful backup is completed.

The default is NEXT SUCCESS.

--overtime=Boolean(false)

If true, then client can exceed its backup window during scheduled backups.

--pageable=Boolean(false)

If true, then client can be paged for the purpose of initiating activation or picking up new backup or restore work.

--pageaddr=String

Specifies the IP address that the Avamar server can use to contact the client.

--pageport=*String*

Specifies the data port that the Avamar server can use to contact the client.

--phone=String

Specifies responsible party telephone number.

--retention-domain=String(/)

Specifies the Avamar server domain that contains the retention policy specified by the --retention argument.

Use mccli domain show to return a list of valid domain names.

--retention=*String*

Specifies an alternative retention policy this client will use for on-demand backups, or when the group retention policy is overridden.

 $-- {\tt type= \{normal \mid vcenter \mid proxy \mid vmachine \mid vcontainer \mid vapp \}}$

Specifies the type of client to add:

- normal—any client that is not one of the other types. This is the default client type.
- vcenter-vCenter client.
- proxy—Avamar proxy.
- vmachine—virtual machine client.
- vcontainer—VMware container.
- vapp—VMware vApp.

The default client type is normal.

--vcontainer-inclusion={dynamic|static}

When adding a VMware container or vApp, specifies the inclusion settings:

- dynamic—includes all contents of the vCenter container, but also continuously
 monitors the container entity in vCenter, so that if changes occur (for example,
 virtual machines or folders are added or deleted), those changes will be
 automatically reflected in Avamar.
- static—only includes what is in the vCenter container at the time it is added to Avamar. If subsequent changes occur in vCenter, they will not be reflected in Avamar.

```
--view-type={datastore | host-cluster | vm-template}
```

When adding a VMware container or vApp, specifies which view will be used to locate the container or vApp inside vCenter:

- datastore—Datastores view
- host-cluster—Hosts and Clusters view
- vm-template—Virtual Machines and Templates view

```
--virtual-center-name=String
```

When adding an Avamar proxy, specifies the vCenter name.

--virtual-center-port=*Integer*

When adding a vCenter client, specifies the vCenter port address.

```
--virtual-center-username=String
```

 $\hbox{--virtual-center-password=} \textit{String}$

When adding a vCenter client, specifies the vCenter administrative username and password.

Event codes

22210	Client successfully added.
22238	Client exists.
22263	Client registration error.
22288	Dataset does not exist.
22289	Retention policy does not exist.
22558	\boldsymbol{A} domain or client with this name already exists.
23012	Invalid encryption method specified on the CLI.
30922	Failed to connect to vCenter.

Notes

The --overtime and --overtime-option arguments interact as follows:

- If you specify --overtime=true but do not specify an --overtime-option, then --overtime-option is automatically set to NEXT SUCCESS.
- If you specify --overtime=false but do not specify an --overtime-option, then --overtime-option is automatically set to NEVER.
- If you supply both overtime and overtime—option, then overtime—option takes precedence.

Examples

This command adds a new client called MyClient:

mccli client add --name=MyClient

This command adds a new client called MyClient, and formats the output in XML:

mccli client add --name=MyClient --xml

```
<CLIOutput>
<Results>
 <ReturnCode>0</ReturnCode>
 <EventCode>22210</EventCode>
 <EventSummary>Client successfully added</EventSummary>
 </Results>
 <Data>
 <Row>
  <Attribute>action</Attribute>
  <Value>add</Value>
 <Row>
  <Attribute>domain</Attribute>
  <Value>/</Value>
 </Row>
  <Attribute>node</Attribute>
  <Value>MyClient</Value>
 </Row>
```

```
<Row>
    <Attribute>clientid</Attribute>
    <Value>70279698b5f755b1bc2f41432b3b3471048478e7</Value>
    </Row>
    </Data>
</CLIOutput>
```

This command adds a new proxy called MyProxy:

mccli client add --name=/clients/MyProxy --type=proxy
--virtual-center-name=vcenter-1.example.com

```
0,22210,Client added
                              Value
Attribute
restoreOnly
                              false
restoreOnly
AllowClientOverrideSchedule
                              false
                              N/A
                              <Plugins/>
plugins
registeredDate
                              N/A
nodeName
                             MyProxy
                             MyProxy
display-nodeName
DSOverride
                              false
                             N/A
checkinDate
                           N/A
windowsHardwareProfile
clientid
                              f8888acc3c2fb8db604bd6a1abbacc5bd57b9a9d
encryptionMethod
                              hiah
pageAddress
                              N/A
canPage
                              true
backedUpDate
                              N/A
action
                              add
AllowFileSelectionOnSccBackups true
                             unKnown
false
agentVersion
pageAddrLocked
                             N/A
windowsID
enabled
                             false
isClientOs
                              false
DATASETID
                              Default:SNAPID
AllowClientAddToDataset
                              false
retryCnt
overtimeOption
                             NEXT SUCCESS
RPOverride
                              false
modifiedDate
                              Thu Aug 25 04:45:21 UTC 2014
AllowSccBackups
                              true
                             N/A
nodeAddress
timeOut
                              10
registered
                              false
POLICYID
                              Default: POLICYID
overrideEncryption
                              false
OverrideStandardSccRetpol false
fullName /clients/MyProxy
```

This command adds a new virtual machine client residing in the vcenter-1.example.com/ VirtualMachines/Lab1 folder:

```
mccli client add --type=vmachine --name=new-vm
--datacenter=Datacenter1
--domain=/vcenter-1.example.com/VirtualMachines
--folder=Lab1
```

```
0,22210,Client added
Attribute Value

restoreOnly false
AllowClientOverrideSchedule false
pagePort N/A
plugins <Plugins><Plugin Build="ALL" Description="Linux VMware Image"
Version="7.1.100"/></Plugins>
```

registeredDate N/A new-vm UgqlbhZtNPdDKnHEpQLMOQ nodeName display-nodeName new-vm DSOverride false N/A checkinDate windowsHardwareProfile N/A 1bdcf9e5f67a0e383202bbbe307473a59131fdcc clientid encryptionMethod high pageAddress N/A canPage true backedUpDate N/A action add AllowFileSelectionOnSccBackups true agentVersion unKnown pageAddrLocked false windowsID N/A true enabled isClientOs false DATASETID VMWARE: SNAPID AllowClientAddToDataset false retryCnt NEXT SUCCESS overtimeOption false RPOverride modifiedDate Thu Aug 25 05:06:38 UTC 2014 true AllowSccBackups nodeAddress N/A timeOut 10 false registered POLICYID Default: POLICYID overrideEncryption false OverrideStandardSccRetpol false

client add-datastore

fullName

The mccli client add-datastore command adds one or more new datastores to be protected by the specified Avamar proxy.

/vcenter-1.example.com/ACMCommunity UgqlbhZtNPdDKnHEpQLMOQ

Syntax

```
mccli client add-datastore --datacenter=String
--datastore-name=String --name=String [--domain=String(/)]
```

Options

--datacenter=String

Specifies a fully qualified datacenter name in vCenter in the format of *path*/ *name*. This argument is required.

--datastore-name=String

Specifies the datastore name to be protected by the Avamar proxy. This argument is required.

Multiple --datastore-name arguments can be supplied with a single mccli client add-datastore command.

--domain=String(/)

Specifies the Avamar server domain that contains the client specified by --name.

--name=String

Specifies the Avamar proxy to which the datastore will be added. String must be a valid Avamar proxy name. This argument is required.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --domain argument is ignored.

Event codes

22236	Client does not exist.
24003	Failed to update datastore mappings of a client.
24004	Datastore mappings of a client successfully updated

Examples

This command adds datastore Storage1 and assigns proxy backupproxy225 to it:

```
mccli client add-datastore --name=/clients/backupproxy225
--datacenter=VAAYU-DEV-WIN --datastore-name=Storage1
```

```
0,24004, Datastore mappings of a client successfully updated.
Attribute Value
------
proxyclient /clients/backupproxy225
```

client backup-group-dataset

The mccli client backup-group-dataset command initiates an on-demand backup of a single client using the group dataset. The client must already be a member of the group, or the backup fails.

This command initiates an on-demand client backup, not an on-demand group backup. Therefore, even if the client is a member of a group that is disabled and you specify the dataset for the group, the backup still occurs.

Syntax

```
mccli client backup-group-dataset --name= String
--group-name=String [--cmd=String [--cmd=...]]
[--domain=String(/)] [--group-domain=String(/)] [--wait[=min]]
```

Options

```
--cmd=String
```

Specifies one ore more optional plug-in commands. You can supply multiple ——cmd arguments, but each argument can only specify one plug-in command.

```
For example, this is valid --cmd syntax:
--cmd="verbose=5" --cmd="throttle=5"

However, this is not valid --cmd syntax:
--cmd="verbose=5 throttle=5"

--domain=String(/)
```

Specifies the Avamar server domain that contains the client specified by --name.

```
--group-domain=String(/)
    String must be
--group-name=String
    String must be
--name=String
```

Specifies which client to back up. This argument is required.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --domain argument is ignored.

```
--wait[=min]
```

Specifies a time period in minutes (min) that this command waits for the initiated operation to complete. If the operation completes before then, status is shown sooner. This option also shows more detailed status. If --wait=0 or --wait (no value) is supplied, the command waits indefinitely for the activity to complete.

Event codes

- 22226 Group disabled.
- 22228 A client was not backed up because it is disabled, retired, or its plug-in(s) has backups disabled.
- 22234 Group does not exist.
- 22236 Client does not exist.
- 22241 Client is not a member of group.
- 22253 Client Adhoc Backup Request Error Exception.
- 22305 Client backup scheduled.

client backup-target

The mccli client backup-target command initiates an on-demand backup of folders or files on a client.

This command returns an activity ID, which can be passed to meeli activity show to get status for this backup activity.

Note

The mccli client backup-target command cannot be used to back up folders or files belonging to clients in the REPLICATE domain.

Syntax

```
mccli client backup-target --name=String --target=String
[--cmd=String [--cmd= ...] [--contained-vm-name=String]
[--domain=String(/)] [--plugin=Integer] [--wait[=min]]
```

Options

```
--cmd=String
```

Specifies one ore more optional plug-in commands. You can supply multiple --cmd arguments, but each argument can only specify one plug-in command.

For example, this is valid --cmd syntax:

```
--cmd="verbose=5" --cmd="throttle=5"
```

However, this is not valid --cmd syntax:

```
--cmd="verbose=5 throttle=5"
```

--contained-vm-name=String

Specifies a virtual machine client within a VMware container or vApp. This option is only valid if the client specified by --name is a VMware container or vApp.

--domain=String(/)

Specifies the Avamar server domain that contains the client specified by --name.

--name=String

Specifies which client to back up. This argument is required.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --domain argument is ignored.

--plugin=Integer

Specifies the plug-in ID.

Use mccli plugin show to return a list of valid numeric plug-in IDs.

--target=String

Specifies the folders or files to include in the backup.

At least one --target argument is required, and you can supply more than one -- target on the same command line.

If backing up a virtual machine, individual disks can be backed up by specifying the corresponding base VMDK file. Multiple virtual disks can be backed up with additional --target arguments.

If backing up non-virtual filesystems, this argument accepts regular expression (regex) pattern matching operators, also known as wildcards.

--wait[=*min*]

Specifies a time period in minutes (min) that this command waits for the initiated operation to complete. If the operation completes before then, status is shown sooner. This option also shows more detailed status. If --wait=0 or --wait (no value) is supplied, the command waits indefinitely for the activity to complete.

Event codes

- 22228 A client was not backed up because it is disabled, retired, or its plug-in(s) has backups disabled.
- 22236 Client does not exist.
- 22253 Client Adhoc Backup Request Error Exception.
- 22305 Client backup scheduled.
- 22309 Invalid plugin specified on the CLI.

Examples

This command backs up the Test1Windows222_1.vmdk virtual disk:

```
mccli client backup-target
```

```
--name=/vcenter-1.example.com/Test1Windows222 --plugin=3016
```

--target=[Storage2] Test1Windows222/Test1Windows222_1.vmdk

```
target [Storage2] Test1Windows222/Test1Windows222_1.vmdk activity-id 9131407958056109
```

This command backs up a the TEST1 VMware container:

```
mccli client backup-target --name=/10.31.183.55/FO2
--contained-vm-name=TEST1 --plugin=3016 --target=ALL
```

client delete

The mccli client delete command permanently deletes a client and its backups from the Avamar server

Note

The \mbox{mccli} client delete command cannot be used to delete clients in the $\mbox{REPLICATE}$ domain.

Syntax

```
mccli client delete --name=String [--domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the client specified by --name.

```
--name=String
```

Specifies the client name. This argument is required.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --domain argument is ignored.

Event codes

22212	Client deleted.
22236	Client does not exist.
22240	Client delete failed.

client edit

The mccli client edit command edits the properties for a client.

There are no default settings for the mccli client edit command. If you enter this command but do not explicitly supply options and values on the command line, then there is no change to the client.

Note

The mccli client edit command cannot be used to edit clients in the REPLICATE domain.

Syntax

```
mccli client edit --name=String [--activated=Boolean(false)]
[--allow-cis-fileselection=Boolean(false)]
[--allow-cis=Boolean(false)]
 --changed-block-tracking=Boolean(false)] [--contact=String]
[--dataset-domain=String(/)] [--dataset=String]
[--domain=String(/)] [--email=String]
[--enabled=Boolean(false)]
[--encryption={High | Medium | None}]
 [--location=String] [--new-name=String]
[--override-cis-retention=Boolean(false)]
[--override-encryption=Boolean(false)]
[--override-retention=Boolean(false)]
[--overtime-option={ALWAYS | NEVER | NEXT | NEXT SUCCESS}]
 --overtime=Boolean(false)] [--page-detection={Automatic | Manual}]
 --pageable=Boolean(false)] [--pageaddr=String]
[--pageport=String] [--phone=String]
[--retention-domain=String(/)] [--retention=String]
[--timeout=String] [--vcontainer-inclusion={dynamic | static}]
 --virtual-center-name=String] [--virtual-center-port=Integer]
[--virtual-center-username=String --virtual-center-password=String]
```

Options

--activated=Boolean(false)

If true, then client is assumed to have been previously activated.

```
--allow-cis-fileselection=Boolean(false)
```

If true, then users can make file selections when they initiate a backup of the client.

```
--allow-cis=Boolean(false)
```

If true, then users can initiate a backup of the client.

```
--changed-block-tracking=Boolean(false)
```

If true, when editing a virtual machine, VMware container, or vApp client, changed block tracking is enabled.

```
--contact=String
```

Specifies responsible party contact information.

```
--dataset-domain=String(/)
```

Specifies the Avamar server domain that contains the dataset specified by the -- dataset argument.

Use mccli domain show to return a list of valid domain names.

```
--dataset=String
```

Specifies an alternative dataset this client will use for on-demand backups, or when the group dataset is overridden. *String* must be a valid dataset name.

Use mccli dataset show to return a list of valid dataset names.

```
--domain=String(/)
```

Specifies the domain for the new client.

```
--email=String
```

Specifies responsible party email address.

--enabled=Boolean(false)

If true, then client is eligible to immediately participate in on-demand and group backup and restore activities.

--encryption={High | Medium | None}

Specifies the encryption method that the client should use when performing ondemand backups and restores, or when the group encryption method is overridden.

Note

The exact encryption technology and bit strength used for any given client/server connection depends on a number of factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides additional information.

--location=*String*

Specifies location information.

--name=*String*

Specifies which client to edit. This argument is required.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --domain argument is ignored.

--new-name=*String*

Specifies a new client name.

--override-cis-retention=Boolean(false)

If true, then this retention policy is used for all user-initiated backups of the client.

--override-encryption=Boolean(false)

If true, then use the encryption method specified by --encryption instead of the group encryption method for scheduled backups.

--override-retention=Boolean(false)

If true, then use the retention policy specified by --retention instead of the group retention policy for scheduled backups.

--overtime-option={ALWAYS | NEVER | NEXT | NEXT SUCCESS}

Specifies scheduled group backup overtime behavior:

- ALWAYS—scheduled group backups can always run past the schedule duration setting.
- NEVER—scheduled group backups can never run past the schedule duration setting.
- NEXT—only the next scheduled group backup can run past the schedule duration setting.
- NEXT_SUCCESS—scheduled group backups can run past the schedule duration setting until a successful backup is completed.

The default is NEXT SUCCESS.

--overtime=Boolean(false)

If true, then client can exceed its backup window during scheduled backups.

--page-detection={Automatic | Manual}

Specifies one of the following client page detection modes:

- Automatic—use automatic paging detection (that is, ignore --pageaddr and --pageport settings)
- Manual—use --pageaddr and --pageport settings
- --pageable=*Boolean(false)*

If true, then client can be paged for the purpose of initiating activation or picking up new backup or restore work.

--pageaddr=*String*

Specifies the IP address that the Avamar server can use to contact the client.

--pageport=*String*

Specifies the data port that the Avamar server can use to contact the client.

--phone=String

Specifies responsible party telephone number.

--retention-domain=String(/)

Specifies the Avamar server domain that contains the retention policy specified by the --retention argument.

Use mccli domain show to return a list of valid domain names.

--retention=String

Specifies an alternative retention policy this client will use for on-demand backups, or when the group retention policy is overridden.

--timeout=*String*

Specifies the client browse timeout in seconds.

--vcontainer-inclusion={dynamic|static}

When adding a VMware container or vApp, specifies the inclusion settings:

- dynamic—includes all contents of the vCenter container, but also continuously
 monitors the container entity in vCenter, so that if changes occur (for example,
 virtual machines or folders are added or deleted), those changes will be
 automatically reflected in Avamar.
- static—only includes what is in the vCenter container at the time it is added to Avamar. If subsequent changes occur in vCenter, they will not be reflected in Avamar.
- --virtual-center-name=*String*

When adding an Avamar proxy, specifies the vCenter name.

--virtual-center-port=*Integer*

When adding a vCenter client, specifies the vCenter port address.

- --virtual-center-username=String
- --virtual-center-password=String

When adding a vCenter client, specifies the vCenter administrative username and password.

Event codes

22211 Client was successfully updated.

58

22236	Client does not exist.
22239	Client update failed.
23003	Invalid dataset name specified on the CLI.
23005	Invalid retention policy name specified on the CLI.
23012	Invalid encryption method specified on the CLI.
30922	Failed to connect to vCenter.

Notes

The --overtime and --overtime-option arguments interact as follows:

- If you specify --overtime=true but do not specify an --overtime-option, then --overtime-option is automatically set to NEXT SUCCESS.
- If you specify --overtime=false but do not specify an --overtime-option, then --overtime-option is automatically set to NEVER.
- If you supply both --overtime and --overtime-option, then --overtime-option takes precedence.

Examples

This command sets the data port for vCenter-1.example.com:

```
mccli client edit --name=/vCenter-1.example.com
--virtual-center-port=446
```

0,22211,Client was updated.

This command renames Proxy-1 to Proxy-2, and adds a contact phone number:

```
mccli client edit --name=/clients/Proxy1
--virtual-center-name=vCenter-1.example.com --new-name=Proxy2
--phone=555-1212
```

0,22211,Client was updated.

This command renames virtual machine client vm-1 to vm-2:

```
mccli client edit --name=/clients/vm-1 --new-name=clients/vm-2
```

0,22211,Client was updated.

This command sets dynamic inclusion for VMware container F02:

```
mccli client edit --name=/10.31.183.55/FO2
--vcontainer-inclusion=dynamic
```

0,22211,Client was updated.

This command turns on changed block tracking for VMware container F02:

```
mccli client edit --name=/10.31.183.55/FO2
--changed-block-tracking=true
```

0,22211,Client was updated.

client import-clients-from-file

The mccli client import-clients-from-file command reads a clients definition input file, then registers any clients defined in that clients definition input file.

Syntax

```
mccli client import-clients-from-file --file=String
[--verbose=Boolean(false)]
```

Options

```
--file=String
```

Specifies the full path and filename of the clients definition input file. The file must be in XML format. This argument is required.

The *EMC Avamar Administration Guide* provides additional information about clients definition files.

--verbose=Boolean(false)

If true, then a list of clients and their load status is output to stdout.

Event codes

22263	Client registration error.
22532	Client(s) successfully bulk-loaded.
23006	CLI client bulk load encountered one or more errors.

client invite

The mocli client invite command initiates activation of a specific client by first paging that client. If the client responds, then activation is completed and a Client ID (CID) is assigned to the client.

Note

The mccli client invite command cannot be used to invite clients to activate in the REPLICATE domain.

Syntax

```
mccli client invite --name=String [--domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the client specified by --name.

--name=*String*

Specifies the client name. This argument is required.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --domain argument is ignored.

Event codes

22236	Client does not exist.
22237	Client invited to activate with server.
22263	Client registration error.
22271	Client registration error - unable to contact client on port. $ \\$
22280	Client reconnect error - host name mismatch.
22282	Client reconnect error - unknown ID.
22295	Client registration error - server not available.

client move

The mocli client move command permanently moves a client and all its backups from one domain to another.

Note

The \mathtt{mccli} client \mathtt{move} command cannot be used to move clients in or out of the REPLICATE domain.

Syntax

```
mccli client move --name=String --new-domain=String
[--domain=String(/)]
```

Options

--domain=String(/)

Specifies the Avamar server domain that contains the client specified by --name.

--name=*String*

Specifies which client to move. This argument is required.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --domain argument is ignored.

--new-domain=String

Specifies the new domain for the client. This argument is required.

Event codes

22515	Client was moved.
22236	Client does not exist.
22501	Failed to move client.
23019	Client move failed - still active.

client remove-datastore

The mccli client remove-datastore command removes one or more datastores from the specified Avamar proxy.

Syntax

```
mccli client remove-datastore --datacenter=String
--datastore-name=String --name=String [--domain=String(/)]
```

Options

```
--datacenter=String
```

Specifies a fully qualified datacenter name in vCenter in the format of *path*/ *name*. This argument is required.

```
--datastore-name=String
```

Specifies the datastore name to be removed from the Avamar proxy. This argument is required.

Multiple --datastore-name arguments are allowed.

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the client specified by --name.

```
--name=String
```

Specifies the Avamar proxy from which the datastore will be removed. This argument is required.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --domain argument is ignored.

Event codes

22236	Client does not exist.
24003	Failed to update datastore mappings of a client.
24004	Datastore mappings of a client successfully updated.

Examples

This command removes datastore Storage1 from client backupproxy225:

```
mccli client remove-datastore --name=/clients/backupproxy225
--datacenter=VAAYU-DEV-WIN --datastore-name=Storage1
```

```
0,24004, Datastore mappings of a client successfully updated.

Attribute Value
------
proxyclient /clients/backupproxy225
```

client retire

The mccli client retire command retires a client from active backup activities. All backups belonging to the client expire on the dates originally assigned to them.

Note

The mccli client retire command cannot be used to retire clients in the REPLICATE domain.

Syntax

```
mccli client retire --name=String
--expiration={YYYY-MM-DD | +nn{D | W | M | Y} | NO_EXPIRATION}
[--domain=String(/)]
```

Options

```
--expiration=\{YYYY-MM-DD \mid +nn\{D \mid W \mid M \mid Y\} \mid NO\_EXPIRATION\}
```

Specifies an expiration date for backups belonging to the retired client. This argument is required.

- YYYY-MM-DD—Specifies an explicit expiration date.
- +nn{D | W | M | Y}—Specifies a duration from today. (For example, +4W specifies 4 weeks from today.)
- NO EXPIRATION—Specifies that backups should never expire.

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the client specified by --name.

```
--name=String
```

Specifies which client to retire. This argument is required.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --domain argument is ignored.

Event codes

22236	Client does not exist.	
22506	Failed to retire a client.	
22512	Client was retired.	

client show

The mccli client show command lists clients and their properties.

Syntax

```
mccli client show [--contained-vm-name=String]
[--contained-vms=Boolean(false)] [--domain=String(/)]
[--name=String] [--recursive=Boolean(false)]
[--replicated=Boolean(false)] [--retired=Boolean(false)]
[--verbose=Boolean(false)]
```

Options

--contained-vm-name=String

Specifies a virtual machine client within a VMware container or vApp. This option is only valid if the client specified by --name is a VMware container or vApp.

--contained-vms=Boolean(false)

If true, then shows details for VMware containers or vApps. This option is only valid if the client specified by --name is a VMware container or vApp.

--domain=*String(/)*

Specifies the Avamar server domain that contains the client specified by --name.

If you supply --retired, then this argument is ignored.

--name=*String*

Specifies a client name. If not supplied, all clients with the domain specified by — domain = are listed.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --domain argument is ignored.

--recursive=Boolean(false)

If true, then the command shows all clients in the domain and all subdomains specified by --domain.

If false or not supplied, then the command only shows clients in the specified domain. Subdomains are not examined.

--replicated=Boolean(false)

If true, then clients in the REPLICATE domain are shown.

If false or not supplied, then clients in the REPLICATE domain are not shown.

--retired=Boolean(false)

If true, then retired clients are listed.

If supplied, then the --domain argument is ignored.

--verbose=*Boolean(false)*

If you do not supply --name and this option is false or not supplied, then only the domain and client name are returned for each client.

If true, then other properties are also returned for each client.

This option is only meaningful when you do not supply the --name argument. When you supply--name, the details for the client are always returned.

Event codes

22236 Client does not exist.

22542 Domain does not exist.

Examples

This command returns a simple list of all clients in the clients domain:

mccli client show --domain=clients

```
0,23000,CLI command completed successfully.

command completed successfully

Name Domain

------
MyClient /clients
```

This command returns a detailed list of properties for MyClient.example.com:

mccli client show --name=/clients/MyClient.example.com

```
0,23000,CLI command completed successfully.
command completed successfully
Attribute
                                                       Value
Name
                                                       MyClient
Fully Qualified Name
                                                       /clients/MyClient.example.com
Operating System
                                                       Windows XP Professional SP 1.0
Paging
Page Address
                                                       MyClient.example.com
Page Port
                                                       28002
Paging Detection
                                                       Automatic
Agent Version
                                                       7.1.100-nnn
                                                       6e6241ae236c2ab58205f413f24d3d6e0
CID
CID Assigned
                                                       2013-10-13 00:00:00 PDT
Activated
                                                       Yes
Activated Date
                                                       2013-10-13 12:28:13 PDT
Disabled
                                                       No
Agent Last Started
                                                       2014-4-107.2.100-nnn7.1.100.nnn
06:00:00 PST
Last Check-in
                                                       2014-4-10 11:00:59 PST
Override Group Retention
                                                       No
Retention Policy
                                                       Default Retention
Allow Overtime
                                                       No
Restore Only
                                                       No
Encryption Method
                                                       High
Override Encryption
                                                       No
Allow client initiated backups
                                                       Yes
Allow file selection in client initiated backups
Override retention policy on client initiated backups No
Contact Name
Contact Phone
                                                       N/A
                                                       N/A
Contact Email
Contact Location
                                                       N/A
Contact Notes
                                                       N/A
Member of Group
                                                        /Default Group
                                                       Windows File System (3001)
Plugin
Initial Install Date
                                                       2014-4-10 12:28:14 PDT
Last Version Registered
                                                       2014-4-10 12:28:14 PDT
                                                       2014-4-10 22:00:41 PST
Last Successful Backup
```

This command shows detailed information for virtual machines in the F02 VMware container:

mccli client show --name=/10.31.183.55/FO2 --contained-vms=true --xml

This command shows detailed information for virtual machine TEST1, which resides in VMware container F02:

mccli client show --name=/10.31.183.55/FO2
--contained-vm-name=TEST1

```
0,23000,CLI command completed successfully.
Attribute
                            Value
Client Name TEST1
Fully Qualified Name /10.31.183.55/HleDynamicClients/TEST1_UCKZ3FGLz70WRRu3nq2ZuA
Client Type Virtual Machine
Paging
                              No
                            6214c7aac9ce678b0b19e4b05475d8fab58e2718
2013-07-14 05:43:38 UTC
CID
CID Assigned
Disabled No
Agent Last Started 2013-07-14 05:43:38 UTC
Override Group Retention No
Retention Policy Default Retention
Overtime Option Overtime until successful backup
Overtime Option
                              No
Restore Only
Encryption Method High
Override Encryption No
Allow CIS
                                Yes
Allow CIS file selection Yes
Override CIS retention No
                      10 seconds
Browse Timeout
Contact Name
                              N/A
                             N/A
N/A
Contact Phone
Contact Email
Contact Email N/A
Contact Location N/A
Contact Notes N/A
Member of Group /10.31.183.55/Default Virtual Machine Group
Plugin Windows VMware Image(3016)
Initial Install Date 2013-07-14 05:43:38 UTC
Last Version Registered 2013-07-14 05:43:38 UTC
Last Successful Backup N/A
```

client show-datastore

The mccli client show-datastore command returns detailed information for a datastore protected by a specific Avamar proxy.

Syntax

```
mccli client show-datastore --name=String [--domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the client specified by --name.

```
--name=String
```

Specifies the Avamar proxy that is protecting the datastore of interest. This argument is required.

Use mccli client show to return a list of valid proxy names.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --domain argument is ignored.

Event codes

22234	Group does not exist.
22236	Client does not exist.
24001	Failed to update proxy client mappings of a group.
24004	Proxy client mappings of a group successfully updated.

Examples

This command shows all datastores protected by client backupproxy225:

mccli client show-datastore --name=/clients/backupproxy225

Name	Type	Accessible	Hosts	Datacenter
Storage1	VMFS	Yes	10.31.183.7	VAAYU-DEV-WIN
Storage2	VMFS	Yes	10.31.183.7	VAAYU-DEV-WIN

client show-plugins

The mccli client show-plugins command lists all Avamar plug-ins installed on a client. If you also specify a plug-in number, then detailed information is returned for that plug-in.

Syntax

```
mccli client show-plugins --name=String
[--plugin=Integer] [--verbose=Boolean(false)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the client specified by --name.

```
--name=String
```

Specifies the client name. This argument is required.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --domain argument is ignored.

```
--plugin=Integer
```

Specifies the plug-in ID.

Use mccli plugin show to return a list of valid numeric plug-in IDs.

--verbose=Boolean(false)

If true, then detailed plug-in information is returned.

Event codes

22236	Client does not exist.
23009	Invalid plugin specified on the CLI.

client validate-clients-from-file

The mccli client validate-clients-from-file command validates a clients definition input file. The validation process ensures that the XML data is properly

formatted and that the file can be successfully processed by the mccli client import-clients-from-file command.

Syntax

```
mccli client validate-clients-from-file --file=String
[--verbose=Boolean(false)]
```

Options

```
--file=String
```

Specifies the full path and filename of the clients definition input file. The file must be in XML format. This argument is required.

The *EMC Avamar Administration Guide* provides additional information about clients definition files.

```
--verbose=Boolean(false)
```

If true, then a list of clients and their load status is output to stdout.

Event codes

23006 CLI client bulk load encountered one or more errors.

dataset

The mccli dataset resource is used to manage backup datasets on the Avamar server.

dataset add

The mccli dataset add command creates a dataset. By default, the initial dataset uses all available source data plug-ins and contains no explicit exclusion or inclusion entry entries. Use other mccli dataset commands to modify dataset properties after it has been created.

Syntax

```
mccli dataset add --name=String
[--alldata=Boolean(true)] [--domain=String(/)]
```

Options

```
--alldata=Boolean(true)
```

If true, then the initial dataset uses all available source data plug-ins and contains no explicit exclusion or inclusion entries.

If false, then the initial dataset is empty.

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the dataset specified by --name.

```
--name=String
```

Specifies the name of the new dataset. This argument is required.

If you supply a fully qualified dataset name (for example, /MyDomain/MyDataset), then the --domain argument is ignored.

Event codes

22219	Dataset created.	
23008	Dataset already exists.	

dataset add-exclude

The mccli dataset add-exclude command adds an exclusion entry to a dataset.

Syntax

```
mccli dataset add-exclude --name=String
{--exclude=String | --exclude-file=String} --plugin=Integer
[--domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the dataset specified by --name.

```
--exclude=String
```

Specifies folders or files to exclude from the dataset.

You must supply either --exclude or --exclude-file.

Multiple --exclude= arguments are allowed.

This argument accepts regular expression (regex) pattern matching operators, also known as wildcards.

```
--exclude-file=filename
```

Specifies the full path of a text *filename* that contains exclusion entries.

Each exclusion entry must conform to allowable --exclude= syntax and be on a single line.

You must supply either --exclude or --exclude-file.

```
--name=String
```

Specifies which dataset to modify. This argument is required.

Use mccli dataset show to return a list of valid dataset names.

If you supply a fully qualified dataset name (for example, /MyDomain/MyDataset), then the --domain argument is ignored.

```
--plugin=Integer
```

Specifies which plug-in ID gets the new exclusion entry. This argument is required.

Use mccli plugin show to return a list of valid numeric plug-in IDs.

Event codes

22220	Dataset modified.
22288	Dataset does not exist.
23009	Invalid plugin specified on the CLI.
23022	Error parsing input file.
23023	Input file could not be found.

dataset add-include

The mccli dataset add-include command adds an inclusion entry to a dataset.

Syntax

```
mccli dataset add-include--name=String
{--include=String | --include-file=String} --plugin=
[--domain=String(/)]
```

Options

--domain=String(/)

Specifies the Avamar server domain that contains the dataset specified by --name.

--include=*String*

Specifies the folders or files to add back to the dataset after an exclusion entry has excluded them.

You must supply either --include or --include-file.

Multiple --include arguments are allowed.

This argument accepts regular expression (regex) pattern matching operators, also known as wildcards.

--include-file=filename

Specifies the full path of a text *filename* that contains inclusion entries.

Each inclusion entry must conform to allowable --include syntax and be on a single line.

You must supply either --include or --include-file.

--name=*String*

Specifies which dataset to modify. This argument is required.

Use mccli dataset show to return a list of valid dataset names.

If you supply a fully qualified dataset name (for example, /MyDomain/MyDataset), then the --domain argument is ignored.

--plugin=*Integer*

Specifies which plug-in ID gets the new inclusion entry. This argument is required Use mccli plugin show to return a list of valid numeric plug-in IDs.

Event codes

22220	Dataset modified.
22288	Dataset does not exist.
23009	Invalid plugin specified on the CLI.
23022	Error parsing input file.
23023	Input file could not be found.

dataset add-option

The mccli dataset add-option command adds a plug-in command (option) to a dataset.

Syntax

```
mccli dataset add-option --name=String
{--option=String [--option=String] ...}
{--value=String [--value=String] ...}
--plugin=Integer [--domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the dataset specified by --name.

```
--name=String
```

Specifies which dataset to modify. This argument is required.

Use mccli dataset show to return a list of valid dataset names.

If you supply a fully qualified dataset name (for example, /MyDomain/MyDataset), then the --domain argument is ignored.

```
--option=String
--value=String
```

Specifies the plug-in command (option) name to add to the dataset. This argument is required.

Multiple --option/--value pairs are allowed.

Each client guide describes the valid plug-in commands for a specific dataset.

```
--plugin=Integer
```

Specifies which plug-in ID gets the new plug-in command (option). This argument is required

Use mccli plugin show to return a list of valid numeric plug-in IDs.

```
--value=String
```

Specifies a value for --option=. This argument is required.

Multiple --option/--value pairs are allowed.

Each client guide describes the valid plug-in commands for a specific dataset.

Event codes

22220	Dataset modified.
22288	Dataset does not exist.
23009	Invalid plugin specified on the CLI.

Notes

Plug-in commands and values, specified by the --option and --value arguments, must occur in equal numbers. Furthermore, the option-value pairing is positional. In other words, the first occurrence of --option is assigned the value specified by the first

occurrence of --value, the second occurrence of --option is assigned the value specified by the second occurrence of --value, and so forth.

dataset add-target

The mccli dataset add-target command adds a target file or folder entry to a dataset.

Syntax

```
mccli dataset add-target --name=String --plugin=Integer
{--target=String | --target-file=String} [--domain=String(/)]
```

Options

--domain=String(/)

Specifies the Avamar server domain that contains the dataset specified by --name.

--name=*String*

Specifies which dataset to modify. This argument is required.

Use mccli dataset show to return a list of valid dataset names.

If you supply a fully qualified dataset name (for example, /MyDomain/MyDataset), then the --domain argument is ignored.

--plugin=Integer

Specifies which plug-in ID gets the new target file or folder entry. This argument is required

Use mccli plugin show to return a list of valid numeric plug-in IDs.

--target=String

Specifies a target file or folder to add to the dataset. This argument is required.

You must supply either -- target or -- target-file.

Multiple -- target arguments are allowed.

This argument accepts regular expression (regex) pattern matching operators, also known as wildcards.

--target-file=filename

Specifies the full path of a text *filename* that contains target entries.

Each target entry must conform to allowable ——target syntax and be on a single line.

You must supply either -- target or -- target-file.

Event codes

22220	Dataset modified.
22288	Dataset does not exist.
23009	Invalid plugin specified on the CLI.
23022	Error parsing input file.
23023	Input file could not be found.

dataset copy

The mccli dataset copy command copies a dataset, creating a new dataset.

Syntax

```
mccli dataset copy --name=String --new-name=String
[--domain=String(/)] [--new-domain=String(/)]
```

Options

--domain=String(/)

Specifies the Avamar server domain that contains the dataset specified by --name.

--name=String

Specifies which dataset to copy. This argument is required.

Use mccli dataset show to return a list of valid dataset names.

If you supply a fully qualified dataset name (for example, /MyDomain/MyDataset), then the --domain argument is ignored.

--new-domain=String(/)

Specifies the Avamar server domain where the new dataset should be created.

--new-name=String

Specifies the new dataset name. This argument is required.

If you supply a fully qualified dataset name (for example, /MyDomain/MyDataset), then the --new-domain argument is ignored.

Event codes

22219 Dataset created.

22288 Dataset does not exist.

dataset delete

The mccli dataset delete command permanently deletes a dataset from the Avamar server. You cannot delete a dataset if it is currently assigned to a client or group.

Syntax

```
mccli dataset delete --name=String [--domain=String(/)]
```

Options

--domain=String(/)

Specifies the Avamar server domain that contains the dataset specified by --name.

--name=*String*

Specifies which dataset to delete. This argument is required.

Use mccli dataset show to return a list of valid dataset names.

If you supply a fully qualified dataset name (for example, $/{\tt MyDomain/MyDataset}$), then the $-{\tt -domain}$ argument is ignored.

Event codes

22221	Dataset deleted.

22288 Dataset does not exist.

dataset delete-exclude

The mccli dataset delete-exclude command permanently deletes exclusion entries from a dataset.

Syntax

```
mccli dataset delete-exclude --name=String
{--all | --exclude=String | --exclude-file=filename}
[--domain=String(/)]
```

Options

--all

Deletes all existing exclusion entries from the dataset.

You must supply --all, --exclude or --exclude-file.

--domain=String(/)

Specifies the Avamar server domain that contains the dataset specified by --name.

--exclude=String

Specifies the exclusion entry to delete from the dataset.

You must supply --all, --exclude or --exclude-file.

Multiple --exclude= arguments are allowed.

This argument accepts regular expression (regex) pattern matching operators, also known as wildcards.

--exclude-file=filename

Specifies the full path of a text *filename* that contains exclusion entries.

Each exclusion entry must conform to allowable --exclude= syntax and be on a single line.

You must supply --all, --exclude or --exclude-file.

--name=*String*

Specifies which dataset to modify. This argument is required.

Use mccli dataset show to return a list of valid dataset names.

If you supply a fully qualified dataset name (for example, /MyDomain/MyDataset), then the --domain argument is ignored.

--plugin=*Integer*

Specifies which plug-in ID gets the new exclusion entry. This argument is required.

Use mccli plugin show to return a list of valid numeric plug-in IDs.

Event codes

22220 Dataset modified.

22288	Dataset does not exist.
23009	Invalid plugin specified on the CLI.
23022	Error parsing input file.
23023	Input file could not be found.

dataset delete-include

The mccli dataset delete-include command permanently deletes inclusion entries from a dataset.

Syntax

```
mccli dataset delete-include --plugin=Integer
{--all | --include=String | --include-file=filename}
[--domain=String(/)]
```

Options

--all

Deletes all existing inclusion entries from the dataset.

--all, --include or --include-file are mutually exclusive. One of those arguments must be supplied with each command.

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the dataset specified by --name.

```
--include=String
```

Specifies the folders or files to add back to the dataset after an exclusion entry has excluded them.

--all, --include or --include-file are mutually exclusive. One of those arguments must be supplied with each command.

Multiple --include= arguments are allowed.

This argument accepts regular expression (regex) pattern matching operators, also known as wildcards.

```
--include-file=filename
```

Specifies the full path of a text *filename* that contains inclusion entries.

Each inclusion entry must conform to allowable --include syntax and be on a single line.

--all, --include or --include-file are mutually exclusive. One of those arguments must be supplied with each command.

--name=*String*

Specifies which dataset to modify. This argument is required.

Use mccli dataset show to return a list of valid dataset names.

If you supply a fully qualified dataset name (for example, /MyDomain/MyDataset), then the --domain argument is ignored.

```
--plugin=Integer
```

Specifies which plug-in ID gets the new inclusion entry. This argument is required Use mccli plugin show to return a list of valid numeric plug-in IDs.

Event codes

22220	Dataset modified.
22288	Dataset does not exist.
23009	Invalid plugin specified on the CLI.
23022	Error parsing input file.
23023	Input file could not be found.

dataset delete-option

The mccli dataset delete-option command permanently deletes a plug-in command (option) from a dataset

Syntax

```
mccli dataset delete-option --name=String
{--option=String [--option=String] ...}
{--value=String [--value=String] ...}
--plugin=Integer [--domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the dataset specified by --name.

```
--name=String
```

Specifies which dataset to modify. This argument is required.

Use mccli dataset show to return a list of valid dataset names.

If you supply a fully qualified dataset name (for example, /MyDomain/MyDataset), then the --domain argument is ignored.

```
--option=String
--value=String
```

Specifies the plug-in command (option) name to delete from the dataset. This argument is required.

Multiple --option/--value pairs are allowed.

Each client guide describes the valid plug-in commands for a specific dataset.

```
--plugin=Integer
```

Specifies which plug-in ID gets the new plug-in command (option). This argument is required

Use mccli plugin show to return a list of valid numeric plug-in IDs.

```
--value=String
```

Specifies a value for --option=. This argument is required.

Multiple --option/--value pairs are allowed.

Each client guide describes the valid plug-in commands for a specific dataset.

Event codes

22220 Dataset modified.

22288	Dataset does not exist.
-------	-------------------------

23009 Invalid plugin specified on the CLI.

dataset delete-target

The mccli dataset delete-target command permanently deletes a target file or folder from an existing dataset.

Syntax

```
mccli dataset delete-target --name=String --plugin=Integer
{--target=String | --target-file=String} [--domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the dataset specified by --name.

--name=String

Specifies which dataset to modify. This argument is required.

Use mccli dataset show to return a list of valid dataset names.

If you supply a fully qualified dataset name (for example, /MyDomain/MyDataset), then the --domain argument is ignored.

--plugin=*Integer*

Specifies which plug-in ID gets the new target file or folder entry. This argument is required

Use mccli plugin show to return a list of valid numeric plug-in IDs.

--target=String

Specifies an existing target file or folder to delete from the dataset. This argument is required.

You must supply either -- target or -- target-file.

Multiple -- target arguments are allowed.

This argument accepts regular expression (regex) pattern matching operators, also known as wildcards.

--target-file=filename

Specifies the full path of a text *filename* that contains target entries.

Each target entry must conform to allowable ——target syntax and be on a single line.

You must supply either -- target or -- target-file.

Event codes

22220	Dataset modified.
22288	Dataset does not exist.
23009	Invalid plugin specified on the CLI.
23022	Error parsing input file.
23023	Input file could not be found.

dataset edit-option

The mccli dataset edit-option command modifies existing dataset options.

Syntax

```
mccli dataset edit-option --name=String
{--option=String [--option=String] ...}
{--value=String [--value=String] ...}
--plugin=Integer [--domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the dataset specified by --name.

```
--name=String
```

Specifies which dataset to modify. This argument is required.

Use mccli dataset show to return a list of valid dataset names.

If you supply a fully qualified dataset name (for example, /MyDomain/MyDataset), then the --domain argument is ignored.

```
--option=String
```

```
--value=String
```

Specifies which plug-in command (option) name to modify. This argument is required.

Multiple --option/--value pairs are allowed.

Each client guide describes the valid plug-in commands for a specific dataset.

```
--plugin=Integer
```

Specifies the plug-in ID. This argument is required

Use mccli plugin show to return a list of valid numeric plug-in IDs.

```
--value=String
```

Specifies a value for --option=. This argument is required.

Multiple --option/--value pairs are allowed.

Each client guide describes the valid plug-in commands for a specific dataset.

Event codes

22220	Dataset modified.
22288	Dataset does not exist.
23009	Invalid plugin specified on the CLI.

Notes

Plug-in commands and values, specified by the --option and --value arguments, must occur in equal numbers. Furthermore, the option-value pairing is positional. In other words, the first occurrence of --option is assigned the value specified by the first occurrence of --value, the second occurrence of --option is assigned the value specified by the second occurrence of --value, and so forth.

dataset replace

The mccli dataset replace command replaces all exclusion and inclusion entries for a dataset with the entries that you supply on the command line.

Syntax

```
mccli dataset add-exclude --name=String --plugin=Integer
[{--exclude=String | --exclude-file=String}]
[{--include=String | --include-file=String}]
[--domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the dataset specified by --name.

```
--exclude=String
```

Specifies folders or files to exclude from the dataset.

You must supply either --exclude or --exclude-file.

```
Multiple --exclude= arguments are allowed.
```

This argument accepts regular expression (regex) pattern matching operators, also known as wildcards.

```
--exclude-file=filename
```

Specifies the full path of a text *filename* that contains exclusion entries.

Each exclusion entry must conform to allowable --exclude= syntax and be on a single line.

You must supply either --exclude or --exclude-file.

```
--include=String
```

Specifies the folders or files to add back to the dataset after an exclusion entry has excluded them.

You must supply either --include or --include-file.

Multiple --include arguments are allowed.

This argument accepts regular expression (regex) pattern matching operators, also known as wildcards.

```
--include-file=filename
```

Specifies the full path of a text *filename* that contains inclusion entries.

Each inclusion entry must conform to allowable --include syntax and be on a single line.

You must supply either --include or --include-file.

```
--name=String
```

Specifies which dataset to modify. This argument is required.

Use mccli dataset show to return a list of valid dataset names.

If you supply a fully qualified dataset name (for example, /MyDomain/MyDataset), then the --domain argument is ignored.

```
--plugin=Integer
```

Specifies which plug-in ID gets the new entries. This argument is required Use mccli plugin show to return a list of valid numeric plug-in IDs.

Event codes

22220	Dataset modified.
22288	Dataset does not exist.
23009	Invalid plugin specified on the CLI.
23022	Error parsing input file.
23023	Input file could not be found.

dataset show

The mccli dataset show command lists all datasets with summary information, or detailed information for a specific dataset.

Syntax

```
mccli dataset show [--domain=String(/)] [--name=String]
[--recursive=Boolean(false)] [--verbose=Boolean(false)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the dataset specified by --name.

```
--name=String
```

Specifies a dataset name. If not supplied, all datasets are listed with summary information.

Use mccli dataset show to return a list of valid dataset names.

If you supply a fully qualified dataset name (for example, /MyDomain/MyDataset), then the --domain argument is ignored.

```
--recursive=Boolean(false)
```

If true, then the command shows all datasets in the domain and any subdomains specified by the --domain argument.

If false or not supplied, then the command only shows datasets in the specified domain. Subdomains are not examined.

```
--verbose=Boolean(false)
```

If true, then detailed dataset information is returned.

If false or not supplied, then only dataset names are returned.

If you also supply --name, then detailed information for that dataset is returned.

Event codes

22288	Dataset does not exist.
22542	Domain does not exist.

Examples

This command returns a simple list of all datasets currently in use:

mccli dataset show

```
0,23000,CLI command completed successfully.

command completed successfully

Dataset Domain
-----
Unix Dataset /
Windows Dataset /
Default Dataset /
Base Dataset /
```

This command returns detailed information for all datasets currently in use:

mccli dataset show --verbose=true

This command:

This command returns detailed information for a single dataset:

```
0,23000,CLI command completed successfully.
command completed successfully
Attribute
                                     Value
                                     Unix Dataset
Name
ID
                                     UNIX:SNAPID
Domain
ReadOnly
                                    false
ALLDATA
                                     true
Num Targets
Linux File System Target
                                    ALL
Linux File System Target ID 1001
Solaris File System Target ALL
Solaris File System Target ID 2001
HP-UX File System Target ALL HP-UX File System Target ID 4001
AIX File System Target ALL AIX File System Target ID 5001
Num Includes
                                     0
                                     12
Num Excludes
Linux File System Exclude /tmp
Linux File System Exclude /var/tmp
Linux File System Exclude /usr/tmp
Linux File System Exclude core
Linux File System Exclude *cache.da
Linux File System Exclude *scan.dat
                                    *cache.dat
Solaris File System Exclude /tmp
Solaris File System Exclude /var/tmp
Solaris File System Exclude /usr/tmp
Solaris File System Exclude
Solaris File System Exclude
                                     core
                                     *cache.dat
Solaris File System Exclude *scan.dat
Num Options
Is Link
                                     false
```

dd

The mccli dd resource is used to manage Data Domain systems for use as Avamar backup targets.

dd add

The mccli dd add command adds a new Data Domain system to an Avamar server.

Syntax

```
mccli dd add --name=String --max-streams=Integer
--user-name=String --password=String --password-confirm=String
[--default-storage=Boolean(false)] [--force]
[--rw-community=String] [--snmp-port=Integer(161)]
[--trap-port=Integer(163)]
```

Options

```
--default-storage=Boolean(false)
```

If true and the Data Domain system is a replication target, then use this Data Domain system as the default storage for data that replicates from the source Data Domain system.

```
--force
```

If another Data Domain system is currently designated as default storage on the Avamar server, and you want this Data Domain system to be the new default storage, you must supply --force with --default-storage to override the current default storage setting (that is, force the change to occur).

```
--max-streams=Integer
```

Specifies the maximum number of Data Domain system streams that Avamar uses for backups, restores, and replication. This argument is required.

```
--name=String
```

Specifies the fully qualified Data Domain system name or IP address. This argument is required.

```
--rw-community=String
```

Specifies the SNMP community for Avamar to have read/write access to the Data Domain system.

```
--snmp-port=Integer(161)
```

Specifies the data port number on the Data Domain system from which to receive and on which to set SNMP objects.

```
--trap-port=Integer(163)
```

Specifies the data port number on the Avamar server to which SNMP trap messages are sent.

```
--user-name=String
--password-confirm=String
```

Specifies the username and password of the Data Domain OST account that Avamar will use to access the Data Domain system for backups, restores, and replication. These arguments are required.

Event codes

- 30934 Added Data Domain system.
- 30937 Failed to add Data Domain system.
- 30940 Data Domain system already exists.
- 30941 Failed to connect to Data Domain system.
- 30942 Unsupported DDOS version.
- 30948 The minimum number of allowed streams was exceeded.
- 30949 The maximum number of allowed streams was exceeded.
- 30953 Added Data Domain system but unable to retrieve the Data Domain system ssh key file.
- 30958 The DDBoost user is not set.
- 30959 The OST is disabled.
- 30960 DDBoost user is disabled.
- 30961 Failed to authenticate with ssh key file.
- 30962 Unable to add ssh public key for user.
- 30963 User does not exist.
- 30964 User is disabled.
- 30965 The user is not an admin user.
- 31004 Data Domain system added but the hostname may not be valid.

dd delete

The mccli dd delete command deletes a Data Domain system from an Avamar server.

Syntax

mccli dd delete --name=String [--force=Boolean(false)]

Options

--name=*String*

Specifies which Data Domain system to delete. This argument is required.

--force=Boolean(false)

If true, then forces deletion of the Data Domain system even if the system cannot be reached, has backups or checkpoints, or is the default replication storage system.

Event codes

30936	Deleted Data Domain system.
30939	Failed to delete Data Domain system.
30941	Failed to connect to Data Domain system.
30943	Data Domain system does not exist.

dd edit

The mccli dd edit command enables you to edit the Data Domain system configuration.

Syntax

```
mccli dd edit --name=String
[--default-storage=Boolean(false)] [--force] [--max-streams=Integer]
[--new-name=String] [--rw-community=String]
[--snmp-port=Integer(161)] [--trap-port=Integer(163)]
[--user-name=String --password=String --password-confirm=String]
```

Options

```
--default-storage=Boolean(false)
```

If true and the Data Domain system is a replication target, then use this Data Domain system as the default storage for data that replicates from the source Data Domain system.

```
--force
```

If another Data Domain system is currently designated as default storage on the Avamar server, and you want this Data Domain system to be the new default storage, you must supply --force with --default-storage to override the current default storage setting (that is, force the change to occur).

```
--max-streams=Integer
```

Specifies the maximum number of Data Domain system streams that Avamar uses for backups, restores, and replication.

```
--name=String
```

Specifies the fully qualified Data Domain system name or IP address. This argument is required.

```
--new-name=String
```

Specifies a new fully qualified Data Domain system name.

```
--rw-community=String
```

Specifies the SNMP community for Avamar to have read/write access to the Data Domain system.

```
--snmp-port=Integer(161)
```

Specifies the data port number on the Data Domain system from which to receive and on which to set SNMP objects.

```
--trap-port=Integer(163)
```

Specifies the data port number on the Avamar server to which SNMP trap messages are sent.

```
--user-name=String
--password=String
```

```
--password-confirm=String
```

Specifies the username and password of the Data Domain OST account that Avamar will use to access the Data Domain system for backups, restores, and replication.

Event codes

30935 Updated Data Domain system in persistent store.

- 30938 Failed to update Data Domain system in persistent store.
- 30941 Failed to connect to Data Domain system.
- 30943 Data Domain system does not exist.
- 30948 The minimum number of allowed streams was exceeded.
- 30949 The maximum number of allowed streams was exceeded.
- 30953 Added Data Domain system but unable to retrieve the Data Domain system ssh key file.
- 30958 The DDBoost user is not set.
- 30959 The OST is disabled.
- 30960 DDBoost user is disabled.
- 30961 Failed to authenticate with ssh key file.
- 30962 Unable to add ssh public key for user.
- 30963 User does not exist.
- 30964 User is disabled.
- 30965 The user is not an admin user.
- 31005 Data Domain system added but the hostname may not be valid.

dd show-prop

The mccli dd show-prop command shows Data Domain system properties.

Syntax

```
mccli dd show-prop [--name=String]
```

Options

--name=*String*

Specifies the fully qualified Data Domain system name or IP address.

If supplied, system properties are returned for that Data Domain system.

If not supplied, a summary report of properties for all known Data Domain systems is returned.

Event codes

30943 Data Domain system does not exist.

Examples

This command returns system properties for a single Data Domain system (datadomain1.example.com):

mccli dd show-prop --name=datadomain1.example.com

```
0,23000,CLI command completed successfully.

Attribute Value

IPv4 Hostname datadomain1.example.com

IPv6 Hostname N/A

Total Capacity (post-comp size) 7623.8 GiB

Server Utilization (post-comp use%) 6%
```

```
Bytes Protected
                                                0 bytes
                                                7189.0 GiB
File System Available (post-comp avail)
File System Used (post-comp used)
                                                434.8 GiB
User Name
                                                customer1
Default Replication Storage System
                                               Yes
Target For Avamar Checkpoint Backups
Maximum Streams For Avamar Checkpoint Backups 0
Maximum Streams
Maximum Streams Limit
                                                90
Instant Access Limit
DDOS Version
                                                5.5.0.4-430231
Serial Number
                                                3FA0924231
Model Number
                                               DD670
Encryption Strength
                                               none
Authentication Mode
                                               none
                                               The Avamar server's time is ahead of DD's.
Monitoring Status
DDBoost Licensed
                                               true
DDBoost Enabled
                                               true
DDBoost User Enabled
                                                true
DDBoost User Status
                                               User Valid
DDBoost Option Status
                                               Option Enabled
SNMP status
                                               Enabled
File System Status
                                               File System Running
Synchronization of maintenance operations
```

This command returns system properties for all Data Domain systems known to this MCS in XML format:

mccli dd show-prop --xml

```
Listening for transport dt socket at address: 8003
<CLIOutput>
 <Results>
  <ReturnCode>0</ReturnCode>
  <EventCode>23000</EventCode>
 <EventSummary>CLI command completed successfully.</EventSummary>
 </Results>
 <Data>
  <Row>
   <IPv4Hostname>10.110.215.208</IPv4Hostname>
   <IPv6Hostname>N/A</IPv6Hostname>
   <TotalCapacity>7623.8 GiB</TotalCapacity>
   <ServerUtilization>6%</ServerUtilization>
   <BytesProtected>0 bytes/BytesProtected>
   <FileSystemAvailable>7189.0 GiB</FileSystemAvailable>
   <FileSystemUsed>434.8 GiB</FileSystemUsed>
   <UserName>ost</UserName>
   <DefaultReplicationStorageSystem>Yes</DefaultReplicationStorageSystem>
   <TargetForAvamarCheckpointBackups>No</TargetForAvamarCheckpointBackups>
   <MaximumStreamsForAvamarCheckpointBackups>0</MaximumStreamsForAvamarCheckpointBackups>
   <MaximumStreams>5</MaximumStreams>
   <MaximumStreamsLimit>90</MaximumStreamsLimit>
   <InstantAccessLimit>1</InstantAccessLimit>
   <DDOSVersion>5.5.0.4-430231/DDOSVersion>
   <SerialNumber>3FA0924231/SerialNumber>
   <ModelNumber>DD670</ModelNumber>
   <EncryptionStrength>none</EncryptionStrength>
   <AuthenticationMode>none</AuthenticationMode>
   <MonitoringStatus>The Avamar server&apos;s time is ahead of DD&apos;s.</MonitoringStatus>
   <DDBoostLicensed>true/DDBoostLicensed>
   <DDBoostEnabled>true</DDBoostEnabled>
   <DDBoostUserEnabled>true</DDBoostUserEnabled>
   <DDBoostUserStatus>User Valid/DDBoostUserStatus>
   <DDBoostOptionStatus>Option Enabled/DDBoostOptionStatus>
   <SNMPstatus>Enabled</SNMPstatus>
   <FileSystemStatus>File System Running</FileSystemStatus>
   <Synchronizationofmaintenanceoperations>on/Synchronizationofmaintenanceoperations>
  </Row>
  <Row>
   <IPv4Hostname>10.31.228.154</IPv4Hostname>
```

```
<IPv6Hostname>N/A</IPv6Hostname>
  <TotalCapacity>404.8 GiB</TotalCapacity>
  <ServerUtilization>0%</ServerUtilization>
  <BytesProtected>0 bytes/BytesProtected>
  <FileSystemAvailable>403.0 GiB</FileSystemAvailable>
  <FileSystemUsed>1.7 GiB</FileSystemUsed>
  <UserName>ost</UserName>
  <DefaultReplicationStorageSystem>No</DefaultReplicationStorageSystem>
  <TargetForAvamarCheckpointBackups>No</TargetForAvamarCheckpointBackups>
  <MaximumStreamsForAvamarCheckpointBackups>0</MaximumStreamsForAvamarCheckpointBackups>
  <MaximumStreams>5</MaximumStreams>
  <MaximumStreamsLimit>16</MaximumStreamsLimit>
  <InstantAccessLimit>1</InstantAccessLimit>
  <DDOSVersion>5.5.0.4-430231/DDOSVersion>
  <SerialNumber>AUDVN985S7AG2T
  <ModelNumber>DDVE</ModelNumber>
  <EncryptionStrength>none</EncryptionStrength>
  <AuthenticationMode>none/AuthenticationMode>
  <MonitoringStatus>The Avamar server&apos;s time is ahead of DD&apos;s.</monitoringStatus>
  <DDBoostLicensed>true
  <DDBoostEnabled>true/DDBoostEnabled>
  <DDBoostUserEnabled>true</DDBoostUserEnabled>
  <DDBoostUserStatus>User Valid/DDBoostUserStatus>
  <DDBoostOptionStatus>Option Enabled/DDBoostOptionStatus>
  <SNMPstatus>Enabled</SNMPstatus>
  <FileSystemStatus>File System Running</FileSystemStatus>
  <Synchronizationofmaintenanceoperations>on/Synchronizationofmaintenanceoperations>
 </Row>
</Data>
</CLIOutput>
```

dd show-util

The mccli dd show-util command shows Data Domain system utilization statistics.

Syntax

```
mccli dd show-util [--name=String]
```

Options

```
--name=String
```

Specifies the fully qualified Data Domain system name or IP address.

If supplied, utilization statistics are returned for that Data Domain system.

If not supplied, utilization statistics for all known Data Domain systems is returned.

Event codes

30943 Data Domain system does not exist.

domain

The mccli domain resource is used to manage Avamar server server domains and subdomains.

domain add

The mccli domain add command creates a new domain or subdomain on the Avamar server.

Syntax

```
mccli domain add --name=String
[--contact=String] [--domain=String(/)]
[--email=String] [--location=String]
[--phone=String]
```

Options

```
--contact=String
```

Specifies responsible party contact information.

```
--domain=String(/)
```

Specifies the parent domain for the new domain.

```
--email=String
```

Specifies responsible party email address.

```
--location=String
```

Specifies location information.

```
--name=String
```

Specifies the name of the new domain. This argument is required.

```
--phone=String
```

Specifies responsible party telephone number.

Event codes

22526	Failed folder add.
22527	Domain added.
22540	Invalid name character.
22541	Domain already exists.
22558	A domain or client with this name already exists.

domain delete

The mccli domain delete command permanently deletes a domain from the Avamar server. Deleting a domain deletes the domain and all subdomains, clients, and backups stored in that domain.

Syntax

```
mccli domain delete --name=String [--domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the parent domain for the new domain.

```
--name=String
```

Specifies which domain to delete. This argument is required.

Use mccli domain show to return a list of valid domain names.

If you supply a fully qualified domain name (for example, /domain/subdomain), then the --domain argument is ignored.

Event codes

22507	Failed domain deletion.
22513	Domain removed.
22542	Domain does not exist.
22543	Domain has groups.
22544	Domain has datasets.
22545	Domain has event profiles.
22627	Domain has schedules.
22628	Domain has retentions.

domain edit

The mccli domain edit command edits the properties for a domain.

Syntax

```
mccli domain edit --name=String
[--contact=String] [--domain=String(/)]
[--email=String] [--location=String]
[--phone=String]
```

Options

```
--contact=String
```

Specifies responsible party contact information.

```
--domain=String(/)
```

Specifies the parent domain.

```
--email=String
```

Specifies responsible party email address.

```
--location=String
```

Specifies location information.

```
--name=String
```

Specifies which domain to edit. This argument is required.

```
--phone=String
```

Specifies responsible party telephone number.

Event codes

22519	Domain modified.
22542	Domain does not exist.

domain show

The mccli domain show command displays properties for a domain.

Syntax

```
mccli domain show --name=String [--domain=String(/)]
[--recursive=Boolean(false)]
```

Options

```
--domain=String(/)
```

Specifies the parent domain under which domains and subdomains are listed.

--name=String

Specifies the name of the domain for which to show information. This argument is required.

Use mccli domain show to return a list of valid domain names.

If you supply a fully qualified domain name (for example, /domain/subdomain), then the --domain argument is ignored.

--recursive=Boolean(false)

If true, then the command examines all domains in the domain and any subdomains.

If false or not supplied, then the command only examines the domain. Subdomains are not examined.

Event codes

22542 Domain does not exist.

dump

The mccli dump resource dumps various DPNProxyService caches for troubleshooting purposes.

Note

The mccli dump resource is strictly reserved for EMC internal use only.

dump clientcache

The mccli dump clientcache command is used to dump the DPNProxyService client cache for troubleshooting purposes.

Note

The mccli dump clientcache command is strictly reserved for EMC internal use only.

Syntax

mccli dump clientcache

dump domaincache

The mccli dump domaincache command is used to dump the DPNProxyService domain cache for troubleshooting purposes.

Note

The mccli dump domaincache command is strictly reserved for EMC internal use only.

Syntax

mccli dump domaincache

dump jobcache

The mccli dump jobcache command is used to dump the DPNProxyService client job cache for troubleshooting purposes.

Note

The mccli dump jobcache command is strictly reserved for EMC internal use only.

Syntax

mccli dump jobcache

event

The \mbox{mccli} event resource is used to access and manage event codes on the Avamar server.

event ack

The mccli event ack command acknowledges events.

Syntax

```
mccli event ack {--all=Boolean(false)
| [--after=String] | [--before=String]
| [--category={APPLICATION | SECURITY | SYSTEM | USER}]
```

```
| [--domain=String(/)] | {[--exclude=String] | [--include=String]}
| [--id=Integer] | [--range=String]
| [--severity={NODE | NODE FATAL | OK | PROCESS
| PROCESS_FATAL | SYSTEM_FATAL | USER | USER_FATAL}]
| [--source={avamar | dd}]
| [--type={AUDIT | DEBUG | ERROR | INFORMATION | INTERNAL | WARNING}]}
```

Options

--after=String

Acknowledges events after the specified date, which must be in the format of *YYYY-MM-DD HH:mm:ss*. The date value can be truncated as needed.

--all=*Boolean(false)*

If true, then all events are acknowledged.

--before=String

Acknowledges events before the specified date, which must be in the format of *YYYY-MM-DD HH:mm:ss*. The date value can be truncated as needed.

--category={APPLICATION | SECURITY | SYSTEM | USER}

Acknowledges events of this category.

--domain=String(/)

Acknowledges events of this Avamar server domain.

--exclude=String

Specifies a comma-separated list of event codes to exclude from acknowledgment. The comma-separated list cannot contain spaces.

The --exclude and --include options are mutually exclusive.

--id=*Integer*

Acknowledges this single event.

--include=String

Specifies a comma-separated list of event codes to include for acknowledgment. The comma-separated list cannot contain spaces.

The --exclude and --include options are mutually exclusive.

--range=String

Acknowledges events of this range of events. *String* must be in the format of *ID-1:ID-2*, where *ID-1* and *ID-2* are the lower and upper limits of the range, respectively.

```
--severity={NODE|NODE_FATAL|OK|PROCESS|PROCESS_FATAL|SYSTEM_FATAL|USER|USER_FATAL}
```

Acknowledges events of this severity.

--source={avamar | dd}

If avamar is specified, then the command acknowledges events for the Avamar server.

Ifdd is specified, then the command acknowledges events for all configured Data Domain systems.

--type={AUDIT | DEBUG | ERROR | INFORMATION | INTERNAL | WARNING} Acknowledges events of this type.

Event codes

23022

Event id does not exist.

Notes

This command requires either the --all option, or some other filtering criteria.

The --exclude and --include options are mutually exclusive.

Output is a count of the events acknowledged.

Examples

This command acknowledges event code 148710:

```
mccli event ack --id=148710
```

```
0,23000,CLI command completed successfully.
Attribute Value
-----events-acked 1
```

event clear-data-integrity-alerts

The mccli event clear-data-integrity-alerts command clears all data integrity alerts for this server.

This command requires a reset code, which must be obtained from EMC Technical Support.

Syntax

```
mccli event clear-data-integrity-alerts --reset-code=String
```

Options

```
--reset-code=String
```

Reset code provided by EMC Technical Support. This argument is required.

Event codes

A data integrity alerts reset code was accepted.A data integrity alerts reset code was rejected.

event get-info

The mccli event get-info command returns detailed information for a specific event code.

Syntax

```
mccli event get-info --code=Integer
[--description=Boolean(false)] [--remedy=Boolean(false)]
[--summary=Boolean(true)]
```

Options

```
--code=Integer
```

Specifies the event code number. This argument is required.

```
--description=Boolean(false)
```

If true, then other properties are also returned, including the remedy and summary properties.

If false or not supplied, then only the numeric code is returned.

```
--remedy=Boolean(false)
```

If true, then event remedy information is returned.

If false or not supplied, then event remedy information is not returned.

```
--summary=Boolean(true)
```

If true or not supplied, then event summary information is returned.

If false, then event summary information is not returned.

event show

The mccli event show command returns event occurrence details.

Syntax

```
mccli event show
[--after=String] [--before=String]
[--category={APPLICATION | SECURITY | SYSTEM | USER}]
[--domain=String(/)] [--exclude=String]
[--id=Integer] [--include=String]
[--severity={NODE | NODE FATAL | OK | PROCESS
| PROCESS_FATAL | SYSTEM_FATAL | USER | USER_FATAL}]
[--source={avamar | dd}]
[--type={AUDIT | DEBUG | ERROR | INFORMATION | INTERNAL | WARNING}]}]
[--unack=Boolean(false)]
```

Options

```
--after=String
```

Shows events after the specified date, which must be in the format of *YYYY-MM-DD HH:mm:ss*. The date value can be truncated as needed.

```
--before=String
```

Shows events before the specified date, which must be in the format of *YYYY-MM-DD HH:mm:ss*. The date value can be truncated as needed.

```
--category={APPLICATION | SECURITY | SYSTEM | USER}
```

Shows events of this category.

```
--domain=String(/)
```

Shows events in this Avamar server domain.

```
--exclude=String
```

Specifies a comma-separated list of event codes to exclude from the command output. The comma-separated list cannot contain spaces.

The --exclude and --include options are mutually exclusive.

```
--id=Integer
```

Shows information for this single event ID.

```
--include=String
```

Specifies a comma-separated list of event codes to include in the command output. The comma-separated list cannot contain spaces.

The --exclude and --include options are mutually exclusive.

```
--severity={NODE | NODE_FATAL | OK | PROCESS | PROCESS_FATAL | SYSTEM FATAL | USER | USER FATAL}
```

Shows events with this severity.

```
--source={avamar | dd}
```

If avamar is specified, then the command shows events for the Avamar server.

Ifdd is specified, then the command shows events for all configured Data Domain systems.

```
--type={AUDIT | DEBUG | ERROR | INFORMATION | INTERNAL | WARNING} Shows events of this type.
```

You can supply more than one --type option on a single command line.

```
--unack=Boolean(false)
```

If true, then only unacknowledged events are returned.

Event codes

23022 Event id does not exist.

Notes

If multiple events are displayed, sorting is by date in descending order.

The --exclude and --include options are mutually exclusive.

Examples

This command returns detailed information for event code 149897:

mccli event show --id=149897

```
0,23000,CLI command completed successfully.
command completed successfully
Attribute Value
             149897
TD
Date
            2014-04-19 14:19:45 PDT
            INFORMATION
Type
             578
Code
Category
             SYSTEM
Severity
             OK
Domain
             hfscheckresults::merge, in checkpoint cp.20130419140741,
Summary
             this ((start 1176995040, nodestart 1176995040, nodefinish
             0, valid false, totalerrors 0)) tried to merge with
             ((start 0, nodestart 0, nodefinish 0, valid false,
             totalerrors 0)) but the uniquestarttime fields differ
SW Source
             DPN: Unknown
For Whom
             N/A
HW Source
             node-10-0-54-249.example.com
Description N/A
             N/A
Remedy
Notes
             N/A
             <data><entry key="code" type="text" value="0578"</pre>
Data
             version=""/><entry key="type" type="text" value="INFO"</pre>
             version=""/><entry key="time" type="text"
value="21:19:45.93935" version=""/><entry key="message"</pre>
             type="text" value="hfscheckresults::merge, in checkpoint
             cp.20130419140741, this ((start 1176995040, nodestart
             1176995040, nodefinish 0, valid false, totalerrors 0))
             tried to merge with ((start 0, nodestart 0, nodefinish 0, valid false, totalerrors 0)) but the uniquestart time \frac{1}{2}
             fields differ" version=""/><entry key="date" type="text"
             value="2014/04/19" version=""/><entry key="thread"</pre>
```

```
type="text" value="srvm-14070642#srv:265"
version=""/></data>
```

group

The mccli group resource is used to manage groups and group policy.

group add

The mccli group add command creates a new group.

Syntax

```
mccli group add --name=String
--dataset=String(Default Dataset) --enabled=Boolean(false)
--retention=(Default Retention) --schedule=(Default Schedule)
[--dataset-domain=String(/)] [--domain=String(/)]
[--encryption={High | Medium | None}]
[--retention-domain=String(/)] [--schedule-domain=String(/)]
```

Options

```
--dataset-domain=String(/)
```

Specifies the Avamar server domain that contains the dataset specified by the -- dataset argument.

--dataset=String(Default Dataset)

Specifies the dataset to assign to the group. This argument is required.

Use mccli dataset show to return a list of valid dataset names.

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the group specified by --name.

```
--enabled=Boolean(false)
```

If true, then the group is eligible to immediately participate in scheduled backup activities. This argument is required .

```
--encryption={High | Medium | None}
```

Specifies the group default encryption method.

Note

The exact encryption technology and bit strength used for any given client/server connection depends on a number of factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides additional information.

```
--name=String
```

Specifies the new group name. This argument is required.

If you supply a fully qualified group name (for example, /MyDomain/MyGroup), then the --domain argument is ignored.

```
--retention-domain=String(/)
```

Specifies the Avamar server domain that contains the retention policy specified by the --retention argument.

```
--retention=(Default Retention)
```

Specifies the retention policy to assign to the group. This argument is required.

Use mccli retention show to return a list of valid retention policy names.

```
--schedule-domain=String(/)
```

Specifies the Avamar server domain that contains the schedule specified by the -- schedule argument.

--schedule=(Default Schedule)

Specifies the schedule to assign to the group. This argument is required.

Use mccli schedule show to return a list of valid schedule names.

Event codes

- 22207 New group created.
- 22233 Group already exists.
- 22235 Group add failed.
- 23003 Invalid dataset name specified on the CLI.
- 23004 Invalid schedule name specified on the CLI.
- 23005 Invalid retention policy name specified on the CLI.
- 23012 Invalid encryption method specified on the CLI.
- 31002 Group add or update failed due to a policy hierarchical management violation.

group add-client

The mccli group add-client command adds a client to a group.

Syntax

```
mccli group add-client --client-name=String --name=String
[--client-domain=String(/)] [--dataset-domain=String(/)]
[--dataset=String] [--domain=String(/)]
```

Options

```
--client-domain=String(/)
```

Specifies the Avamar server domain that contains the client specified by --client-name.

```
--client-name=String
```

Specifies which client to add to the group. This argument is required.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified dataset name (for example, /clients/MyClient), then the --client-domain argument is ignored.

```
--dataset-domain=String(/)
```

Specifies the Avamar server domain that contains the dataset specified by the -- dataset argument.

```
--dataset=String
```

Specifies an alternative dataset this client will use when this group default dataset is overridden.

Use mccli dataset show to return a list of valid dataset names.

--domain=String(/)

Specifies the Avamar server domain that contains the group specified by --name.

--name=String

Specifies which group to modify. This argument is required.

Use mccli group show to return a list of valid group names.

If you supply a fully qualified group name (for example, /MyDomain/MyGroup), then the --domain argument is ignored.

Event codes

22234	Group does not exist.
22236	Client does not exist.
22242	Client is already a member of this group.
22243	Client group membership successfully updated.
22269	Unable to add a client to a group.
22358	Unable to add a client to group due to incompatibility.

group add-proxy

The mccli group add-proxy command adds the specified Avamar proxy to the specified group.

Syntax

```
mccli group add-proxy --name=String --proxy-name=String
[--domain=String(/)] [--proxy-domain=String(/)]
```

Options

--domain=String(/)

Specifies the Avamar server domain that contains the group specified by --name.

--name=*String*

Specifies which group to modify. This argument is required.

Use mccli group show to return a list of valid group names.

If you supply a fully qualified group name (for example, /MyDomain/MyGroup), then the --domain argument is ignored.

--proxy-domain=String(/)

Specifies the Avamar server domain that contains the proxy specified by --proxy-name.

--proxy-name=*String*

Specifies which proxy to add to the group. This argument is required.

Use mccli client show to return a list of valid proxy names.

If you supply a fully qualified proxy name (for example, /clients/MyProxy), then the --proxy-domain argument is ignored.

Event codes

22234	Group does not exist.
22236	Client does not exist.
24001	Failed to update proxy client mappings of a group.
24002	Proxy client mappings of a group successfully updated.

Examples

This command adds proxy backupproxy225 to the Test1 group:

```
mccli group add-proxy --domain=/vcenter-1.example.com --name=Test1
--proxy-domain=/clients --proxy-name=backupproxy225
```

```
0,24002,Proxy client mappings of a group successfully updated.
Attribute Value
------
group /vcenter-1.example.com/Test1
```

group backup

The mccli group backup command initiates an on-demand group backup.

Syntax

```
mccli group backup --name=String [--domain=String(/)] [--wait[=min]]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the group specified by --name.

```
--name=String
```

Specifies which group to back up. This argument is required.

Use mccli group show to return a list of valid group names.

If you supply a fully qualified group name (for example, /MyDomain/MyGroup), then the --domain argument is ignored.

```
--wait[=min]
```

Specifies a time period in minutes (min) that this command waits for the initiated operation to complete. If the operation completes before then, status is shown sooner. This option also shows more detailed status. If --wait=0 or --wait (no value) is supplied, the command waits indefinitely for the activity to complete.

Event codes

- 22226 Group disabled.
- 22227 Group does not contain any clients.
- 22228 A client was not backed up because it is disabled, retired or one or more of its plug-ins has backups disabled.
- 22234 Group does not exist.
- 22301 Scheduled group backups initiated for all clients.
- 22311 Scheduled group backups failed to start.

23028 Invalid group type.

group copy

The mccli group copy command copies an existing group, creating a new group. The new group inherits all the properties and settings of the original group except for client members. No clients are assigned to the new group.

Note

You must copy groups within the same domain. You cannot copy a group to another domain under any circumstances.

Syntax

```
mccli group copy --name=String --new-name=String
[--domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the group specified by --name.

```
--name=String
```

Specifies which group to copy. This argument is required.

Use mccli group show to return a list of valid group names.

If you supply a fully qualified group name (for example, /MyDomain/MyGroup), then the --domain argument is ignored.

```
--new-name=String
```

Specifies the name for the new group. This argument is required.

Event codes

22207	New group created.
22233	Group already exists.
22234	Group does not exist.
22235	Group add failed.
22540	Invalid name character.

group delete

The mccli group delete command permanently deletes a group from the Avamar server.

A client must always be a member of at least one group. Therefore, if the group that you are deleting contains any clients that are not also members of at least one other group, then you must move those clients to other groups using the mccli group move-client command before you delete the group.

Syntax

```
mccli group delete --name=String [--domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the group specified by --name.

```
--name=String
```

Specifies which group to delete. This argument is required.

Use mccli group show to return a list of valid group names.

If you supply a fully qualified group name (for example, /MyDomain/MyGroup), then the --domain argument is ignored.

Event codes

- 22209 Group successfully deleted.
- 22234 Group does not exist.
- 22247 Cannot delete the group because the client members are not present in other groups.

group edit

The mccli group edit command edits properties for a group.

There are no default settings for the mccli group edit command. If you enter the command but do not supply options and values on the command line, then no changes are made to the group.

Syntax

```
mccli group add [--dataset-domain=String(/)]
[--dataset=String(Default Dataset)] [--domain=String(/)]
[--enabled=Boolean(false)]
[--encryption={High | Medium | None}]
[--name=String] [--retention-domain=String(/)]
[--retention=(Default Retention)] [--schedule-domain=String(/)]
[--schedule=(Default Schedule)]
```

Options

```
--dataset-domain=String(/)
```

Specifies the Avamar server domain that contains the dataset specified by the -- dataset argument.

```
--dataset=String(Default Dataset)
```

Specifies the dataset to assign to the group. This argument is required.

Use mccli dataset show to return a list of valid dataset names.

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the group specified by --name.

```
--enabled=Boolean(false)
```

If true, then the group is eligible to immediately participate in scheduled backup activities. This argument is required .

```
--encryption={High | Medium | None}
```

Specifies the group default encryption method.

Note

The exact encryption technology and bit strength used for any given client/server connection depends on a number of factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides additional information.

--name=String

Specifies the group name. This argument is required.

If you supply a fully qualified group name (for example, /MyDomain/MyGroup), then the --domain argument is ignored.

--retention-domain=String(/)

Specifies the Avamar server domain that contains the retention policy specified by the --retention argument.

--retention=(Default Retention)

Specifies the retention policy to assign to the group. This argument is required.

Use mccli retention show to return a list of valid retention policy names.

--schedule-domain=String(/)

Specifies the Avamar server domain that contains the schedule specified by the -- schedule argument.

--schedule=(Default Schedule)

Specifies the schedule to assign to the group. This argument is required.

Use mccli schedule show to return a list of valid schedule names.

Event codes

- 22208 Group successfully modified.
- 22234 Group does not exist.
- 23003 Invalid dataset name specified on the CLI.
- 23004 Invalid schedule name specified on the CLI.
- 23005 Invalid retention policy name specified on the CLI.
- 23012 Invalid encryption method specified on the CLI.
- 31002 Group add or update failed due to a policy hierarchical management violation.

group export

The mccli group export command exports group settings (that is, name, domain, encryption method, and so forth), and assigned policy objects (dataset, schedule, and retention policy) to an XML file. However, exported groups exported do not contain a list of client members.

Syntax

```
mccli group export --name=String --file=String
[--domain=String(/)] [--force=Boolean(false)]
```

Options

--domain=String(/)

Specifies the Avamar server domain that contains the group specified by --name.

```
--file=String
```

Specifies the name of the export XML file to create. This argument is required.

```
--force=Boolean(false)
```

If true, then the option forces the overwrite of an existing XML file.

```
--name=String
```

Specifies which group to export. This argument is required.

Use mccli group show to return a list of valid group names.

If you supply a fully qualified group name (for example, /MyDomain/MyGroup), then the --domain argument is ignored.

Event codes

22234

Group does not exist.

group move-client

The mccli group move-client command moves a client from one group to another.

Syntax

```
mccli group move-client --client-name=String
--old-group-name=String --name=String
[--client-domain=String(/)] [--domain=String(/)]
[--old-group-domain=String(/)]
```

Options

```
--client-domain=String(/)
```

Specifies the Avamar server domain that contains the client specified by --client-name.

```
--client-name=String
```

Specifies which client to move. This argument is required.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --domain argument is ignored.

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the group specified by --name.

```
--name=String
```

Specifies the target group (that is, the group that receives the client following the move). This argument is required.

Use mccli group show to return a list of valid group names.

If you supply a fully qualified group name (for example, /MyDomain/MyGroup), then the --domain argument is ignored.

```
--old-group-domain=String(/)
```

Specifies the Avamar server domain that contains the group specified by --old-group-name.

--old-group-name=String

Specifies the source group (that is, the group which the client was a member of prior to the move). This argument is required.

Use mccli group show to return a list of valid group names.

If you supply a fully qualified group name (for example, /MyDomain/MyGroup), then the --domain argument is ignored.

Event codes

22234	Group does not exist.
22236	Client does not exist.
22241	Client is not a member of old group.
22242	Client is already a member of new group.
22243	Client group membership successfully updated.

group remove-client

The mccli group remove-client command removes a client from a group.

A client must always be a member of at least one group. Therefore, if the client belongs only to the group from which you want to remove it, then you must first add the client to another group using the mccli group add-client command.

Syntax

```
mccli group remove-client --client-name=String --name=String
[--client-domain=String(/)] [--domain=String(/)]
```

Options

```
--client-domain=String(/)
```

Specifies the Avamar server domain that contains the client specified by --client-name.

```
--client-name=String
```

Specifies which client to remove. This argument is required.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /clients/MyClient), then the --domain argument is ignored.

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the group specified by --name.

```
--name=String
```

Specifies the group from which to remove the client. This argument is required.

Use mccli group show to return a list of valid group names.

If you supply a fully qualified group name (for example, /MyDomain/MyGroup), then the --domain argument is ignored.

Event codes

22234	Group does not exist.
22236	Client does not exist.
22241	Client is not a member of old group.
22243	${\it Client group membership successfully updated.}$
22246	Client is not a member of any other group.
22270	Unable to remove a client from a group.

group remove-proxy

The mccli group remove-proxy command removes the specified Avamar proxy from the specified group.

Syntax

```
mccli group remove-proxy --name=String
--proxy-name=String [--domain=String(/)]
[--proxy-domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the group specified by --name.

```
--name=String
```

Specifies the group from which to remove the proxy. This argument is required.

Use mccli group show to return a list of valid group names.

If you supply a fully qualified group name (for example, /MyDomain/MyGroup), then the --domain argument is ignored.

```
--proxy-domain=String(/)
```

Specifies the Avamar server domain that contains the proxy specified by --proxy-name.

```
--proxy-name=String
```

Specifies which proxy to remove. This argument is required.

Use mccli client show to return a list of valid proxy names.

If you supply a fully qualified prpxy name (for example, /clients/MyProxy), then the --domain argument is ignored.

Event codes

22234	Group does not exist.
22236	Client does not exist.
24001	Failed to update proxy client mappings of a group.
24004	Proxy client mappings of a group successfully updated.

Examples

This command removes proxy backupproxy225 from the Test1 group:

mccli group remove-proxy --domain=/vcenter-1.example.com --name=Test1
--proxy-domain=/clients --proxy-name=backupproxy225

```
0,24002,Proxy client mappings of a group successfully updated.
Attribute Value
------
group /vcenter-1.example.com/Test1
```

group replicate

The mccli group replicate command replicates the specified group. It is equivalent to the Avamar Administrator Replicate Now command.

Syntax

```
mccli group replicate --name=String
[--domain=String(/)] [--wait[=min]]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the group specified by --name.

```
--name=String
```

Specifies which group to replicate. This argument is required.

Use mccli group show to return a list of valid group names.

If you supply a fully qualified group name (for example, /MyDomain/MyGroup), then the --domain argument is ignored.

```
--wait[=min]
```

Specifies a time period in minutes (min) that this command waits for the initiated operation to complete. If the operation completes before then, status is shown sooner. This option also shows more detailed status. If --wait=0 or --wait (no value) is supplied, the command waits indefinitely for the activity to complete.

Event codes

22226	Group disabled.
22234	Group does not exist.
22441	Scheduled client replicate (Success).
22801	Login failure.
23028	Invalid group type.
30930	Expired Retention (Expiration).
30978	No proxy for replication.

group show

The mccli group show command returns information for all groups.

Syntax

```
mccli group show [--clients=Boolean(false)]
[--domain=String(/)] [--name=String]
```

```
[--proxy-clients=Boolean(false)] [--recursive=Boolean(false)] [--verbose=Boolean(false)]
```

Options

--clients=Boolean(false)

If true, then all clients that belong to the group are listed.

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the group specified by --name.

```
--name=String
```

Specifies the group for which to show information. If not supplied, all groups in the domain are listed.

Use mccli group show to return a list of valid group names.

If you supply a fully qualified group name (for example, /MyDomain/MyGroup), then the --domain argument is ignored.

```
--proxy-clients=Boolean(false)
```

If true, then the command shows all proxies belonging to this group. This option is only valid fro vCenter groups.

```
--recursive=Boolean(false)
```

If true, then the command shows all groups in the domain and any subdomains specified by the --domain argument..

If false or not supplied, then the command only shows groups in the domain. Groups in subdomains are not displayed.

```
--verbose=Boolean(false)
```

If true, then detailed information is returned.

If false or not supplied, then only the group names are returned.

Event codes

22542

Domain does not exist.

Examples

This command returns a simple list of all groups in use:

mccli group show

This command returns detailed information for a single group:

mccli group show --name='Default Group'

```
0,23000,CLI command completed successfully.

command completed successfully

Attribute Value
-----

Name Default Group

Domain /

Type Normal
```

```
Enabled false
Dataset Default Dataset
Schedule Default Schedule
Retention Policy Default Retention
Encryption Method High
```

This command returns all proxies belonging to the Default Virtual Machine Group in vCenter 10.31.183.85:

```
mccli group show --proxy-clients=true
--name=/10.31.183.85/Default Virtual Machine Group
```

group show-members

The mccli group show-members command returns a list of all members for a group.

Syntax

```
mccli group show-members [--domain=String(/)] [--name=String]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the group specified by --name.

```
--name=String
```

Specifies the group for which to show client members. If not supplied, all groups in the domain are listed.

Use mccli group show to return a list of valid group names.

If you supply a fully qualified group name (for example, /MyDomain/MyGroup), then the --domain argument is ignored.

Event codes

22234 Group does not exist.

Examples

This command returns a simple list of all clients in the Default Virtual Machine Group:

mccli group show-client-members

```
--name=/10.31.183.55/Default Virtual Machine Group --xml
```

```
<GroupType>Default Virtual Machine Group
     <Client>/10.31.183.55/HleDynamicClients/TEST1</Client>
     <ClientType>Virtual Machine</ClientType>
  </Row>
   <Row>
     <Group>/10.31.183.55/Default Virtual Machine Group/Group>
     <GroupType>Default Virtual Machine Group
     <Client>/10.31.183.55/APP1</Client>
     <ClientType>Virtual Container</ClientType>
   </Row>
   <Row>
     <Group>/10.31.183.55/Default Virtual Machine Group/Group>
     <GroupType>Default Virtual Machine Group
     <Client>/10.31.183.55/HleDynamicClients/ABCD1</Client>
     <ClientType>Virtual Machine</ClientType>
   </Row>
   <Row>
     <Group>/10.31.183.55/Default Virtual Machine Group/Group>
     <GroupType>Default Virtual Machine Group
     <Client>/10.31.183.55/HleDynamicClients/VA1</Client>
     <ClientType>Virtual Container</ClientType>
   </Row>
 </Data>
</CLIOutput>
```

help

The mccli help resource shows online help for a resource, and then exits.

Syntax

```
mccli help {activity | agent | backup
| checkpoint | client | dataset | dd | domain
| dump | event | group | help | mcs
| plugin | retention | schedule | server | user
| vcenter | version | vmcache}
```

mcs

The mccli mcs resource is used to control various MCS functions.

mcs import

The mccli mcs import command accepts an XML file created by the mccli group export command and imports the group and its policy objects (that is, dataset, schedule, and retention policy) into the target Avamar server. The group name remains the same, but you can specify a new target domain.

Syntax

```
mccli mcs import --file=String
[--force=Boolean(false)] [--prefix=String]
[--target-domain=String]
```

Options

```
--file=String
```

Specifies the name of the import XML file. This argument is required.

```
--force=Boolean(false)
```

XML files created by the export command are digitally signed. If an XML file is edited or manually created, then digital signature verification fails during import.

If true, then the XML import is forced without validation of the digital signature.

If false or not supplied, then an error is returned, and the file is not imported.

```
--prefix=String
```

Specifies a prefix *String* that is affixed to the beginning of the imported object names. This is done to avoid conflicts and distinguish imported objects from existing ones that might otherwise have similar names.

```
--target-domain=String
```

Specifies the domain on the target server for the group and its policy objects (that is, dataset, schedule, and retention policy).

Original domain hierarchy for the imported objects is not preserved. In other words, all imported objects reside at the top-most level of the domain.

The target domain must already exist on the target server. If not, then the command returns an error.

To avoid conflicts, if a policy object with the same name already exists in the target domain, then _1, _2, _3 and so forth is appended to the name of the newly imported policy object.

Event codes

22540

Invalid name character.

mcs list

The mccli mcs list command accepts an XML file created by the group export command and lists all groups and group policy objects (that is, dataset, schedule, and retention policy) in that file.

Syntax

```
mccli mcs list --file=String
```

Options

```
--file=String
```

Specifies the name of the import XML file. This argument is required.

mcs reboot-proxy

The mccli mcs reboot-proxy command reboots VMware proxies.

Syntax

```
mccli mcs reboot-proxy [--all=Boolean(false)] [--name=String]
```

Options

```
--all=Boolean(false)
```

If true, then reboot all known Avamar proxies.

```
--name=String
```

Specifies which proxy to reboot. *String* must be a fully qualified Avamar proxy name.

Use mccli client show to return a list of valid proxy names.

Multiple -- name = arguments are allowed on the same command line.

mcs resume-scheduler

The mccli mcs resume-scheduler command turns on the MCS scheduler so that scheduled operations occur at the scheduled times.

Syntax

mccli mcs resume-scheduler

Event codes

- 22308 Scheduler successfully resumed.
- 22310 Change of the scheduler status to suspended or resume failed.
- 22631 Server has reached the capacity health check limit.

mcs scheduler-status

The mccli mcs scheduler-status command returns the status of the MCS scheduler.

Syntax

mccli mcs scheduler-status

mcs stop

The mccli mcs stop command shuts down the MCS.

Syntax

mccli mcs stop

mcs suspend-scheduler

The mccli mcs suspend-scheduler command disables the MCS scheduler. When this occurs, no scheduled operations are performed until the scheduler is re-enabled using the mccli mcs resume-scheduler command.

Syntax

mccli mcs suspend-scheduler

Event codes

- 22309 Scheduler successfully suspended.
- 22310 Change of the scheduler status to suspended or resume failed.

mcs waitforflushcomplete

The mccli mcs waitforflushcomplete command causes the MCS to wait for any in-progress flush to complete.

Syntax

mccli mcs waitforflushcomplete

plugin

The mccli plugin resource is used to manage client plug-ins on the Avamar server.

plugin show

The mccli plugin show command shows summary properties for all client plug-ins.

Syntax

mccli plugin show

plugin update

The mccli plugin update command updates the Avamar server plug-in catalog.

Note

The mccli plugin update command is strictly reserved for EMC internal use only.

Syntax

mccli plugin update

Event codes

21010 Plugin catalog dynamically updated.

retention

The mccli retention resource is used to create and manage backup retention policies.

Advanced retention descriptors

All advanced retention options, which begin with --adv-, require a descriptor as a value.

The following table lists valid advanced retention descriptors.

Table 9 Advanced retention descriptors

Descriptor	Description	Examples
+nnnD Specifies the number (nnn) of calendar days (D) .	' ' '	Specify +5D to retain five daily backups.
	Specify +13D to retain 13 daily backups.	
+ <i>nn</i> ₩	Specifies the number (<i>nn</i>) of calendar weeks (W).	Specify $+1$ W to retain one week of daily or weekly backups.
		Specify +13W to retain 13 weeks of daily or weekly backups.
+ <i>nn</i> M	Specifies the number (<i>nn</i>) of calendar months (M).	Specify $+1M$ to retain one month of daily, weekly, or monthly backups.
		Specify +9M to retain nine months of daily, weekly, or monthly backups.
+ <i>nn</i> Y	Specifies the number (<i>nn</i>) of calendar years (Y).	Specify +1Y to retain one year of daily, weekly, monthly, or yearly backups.
		Specify +5Y to retain five years of daily, weekly, monthly, or yearly backups.

retention add

The mccli retention add command creates a retention policy.

Syntax

```
mccli retention add --name=String
[--adv-daily=String(+1W)] [--adv-weekly=String(+1M)]
[--adv-monthly=String(+1Y)] [--adv-yearly=String(+1Y)]
[--basic={ NO_EXPIRATION| YYYY-MM-DD | +nn{ D | W | M | Y}]
[--domain=String(/)] [--override=Boolean(false)]
```

Options

```
--adv-daily=String(+1W)

Specifies the daily advanced retention setting.

String must be +nnnD , +nnW, +nnM, or +nnY.

--adv-weekly=String(+1M)

Specifies the weekly advanced retention setting.

String must be +nnnD , +nnW, +nnM, or +nnY.

--adv-monthly=String(+1Y)

Specifies the monthly advanced retention setting.

String must be +nnnD , +nnW, +nnM, or +nnY.

--adv-yearly=String(+1Y)

Specifies the yearly advanced retention setting.

String must be +nnnD , +nnW, +nnM, or +nnY.

--basic={NO_EXPIRATION| YYYY-MM-DD|+nn{D|W|M|Y}}
```

Specifies basic retention, which assigns a fixed expiration date in one of the following formats:

- YYYY-MM-DD specifies an explicit calendar date
- $+nn\{D \mid W \mid M \mid Y\}$ specifies a duration from today (for example, +4W specifies four weeks from today)
- NO_EXPIRATION specifies that the backup is retained indefinitely (that is, it never expires)

--domain=String(/)

Specifies the Avamar server domain that contains the retention policy specified by -- name.

```
--name=String
```

Specifies a name for the new retention policy. This argument is required.

Use mccli retention show to return a list of valid retention policy names.

If you supply a fully qualified retention policy name (for example, /MyDomain/MyRetentionPolicy), then the --domain argument is ignored.

```
--override=Boolean(false)
```

If true, then basic retention settings are overridden in favor of advanced retention settings. This option only applies to scheduled backups.

Notes

If you do not specify options, then the new retention policy has a basic expiration setting of \mathtt{NO} EXPIRATION and the advanced options are set as follows:

- Retain one week of daily backups.
- Retain one month of weekly backups.
- Retain one year of monthly backups.
- Retain one year of yearly backups.

However, unless the --override option is set true, then these settings are not enabled. Basic retention settings are used instead of advanced retention settings.

Event codes

22216	Retention Policy created.
23005	Invalid Retention Policy specified on the CLI.
23011	Retention Policy already exists.

retention copy

The mccli retention copy command copies an existing retention policy, creating a new retention policy.

Syntax

```
mccli retention copy --name=String --new-name=String
[--domain=String(/)] [--new-domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the retention policy specified by -- name.

--name=*String*

Specifies which retention policy to copy. This argument is required.

Use mccli retention show to return a list of valid retention policy names.

If you supply a fully qualified retention policy name (for example, /MyDomain/MyRetentionPolicy), then the --domain argument is ignored.

--new-domain=String(/)

Specifies the Avamar server domain that contains the retention policy specified by -- new-name.

--new-name=String

Specifies a name for the new retention policy. This argument is required.

If you supply a fully qualified retention policy name (for example, /MyDomain/MyRetentionPolicy), then the --domain argument is ignored.

Event codes

22216 Retention Policy created.

22289 Retention policy does not exist.

retention delete

The mccli retention delete command permanently deletes a retention policy from the Avamar server.

You cannot delete a retention policy if it is currently assigned to a client or group.

Syntax

```
mccli retention copy --name=String [--domain=String(/)]
```

Options

--domain=String(/)

Specifies the Avamar server domain that contains the retention policy specified by — name.

--name=*String*

Specifies which retention policy to delete. This argument is required.

Use mccli retention show to return a list of valid retention policy names.

If you supply a fully qualified retention policy name (for example, /MyDomain/MyRetentionPolicy), then the --domain argument is ignored.

Event codes

22218 Retention Policy deleted.

22289 Retention policy does not exist.

retention edit

The mccli retention edit command edits the properties for a retention policy.

There are no default settings for the mccli retention edit command. If you enter the command but do not explicitly supply options and values on the command line, then no changes are applied to the retention policy.

Syntax

```
mccli retention add --name=String
[--adv-daily=String(+1W)] [--adv-weekly=String(+1M)]
[--adv-monthly=String(+1Y)] [--adv-yearly=String(+1Y)]
[--basic={ NO_EXPIRATION| YYYY-MM-DD | +nn{ D | W | M | Y}]
[--domain=String(/)] [--override=Boolean(false)]
```

Options

```
--adv-daily=String(+1W)
```

Specifies the daily advanced retention setting.

```
String must be +nnn\mathbb{D}, +nn\mathbb{W}, +nn\mathbb{M}, or +nn\mathbb{Y}.
```

```
--adv-weekly=String(+1M)
```

Specifies the weekly advanced retention setting.

```
String must be +nnn\mathbb{D}, +nn\mathbb{W}, +nn\mathbb{M}, or +nn\mathbb{Y}.
```

```
--adv-monthly=String(+1Y)
```

Specifies the monthly advanced retention setting.

```
String must be +nnn\mathbb{D}, +nn\mathbb{W}, +nn\mathbb{M}, or +nn\mathbb{Y}.
```

```
--adv-yearly=String(+1Y)
```

Specifies the yearly advanced retention setting.

```
String must be +nnn\mathbb{D}, +nn\mathbb{M}, +nn\mathbb{M}, or +nn\mathbb{Y}.
```

```
--basic={NO EXPIRATION | YYYY-MM-DD | +nn{D | W | M | Y}]
```

Specifies basic retention, which assigns a fixed expiration date in one of the following formats:

- YYYY-MM-DD specifies an explicit calendar date
- $+nn\{D \mid W \mid M \mid Y\}$ specifies a duration from today (for example, +4W specifies four weeks from today)
- NO_EXPIRATION specifies that the backup is retained indefinitely (that is, it never expires)

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the retention policy specified by -- name.

```
--name=String
```

Specifies which retention policy to modify. This argument is required.

Use mccli retention show to return a list of valid retention policy names.

If you supply a fully qualified retention policy name (for example, /MyDomain/MyRetentionPolicy), then the --domain argument is ignored.

```
--override=Boolean(false)
```

If true, then basic retention settings are overridden in favor of advanced retention settings. This option only applies to scheduled backups.

Event codes

22217	Retention Policy modified.
22289	Retention policy does not exist.
23005	Invalid Retention Policy specified on the CLI.

retention show

The mccli retention show command returns information for all retention policies in an Avamar domain.

Syntax

```
mccli retention copy [--domain=String(/)] [--name=String]
[--recursive=Boolean(false)] [--verbose=Boolean(false)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the retention policy specified by -- name.

```
--name=String
```

Specifies a retention policy name. If not supplied, all retention policies are listed with summary information.

Use mccli retention show to return a list of valid retention policy names.

If you supply a fully qualified retention policy name (for example, /MyDomain/MyRetentionPolicy), then the --domain argument is ignored.

```
--recursive=Boolean(false)
```

If true, then the command shows all retention policies in the domain and any subdomains specified by the --domain argument.

If false or not supplied, then the command only shows retention policies in the specified domain. Subdomains are not examined.

```
--verbose=Boolean(false)
```

If true, then detailed retention policy information is returned.

If false or not supplied, then only retention policy names are returned.

If you also supply --name, then detailed information for that retention policy is returned.

Event codes

22289	Retention policy does not exist.
22542	Domain does not exist.

Examples

This command returns verbose information for all retention policies:

```
mccli retention show --verbose
```

This command lists information for the Default Retention policy:

mccli retention show --name='Default Retention'

```
0,23000,CLI command completed successfully.

Attribute Value
-----

Name Default Retention

Basic Expiration Date 90 Days

Override Yes

Keep days of daily 1
```

schedule

The mccli schedule resource is used to manage Avamar server schedules.

schedule add

The mccli schedule add command creates a new schedule.

Syntax

```
mccli schedule add --name=String
[--days={SU | M | TU | W | TH | F | SA}]
[--desc=String] [--duration=String] [--domain=String(/)]
[--nth-day={[1-28] | last}] [--on-demand=Boolean(false)]
[--start=String] [--time=String] [--tz=String]
[--week={first | second | third | fourth | last}]
```

Options

```
--days={SU | M | TU | W | TH | F | SA}
```

Specifies which day of the week the schedule will run.

Separate multiple values with commas.

```
--desc=String
```

Specifies a short text description of the schedule.

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the schedule specified by --name.

```
--duration=String
```

Specifies a backup window duration.

String must be in the format of HH:MM.

If you do not supply --duration, then the default duration for a daily schedule is one hour and the default duration for a weekly schedule is eight hours.

```
--name=String
```

Specifies a name for the new schedule. This argument is required.

Use mccli schedule show to return a list of valid schedule names.

If you supply a fully qualified schedule name (for example, /MyDomain/MySchedule), then the --domain argument is ignored.

 $--nth-day=\{[1-28] | last\}$

Creates a schedule that runs on the specified calendar day of each month. *String* must be a valid numerical calendar date between 1 and 28, or last.

--on-demand=Boolean(false)

If true, then the new schedule is designated as an on-demand schedule, which also overrides other schedule type designations.

If false or not supplied, then.

--start=*String*

Specifies the earliest start time for the schedule. *String* must be in the format of *HH:MM*.

The --start option does not apply for daily schedules.

If you do not specify --start for a weekly schedule, then the default start time is 10 p.m. in the time zone in which the schedule was created.

--time=String

Creates a schedule that runs daily at the specified time of the day. *String* must be in the format of *HH:MM*.

Multiple --time options can be specified on the same command line.

--tz=*String*

Specifies the time zone for the schedule. If not supplied, then the local time zone is used.

Use mccli schedule show-timezones to return a list of valid time zone names.

--week={first | second | third | fourth | last}

Creates a schedule that runs on the specified week each month.

Notes

You must specify either --days, --nth-day, --time, or --week to indicate the schedule recurrence. Specify --days to create a weekly schedule, --time to create a daily schedule, and --nth-day or --week to create a monthly schedule.

If you specify ——duration, then the default duration for a daily schedule is one hour and the default duration for a weekly schedule is eight hours.

The --start option does not apply for daily schedules.

If you do not specify the --start option for a weekly schedule, then the default start time is 10 p.m. in the time zone in which the schedule was created.

If you do not specify the --tz option, then the default time zone is the local time zone.

Event codes

22213	Schedule created.
22248	Schedule already exists.
22540	Invalid name character.
22542	Domain does not exist.

Examples

This command creates a new monthly schedule that runs on the second Friday of each month:

```
mccli schedule add --name=monthly_2nd_fri --week=second --days=Friday
```

This command creates a new monthly schedule that runs on the 28th calendar day of each month:

```
mccli schedule add --name=monthly 28th --nth-day=28
```

schedule copy

The mccli schedule copy command copies an existing schedule, creating a new schedule.

Syntax

```
mccli schedule copy --name=String --new-name=String
[--domain=String(/)] [--new-domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the schedule specified by --name.

```
--name=String
```

Specifies which schedule to copy. This argument is required.

Use mccli schedule show to return a list of valid schedule names.

If you supply a fully qualified schedule name (for example, /MyDomain/MySchedule), then the --domain argument is ignored.

```
--new-domain=String(/)
```

Specifies the Avamar server domain that contains the schedule specified by --new-name.

```
--new-name=String
```

Specifies a name for the new schedule. This argument is required.

If you supply a fully qualified schedule name (for example, /MyDomain/MySchedule), then the --domain argument is ignored.

Event codes

22213	Schedule created.
22248	Schedule already exists.
22249	Schedule does not exist.

schedule delete

The \mbox{mccli} schedule delete command permanently deletes a schedule from the Avamar server.

You cannot delete a schedule if it is assigned to a group or event profile.

Syntax

```
mccli schedule delete --name=String [--domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the schedule specified by --name.

```
--name=String
```

Specifies which schedule to delete. This argument is required.

Use mccli schedule show to return a list of valid schedule names.

If you supply a fully qualified schedule name (for example, /MyDomain/MySchedule), then the --domain argument is ignored.

Event codes

- 22215 Schedule deleted.
- 22249 Schedule does not exist.
- 22277 Failed to delete a schedule because it is being used by a group or an event profile.
- 22530 Schedule is read-only.
- 22531 Unexpected exception occurred.

schedule edit

The mccli schedule edit command edits the properties for a schedule.

There are no default settings for the mccli schedule edit command. If you enter the command but do not explicitly supply options and values on the command line, then there are no changes to the schedule.

Syntax

```
mccli schedule edit --name=String
[--days={SU | M | TU | W | TH | F | SA}]
[--desc=String] [--duration=String] [--domain=String(/)]
[--nth-day={[1-28] | last}] [--on-demand=Boolean(false)]
[--start=String] [--time=String] [--tz=String]
[--week={first | second | third | fourth | last}]
```

Options

```
--days={SU | M | TU | W | TH | F | SA}
```

Specifies which day of the week the schedule will run.

Separate multiple values with commas.

```
--desc=String
```

Specifies a short text description of the schedule.

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the schedule specified by --name.

```
--duration=String
```

Specifies a backup window duration.

String must be in the format of HH:MM.

If you do not supply --duration, then the default duration for a daily schedule is one hour and the default duration for a weekly schedule is eight hours.

--name=*String*

Specifies which schedule to modify. This argument is required.

Use mccli schedule show to return a list of valid schedule names.

If you supply a fully qualified schedule name (for example, /MyDomain/MySchedule), then the --domain argument is ignored.

--nth-day={[1-28] | last}

Creates a schedule that runs on the specified calendar day of each month. *String* must be a valid numerical calendar date between 1 and 28, or last.

--on-demand=Boolean(false)

If true, then the new schedule is designated as an on-demand schedule, which also overrides other schedule type designations.

If false or not supplied, then.

--start=*String*

Specifies the earliest start time for the schedule. *String* must be in the format of *HH:MM*.

The --start option does not apply for daily schedules.

If you do not specify --start for a weekly schedule, then the default start time is 10 p.m. in the time zone in which the schedule was created.

--time=String

Creates a schedule that runs daily at the specified time of the day. *String* must be in the format of *HH:MM*.

Multiple --time options can be specified on the same command line.

--tz=*String*

Specifies the time zone for the schedule. If not supplied, then the local time zone is used.

Use mccli schedule show-timezones to return a list of valid time zone names.

--week={first|second|third|fourth|last}

Creates a schedule that runs on the specified week each month.

Notes

You must specify either --days, --nth-day, --time, or --week to indicate the schedule recurrence. Specify --days to create a weekly schedule, --time to create a daily schedule, and --nth-day or --week to create a monthly schedule.

If you specify ——duration, then the default duration for a daily schedule is one hour and the default duration for a weekly schedule is eight hours.

The --start option does not apply for daily schedules.

If you do not specify the --start option for a weekly schedule, then the default start time is 10 p.m. in the time zone in which the schedule was created.

If you do not specify the --tz option, then the default time zone is the local time zone.

Event codes

22214	Schedule modified.
22249	Schedule does not exist.

Examples

This command modifies a monthly schedule to run on the last calendar day of each month.

```
mccli schedule edit --name=monthly --nth-day=last
```

schedule show

The mccli schedule show command lists all schedules and detailed schedule information.

Syntax

```
mccli schedule show [--domain=String(/)] [--name=String]
[--recursive=Boolean(false)] [--verbose=Boolean(false)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain that contains the schedule specified by --name.

```
--name=String
```

Specifies which schedule to delete. This argument is required.

Use mccli schedule show to return a list of valid schedule names.

If you supply a fully qualified schedule name (for example, /MyDomain/MySchedule), then the --domain argument is ignored.

```
--recursive=Boolean(false)
```

If true, then the command shows all schedules in the domain and any subdomains specified by the --domain argument.

If false or not supplied, then the command only shows schedules in the specified domain. Subdomains are not examined.

```
--verbose=Boolean(false)
```

If true, then detailed schedule information is returned.

If false or not supplied, then only schedule names are returned.

If you also supply --name, then detailed information for that schedule is returned.

Event codes

22249	Schedule does not exist.
22542	Domain does not exist

Examples

This command returns detailed information for the Default Schedule:

```
mccli schedule show --name='Default Schedule'
```

```
0,23000,CLI command completed successfully.
Attribute
                             Value
                              Default Schedule
Name
Domain
ReadOnly
                              true
                             America/Los Angeles
Native Timezone
Daylight Savings Adjustment (m) 60
Next Run Time
                               2014-09-20 10:00 PM
Start Time
                              10:00 PM Pacific Daylight Time
Backup Window Duration (hours) 8.0
Repeat
                              Weekly
Days of Week
                              Sun, Mon, Tue, Wed, Thu, Fri, Sat
Delay Start Until
End Policy
                              No End Date
Description
                              N/A
```

schedule show-timezones

The mccli schedule show-timezones command lists all valid time zones, which you can supply with other mccli schedule commands using the --tz option.

Syntax

```
mccli schedule show-timezones
```

server

The mccli server resource is used to monitor various Avamar server functions.

server show-prop

The mccli server show-prop command returns detailed properties for the Avamar server.

If you run mccli server show-prop without options, then a summary of server properties is shown.

Syntax

```
mccli server show-prop [--gc=Boolean(false)]
[--maintenance=Boolean(false)]
{[--module={module | ALL}] |
[--node={module.node | ALL} [--partition={partition | ALL}]]}
[--verbose=]
```

Options

--qc=Boolean(false)

If true, then detailed garbage collection information is shown.

--maintenance=Boolean(false)

If true, then detailed maintenance activity information is shown.

If false or not supplied, then.

--module={module | ALL}

Specifies an Avamar server module.

String must be a valid Avamar server module designator. Module designators are typically single-digit integers beginning with zero. For example, 0, 1, 2, and so forth.

A value of ALL returns status for all modules.

The --module and --node options are mutually exclusive.

```
--node={module.node | ALL}
```

Specifies an Avamar server node.

String must be a valid Avamar server numeric node designator in the format of *module.node*. For example, 0.0 is typically the first storage node in a multi-node server.

A value of ALL returns status for all nodes.

The --module and --node options are mutually exclusive.

```
--partition={partition | ALL}
```

Specifies an Avamar server data partition.

String must be a valid Avamar server partition designator. Partition designators are typically single-digit integers beginning with zero. For example, 0, 1, 2, and so forth.

A value of ALL returns status for all server data partitions.

```
The --partition option requires --node.
```

```
--verbose=
```

If supplied, then maximum information is returned..

Examples

This command returns a summary of server properties:

mccli server show-prop

```
0,23000,CLI command completed successfully.
  Attribute
                                                                                                                                                                                               Value
                                                                                                                                                                                               Node Offline
   State
Active sessions

Total capacity
Capacity used
Server utilization
Bytes protected
Bytes protected quota
License expiration

Note Offline
Note of Fine Note of Fine Note

0.0 bytes
Not configured
Note of Fine Note of
 Last validated checkpoint 2014-10-01 04:00:28 PDT System Name avamar-1 System ID
 Time since Server initialization 17 days 21h:13m
                                                                                                                                                                                               avamar-1
1216944475@00:19:B9:BA:14:EA
avamar-1.example.com
 HFSAddr
 HFSPort
                                                                                                                                                                                                 27000
                                                                                                                                                                                            10.6.248.196
   IP address
  Number of nodes
  Nodes Online
                                                                                                                                                                                                       1
  Nodes Offline
   Nodes Read-only
                                                                                                                                                                                                        0
   Nodes Timed-out
```

This command returns information for server node 0.0 partition zero (0):

mccli server show-prop --node=0.0 --partition=0

```
0,23000,CLI command completed successfully.

Attribute Value
-----
Node ID 0.0
State ONLINE
Runlevel fullaccess
```

```
Accessmode
                                 mhpu+0hpu+0hpu
                                 26000
Port
                                 27000
Dispatcher
                                 600 days 18h:08m
Server uptime
Server utilization
                                0.1%
Number of stripes
                                22
                                7.1.0-nnn
Server version
Version
                                 v2.6.9-67.ELsmp
Node uptime
                                 600 days 00h:07m
Total capacity
                                86.0 TB
Capacity used
                                 6.4 TB
Load average
                                0.22
CPU %
                                 1.9%
Disk reads
                                 0.11/sec
Disk writes
                                2.21/sec
                                2K/sec
Network reads
Network writes
                                 2K/sec
IP address
                                 10.6.249.38
Mac address
                                 00:13:72:59:8F:AE
Number of partitions
```

This command returns detailed garbage collection information:

mccli server show-prop --gc=true

```
0,23000,CLI command completed successfully.
Attribute
                              Value
Status
                                idle
Result
                               OK
                               2014-4-10 08:15:00 UTC
Start time
End time
                               2014-4-10 08:15:17 UTC
Passes
                               81.9 KB
Bytes recovered
Chunks deleted
                               16
Index stripes
                                6
Index stripes processed
```

This command returns detailed maintenance activity information:

mccli server show-prop --maintenance=true

```
0,23000,CLI command completed successfully.
Attribute Value
-----
Suspended No
```

server show-services

The mccli server show-services command returns information about Avamar server services.

Syntax

```
mccli server show-services [--service=String]
```

Options

```
--service=String
```

If supplied, shows information for that specific service.

If not supplied, then all services are shown.

server show-util

The mccli server show-util command returns capacity utilization information from the Avamar server.

Syntax

```
mccli server show-util {[--module={module | ALL}]
| [--node={module.node | ALL}]}
```

If you run mccli server show-util without command options, then a summary of server capacity utilization is shown.

Options

```
--module={module | ALL}
```

Specifies an Avamar server module.

String must be a valid Avamar server module designator. Module designators are typically single-digit integers beginning with zero. For example, 0, 1, 2, and so forth.

A value of ALL returns status for all modules.

The --module and --node options are mutually exclusive.

```
--node={module.node | ALL}
```

Specifies an Avamar server node.

String must be a valid Avamar server numeric node designator in the format of *module.node*. For example, 0.0 is typically the first storage node in a multi-node server.

A value of ALL returns status for all nodes.

The --module and --node options are mutually exclusive.

server start-service

The mccli server start-service command starts a service that is currently stopped.

Syntax

```
mccli server start-service --service=String
```

Options

```
--service=String
```

Which service to start. This argument is required.

Use mccli server show-services to return a list of valid service names.

server stop-service

The mccli server stop-service command stops a service that is currently running.

Syntax

```
mccli server stop-service --service=String
```

Options

```
--service=String
```

Which service to stop. This argument is required.

Use mccli server show-services to return a list of valid service names.

user

The mccli user resource is used to manage backup user accounts.

user add

The mccli user add command creates a backup user account for a client or domain.

Syntax

```
mccli user add {--client-domain=String
| --client-name=String [--client-domain=String]}
--name=String --password=String --password-confirm=String
--role={ActivityOperator | Administrator | Auditor | Backup
| BackupOperator | BackupRestore | BackupRestoreOperator | Restore
| RestoreIgnoreFilePermissions | RestoreOperator}
[--authenticator=String(Axion)]
```

Options

```
--authenticator=String(Axion)
```

Specifies the authentication system to use to grant the new user access to the Avamar server.

String must be either Axion or the name of another valid authentication system that has been configured for use with the Avamar server; *String* is case-insensitive.

Use mccli user show-auth to return a list of valid authentication system names.

```
--client-domain=String
```

Specifies the Avamar server domain for the new user.

If you supply only --client-domain, then the user is added to the domain.

If you supply both --client-domain and --client-name, then the user is added to that client. If you supply only --client-domain, then the user is added to the domain.

Use mccli domain show to return a list of valid domain names.

Note

You cannot add new user accounts to the MC_RETIRED domain or to any clients in that domain.

```
--client-name=String
```

Specifies which client gets the new user account.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /client/MyClient), then the --domain argument is ignored.

```
--name=String
```

```
--password=String
```

Specifies the user name and password for the new user account. These arguments are required.

--role={ActivityOperator|Administrator|Auditor|Backup|
BackupOperator|BackupRestore|BackupRestoreOperator|Restore
| RestoreIgnoreFilePermissions | RestoreOperator}

Specifies a role for the user. This argument is required.

You can only assign the RestoreIgnoreFilePermissions role if you use an external authentication system.

Event codes

22528	Failed to add user.
22529	User added.
22540	Invalid name character.
22542	Domain does not exist.
22546	Password mismatch.
22548	User already exists.
22549	Invalid privilege.
22550	Invalid authenticator.

Examples

This command adds a new user account, jsmith, with Administrator privileges to / clients/MyDomain:

mccli user add --name=jsmith --client-domain=/clients/MyDomain
--role=Administrator --password=XXXXXX --password-confirm=XXXXXXX

```
0,22529, User added.

Attribute Value
-----
user <appuser authentication="Avamar Authentication System"
folder="/clients/MyDomain" name="jsmith"
privilege="Administrator"/>
```

This command adds a new user account, jsmith, with backup privileges to /clients/MyClient:

```
mccli user add --name=jsmith --client-domain=/clients --client-
name=MyClient
```

--role=Administrator --password=XXXXXX --password-confirm=XXXXXX

```
0,22529, User added.
Attribute Value
------
user <appuser authentication="Avamar Authentication System"
folder="/clients/MyClient" name="jsmith" privilege="Back up
Only"/>
```

⁻⁻password-confirm=*String*

user authenticate

The mccli user authenticate command verifies user authentication settings. This is useful for testing user names, passwords, and authentication system settings before creating a new user account.

Syntax

```
mccli user authenticate {--client-domain=String
| --client-name=String [--client-domain=String]}
--name=String --password=String
[--authenticator=String(Axion)]
```

Options

```
--authenticator=String(Axion)
```

Specifies the authentication system associated with the user account.

String must be either Axion or the name of another valid authentication system that has been configured for use with the Avamar server; *String* is case-insensitive.

Use mccli user show-auth to return a list of valid authentication system names.

```
--client-domain=String
```

Specifies the Avamar server domain associated with the client or user account.

If you supply only --client-domain, then the user is authenticated to that domain.

If you supply both --client-domain and --client-name, then the user is authenticated to that client. If you supply only --client-domain, then the user is authenticated to the domain.

Use mccli domain show to return a list of valid domain names.

```
--client-name=String
```

Specifies the name of the client associated with the user account.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /client/MyClient), then the --domain argument is ignored.

```
--name=String
--password=String
```

Specifies a user name and password. These arguments are required.

Event codes

22348	Successful authenticate.
22349	Failed authenticate.
22542	Domain does not exist.
22550	Invalid authenticator.
22801	Login failure.

user delete

The \mbox{mccli} user delete command permanently deletes a user from the Avamar server.

Syntax

```
mccli user delete {--client-domain=String
| --client-name=String [--client-domain=String]}
--name=String [--authenticator=String(Axion)]
```

Options

--authenticator=String(Axion)

Specifies the authentication system associated with the user account.

String must be either Axion or the name of another valid authentication system that has been configured for use with the Avamar server; String is case-insensitive.

Use mccli user show-auth to return a list of valid authentication system names.

```
--client-domain=String
```

Specifies the Avamar server domain associated with the client or user account.

If you supply only --client-domain, then the user is deleted from the domain.

If you supply both --client-domain and --client-name, then the user is deleted from that client. If you supply only --client-domain, then the user is deleted from that to the domain.

Use mccli domain show to return a list of valid domain names.

```
--client-name=String
```

Specifies the name of the client associated with the user account.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /client/MyClient), then the --domain argument is ignored.

```
--name=String
```

Specifies which user to delete. This argument is required.

Event codes

22522	Failed user delete.
22523	User deleted.
22540	Invalid name character.
22542	Domain does not exist.
22547	User does not exist.
22550	Invalid authenticator.
22600	Server inactive.

user edit

The mccli user edit command edits the properties for a user.

Syntax

```
mccli user edit --name=String {--client-domain=String
| --client-name=String [--client-domain=String]}
[--authenticator=String(Axion)]
[--role={ActivityOperator | Administrator | Auditor | Backup
| BackupOperator | BackupRestore | BackupRestoreOperator | Restore
| RestoreIgnoreFilePermissions | RestoreOperator}]
```

Options

```
--authenticator=String(Axion)
```

Specifies the authentication system associated with the user account.

String must be either Axion or the name of another valid authentication system that has been configured for use with the Avamar server; String is case-insensitive.

Use mccli user show-auth to return a list of valid authentication system names.

```
--client-domain=String
```

Specifies the Avamar server domain associated with the client or user account.

If you supply only --client-domain, then the user is deleted from the domain.

If you supply both --client-domain and --client-name, then the user is deleted from that client. If you supply only --client-domain, then the user is deleted from that to the domain.

Use mccli domain show to return a list of valid domain names.

```
--client-name=String
```

Specifies the name of the client associated with the user account.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /client/MyClient), then the --domain argument is ignored.

```
--name=String
--password=String
```

--password-confirm=String

Specifies the user name and password for the user account. The --name= argument is required.

--role={ActivityOperator|Administrator|Auditor|Backup|
BackupOperator|BackupRestore|BackupRestoreOperator|Restore
| RestoreIgnoreFilePermissions|RestoreOperator}

Specifies a role for the user.

You can only assign the RestoreIgnoreFilePermissions role if you use an external authentication system.

Event codes

22520 User updated.

22521	Failed user update.
22542	Domain does not exist.
22546	Password mismatch.
22547	User does not exist.
22549	Invalid privilege.
22550	Invalid authenticator.
22551	Can not edit reserved user.
23001	Missing required arguments.

user show

The mccli user show command displays properties for users on an access list for a client or domain.

Syntax

```
mccli user show --name=String {--client-domain=String
| --client-name=String [--client-domain=String]}
[--authenticator=String(Axion)]
```

Options

```
--authenticator=String(Axion)
```

Specifies the authentication system associated with the user account.

String must be either Axion or the name of another valid authentication system that has been configured for use with the Avamar server; String is case-insensitive.

Use mccli user show-auth to return a list of valid authentication system names.

```
--client-domain=String
```

Specifies the Avamar server domain associated with the client or user account.

If you supply only --client-domain, then the user is deleted from the domain.

If you supply both --client-domain and --client-name, then the user is deleted from that client. If you supply only --client-domain, then the user is deleted from that to the domain.

Use mccli domain show to return a list of valid domain names.

```
--client-name=String
```

Specifies the name of the client associated with the user account.

Use mccli client show to return a list of valid client names.

If you supply a fully qualified client name (for example, /client/MyClient), then the --domain argument is ignored.

```
--name=String
```

Specifies the user name and password for the user account. The --name argument is required.

⁻⁻password=*String*

⁻⁻password-confirm=*String*

--recursive=Boolean(false)

If true, then the command shows all users in the domain and any subdomains specified by the --domain argument.

If false or not supplied, then the command only shows users in the specified domain. Subdomains are not examined.

Event codes

22542	Domain does not exist.
22547	User does not exist.

user show-auth

The mccli user show-auth command displays all authentication systems configured for use with the Avamar server.

Syntax

```
mccli user show-auth
```

vcenter browse

The mccli vcenter browse command is used to browse a vCenter for virtual machines, either by specifying a folder path, or ESX server or datacenter names. Both Host and Clusters, and VMs and Templates views are supported.

Syntax

```
mccli vcenter browse --name=String
[--container-path=String] [--datacenter=String]
[--esx-host=String] [--folder=String]
[--recursive=Boolean(false)]
[--type={DATACENTER | DATASTORE | NETWORK | VAPP | VM}]
[--vsphere-hosts-clusters-view=Boolean(false)]
```

Options

```
--container-path=String
```

When Specifies a container path within the specified datacenter. *String* can be a vApp container in the VMs and Templates view, or a resource pool in the Hosts and Clusters view.

```
--datacenter=String
```

Specifies a fully qualified datacenter name in vCenter.

This option is only valid when browsing for virtual machines or vApps.

```
--esx-host=String
```

Specifies a fully qualified ESX server hostname in a datacenter.

This option is only valid when browsing for virtual machines or vApps in the vSphere Hosts and Clusters view (that is, --vsphere-hosts-clusters-view=true).

```
--folder=String
```

Specifies a folder path within the specified datacenter.

This option is only valid when browsing for virtual machines or vApps in the vSphere VMs and Templates view (that is, --vsphere-hosts-clusters-view=false).

--name=*String*

Specifies the vCenter name. This argument is required.

--recursive=Boolean(false)

If true, then command browse all levels of the specified folder path in a datacenter.

This option is only valid when browsing for virtual machines or vApps.

--type={DATACENTER | DATASTORE | NETWORK | VAPP | VM}

Specifies the type of entity that should be searched for by this command.

- DATACENTER—Browse for datacenters. Returns datacenter names and locations.
- DATASTORE—Browse datastores. Returns detailed datastore information such as Datacenters, Name, Type, Accessible/Not, Hosts.
- NETWORK—Browse for virtual networks. Returns all available networks and their hosts.
- VAPP—Browse for vApps.
- VM—Browse virtual machines. Returns detailed virtual machine information such as Name, Guest OS, Server, Location, Template, Powered On/Off, Changed Block Tracking, and Is protected.

The default entity type is VM.

```
--vsphere-hosts-clusters-view=Boolean(false)
```

If true, then the vSphere Hosts and Clusters view is processed.

If false or not supplied, then the vSphere VMs and Templates view is processed.

This option is only valid when browsing for virtual machines or vApps.

Examples

This command recursively browses vCenter vcenter-1.example.com for virtual machines:

mccli vcenter browse --name=vcenter-1.example.com --recursive=true
--xml

```
<CLIOutput>
<Results>
 <ReturnCode>1</ReturnCode>
 <EventCode>23999</EventCode>
 <EventSummary />
</Results>
<Data>
 <Row>
  <Name>ACMCommunity</Name>
  <GuestOS>debian5Guest</GuestOS>
  <Server>10.31.183.7
  <Location>/VAAYU-DEV-WIN/vm/Test1/Test1/ACMCommunity</Location>
  <Template>No</Template>
  <PoweredOn>Yes</PoweredOn>
  <ChangedBlock>No</ChangedBlock>
  <Protected>Yes</Protected>
 </Row>
 <Row>
  <Name>RHEL564BUILDDOWNLOAD224</Name>
  <Guest0S>rhel5_64Guest</Guest0S>
<Server>10.31.183.7</server>
  <Location>
    /VAAYU-DEV-WIN/vm/Discovered virtualmachine/RHEL564BUILDDOWNLOAD224
  </Location>
  <Template>No</Template>
  <PoweredOn>Yes</PoweredOn>
  <ChangedBlock>No</ChangedBlock>
  <Protected>No</Protected>
```

```
</Row>
</Data>
</CLIOutput>
```

This command browses vcenter-1.example.com for datastores:

mccli vcenter browse --name=vcenter-1.example.com --type=DATASTORE
--xml

```
        Name
        Type
        Accessible
        Hosts
        Datacenter

        -----
        -----
        ------

        Storage1
        VMFS
        Yes
        10.31.183.7
        VAAYU-DEV-WIN

        Storage2
        VMFS
        Yes
        10.31.183.7
        VAAYU-DEV-WIN
```

This command browses vCenter vcenter-1.example.com for virtual machines in datacenter VAAYU-DEV-WIN Hosts and Clusters view:

```
mccli vcenter browse --name=vcenter-1.example.com
--datacenter=VAAYU-DEV-WIN --esx-host=10.31.183.7
--vsphere-hosts-clusters-view=true --xml
```

```
<CLIOutput>
<Results>
 <ReturnCode>1</ReturnCode>
 <EventCode>23999</EventCode>
 <EventSummary />
</Results>
<Data>
 <Row>
  <Name>ACMCommunity</Name>
  <GuestOS>debian5Guest</GuestOS>
  <Server>10.31.183.7
  <Location>
   /VAAYU-DEV-WIN/host/10.31.183.7/10.31.183.7/ACMCommunity
  </Location>
  <Template>No</Template>
  <PoweredOn>Yes</PoweredOn>
  <ChangedBlock>No</ChangedBlock>
  <Protected>Yes</Protected>
 </Row>
 <Row>
  <Name>RHEL564BUILDDOWNLOAD224</Name>
  <GuestOS>rhel5 64Guest</GuestOS>
  <Server>10.31.183.7
  <Location>
   /VAAYU-DEV-WIN/host/10.31.183.7/10.31.183.7/RHEL564BUILDDOWNLOAD224
  </Location>
  <Template>No</Template>
  <PoweredOn>Yes</PoweredOn>
  <ChangedBlock>No</ChangedBlock>
  <Protected>No</Protected>
 </Row>
</Data>
```

This command recursively returns a list of virtual networks and the hosts that use them:

mccli vcenter browse --type=NETWORK --name=10.31.183.55

This command browses for vApps in datacenter DCF1/DCF2 in folders FO1/FO2:

```
mccli vcenter browse --type=VAPP --name=10.31.183.55
--datacenter=DCF1/DCF2 --folder=F01/F02 --recursive=true --xml
```

```
Listening for transport dt socket at address: 8003
<CLIOutput>
 <Results>
 <ReturnCode>1</ReturnCode>
 <EventCode>23999</EventCode>
 <EventSummary />
 </Results>
 <Data>
  <Row>
   <Name>VA1</Name>
   <GuestOS>N/A</GuestOS>
   <Server>10.31.183.17
   <Location>/DCF1/DCF2/vm/F01/F02/VA1/</Location>
   <Template>No</Template>
   <PoweredOn>No</PoweredOn>
   <ChangedBlock>No</ChangedBlock>
  <Protected>No</Protected>
 </Row>
 </Data>
</CLIOutput>
```

version show

The mccli version show command returns the version of MCCLI currently installed, and then exits.

Syntax

mccli version show

vmcache

The mccli vmcache resource is used to used to assist with debugging possible vCenter data cache synchronization issues.

Note

The mccli vmcache resource is strictly reserved for EMC internal use only.

vmcache show

The mccli vmcache show command is used to examine cached vCenter data.

Note

The mccli vmcache show command is strictly reserved for EMC internal use only.

Syntax

```
mccli vmcache show --name=String [--domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain with the virtual machine or container entity specified by the --name argument. This argument is required.

```
--name=String
```

Specifies the virtual machine or container entity for which to show cached vCenter data. This argument is required.

Examples

This command shows cached vCenter data for a single virtual machine:

mccli vmcache show --domain=vcenter-1.example.com/ContainerClients
-name=my-vm

This command shows cached vCenter data for a container entity:

mccli vmcache show --domain=vcenter-1.example.com --name=my-container

vmcache sync

The mccli vmcache sync command is used to manually synchronize cached vCenter data.

Note

The mccli vmcache sync command is strictly reserved for EMC internal use only.

Syntax

```
mccli vmcache sync --name=String [--domain=String(/)]
```

Options

```
--domain=String(/)
```

Specifies the Avamar server domain with the virtual machine or container entity specified by the --name argument. This argument is required.

```
--name=String
```

Specifies the virtual machine or container entity for which to show cached vCenter data. This argument is required.

Examples

This command synchronizes a single virtual machine's cached vCenter data:

```
mccli vmcache sync --name=my-vm
--domain=vcenter-1.example.com/ContainerClients
```

This command synchronizes a container entity's cached vCenter data:

mccli vmcache sync --name=my-container --domain=vcenter-1.example.com

APPENDIX A

Utilities and Configuration Files

This chapter includes the following topics:

•	avsetup mccli	140
•	mccli.xml	140
•	mcclimcs.xml	141

avsetup_mccli

The avsetup mccli utility configures the MCCLI.

By default the MCCLI RPM installs essential files to the locations in the following table.

Table 10 MCCLI essential files

Location	Essential files
/usr/local/avamar/bin	Binary and executables
/usr/local/avamar/doc	Documentation and report templates
/usr/local/avamar/lib	Resource libraries and initial configuration files

The RPM documentation provides instructions on installing the MCCLI application to a folder other than the default /usr/local/avamar location.

The default paths in the following table are used by the MCCLI during command invocation.

Table 11 MCCLI default paths

Default path	Description
/usr/java/jre1.6.0_12	Location of JRE installation
/usr/local/avamar	Location of MCCLI installation (this is also known as \$AVAMAR_ROOT)
~/.avamardata/var	Location of user command invocation data and logs (this is also known as \$USER_ROOT)

You can modify these path assignments at any time by rerunning the avsetup_mccli utility.

Additionally, $avsetup_mccli$ also prompts you to specify values for all mccli global options. When you specify these values during the interactive $avsetup_mccli$ session, it automatically updates the mcclimcs.xml default options file.

mccli.xml

The $\mathtt{mccli.xml}$ preferences file contains the parameters that you can edit for the MCCLI application.

The default version of mccli.xml is located in \$AVAMAR_ROOT/lib. Each time the MCCLI application is run, \$USER_ROOT/.avamardata/var/mc/cli_data/prefs is examined to determine if a working copy of mccli.xml is present. If mccli.xml is not present in \$USER_ROOT/.avamardata/var/mc/cli_data/prefs, then the default copy of mccli.xml is copied to that location from \$AVAMAR_ROOT/lib.

When any MCCLI command is invoked, \$USER_ROOT/.avamardata/var/mc/cli_data/prefs/mccli.xml is read, and those settings are used for that command session.

The mccli.xml contains the two parameters described in the following table.

Table 12 Parameters in mccli.xml

Parameter	Essential files
event_monitor_display_limit	Sets the maximum number of events to retrieve.
mcs_config_file	Stores the location of the mcclimcs.xml default options file.

mcclimcs.xml

The mcclimcs.xml is an XML file that stores custom mccli command parameters and profile settings that are used when you invoke any mccli command.

Default command parameters

The mcclimcs.xml preferences file can be used to set a default value for any mccli command parameter. Any default values set in this file are used unless another value is explicitly supplied on the command line. Additionally, these default values are global, meaning that they are used by all profiles.

Profiles

Each profile is an element in the XML document and is distinguishable by the mcsprofile attribute, which identifies the name of the profile. Each profile contains a list of default options to use with the MCS specified for that profile.

You can designate one profile as the default profile. This default profile is used if no MCS information is specified on the command line global options. Otherwise, the profile name of the MCS is all that is required on the command line, and the remainder of the options are read from the configuration file.

One or all of the options can be specified on the command line to override entries in the mcclimcs.xml file.

Note

If the server hostname or data port assignment are changed for any reason (for example, after running the resite utility), or the user account name or password used to run mccli commands is changed for any reason, you must manually update the corresponding settings in the mcclimcs.xml preferences file to account for those changes.

Behavior

The default version of mcclimcs.xml is located in \$AVAMAR_ROOT/lib. Each time the MCCLI application is run, \$USER_ROOT/.avamardata/var/mc/cli_data/prefs is examined to determine if a working copy of mcclimcs.xml is present.

If $SUSER_ROOT/.avamardata/var/mc/cli_data/prefs/mcclimcs.xml is not present, then the default copy of mcclimcs.xml is copied to that location from $AVAMAR ROOT/lib.$

Example 1 Make mccli activity show only return active jobs

This setting constrains the mccli activity show command to only show active jobs, as if the --active=true option was supplied on the command line.

Example 1 Make mccli activity show only return active jobs (continued)

```
<Resource Name="activity">
  <Command Name="show">
  <Options>
   <Option Name="active" Value="true" />
  </Options>
  </Command>
</Resource>
```

Example 2 Make mccli client add set new client data port to 29123

These settings affect the mccli client add command so that any new client is enabled and its page data port is set to 29123 as if the --enabled=true and --pageport=29123 options were supplied on the command line.

Example 3 Add a new service account profile to the mcclimcs.xml file and encrypt the account password

To add a new service account to the mcclimcs.xml file, duplicate the existing MCS section and update the duplicated section as follows:

```
MCS

mcsprofile="local"
    mcsaddr="address"
    mcsport="port"
    mcsuserid="MCUser"
    mcspasswd="password"

/>

MCS

mcsprofile="service"
    mcsaddr="address"
    mcsport="port"
    mcsuserid="ServiceUserName"
    mcspasswd="ServiceUserPassword"

/>
```

Encrypt the profile password by running the following command as root:

```
mccipher encrypt -c /usr/local/avamar/lib/mcclimcs.xml:service
```

Delete the existing /home/admin/.avamardata/var/mc/cli_data/prefs/mcclimcs.xml file and verify that the new profile works by running the following command:

Example 3 Add a new service account profile to the mcclimcs.xml file and encrypt the account password (continued)

mccli activity show --mcsprofile=service

Utilities and Configuration Files

GLOSSARY

Α

Avamar Administrator

A graphical management console software application that is used to remotely administer an Avamar system from a supported Windows or Linux client computer.

Avamar client A computer or workstation that runs Avamar software and accesses the Avamar server over a network connection. Avamar client software comprises a client agent and one or more plug-ins.

Avamar server

The server component of the Avamar client/server system. Avamar server is a faulttolerant, high-availability system that efficiently stores the backups from all protected clients. It also provides essential processes and services required for data restores, client access, and remote system administration. Avamar server runs as a distributed application across multiple networked storage nodes.

В

browse

The process of viewing data that is available for backup on a client computer or restore from the Avamar server.

 \mathbf{C}

checkpoint A server backup taken for the express purpose of assisting with disaster recovery of the Avamar server.

client A computer or workstation that runs Avamar software and accesses the Avamar server over a network connection. Avamar client software consists of a client agent and one or more plug-ins.

client agent

A platform-specific software process that runs on the client and communicates with the Management Console Server (MCS) and with any plug-ins installed on that client.

client registration

The process of establishing an identity with the Avamar server. When Avamar recognizes the client, it assigns a unique client ID (CID), which it passes back to the client during client activation.

See also registration

D

Data Domain system

Disk-based deduplication appliances and gateways that provide data protection and disaster recovery (DR) in the enterprise environment.

dataset

A policy that defines a set of files, directories, and file systems for each supported platform that are included or excluded in backups across a group of clients. A dataset is a persistent and reusable Avamar policy that can be named and attached to multiple groups.

domain

A feature in Avamar Administrator that is used to organize large numbers of clients into named areas of control and management.

G

group

A level of organization in Avamar Administrator for one or more Avamar clients. All clients in an Avamar group use the same group policies, which include the *dataset*, *schedule*, and *retention policy*.

group policy

The *dataset*, *schedule*, and *retention policy* for all clients in an Avamar group.

J

JRE Java Runtime Environment.

M

MCS

Management console server. The server subsystem that provides centralized administration (scheduling, monitoring, and management) for the Avamar server. The MCS also runs the server-side processes used by *Avamar Administrator*.

Ρ

plug-in

Avamar client software that recognizes a particular kind of data resident on that client.

plug-in options

Options that you specify during backup or restore to control backup or restore functionality.

policy

A set of rules for client backups that can be named and applied to multiple groups. Groups have dataset, schedule, and retention policies.

R

registration

The process of establishing an identity with the Avamar server. When Avamar recognizes the client, it assigns a unique client ID (CID), which it passes back to the client during *client activation*.

See also client registration

restore

An operation that retrieves one or more file systems, directories, files, or data objects from a backup and writes the data to a designated location.

retention

The time setting to automatically delete backups on an Avamar server. Retention can be set to permanent for backups that should not be deleted from an Avamar server. Retention is a persistent and reusable Avamar policy that can be named and attached to multiple groups.

roles

A setting in Avamar Administrator that controls which operations each user can perform in the Avamar server. Roles are assigned on a user-by-user basis. S

schedule

The ability to control the frequency and the start and end time each day for backups of clients in a group. A schedule is a persistent and reusable Avamar policy that can be named and attached to multiple groups.

Glossary