

Install Astra Control Center

Astra Control Center

Dave Bagwell, amitha August 04, 2021

This PDF was generated from https://docs.netapp.com/us-en/astra-control-center/get-started/install_acc.html on August 26, 2021. Always check docs.netapp.com for the latest.

Table of Contents

ln:	stall Astra Control Center	. 1
	Install Astra Control Center	. 1
	Log in to the Astra Control Center UI	12
	Troubleshoot the installation	12
	What's next.	12

Install Astra Control Center

To install Astra Control Center, do the following steps:

- Install Astra Control Center
- Log in to the Astra Control Center UI

Install Astra Control Center

To install Astra Control Center, download the installation bundle from the NetApp Support Site and perform a series a commands to install Astra Control Center Operator and Astra Control Center in your environment. You can use this procedure to install Astra Control Center in internet-connected or air-gapped environments.

What you'll need

- Before you begin installation, prepare your environment for Astra Control Center deployment.
- From your OpenShift cluster, ensure all cluster operators are in a healthy state (available is true):

```
oc get clusteroperators
```

From your OpenShift cluster, ensure all API services are in a healthy state (available is true):

```
oc get apiservices
```

About this task

The Astra Control Center installation process does the following:

- Installs the Astra components into the netapp-acc (or custom named) namespace.
- · Creates a default account.
- Establishes a default administrative user email address and default one-time password of ACC-<UUID_of_installation> for this instance of Astra Control Center. This user is assigned the Owner role in the system and is needed for first time login to the UI.
- · Helps you determine that all Astra Control Center pods are running.
- · Installs the Astra UI.



Podman commands can be used in place of Docker commands if you are using Red Hat's Podman repository.

Steps

- 1. Download the Astra Control Center bundle (astra-control-center-[version].tar.gz) from the NetApp Support Site.
- 2. Download the zip of Astra Control Center certificates and keys from NetApp Support Site.
- 3. (Optional) Use the following command to verify the signature of the bundle:

```
openssl dgst -sha256 -verify astra-control-center[version].pub
-signature <astra-control-center[version].sig astra-control-
center[version].tar.gz</pre>
```

4. Extract the images:

```
tar -vxzf astra-control-center-[version].tar.gz
```

5. Change to the Astra directory.

```
cd astra-control-center-[version]
```

- 6. Add the files in the Astra Control Center image directory to your local registry.
 - 1

See a sample script for the automatic loading of images below.

a. Log in to your Docker registry:

```
docker login [Docker_registry_path]
```

- b. Load the images into Docker.
- c. Tag the images.
- d. Push the images to your local registry.

```
export REGISTRY=[Docker_registry_path]
for astraImageFile in $(ls images/*.tar)
    # Load to local cache. And store the name of the loaded image trimming
the 'Loaded images: '
    do astraImage=$(docker load --input ${astraImageFile} | sed 's/Loaded
image(s): //')
    astraImage=$(echo ${astraImage} | sed 's!localhost/!!')
    # Tag with local image repo.
    docker tag ${astraImage} ${REGISTRY}/${astraImage}
    # Push to the local repo.
    docker push ${REGISTRY}/${astraImage}
done
```

- 7. (For registries with auth requirements only) If you use a registry that requires authentication, you need to do the following:
 - a. Create the netapp-acc-operator namespace:

kubectl create ns netapp-acc-operator

Response:

namespace/netapp-acc-operator created

b. Create a secret for the netapp-acc-operator namespace. Add Docker information and run the following command:

kubectl create secret docker-registry astra-registry-cred -n netappacc-operator --docker-server=[Docker_registry_path] --docker
-username=[username] --docker-password=[token]

Sample response:

secret/astra-registry-cred created

c. Create the netapp-acc (or custom named) namespace.

kubectl create ns [netapp-acc or custom]

Sample response:

namespace/netapp-acc created

d. Create a secret for the netapp-acc (or custom named) namespace. Add Docker information and run the following command:

kubectl create secret docker-registry astra-registry-cred -n [netappacc or custom] --docker-server=[Docker_registry_path] --docker
-username=[username] --docker-password=[token]

Response

secret/astra-registry-cred created

8. Edit the Astra Control Center operator deployment yaml (astra_control_center_operator_deploy.yaml) to refer to your local registry and secret.

```
vim astra_control_center_operator_deploy.yaml
```

a. If you use a registry that requires authentication, replace the default line of imagePullSecrets: [] with the following:

```
imagePullSecrets:
  - name: astra-registry-cred
```

- b. Change [Docker_registry_path] for the kube-rbac-prox image to the registry path where you pushed the images in a previous step.
- c. Change [Docker_registry_path] for the acc-operator-controller-manager image to the registry path where you pushed the images in a previous step.

```
apiVersion: apps/v1
kind: Deployment
metadata:
  labels:
    control-plane: controller-manager
  name: acc-operator-controller-manager
 namespace: netapp-acc-operator
spec:
 replicas: 1
  selector:
    matchLabels:
      control-plane: controller-manager
  template:
    metadata:
      labels:
        control-plane: controller-manager
    spec:
      containers:
      - args:
        - --secure-listen-address=0.0.0.0:8443
        - --upstream=http://127.0.0.1:8080/
        - --logtostderr=true
        - -v=10
        image: [Docker registry path]/kube-rbac-proxy:v0.5.0
        name: kube-rbac-proxy
        ports:
        - containerPort: 8443
         name: https
      - args:
        - --health-probe-bind-address=:8081
        - --metrics-bind-address=127.0.0.1:8080
        - --leader-elect
        command:
        - /manager
        env:
        - name: ACCOP LOG LEVEL
         value: "2"
        image: [Docker registry path]/acc-operator:[version x.y.z]
        imagePullPolicy: IfNotPresent
      imagePullSecrets: []
```

9. Edit the Astra Control Center custom resource (CR) file (astra control center min.yaml):

```
vim astra_control_center_min.yaml
```



If additional customizations are required for your environment, you can use astra_control_center.yaml as an alternative CR. astra_control_center_min.yaml is the default CR and is suitable for most installations.



Properties configured by the CR cannot be changed after initial Astra Control Center deployment.

- a. Change [Docker_registry_path] to the registry path where you pushed the images in the previous step.
- b. Change the accountName string to the name you want to associate with the account.
- c. Change the astraAddress string to the FQDN you want to use in your browser to access Astra. Do not use http://orhttps://in the address. Copy this FQDN for use in a later step.
- d. Change the email string to the default initial administrator address. Copy this email address for use in a later step.
- e. Change enrolled for autoSupport to false for sites without internet connectivity or retain true for connected sites.
- f. (Optional) Add a first name firstName and last name lastName of the user associated with the account. You can perform this step now or later within the UI.
- g. If you are not using a registry that requires authorization, delete the secret line.

```
apiVersion: astra.netapp.io/v1
kind: AstraControlCenter
metadata:
  name: astra
spec:
  accountName: "Example"
  astraVersion: "ASTRA VERSION"
  astraAddress: "astra.example.com"
  autoSupport:
    enrolled: true
  email: "[admin@example.com]"
  firstName: "SRE"
  lastName: "Admin"
  imageRegistry:
    name: "[Docker registry path]"
    secret: "astra-registry-cred"
```

10. Install the Astra Control Center operator:

```
kubectl apply -f astra_control_center_operator_deploy.yaml
```

Sample response:

```
namespace/netapp-acc-operator created
customresourcedefinition.apiextensions.k8s.io/astracontrolcenters.astra.
netapp.io created
role.rbac.authorization.k8s.io/acc-operator-leader-election-role created
clusterrole.rbac.authorization.k8s.io/acc-operator-manager-role created
clusterrole.rbac.authorization.k8s.io/acc-operator-metrics-reader
created
clusterrole.rbac.authorization.k8s.io/acc-operator-proxy-role created
rolebinding.rbac.authorization.k8s.io/acc-operator-leader-election-
rolebinding created
clusterrolebinding.rbac.authorization.k8s.io/acc-operator-manager-
rolebinding created
clusterrolebinding.rbac.authorization.k8s.io/acc-operator-proxy-
rolebinding created
configmap/acc-operator-manager-config created
service/acc-operator-controller-manager-metrics-service created
deployment.apps/acc-operator-controller-manager created
```

11. If you didn't already do so in a previous step, create the netapp-acc (or custom) namespace:

```
kubectl create ns [netapp-acc or custom]
```

Sample response:

```
namespace/netapp-acc created
```

12. Install Astra Control Center in the netapp-acc (or your custom) namespace:

```
kubectl apply -f astra_control_center_min.yaml -n [netapp-acc or custom]
```

Sample response:

```
astracontrolcenter.astra.netapp.io/astra created
```

13. Verify that all system components installed successfully.

```
kubectl get pods -n [netapp-acc or custom]
```

Each pod should have a status of Running. It may take several minutes before the system pods are deployed.

Sample response:

NAME	READY	STATUS	RESTARTS
AGE			
acc-helm-repo-5fdfff786f-gkv6z	1/1	Running	0
4m58s			
activity-649f869bf7-jn5gs	1/1	Running	0
3m14s			
asup-79846b5fdc-s9s97	1/1	Running	0
3m10s			
authentication-84c78f5cf4-qhx9t	1/1	Running	0
118s			
billing-9b8496787-v8rzv	1/1	Running	0
2m54s			
bucketservice-5fb876d9d5-wkfvz	1/1	Running	0
3m26s			
cloud-extension-f9f4f59c6-dz6s6	1/1	Running	0
3m			
cloud-insights-service-5676b8c6d4-6q7lv	1/1	Running	0
2m52s	- /-		
composite-compute-7dcc9c6d6c-lxdr6	1/1	Running	0
2m50s	1 /1		
composite-volume-74dbfd7577-cd42b	1/1	Running	0
3m2s	1 /1		
credentials-75dbf46f9d-5qm2b	1/1	Running	0
3m32s	1 /1		0
entitlement-6cf875cb48-gkvhp	1/1	Running	0
3m12s	1 /1	D	0
features-74fd97bb46-vss2n	1/1	Running	0
3m6s	1 /1	D	0
fluent-bit-ds-2g9jb 113s	1/1	Running	0
	1 /1	D	0
fluent-bit-ds-5tg5h 113s	1/1	Running	0
fluent-bit-ds-qfxb8	1/1	Running	0
113s	Ι/ Ι	Rumming	U
graphql-server-7769f98b86-p4qrv	1/1	Running	0
90s	1/1	Rullilling	O
identity-566c566cd5-ntfj6	1/1	Running	0
3m16s	т/ т	Nullililig	O
influxdb2-0	1/1	Running	0
4m43s	т/ т	Ruillizing	J
krakend-5cb8d56978-44q66	1/1	Running	0
93s	1 / 1	ramming	<u> </u>
license-66cbbc6f48-27kgf	1/1	Running	0
3m4s	1 / 1	ramming	Ų.
JIII J			

login-ui-584f7fd84b-dmdrp	1/1	Running	0
87s loki-0	1/1	Running	0
4m44s		3	
metrics-ingestion-service-6dcfddf45f-mhnvh 3m8s	1/1	Running	0
monitoring-operator-78d67b4d4-nxs6v 116s	2/2	Running	0
nats-0	1/1	Running	0
4m40s			
nats-1	1/1	Running	0
4m26s	1 /1	-	
nats-2 4m15s	1/1	Running	0
nautilus-9b664bc55-rn9t8	1/1	Running	0
2m56s		-	
openapi-dc5ddfb7d-6q8vh	1/1	Running	0
3m20s			
polaris-consul-consul-5tjs7 4m43s	1/1	Running	0
polaris-consul-consul-5wbnx	1/1	Running	0
4m43s	_, _		
polaris-consul-consul-bfv17	1/1	Running	0
4m43s			
polaris-consul-consul-server-0	1/1	Running	0
4m43s polaris-consul-consul-server-1	1/1	Running	0
4m43s	Ι/ Ι	Rumming	0
polaris-consul-consul-server-2	1/1	Running	0
4m43s			
polaris-mongodb-0	2/2	Running	0
4m49s	0.70	-	
polaris-mongodb-1 4m22s	2/2	Running	0
polaris-mongodb-arbiter-0	1/1	Running	0
4m49s	,	- 5	
polaris-ui-6648875998-75d98	1/1	Running	0
92s			
polaris-vault-0	1/1	Running	0
4m41s	1 /1	D	0
polaris-vault-1 4m41s	1/1	Running	0
polaris-vault-2	1/1	Running	0
4m41s	- / -	Tallilling	
storage-backend-metrics-69546f4fc8-m7lfj 3m22s	1/1	Running	0

storage-provider-5d46f755b-qfv89	1/1	Running	0
3m30s			
support-5dc579865c-z4pwq	1/1	Running	0
3m18s			
telegraf-ds-4452f	1/1	Running	0
113s			
telegraf-ds-gnqxl	1/1	Running	0
113s			
telegraf-ds-jhw74	1/1	Running	0
113s			
telegraf-rs-gg6m4	1/1	Running	0
113s			
telemetry-service-6dcc875f98-zft26	1/1	Running	0
3m24s			
tenancy-7f7f77f699-q716w	1/1	Running	0
3m28s			
traefik-769d846f9b-c9crt	1/1	Running	0
83s			
traefik-769d846f9b-19n4k	1/1	Running	0
67s			
trident-svc-8649c8bfc5-pdj79	1/1	Running	0
2m57s			
vault-controller-745879f98b-49c5v	1/1	Running	0
4m51s			

14. (Optional) To ensure the installation is completed, you can watch the acc-operator logs using the following command.

```
kubectl logs deploy/acc-operator-controller-manager -n netapp-acc-
operator -c manager -f
```

15. When all the pods are running, verify installation success by retrieving the AstraControlCenter instance installed by the ACC Operator.

```
kubectl get acc -o yaml -n netapp-acc
```

16. Check the status.deploymentState field in the response for the Deployed value. If deployment was unsuccessful, an error message appears instead.



You will use the uuid in the next step.

```
apiVersion: v1
items:
- apiVersion: astra.netapp.io/v1
  kind: AstraControlCenter
 metadata:
    creationTimestamp: "2021-07-28T21:36:49Z"
    finalizers:
    - astracontrolcenter.netapp.io/finalizer
   generation: 1
    name: astra
    namespace: netapp-acc
    resourceVersion: "27797604"
    selfLink: /apis/astra.netapp.io/v1/namespaces/netapp-
acc/astracontrolcenters/astra
    uid: 61cd8b65-047b-431a-ba35-510afcb845f1
  spec:
    accountName: Example
    astraAddress: astra.example.com
    astraResourcesScaler: "Off"
    astraVersion: 21.08.52
    autoSupport:
      enrolled: false
    email: admin@example.com
    firstName: SRE
    lastName: Admin
    imageRegistry:
      name: registry name/astra
  status:
    certManager: deploy
    deploymentState: Deployed
    observedGeneration: 1
    observedVersion: 21.08.52
    postInstall: Complete
    uuid: c49008a5-4ef1-4c5d-a53e-830daf994116
kind: List
metadata:
  resourceVersion: ""
  selfLink: ""
```

17. To get the one-time password you will use when you log in to Astra Control Center, copy the status.uuid value from the response in the previous step. The password is ACC- followed by the UUID value (ACC-[UUID] or, in this example, ACC-c49008a5-4ef1-4c5d-a53e-830daf994116).

Log in to the Astra Control Center UI

After installing ACC, you will change the password for the default administrator and log in to the ACC UI dashboard.

Steps

- 1. In a browser, enter the FQDN you used in the astraAddress in the astra control center min.yaml CR when you installed ACC.
- Accept the self-signed certificates when prompted.
 - 1

You can create a custom certificate after login.

3. At the Astra Control Center login page, enter the value you used for email in astra_control_center_min.yaml CR when you installed ACC, followed by the one-time password (ACC-[UUID]).



If you enter an incorrect password three times, the admin account will be locked for 15 minutes.

- 4. Select Login.
- 5. Change the password when prompted.



If this is your first login and you forget the password and no other administrative user accounts have yet been created, contact NetApp Support for password recovery assistance.

6. (Optional) Remove the existing self-signed TLS certificate and replace it with a custom TLS certificate signed by a Certificate Authority (CA).

Troubleshoot the installation

If any of the services are in Error status, you can inspect the logs. Look for API response codes in the 400 to 500 range. Those indicate the place where a failure happened.

Steps

1. To inspect the Astra Control Center operator logs, enter the following:

```
kubectl logs --follow -n netapp-acc-operator $(kubectl get pods -n
netapp-acc-operator -o name) -c manager
```

What's next

Complete the deployment by performing setup tasks.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.