User Guide for GASV and GASVPro (Version 2.0)

Contents

1	Intr	roduction	2
	1.1	Summary	2
	1.2	Requirements	2
	1.3	GASV Workflow	2
	1.4	GASV Algorithm	3
	1.5	Installation	3
2	Qui	ckstart Guide to GASV	4
	2.1	Using BAMToGASV to Preprocess BAM files	4
	2.2		5
	2.3	Useful GASV Examples	6
3	BA.	MToGASV	7
•	3.1		7
	3.2	Command Line Options	
	3.3	Output of BAMToGASV	9
	0.0		
4	$\mathbf{G}\mathbf{A}$	${f SV}$	10
	4.1	GASV Command Line Options	10
	4.2	Input File Formats	11
		4.2.1 Paired-Read Mapping (PR) File Format	11
		4.2.2 Batch File Format (*.in files)	12
	4.3	Structural Variation Predictions	12
		4.3.1 Structural Variant Types	12
		4.3.2 Standard Clusters File Format	14
		4.3.3 Additional Output Options	14
5	$\mathbf{G}\mathbf{A}$	SVPro	16
	5.1	GASVPro Input Parameters	16
	5.2	Running GASVPro	
	5.3	GASVPro Output	

1 Introduction

GASV is software to identify structural variants from paired-end mapping data.

If you use GASV in your research, please cite:

S. Sindi, E. Helman, A. Bashir, B.J. Raphael. A Geometric Approach for Classification and Comparison of Structural Variants. Joint: 17th Annual International Conference on Intelligent Systems in Molecular Biology and 8th Annual International European Conference on Computational Biology (ISMB/ECCB 09). Bioinformatics 2009 25(12):i222-i230.

This product includes software developed by the Solution Engineering, Inc. (http://www.seisw.com/).

Contact: Benjamin Raphael at gasv@cs.brown.edu

Version: 2.0

Version Date: May 30 2012

1.1 Summary

The GASV software utilizes a geometric algorithm to predict structural variation (SV) from a set of discordant mappings of paired-reads (PRs).

1.2 Requirements

Requires: Perl, Java 5 (or higher), *nix OS.

Tested with: Perl v5.10.0, Java 6, Linux 2.6.26

Building GASV from the source requires ant, available at: http://ant.apache.org/

1.3 GASV Workflow

The primary GASV workflow is an analysis pipeline for SV detection from a set of pairedend mappings (PEM) given in the form of a GASV

(a) Process BAM file of unique paired-end mappings (PEM)

(b) Identify structural variation (SVs) by clustering discordant fragments.

(c) Probabilistic algorithm, improves specificity of GASV predictions by incorporating read depth (RD) signals for SV prediction.

Figure 1: **GASV Workflow**

BAM file. In most workflows the BAM file is pre-processed for analysis with GASV using BAMTo-GASV (Figure 1(a)) followed by analysis with GASV (Figure 1(b)) to determine a set of potential SVs genome wide. Further downstream analysis of GASV predictions may be conducted with GASVPro, a probabilistic algorithm which integrates read-depth (RD) to improve specificity by eliminating false-positive predictions.

1.4 GASV Algorithm

The GASV algorithm reports structural variant events defined by clusters of discordantly mapped fragments and explicitly represents uncertainty variant endpoints. We briefly overview the approach used in GASV; for a more detailed discussion of the GASV algorithm, refer to Sindi et al. (2009).




Figure 2: GASV Algorithm of Structural Variation Detection from Paired-End Sequencing. (Top) Fragments (black arches) from a test genome are sequenced from both ends and the resulting paired reads are mapped to a reference genome. Fragments containing the breakpoint of a structural variant (black arches with arrows) have a discordant mapping (red). (Bottom) GASV represents the uncertainty in breakpoint location as a breakend polygon (black trapezoids). GASV clusters fragments by computing polygon intersections (shaded red trapezoid) which correspond to fragments supporting the same variant.

A discordant mapping indicates a structural variant in the test genome defined by a novel adjacency (a,b), where positions a and b are adjacent in the test genome, but not in the reference genome (see Figure 2). A single fragment alone does not uniquely specify the pair of breakends (a,b) defining the rearrangement, but rather defines uncertainty in the location of the breakends. Formally, if we assume that a discordant fragment corresponds to exactly one structural variant, then the mapped locations, x and y, of the fragment endpoints (without loss of generality we restrict x < y), and the breakends a and b satisfy

$$L_{\min} \le \operatorname{sign}(x)(a-x) + \operatorname{sign}(y)(b-y) \le L_{\max},$$

where $\operatorname{sign}(x)$ and $\operatorname{sign}(y)$ are 1 if the reads align to the positive strand and have convergent orientation and -1 otherwise. Here we assume convergent orientation is when reads have opposite orientation with the left read forward and the right read reversed as in the case for Illumina sequencing technology. (Other sequencing protocols will may have different notions of convergent orientation.) The inequality (1) defines a trapezoid in the plane; discordant fragments corresponding to the same structural variant

will have overlapping trapezoids and their intersection can be used to further refine the uncertainty in breakend location as in Figure 2. The final set of SV predictions from GASV corresponds to these polygonal intersections.

1.5 Installation

You may either download executable jar files from

http://code.google.com/p/gasv/downloads/

or build our code directly from the source.

Building GASV from the source requires ant, available at: http://ant.apache.org/. To install from the source check out a read-only working copy from

% svn checkout http://gasv.googlecode.com/svn/trunk/ gasv-read-only

and install from the command line with ant

% ant

During installation the java *class files are built into the build subdirectory. After installation the following executable jar files are created:

bin/GASV.jar
bin/BAMToGASV.jar

2 Quickstart Guide to GASV

This Quickstart Guide will demonstrate many features of GASV including determining the structural variants from paired-read sequences (PRs) whose mappings are encoded in a BAM file.

To demonstrate using BAMToGASV preprocessor in conjunction with GASV, we will use the file "Example.bam" available as a separate download from the GASV website:

http://code.google.com/p/gasv

More documentation is available for both GASV and BAMToGASV Preprocessor in sections below.

2.1 Using BAMToGASV to Preprocess BAM files

The following command creates GASV input files by considering paired-reads (PRs) from the BAM file "Example.bam" (this particular BAM file contains no library information and contains only reads from chr17, so no translocations):

% java -Xms512m -Xmx2048m -jar BAMToGASV.jar Example.bam

As we detail further below, there are many options available for BAMToGASV. For example, use a minimum quality of 30 and determine Lmin/Lmax by 3 standard deviations away from the mean, the command is

% java -Xms512m -Xmx2048m -jar BAMToGASV.jar Example.bam -MAPPING_QUALITY 30 -CUTOFF_LMINLMAX SD=3

If the BAM file contains multiple libraries, to process them as one set (rather than indvididually) the command is

```
% java -Xms512m -Xmx2048m -jar BAMToGASV.jar Example.bam -LIBRARY_SEPARATED all
```

Running the above command creates the following files:

Example.bam.info
Example.bam.gasv.in
Example.bam_all.deletion
Example.bam_all.divergent
Example.bam_all.insertion
Example.bam_all.inversion
Example.bam_all.translocation

Example.info contains information about the concordant fragment length distribution. Example.gasv.in is a batch file of all PR files (except insertions) for input to the GASV program. The rest of the files are PR files in the GASV input format, separated by variant type.

2.2 Run GASV to Compute Structural Variants

The following command will report inversion, deletion and divergent structural variants using the batch input file produced by BAMToGASV. Note the default behavior of GASV is to only report variants with at least 4 supporting fragments. In addition, if GASV.jar has not been added to the PATH, then a fully qualified pathname must be used.

```
% java -jar GASV.jar --batch Example.bam.gasv.in
```

Below is the contents of the *clusters file created, Example.bam.gasv.in.clusters:

```
#Cluster_ID: LeftChr: LeftBreakPoint:
                                         RightChr: RightBreakPoint:
                                                                     Num PRS: Localization: Type:
c99
            17
                     660077,660155
                                         17
                                                  660177,660255
                                                                     4
                                                                               39.8
                                                                                             D
c106
             17
                      685625,685815
                                         17
                                                  685996,686186
                                                                      4
                                                                               100.6
                                                                                             D
c4552
             17
                      34908617,34908798 17
                                                  34908870,34909051 5
                                                                               68.4
                                                                                             D
c5262
            17
                      40566182,40566317 17
                                                  40567335,40567462 4
                                                                               68.3
                                                                                             IR
c6367
             17
                      50617507,50617679 17
                                                   50617548,50617720
                                                                               87.8
                                                                                             D
```

The tab separated fields indicate that there are 5 predictions, 4 deletions and 1 inversion structural variant on chromosome 17. Examining the fourth line more carefully, cluster c5262 supports an inversion with left breakpoint occurs between positions 40566182, 40566316 and the right breakpoint between positions 40567335, 40567462.

In addition, the final columns tell us:

• 4 fragments support this SV (Num PRs = 4)

- The breakpoint localization is 68. The smaller the localization the more precisely the structural variant breakpoint is determined. Refer below and to Sindi, et al. (2009) for more discussion of localization.
- This variant is a reciprocal inversion (Type = IR) Among the 4 PRs at least one is in the ++ orientation (contains the left breakpoint) and one in the -- orientation (contains the right breakpoint).

2.3 Useful GASV Examples

1. --minClusterSize <val> Report only predictions with at least a minimum number of supporting fragments. (By default, this parameter is set to 4.) For increased sensitivity, users can lower the threshold. For example to obtain all predictions supported by at least 2 mappings:

```
% java -jar GASV.jar --minClusterSize 2 --batch Example.bam.gasv.in
```

- 2. --maximal In some cases a set of overlapping fragments may correspond to multiple breakpoints. The "--maximal" option will output all maximal breakpoint events.
- 3. --maxPairedEndsPerWin <val> The speed at which GASV runs corresponds to the number of fragments in a particular genomic region. Often some genomic regions (such as centromeres) will have a high density of discordant fragments. GASV's running time can be significantly increased by skipping such high density regions with the "--maxPairedEndsPerWin" option.
- 4. --output <val> As we detail below, there are three different output formats that can be specified for *clusters file. The reads format, "--output reads" will list the names of the reads in a cluster.

```
% java -jar GASV.jar --output reads --batch Example.bam.gasv.in
```

3 BAMToGASV

BAMToGASV generates GASV formatted input files from the SAM/BAM alignment format. SAM files are also accepted as input, but for clarity this manual will refer to BAM files only. Picard, a Java tool for processing BAM files, is packaged in the JAR file. Running BAMToGASV with no arguments produces basic usage information.

3.1 Requirements

BAMToGASV is currently designed to process BAM files where each read has at most one reported mapping.

Java 6 is required to run BAMtoGASV. We suggest initializing the Java heap size using the -Xms512m -Xmx2048m options, which requires running on a machine with more than 2G of memory. The BAM file must containing pairing information in the flags - if it does not, then Picard's fixmate function is called to make a new BAM file with pairing information and then the program exits.

3.2 Command Line Options

java -Xms512m -Xmx2048m -jar BAMToGASV.jar <BAMFile> [Options]

-LIBRARY_SEPARATED <String> (Default: sep)

Determines whether or not to consider multiple libraries separately

sep Produce a set of output files for each library.

all Produce a single set of output files for all libraries.

If no libary information is provided in the BAM file header, it will default to the 'all' setting. In the case where no library info is found or 'all' is passed as -LIBRARY_SEPARATED, the word "all" is used as the LIBRARY_ID in the output file names.

-OUTPUT_PREFIX <String> (Default: BAM filename)

The prefix for your output files.

-CUTOFF_LMINLMAX <String> (Default: PCT=99%)

Specifies lower and upper bounds on the fragment distribution.

PCT=X% Take the quantile on the top/bottom X percent.

SD=X Take the standard deviation above/below the mean.

EXACT=X,Y Set Lmin to X and Lmax to Y.

FILE=fname File of the form 'libname> <CUTOFF_LMINLMAX>' for using different cutoffs for individual libraries.

EXAMPLE:

library_id1 EXACT=123,456

library_id2 SD=3

library_id3 PCT=90%

In the case that the computed Lmax is smaller than twice the read length (which is the minimum fragment length), Lmax is reset to be twice the read length.

-USE_NUMBER_READS <Integer> (Default: 500000)

The number of fragments in the BAM file to use in computing Lmax and Lmin. Note that a relatively small number of fragments will be sufficient to get a good estimate of Lmin and Lmax. Depending on the size of the BAM file and running time constraints between 500,000 or 1,000,000 would be sufficient for most applications. If EXACT=X,Y is specified for the CUTOFF_LMINLMAX argument, no fragments will be used, and USE_NUMBER_READS argument is ignored.

-CHROMOSOME_NAMING_FILE <String> (Default: none)

File of the form '<ChrName>\t<Integer>' for specifying non-default chromosome namings. This is an optional parameter, you do not need this option if you are using the default chromosome naming references (a number, X, Y, chr+a number, chrX, and chrY). The second column contains unique integer IDs for each non-default chromosome name.

EXAMPLE:

Ca21chr1 1

Ca21chr2 2

Ca21-mtDNA 9

-PROPER_LENGTH <Integer> (Default: 10000)

Ignore PRs with separation larger than PROPER_LENGTH when calculating Lmin and Lmax. Extreme outliers (PRs with mapped length >10Mb) can cause huge standard deviation values which will produce large values for Lmax in with the SD option. If you use EXACT=X,Y or PCT=X% as CUTOFF_LMINLMAX, this option will not be considered.

-PLATFORM <String> (Default: Illumina)

Paired Illumina reads are sequenced from different strands of the fragment, while paired SOLiD reads are sequenced from the same strand of the fragment.

Illumina Reads are sequenced with an Illumina-like platform.

SOLiD Reads are sequenced with a SOLiD-like platform.

If the BAM header information reports a platform different from the -PLATFORM option, a warning is emitted but the program continues with the -PLATFORM option.

-WRITE_CONCORDANT <Boolean> (Default: False)

Writes a file of concordant PRs of the form '<chr> <start> <end>' to an OUTPUT_PREFIX.LIBRARY_ID.concordant file. WARNING - this may be a very large file. In a future release this will be a compressed binary file.

-WRITE_LOWQ <Boolean> (Default: False)

Writes a file of low-quality pairs (pairs where at least on read has quality below -MAPPING_QUALITY). WARNING - this may be a very large file.

-VALIDATION_STRINGENCY <String> (Default: silent)

Picard performs internal testing of BAM records as they are read into the BAMtoGASV program. The VALIDATION_STRINGENCY option determines how stringent this internal testing is.

silent Read SAM records without any validation.

lenient Read SAM records and emit a warning when a record is not formatted properly.

strict Read SAM records and die when a record is not formatted properly.

Picard's default setting is Strict; however, this assumes a very well-formatted BAM file from Illumina sequencing. If the output files are empty or not what you expect, we suggest running with VALIDATION_STRINGENCY set to lenient or strict to determine improperly-formatted BAM records.

3.3 Output of BAMToGASV

The output of BAMToGASV is a series of discordant PR files (see description below for GASV), an info file with summary statistics on the various libraries, and a batch input file for GASV.

Discordant fragments are grouped into output files according to the type of structural variant they indicate: deletion, insertion, inversion and translocation. Divergent fragments indicate a inter-chromosomal rearrangement that is not a deletion, inversion, or insertion.

OUTPUT_PREFIX(_LIBRARY_ID).deletion

OUTPUT_PREFIX(_LIBRARY_ID).divergent

OUTPUT_PREFIX(_LIBRARY_ID).insertion

OUTPUT_PREFIX(_LIBRARY_ID).inversion

OUTPUT_PREFIX(_LIBRARY_ID).translocation

OUTPUT_PREFIX.info

OUTPUT_PREFIX.gasv.in

In addition to a GASV formatted input file, GASV requires the minimum/maximum allowable fragment length (Lmin/Lmax) for concordant pairs. The values of Lmin and Lmax are automatically computed by the BAMToGASV. The calculated values of Lmin and Lmax are output to stdout and written to OUTPUT_PREFIX.info. In the Quickstart guide, the contents of Example.bam.info are:

LibraryName	Lmin	Lmax
all	153	246

The batch input file is written to OUTPUT_PREFIX.gasv.in. It is a GASV input format that is described below. All PR files except insertions are written to this file; GASV does not currently support insertions.

Note: The output produced from BAMToGASV.jar may slightly differ from output produced by earlier versions. Refer to RELEASE_NOTES.txt for more information.

4 GASV

GASV.jar runs the GASV algorithm on a set of discordant fragment mappings and reports a set of SV predictions. GASV.jar can be run directly on the output of BAMToGASV, using a "gasv.in" file:

```
java -jar GASV.jar <InputFile>.gasv.in
```

4.1 GASV Command Line Options

There are many options to GASV which will allow users to customize their own SV analysis pipeline. Running GASV.jar with no arguments produces basic usage information.

- --help Outputs detailed information on options to GASV.
- **--nohead** Output file will not have a header.
- **--outputdir** <dir> Directory into which output file will be placed.
- --verbose Prints extra info to standard output.
- --debug Run program in debug mode
- --fast Makes GASV run faster, but risks OutOfMemory errors
- --batch Input file(s) are GASV Batch Files (*.in files listing PR files), rather than the PR file(s) themselves. The --lmin and --lmax options are ignored if --batch is specified.
- --lmin <int>> Specify integer value to use for Lmin variable. Default value used otherwise. Ignored if the -batch option is specified.
- --lmax <int> Specify integer value to use for Lmax variable. Default value used otherwise. Ignored if the -batch option is specified.
- --minClusterSize <int> Only those clusters with at least <int> supporting PRs are reported.

- --maxClusterSize <int> Only those clusters with at most <int> supporting PRs are reported.
- --maxCliqueSize <int> For clusters with greater than<int> paired end sequences, calculation of maximal sub clusters is performed. Also only at most <int> PR names will be output per cluster (though numPR column will still reflect real number of PRs). Localization for such clusters is always -1.
- --maxPairedEndsPerWin <int> Does not apply if --fast otion used. If more than <int> paired end sequences are found in the current window, any extra paired end sequences are discarded.
- --maximal For each connected component without a common intersection (localization reported as -1), the maximal sub-clusters (each with a common intersection) will be reported.
- --numChrom <int> Specify number of chromosomes in the genome. Default is 24.
- --output <mode> Specify the GASV cluster output mode (see Output File Formats).
 - 1. standard: Default output mode
 - 2. reads: Default mode and names of supporting fragments
 - 3. regions: Detailed mode with region coordinates and fragment names
- --nonreciprocal Only PRs with exact matching orientations will be clustered together. E.g. +/+ and -/- inversion PRs will be segregated into separate clusters. (See Figures 3 and 4.)

4.2 Input File Formats

GASV accepts two types of input files; either a set of discordant mappings or a batch file listing multiple files of discordant mappings. If you are using a BAM file, these files will be automatically created with BAMToGASV.jar. Although, users may supply their own files.

4.2.1 Paired-Read Mapping (PR) File Format

Paired-read (PR) files are used for input of mapped paired-end sequences. Each line in the file specifies a paired-mapping. The 9 columns are tab-separated in the following format:

Name: A string with a unique PR identifier.

Left Chromosome: The chromosome where the left read mapped. (Acceptable formats: CHR1, chr1, 1.)

Left Mapped Start: The start coordinate in the reference of the left read mapping.

Left Mapped End: The end coordinate in the reference of the left read mapping.

Left End Orientation: The orientation of the left read. (Acceptable formats: include +/-, Plus/Minus)

Right Chromosome: Chromosome where the right read mapped.

Right Mapped Start: The start coordinate in the reference of the right read mapping.

Right Mapped End: The end coordinate in the reference of the right read mapping.

Right End Orientation: The orientation of the right read.

IMPORTANT PRE-PROCESSING STEP

PR files must be in sorted order prior to running GASV. If your PR files were created with BAMToGASV.jar they will already be sorted. Otherwise before running GASV you should run the sorting script:

Example: ./scripts/sortPR.bash PRFileToSort

Note: Since mapped start and end are in terms of the reference sequence, Start < End. (See Table 1 for example.)

```
PRA
          146590306
                      146591106
      1
                                     1
                                          146630713
                                                      146631513
PRB
      2
          46590283
                      46591083
                                     1
                                          146630714
                                                      146631514
PRC
      2
                      46591083
          46590283
                                     1
                                          156630714
                                                      156631514
PRD
          146586311
                      146587111
                                     10
                                          146633908
                                  +
                                                      146634708
```

Table 1: Example PR file format

4.2.2 Batch File Format (*.in files)

The GASV Batch input files provide a list of the PR file(s) to be processed. As mentioned above, each of the PR files must be sorted by chromosome and genomic coordinates. The BAMToGASV program does this automatically. If your data comes from elsewhere, the script ./scripts/sortPR.bash should be used to sort files prior to running GASV.

For PR files, each line gives the name of a PR file, the word "PR" to indicate the file type, and the minimum (Lmin) and maximum (Lmax) fragment length for paired-read mappings in the file. Columns are tab-separated in the following format:

FILE PR Lmin Lmax

4.3 Structural Variation Predictions

GASV outputs a clusters file named <InputFile>.clusters that lists all SV predictions with supporting information. There are three possible output formats for clusters files (detailed below). We first describe the different structural variant types reported by GASV, and provide illustrative figures for translocations (Figure 3) and inversions (Figure 4).

4.3.1 Structural Variant Types

GASV Structural Variant Types

 \mathbf{D} = Deletion

I = Inversion (see Figure 4)

IR = Reciprocal Inversion(both ++ and --)

I+ = Inversion (++ side only)

I- = Inversion (-- side only)

V = Divergent

 \mathbf{DV} = Combination of divergent and deletion discordant PRs.

T = Translocation; (see below and Figure 3)

TR = Reciprocal Translocation

TN = Nonreciprocal




Figure 3: GASV Algorithm Translocation Definition.




Figure 4: GASV Algorithm Inversion Definition.

The GASV algorithm distinguishes between several types of translocations based on the orientations of the respective chromosomes at the join (Figure 3); opposite (-) or same (+); and which resulting chromosome in the test genome was observed; type 1 or type 2. In the top panel of Figure 3, we illustrate the break and join event creating the translocation. While in the bottom panel, we show the resulting chromosomes present in the test genome, from which segments were sampled. As default mode, GASV will attempt to merge predictions from both type 1

and type 2 fragments to identify reciprocal translocation events (TR+ or TR-). If the --noreciprocal flag has been set, clusters from type 1 and type 2 fragments will always be reported separately (TN-1,

TN-2, TN+1, TN+2). A similar criteria applies to inversion structural variants (see Figure 4).

4.3.2 Standard Clusters File Format

Columns are tab-separated in the following format:

#Cluster_ID: Unique text identifier for the cluster c<cluster_number>. In --maximal mode, the sub-clusters are named as in: c[MajorClusterNumber].[MinorSubclusterNumber]

LeftChr: Chromosome containing the left breakpoint.

LeftBreakPoint: Interval containing the left breakpoint.

RightChr: Chromosome containing the right breakpoint. (Note that except for translocations LeftChr = RightChr).

RightBreakPoint: Interval containing the right breakpoint.

Num PRS: Number of PRs that support this variant.

Localization: Square root of the breakpoint region (polygon of intersection). The smaller the localization, the more precisely the breakpoint can be determined. See below for more information on localization.

Type: The type of structural variant indicated (See Section 4.3.1).

Example Clusters File:

```
#Cluster_ID: LeftChr: LeftBreakPoint: RightChr: RightBreakPoint: Num PRS: Localization: Type: c521 17 40566182,40566330 17 40567335,40567463 4 86.4 IR
```

Table 2: GASV Default Clusters Format

Note: If the localization is equal to -1, this means that while a set of PRs overlap, there is not a single structural variant that can explain the data. Running GASV with the "--maximal" flag will output all maximal structural variant predictions from such a cluster.

For examples and more information on maximality, and localization refer to Sindi, et al. (2009).

4.3.3 Additional Output Options

GASV provides two additional formatting options for the clusters file. These options are accessible by using the --output <val> option.

reads: The same as "standard" but has an additional column with a comma separated list of the names of names of PRs in each cluster.

regions: Highly detailed output that specifying the coordinates of the breakpoint polygon itself. The tab separated columns are:

#Cluster_ID:

Num PRS:

Localization:

Type:

List of PRS:

LeftChr:

RightChr:

Boundary Points:

The boundary points are given in the form: $x_1, y_1, x_2, y_2, ...$ where the points (x_i, y_i) correspond to the boundary of the breakpoint polygon.

Note: The output produced from GASV.jar may differ from output produced by earlier versions of GASV. Refer to RELEASE_NOTES.txt for more information.

5 GASVPro

GASVPro is a probabilistic version of our original GASV algorithm. GASVPro combines read depth information along with discordant paired-read mappings into a single probabilistic model. When multiple alignments of a read are given, GASVPro utilizes a Markov Chain Monte Carlo procedure to sample over the space of possible alignments.

5.1 GASVPro Input Parameters

Because GASVPro was designed to be run after BAMtoGASV and GASV, the input files to GASVPro will appear familiar to those who have experience with the GASV pipeline. There are also a number of probabilistic and statistical parameters that GASVPro requires.

Input Files

- Clusters File: must be in GASV Default Clusters Format (see section 4.3.2). **NOTE:** The —output regions parameter must be passed to GASV to produce a clusters file of the correct format.
- Concordant File: must be in BAMtoGASV default output format (<chr> <start> <end>).

 The BAMtoGASV preprocessor produces these files with the -WRITE_CONCORDANT option set to True. See section 3.2 for details. This file must be sorted numerically by start coordinate.
- Uniqueness Files: must provide a directory in which uniqueness track files (of format <start> <end> <unique>) are named chr1...chrN. These files also must be sorted numerically by start coordinate.

Numerical Parameters

- Average Fragment Length [Lavg] & Average Read Length [ReadLen]: follow from sequencing libraries. In the event of multiple libraries, use the average over all datasets.
- Lambda & Perr: parameters for probabilistic model, see manuscript.
- Minimum Fragment Size Limit: this value is the smallest variant that GASVPro will use concordant coverage on.
- **Tolerance**: Tolerance is used to remove regions that have abnormally high concordant coverage and, thus, can be eliminated from consideration as a structural variant. A tolerance of t will eliminate from further consideration as a potential structural variant a prediction with N concordant fragments provided $P(\geq N \mid \text{no variant}) > t$.
- Max Chromosome Number: this is the highest numerical value label of all the chromosomes in the Clusters File.
- Max Uniqueness Value: this parameter is the value assigned to the most mappable regions in the uniqueness files.
- Minimum Scaled Uniqueness: this parameter is the minimum value to which GASVPro will scale the uniqueness values for each variant. **NOTE:** When this parameter is set to 1, all regions will have the same uniqueness value.
- **Verbose**: specifying Y will print information for each cluster processed.

5.2 Running GASVPro

There are two ways to run GASVPro: via command-line arguments or via a parameters file. We have provided a parameters file for running GASVPro, and highly recommend its use for convenience and to ensure input accuracy. The parameters file also allows for clean record-keeping and can be annotated.

```
# A Sample GASVPro parameters file
# Annotation can appear on any line beginning with a hash mark (#).
clusterFile: <ClusterFile>
ConcordantFile: <ConcordanceFile>
UNIQUEFile: <UniquenessFile/Directory>
Lavg: <value>
ReadLen: <value>
Lambda: <value>
Perr: <value>
Limit: <value>
Tolerance: <value>
MaxChrNumber: <value>
MaxUniqueValue: <value>
MinScaledUniqueness: <value>
Verbose: Y
```

Figure 5: A Sample GASVPro Parameters File

Using a parameters file allows the user to run GASVPro with the following command:

```
% ./GASVPro {ParametersFile}
```

5.3 GASVPro Output

After successful completion GASVPro will output two files, a .clusters file and a .coverage file. Input parameters relevant to subsequent steps in the GASV pipeline will also be included in the filenames. The .clusters file contains the variance probabilities that GASVPro calculated. Here is an example GASVPro output, contained in the .clusters file:

Table 3: An Example GASVPro Output Cluster

The field c1_-650.01_-297.342 has the cluster name 'c1' appended with the likelihood c1 is a variant (-650.01) and the likelihood that c1 is not a variant (-297.342). The rest of the information in the .clusters file is carried over from the input file.