Euler's formula

$$e^{j\theta} = \cos(\theta) + j\sin(\theta)$$

 $e^{-j\theta} = \cos(\theta) - j\sin(\theta)$

Chapter 1

1.2.2 Bounded signals

A continuous-time signal x(t) is bounded if there **sinc** $(\frac{t}{T})$: exists an M such that $0 < M < \infty$ and $\forall t | x(t) | \leq M$ (has an upper and lower range

1.2.3 Absolutely integrable signals

A continuous-time signal x(t) is absolutely inte- $\int |x(t)|dt < \infty$

1.2.4 Periodc and aperiodic signals

Periodic: there is a non-zero positive value. T. satisfying $x(t) = x(t+T) \ \forall t$

Aperiodic: not periodic

1.2.6 Energy and Power Signals **Energy signals**

$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt$$
 (1.3a)

$$x(t)$$
 is an energy signal $\iff 0 < E < \infty$

Power signals


$$P = \lim_{\tau \to \infty} \frac{1}{2\tau} \int_{-\pi}^{\tau} |x(t)|^2 dt \qquad (1.4a)$$

x(t) is a power signal $\iff 0 < P < \infty$ (1.4b)


If x(t) is a periodic signal, average power may be computed by

$$\frac{1}{T} \int_0^T \left| x(t) \right|^2 dt$$


- Energy signals have 0 average power, bc E = finite implies P = 0
- · Power signals have infinite total energy, bc P = finite implies $E = \infty$
- All bounded periodic signals are power signals $\mathbf{u}(\mathbf{t})$:




sgn(t):




 $\mathbf{rect}(\frac{t}{T})$:




 $\operatorname{tri}(\frac{t}{T})$:










(1.3b)
$$e^{-\alpha|t|}$$
:



Sinusoidal signals

It signals
$$x(t) = \mu \cos(\omega_0 t + \phi)$$
 $= \mu \cos(2\pi f_0 t + \phi)$ $= \mu \cos(\frac{2\pi t}{T} + \phi)$ $T_0 = \frac{2\pi}{\omega_0} = \frac{1}{f_0}$

Chapter 2

2.1 Time-domain Operations

2.1.1 Time-Scaling

 $x(\alpha t)$: Scale x-axis by a factor of $\frac{1}{\alpha}$ x(-t): Reflect about x-axis

2.1.2 Time-Shifting

 $\beta > 0$: Delaying x(t) by β units of time (translate right along x-axis)

 $\beta > 0$: Advancing x(t) by β units of time (translate left along x-axis)

2.1.5 Convolution of 2 Signals

$$x(t) * y(t) = \int_{-\infty}^{\infty} x(\alpha)y(t-\alpha) d\alpha$$

Properties of convolutions

- 1. Commutative: f * q = q * f
- 2. Associative: f * (q * h) = (f * q) * h
- 3. Distributive: f * (g + h) = (f * g) + (f * h)

2.2 Dirac- δ function

$$\delta(t) = \begin{cases} \infty; & t = 0 \\ 0; & t \neq 0 \end{cases}$$

- 1. Symmetry: $\delta(t) = \delta(-t)$
- 2. Sampling:

$$x(t)\delta(t-\lambda) = x(\lambda)\delta(t-\lambda) \tag{2.4}$$

$$\int_{-\infty}^{\infty} x(t)\delta(t-\lambda)dt$$

$$= x(\lambda)\int_{-\infty}^{\infty} \delta(t-\lambda)dt = x(\lambda)$$
 (2.5)

$$x(t) * \delta(t - \lambda)$$

$$= \int_{-\infty}^{\infty} x(\zeta)\delta(t - \zeta - \lambda)d\zeta$$

$$= \int_{-\infty}^{\infty} x(\zeta)\delta(\zeta - (t - \lambda))d\zeta = x(t - \lambda)$$

2.2.1 Dirac- δ Comb function

$$\sum_{n=-\infty}^{\infty} \delta(t - nT)$$

$$= \ldots + \delta(t+T) + \delta(t) + \delta(t-T) + \ldots$$

Convolution with Dirac- δ Comb function $x_p(t) = x(t) * \sum \delta(t - nT)$

$$= \sum x(t - nT)$$

x(t) is known as the generating function.

Multiplication with the Dirac- δ Comb func- Spectrum of exponentially decaying pulse tion

Used for sampling

$$x_s(t) = x(t) \times \sum_n \delta(t - nT)$$

$$= \sum_n x(t) \times \delta(t - nT)$$

$$= \sum_n x(nT)\delta(t - nT)$$

Chapter 3

3.2 Spectrum of a Sinusoid

Spectrum of a Complex Exponential Signal $\tilde{x}(t) = \mu e^{j(2\pi f_0 t + \phi)} = \mu e^{j\phi} \times e^{j2\pi f_0 t}$

where μ : magnitude spectrum, ϕ : phase spectrum, f_0 : frequency

Spectrum of a Cosine Signal

$$\mu\cos(2\pi f_0 t + \phi)$$

$$= \frac{\mu}{2} e^{j\phi} e^{j2\pi f_0 t} + \frac{\mu}{2} e^{j(-\phi)} e^{j2\pi(-f_0)t}$$

$$\mu \sin(2\pi f_0 t + \phi) = \frac{\mu}{2} e^{j(\phi - 0.5\pi)} e^{j2\pi f_0 t} + \frac{\mu}{2} e^{j(-\phi + 0.5\pi)} e^{j2\pi(-f_0)t}$$

Complex exponential Fourier Series

$$x_p(t) = \sum_{k=-\infty}^{\infty} c_k e^{j2\pi kt/T_p}$$

$$=\sum_{k=-\infty}^{\infty}c_ke^{j2\pi kf_pt} \qquad (3.1a)$$

$$c_{k} = \frac{1}{T_{p}} \int_{t_{0}}^{t_{0} + T_{p}} x_{p}(t) e^{-j2\pi kt/T_{p}} dt, k \in \mathbb{Z}$$
(3.1b)

Properties:

(2.3) Trigonometric Fourier Series

$$x_p(t) = a_0 + 2 \sum_{k=1}^{\infty} [a_k \cos(2\pi kt/T_p)]$$

$$+b_k\sin(2\pi kt/T_p)]$$

$$\int_{-\infty}^{\infty} x(t)\delta(t-\lambda)dt + b_k \sin(2\pi kt/T_p) dt + b_k \sin(2\pi kt/T_p)$$

Chapter 4

Dirichlet Conditions

Conditions for existence of Fourier Transform:

- 1. x(t) has only a finite number of maxima and minima in any finite time interval
- 2. x(t) has only a finite number of discontinu- Multiplication in the Time Domain / Convoities in any finite time interval
- 3. x(t) is absolutely integrable

3 is weak Dirichlet condition: satisfied by most energy signals, violated by all power signals.

4.1 Fourier Transform

Forward Fourier Transform

$$X(f) = \int_{-\infty}^{\infty} x(t)e^{-j2\pi ft}dt$$
 (4.1a)

Inverse Fourier Transform
$$x(t) = \int_{-\infty}^{\infty} X(f)e^{j2\pi ft}df \qquad (4.1b)$$

$x(t) = Ae^{-\alpha t}u(t)$

$$= \begin{cases} Ae^{-\alpha t}; & t > 0\\ 0; & t < 0 \end{cases}$$

Assume
$$\alpha > 0$$

$$X(f) = \frac{A}{\alpha + j2\pi f}$$

4.2 Properties of Fourier Transform

- $X(f) = \Im\{x(t)\}$ denotes the Fourier transform of x(t)
- $x(t) = \Im^{-1}\{X(t)\}\$ denotes the inverse Fourier transform of X(f)
- $x(t) \rightleftharpoons X(f)$ denotes a Fourier transform pair with the time-domain on the LHS and frequency-domain on the RHS.

Linearity

$$\begin{array}{l} \text{If } x_1(t)\rightleftarrows X_1(f) \text{ and } x_2(t)\rightleftarrows X_2(f) \text{, then} \\ \alpha x_1(t)+\beta x_2(t)\rightleftarrows \alpha X_1(f)+\beta X_2(f) \end{array} \tag{4.2}$$

Time Scaling

$$x(\beta t) \rightleftharpoons \frac{1}{|\beta|} X\left(\frac{f}{\beta}\right)$$
 (4.3)

Duality

$$X(t) \rightleftarrows x(-f)$$
 (4.4)
or
 $X(-t) \rightleftarrows x(f)$

Time Shifting

$$x(t - t_0) \rightleftharpoons X(f)e^{-j2\pi f t_0}$$

$$x(t + t_0) \rightleftharpoons X(f)e^{j2\pi f t_0}$$

$$(4.5)$$

Frequency Shifting (Modulation)

$$x(t)e^{j2\pi f_0 t} \rightleftharpoons X(f - f_0)$$

$$x(t)e^{-j2\pi f_0 t} \rightleftharpoons X(f + f_0)$$

$$(4.6)$$

Differentiation in the Time Domain

$$\frac{d}{dt}x(t) \rightleftharpoons j2\pi f \cdot X(f) \tag{4.7}$$

Integration in the Time Domain

$$\int_{-\infty}^{t} x(\tau) \ d\tau \rightleftarrows \frac{1}{j2\pi f} X(f) + \frac{1}{2} X(0) \delta(f) \tag{4.8}$$

Convolution in the Time Domain / Multipli- $^{(3.2)}$ cation in the Frequency Domain

$$x_1(t) * x_2(t)$$

$$= \int_{-\infty}^{\infty} x_1(\alpha) x_2(t-\alpha) \ d\alpha \rightleftharpoons X_1(f) X_2(f)$$
(4.9a)

lution in the Frequency Domain

$$x_1(t)x_2(t) \rightleftharpoons \int_{-\infty}^{\infty} X_1(\alpha)X_2(f-\alpha) d\alpha$$
$$= X_1(f) * X_2(f)$$
(4.9b)

4.3 Spectral properties of a REAL signal

- If x(t) is **REAL** $(x^*(t) = x(t))$, then
 - X(f) is conjugate symmetric $(X^*(f))$
- |X(f)| is even (|X(f)| = |X(-f)|)
- $\angle X(f)$ is odd $(\angle X(f) = -\angle X(-f))$
- If x(t) is **REAL** and **EVEN** ($x^*(t) = x(t) \land$ x(-t) = x(t), then
- X(f) is real $(X^* f = X(f))$
- X(f) is even (X(-f) = X(f))
- If x(t) is **REAL** and **ODD** $(x^*(t) = x(t) \land$ x(-t) = -x(t), then
- X(f) is imaginary $(X^*(f) = -X(f))$
- X(f) is odd (X(-f) = -X(f))


The above can apply to Fourier series coefficients of periodic signals too:


- $x_p(t)$ is **REAL**
- c_k is conjugate symmetric $(c_k^* = c_{-k})$
- $|c_k|$ has even symmetry $(|c_k| = |c_{-k}|)$
- $\angle c_k$ has odd symmetry $(\angle c_k = -\angle c_{-k})$
- $x_n(t)$ is **REAL** and **EVEN**
- c_k is real $(c_k^* = c_k)$
- c_k is even $(c_k = c_{-k})$
- x_n(t) is **REAL** and **ODD** - c_k is imaginary $(c_k^* = -c_k)$
- $-c_k$ is odd $(c_k = -c_{-k})$

4.4 Spectrum of Signals that are not Absolutely Integrable

$$\Im\{K\delta(t)\} = \int_{-\infty}^{\infty} K\delta(t)e^{-j2\pi ft}dt = K$$
(4.13)

By duality,
$$\Im\{K\} = K\delta(f)$$





4.4.1 Spectrm of Unit Step and Signum function


$$\Im\{u(t)\} = \frac{1}{j2\pi f} + \frac{1}{2}\delta(f)$$
$$\Im\{\operatorname{Sgn}(t)\} = \frac{1}{j\pi f}$$

4.4.2 Continuous-Frequency Spectrum of Periodic Signals

The following make use of the fact that

$$\Im\{k\} = K\delta(f) \tag{4.14}$$

$$x_{dc}(t) = K$$
$$X_{dc}(f) = \Im\{k\} = K\Im\{1\} = K\delta(f)$$



Complex Exponential

$$\bar{x}(t) = Ke^{j2\pi f_0 t}$$


$$\tilde{X}(f) = \Im\{Ke^{j2\pi f_0 t}\} = K\delta(f - f_0)$$



Cosine


$$\Im\{K\cos(2\pi f_0 t)\}\$$


$$=\frac{K}{2}\delta(f-f_0) + \frac{K}{2}\delta(f+f_0)$$



Sine

$$\begin{cases} K\sin(2\pi f_0t) \} \\ = \frac{K}{j2}\delta(f-f_0) - \frac{K}{j2}\delta(f+f_0) \\ = \frac{K}{j2}\delta(f-f_0) - \frac{K}{j2}\delta(f-f_0) \\ + \frac{K}{2}\delta(f-f_0) + \frac{K}{2}\delta(f-f_0) \\ + \frac{K}{2}\delta(f+f_0) \end{cases}$$
 Total energy of a signal $x(t)$ is defined as
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt \text{ (Joules)}$$
 (5.1)
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt = \int_{-\infty}^{\infty} |x(f)|^2 df,$$
 (5.2)
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt = \int_{-\infty}^{\infty} |x(f)|^2 df,$$
 (5.2)
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt = \int_{-\infty}^{\infty} |x(t)|^2 df,$$
 (5.2)
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt = \int_{-\infty}^{\infty} |x(t)|^2 df,$$
 (5.2)
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt = \int_{-\infty}^{\infty} |x(t)|^2 df,$$
 (5.2)
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt = \int_{-\infty}^{\infty} |x(t)|^2 df,$$
 (5.2)
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt = \int_{-\infty}^{\infty} |x(t)|^2 dt,$$
 (5.2)
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt = \int_{-\infty}^{\infty} |x(t)|^2 dt,$$
 (5.2)
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt = \int_{-\infty}^{\infty} |x(t)|^2 dt.$$
 (5.2)
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt.$$
 (5.2)
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt.$$
 where
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt.$$
 (5.2)
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt.$$
 (5.2)
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt.$$






Arbitrary periodic signals

Let $x_n(t)$ be a periodic signal with period T_n and fundamental frequency f_n


amental frequency
$$f_p$$

$$X_p(f) = \sum_{k=-\infty}^{\infty} c_k \delta(f - kf_p) \qquad (4.16)$$


$$= \int_{-\infty}^{\infty} \lim_{W \to \infty} \frac{1}{2W} |X_W(f)|^2 df$$
Power Spectral Density



4.4.2.1 Spectrum of Dirac- δ Comb function









Chapter 5

5.1 Energy Spectral Density (ESD)

Total energy of a signal x(t) is defined as

From Energy of a signal
$$x(t)$$
 is defined as
$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt \text{ (Joules)} \tag{5.1}$$
 Rayleigh Energy Theorem

$$E = \int_{-\infty}^{\infty} |x(t)|^2 dt = \int_{-\infty}^{\infty} |X(f)|^2 df, \quad (5.2)$$
 where $X(f) = \Im\{x(t)\}$ is the spectrum of the ignal.

Energy Spectral Density

$$E_x(f) = |X(f)|^2$$
 Joules Hz⁻¹

Properties of $E_x(f)$

1. $E_x(f)$ is a real function of f

2. $E_x(f) > 0 \quad \forall f$

3. $E_x(f)$ is an even function of f if x(t) is real. increased from 0 Hz.

5.2 Power Spectral Density (PSD)

In the time-domain, the average power of a signal x(t) is defined as

$$x(t)$$
 is defined as
$$P = \lim_{\tau \to \infty} \frac{1}{2\tau} \int_{-\tau}^{\tau} |x(t)|^2 dt \qquad (5.4)$$
 Windowed version of $x(t)$:

$$x_W(t) = x(t)\operatorname{rect}\left(\frac{t}{2W}\right)$$
 (5.5)

Parseval Power Theorem
$$P = \lim_{W \to \infty} \frac{1}{2W} \int_{-W}^{W} |x(t)|^2 dt$$

$$P_x(f) = \lim_{W \to \infty} \frac{1}{2W} |X_W(f)|^2 \text{ Watts Hz}^{-1}$$
(5.10)

Properties of $P_x(f)$

1. $P_x(f)$ is a real function of f

2. $P_x(f) \geq 0 \quad \forall f$

3. $P_x(f)$ is an even function of f if x(t) is real.

5.2.1 PSD of Periodic Signals

From chapter 4 equation 4.16:

$$X_p(f) = \sum_{k=-\infty}^{\infty} c_k \delta(f - kf_p)$$

PSD of $x_n(t)$

$$P_x(f) = \sum_{k=-\infty}^{\infty} |c_k|^2 \delta(f - kf_p) \qquad (5.12)$$

Average power of $x_n(t)$

$$P = \int_{-\infty}^{\infty} P_x(f)df = \sum_{k=-\infty}^{\infty} |c_k|^2$$
 (5.13)


5.3.1 Bandlimited Signals

Lowpass signal

A signal x(t) is said to be a bandlimited lowpass signal if its magnitude spectrum is concentrated around 0 Hz, and at the same time satisfies

$$|X(f)| = 0; |f| > B$$
 (5.14)


where B is defined as the bandwidth of the signal.



Bandpass signal


A signal x(t) is said to be a bandlimited bandpass signal if its magnitude spectrum is concentrated around a non-zero center frequency f_c , and at (5.1) the same time satisfies

 $|X(f)| = 0; \quad ||f| - f_c| > B/2$ (5.15) where B is defined as the bandwidth of the signal



5.3.2 Signals with Unrestricted Band (5.3) **5.3.2.1 3dB Bandwidth**

Lowpass signal: The frequency where $|X(f)| = |X(0)|/\sqrt{2}$ first occurs (or where $|X(f)|^2 = |X(0)|^2/2$ first occurs) when f is




Bandpass signal:




5.3.2.2 1st-null Bandwidth

Lowpass signal: The frequency at which |X(f)| = 0 first occurs when f is increased from




Bandpass signal:




5.3.2.3 M% Energy Containment Bandwidth A system is BIBO stable (bounded-input/bounded-

Smallest bandwidth that contains at least M% of output) if for every bounded input x(t) where (5.12) the total signal energy $E = \int_{-\infty}^{\infty} E_x(f) df$



Bandpass:




5.3.2.4 M% Power Containment Bandwidth

The smallest bandwidth that contains at least M% of the average signal power. For a periodic signal, the aerage power is given by

$$P = \int_{-\infty}^{\infty} P_x(f) df = \sum_{k=-\infty}^{\infty} |c_k|^2$$

where $f_p(Hz)$ is the fundamental frequency and c_k 's are the Fourier series coefficients.



where K is the smallest positive integer that sat-

$$\sum_{k=-k}^{K} |c_k|^2 \ge \frac{M}{100} \times P$$

Chapter 6

6.1 Systems

- A system is a mathematical model of a physical process that relates the input (or excitation) signal to the output (or response) signal.
- With an input x(t) and an output y(t), the system may be viewed as a transformation (or mapping) of x(t) into y(t), mathematically expressed as $y(t) = \mathbf{T}[x(t)]$

6.2 Classification of Systems

6.2.1 Systems with Memory and Without Memory

A system is said to be memoryless (or static) if its output at a given time is dependent on only the input at that time.

Otherwise, the system is said to have memory (or to be dynamic).

6.2.2 Causal and Noncausal Systems

A system is said to be causal (or non-anticipative) if its output, y(t), at the present time depends on only the present and/or past values of its input. x(t).

not possible for a causal system to produce an output before an input is applied. $\therefore \forall t <$ $0 \ y(t) = 0.$

6.2.3 Stable and Unstable Systems

$$\forall t \ |x(t)| \le k \tag{6.2}$$

(6.3)

the system produces a bounded output y(t) where

$$\forall t \ |y(t)| \leq L$$
 in which K and L are positive constants.

6.2.4 Linear and Nonlinear Systems

A linear system is one that satisfies the following

two conditions:

$$\mathbf{T}[x_1(t) + x_2(t)] = \mathbf{T}[x_1(t)] + \mathbf{T}[x_2(t)]$$

$$= y_1(t) + y_2(t)$$
(6.4)

$$\mathbf{T}[\alpha x(t)] = \alpha \mathbf{T}[x(t)] = \alpha y(t) \qquad (6.5)$$

(6.4) and (6.5) can be combined into: $\mathbf{T}[\alpha_1 x_1(t) + \alpha_2 x_2(t)]$

$$\mathbf{T}[\alpha_1 x_1(t) + \alpha_2 x_2(t)]$$

$$= \alpha_1 \mathbf{T}[x_1(t)] + \alpha_2 \mathbf{T}[x_2(t)] \qquad (6.6)$$

$$= \alpha_1 y_1(t) + \alpha_2 y_2(t)$$

(6.6) is known as the superposition property. Important property of linear systems:

$$x(t) = 0 \implies y(t) = 0$$

6.2.5 Time-Invariant and Time-Varying Sys-

A system is time-invariant if a time shift (delay or advance) in the input signal, x(t), causes the same time shift in the output signal, y(t).

$$\mathbf{T}[x(t-\tau)] = y(t-\tau) \tag{6.7}$$

A time-varying system is one which does not satisfy (6.7).

Laplace Transform

$$\tilde{F}(s) = \mathcal{L}\left\{f(t)\right\} = \int_0^\infty f(t)e^{-st}dt \quad (6.8)$$

where s is a complex variable.

Inverse Laplace Transform

$$f(t) = \mathcal{L}^{-1} \left\{ \tilde{F}(s) \right\} = \frac{1}{2\pi j} \int_{\gamma - j\infty}^{\gamma + j\infty} \tilde{F}(s) ds$$
 (6.9)

Chapter 7

7.1 Impulse Response

Impulse response, h(t), of a continuous-time LT system is defined as the response/output of the system when the input is a unit impulse, $\delta(t)$.

$$\delta(t) \to \text{LTI system} \to h(t)$$

where

$$h(t) = \mathbf{T}[\delta(t)] \tag{7.1}$$

From replication property,

$$x(t) = x(t) * \delta(t) = \int_{-\infty}^{\infty} x(\tau)\delta(t - \tau)d\tau$$
 (7.2)

Substituting (7.2) into (6.1),

$$y(t) = \mathbf{T}[x(t)]$$

$$= \mathbf{T} \left[\int_{-\infty}^{\infty} x(\tau) \delta(t - \tau) d\tau \right]$$

$$= \int_{-\infty}^{\infty} x(\tau) \mathbf{T}[\delta(t-\tau)] d\tau$$
 the system is time-invariant, by applying

As the system is time-invariant, by applying (6.7) to (7.1),

$$h(t - \tau) = \mathbf{T} \left[\delta(t - \tau) \right]$$
 (7.4)

$$y(t) = \int_{-\infty}^{\infty} x(\tau)h(t-\tau)d\tau$$

$$= x(t) * h(t)$$
(7.5)

Therefore

$$\mathbf{T}[x(t)] = y(t) = x(t) * h(t)$$

7.1.1 Step Response

Step response: the output of the system when input is unit step function

$$u(t) \to h(t) \to o(t) = \int_{-\infty}^{\infty} h(\tau)u(t-\tau)d\tau$$

= $\int_{-\infty}^{t} h(\tau)d\tau$

Step response equals integration of impulse response:

 $o(t) = \int_{-\infty}^{\infty} h(\tau) d\tau$

Impulse response equals differentiation of step $h(t) = \frac{d}{dt}o(t)$

7.2 Frequency Response


The frequency response (H(f)) of an LTI system is defined as the Fourier transform of the system impulse response h(t)

$$H(f) = \Im\{h(t)\} = \int_{-\infty}^{\infty} h(t)e^{-j2\pi f t} dt$$
(7.6)

$$y(t) = x(t) * h(t)$$

$$Y(f) = X(f) \cdot H(f)$$
(7.7)

$$\begin{array}{c} \chi_{(f)} & \chi_{(f)} & \chi_{(f)} = \chi_{(f)} \times \chi_{(f)} \times \chi_{(f)} \\ \chi_{(f)} & \chi_{(f)} & \chi_{(f)} \times \chi_{(f)} \times \chi_{(f)} \\ H(f) & = |H(f)| e^{j \angle H(f)} \end{array}$$



where |H(f)| is called the magnitude response and $\angle H(f)$ is called the phase response of the system.

7.3 Transfer Function

The transfer function $\tilde{H}(s)$ of an LTI system is defined as the Laplace transform of h(t)

$$\tilde{H}(s) = \mathcal{L}\left\{h(t)\right\} = \int_0^\infty h(t)e^{-st}dt \qquad (7.9)$$
 where $s = \sigma + j\omega$ is a complex variable.
$$y(t) = x(t) * h(t)$$

$$\tilde{Y}(s) = \tilde{X}(s) \cdot \tilde{H}(s)$$
 (7.10)

$$\begin{array}{c|c}
\widetilde{\chi}(i) & \widetilde{H}(i) \\
\hline
\chi(i) & \chi(i) & \chi(i) = \chi(i) H(i) \\
\hline
\chi(i) & \chi(i) = \chi(i) \chi(i) \\
\hline
\chi(i) & \chi(i) = \chi(i) \chi(i) \\
\hline
\chi(i) & \chi(i) = \chi(i) \chi(i) \\
\hline
\chi(i) & \chi(i) & \chi(i) \\
\hline
\chi(i) & \chi(i$$

7.4 Relationship between Transfer Function (7.3) and Frequency Response


Substituting $s = j\omega$ into (7.9), we get $\tilde{H}(s)\Big|_{s=j\omega} = \tilde{H}(j\omega) = \int_{0}^{\infty} h(t)e^{-j\omega t}dt$

Sub
$$\omega=2\pi f$$
 into (7.11):
$$\tilde{H}(j\omega)\Big|_{\omega=2\pi f}=\int_0^\infty h(t)e^{-j2\pi ft}dt \quad \mbox{(7.12)}$$
 For causal LTI systems, $\forall t<0\ h(t)=0$. Hence

(7.5) (7.6) and (7.12) are equivalent.

$$H(f) = \tilde{H}(j\omega)\Big|_{\omega = 2\pi f} \tag{7.13}$$

Not always true. See APPENDIX.



where $|\tilde{H}(j\omega)|$ is called the magnitude response and $\angle \tilde{H}(j\omega)$ is called the phase response of the system.

7.4 Sinusoidal Response at Steady-State

Let system input at steady-state be


$$x(t) = Ae^{j(2\pi f_0 t + \psi)}$$
 (7.15)

$$X(f) = Ae^{j\psi}\delta(f - f_0) \tag{7.16}$$

$$Y(f) = A |H(f_0)| e^{j(\psi + \angle H(f_0))} \delta(f - f_0)$$


$$y(t) = \Im^{-1} \{Y(f)\}\$$

$$= A |H(f_0)| e^{j(2\pi f_0 t + \psi + \angle H(f_0))}$$
(7.18)





Steady-state Sinusoidal Response of a LTI System in f-domain



Steady-state Sinusoidal Response of a LTI System in ω-domain

7.6 LTI Systems Described by Differential

LTI systems represented by linear constant- Poles: $s_{1,2} = -\alpha \pm j\omega_0$ coefficient differential equations have the general $h(t) = e^{-\alpha t} \sin(\omega_0 t) u(t)$

$$\sum_{n=0}^{N} a_n \frac{d^n y(t)}{dt^n} = \sum_{m=0}^{M} b_m \frac{d^m x(t)}{dt^m}$$
 (7.21)
$$\underline{\underline{\sigma}} = 0$$

where x(t) is input, y(t) is output, and a_n , b_m are real constants.

7.6.1 Transfer Function

tial conditions set to 0.

$$\sum_{n=0}^{N} a_n \tilde{Y}(s) s^n = \sum_{m=0}^{M} b_m \tilde{X}(s) s^m$$
 (7.2)
$$\tilde{H}(s) = \frac{\tilde{Y}(s)}{\tilde{X}(s)}$$

$$= \left(\sum_{m=0}^{M} b_m s^m \middle/ \sum_{n=0}^{N} a_n s^n \right)$$

$$= \frac{b_M s^M + b_{M-1} s^{M-1} + \dots + b_0}{a_N s^N + a_{N-1} s^{N-1} + \dots + a_0}$$

$$\tilde{H}(s) = K \frac{\left(\frac{s}{z_1} + 1\right)\left(\frac{s}{z_2} + 1\right)\dots\left(\frac{s}{z_M} + 1\right)}{\left(\frac{s}{p_1} + 1\right)\left(\frac{s}{p_2} + 1\right)\dots\left(\frac{s}{p_N} + 1\right)}$$
$$K = \frac{a_0}{L}$$

$$\tilde{H}(s) = K' \frac{(s+z_1)(s+z_2)\dots(s+z_M)}{(s+p_1)(s+p_2)\dots(s+p_N)}$$

 $\forall n \in \{1, 2, \dots, N\}$

• $-p_n$ are roots of the denominator polynomial of $\tilde{H}(s)$

- $\tilde{H}(-p_n) = \infty$
- $-p_n$ are called **poles** of $\tilde{H}(s)$

 $\forall m \in \{1, 2, \ldots, M\}$

- $-z_m$ are roots of the numerator polynomial of $\tilde{H}(s) = \frac{1}{s-\alpha}$ $\tilde{H}(s)$
- $\tilde{H}(-z_m) = 0$
- $-z_m$ are called **zeros** of $\tilde{H}(s)$


The system is said to have N poles and M zeros, and the difference N-M is called pole-zero $\stackrel{\overline{\omega}}{\equiv}$


7.6.2 System Stability **BIBO Stable**


- All system poles lying on the left-half s-plane
- h(t) will converge to 0 as t tends to infinity

$$\lim_{t\to\infty}h(t)=0$$
 g.
$$(s)=\frac{1}{t}$$

$$\tilde{H}(s) = \frac{1}{s+\alpha}$$
Pole: $s = -\alpha$
 $h(t) = e^{-\alpha t}u(t)$








Marginally Stable

- Applying Laplace to both sides of (7.21) with ini• One or more non-repeated system poles lying on the imaginary axis of the s-plane and no system pole lying on the right half s-plane.
 - but neither will it converge to zero as t tends

 $\lim_{t\to\infty} |h(t)| \neq \infty \text{ and } \lim_{t\to\infty} h(t) \neq 0$

E.g.
$$\tilde{H}(s) = \frac{1}{s}$$
 Pole: $s = 0$ $h(t) = u(t)$







(7.23c) Unstable (Case 1)

- One or more system poles lying on the righthalf s-plane
- h(t) will "blow up" and become unbounded as t tends to infinity $\lim_{t\to\infty} |h(t)| = \infty$







Unstable (Case 2)


- One or more repeated system poles lying on the imaginary axis
- h(t) will "blow up" and become unbounded as t tends to infinity

$$\lim_{t\to\infty}|h(t)|=\infty$$

 $\tilde{H}(s) = \frac{1}{2}$









7.7 First Order System (Standard Form) 7.7.1 Differential Eqn, Transfer Func, Impulse Response and Step Response

• Differential equation:

$$T\frac{dy(\hat{t})}{dt} + y(t) = Kx(t)$$
 (7.26)

where

- x(t): system input
- y(t): system output
- K: DC gain
- T: time-constant
- Transfer Function $\tilde{H}(s)$:

$$Ts\tilde{Y}(s) + \tilde{Y}(s) = K\tilde{X}(s)$$

$$\rightarrow \tilde{H}(s) = \frac{\tilde{Y}(s)}{\tilde{X}(s)} = \frac{K}{Ts+1}$$
(7.27)

Pole: $s_1 = -\frac{1}{7}$

Impulse Response h(t)

$$h(t) = \mathcal{L}^{-1} \left\{ \tilde{H}(s) \right\} = \frac{K}{T} e^{-t/T} u(t)$$

• Step Response o(t)

$$o(t) = \int_{-\infty}^{t} h(\tau)d\tau = \mathcal{L}^{-1} \left\{ \frac{1}{s} \tilde{H}(s) \right\}$$
$$= K \left[1 - e^{-t/T} \right] u(t)$$

7.8 Second Order System (Standard Form) 7.8.1 Differential Eqn and Transfer Func

· Differential equation:

$$\frac{d^2y(t)}{dt^2}+2\zeta\omega_n\frac{dy(t)}{dt}+\omega_n^2y(t)=K\omega_n^2x(t) \eqno(7.28)$$

where


- x(t): system input
- y(t): system output
- ζ : damping ratio
- ω_n : undamped natural frequency (when $\zeta < 1$
- K: DC gain
- Transfer function $\tilde{H}(s)$


$$s^{2}\tilde{Y}(s) + 2\zeta\omega_{n}s\tilde{Y}(s) + \omega_{n}^{2}\tilde{Y}(s)$$


$$=K\omega_n^2 \tilde{X}(s)$$

$$\implies \tilde{H}(s) = \frac{\tilde{Y}(s)}{\tilde{X}(s)} = \frac{K\omega_n^2}{s^2 + 2\zeta\omega_n s + \omega_n^2}$$
(7.29)

- Phase plot: plot of $\angle \tilde{H}(j\omega)$ in degrees
- x-axis is logarithmically scaled (semilog-x: scale is log, but labels are still linear)
- · Only positive frequency side visualized (which suffices for real systems as $|\tilde{H}(j\omega)|$ and $\angle \tilde{H}(j\omega)$ are even and odd functions of ω respectively)
- 0.01 to 0.001...







7.8.2 Impulse Response and Step Response **7.8.2.1** Overdamped System ($\zeta > 1$)

Chapter 8

Bode plot: approximate visualization of frequency response, $\tilde{H}(j\omega)$ of a system

• Magnitude plot: plot of $\left| \tilde{H}(j\omega) \right|_{dB} =$ $20\log_{10}\left(\left|\tilde{H}(j\omega)\right|\right)dB$

