Link State and Distance Vector Routing: Code Documentation

Teaching Fellow: Qiao Xiang, Yuchen Yang qiao.xiang@cs.yale.edu, yuchen.yang@yale.edu

In this project, we will be using the emerging ns-3 discrete network simulator (www.nsnam.org) to design and implement core routing protocols. Your assignment is to extend ns-3 to support efficient routing using link-state and distance-vector protocols.

The goal of this documentation is to provide you and your team with a starting point for understanding portions of the ns-3 code relevant to this project. An important goal of this project is to provide you the opportunity to read and understand a sizable piece of software and extend it. Hence, we have deliberately not included all the details about the ns-3 code, particularly on specific APIs.

Please be aware that no amount of documentation can replace actual reading and running of the code itself. So rather than spend hours digesting this document without looking at the code, make sure you treat this document as a reference guide while you run the simulator and step through the control flow of various interacting software modules. To get into the habit of working as a team, we encourage you to spend a day or two to get your entire group together to try to understand the code as a team, and help each other out.

You may post all questions regarding this project on Piazza or directly send them to the TFs via email.

1 Getting Started

In this project, we provide a version of ns-3.9 release. Instead of downloading the entire ns3 package from the ns3 website, please use the provided sample code. The entire ns-3 code has hundreds of thousands of lines of code. For the purpose of this project, we have isolated all the code that you need to learn and modify within the **cs433** folder. Note that some extra credits may require changing files outside this directory, please make sure that you get the regular credits working before you work on the extra credits. If you are interested in learning about how our code interacts with the rest of ns-3, you should feel free to investigate further. There are a few useful data structures of ns-3 that you will need to learn along the way.

1.1 Code Structure and Compilation

Description of files

The **cs433** folder contains the following files shown in Figure 1. Before the actual implementation, you need to read and understand the APIs within the code. To help you understand each function, we have added some comments in the function headers. The files you have to modify are:

- ns-3/cs433/ls-routing-protocol/ls-routing-protocol.cc: This file contains all the event handlers that you need to implement for handling incoming/outgoing route messages.
 - For each incoming message, you need to implement the logic to handle the message, update local routing tables, and send out outgoing messages
 - Periodic/triggered link-state updates should be transmitted and handed within this class.
 - Once the routing table is computed, handlers for forwarding messages should be implemented here, i.e. given an incoming message, forward the message along the computed next hop to the destination.
- ns-3/cs433/ls-routing-protocol/ls-message.cc. This file implements all the packet formats used in the above file. To implement your link-state protocol, feel free to extend this file to add new packet formats, for instance, "hello" packets for neighbor discovery, and "lsa" for link-state advertisements.




Figure 1: Code Structure

Distance-vector has a similar set of files in the dv-routing-protocol directory. The functionality of route computation and forwarding needs to be implemented as well. We omit discussing this directory since it is similar to that of link-state.

The test application that we provide:

• ns-3/cs433/test-app/test-app.cc: This is an example application that we have provided to test your link-state or distance vector implementation. This application periodically generates a small packet to be transmitted from any source to any destination nodes. Feel free to modify test-app.cc to include your tests. While debugging your code, it is advisable to modify our test-app.cc to do something simpler, for instance, sending just one message from a fixed source to destination.

The inputs to your implementation include:

- ns-3/cs433/topologies: see Section 3 on description of input topology. This is essentially the input network to the ns-3 simulation.
- ns-3/cs433/scenarios: see Section 4 on description of the scenario file. This is a step-by-step scenario file that you can customize to start/stop a network, bring up/down links, output network state, etc.

Main simulation code:

• ns-3/cs433/simulator-main.cc: This contains the main driver program for your simulation. It takes as input the topology and scenario file, and executes the scenario. In the process, commands from the scenario file are sent to ls-routing-protocol.cc and dv-routing-protocol.cc, for instance, to generate a table dump, etc. Basically, our simulator-main handles basic commands related to link/node topology changes, and redirect routing-related commands to other modules. For instance, routing related commands are sent to ls-routing-protocol.cc and dv-routing-protocol.cc, while test-case specific commands are sent to test-app.cc. This file also generates optional outputs traces for animation. DO NOT MODIFY simulator-main.cc

Compilation

Please refer to the README file in **cs433** directory on how to compile the code. Make sure you set up LD_LIBRARY_PATH with the following command in your .bashrc file:

export LD_LIBRARY_PATH=\$LD_LIBRARY_PATH:foo/ns-3/build:foo/ns-3/build/debug where "foo" is the directory you put the ns-3 folder in, and then use source /.bashrc

and

echo \$LD_LIBRARY_PATH

to make sure it is setup correctly. Note that these commands are tested on the Zoo machines. In other platforms, you may need to setup DYLD_LIBRARY_PATH instead of LD_LIBRARY_PATH

You should feel free to add new helper source files, for instance, creating your own classes for route entries, neighbor entries, etc. Whenever you add a new file, you need to modify the wscript file within the subdirectory where your new file resides. Failure to do this means that the new file may be excluded from the build.

Running and interacting with the simulator

Now that you have successfully compiled your code, you can run the simulator as follows:

./build/debug/cs433/simulator-main —inet-topo=<topology-file> —scenario=<scenario-file> —rout-ing=<LS/DV/ANY/NS3>

The compiled binaries are located in the build directory. Go to the main ns-3 directory, and run the command above. To understand the commands above, run "./build/debug/cs433/simulator-main —help"

2 Overall Architecture

For most part, you do not need to read any additional files beyond those in **cs433** directory. However for debugging purposes, it is important to understand the interactions of your code with other parts of ns-3. We provide a high-level overview in Figure 2.




Figure 2: Overall Architecture

The figure above shows layers 2-5 from the perspective of a single ns-3 node. At the link layer, each node has multiple IP addresses and interfaces/device (See Section 4 for details). At the IP stack (layer 3), IP packets are forwarded as follows:

- routeInput() receives a message from one of the devices. Your implementation has to determine the next hop to be taken for this message and forward the message to the appropriate device or the local host (if the destination is itself).
- routeOutput() takes messages that originated from the local node, and then performs a similar next-hop forwarding or to the local host (if the destination is itself).

To understand how routeInput() and routeOutput() are used, you may refer to the OLSR code in src/routing/olsr. You do not need to implement multicast for this project.

Note that all control messages used in link-state and distance-vector are sent via UDP protocol in layer 5 to immediate neighbors. This is counter-intuitive at first, since these protocols are implemented in layer 3, while UDP is a layer 4 service. However, this is a common practice to utilize the UDP protocol to bootstrap the protocol itself, where UDP is initially used for communicating with direct neighbors within the same subnet for exchanging control messages. However, once your routing protocol works, you should be able to write an application that uses UDP sockets to send packets to a destination node that is multiple hops away.

3 Input Topology

Your simulation has to take in an initial input topology. Our topology uses the Inettopology format (http://topology.eecs.umich.edu/inet/). Before describing the specifics of the topology, we first describe conceptually what the topology looks like.

Point-to-point topology




Figure 3: Point-to-Point Topology

Figure 3 shows an example point-to-point topology. Each node has a set of neighbors, one for each of its interfaces/device. The figure above contains also subnets and masks, which you need not worry about for this project. However, we included them in case you are interested to learn more.

In the topology file, we refer to nodes by node numbers, e.g. $0,1,2,\ldots$ However, once the topology is initialized, our simulator-main assigns to each node multiple IP addresses. The reason why each node requires multiple IP addresses is that it participates in multiple subsets (which you need not worry about). Our simulator-main will select one of the IP addresses as the unique identifier of the node(hint: look for the m_mainAddress variable in the code). This identifier is what the node should advertise to its neighbors for computing routes. For instance, if node 0 has IP addresses $IP_{0,1}, IP_{0,2}$, and $IP_{0,3}, IP_{0,1}$ is selected as the unique identifier. We have also provided APIs that will map from the Inet node number to the corresponding unique IP address (and vice versa). However, we have included this discussion here for your own understanding should you be curious to learn how addressing works in a pt-to-pt network.

Generating the Inet Topology

To generate the topology, you have to run the topology generator located inside ns-3/inet-3.0. To run the topology, use the following command: ./inet n <Num >

The command will create a point-to-point topology with Num nodes. Please feel free to also manually generate your own topology. To learn about the Inet topology format, refer to the above website. To see an example topology, refer to ns-3/cs433/topologies.

4 Scenario File

After the simulator has started the network, the scenario file is used to generate network events, such as link failures, node additions/failures, sending messages, dump commands to display network state, etc. We have provided an example scenario file at ns-3/cs433/scenarios/10-ls.sce. This scenario file contains most of the commands indicated below. Your goal is to read this scenario file and understand what it is doing. For your own testing purposes, you probably should write your own (simpler) scenarios initially, and feel free to add your own commands (for example, commands to dump link-state updates and network statistics).

- <Node Number > refers to a node in the simulator (from 0, 1, 2, ...).
- <Module Name >refers to the protocol /module, e.g. LS, DV, or the application e.g. APP(test-app.cc). Our simulator-main.cc will direct the command based on the module name to the appropriate code that implements the command handles. (ls-routing-protocol.cc, dv-routing-protocol.cc, or test-app.cc).
- <Command >is the command to be sent to the node, e.g. VERBOSE is to turn on debugging messages, and PING is to send ping messages to another node.
- <Arguments > is any additional arguments required specific to the command.

For instance, the command "1 LS VERBOSE TRAFFIC ON" will result in node 1 turning on all the traffic traces for the link-state protocol. "* LS VERBOSE TRAFFIC ON" will turn on the link-state traces for all nodes. Detailed command syntax provided are shown in Figure 4. And the commands you need to implement for this project are listed in Figure 5. There is a similar set of commands for DV (replace "LS" with "DV").

Interactive Scenario Mode

In addition to using the scenario file, you can also enter the scenario commands interactively via the keyboard. While the simulation is running, there is a command prompt that you can use to enter the commands described above.

Acknowledgment

This project was part of the "Networked Systems Programming Projects in ns-3" taught in University of Pennsylvania. Interested readers may refer to http://netdb.cis.upenn.edu/cis553projects/ for more information.

| Command | Modules | Remarks | Example |
|--|-------------|--|---|
| VERBOSE <type> <on off=""></on></type> | LS, DV, APP | Turn on debugging messages. | 1 LS VERBOSE TRAFFIC ON |
| | | (TYPE> 1. TRAFFIC: Use this when data is sent/received. 2. ERROR: Use this when error messages are to be printed. 3. DEBUG: Use this to print debug logs. 4. STATUS: Use this to print status messages. 5. ALL: Use this to switch all traces at once. | Switches on TRAFFIC traces for node 1. |
| | | Note: ERROR and STATUS verbose is ON by default | |
| PING <node> <message></message></node> | LS, DV, APP | Send PING to a node. | 1 LS PING 2 hi! |
| | | Note that for LS and DV modules, PING can only be sent to immediate neighbors. We have added this functionality as an example for students to implement their neighbor discovery for milestone 1. | Node 1 sends PING request to node 2 with a message: "hi!" You may also use "*" |
| | | | wildcard with APP module: |
| | | On the other hand, the APP module PING is multi-hop, which means the PING message ought to be forwarded to the destination | 1 APP PING * "hello!" |
| | | node using the routing tables computed by LS or DV. | Node 1 sends PING to all the nodes in the topology. |
| TRAFFIC <start stop=""></start> | APP | Start sending traffic towards a node. Traffic is nothing but PING packets sent every 2 milliseconds. | 1 APP TRAFFIC START * Node 1 starts sending traffic to all the nodes in the topology |
| NODELINKS <up down=""> <node number=""></node></up> | | Bring up/down all links of a node. | NODELINKS DOWN 1 Brings down all links on |
| | | | node 1. |
| LINK < UP/DOWN> <node- A> <node-b></node-b></node- | | Brings up/down all links between NODE A and NODE B | LINK DOWN 1 8 Bring down link(s) between node 1 and 8. |
| LINK <up down=""> <link NUMBER></link </up> | | Bring up/down a specific link as defined in topology file | LINK DOWN 6 Bring down 7th link defined in topology file |
| TIME <milliseconds></milliseconds> | | Advance scenario file time before next command. | TIME 100 Advance time by 100 milliseconds |
| QUIT | | Quit Simulator | |

Figure 4: Command Syntax

| Command | Remarks | Example |
|----------------|--------------------------|---------------------|
| DUMP ROUTES | Print out routing tables | 1 LS DUMP ROUTES |
| DUMP NEIGHBORS | Print out neighbors | 1 LS DUMP NEIGHBORS |

Figure 5: Commands to be implemented