# Lecture 17: Synchronization

(Producer-Consumer, Condition Variables, and Semaphores)

Xin Liu

Florida State University xliu15@fsu.edu

COP 4610 Operating Systems https://xinliulab.github.io/FSU-COP4610-Operating-Systems/

# **Revisiting Spinlocks**

## Spinlocks

- A spinlock is a simple lock where a thread constantly checks for lock availability.
- Imagine a single key to a critical section. The first thread to acquire the key can enter.
- Hardware instructions ensure atomic key exchange.

## **Understanding Spinlocks Thoroughly**

The single atomic instruction (xchg) ensures no race condition.

```
// 0 means unlocked, 1 means locked
int lock = 0:
void acquire_lock(int *lock) {
  while (*lock != 0) {}
  *lock = 1:
void release_lock(int *lock) {
  *lock = 0:
void *foo(void *arg) {
  acquire_lock(&lock);
  // Critical section: Do work here ...
  release_lock(&lock):
  return NULL:
```

```
// 0 means unlocked, 1 means locked
int lock = 0:
int xchg(int *addr, int newval) {
  int result:
  asm volatile (
    "lock xchg %0, %1"
    : "+m" (*addr), "=a" (result)
     : "1" (newval)
  return result:
void acquire_lock(int *lock) {
  while (xchg(lock, 1)) {}
void release_lock(int *lock) {
  xchg(lock, 0);
void *foo(void *arg) {
  acquire_lock(&lock);
  // Critical section: Do work here
  release_lock(&lock):
  return NULL:
```

## Rules for Acquiring a Lock

- **Grab first, verify later:** Don't bother checking if the lock is free. Just grab it and verify its status later.
- Be Water: Grab that lock as quickly as possible before anyone else does.



Recap

## Recap: Spinlocks

## Spinlocks

- A spinlock is a simple lock where a thread constantly checks for lock availability.
- Imagine a single key to a critical section. The first thread to acquire the key can enter.
- Hardware instructions ensure atomic key exchange.

## Performance Issue

- Spinlocks can cause inefficiency, especially if many threads compete for the same lock, leading to frequent context switches (Grab first, verify later).
- If a thread holding the lock is swapped out, all other threads continue busy-waiting, wasting CPU resources, because the CPU still considers them active (either in the Running or Ready to Run state).

Recap

# Recap: Mutexes and Futexes

## Mutexes

- The lock is managed by the OS kernel.
- When a thread attempts to acquire a mutex that is already locked, the OS puts the thread to sleep (blocked state) instead of busy-waiting.
- The kernel wakes up the thread when the lock becomes available, preventing it from wasting CPU time while waiting for the lock.

## **Futexes**

- A futex is a combination of spinlocks and mutexes.
- It starts with spinning and escalates to a kernel-based mutex when needed.
- This hybrid approach improves performance by reducing both busy-waiting in user space and context switches to the kernel.

# Example: Mutex with 3 Threads (Sleep and Wake-up)

- **1 Thread X** acquires the lock first and enters the critical section.
- 2 Thread Y and Thread Z attempt to acquire the lock but go into a sleep (blocked state) since the lock is already held by X.
- Once X finishes and releases the lock, the OS wakes up Y, typically following a first-come, first-served policy (FIFO) or priority-based scheduling.
- After Thread Y completes its critical section and releases the lock, the OS wakes up Z, which then acquires the lock.
- The waking mechanism is managed by the OS, which monitors the release of the lock and uses it as the signal to wake the next waiting thread.

# **Building on Previous Experience**

```
int lock = 0; // Spinlock variable
// Not provided by pthread.h, so defined here.
int xchg(int *addr, int newval) {
    int result;
    asm volatile (
        "lock xchq %0, %1"
        : "+m" (*addr), "=a" (result)
        : "1" (newval)
        : "cc"
    );
    return result;
void acquire_lock(int *lock) {while (xchg(lock, 1)) {}}
void release lock(int *lock) {xchg(lock, 0);}
void *foo(void *arg) {
    acquire_lock(&lock);
    // Critical section: Do work here ...
    release lock(&lock);
    return NULL;
```

## The Essence of Collaborative Relationships

 Collaborative relationships are a combination of Competition Relationships and Dependency Relationships

# Competition Relationships

- Involves access and modification of shared resources within threads
- When threads are independent
  - The main concern is to avoid Competition Relationships
  - Use synchronization mechanisms like Spinlocks and Mutex Locks
  - Ensure only one thread accesses the shared resource at a time
  - Avoid data inconsistency and race conditions
- Focus on safe access within threads



# Dependency Relationships

- Involves execution order and causal relationships between threads
- When one thread must complete before another can execute
  - Use mechanisms like Condition Variables and Semaphores
  - Control the execution order of threads
  - Satisfy logical dependency requirements
- Focus on correct coordination between threads

# Real-World Application

## **Core Question**

 How do you coordinate multiple threads to handle tasks efficiently in real-world systems?

## Example: E-commerce Platform Order Processing System

- Order Validation: Check product inventory, user balance, and coupon validity.
- **Payment Processing:** Deduct from user accounts or process third-party payments.
- Inventory Update: Deduct product stock to prevent overselling.
- **Logistics Arrangement:** Generate shipping orders and arrange delivery.
- Notify Users: Send confirmation emails or SMS to users.



# Real-World Application (Cont.)

## Challenges and Solutions

- Managing Shared Resources (Competition):
  - Multiple threads updating inventory or user balances may cause race conditions.
  - **Solution:** Use Mutex locks to ensure only one thread modifies shared resources at a time.
  - Also, use transactions to roll back in case of failures, ensuring data consistency.
- Managing Dependencies Between Threads (Dependency):
  - Notification threads must wait until order processing is complete.
  - Solution: Use condition variables or semaphores to signal thread progress and control execution order.
  - Task queues can be used to arrange execution based on dependencies.

## Outline: How to Coordinate Threads

- Producer-Consumer Problem
- Condition Variables
- Semaphores



# Synchronization Model

# **Modeling Synchronization Problems**

## Producer-Consumer Problem

 A fundamental synchronization problem that allows you to solve 99.9% of real-world concurrency issues.

## Dining Philosophers Problem

 Another classic problem that demonstrates how multiple entities share limited resources (like CPUs).

# **Key Tools**

## **Condition Variables**

• A flexible synchronization primitive that allows threads to wait until a specific condition is met.

## Semaphores

• A more rigid mechanism used to control access to shared resources by multiple threads.

## **Producer-Consumer Problem**

## Producer "O" and Consumer "X"

## **Producer:**

- Produces an item ("O")
- Waits if storage is full
- Must be synchronized with the consumer

## Consumer:

- Consumes an item ("X")
- Waits if no item is available
- Synchronization ensures no consumption before production
- We need to ensure that the symbols ("O" and "X") are printed in a valid sequence:
- Example:
  - *n* = 3,000xx0xx000 (valid)
  - *n* = **3**,0000XXXX, 00XXX (invalid)

# Why Producer-Consumer is Widely Representative

- Involves two types of threads: Producers (generate data) and Consumers (process data)
- Producers don't overflow the buffer and consumers don't try to consume data that's not yet available.

## **Challenges:**

- Synchronization and mutual exclusion
- Managing dependencies and inter-thread communication

## **Initial Attempt**

- Ensure the condition is met using mutex locks.
  - Have A Try: producer\_consumer.c
- Stress Testing
  - Have A Try: producer\_consumer.c
  - Command: ./producer\_consumer 2 | python3 pc\_checker.py 2

### Bad News:

- After running the program for several hours, it actually failed!
- The issue is difficult to reproduce and to fix.
- Concurrent programming is highly challenging.

## Good News:

- The problem occurred while it was in your hands.
- Avoid taking shortcuts and always stick to the most reliable methods.



# Condition Variables: A Universal Synchronization Method

# The Essence of Synchronization

 The essence of synchronization is ensuring that multiple threads or processes reach a **known state** at the same time, so that they can proceed in coordination.

## **Example:**

- Imagine two people (threads) trying to meet for dinner (a task).
- One is playing a game (task A), and the other is fixing a bug (task B).
- They can't start dinner (synchronized task) until both have finished their tasks (known state).
- Even if one person finishes earlier, they must wait for the other.

## **Core Concept**

• The core of synchronization is waiting for all necessary conditions to be met before proceeding together.

## Synchronization Example

- From the very beginning when you started working with threads, you were already using synchronization.
- Can you find which part is synchronization?

```
pthread_t t1, t2;

pthread_create(&t1, NULL, foo, NULL);
pthread_create(&t2, NULL, foo, NULL);

pthread_join(t1, NULL);
pthread_join(t2, NULL);
```

## Synchronization Example (Cont.)

- From the very beginning when you started working with threads, you were already using synchronization.
- Can you find which part is synchronization?
  - pthread\_join ensures that the main thread waits for the other threads to finish before continuing.
  - This is a form of synchronization because it guarantees that all threads reach a known state (completion) before the program proceeds.

```
pthread_t t1, t2;

pthread_create(&t1, NULL, foo, NULL);
pthread_create(&t2, NULL, foo, NULL);

pthread_join(t1, NULL);
pthread_join(t2, NULL);
```

## Problems with Initial Attempt

```
void *Tproduce(void *arg) {
  while (1) {
retrv:
    pthread_mutex_lock(&lk);
    if (count == n) {
      pthread_mutex_unlock(&
    1k);
      goto retry;
    count++;
    printf("0");
    pthread mutex unlock(&lk
    );
  return NULL:
```

```
void *Tconsume(void *arg) {
  while (1) {
retrv:
    pthread_mutex_lock(&lk);
    if (count == 0) {
      pthread mutex unlock(&
    1k);
      goto retry;
    count --;
    printf("X");
    pthread mutex unlock(&lk
    );
  return NULL;
```

## Problems with Initial Attempt (Cont.)

- Busy Waiting: Both producer and consumer continuously retry when the buffer is full or empty. This leads to a waste of CPU resources.
- Resource Contention: Multiple threads constantly lock and unlock the same mutex without meaningful progress when conditions are not met, causing unnecessary contention.
- High CPU Utilization: The goto retry causes the threads to remain in a tight loop, consuming CPU cycles even when they should be waiting.

# Why Avoid Busy Waiting?

## "Haste makes waste."

Constant spinning and busy waiting lead to errors. Slowing down with condition variables reduces mistakes.

Have A Try: <u>condition\_varaibles.c</u>



# Tip 1: pthread\_cond\_wait

```
void *Tproduce(void *arg) {
  while (1) {
    pthread_mutex_lock(&lk);
    while (count == n) {
      pthread_cond_wait(&
   not full, &lk);
    count++;
    printf("0");
    pthread_cond_signal(&
   not_empty);
    pthread mutex unlock(&lk
   );
  return NULL:
```

```
void *Tconsume(void *arg) {
  while (1) {
    pthread_mutex_lock(&lk);
    while (count == 0) {
      pthread_cond_wait(&
   not empty, &lk);
    count --:
    printf("X");
    pthread_cond_signal(&
   not full);
    pthread mutex unlock (&lk
    );
  return NULL;
```

## Tip 1: pthread\_cond\_wait (Cont')

- pthread\_cond\_wait: A thread goes to sleep and releases the mutex while waiting for a condition (e.g., buffer not empty/full).
- pthread\_cond\_wait must be used with a mutex.
  - The thread must first acquire the mutex lock before calling pthread\_cond\_wait.
    - pthread\_cond\_wait only handles waiting for a condition to be met, it does not handle acquiring the lock.

## Tip 2: pthread\_cond\_signal

```
void *Tproduce(void *arg) {
  while (1) {
    pthread_mutex_lock(&lk);
    while (count == n) {
      pthread_cond_wait(&
   not full, &lk);
    count++;
    printf("0");
    pthread_cond_signal(&
   not_empty);
    pthread mutex unlock(&lk
   );
  return NULL:
```

```
void *Tconsume(void *arg) {
  while (1) {
    pthread_mutex_lock(&lk);
    while (count == 0) {
      pthread_cond_wait(&
   not empty, &lk);
    count --:
    printf("X");
    pthread_cond_signal(&
   not_full);
    pthread mutex unlock (&lk
    );
  return NULL;
```

## Tip 2: pthread\_cond\_signal (Cont')

- pthread\_cond\_signal: Wake up one waiting thread when the condition is met (e.g., an item is produced or consumed).
  - Which thread is woken up?
    - If multiple threads are waiting, the OS decides which thread to wake up based on a scheduling policy, usually first-come, first-served (FIFO) or priority-based.

## Tip 3: You can also use pthread\_cond\_broadcast

```
void *Tproduce(void *arg) {
  while (1) {
    pthread_mutex_lock(&lk);
    while (count == n) {
      pthread_cond_wait(&
   not_full, &lk);
    count++;
    printf("0");
    pthread_cond_broadcast(&
   not_empty);
    pthread mutex unlock(&lk
   );
  return NULL:
```

```
void *Tconsume(void *arg) {
  while (1) {
    pthread_mutex_lock(&lk);
    while (count == 0) {
      pthread_cond_wait(&
   not empty, &lk);
    count --:
    printf("X");
    pthread_cond_broadcast(&
   not full);
    pthread mutex unlock (&lk
    );
  return NULL;
```

## Tip 3: pthread\_cond\_broadcast

- pthread\_cond\_broadcast: Wake up all waiting threads when the condition is met.
  - When to use pthread\_cond\_broadcast?
    - Use pthread\_cond\_broadcast when a global state changes that
      affects all threads.

# The Most Important Tip: Two Condition Variables!

```
pthread_cond_t not_full = PTHREAD_COND_INITIALIZER;
pthread_cond_t not_empty = PTHREAD_COND_INITIALIZER;
```

- Avoid waking the same type of thread:
  - Producers should not wake other producers, and consumers should not wake other consumers.
  - Producer thread:
    - Waits on not\_full when the buffer is full.
    - Signals not\_empty after producing an item, allowing consumers to wake up and consume.
  - Consumer thread:
    - Waits on not\_empty when the buffer is empty.
    - Signals not\_full after consuming an item, allowing producers to wake up and produce.

# Deadlock with Single Condition Variable Example

pthread\_cond\_t buffer\_change = PTHREAD\_COND\_INITIALIZER;

- Scenario:
  - Buffer size ( n = 1 )
  - 2 producer threads (P1, P2) and 2 consumer threads (C1, C2)
  - The buffer is empty and C1 and C2 are sleeping
  - P2 is also sleeping due to the buffer being full previously.
- Process:
  - P1 produces an item, filling the buffer (count = 1), then signals 'buffer\_change' (P1 is ready to run and not sleeping)
  - The signal wakes up P2
  - P2 is woken up, but finds the buffer is full, so P2 goes back to sleep without sending any signal
  - P1 is scheduled by the OS, but P1 also finds the buffer is full and goes to sleep without sending any signal
  - The OS may now try to schedule C1 or C2, but they are still sleeping, waiting for the signal that hasn't been sent
- Result:
  - All threads are now in a sleeping state, resulting in deadlock

## Cause of Single Condition Variable Deadlock

- All threads rely on a signal to wake up, rather than automatically waking when the condition becomes true.
- A single condition variable may wake up the same type of thread repeatedly.
- No further signals can be sent, leading to deadlock.
- Role of the Operating System:
  - Manages thread scheduling and CPU time allocation
  - Does not manage thread synchronization or signal passing
  - Cannot wake threads
- Thread Communication:
  - Synchronization happens through condition variables (signals) and mutexes
  - Signals must be explicitly sent and received between threads
  - Proper signal passing is critical for correct thread coordination



## Why Two Condition Variables Prevent Deadlock

- A producer's 'not\_empty' signal only wakes consumers.
- A consumer's 'not\_full' signal only wakes producers.
- At least one thread type can always proceed and change the buffer state
- Eliminates the possibility of all threads waiting at the same time

## **Limitations of Condition Variables**

- Imagine a buffer with 5 slots, initially empty / full.
- If 5 producer / consumer threads want to produce / consume 'O', a condition variable only allows one thread to produce / consume at a time.
- But what if we want multiple threads to produce / consume 'O' concurrently?

# Semaphores

- Semaphore is a synchronization mechanism used to control access to shared resources in concurrent systems.
- It acts as an integer counter that tracks the availability of a limited number of resources.
- It can allow multiple threads to enter the critical section simultaneously.
  - However, you must ensure that there are no race conditions when multiple threads are in the critical section. If there are no such issues, semaphores can be used effectively.

# **Semaphore Operations**

- Semaphores were first introduced by Edsger W. Dijkstra in the 1960s.
- Semaphores operate similarly to condition variables, allowing threads to wait and be signaled based on certain conditions.

## Semaphores have two primary operations:

- P operation (from Dutch proberen, meaning "to try"):
  - Decreases the semaphore's value by 1.
  - If the value becomes negative, the thread performing the P operation is blocked until the semaphore's value becomes positive.
- **V operation** (from Dutch *verhogen*, meaning "to increment"):
  - Increases the semaphore's value by 1.
  - If there are any blocked threads, the V operation wakes up one of them.



# Code Comparison

```
// Condition Variables
void *Tproduce(void *arg) {
 while (1) {
    pthread mutex lock(&lk);
    while (count == n) { pthread_cond_wait(&not_full, &lk);}
    count++;
    printf("0");
    pthread_cond_signal(&not_empty);
    pthread_mutex_unlock(&lk);
  return NULL;
void *Tconsume(void *arg) {
  while (1) {
    pthread_mutex_lock(&lk);
    while (count == 0) { pthread_cond_wait(&not_empty, &lk);}
    count --:
    printf("X");
    pthread_cond_signal(&not_full);
    pthread_mutex_unlock(&lk);
  return NULL:
```

# Code Comparison (Cont.)

```
// Semaphores
void *Tproduce(void *arg) {
  while (1) {
    P(&empty_sem);
    pthread_mutex_lock(&mutex);
    printf("0");
    pthread_mutex_unlock(&mutex);
    V(&full_sem);
  return NULL:
void *Tconsume(void *arg) {
  while (1) {
    P(&full_sem);
    pthread_mutex_lock(&mutex);
    printf("X");
    pthread_mutex_unlock(&mutex);
    V(&empty_sem);
  return NULL;
```

# Semaphores vs Condition Variables: Key Differences

## Resource Management:

- Semaphores have a built-in counter to manage resource availability.
- Condition variables do not track resource availability. The programmer must manage resource state manually.

## Wait/Wake Mechanism:

- Semaphores use the P (wait) and V (signal) operations to automatically handle the blocking and unblocking of threads.
- Condition variables use pthread\_cond\_wait() to put a thread to sleep and pthread\_cond\_signal() or pthread\_cond\_broadcast() to wake up waiting threads.

## Mutex Usage:

- Semaphores can be used with or without a mutex, allowing multiple threads to access the critical section simultaneously based on the semaphore's value.
- Condition variables must be used with a mutex, typically allowing only one thread in the critical section at a time, even if multiple threads are woken up.

Have A Try: semaphore.c



# Semaphores without Mutex

```
void *Tproduce(void *arg) {
   while (1) {
     P(&empty_sem);
     printf("O");
     V(&full_sem);
   }
   return NULL;
}
```

```
void *Tconsume(void *arg) {
   while (1) {
     P(&full_sem);
     printf("X");
     V(&empty_sem);
   }
   return NULL;
}
```

Have A Try: semaphore\_no\_mutex.c

# Considerations for Semaphore Usage

- If you plan to implement more complex buffer operations (e.g., actually storing data instead of just printing characters), you will need to use a mutex to avoid race conditions.
- While semaphores may seem convenient, they become less effective as more rules are added, making them harder to manage.
- It's often better to use condition variables for complex synchronization needs.

## **Takeaways**

- Most of the synchronization problems you will face are just variations of the **Producer-Consumer problem**.
- Mastering condition variables is enough to handle most real-world scenarios.
- The rest is just icing on the cake.

