Lecture 16: Concurrency Synchronization

(Producer-Consumer, Condition Variables, and Semaphores)

Xin Liu

Florida State University xliu15@fsu.edu

COP 4610 Operating Systems https://xinliulab.github.io/FSU-COP4610-Operating-Systems/

Outline

- Producer-Consumer Problem
- Condition Variables
- Semaphores



Revisiting Spinlocks

Spinlocks

- A spinlock is a simple lock where a thread constantly checks for lock availability.
- Imagine a single key to a critical section. The first thread to acquire the key can enter.
- Hardware instructions ensure atomic key exchange.

Understanding Spinlocks Thoroughly

The single atomic instruction (xchg) ensures no race condition.

```
// 0 means unlocked 1 means locked
int lock = 0:
void acquire_lock(int *lock) {
   while (*lock != 0) {}
   *lock = 1:
void release_lock(int *lock) {
   *lock = 0:
void *foo(void *arg) {
   acquire_lock(&lock);
   // Critical section: Do work here ...
   release_lock(&lock):
   return NULL;
```

```
// 0 means unlocked, 1 means locked
int lock = 0:
int xchg(int *addr. int newval) {
    int result:
    asm volatile (
        "lock xchg %0, %1"
        : "+m" (*addr), "=a" (result)
        : "1" (newval)
        : "cc"
    return result:
void acquire_lock(int *lock) {
    while (xchg(lock, 1)) { }
void release_lock(int *lock) {
    xchg(lock, 0);
void *foo(void *arg) {
    acquire_lock(&lock);
    // Critical section: Do work here ...
    release_lock(&lock):
    return NULL;
```

Rules for Acquiring a Lock

- **Grab first, verify later:** Don't bother checking if the lock is free. Just grab it and verify its status later.
- **Be fast:** Grab that lock as quickly as possible before anyone else does.

Recap: Spinlocks

Spinlocks

- A spinlock is a simple lock where a thread constantly checks for lock availability.
- Imagine a single key to a critical section. The first thread to acquire the key can enter.
- Hardware instructions ensure atomic key exchange.

Performance Issue

- Spinlocks can cause inefficiency, especially if many threads compete for the same lock, leading to frequent context switches (Grab first, verify later).
- If a thread holding the lock is swapped out, all other threads continue busy-waiting, wasting CPU resources, because the CPU still considers them active (either in the Running or Ready to Run state).

Recap: Mutexes and Futexes

Mutexes

- The lock is managed by the OS kernel.
- When a thread attempts to acquire a mutex that is already locked, the OS puts the thread to sleep (blocked state) instead of busy-waiting.
- The kernel wakes up the thread when the lock becomes available, preventing it from wasting CPU time while waiting for the lock.

Futexes

Recap

- A futex is a combination of spinlocks and mutexes.
- It starts with spinning and escalates to a kernel-based mutex when needed.
- This hybrid approach improves performance by reducing both busy-waiting in user space and context switches to the kernel.

Example: Mutex with 3 Threads (Sleep and Wake-up)

- **1 Thread X** acquires the lock first and enters the critical section.
- 2 Thread Y and Thread Z attempt to acquire the lock but go into a sleep (blocked state) since the lock is already held by X.
- Once X finishes and releases the lock, the OS wakes up Y, typically following a first-come, first-served policy (FIFO) or priority-based scheduling.
- 4 After Thread Y completes its critical section and releases the lock, the OS wakes up Z, which then acquires the lock.
- The waking mechanism is managed by the OS, which monitors the release of the lock and uses it as the signal to wake the next waiting thread.

Building on Previous Experience

• We started with the thread library (#include <pthread.h>) and implemented simple threads and spinlocks.

```
pthread_t t1, t2;

pthread_create(&t1,
    NULL, foo, NULL);
pthread_create(&t2,
    NULL, foo, NULL);
```

```
int lock = 0; // Spinlock
   variable
// Atomic exchange function to
   swap *addr with newval.
// Not provided by pthread.h, so
   defined here.
int xchq(int *addr, int newval) {
   int result;
   asm volatile (
      "lock xchq %0, %1"
      : "+m" (*addr), "=a" (
        result)
      : "1" (newval)
      : "cc"
   );
   return result;
```

Concurrency: What We Have Learned So Far

Date	Topic
9/4 (W)	L3: Introduction to Concurrency
	(OS State Machine, Process & Thread, Amdahl's Law)
9/9 (M)	L4: CPU Scheduling
	(OS Boot, Process Creation, Address Space, Scheduling)
9/11 (W)	L5: Independent & Cooperating Threads
	(Race Condition and Loss of Atomicity)
9/16 (M)	L6: Concurrency Control: Mutual Exclusion
	(Lock Failures, Peterson's Algorithm, and Spin Locks)
9/18 (W)	L7: UNIX Shell / Project 1 Hints
9/23 (M)	L8: Concurrency Control: Advanced Mutual Exclusion
	(Mutex & Futex Locks)



The Essence of Collaborative Relationships

 Collaborative relationships are a combination of Competition Relationships and Dependency Relationships

Competition Relationships

- Involves access and modification of shared resources within threads
- When threads are independent
 - The main concern is to avoid Competition Relationships
 - Use synchronization mechanisms like Spinlocks and Mutex Locks
 - Ensure only one thread accesses the shared resource at a time
 - Avoid data inconsistency and race conditions
- Focus on safe access within threads



Dependency Relationships

- Involves execution order and causal relationships between threads
- When one thread must complete before another can execute
 - Use mechanisms like Condition Variables and Semaphores
 - Control the execution order of threads
 - Satisfy logical dependency requirements
- Focus on correct coordination between threads

Real-World Application

Core Question

 How do you coordinate multiple threads to handle tasks efficiently in real-world systems?

Example: E-commerce Platform Order Processing System

- Order Validation: Check product inventory, user balance, and coupon validity.
- **Payment Processing:** Deduct from user accounts or process third-party payments.
- **Inventory Update:** Deduct product stock to prevent overselling.
- **Logistics Arrangement:** Generate shipping orders and arrange delivery.
- Notify Users: Send confirmation emails or SMS to users.



Real-World Application (Cont.)

Challenges and Solutions

- Managing Shared Resources (Competition):
 - Multiple threads updating inventory or user balances may cause race conditions.
 - **Solution:** Use Mutex locks to ensure only one thread modifies shared resources at a time.
 - Also, use transactions to roll back in case of failures, ensuring data consistency.
- Managing Dependencies Between Threads (Dependency):
 - Notification threads must wait until order processing is complete.
 - Solution: Use condition variables or semaphores to signal thread progress and control execution order.
 - Task queues can be used to arrange execution based on dependencies.

Objective of this Lecture

 By the end of this lecture, you'll know how to utilize multiple CPUs for running parallel algorithms.

Modeling Concurrent Problems

Producer-Consumer Problem

 A fundamental synchronization problem that allows you to solve 99.9% of real-world concurrency issues.

Dining Philosophers Problem

 Another classic problem that demonstrates how multiple entities share limited resources (like CPUs).

Key Tools

Condition Variables

• A flexible synchronization primitive that allows threads to wait until a specific condition is met.

Semaphores

 A more rigid mechanism used to control access to shared resources by multiple threads.

Producer-Consumer Problem

Producer "O" and Consumer "X"

Producer:

- Produces an item ("O")
- Waits if storage is full
- Must be synchronized with the consumer

Consumer:

- Consumes an item ("X")
- Waits if no item is available
- Synchronization ensures no consumption before production
- We need to ensure that the symbols ("O" and "X") are printed in a valid sequence:
- Example:
 - *n* = 3,000XX0XX000 (valid)
 - *n* = **3**,0000XXXX, 00XXX (invalid)

Why Producer-Consumer is Widely Representative

- Involves two types of threads: Producers (generate data) and Consumers (process data)
- Producers don't overflow the buffer and consumers don't try to consume data that's not yet available.

Challenges:

- Synchronization and mutual exclusion
- Managing dependencies and inter-thread communication

Initial Attempt

- Ensure the condition is met using mutex locks.
 - Link of Code: **Producer-Consumer Example Code**
- Stress Testing
 - Link of Code: <u>Stress Test Checker Code</u>
 - Command: ./a.out 2 | python3 pc_checker.py 2

Bad News:

- After running the program for several hours, it actually failed!
- The issue is difficult to reproduce and to fix.
- Concurrent programming is highly challenging.

Good News:

- The problem occurred while it was in your hands.
- Avoid taking shortcuts and always stick to the most reliable methods.



Condition Variables: A Universal Synchronization Method

The Essence of Synchronization

 The essence of synchronization is ensuring that multiple threads or processes reach a **known state** at the same time, so that they can proceed in coordination.

Example:

- Imagine two people (threads) trying to meet for dinner (a task).
- One is playing a game (task A), and the other is fixing a bug (task B).
- They can't start dinner (synchronized task) until both have finished their tasks (known state).
- Even if one person finishes earlier, they must wait for the other.

Core Concept

 The core of synchronization is waiting for all necessary conditions to be met before proceeding together.

Synchronization Example

- From the very beginning when you started working with threads, you were already using synchronization.
- Can you find which part is synchronization?

```
pthread t t1, t2;
pthread create (&t1, NULL, foo, NULL);
pthread create (&t2, NULL, foo, NULL);
pthread join(t1, NULL);
pthread join(t2, NULL);
```

Synchronization Example (Cont.)

- From the very beginning when you started working with threads, you were already using synchronization.
- Can you find which part is synchronization?
 - pthread_join ensures that the main thread waits for the other threads to finish before continuing.
 - This is a form of synchronization because it guarantees that all threads reach a known state (completion) before the program proceeds.

```
pthread_t t1, t2;

pthread_create(&t1, NULL, foo, NULL);
pthread_create(&t2, NULL, foo, NULL);

pthread_join(t1, NULL);
pthread_join(t2, NULL);
```

Problems with Initial Attempt

```
void *Tproduce(void *arg)
 while (1) {
retry:
   pthread mutex lock(&lk
   if (count == n) {
    pthread_mutex_unlock
        (&lk);
    goto retry;
   count++;
   printf("0");
   pthread_mutex_unlock(&
      lk);
 return NULL;
```

```
void *Tconsume(void *arg)
 while (1) {
retry:
   pthread mutex lock(&lk
   if (count == 0) {
    pthread_mutex_unlock
        (&lk);
    goto retry;
   count --;
   printf("X");
   pthread_mutex_unlock(&
      lk);
 return NULL;
```

Problems with Initial Attempt (Cont.)

```
void *Tproduce(void *arg)
 while (1) {
retry:
   pthread mutex lock(&lk
   if (count == n) {
    pthread mutex unlock
        (&lk);
    goto retry;
   count++;
   printf("0");
   pthread_mutex_unlock(&
      lk);
 return NULL;
```

```
void *Tconsume(void *arg)
 while (1) {
retrv:
   pthread mutex lock(&lk
   if (count == 0) {
    pthread mutex unlock
        (&lk);
    goto retry;
   count --;
   printf("X");
   pthread_mutex_unlock(&
      lk);
 return NULL;
```

Why Avoid Busy Waiting?

"Haste makes waste."

Constant spinning and busy waiting lead to errors. Slowing down with condition variables reduces mistakes.

• Link of Code: Condition Varaibles Example Code

Tip 1: pthread_cond_wait

```
void *Tproduce(void *arg)
 while (1) {
   pthread_mutex_lock(&lk
   while (count == n) {
    pthread cond wait (&
        not full, &lk);
   count++;
   printf("0");
   pthread cond signal (&
      not empty);
   pthread_mutex_unlock(&
      lk);
 return NULL;
```

```
void *Tconsume(void *arg)
 while (1) {
   pthread_mutex_lock(&lk
   while (count == 0) {
    pthread cond wait (&
        not empty, &lk);
   count --:
   printf("X");
   pthread cond signal (&
      not full);
   pthread_mutex_unlock(&
      lk);
 return NULL;
```

• pthread_cond_wait: A thread goes to sleep and releases the

Tip 2: pthread_cond_signal

```
void *Tproduce(void *arg)
 while (1) {
   pthread_mutex_lock(&lk
   while (count == n) {
    pthread_cond_wait(&
        not full, &lk);
   count++;
   printf("0");
   pthread cond signal (&
      not empty);
   pthread_mutex_unlock(&
      lk);
 return NULL;
```

```
void *Tconsume(void *arg)
 while (1) {
   pthread_mutex_lock(&lk
   while (count == 0) {
    pthread cond wait (&
        not empty, &lk);
   count --:
   printf("X");
   pthread cond signal (&
      not full);
   pthread_mutex_unlock(&
      lk);
 return NULL;
```

29 / 41

• pthread_cond_signal: Wake up one waiting thread when the

Tip 3: You can also use pthread_cond_broadcast

```
void *Tproduce(void *arg)
 while (1) {
   pthread_mutex_lock(&lk
   while (count == n) {
    pthread cond wait (&
        not full, &lk);
   count++;
   printf("0");
   pthread cond broadcast
       (&not empty);
   pthread_mutex_unlock(&
      lk);
 return NULL;
```

```
void *Tconsume(void *arg)
 while (1) {
   pthread_mutex_lock(&lk
   while (count == 0) {
    pthread cond wait (&
        not empty, &lk);
   count --:
   printf("X");
   pthread cond broadcast
       (&not full);
   pthread_mutex_unlock(&
      lk);
 return NULL;
```

• pthread_cond_broadcast: Wake up all waiting threads when a

The Most Important Tip: Two Condition Variables!

```
pthread cond t not full = PTHREAD COND INITIALIZER;
pthread cond t not empty = PTHREAD COND INITIALIZER;
```

- Avoid waking the same type of thread:
 - Producers should not wake other producers, and consumers should not wake other consumers.
 - Producer thread:
 - Waits on not, full when the buffer is full.
 - Signals not_empty after producing an item, allowing consumers to wake up and consume.
 - Consumer thread:
 - Waits on not_empty when the buffer is empty.
 - Signals not_full after consuming an item, allowing producers to wake up and produce.
- Link of Code: Single Condition Varaible Example Code



Deadlock with Single Condition Variable Example

```
pthread_cond_t buffer_change = PTHREAD_COND_INITIALIZER;
```

- Scenario:
 - Buffer size (n = 1)
 - 2 producer threads (P1, P2) and 2 consumer threads (C1, C2)
 - The buffer is empty and C1 and C2 are sleeping
 - P2 is also sleeping due to the buffer being full previously.
- Process:
 - P1 produces an item, filling the buffer (count = 1), then signals 'buffer_change' (P1 is ready to run and not sleeping)
 - The signal wakes up P2
 - P2 is woken up, but finds the buffer is full, so P2 goes back to sleep without sending any signal
 - P1 is scheduled by the OS, but P1 also finds the buffer is full and goes to sleep without sending any signal
 - The OS may now try to schedule C1 or C2, but they are still sleeping, waiting for the signal that hasn't been sent
- Result:
 - All threads are now in a sleeping state, resulting in deadlock

Cause of Single Condition Variable Deadlock

- All threads rely on a signal to wake up, rather than automatically waking when the condition becomes true.
- A single condition variable may wake up the same type of thread repeatedly.
- No further signals can be sent, leading to deadlock.
- Role of the Operating System:
 - Manages thread scheduling and CPU time allocation
 - Does not manage thread synchronization or signal passing
 - Cannot wake threads
- Thread Communication:
 - Synchronization happens through condition variables (signals) and mutexes
 - Signals must be explicitly sent and received between threads
 - Proper signal passing is critical for correct thread coordination



Why Two Condition Variables Prevent Deadlock

- A producer's 'not_empty' signal only wakes consumers.
- A consumer's 'not_full' signal only wakes producers.
- At least one thread type can always proceed and change the buffer state
- Eliminates the possibility of all threads waiting at the same time

34 / 41

Limitations of Condition Variables

- Imagine a buffer with 5 slots, initially empty / full.
- If 5 producer / consumer threads want to produce / consume 'O', a condition variable only allows one thread to produce / consume at a time.
- But what if we want multiple threads to produce / consume 'O' concurrently?

Semaphores

- Semaphore is a synchronization mechanism used to control access to shared resources in concurrent systems.
- It acts as an integer counter that tracks the availability of a limited number of resources.
- It can allow multiple threads to enter the critical section simultaneously.
 - However, you must ensure that there are no race conditions when multiple threads are in the critical section. If there are no such issues, semaphores can be used effectively.

Semaphore Operations

- Semaphores were first introduced by Edsger W. Dijkstra in the 1960s.
- Semaphores operate similarly to condition variables, allowing threads to wait and be signaled based on certain conditions.

Semaphores have two primary operations:

- P operation (from Dutch proberen, meaning "to try"):
 - Decreases the semaphore's value by 1.
 - If the value becomes negative, the thread performing the P operation is blocked until the semaphore's value becomes positive.
- **V operation** (from Dutch *verhogen*, meaning "to increment"):
 - Increases the semaphore's value by 1.
 - If there are any blocked threads, the V operation wakes up one of them.



Code Comparison

```
// Condition Variables
void *Tproduce(void *arg)
 while (1) {
   pthread mutex lock(&lk
   while (count == n) {
    pthread cond wait (&
        not full, &lk);
   count++;
   printf("0");
   pthread cond signal (&
      not_empty);
   pthread_mutex_unlock(&
      lk);
 return NULL;
```

```
// Semaphores
void *Tproduce(void *arg)
 while (1) {
   P(&empty sem);
   pthread_mutex_lock(&
      mutex);
   printf("0");
   pthread mutex unlock(&
      mutex);
   V(&full sem);
 return NULL;
```

Semaphores vs Condition Variables: Key Differences

Resource Management:

- Semaphores have a built-in counter to manage resource availability.
- Condition variables do not track resource availability. The programmer must manage resource state manually.

• Wait/Wake Mechanism:

- Semaphores use the P (wait) and V (signal) operations to automatically handle the blocking and unblocking of threads.
- Condition variables use **pthread_cond_wait()** to put a thread to sleep and pthread_cond_signal() or pthread_cond_broadcast() to wake up waiting threads.

Mutex Usage:

- Semaphores can be used with or without a mutex, allowing multiple threads to access the critical section simultaneously based on the semaphore's value.
- Condition variables must be used with a mutex, typically allowing only one thread in the critical section at a time, even if multiple threads are woken up.

39 / 41

Semaphores without Mutex

```
void *Tproduce(void *arg)
    {
    while (1) {
       P(&empty_sem);
       printf("O");
       V(&full_sem);
    }
    return NULL;
}
```

```
void *Tconsume(void *arg)
{
  while (1) {
    P(&full_sem);
    printf("X");
    V(&empty_sem);
  }
  return NULL;
}
```

Link of Code: Semaphores without Mutex Example Code

Considerations for Semaphore Usage

- If you plan to implement more complex buffer operations (e.g., actually storing data instead of just printing characters), you will need to use a mutex to avoid race conditions.
- While semaphores may seem convenient, they become less effective as more rules are added, making them harder to

Takeaways

- Most of the synchronization problems you will face are just variations of the **Producer-Consumer problem**.
- Mastering condition variables is enough to handle most real-world scenarios.
- The rest is just icing on the cake.

