NSD NETWORK DAY03

1. 案例1: 动态路由


2. <u>案例2</u>: 基本ACL的配置 (1) 3. 案例3: 基本ACL的配置 (2)

4. 案例4: 高级ACL

1案例1: 动态路由

1.1 问题

通过配置静态路由协议ospf实现全网互通



1.2 步骤

S3700交换机配置

- 01. [Huawei]vlan batch 2 3 //创建VLAN2、3
 02. [Huawei]interface Ethernet0/0/2
 03. [Huawei-Ethernet0/0/2]port default vlan 2
 04. [Huawei]interface Ethernet0/0/3
 05. [Huawei-Ethernet0/0/3]port default vlan 3
 06. [Huawei]interface Ethernet0/0/22
 07. [Huawei-Ethernet0/0/22]port link-type trunk

[Huawei-Ethernet0/0/22]port trunk allow-pass vlan all

S5700交换机配置

08.

Top

01. [Huawei]vlan batch 2 3 4 //创建VLAN2、3、4

- 02. [Huawei]interface Vlanif 1
- 03. [Huawei-Vlanif4]ip address 192.168.1.254 24
- 04. [Huawei]interface Vlanif 2
- 05. [Huawei-Vlanif4]ip address 192.168.2.254 24
- 06. [Huawei]interface Vlanif 3
- 07. [Huawei-Vlanif4]ip address 192.168.3.254 24
- 08. [Huawei]interface Vlanif 4
- 09. [Huawei-Vlanif4]ip address 192.168.4.1 24

10.

- 11. [Huawei]interface GigabitEthernet 0/0/1
- 12. [Huawei-GigabitEthernet0/0/1] port link-type trunk
- 13. [Huawei-GigabitEthernet0/0/1] port trunk allow-pass vlan all
- 14. [Huawei]interface GigabitEthernet 0/0/2
- 15. [Huawei-GigabitEthernet0/0/2] port link-type access
- 16. [Huawei-GigabitEthernet0/0/2] port default vlan 4
- 17. [Huawei]ospf 1
- 18. [Huawei-ospf-1]area 0
- 19. [Huawei-ospf-1-area-0.0.0.0]network 192.168.1.0 0.0.0.255
- 20. [Huawei-ospf-1-area-0.0.0.0]network 192.168.2.0 0.0.0.255
- 21. [Huawei-ospf-1-area-0.0.0.0]network 192.168.3.0 0.0.0.255
- 22. [Huawei-ospf-1-area-0.0.0.0]network 192.168.4.0 0.0.0.255
- 23. [Huawei]ip route-static 0.0.0.0 0.0.0.0 192.168.4.2

路由器配置

- 01. [Huawei]interface GigabitEthernet 0/0/0
- 02. [Huawei-GigabitEthernet0/0/0] ip address 192.168.4.2 24
- 03. [Huawei]interface GigabitEthernet 0/0/1
- 04. [Huawei-GigabitEthernet0/0/0] ip address 192.168.5.254 24
- 05. [Huawei]ospf 1
- 06. [Huawei-ospf-1]area 0
- 07. [Huawei-ospf-1-area-0.0.0.0]network 192.168.4.0 0.0.0.255

2 案例2:基本ACL的配置 (1)

2.1 问题

按照图-2所示拓扑结构,禁止主机pc2与pc1通信,而允许所有其他流量

Top




图-2

2.2 步骤

- 1,为路由器g0/0/0接口配置ip 192.168.1.254,为路由器g0/0/1接口配置ip 192.168.2.254
 - 01. [Huawei]interface GigabitEthernet 0/0/0
 - 02. [Huawei-GigabitEthernet0/0/0] ip address 192.168.1.254 24
 - 03. [Huawei]acl 2000
 - 04. [Huawei-acl-basic-2000]rule deny source 192.168.2.1 0
 - 05. [Huawei]interface GigabitEthernet 0/0/1
 - 06. [Huawei-GigabitEthernet0/0/1]ip address 192.168.2.254 24
 - 07. [Huawei-GigabitEthernet0/0/1]traffic-filter inbound acl 2000

3 案例3:基本ACL的配置 (2)

3.1 问题

按照图-3所示拓扑结构,允许主机pc2与pc1互通,而禁止其他设备访问pc1




图-3

3.2 步骤

注:此案例需要提前配置好所有设备的ip地址

<u>Top</u>

- 01. [Huawei]acl 2001
- 02. [Huawei-acl-basic-2001]rule permit source 192.168.2.1 0
- 03. [Huawei-acl-basic-2001]rule deny source any
- 04. [Huawei]interface GigabitEthernet 0/0/1
- 05. [Huawei-GigabitEthernet0/0/1]undo traffic-filter inbound acl 2000
- 06. [Huawei-GigabitEthernet0/0/1] traffic-filter inbound acl 2001

4 案例4: 高级ACL

4.1 问题

按照图-4所示拓扑结构,禁止pc2访问pc1的ftp服务,禁止pc3访问pc1的www服务,所有主机的 其他服务不受限制




图-4

4.2 步骤

注:此案例需要提前配置好所有设备的ip地址

- 01. [Huawei]acl 3000
- 02. [Huawei-acl-adv-3000]rule deny tcp source 192.168.2.1 0 destination 192.168.1.1
- 03. 0 destination-port eq 21
- 04. [Huawei-acl-adv-3000]rule deny tcp source 192.168.2.2 0 destination 192.168.1.1
- 05. 0 destination-port eq 80
- 06. [Huawei]interface g0/0/1
- 07. [Huawei-GigabitEthernet0/0/1]traffic-filter inbound acl 3000 //在接口中应用acl

Top