Moving Picture Experts Group (MPEG) of ISO/IEC JTC 1/SC 29/WG 7

April 2022, Online

Title: V3C/V-PCC test model v18.0 user manual

Status: Draft

Purpose: User manualAuthor(s): Julien Ricard

julien.ricard@interdigital.com

Document: MPEG-wXXXXX

Source: 3DG

Abstract

This document is a user manual describing usage of reference software for the V3C/V-PCC project. It applies to version 18.0 of the software.

Contents

1	Gen	eral Information	1
	1.1	Bug reporting	2
2	Obta	nining the software	2
	2.1	Clone	2
	2.2	Building	2
		2.2.1 Scripts	2
		2.2.2 OSX	2
		2.2.3 Linux	2
		2.2.4 Windows	2
		2.2.5 External dependencies	2
3	Stru	cture of the test model	4
4	Usin	g the codec	5
	4.1	Principle	5
	4.2		5
	4.3	Examples	6
		4.3.1 Encoder	6
		4.3.2 Decoder	6
		4.3.3 Metrics	6
		4.3.4 Scripts	7
		4.3.5 SHVC Information	7
	4.4	General options	8
		4.4.1 Encoder parameters	8
		4.4.2 Decoder parameters	3
		4.4.3 Metrics parameters	4
5	Refe	rences 15	5

1 General Information

Reference software is being made available to provide a reference implementation of the V3C standard being developed by MPEG (ISO/IEC JTC 1/SC 29/WG 7). One of the main goals of the reference software is to provide a basis upon which to conduct experiments in order to determine which coding tools provide desired coding performance. It is not meant to be a particularly efficient implementation of anything, and one may notice its apparent unsuitability for a particular use. It should not be construed to be a reflection of how complex a production-quality implementation of a future V3C standard would be.

This document aims to provide guidance on the usage of the reference software. It is widely suspected

to be incomplete and suggestions for improvements are welcome. Such suggestions and general inquiries may be sent to the general MPEG 3DGC email reflector at mpeg-3dgc@gti.ssr.upm.es (registration required).

1.1 Bug reporting

Bugs should be reported on the issue tracker set up at http://mpegx.int-evry.fr/software/MPEG/PCC/TM/mpeg-pcc-tmc2/issues.

2 Obtaining the software

2.1 Clone

The authoritative location of the software is the following git repository: http://mpegx.int-evry.fr/software/MPEG/PCC/TM/mpeg-pcc-tmc2

Each released version may be identified by a version control system tag in the form release-v18.0 [1].

An example:

```
$ git clone \
   http://mpegx.int-evry.fr/software/MPEG/PCC/mpeg-pcc-tmc2.git
$ cd mpeg-pcc-tmc2
```

It is strongly advised to obtain the software using the version control system rather than to download a zip (or other archive) of a particular release. The build system uses the version control system to accurately identify the version being built.

2.2 Building

The codec is supported on Linux, OSX and Windows platforms. The build configuration is managed using CMake.

It is strongly advised to build the software in a separate build directory.

2.2.1 Scripts

Bash scripts can be use to build mpeg-pcc-tmc2 project: - build.sh: build solutions.

- clear.sh: clear solututions (./clear.sh all: to clear dependencies)

2.2.2 OSX

```
$ mkdir build
$ cd build
$ cmake ..
$ cmake --build . --config Release --parallel 8
2.2.3 Linux
$ mkdir build
$ cd build
$ cmake ..
$ cmake --build . --config Release --parallel 8
2.2.4 Windows
$ md build
$ cd build
$ cmake ..
$ cmake ..
$ cmake --build . --config Release --parallel 8
```

2.2.5 External dependencies

According to the CMake options defined in the CMakeLists.txt, the TMC2 required some external dependencies to work:

- USE_JMAPP_VIDEO_CODEC: use JM software to encoder and decoder videos (codecId parameters must be set equal to 0 and the videoEncoderOccupancyPath, videoEncoderGeometryPath and videoEncoderAttributePath but be set the JM applications)
- USE_HMAPP_VIDEO_CODEC: use HM software to encoder and decoder videos (codecId parametesr must be set equal to 1 and the videoEncoderOccupancyPath, videoEncoderGeometryPath and videoEncoderAttributePath but be set the JM applications)

- USE_JMLIB_VIDEO_CODEC: use JM library to encoder and decoder videos (codecId parameter must be set equal to 2)
- USE_HMLIB_VIDEO_CODEC: use HM library to encoder and decoder videos (codecId parameter must be set equal to 3)
- USE_VTMLIB_VIDEO_CODEC: use VTM library to encoder and decoder videos (codecId parameter must be set equal to 4)
- USE_FFMPEG_VIDEO_CODEC: use FFMPEG library to encoder and decoder videos (codecId parameter must be set equal to 5). This mode is only available in the FFMPEG branch.
- USE_SHMAPP_VIDEO_CODEC: use SHM software to encoder and decoder videos (codecId parameters must be set equal to 6, the videoEncoderGeometryPath and videoEncoderAttributePath using the SHM application, and the videoEncoderOccupancyPath using the HM application)
- USE_HDRTOOLS: use HDRTools to convert the raw video files.

The video encoder softwares and libraries can be found in the corresponding repositories:

- JM: https://vcgit.hhi.fraunhofer.de/jct-vc/JM.git
- HM: https://vcgit.hhi.fraunhofer.de/jvet/HM.git
- VTM: https://vcgit.hhi.fraunhofer.de/jvet/VVCSoftware_VTM.git
- SHM: https://vcgit.hhi.fraunhofer.de/jvet/SHM.git

Some changes have been made on these libraries to allow to use the three libraries at the same time and to increase the codec efficiencies for the V3C contents. the three codecs must be patch with the files:

- JM: dependencies/jm-modification/PCC_JM.patch
- HM: dependencies/hm-modification/pcc_me-ext_and_namespace_for_HM-16.20+SCM-8.8.patch
- VTM: dependencies/vtm-modification/adaptions_for_vtm_11_2.patch

By default according the the CMake options, the dependencies are cloned and patched by the cmake process.

The external dependencies could be downloaded, built and linked independenly.

JM:

```
$ git clone checkout \
       https://vcgit.hhi.fraunhofer.de/jct-vc/JM.git \
       dependencies/jm19.0_lib
   $ cd dependencies/jm19.0_lib
   $ git patch ../jm-modification/PCC_JM.patch
HM:
   $ git clone checkout \
       https://vcgit.hhi.fraunhofer.de/jvet/HM.git \
       dependencies/HM-16.20+SCM-8.8
   $ cd dependencies/HM-16.20+SCM-8.8
   $ git patch ../hm-modification/\
               pcc_me-ext_and_namespace_for_HM-16.20+SCM-8.8.patch
VTM:
   $ git clone checkout \
       https://vcgit.hhi.fraunhofer.de/jvet/VVCSoftware_VTM.git \
       dependencies/VTM-11.2
   $ cd dependencies/VTM-11.2
   $ git patch .../vtm-modification/adaptions_for_vtm_11_2.patch
HDRTools:
    $ git clone -b 0.17-dev \
```

```
https://gitlab.com/standards/HDRTools.git \
dependencies/HDRTools
```

The pointcloud metrics can be computed inside the TM2 encoder and decoder according to the input parameters:

- computeMetrics: Compute metrics
- uncompressedDataPath: Input pointcloud to encode. Multi-frame sequences may be represented by %04i
- normalDataPath: Input pointcloud to encode. Multi-frame sequences may be represented by %04i
- resolution: Specify the intrinsic resolution
- dropdups: 0(detect), 1(drop), 2(average) subsequent points with same coordinates
- neighborsProc: 0(undefined), 1(average), 2(weighted average), 3(min), 4(max) neighbors with same geometric distance

The computations of the metrics are the same than the distances computed with the pcc_distortion software that can be found in: http://mpegx.int-evry.fr/software/MPEG/PCC/mpeg-pcc-dmetric.git.

3 Structure of the test model

This software consists of mutliple executables and libraries. The two main applications are PccAppEncoder and PccAppDecoder, that are the applications used to encode and decode the point clouds. These software are directly linked to the two main libraries: PccLibEncoder and PccLibDecoder that containe the main encoder and decoder processes. The processes and the data structures used both by encoder and decoder are in the PccLibCommon library. The VPCC bitstreams data structures are defined in library: PccLibBitstreamCommon. The encoder and decoder bitstreamer writing and reading processes are stored in to separate libraries: PccLibBitstreamWriter and PccLibBitstreamReader.

Additional of these two libraries, the virtual wrapper libraries are used to encode video (PccLibVideoEncoder), to decode video (PccLibVideoDecoder) and to perform color conversion of the video streams (PccLibColorConverter). These libraries are wrappers and are used to launch external applications or libraries: HDRTools, HM Encoder/Decoder (TLibEncoder/TLibDecoder). These libraries defined application program interfaces (API) to easyly launch external processes to perform these tasks without change the VPCC source code.

The below figure is the module dependency draph of the VPCC reference software.




Figure 1 – Structure of the test model

4 Using the codec

```
$ ../bin/PccAppEncoder [--help] [-c config.cfg] [--parameter=value] $ ../bin/PccAppDecoder [--help] [--parameter=value]
```

\$../bin/PccAppMetrics [--help] [--parameter=value]

4.1 Principle

The encoder takes as input a PLY file describing a point cloud with integer positions and, optionally, per-point integer colour attributes.

The output of the encoder is a binary bitstream encapsulated using the V3C annex-B format.

Conversely, the decoder takes as input a compressed bitstream file in V3C annex-B format and produces a reconstructed PLY file with position and any present attribute values.

The software may be configured using either command line arguments or from a configuration file specified using the -c|-config= option.

Sample configuration files are provided in the cfg/ directory.

Parameters are set by the last value encountered on the command line. Therefore if a setting is set via a configuration file, and then a subsequent command line parameter changes that same setting, the command line parameter value will be used.

4.2 Common test condition configurations

Configuration files are provided in the cfg directory to aid configuring the encoder. The general pattern of usage is illustrated below, where multiple configuration files control different aspects of the test conditions.

NB: parameters set in one configuration file override the same parameter in earlier files. ie. order matters.

Further help text describing option usage is available using "./bin/PccAppEncoder -help" or "./bin/PccAppDecoder

-help".

4.3 Examples

4.3.1 Encoder

The next command line encodes one streams:

```
$ ./bin/PccAppEncoder \
    --config=./cfg/common/ctc-common.cfg \
    --config=./cfg/condition/ctc-all-intra.cfg \
    --config=./cfg/sequence/queen.cfg \
    --config=./cfg/rate/ctc-r1.cfg \
    --colorTransform=0 \
    --configurationFolder=./cfg/ \
    --uncompressedDataFolder=./People/ \
    --colorSpaceConversionPath=HDRConvert \
    --videoEncoderPath=TAppEncoderHighBitDepthStatic \
    --videoEncoderOccupancyMapPath=TAppEncoderHighBitDepthStatic \
    --compressedStreamPath=./S22C2AI_queen/S22C2AIR01_queen.bin \
    --frameCount=32
```

To compute the metrics in the encode, the normal of the source point cloud must be given to the encoder. The next parameter must be added to the previous command:

```
--normalDataPath=./People/Technicolor/queen_n/frame_%04d_n.ply
```

4.3.2 Decoder

The next command line decodes one streams:

```
$ ./bin/PccAppDecoder \
    --startFrameNumber=0000 \
    --compressedStreamPath=./S22C2AI_queen/S22C2AIR01_queen.bin \
    --reconstructedDataPath=./S22C2AI_queen/S22C2AIR01_queen_dec_%04d.ply \
    --videoDecoderPath=TAppDecoderHighBitDepthStatic \
    --videoDecoderOccupancyMapPath=TAppDecoderHighBitDepthStatic \
    --colorSpaceConversionPath=./external/HDRTools/bin/HDRConvert \
    --inverseColorSpaceConversionConfig=./cfg/hdrconvert/yuv420torgb444.cfg \
    --nbThread=1 \
    --colorTransform=0 \
```

To compute the metrics in the decoder, the normal of the source point cloud and the source PLY must be given to the decoder. The next parameter must be added to the previous command:

```
--config=./cfg/sequence/queen.cfg \
--uncompressedDataFolder=./People/ \
--normalDataPath=./People/Technicolor/queen_n/frame_%04d_n.ply
```

4.3.3 Metrics

PccAppMetrics could be used to test the PccLibMetrics. For CTC experiments, it's sugested to used mpeg-pcc-dmetrics: http://mpegx.int-evry.fr/software/MPEG/PCC/mpeg-pcc-dmetric.git.

For example, mpeg-pcc-dmetric and PccAppMetric could be used with the next command line:

```
$ ../bin/PccAppMetrics \
   --uncompressedDataPath=longdress_vox10_1051.ply \
   --reconstructedDataPath=./S26C2AIR01_longdress_dec_1051.ply \
   --normalDataPath=./People/8i/longdress_n/longdress_vox10_1051_n.ply \
   --resolution=1023 \
   --frameCount=1

$ ./mpeg-pcc-demetric/test/pc_error \
```

```
--fileA=./People/8i/8iVFBv2/longdress/Ply/longdress_vox10_1051.ply \
--fileB=S26C2AIR01_longdress_dec_1051.ply \
--inputNorm=./People/8i/longdress_n/longdress_vox10_1051_n.ply \
--color=1 \
--resolution= 1023
```

The two softwares give the same results.

4.3.4 Scripts

More examples of running could be found in ./test/runme_linux.sh.

These examples can be start based on your system with the following scripts: * ./test/runme_linux.sh * ./test/runme_windows.bat * ./test/runme_osx.sh

The V3C common test condition (CTC) command lines could be found in ./test/ctc_command_line.sh.

4.3.5 SHVC Information

The SHVC software used in the program can be obtained from the link below:

```
https://hevc.hhi.fraunhofer.de/svn/svn_SHVCSoftware/tags/SHM-12.4/
```

The additional Enhanced Layer will be used by SHVC codec according to the number of entries entered in the SHVCLayer in the encoder. SHVCRateX and SHVCRateY refer to the width and height resolution reduction rate of 2D images of additional layers. The decoder uses the video corresponding to the layer entered into the SHVCLayerID. LID 0 has the lowest density, and if 3 layers are used, LID 2 has the same density as V-PCC TMC2 output. Occupancy Map video encode/decode using same version of HM encooder/decoder.

SHVC Running 3layer PccAppEncoder

```
$ ./bin/PccAppEncoder \
    --configurationFolder=cfg/ \
    --config=cfg/common/ctc-common.cfg \
    --config=cfg/condition/ctc-random-access-svc-3L.cfg \
    --config=cfg/sequence/longdress_vox10.cfg \
    --config=cfg/rate/ctc-r3.cfg \
    --uncompressedDataFolder=Dynamic_Objects/People/ \
    --frameCount=1 \
    --videoEncoderGeometryPath=..\bin\win\TAppEncoder.exe \
    --videoEncoderAttributePath=..\bin\win\TAppEncoder.exe \
    --videoEncoderOccupancyPath=..\bin\win\occupancy\TAppEncoder.exe \
    --colorSpaceConversionPath=../external/HDRTools/bin/HDRConvert \
    --reconstructedDataPath=S26C03R03_rec_%04d.ply \
    --compressedStreamPath=S26C03R03.bin \
    --SHVCLayer=2 \
    --SHVCRateX=2 \setminus
    --SHVCRateY=2
```

SHVC Running 3layer PccAppDecoder

4.4 General options

The next tables shows the parameters of the encoder, decoder and metrics programs.

4.4.1 Encoder parameters

help This help text Global config Configuration file name configurationFolder Folder where the configuration files are stored, use for cfg relative paths. uncompressedDataFolder Folder where the uncompress input data are stored, use for cfg relative paths. uncompressedDataPath Input pointcloud to encode. Multi-frame sequences may be represented by %04i compressedStreamPath Output(encoder)/Input(decoder) compressed bitstream reconstructedDataPath Output decoded pointcloud. Multi-frame sequences may be represented by %04i forcedSsvhUnitSizePrecisionBytes forced SSVH unit size precision bytes startFrameNumber First frame number in sequence to encode/decode frameCount Number of frames to encode groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444 to YUV420 conversion
configurationFolder configurationFolder Folder where the configuration files are stored, use for cfg relative paths. uncompressedDataFolder Folder where the uncompress input data are stored, use for cfg relative paths. uncompressedDataPath Input pointcloud to encode. Multi-frame sequences may be represented by %04i compressedStreamPath Output(encoder)/Input(decoder) compressed bitstream reconstructedDataPath Output decoded pointcloud. Multi-frame sequences may be represented by %04i forcedSsvhUnitSizePrecisionBytes forced SSVH unit size precision bytes startFrameNumber First frame number in sequence to encode/decode frameCount Number of frames to encode groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
configurationFolder Folder where the configuration files are stored, use for cfg relative paths. uncompressedDataFolder Folder where the uncompress input data are stored, use for cfg relative paths. uncompressedDataPath Input pointcloud to encode. Multi-frame sequences may be represented by %04i compressedStreamPath Output(encoder)/Input(decoder) compressed bitstream reconstructedDataPath Output decoded pointcloud. Multi-frame sequences may be represented by %04i forcedSsvhUnitSizePrecisionBytes forced SsVH unit size precision bytes startFrameNumber First frame number in sequence to encode/decode frameCount Number of frames to encode groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
stored,use for cfg relative paths. uncompressedDataFolder Folder where the uncompress input data are stored, use for cfg relative paths. uncompressedDataPath Input pointcloud to encode. Multi-frame sequences may be represented by %04i compressedStreamPath Output(encoder)/Input(decoder) compressed bitstream reconstructedDataPath Output decoded pointcloud. Multi-frame sequences may be represented by %04i forcedSsvhUnitSizePrecisionBytes startFrameNumber First frame number in sequence to encode/decode frameCount Number of frames to encode groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
uncompressedDataFolder Folder where the uncompress input data are stored, use for cfg relative paths. Input pointcloud to encode. Multi-frame sequences may be represented by %04i compressedStreamPath Output(encoder)/Input(decoder) compressed bitstream reconstructedDataPath Output decoded pointcloud. Multi-frame sequences may be represented by %04i forcedSsvhUnitSizePrecisionBytes startFrameNumber First frame number in sequence to encode/decode frameCount Number of frames to encode groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
stored, use for cfg relative paths. uncompressedDataPath Input pointcloud to encode. Multi-frame sequences may be represented by %04i compressedStreamPath Output(encoder)/Input(decoder) compressed bitstream reconstructedDataPath Output decoded pointcloud. Multi-frame sequences may be represented by %04i forcedSsvhUnitSizePrecisionBytes startFrameNumber First frame number in sequence to encode/decode frameCount groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
uncompressedDataPath Input pointcloud to encode. Multi-frame sequences may be represented by %04i compressedStreamPath Output(encoder)/Input(decoder) compressed bitstream reconstructedDataPath Output decoded pointcloud. Multi-frame sequences may be represented by %04i forcedSsvhUnitSizePrecisionBytes startFrameNumber First frame number in sequence to encode/decode frameCount groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
sequences may be represented by %04i CompressedStreamPath Output(encoder)/Input(decoder) compressed bitstream reconstructedDataPath Output decoded pointcloud. Multi-frame sequences may be represented by %04i forcedSsvhUnitSizePrecisionBytes forced SSVH unit size precision bytes startFrameNumber First frame number in sequence to encode/decode frameCount groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
compressedStreamPath Output(encoder)/Input(decoder) compressed bitstream reconstructedDataPath Output decoded pointcloud. Multi-frame sequences may be represented by %04i forcedSsvhUnitSizePrecisionBytes startFrameNumber First frame number in sequence to encode/decode frameCount Number of frames to encode groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
reconstructedDataPath Output decoded pointcloud. Multi-frame sequences may be represented by %04i forcedSsvhUnitSizePrecisionBytes startFrameNumber First frame number in sequence to encode/decode frameCount Number of frames to encode groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
reconstructedDataPath Output decoded pointcloud. Multi-frame sequences may be represented by %04i forcedSsvhUnitSizePrecisionBytes startFrameNumber First frame number in sequence to encode/decode frameCount groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
sequences may be represented by %04i forcedSsvhUnitSizePrecisionBytes forced SSVH unit size precision bytes startFrameNumber First frame number in sequence to encode/decode frameCount Number of frames to encode groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
forcedSsvhUnitSizePrecisionBytes startFrameNumber First frame number in sequence to encode/decode frameCount groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
startFrameNumber First frame number in sequence to encode/decode frameCount Number of frames to encode groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
frameCount Number of frames to encode groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
frameCount groupOfFramesSize Random access period colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
groupOfFramesSize colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
colorTransform The colour transform to be applied: 0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
0: none 1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
1: RGB to YCbCr (Rec.709) colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
colorSpaceConversionPath Path to the HDRConvert. If unset, an internal color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
color space conversion is used colorSpaceConversionConfig HDRConvert configuration file used for RGB444
colorSpaceConversionConfig HDRConvert configuration file used for RGB444
to YUV420 conversion
inverseColorSpaceConversionConfig HDRConvert configuration file used for YUV420
to RGB444 conversion
gridBasedSegmentation Voxel dimension for grid-based segmentation (GBS)
voxelDimensionGridBased Voxel dimension for grid-based segmentation (GBS)
Segmentation
nnNormalEstimation Number of points used for normal estimation
normalOrientation Normal orientation: 0: None 1: spanning tree,
2:view point, 3:cubemap projection
gridBasedRefineSegmentation Use grid-based approach for segmentation
refinement
maxNNCountRefineSegmentation Number of nearest neighbors used during
segmentation refinement
iterationCountRefineSegmentation Number of iterations performed during
segmentation refinement
voxelDimensionRefineSegmentation Voxel dimension for segmentation refinement
(must be a power of 2)
searchRadiusRefineSegmentation Search radius for segmentation refinement
occupancyResolution Resolution of packing block(a block contain
only one patch)
enablePatchSplitting Enable patch splitting
maxPatchSize Maximum patch size for segmentation
log2QuantizerSizeX log2 of Quantization step for patch size X:
0. pixel precision 4.16 as before

log2QuantizerSizeY	log2 of Quantization step for patch size Y:
	0. pixel precision 4.16 as before
minPointCountPerCCPatch	Minimum number of points for a connected
Segmentation	component to be retained as a patch
maxNNCountPatchSegmentation	Number of nearest neighbors used during
	connected components extraction
surfaceThickness	Surface thickness
depthQuantizationStep	minimum level for patches
maxAllowedDist2RawPointsDetection	Maximum distance for a point to be ignored
	during raw points detection
maxAllowedDist2RawPointsSelection	Maximum distance for a point to be ignored
	during raw points selection
lambdaRefineSegmentation	Controls the smoothness of the patch
	boundaries during segmentation refinement
minimumImageWidth	Minimum width of packed patch frame
minimumImageHeight	Minimum height of packed patch frame
maxCandidateCount	Maximum nuber of candidates in list L
occupancyPrecision	Occupancy map B0 precision
occupancyMapConfig	Occupancy map encoder config file
occupancyMapQP	QP for compression of occupancy map video
enhancedOccupancyMapCode	Use enhanced-delta-depth code
EOMFixBitCount	enhanced occupancy map fixed bit count
occupancyMapRefinement	Use occupancy map refinement
decodedAtlasInformationHash	Enable decoded atlas information hash: 0. disable
	1.MD5 2.CRC 3.Checksum
attributeTransferFilterType	Exclude geometry smoothing from attribute transfer
flagGeometrySmoothing	Enable geometry smoothing
neighborCountSmoothing	Neighbor count smoothing
radius2Smoothing	Radius to smoothing
radius2BoundaryDetection	Radius to boundary detection
thresholdSmoothing	Threshold smoothing
patchExpansion	Use occupancy map refinement
gridSmoothing	Enable grid smoothing
gridSize	grid size for the smoothing
thresholdColorSmoothing	Threshold of color smoothing
cgridSize	grid size for the color smoothing
thresholdColorDifference	Threshold of color difference between cells
thresholdColorVariation	Threshold of color variation in cells
flagColorSmoothing	Enable color smoothing
thresholdColorPreSmoothing	Threshold of color pre-smoothing
thresholdColorPreSmoothingLocal	
	Threshold of color pre-smoothing local
Entropy	entropy Padius of color pro smoothing
radius2ColorPreSmoothing	Radius of color pre-smoothing
neighborCountColorPreSmoothing	Neighbor count for color pre-smoothing
flagColorPreSmoothing	Enable color pre-smoothing
bestColorSearchRange	Best color search range
numNeighborsColorTransferFwd	Number of neighbors creating Fwd list
numNeighborsColorTransferBwd	Number of neighbors creating Bwd list
useDistWeightedAverageFwd	Distance weighted average for Fwd list
useDistWeightedAverageBwd	Distance weighted average for Bwd list
skipAvgIfIdenticalSourcePoint	Skip avgeraging if target is identical to a

PresentFwd	Fwd point
skipAvgIfIdenticalSourcePoint	Skip avgeraging if target is identical to a
PresentBwd	Bwd point
distOffsetFwd	Distance offset to avoid infinite weight
distOffsetBwd	Distance offset to avoid infinite weight
maxGeometryDist2Fwd	Maximum allowed distance for a Fwd point
maxGeometryDist2Bwd	Maximum allowed distance for a Bwd point
maxColorDist2Fwd	Maximum allowed pari-wise color distance for
	Fwd list
maxColorDist2Bwd	Maximum allowed pari-wise color distance for
	Bwd list
excludeColorOutlier	Exclude color outliers from the NN set
thresholdColorOutlierDist	Threshold of color distance to exclude
	outliers from the NN set
videoEncoderOccupancyPath	Occupancy video encoder executable path
videoEncoderGeometryPath	Geometry video encoder executable path
videoEncoderAttributePath	Attribute video encoder executable path
videoEncoderOccupancyCodecId	Occupancy video encoder codec id
videoEncoderGeometryCodecId	Geometry video encoder codec id
videoEncoderAttributeCodecId	Attribute video encoder codec id
videoEncoderInternalBitdepth	Video encoder internal bitdepth
byteStreamVideoEncoderOccupancy	Attribute video encoder outputs byteStream
byteStreamVideoEncoderGeometry	Attribute video encoder outputs byteStream
byteStreamVideoEncoderAttribute	Attribute video encoder outputs byteStream
geometryQP	QP for compression of geometry video
attributeQP	QP for compression of attribute video
auxGeometryQP	QP for compression of auxiliary geometry
	video : default=4 for lossy raw points,
	geometryQP for lossless raw points
auxAttributeQP	QP for compression of auxiliary attribute video
geometryConfig	HM configuration file for geometry compression
geometry0Config	HM configuration file for geometry 0 compression
geometry1Config	HM configuration file for geometry 1 compression
attributeConfig	HM configuration file for attribute compression
attribute0Config	HM configuration file for attribute 0 compression
attribute1Config	HM configuration file for attribute 1 compression
rawPointsPatch	Enable raw points patch
noAttributes	Disable encoding of attributes
attributeVideo444	Use 444 format for attribute video
useRawPointsSeparateVideo	Compress raw points with video codec
attributeRawSeparateVideoWidth	Width of the MP's attribute in separate video
geometryMPConfig	HM configuration file for raw points geometry
8. a. j - a. g	compression
attributeMPConfig	HM configuration file for raw points
	attribute compression
nbThread	Number of thread used for parallel processing
keepIntermediateFiles	Keep intermediate files: RGB, YUV and bin
absoluteD1	Absolute D1
absoluteT1	Absolute T1
multipleStreams	number of video(geometry and attribute) streams
deltaQPD0	qp adjustment for geometry0 video: 0, +3, -3
deltaQPD1	qp adjustment for geometry1 video: 0, +3, -3
	Tr angularitation Boombar j. Hacor o, 15, 5

deltaQPT0	qp adjustment for attribute0 video: 0, +3, -3
deltaQPT1	qp adjustment for attribute1 video: 0, +3, -3
constrainedPack	Temporally consistent patch packing
levelOfDetailX	levelOfDetail: X axis in 2D space (should be
	greater than 1)
levelOfDetailY	levelOfDetail: Y axis in 2D space (should be
	greater than 1)
groupDilation	Group Dilation
offsetLossyOM	Value to be assigned to non-zero occupancy map
	positions (default=0)
thresholdLossyOM	Threshold for converting non-binary occupancy
	map to binary (default=0)
prefilterLossyOM	Selects whether the occupany map is prefiltered
	before lossy compression (default=false)
shvcLayerIndex	Decode Layer ID number using SHVC codec
shvcRateX	SHVCRateX: reduce rate of each SHVC layer X
	axis in 2D space (should be greater than 1)
shvcRateY	SHVCRateY: reduce rate of each SHVC layer Y
	axis in 2D space (should be greater than 1)
patchColorSubsampling	Enable per patch color sub-sampling
maxNumRefAtalsList	maximum Number of Reference Atlas Frame list,
	default: 1
maxNumRefAtlasFrame	maximum Number of Reference Atlas Frame per
	list, default: 1
pointLocalReconstruction	Use point local reconstruction
mapCountMinus1	Numbers of layers (rename to maps?)
singleMapPixelInterleaving	Use single layer pixel interleaving
removeDuplicatePoints	Remove duplicate points(
surfaceSeparation	surface separation
highGradientSeparation	Separate high gradient points from a patch
minGradient	Minimun gradient for a point to be separated
minNumHighGradientPoints	Minimum number of connected high gradient
The state of the s	points to be separated from a patch
packingStrategy	Patches packing strategy(0: anchor packing,
pacinings autogy	1(default): flexible packing, 2: tetris
	packing)
useEightOrientations	Allow either 2 orientations (0(default): NULL
useDigitt Strentutions	AND SWAP), or 8 orientation (1))
safeGuardDistance	Number of empty blocks that must exist between
sure Guard Distance	the patches (default=1)
attributeBGFill	Selects the background filling operation for
attitude St in	attribute only (0: patch-edge extension,
	1(default): smoothed push-pull algorithm), 2:
	harmonic background filling
lossyRawPointsPatch	Lossy raw points patch(0: no lossy raw points
1000 j i will office aton	patch, 1: enable lossy raw points patch
	(default=0)
minNormSumOfInvDist4MPSelection	Minimum normalized sum of inverse distance
mmvormounioniv Distable Selection	for raw points selection: double value
	-
alahalDatah Allaastian	between 0.0 and 1.0 (default=0.35)
globalPatchAllocation	Global temporally consistent patch
	allocation.(0: anchor's packing

	method(default), 1: gpa algorithm, 2: gtp algorithm)
globalPackingStrategyGOF	Number of frames to pack globally (0:(entire GOF))
globalPackingStrategyReset	Remove the reference to the previous frame (0(default), 1)
globalPackingStrategyThreshold	Matched patches area ratio threshold (decides if connections are valid or not, 0(default))
patchPrecedenceOrder	Order of patches
lowDelayEncoding	Low Delay encoding (0(default): do nothing, 1: does not allow overlap of patches bounding boxes for low delay encoding)
geometryPadding	Selects the background filling operation for geometry (0: anchor, 1(default): 3D geometry padding)
apply3dMotionCompensation	Use auxilliary information for 3d motion compensation.(0: conventional video coding, 1: 3D motion compensated)
usePccRDO	Use HEVC PCC RDO optimization
geometry3dCoordinatesBitdepth	Bit depth of geomtery 3D coordinates
geometryNominal2dBitdepth	Bit depth of geometry 2D
nbPlrmMode	Number of PLR mode
patchSize	Size of Patch for PLR
enhancedProjectionPlane	Use enhanced Projection Plane(0: OFF, 1: ON)
minWeightEPP	Minimum value
additionalProjectionPlaneMode	additional projection plane mode: 0:none 1:Y-Axis 2:X-Axis 3:Z-Axis 4:All-Axis 5:apply
CALLEY ID CONT	to portion
partialAdditionalProjectionPlane	The value determines the partial point cloud.
	It's available with only
numMaxTilePerFrame	additionalProjectionPlaneMode(5) number of maximum tiles in a frame
uniformPartitionSpacing tilePartitionWidth	indictation of uniform partitioning uniform partition width in the unit of 64 pixels
tilePartitionHeight	uniform partition width in the unit of 64 pixels uniform partition height in the unit of 64 pixels
tilePartitionWidthList	non uniform partition width in the unit of 64 pixels
tilePartitionHeightListnon tileSegmentationType	uniform partition height in the unit of 64 pixels tile segmentation method : 0.no tile partition
thesegmentation type	1. 3D ROI based 2.2D Patch size based
enablePointCloudPartitioning	enablePointCloudPartitioning
roiBoundingBoxMinX	roiBoundingBoxMinX
roiBoundingBoxMaxX	roiBoundingBoxMaxX
roiBoundingBoxMinY	roiBoundingBoxMinY
roiBoundingBoxMaxY	roiBoundingBoxMaxY
roiBoundingBoxMinZ	roiBoundingBoxMinZ
roiBoundingBoxMaxZ	roiBoundingBoxMaxZ
numTilesHor	numTilesHor
tileHeightToWidthRatio	tileHeightToWidthRatio
numCutsAlong1stLongestAxis	numCutsAlong1stLongestAxis
numCutsAlong2ndLongestAxis	numCutsAlong2ndLongestAxis
numCutsAlong3rdLongestAx1s	numCutsAlong3rdLongestAxis
numCutsAlong3rdLongestAxis mortonOrderSortRawPoints	numCutsAlong3rdLongestAxis mortonOrderSortRawPoints

pbfEnableFlag	Enable patch block filtering
pbfFilterSize	pbfFilterSize
pbfPassesCount	pbfPassesCount
pbfLog2Threshold	pbfLog2Threshold
computeChecksum	Compute checksum
computeMetrics	Compute metrics
normalDataPath	Input pointcloud to encode. Multi-frame
	sequences may be represented by %04i
resolution	Specify the intrinsic resolution
dropdups	0(detect), 1(drop), 2(average) subsequent
	points with same coordinates
neighborsProc	0(undefined), 1(average), 2(weighted
	average), 3(min), 4(max) neighbors with same
	geometric distance
tierFlag	Tier Flag
profileCodecGroupIdc	Profile Codec Group Idc
profileToolsetIdc	Profile Toolset Idc
profileReconstructionIdc	Profile Reconstruction Idc
levelIdc	Level Idc
avcCodecIdIndex	Index for avc codec
hevcCodecIdIndex	Index for hevc codec
shvcCodecIdIndex	Index for shvc codec
vvcCodecIdIndex	Index for vvc codec
oneV3CFrameOnlyFlag	One V3C Frame Only Flag

4.4.2 Decoder parameters

Parameter=Value	Usage
help	This help text
Global	
c,config	Configuration file name
compressedStreamPath	Input
	compressed bitstream
reconstructedDataPath	Output decoded pointcloud. Multi-frame
	sequences may be represented by %04i
startFrameNumber	Fist frame number in sequence to
	encode/decode
colorTransform	The colour transform to be applied:
	0: none
	1: RGB to YCbCr (Rec.709)
colorSpaceConversion	Path to the HDRConvert. If unset, an
Path	internal color space conversion is
	used
inverseColorSpaceConversion	HDRConvert configuration file used for
Config	YUV420 to RGB444 conversion
videoDecoderOccupancyPath	Occupancy video decoder executable
videoDecoderGeometryPath	Geometry video decoder executable
videoDecoderAttributePath	Attribute video decoder executable
byteStreamVideoCoderOccupancy	Occupancy video decoder inputs byteStream
byteStreamVideoCoderGeometry	Geometry video decoder inputs byteStream
byteStreamVideoCoderAttribute	Attribute video decoder inputs byteStream
nbThread	Number of thread used for parallel

	processing
attributeTransferFilterType	Exclude geometry smoothing from attribute
	transfer
keepIntermediateFiles	Keep intermediate files: RGB, YUV and bin
shvcLayerIndex	Decode Layer ID number using SHVC codec
patchColorSubsampling	Enable per-patch color up-sampling
Metrics	
computeChecksum	Compute checksum
computeMetrics	Compute metrics
uncompressedDataFolder	Folder where the uncompress input data are
	stored, use for cfg relative paths.
startFrameNumber	Fist frame number in sequence to
	encode/decode
frameCount	Number of frames to encode
groupOfFramesSize	Random access period
uncompressedDataPath	Input pointcloud to encode. Multi-frame
	sequences may be represented by %04i
reconstructedDataPath	Output decoded pointcloud. Multi-frame
	sequences may be represented by %04i
normalDataPath	Input pointcloud to encode. Multi-frame
	sequences may be represented by %04i
resolution	Specify the intrinsic resolution
dropdups	0(detect), 1(drop), 2(average) subsequent
	points with same coordinates
neighborsProc	0(undefined), 1(average), 2(weighted
	average), 3(min), 4(max) neighbors with
	same geometric distance
nbThread	Number of thread used for parallel
	processing
minimumImageHeight	Ignore parameter
flagColorPreSmoothing	Ignore parameter
surfaceSeparation	Ignore parameter
Conformance	
checkConformance	Check conformance
path	Root directory of conformance files +
	prefix: S26C03R03_
level	Level indice
fps	Frame per second

4.4.3 Metrics parameters

Usage
This help text
Compute checksum
Compute metrics
Fist frame number in sequence to
encode/decode
Number of frames to encode
Input pointcloud to encode. Multi-frame
sequences may be represented by %04i
Output decoded pointcloud. Multi-frame
sequences may be represented by %04i

Input pointcloud to encode. Multi-frame
sequences may be represented by %04i
Specify the intrinsic resolution
0(detect), 1(drop), 2(average) subsequent
points with same coordinates
0(undefined), 1(average), 2(weighted
average), 3(min), 4(max) neighbors with
same geometric distance
Number of thread used for parallel
processing
Ignore parameter
Ignore parameter
Ignore parameter

5 References

- [1] "Common Test Conditions for PCC", ISO/IEC JTC1/SC29/WG07 MPEG/N00038, Jul. 2020, Online.
- [2] "V-PCC Test Model v18", ISO/IEC JTC1/SC29/WG07 MPEG/N00311, Apr. 2022, Online.