I/O Systems Operating Systems – EDA093/DIT401

Vincenzo Gulisano

vincenzo.gulisano@chalmers.se



Reading instructions

• Chapter 5.1 to 5.3

(extra facultative reading: 13.1-13.7 from Silberschatz Operating System Concepts)

Agenda

- Introduction
- I/O Hardware
- Application I/O Interface
- Kernel I/O Subsystem
- Performance

Agenda

- Introduction
- I/O Hardware
- Application I/O Interface
- Kernel I/O Subsystem
- Performance

Introduction

- Main jobs of a computer: I/O & processing.
- Role of OS: manage & control I/O operations & I/O devices.

OBJECTIVES:

- Explore structure of an OS's I/O subsystem
- Principles & complexities of I/O hardware
- Explain the performance aspects of I/O hardware & software.

Introduction









I/O challenge: control as good as possible the devices of a given architecture

Why is it a challenge?

- 1. Variability of I/O devices (in their function & speed)
 Varied methods are needed to control them.
- 2. Increasing standardization of software & hardware vs Increasing types of devices
- 3. Different details & oddities of devices

How does the OS address the challenge?

- dedicated I/O subsystem in the kernel
- **device drivers** that provide a **device access** interface to the I/O subsystem

Agenda

- Introduction
- I/O Hardware
- Application I/O Interface
- Kernel I/O Subsystem
- Performance

I/O Hardware

We have different types of hardware usually available in a computer:

- Storage devices (disks)
- Transmission devices (network cards)
- Human-interface devices (screen, keyboard, mouse)

All of them exchange information by sending signals (via cable or air)



How do they communicate with the CPU, then?



I/O Hardware

Common concepts:

- **Port**: the connection point (e.g., serial port)
- **Bus**: a set of wires & a protocol that specifies a set of messages that can be sent on the wires.
 - Messages conveyed by patterns of electrical voltages with different timings.
 - Buses vary in signaling methods, speed, throughput & connection methods.
- When device A plugs to device B and device B plugs to device C... We say A,B,C,... form a **daisy chain**
 - A daisy chain also operates as a bus


Typical PC bus structure

Important concepts:

- PCI bus: connects the processor-memory subsystem to the fast devices.
- Expansion bus: connects relatively slow devices.
- **Controller**: a collection of electronics that can operate a port, a bus or a device.

Example 1: Serial-port controller

- A single chip (on the host) that controls the signals on the wires of a serial port. Example 2: SCSI controller
- Contains a processor, a microcode, private memory to process the SCSI protocol messages (e.g., disk drive a circuit board).



I/O Hardware



How can the processor give commands & data to a controller to accomplish a I/O transfer?


1st Way of Communication

- Processor reads & writes bit patterns in the controllers' registers.
 - Use of special I/O instructions that specify the transfer of a byte or word to an I/O port address.
 - I/O instruction triggers bus lines to select the proper device & move bits into or out of a device register.


2nd Way of Communication: Memory mapped I/O

- Device-control registers are mapped into the address space of the processor.
- CPU executes I/O requests using the standard data transfer instructions to read and write the device-control registers.
- → Some systems use both ways of communication.


Processor reads & writes bit patterns in the controllers' registers



Memory mapped I/O



Example of Memory mapped I/O: graphics controller



Graphics controller: has large memory-mapped region to hold screen contents. Process **sends output** to the screen by writing data into the memory-mapped region. Controller generates **screen image** based on the contents of the memory.

Device I/O Port Locations on PCs

Usual I/O port addresses for PCs

I/O address range (hexadecimal)	device	
000-00F	DMA controller	
020–021	interrupt controller	
040–043	timer	
200–20F	game controller	
2F8–2FF	serial port (secondary)	
320–32F	hard-disk controller	
378–37F	parallel port	
3D0-3DF	graphics controller	
3F0-3F7	diskette-drive controller	
3F8–3FF	serial port (primary)	

I/O Hardware

I/O port typically consists of:

- Data-in register: is read by the host to get input (e.g. 1 to 4 bytes in size)
- Data-out register: is written by the host to send output
- Status register: contains bits that can be read by the host. Indicates states such as:
 - whether the current command has completed
 - whether a byte is available to be read
 - whether a device error has occurred
- Control register: to start a command or to change the mode of a device.

Example 1: a certain bit in the control register of a serial port chooses between full-duplex & half-duplex communication.

Example 2: another bit sets the word length to 7 or 8 bits, Other bits select one of the speeds supported by the serial port

Interaction between host and controller

- Complete interaction protocol between the host & a controller can be intricate.
 - **busy-waiting / polling:** the host is continuously trying to get access to the device via the controller
 - interrupt: the controller alerts the host when the device is available

Polling – Handshaking procedure

- 2 bits are used to coordinate the producer-consumer relationship between the controller & the host.
- Controller indicates its **state** through the busy bit in the status register.
- Host **signals** its wishes via the command-ready bit in the command register. **Command ready bit**: if it is set a command is available for the controller
- busy-waiting / polling: it is a loop, reading the status register over and over until the busy bit becomes clear.

Reasonable: If device controller & device are fast **Inefficient**: attempted repeatedly but device is busy.


• In such cases: hardware controller should notify the CPU when the device becomes ready for service \rightarrow this hardware mechanism is called interrupt.

Interrupts

Basic mechanism

- 1. CPU hardware has a wire called interrupt request line
- 2. CPU senses the interrupt request line after executing every instruction.
- 3. If yes, CPU performs a save state & jumps to the interrupt handler routine at a fixed address in memory.
- 4. Interrupt handler (IH): What was the cause of the interrupt?
- 5. IH performs the necessary processing, performs state restore
- 6. ... executes a return from interrupt instruction → return CPU to the execution state prior to the interrupt

Interrupts



Interrupts - Dictionary

- The device controller <u>raises</u> an interrupt
-by asserting a signal on the interrupt request line
- CPU <u>catches</u> the interrupt
- CPU <u>dispatches</u> it to the interrupt handler
- Handler <u>clears</u> the interrupt by servicing the device

Interrupts

Sophisticated Interrupt Handling

In a modern OS: we need sophisticated interrupt handling features

- Ability to defer interrupt handling during critical processing
- Efficient way to locate the proper interrupt handler for a device without asking all devices to see which one raised the interrupt
- Multi-level interrupts so that the OS can distinguish between **high** & **low level priority** interrupts

In modern OS these provided by CPU & interrupt controller hardware

Interrupts

Two interrupt request lines:

- Nonmaskable interrupt: reserved for events such as unrecoverable memory errors.
- Maskable interrupt: can be turned off by CPU before the execution of critical instruction requests.

Interrupt mechanism accepts an address: a number that selects a specific interrupt-handling routine from a small set.

This address is an **offset** in a table called interrupt vector

This vector contains the memory addresses of specialized interrupt handlers.

Interrupts – Intel Pentium processor event-vector table

	vector number	description
nonmaskab	0	divide error
	1	debug exception
	2	null interrupt
	3	breakpoint
	4	INTO-detected overflow
	5	bound range exception
	6	invalid opcode
	7	device not available
	8	double fault
	ole 9	coprocessor segment overrun (reserved)
	10	invalid task state segment
	11	segment not present
	12	stack fault
	13	general protection
	14	page fault
	15	(Intel reserved, do not use)
	16	floating-point error
	17	alignment check
	18	machine check
	19–31	(Intel reserved, do not use)
	32–255	maskable interrupts

Interrupts

OS & interrupts interaction

- A modern OS interacts with the interrupt mechanism in several ways.
- At boot time, **probes** the buses to see which devices are present and **installs the corresponding interrupt handler**.
- During I/O, device controllers **raise interrupts** when they are ready for service. These interrupts may mean:
 - output has completed
 - input data are available
 - or a failure has been detected

Direct Memory Access

Direct Memory Access

- Devices with large transfer e.g. disk drive.

 Not a good idea to use an expensive general-purpose processor to watch status bits & feed data into a controller register

 programmed I/O process.
- Use instead DMA controller
- Bypasses CPU to transfer data directly between I/O device & memory

DMA transfer


- To initiate a DMA transfer, host writes a DMA command block into memory.
- Block contains:
 - a pointer to the source of the transfer
 - a pointer to the destination of the transfer
 - a count of the number of bytes to be transferred.

Direct Memory Access

Handshaking between DMA controller & device controller

- Performed via a pair of wires: DMA request & DMA-acknowledge.
- A word of data available for transfer → device controller places a signal on the DMA-request wire
- DMA controller:
 - places the desired memory address on the memory-address wires.
 - places a signal on the DMA-acknowledge wire.
- Device controller receives the DMA-acknowledge signal & transfers the word of data to memory & removes the DMA-request signal.

Six Step Process to Perform DMA Transfer



Agenda


- Introduction
- I/O Hardware
- Application I/O Interface
- Kernel I/O Subsystem
- Performance

Application I/O Interface

• Goals:

- **Abstract away** the detailed differences in I/O devices by identifying a few general kinds.
- Encapsulate device behaviors in general
- Device-driver layer **hides differences** among I/O controllers from kernel.
- Make I/O subsystem independent of the hardware:
 - Simplifies the job of the OS.
 - Benefits the hardware manufacturers
 - Attach peripherals without waiting for new support code
 - BUT: each type of OS has its own standards for the device-driver interface.

Application I/O Interface



Application I/O Interface

aspect	variation	example
data-transfer mode	character block	terminal disk
access method	sequential random	modem CD-ROM
transfer schedule	synchronous asynchronous	tape keyboard
sharing	dedicated sharable	tape keyboard
device speed	latency seek time transfer rate delay between operations	
I/O direction	read only write only read–write	CD-ROM graphics controller disk

Devices vary in many dimensions:

- Character-stream or block: bytes one by one or blocks of bytes
- Sequential or random access: fixed order or random
- Synchronous or asynchronous: data transfers with predictable response times or not
- Sharable or dedicated: used concurrently by several processes or not
- Speed of operation: speeds range form a few bytes to gigabytes per sec
- Read-write, read only or write only: some both directions, others not

Block and Character Devices

Block devices include disk drives

Block-device interface all necessary aspects for accessing disk drives & other block-oriented devices

- Commands include read(), write(), seek()
- Memory-mapped file access possible

Character devices

- Include keyboards, mouse, serial ports
- Commands include get(), put()
- Libraries layered on top allow line editing

Network Devices

Network Devices

- Network I/O differs significantly form disks, the interface is not read(), write() and seek()
- Unix & Windows include socket interface
- System calls in the socket interface enable an application to
 - Create a socket
 - Connect to a remote socket

Socket Interface

- Connect local socket to a remote address
- Listen remote application to plug into the local socket
- Send & receive packets over the connection
- select() > return which sockets have a packet waiting to be received

Clocks & Timers

- Give current time.
- Give elapsed time.
- Set a timer to **trigger** operation X at time T.
- Programmable hardware interval timer: hardware to measure elapsed time & trigger operations
- Example: wait a certain amount of time & then generate an interrupt Cancel operations preceding too slowly
- Usual interrupt rate: between 18 & 60 ticks per sec.
- Hardware clock constructed from a high-frequency counter.

Blocking & Nonblocking I/O

Blocking

- Process suspended until I/O completed
- Moved from run queue to wait queue
- Later moved back to run queue & resumes
- Easy to use & understand
- Insufficient for some needs

Nonblocking

- Example: a user interface that receives keyboard & mouse input while processing & displaying data on screen.
- Implemented via multi-threading (a thread does the blocking part, another processes results)
- Returns quickly with a return value indicating how many bytes were transferred.

Blocking & Nonblocking I/O

Asynchronous

- Process runs while I/O executes
- Returns immediately without waiting for I/O to complete
- Difficult to use
- I/O subsystem signals process when I/O completed

Agenda

- Introduction
- I/O Hardware
- Application I/O Interface
- Kernel I/O Subsystem
- Performance

Kernel I/O subsystem

- Provides many services related to I/O, including:
 - I/O scheduling
 - Buffering / Caching / Spooling
 - Error handling
 - I/O protection

I/O Scheduling

Goal: schedule I/O requests in a **good order** before executing them

- Improve overall performance
- Share device access **fairly** among processes
- **Reduce** the average waiting time for I/O to complete
- Some OS maintain a wait queue of requests for each device
- Some OS try fairness


Example

- Application 1 needs a block near the end of a disk
- Application 2 needs a block near the beginning
- Application 3 needs a block near the middle of the disk

Best Scheduling: 2,3,1

Device status table

• When a kernel supports **asynchronous** I/O and might schedule requests in different orders, it must be able to keep track of many I/O requests




Buffering

• Another way to improve performance \rightarrow Use storage space in main memory or on disk via buffering, caching, spooling

Buffering

- Buffer: memory area that stores data being transferred between two devices or between a device & an application.
- Example:
 - File received via modem for storage on the hard disk.
 - Buffer created in main memory to accumulate the bytes received from the modem.
 - Buffer full \rightarrow write data on the disk
 - Disk write **not instantaneous**: two buffers are needed \rightarrow Double buffering

Buffering – Differences in device speeds



Enormous differences in device speeds for typical hardware!

Sun Enterprise 6000 device-transfer rates (logarithmic)

Caching – Spooling

Caching

- Cache: holds a copy on faster storage of an item that resides elsewhere
- Easier access → Key to performance

Spooling

- Hold output for a device
- If device can serve only one request at a time (e.g. printing) Devices that cannot accept interleaved data streams.

Error Handling

Error Handling

- Devices and I/O transfers can fail in many ways.
 - Transient reasons: a network becomes overloaded
 - Permanent reasons: a disk controller becomes defective
- OS can recover from disk read, device unavailable, transient write failures
- Most return an error number or code when I/O request fails
- System error logs hold problem reports

I/O Protection

- **Necessary**: User access may attempt to disrupt normal operation via illegal I/O instructions.
- All I/O instructions defined to be **privileged** → Users cannot issue them directly
- To do I/O a user program **executes** a system call
- OS checks if request is valid
- If yes it is executed.
- Memory mapped & I/O port memory locations must be **protected**

Agenda

- Introduction
- I/O Hardware
- Application I/O Interface
- Kernel I/O Subsystem
- Performance


Performance

I/O has major impact in system performance:

Why?

- Places heavy demands on CPU to execute device driver
- Schedule processes fairly & efficiently
- Context switches due to interrupts
- •

Example of performance: remote login



How to improve performance?

- Reduce number of context switches
- Reduce number of times data must be copied in memory (between device & application)
- Reduce frequency of interrupts
 Use large transfers, smart controllers
- Use DMA
- Balance CPU, memory, bus and I/O performance for highest throughput

Performance

