Oracle® Communications Network Charging and Control

ACS Provisioning Interface Commands Release 6.0.1

April 2017



Copyright

Copyright © 2017, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Document Conventions	
Chapter 1	
PI Commands Overview	1
Overview	1
Command List	
Chapter 2	
piAcsSms Package	3
Overview	
Adding a CLI to ACS Numbers by Using PI	3
Deleting a CLI From ACS Numbers	
Querying a CLI in ACS Numbers	
Exporting a Control Plan	
Importing a Control Plan Deleting a Control Plan	
Adding an ACS Customer	
Querying an ACS Customer	
Changing a Profile Entry	
Querying a Profile Entry	
Adding Customer Service Numbers	
Changing the Scheduled Control Plan	
Querying Customer Service Numbers	
Deleting Customer Service Numbers	
Adding Customer Termination Numbers	
Querying Customer Termination Numbers Deleting Customer Termination Numbers	
Managing FCI Data by Using PI	
Chapter 3	
Error Code Lists	23
Overview	23
PI Chassis Errors	
PI Command Errors	24
Glossary of Terms	29
Index	31

About This Document

Scope

The scope of this document includes all the information required to configure the Provisioning Interface commands.

Audience

The audience for this document includes system administrators responsible for the monitoring, maintenance, and configuration of the Oracle Communications Network Charging and Control IN applications.

Prerequisites

A solid understanding of UNIX and a familiarity with IN concepts are an essential prerequisite for safely using the information contained in this technical guide.

Although it is not a prerequisite to using this guide, familiarity with the target platform would be an advantage.

This manual describes system tasks that should only be carried out by suitably trained operators.

Related Documents

The following documents are related to this document:

- Provisioning Interface User's and Technical Guide
- Virtual Private Network User's Guide
- Charging Control Services Provisioning Interface Commands

Document Conventions

Typographical Conventions

The following terms and typographical conventions are used in the Oracle Communications Network Charging and Control (NCC) documentation.

Formatting Convention	Type of Information	
Special Bold	Items you must select, such as names of tabs.	
	Names of database tables and fields.	
Italics	Name of a document, chapter, topic or other publication.	
	Emphasis within text.	
Button	The name of a button to click or a key to press.	
	Example: To close the window, either click Close , or press Esc .	
Key+Key	Key combinations for which the user must press and hold down one key and then press another.	
	Example: Ctrl+P or Alt+F4.	
Monospace	Examples of code or standard output.	
Monospace Bold	Text that you must enter.	
variable	Used to indicate variables or text that should be replaced with an actual value.	
menu option > menu option >	Used to indicate the cascading menu option to be selected.	
	Example: Operator Functions > Report Functions	
hypertext link	Used to indicate a hypertext link.	

Specialized terms and acronyms are defined in the glossary at the end of this guide.

PI Commands Overview

Overview

Introduction

The provisioning interface (PI) uses TCP/IP-based UNIX sockets to receive provisioning commands and parameters. These are translated into SQL commands that update prepaid application tables of the SMF and E2BE Oracle databases. This chapter defines the rules and packages required to translate the provisioning commands into SQL commands.

In this chapter

This chapter contains the following topics.

Command List

ACS PI Command List

The following table lists the ACS PI functions and their corresponding commands. To use these commands, the piAcsSms package must be installed.

Function	PI Command
Add CLI to ACS Numbers	ACSCLI=ADD
Delete a CLI from ACS Numbers	ACSCLI=DEL
Query a CLI using ACS Numbers	ACSCLI=QRY
Export a control plan for an ACS customer.	ACSCPL=EXP
Import a control plan for an ACS customer.	ACSCPL=IMP
Delete a control plan for an ACS customer.	ACSCPL=DEL
Add an ACS customer.	ACSCST=ADD
Query an ACS customer.	ACSCST=QRY
Change a profile entry.	ACSPFL=CHG
Query a profile entry.	ACSPFL=QRY
Add a service number and associated control plan for a customer.	ACSSNM=ADD
Change the scheduled a control plan for a service number.	ACSSNM=CHG
Query a service number for a customer.	ACSSNM=QRY
Delete a service number and associated control plan for a customer.	ACSSNM=DEL
Add a termination number for a customer.	ACSTNM=ADD
Query a termination number for a customer.	ACSTNM=QRY
Delete a termination number for a customer.	ACSTNM=DEL

About Service Provider Restrictions

For security reasons, the data that a PI user can query or modify is restricted by service provider. This means that you can run PI commands to query or modify the data only for a service provider that is associated with your PI user.

The system administrator specifies which service providers to associate with your PI user on the **Users** tab in the Administration screen in the PI UI. For more information, see *PI User's and Technical Guide*.

Attempts to run PI commands for a service provider that is not associated with your PI user will result in a negative acknowledgement (NACK) message being returned.

piAcsSms Package

Overview

Introduction

This chapter describes the available PI commands for provisioning ACS customers, CLIs, and profile entries on the SMS.

These commands are added by the piAcsSms package that is installed when you install NCC. For more information about the installed PI packages, see PI User's and Technical Guide.

In this chapter

This chapter contains the following topics. Deleting a CLI From ACS Numbers4 Querying a CLI in ACS Numbers5 Importing a Control Plan......6 Adding an ACS Customer8

Adding a CLI to ACS Numbers by Using PI

About Adding a CLI to ACS Numbers by Using PI

Use the ACSCLI=ADD PI command to add a new CLI in ACS Numbers, and to schedule the specified control plan for the CLI. Specify an existing CLI to update the CLI with new data.

Note: You must specify an existing control plan in the CALLPLAN parameter.

You can also set the list of allowed numbers for the CLI by specifying the optional ALLOWED parameter. If you do not specify ALLOWED, then the PI sets the IGNORE flag for the number list.

After successfully adding a CLI to ACS Numbers, the PI returns this message:

ACSCLI=ADD: ACK;

If unsuccessful, the PI may return these error codes: 101, 102, 103, 105, 106, 107, 108, 109 and 110.

Required Parameters

Here are the required parameters for this command.

CLI

Syntax: CLI=num

Description: CLI for the subscriber.

Format: 18-digit number (greater than 0)

Example: CLI=1234567

CALLPLAN

Syntax: CALLPLAN=Cp

Description: The name of the control plan for the service.

Format: 50 character string Example: CALLPLAN=CP2

Optional Parameters

ACSCLI=ADD accepts the following optional parameters.

ALLOWED

Syntax: ALLOWED="cell|cell|..."

Description: A pipe (|) separated list of up to 100 cells, where each cell value is an allowed

number for the CLI.

Format: "CELL1|CELL2..."

Note: Each *cell* value is a 15-digit number (zero padded), formatted as follows:

MSCID + ServingCellID

Where:

MSCID (Optional) consists of a six digit market ID followed by a three

digit switch number

• ServingCellID is a six digit number

Example: ALLOWED="123456789012345|223456789012345"

Deleting a CLI From ACS Numbers

About Deleting a CLI in ACS Numbers by Using PI

Use the ACSCLI=DEL PI command to delete a CLI from ACS Numbers. Deleting the CLI also unschedules any control plans that are scheduled for the CLI.

After successfully deleting a CLI from ACS Numbers, the PI returns this message:

ACSCLI=DEL: ACK;

If unsuccessful, the PI may return these error codes: 101, 102, 104, 105, 107, 108, 109 and 110.

Required Parameter

Here is the required parameter for this command.

CLI

Syntax: CLI = num

The CLI for the subscriber. The CLI must exist already. Description:

Format: 18-digit number (greater than 0)

CLI=1234567 Example:

Querying a CLI in ACS Numbers

About Querying a CLI in ACS Numbers by Using PI

Use the ACSCLI=QRY PI command to query the ACS Numbers data for the list of allowed numbers for a specified CLI.

After successfully querying a CLI in ACS Numbers, the PI returns this message:

ACSCLI=QRY:ACK:ALLOWED=cell1|cell2|...;

Where cell is a number from the allowed numbers list for the CLI. For details about cell number formats. see ALLOWED (on page 4) parameter description.

If unsuccessful, the PI may return these error codes: 101, 102, 104, 105, 107 and 109.

Required Parameter

Here is the required parameter for this command.

CLI

Syntax: CLI=num

Description: The CLI for the subscriber. The CLI must exist already.

Format: 18-digit number (greater than 0)

CLI=1234567 Example:

Exporting a Control Plan

About Exporting a Control Plan by Using Pl

Use the ACSCPL=EXP PI command to export a control plan for a specified ACS customer to a .cpl file. For example, the following PI command exports the Postpaid control plan for the Telco customer:

ACSCPL=EXP: CUSTOMER=Telco, CALLPLAN=Postpaid;

The PI exports the control plan to the following directory by default:

/IN/service packages/PI/callplans

You can set a different control plan export directory by configuring the exportCallPlanDirectory parameter in the pi, ACSCPL section of the eserv.config configuration file. See PI User's and Technical Guide for more information.

After successfully exporting a control plan, the PI returns this message:

ACSCPL=EXP:FILENAME=export path/filename;

Where:

- export_path is the full directory path for the exported control plan file on the SMS; for example, /IN/service_packages/callplans
- *filename* has the following format, based on the customer name, control plan name and control plan version number: *customer__controlplan__version.cpl*; for example, Telco__Postpaid__1.cpl

If unsuccessful, the PI may return these error codes: 101, 102, 103, 107, and 118,

Required Parameters

Here are the required parameters for this command.

CUSTOMER

Syntax: CUSTOMER=name

Description: The name of an existing customer.

Type: String
Optionality: Required

Allowed: A string of up to 50 characters.

Example: CUSTOMER=Customer A

CALLPLAN

Syntax: CALLPLAN=string

Description: The name of the control plan. You must specify an existing control plan that

belongs to the specified customer.

Type: String
Optionality: Required

Allowed: A string of up to 50 characters. Example: CALLPLAN=Control Plan 2

Importing a Control Plan

About Importing a Control Plan by Using Pl

Use the ACSCPL=IMP PI command to import a control plan for a specified ACS customer from a .cpl file, and to compile the control plan after it is imported. For example, the following PI command imports the Postpaid control plan for the Telco customer from the Postpaid_test.cpl file:

ACSCPL=IMP:CUSTOMER=Telco,CALLPLAN=Postpaid,FILENAME=/IN/service_packages/PI/callplans/Postpaid_test.cpl;

If the control plan:

- Does not exist for the specified customer, then the PI creates a new control plan and sets its version number to 1 (one)
- Already exists for the specified customer, then the PI updates the control plan and increments its version number, provided that:
 - Only a single successfully compiled version of the control plan exists
 - No other control plans use the control plan structure
 - The control plan is not associated with an ACS service number, an ACS CLI number, or a CCS product type

After successfully importing and compiling a control plan, the PI returns this message:

ACSCPL=IMP:ACK;

If unsuccessful, the PI may return these error codes: 101, 102, 107, 118, 120 and 121.

Required Parameters

Here are the required parameters for this command.

CUSTOMER

Syntax:

CUSTOMER=name

Description:

The name of an existing customer.

Type:

String

Optionality:

Required

Allowed:

A string of up to 50 characters.

Example:

CUSTOMER=Customer A

CALLPLAN

Syntax:

CALLPLAN=string

Description:

The name that the new control plan will use.

Type:

String

Optionality:

Required

Allowed: Example: A string of up to 50 characters. CALLPLAN=Control Plan 2

FILENAME

Syntax:

FILENAME=string

Description:

The name of the .cpl import file. Specify the filename by using the following

format:

file name.cpl

Where file_name includes the full directory path of the .cpl import file on the SMS;

for example, /IN/service_packages/PI/callplans/Postpaid_test.cpl.

Type: Optionality: String

Example:

Required FILENAME=/IN/service_packages/PI/callplans/Postpaid_test.cpl

Deleting a Control Plan

About Deleting a Control Plan by Using Pl

Use the ACSCPL=DEL PI command to delete a control plan for a specified ACS customer. For example, the following PI command deletes the Postpaid control plan for the Telco customer:

ACSCPL=DEL: CUSTOMER=Telco, CALLPLAN=Postpaid;

You can delete a control plan providing:

- Only one entry for the control plan exists in the database
- The control plan structure is not being used by other control plans

 The control plan is not associated with an ACS service number, an ACS CLI number, or a CCS product type

After successfully deleting a control plan, the PI returns this message:

ACSCPL=DEL:ACK;

If unsuccessful, the PI may return these error codes: 101, 102, 103, 107 and 118.

Required Parameters

Here are the required parameters for this command.

CUSTOMER

Syntax: CUSTOMER=name

Description: The name of an existing customer.

Type: String
Optionality: Required

Allowed: A string of up to 50 characters.

Example: CUSTOMER=Customer A

CALLPLAN

Svntax: CALLPLAN=string

Description: The name of the control plan. You must specify an existing control plan that

belongs to the specified customer.

Type: String
Optionality: Required

Allowed: A string of up to 50 characters.

Example: CALLPLAN=Control Plan 2

Adding an ACS Customer

About Adding an ACS Customer by Using PI

Use the ACSCST=ADD PI command to add an ACS customer to the database.

To successfully add a customer, your PI user must be associated with the default service provider named "Boss". A negative acknowledgement (NACK) is returned if you attempt to add a customer and your PI user is not associated with the "Boss" service provider. See *About Service Provider Restrictions* (on page 2) for more information.

Note: The "Boss" service provider is automatically created at installation.

After successfully adding a customer, the PI returns this message:

ACSCST=ADD:ACK;

If unsuccessful, the PI can return any of the following error codes: 136, 137, 138, 140, or 142.

Required Parameters

Here are the required parameters for this command.

CUSTOMER

Syntax: CUSTOMER=name

Description: The name of the customer to add.

Type:

String

Optionality:

Required.

Allowed:

A string of up to 50 characters.

Example:

CUSTOMER=Customer A

PARENT

Syntax:

PARENT=string

Description:

The name of the customer's parent customer.

Type:

String

Optionality:

Required if the RESELLER_FLAG is set to A. The parent customer must be a

reseller.

Optional if the RESELLER_FLAG is set to N or null.

If RESELLER FLAG is set to R, then you cannot set the parent customer.

Allowed:

A string of up to 50 characters.

Example:

PARENT=Customer A

Optional Parameters

ACSCST=ADD accepts the following optional parameters.

DESCRIPTION

Syntax:

DESCRIPTION=string

Description:

The customer's description.

Type:

String

Optionality:

Optional.

Allowed:

A string of up to 2000 characters.

Example:

DESCRIPTION=A customer description

CUSTOMER_REFERENCE

Syntax:

CUSTOMER REFERENCE=string

Description:

The customer reference ID.

Type:

String

Optionality:

Optional

Allowed:

A string of up to 749 characters.

Example:

CUSTOMER REFERENCE=CRX001A

TELCO MANAGED

Syntax:

TELCO MANAGED=Y | N

Description:

Specifies whether the customer is managed by the operator.

Type:

Boolean

Optionality:

Optional (default used if not set).

Allowed:

Y – The customer is managed by the operator.

Υ

N – The customer is not managed by the operator.

Default: Example:

TELCO MANAGED=N

RESELLER FLAG

Syntax: RESELLER FLAG=N|R|A

Description: Defines whether or not the customer is a reseller or an agent.

Type: String

Optionality: Optional (default used if not set).

Allowed: N – The customer is not a reseller or an agent.

R – The customer is a reseller.A – The customer is an agent.

Default: N

Example: RESELLER FLAG=N

Querying an ACS Customer

About Querying an ACS Customer by Using PI

Use the ACSCST=QRY PI command to query the database for the details of the specified ACS customer. After successfully performing a customer query, the PI returns this message:

```
ACSCST=QRY:ACK:

CUSTOMER=name, DESCRIPTION=customer_description,

CUSTOMER_REFERENCE=customer_reference, TELCO_MAN=Y|N, RESELLER_FLAG=N|R|A,

[PARENT=parent name]
```

Where:

- name is the name of the customer.
- customer description is the description for the customer.
- customer reference is the customer reference ID.
- parent_name is name of the customer's parent. No value is returned when the operator is the customer's parent.

If the PI fails to find the specified customer, then the PI returns error code 118.

Required Parameter

Here is the required parameter for this command.

CUSTOMER

Syntax: CUSTOMER=name

Description: The name of an existing customer.

Type: String
Optionality: Required

Allowed: A string of up to 50 characters.

Example: CUSTOMER=Customer A

Changing a Profile Entry

About Changing a Profile Entry by Using Pl

Use the ACSPFL=CHG PI command to change a profile entry in the database. After successfully changing a profile entry, the PI returns this message:

ACSPFL=CHG:ACK;

If unsuccessful, then the PI may return these error codes: 101, 102, 107, 110, 111, 112, 113, 114, 115, 116 and 117.

Required Parameters

Here are the required parameters for this command.

TABLE

Syntax:

TABLE=table

Description:

The name of the profile table that holds the profile entry you want to change or

query. You must specify an existing profile table.

Type:

30-character string

Example:

TABLE=ACS PROFILE DETAILS

ID

Syntax:

ID=id

Description:

The ID of the row.

Type:

Integer

Example:

ID=45

TAG

Syntax: **Description:** TAG=tag id

Type:

The profile tag.

Hex or String

Allowed:

Either a hexadecimal value prefixed by 0x, for example, 0x123ABC or a pre-

defined name corresponding to PROFILE TAG NAME in the

ACS_PROFILE_DETAILS table.

Default:

HEX

Notes:

If TAG is:

A predefined name, any specified TYPE is ignored

A hexadecimal value, and TYPE is omitted, the value will be returned as

hexadecimal data

Omitted, a hex dump of the whole profile is returned

Example:

TAG=0x123ABC

Optional Parameters

The ACSPFL=CHG PI command accepts the following optional parameters.

PROFILE_COL

Syntax:

PROFILE COL=column name

Description:

The name of the profile column.

Type:

String

Optionality:

Optional (default used if omitted)

Allowed:

A valid profile column name from the specified profile table.

Default:

PROFILE

Example:

PROFILE_COL=CLI

ID_COL

Type: String

Optionality: Optional (default used if omitted).

Allowed: ID
Default: ID

Notes: A valid column in TABLE containing unique ID.

Example: ID_COL=ID

TYPE

Syntax: $TYPE=tag_type$ Description: The type of the tag.

Type: String

Optionality: Optional (default used if omitted).

Allowed: Valid options are:

STRING – String valueDATE – Date value

• INTEGER – 32-bit signed integer value

HEX – Raw hexadecimal dataTN – Telephone number

Default: HEX

Notes: DATE type values have the following format: YYYYDDMMHHMMSS; for example,

20131609100500.

Example: TYPE=DATE

VALUE

Syntax: VALUE=val

Description: The value of the tag.

Type: Defined by the TYPE parameter.

Optionality: Optional

Allowed:

Default: If VALUE is not specified, any existing profile tag will be deleted.

Notes: For TYPE = TN, the VALUE format:

Must contain only numeric digits

· First character is interpreted as a TN type

TN type has range 0-5

TN has max length 33 characters (including TN type)

Examples: VALUE=12345 Integer type

VALUE=Monday String type

VALUE=2009010112345 Date type (YYYYMMDDHHMMSS)

VALUE=0x123ABC Hex type
VALUE=12345 TN type

Querying a Profile Entry

About Querying a Profile Entry by Using PI

Use the ACSPFL=QRY PI command to query a profile entry in the database.

After successfully querying a profile entry, the PI returns this message if TAG was specified:

- ACSPFL=ORY: ACK: TAG=tag, VALUE=value;
- ACSPFL=QRY:ACK:TAG=tag;

The PI returns this message if TAG was not specified:

```
ACSPFL=QRY:ACK:
    TAG=hex tag, VALUE=hex value[,
   TAG=hex tag, VALUE=hex value[,
    ...11;
```

Note: No carriage returns are returned.

If unsuccessful, then the PI may return these error codes: 101, 102, 107, 111, 112, 113, 114, 115 and 116.

Required Parameters

Here are the required parameters for this command.

TABLE

Syntax: TABLE=table

Description: The name of the profile table that holds the profile entry you want to change or

query. You must specify an existing profile table.

Type: 30-character string

Example: TABLE=ACS PROFILE DETAILS

TD

Syntax: ID=id

Description: The ID of the row.

Type: Integer ID=45Example:

Optional Parameters

The ACSPFL=QRY PI command accepts the following optional parameters.

PROFILE COL

Syntax: PROFILE COL=column name Description: The name of the profile column.

Type: String

Optionality: Optional (default used if omitted)

Allowed: A valid profile column name from the specified profile table.

Default: **PROFILE**

Example: PROFILE COL=CLI

Chapter 2

ID_COL

Type: String

Optionality: Optional (default used if omitted).

Allowed: ID Default: ID

Notes: A valid column in TABLE containing unique ID.

Example: ID COL=ID

TAG

Allowed: Either a hexadecimal value prefixed by 0x, for example, 0x123ABC or a pre-

defined name corresponding to PROFILE_TAG_NAME in the

ACS_PROFILE_DETAILS table.

Default: HEX
Notes: If TAG is:

A predefined name, any specified TYPE is ignored

A hexadecimal value, and TYPE is omitted, the value will be returned as

hexadecimal data

Omitted, a hex dump of the whole profile is returned

Example: TAG= 0×123 ABC

TYPE

Type: String

Optionality: Optional (default used if omitted).

Allowed: Valid options are:

STRING – String valueDATE – Date value

• INTEGER - 32-bit signed integer value

HEX – Raw hexadecimal data

TN – Telephone number

Default: HEX

Notes: DATE type values have the following format: YYYYDDMMHHMMSS; for example,

20131609100500.

Example: TYPE=DATE

Adding Customer Service Numbers

About Adding Customer Service Numbers by Using PI

Use the ACSSNM=ADD PI command to add a service number for a specified ACS customer. You can also use this command to add a scheduled control plan to the service number. After successfully adding a service number for a customer, the PI returns this message:

ACSSNM=ADD:ACK;

If unsuccessful, then the PI may return any of the following error codes: 118, 140, 141, or 143.

Required Parameters

Here are the required parameters for this command.

CUSTOMER

Syntax: CUSTOMER=name

Description: The name of an existing customer.

Type: String Optionality: Required

Allowed: A string of up to 50 characters. Example: CUSTOMER=Customer A

SERVICE NUMBER

Syntax: SERVICE NUMBER=string

Description: The service number to add or delete.

Type: String Optionality: Required

Allowed: A string of up to 32 characters. Valid characters are 0-9, A-F, *, #.

Example: SERVICE NUMBER=115

Optional Parameter

The ACSSSN=ADD PI command accepts the following optional parameter.

CONTROLPLAN

Syntax: CONTROLPLAN=string **Description:** The control plan name.

Type: String Optionality: Optional

Allowed: A string of up to 50 characters Example: CONTROLPLAN=Control Plan 2

Changing the Scheduled Control Plan

About Changing the Scheduled Control Plan by Using Pl

Use the ACSSNM=CHG PI command to change or add the control plan that is scheduled for a customer service number. You can schedule a future date when the control plan will become active for the service number. Otherwise the control plan is activated immediately for the service number. For example, the following PI command schedules the Postpaid control plan for the 012234787 service number for the Telco customer:

ACSSNM=CHG:CUSTOMER=Telco,SERVICE_NUMBER=012234787,CONTROLPLAN=Postpaid,SCHE DULE DATE=20130901080000;

After successfully updating the control plan scheduled to a customer service number, the PI returns this message:

ACSSNM=CHG:ACK;

If unsuccessful, then the PI may return any of the following error codes: 101, 102, 103, 108, 118, 141, 143, 144, or 145.

Required Parameters

Here are the required parameters for this command.

CUSTOMER

Syntax: CUSTOMER=name

Description: The name of an existing customer.

Type: String
Optionality: Required

Allowed: A string of up to 50 characters.

Example: CUSTOMER=Customer A

SERVICE NUMBER

Syntax: SERVICE NUMBER=string

Description: The service number for which you want to add or change the scheduled control

plan.

Type: String
Optionality: Required

Allowed: A string of up to 32 characters. Valid characters are 0–9, A–F, *, #.

Example: SERVICE NUMBER=012234787

CONTROLPLAN

Syntax: CONTROLPLAN=string

Description: The name of an existing control plan that the service number will use.

Type: String
Optionality: Required

Allowed: A string of up to 50 characters

Example: CONTROLPLAN=Control Plan 2

Optional Parameter

The ACSSSN=CHG PI command accepts the following optional parameter.

SCHEDULE DATE

Syntax: SCHEDULE DATE=date

Description: The date when the control plan will be activated for the service number. Specify a

date in the following format: YYYYMMDDHHmmSS.

Type: String Optionality: Optional

Notes: To activate the control plan immediately for the service number, do not specify a

schedule date.

SCHEDULE DATE=20130901080000 Example:

Querying Customer Service Numbers

About Querying Customer Service Numbers by Using PI

Use the ACSSNM=QRY PI command to guery the database for the details of the service numbers allocated to a specified ACS customer. After successfully performing a service number query, the PI returns this message:

```
ACSSNM=QRY:ACK:
    CUSTOMER=name, SERVICE NUMBER=n[,SERVICE NUMBER=n][,...]
```

Where:

- name is the name of the customer.
- n is a service number allocated to the customer.

If unsuccessful, then the PI may return either of the following error codes: 118 or 140.

Required Parameter

Here is the required parameter for this command.

CUSTOMER

Syntax: CUSTOMER=name

Description: The name of an existing customer.

Type: String Optionality: Required

Allowed: A string of up to 50 characters. Example: CUSTOMER=Customer A

Deleting Customer Service Numbers

About Deleting Customer Service Numbers by Using PI

Use the ACSSNM=DEL PI command to delete a service number for a specified ACS customer. After successfully deleting a service number, the PI returns this message:

ACSSNM=DEL:ACK;

If unsuccessful, then the PI may return either of the following error codes: 118 or 140.

Required Parameters

Here are the required parameters for this command.

CUSTOMER

Syntax: CUSTOMER=name

Description: The name of an existing customer.

Type: String
Optionality: Required

Allowed: A string of up to 50 characters.

Example: CUSTOMER=Customer A

SERVICE_NUMBER

Syntax: SERVICE NUMBER=string

Description: The service number to add or delete.

Type: String
Optionality: Required

Allowed: A string of up to 32 characters. Valid characters are 0–9, A–F, *, #.

Example: SERVICE NUMBER=115

Adding Customer Termination Numbers

About Adding Customer Termination Numbers by Using PI

Use the PI ACSTNM=ADD command to add termination numbers for a specified ACS customer.

To add a single termination number for a customer specify, only the *CUSTOMER* (on page 6) and *PREFIX* (on page 19) parameters.

To add a range of termination numbers for a customer, specify all the parameters. You specify the range by using a combination of the PREFIX, *MIN_LENGTH* (on page 19) and *MAX_LENGTH* (on page 19) parameters. For example, you could specify the following range:

```
PREFIX=01473, MIN LENGTH=6, MAX LENTGH=10
```

The resulting termination number range would be: 01473XYYYY

Where X is a digit that must be present in the termination number, and Y is a digit that may be present up to MAX_LENGTH.

After successfully adding termination numbers for a customer, the PI returns this message:

```
ACSTNM=ADD:ACK;
```

If unsuccessful, then the termination numbers are not added and the PI may return any of the following error codes: 118, 130, 131, 132, 133, 139, or 140.

Required Parameters

Here are the required parameters for this command.

CUSTOMER

Syntax: CUSTOMER=name

Description: The name of an existing customer.

Type: String
Optionality: Required

Allowed: A string of up to 50 characters.

CUSTOMER=Customer A Example:

PREFIX

Syntax: PREFIX=string

Description: The termination number prefix to add or delete.

Type: String Optionality: Required.

Allowed: A string of up to 32 characters. Valid characters are 0–9, A–F, *, #.

Example: PREFIX=0179

Optional Parameters

ACSTNM=ADD accepts the following optional parameters.

MIN LENGTH

Syntax: MIN LENGTH=integer

Description: The minimum length for the termination number.

Type: Integer

Optionality: Optional (default used if not set).

Allowed: A value that is not less than the PREFIX length and not greater than 32.

Default: PREFIX length Example: MIN LENGTH=4

MIN_LENGTH

Syntax: MAX LENGTH=integer

Description: The maximum length for the termination number.

Type: Integer

Optionality: Optional (default used if not set).

Allowed: A value that is not less than MIN_LENGTH and not greater than 32.

PREFIX length plus one (1), or 32 if the PREFIX length is 32. Default:

MAX LENGTH=10 Example:

Querying Customer Termination Numbers

About Querying Customer Termination Numbers by Using PI

Use the ACSTNM=QRY PI command to query the database for the details of the termination numbers assigned to a specified ACS customer. After successfully performing a termination number guery, the PI returns this message:

```
ACSTNM=ORY: ACK:
   CUSTOMER=name, TERMINATION NUMBER=n[, TERMINATION NUMBER=n[,...]]
```

Where:

- name is the name of the customer.
- n is a valid termination number for the customer.

If unsuccessful, then the PI may return the following error codes: 118 or 140.

Required Parameters

Here are the required parameters for this command.

CUSTOMER

Syntax: CUSTOMER=name

Description: The name of an existing customer.

Type: String
Optionality: Required

Allowed: A string of up to 50 characters.

Example: CUSTOMER=Customer A

PREFIX

Syntax: PREFIX=string

Description: The termination number prefix to add or delete.

Type: String
Optionality: Required.

Allowed: A string of up to 32 characters. Valid characters are 0–9, A–F, *, #.

Example: PREFIX=0179

Deleting Customer Termination Numbers

About Deleting Customer Termination Numbers by Using PI

Use the ACSTNM=DEL PI command to delete a termination number prefix for a specified ACS customer. After successfully deleting a termination number prefix, the PI returns this message:

ACSTNM=DEL: ACK;

If unsuccessful, then the PI may return any of the following error codes: 118, 134, or 140.

Required Parameter

Here is the required parameter for this command.

CUSTOMER

Syntax: CUSTOMER=name

Description: The name of an existing customer.

Type: String
Optionality: Required

Allowed: A string of up to 50 characters.

Example: CUSTOMER=Customer A

Managing FCI Data by Using PI

About Managing FCI Data by Using PI

Use the ACSPFL=CHG PI command to update the furnish charging information (FCI) data held in the following profile tags in the ACS service number profile block:

- FCI Country Code
- FCI On
- FCI Service Code

For more information about using ACSPFL=CHG, see Changing a Profile Entry (on page 10).

Use the ACSPFL=QRY PI command to query the FCI data for a customer. For more information, see Querying a Profile Entry (on page 13).

For more information about profile blocks and profile tags, see the discussion on the main components of ACS in ACS Technical Guide.

Error Code Lists

Overview

Introduction

This chapter explains the error codes for Oracle Communications Network Charging and Control (NCC) provisioning interface (PI) commands.

In this chapter

This chapter contains the following topics.	
PI Chassis Errors	23
PI Command Errors	

PI Chassis Errors

Format

NACK: Code-Message;

Example: ACSCLI=QRY:NACK:70-TOO MANY SESSIONS

Error List

This table describes the PI Chassis error codes.

Code	Message	Description
70	TOO MANY SESSIONS	All PI sessions are in use.
71	LOGON SYNTAX ERROR	The login string was incorrectly formatted.
72	INVALID LOGON - username, password	Invalid username and/or password
73	INVALID LOGON - user not allowed on this port	The user attempted to log in to the wrong PI port.
74	INVALID LOGON - host	The PI client is unknown.
75	UNKNOWN COMMAND	Client sent an unknown command.
76	USER DOES NOT HAVE SUFFICIENT SECURITY	The user's security level is less than the command's security level.
77	SYNSTAMP NOT FOUND	Synstamps are turned on, but the client did not send one.
78	SYNSTAMP NOT VALID	Synstamps are turned on, but the synstamp sent by the client is invalid.

Code	Message	Description
79	INVALID OR MISSING CHECKSUM	Checksums are turned on, but the client is one of the following: Did not send one It was invalid
80	UNKNOWN PARAMETER FOR COMMAND	A parameter was sent that was not valid for this command.
81	MISSING PARAMETERS FROM COMMAND	A required parameter is missing.
82		Undefined
83	DUPLICATE PARAMETER	The client sent two identically named parameters.
84	ERROR RUNNING PROCEDURE	An internal error occurred running the command.
85	USER SESSION TERMINATED	The user's session has been terminated by an administrator.
86	COMMAND TOO BIG	The command sent is too long. Indicates an incorrectly formatted command.
87	COMMAND SYNTAX ERROR	The command sent is incorrectly formatted.
88	PARAMETER NAME TOO BIG	A parameter name is too long. Indicates the command was incorrectly formatted.
89	PARAMETER VALUE TOO BIG	A parameter value is too long. Indicates the command was incorrectly formatted.
90	SYNSTAMP OUT OF PLACE	The synstamp is not at the end of the command, but before the checksum.
91	TIMEOUT	The command took too long to run.

PI Command Errors

Format

Command: NACK: Code-Message: value;

Where:

- Command is the PI command
- Code is the PI error code
- Message is the PI error message and can contain any characters except semi-colon
- In the message, value will be replaced with a suitable value by the command.

Example: ACSCLI=QRY:NACK:104-CLI does not exist:912233445566

Error List

This table lists the error codes and error code descriptions for the PI commands listed in the ACS PI command list.

Code	Message	Commands
101	text	All commands
	Where the <i>text</i> contains the details of the error. This error is used to report any other errors that are not defined below.	

Code	Message	Commands
102	Badly formatted parameter <i>parameter</i>	All commands
	Where parameter is the name of the parameter causing the error.	
103	CALLPLAN does not exist control_plan	ACSCLI=ADD
	Where <i>control_plan</i> is the name of an invalid control plan.	ACSCPL=EXP
		ACSCPL=DEL
		ACSSNM=CHG
104	CLI does not exist <i>cli</i>	ACSCLI=DEL
	Where <i>cli</i> is an invalid CLI number.	ACSCLI=QRY
105	No required parameters	All commands
106	Too many numbers in ALLOWED list	ACSCLI=ADD
107	Invalid action action	All commands
	Where action is an invalid command action.	
108	SQL write error	ACSCLI=ADD
		ACSCLI=DEL
	SOL read error	ACSSNM=CHG
109	SQL Tead ellor	ACSCLI=ADD ACSCLI=DEL
		ACSCLI=DEL ACSCLI=QRY
110	Internal error encoding profile	ACSCLI=ADD
		ACSCLI=DEL
		ACSPFL=CHG
111	TABLE does not exist table_name	ACSPFL=CHG
	Where table_name is an invalid database table name. ID COLUMN does not exist column name	ACSPFL=QRY
112	Where <i>column_name</i> is an invalid column name for the specified	ACSPFL=CHG ACSPFL=QRY
	table.	ACOIT L-QIVI
113	ID does not exist id	ACSPFL=CHG
	Where id is invalid.	ACSPFL=QRY
114	PROFILE_COLUMN does not exist column_name	ACSPFL=CHG
	Where <i>column_name</i> is an invalid column name for the profile.	ACSPFL=QRY
115	TAG does not exist tag_name	ACSPFL=CHG
	Where tag_name is an invalid name for the specified profile tag. TYPE is not valid type name	ACSPFL=QRY
116	Where <i>type_name</i> is an invalid profile type.	ACSPFL=CHG ACSPFL=QRY
	This is type_name to an invalid profile type.	AUGET LEGIT
117	VALUE is not valid <i>value</i>	ACSPFL=CHG
	Where value is an invalid value for the specified profile tag.	ACSPFL=QRY

Code	Message	Commands
118	Customer does not exist customer_name	ACSCST=QRY
	Where customer_name is not a valid ACS customer.	ACSCPL=EXP
		ACSCPL=IMP
		ACSCPL=DEL
		ACSSNM=ADD
		ACSSNM=CHG
		ACSSNM=QRY
		ACSSNM=DEL
		ACSTNM=ADD
		ACSTNM=QRY
		ACSTNM=DEL
120	FILENAME does not exist file_name	ACSCPL=IMP
121	FILENAME has insufficient permissions file_name	ACSCPL=IMP
130	Invalid termination prefix	ACSTNM=ADD
131	Invalid minimum termination length	ACSTNM=ADD
132	Invalid maximum termination length	ACSTNM=ADD
133	Overlapping termination ranges not allowed	ACSTNM=ADD
134	Termination number or range does not exist	ACSTNM=DEL
135	Service number not found for customer	ACSSNM=DEL
136	Parent customer not found	ACSCST=ADD
137	Reseller cannot have a parent customer	ACSCST=ADD
138	Reseller cannot have a parent customer	ACSCST=ADD
139	Minimum termination number length greater than maximum termination number length	ACSTNM=ADD
140	Duplicate service numbers not allowed	ACSCST=ADD
		ACSSNM=ADD
		ACSSNM=QRY
		ACSSNM=DEL
		ACSTNM=ADD
		ACSTNM=QRY
		ACSTNM=DEL
141	Parameter too long	ACSSNM=CHG
142	Customer already exists	ACSCST=ADD
143	Invalid service number	ACSSNM=ADD
	Toward de control of the control of	ACSSNM=CHG
144	Invalid customer name	ACST=ADD
		ACSPL=IMP
		ACSPL=EXP
		ACSPL=DEL
145	Parameter too short	ACSSNM=CHG
146	Invalid date	ACSSNM=CHG

Glossary of Terms

ACS

Advanced Control Services configuration platform.

ANI

Automatic Number Identification - Term used in the USA by long-distance carriers for CLI.

CCS

- 1) Charging Control Services component.
- 2) Common Channel Signalling. A signalling system used in telephone networks that separates signalling information from user data.

CLI

Calling Line Identification - the telephone number of the caller. Also referred to as ANI.

DTMF

Dual Tone Multi-Frequency - system used by touch tone telephones where one high and one low frequency, or tone, is assigned to each touch tone button on the phone.

FCI

Furnish Charging Information. An INAP operation sent from ACS to the SSP to control the contents of EDRs produced by the SSP.

GUI

Graphical User Interface

IN

Intelligent Network

INAP

Intelligent Network Application Part - a protocol offering real time communication between IN elements.

IP

- 1) Internet Protocol
- 2) Intelligent Peripheral This is a node in an Intelligent Network containing a Specialized Resource Function (SRF).

MIN

Mobile Identification Number, also known as an MSID.

MSID

Mobile Subscriber Identification, also known as an MIN.

ы

Provisioning Interface - used for bulk database updates/configuration instead of GUI based configuration.

SLC

Service Logic Controller (formerly UAS).

SMS

Depending on context, can be:

- Service Management System hardware platform
- Short Message Service
- Service Management System platform
- NCC Service Management System application

SQL

Structured Query Language is a database query language.

SRF

Specialized Resource Function – This is a node on an IN which can connect to both the SSP and the SLC and delivers additional special resources into the call, mostly related to voice data, for example play voice announcements or collect DTMF tones from the user. Can be present on an SSP or an Intelligent Peripheral (IP).

SSP

Service Switching Point

TCP

Transmission Control Protocol. This is a reliable octet streaming protocol used by the majority of applications on the Internet. It provides a connection-oriented, full-duplex, point to point service between hosts.

Telco

Telecommunications Provider. This is the company that provides the telephone service to customers.

Telecommunications Provider

See Telco.

Deleting a CLI From ACS Numbers • 4 Α Deleting a Control Plan • 7 Deleting Customer Service Numbers • 17 About Adding a CLI to ACS Numbers by Using Deleting Customer Termination Numbers • 20 PI • 3 **DESCRIPTION • 9** About Adding an ACS Customer by Using PI • 8 Document Conventions • vi About Adding Customer Service Numbers by **DTMF • 29** Using PI • 15 **About Adding Customer Termination Numbers** Ε by Using PI • 18 Error Code Lists • 23 About Changing a Profile Entry by Using PI • 10 Error List • 23, 24 About Changing the Scheduled Control Plan by Exporting a Control Plan • 5 Using PI • 16 About Deleting a CLI in ACS Numbers by Using F PI • 4 FCI • 29 About Deleting a Control Plan by Using PI • 7 FILENAME • 7 About Deleting Customer Service Numbers by Format • 23, 24 Using PI • 17 **About Deleting Customer Termination Numbers** G by Using PI • 20 About Exporting a Control Plan by Using PI • 5 GUI • 29 About Importing a Control Plan by Using PI • 6 About Managing FCI Data by Using PI • 21 About Querying a CLI in ACS Numbers by ID • 11, 13 Using PI • 5 ID COL • 12. 14 About Querying a Profile Entry by Using PI • 13 Importing a Control Plan • 6 About Querying an ACS Customer by Using PI IN • 29 **INAP • 29** About Querving Customer Service Numbers by IP • 29 Using PI • 17 M **About Querying Customer Termination** Numbers by Using PI • 19 Managing FCI Data by Using PI • 21 About Service Provider Restrictions • 2, 8 MIN • 29 About This Document • v MIN LENGTH • 18, 19 ACS • 29 MSID • 30 ACS PI Command List • 1 Adding a CLI to ACS Numbers by Using PI • 3 Adding an ACS Customer • 8 Optional Parameter • 15, 16 Adding Customer Service Numbers • 15 Optional Parameters • 4, 9, 11, 13, 19 Adding Customer Termination Numbers • 18 Overview • 1, 3, 23 ALLOWED • 4.5 ANI • 29 Audience • v PARENT • 9 PI • 30 PI Chassis Errors • 23 CALLPLAN • 4, 6, 7, 8 PI Command Errors • 24 CCS • 29 PI Commands Overview • 1 Changing a Profile Entry • 10, 21 piAcsSms Package • 3 Changing the Scheduled Control Plan • 16 PREFIX • 18, 19, 20 CLI • 4, 5, 29 Prerequisites • v Command List • 1 PROFILE COL • 11, 13 CONTROLPLAN • 15, 16 Copyright • ii CUSTOMER • 6, 7, 8, 10, 15, 16, 17, 18, 20 **CUSTOMER REFERENCE • 9** Querying a CLI in ACS Numbers • 5 Querying a Profile Entry • 13, 21

D

Index

```
Querving an ACS Customer • 10
Querying Customer Service Numbers • 17
Querying Customer Termination Numbers • 19
R
Related Documents • v
Required Parameter • 5, 10, 17, 20
Required Parameters • 4, 6, 7, 8, 11, 13, 15, 16,
RESELLER_FLAG • 10
S
SCHEDULE DATE • 17
Scope • v
SERVICE_NUMBER • 15, 16, 18
SLC • 30
SMS • 30
SQL • 30
SRF • 30
SSP • 30
Т
TABLE • 11, 13
TAG • 11, 14
TCP • 30
Telco • 30
TELCO_MANAGED • 9
Telecommunications Provider • 30
TYPE • 12, 14
Typographical Conventions • vi
V
VALUE • 12
```