Oracle® Communications Network Charging and Control

Diameter Control Agent Technical Guide Release 6.0.1

April 2017



Copyright

Copyright © 2017, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

About This Document Document Conventions	
Chapter 1	
•	_
System Overview	1
Overview What is Diameter Control Agent?	
Chapter 2	
Configuration	5
Overview	F
Configuration Overview	
eserv.config Configuration	
SLEE.cfg Configuration	
RAR Configuration	
acs.conf Configuration	
Prepaid Charging Configuration	
Feature Node ConfigurationINAP Extensions	
Parameter Mappings	
Business Scenarios	
Chapter 3	
Background Processes	23
Overview	23
diameterControlAgent Process	
DCADefaults Configuration Section	
DCAInstances Configuration Section	
Services Configuration	58
PeerSchemes Configuration Section	
Statistics Logged by diameterControlAgent	78
Chapter 4	
Service Specific AVP Mappings	81
Overview	81
Introduction	81
Basic Array	
Key Array	
Array with Conditions	
Array with Context	
Prefix Tree	
Timestamp	

Chapter 5

Control Plans	117
Overview Check Balance Direct Debiting Price Enquiry Refund Account Session No Redirect Session Redirect	
Chapter 6	127
About Installation and Removal	127
OverviewInstallation and Removal Overview	127
Chapter 7	
Diameter Charging Agent Call Flows	129
Call Flow Overview Initial Request Success Initial Request Release Call Initial Request Multiple Requested Service Units AVP Pass-Through DCA to DCD Screening Successful Screening Call Disallowed Screening Failure Update Request Terminate Request	
Glossary of Terms	137
Index	143

About This Document

Scope

The scope of this document includes all the information required to install, configure and administer the Diameter Control Agent application.

Audience

This guide was written primarily for system administrators and persons installing, configuring and administering the Diameter Control Agent application. However, sections of the document may be useful to anyone requiring an introduction to the application.

Prerequisites

A solid understanding of UNIX and a familiarity with IN concepts are an essential prerequisite for safely using the information contained in this technical guide. Attempting to install, remove, configure or otherwise alter the described system without the appropriate background skills, could cause damage to the system; including temporary or permanent incorrect operation, loss of service, and may render your system beyond recovery.

A familiarity with the Diameter protocol is also required. Refer to the following:

- Internet Engineering Task Force (IETF) specifications:
 - RFC 3588 Diameter Base Protocol
 - RFC 4006 Diameter Credit-Control Application
 - RFC 4005 Diameter Network Access Server Application
- 3GPP TS 32.299 V11.3.0 (2012-03) 3rd Generation Partnership Project; Technical Specification Group Service and System Aspects; Telecommunication management; Charging management; Diameter charging applications (Release 11)

Although it is not a prerequisite to using this guide, familiarity with the target platform would be an advantage.

This manual describes system tasks that should only be carried out by suitably trained operators.

Related Documents

The following documents are related to this document:

- Advanced Control Services Technical Guide
- Charging Control Services Technical Guide
- Charging Control Services User's Guide
- Service Management System Technical Guide
- Service Management System User's Guide
- Service Logic Execution Environment Technical Guide

Document Conventions

Typographical Conventions

The following terms and typographical conventions are used in the Oracle Communications Network Charging and Control (NCC) documentation.

Formatting Convention	Type of Information
Special Bold	Items you must select, such as names of tabs.
	Names of database tables and fields.
Italics	Name of a document, chapter, topic or other publication.
	Emphasis within text.
Button	The name of a button to click or a key to press.
	Example: To close the window, either click Close , or press Esc .
Key+Key	Key combinations for which the user must press and hold down one key and then press another.
	Example: Ctrl+P or Alt+F4.
Monospace	Examples of code or standard output.
Monospace Bold	Text that you must enter.
variable	Used to indicate variables or text that should be replaced with an actual value.
menu option > menu option >	Used to indicate the cascading menu option to be selected.
	Example: Operator Functions > Report Functions
hypertext link	Used to indicate a hypertext link.

Specialized terms and acronyms are defined in the glossary at the end of this guide.

System Overview

Overview

Introduction

This chapter provides a high-level overview of the application. It explains the basic functionality of the system and lists the main components.

It is not intended to advise on any specific Oracle Communications Network Charging and Control (NCC) network or service implications of the product.

In this Chapter

This chapter contains the following topics.	
What is Diameter Control Agent?1	

What is Diameter Control Agent?

Introduction

The Diameter Control Agent (DCA) is a SLEE interface used to translate between Diameter messages and CAP 3 INAP.

Diameter is a protocol which has been designed to supersede RADIUS, and which facilitates AAA (Authentication, Authorization and Accounting), and Credit-Control. This protocol forms the basis of a Credit-Control solution for Oracle IMS (IP Multimedia Subsystem) products.

The DCA acts as a Diameter based credit control server. In doing so, it provides an interface to the Prepaid Charging product (CCS component), to facilitate the use of the billing functionality provided there.

Features

The DCA provides the following features:

- Provides support for AVPs specified in TS 32.299.
 - Allows an AVP to be mapped to any INAP operation argument; for example, InitialDP.calledPartyNumber
 - Allows AVPs from any CCR to be mapped to ACS profile fields
 - Allows ACS Profile fields to be mapped to any CCA response sent to a CC-Client
 - Allows specification of complex mappings between AVPs and ACS Profile fields (including type ARRAY)
- Supports call-screening without the need to start a billing session.
- Provides free call support (the ability to send DIAMETER CREDIT CONTROL NOT APPLICABLE as a response).
- Support for Mobile Network operators (MNO) who provide their own variations on 3GPP and IETF Diameter standards for Credit Control, including:
 - Service triggering

- Extensions to standards based enumerated values
- Default units may be assumed by operators, but be specified explicitly later in the call flows
- Ability to track elapsed-time at the interface and report back to the client
- Allows result-codes set by the interface to be mapped
- Supports the use of non-standard capabilities negotiation


Per-Message Type AVP Mapping

The AVP mapping rules configurable in DCA are:

- CCR INITIAL_REQUEST
- CCR EVENT_REQUEST
- CCA INITIAL_REQUEST
- CCA EVENT_REQUEST
- CCR UPDATE_REQUEST (one or more existing services) + CCA UPDATE_REQUEST
- CCR TERMINATION_REQUEST + CCA TERMINATION_REQUEST

Diagram

Here is a high level diagram showing Diameter Control Agent in the context of NCC components.



DCA Components

In this diagram, the components that are specific to DCA are:

- **Diameter Client**
- Diameter messages
- DCA interface
- CAP3/INAP within the SLEE

Screening

DCA screening provides the ability to configure one or more service entries in the **eserv.config** file that do not specify a Service-Identifier or a Rating-Group. Additionally, these services contain a flag indicating that they are for screening. Screening is only available if no default Rating-Group has been specified in the config file.

When a Diameter Initial CCR is received by DCA with no Service-Identifier or Rating-Group, DCA will check the configured services for a service that matches the remaining AVPs. If such a service is found, then the corresponding control plan will be triggered.

The control plans used for screening can perform logic, and will return the result of screening by returning either a continue for success, or a release for failure. In both cases, extra information can be passed between the CCR/CCA and ACS using the inbound and outbound AVP mapping features listed in *Per-Message Type AVP Mapping* (on page 2).

On receipt of the continue or release from ACS, DCA will shut down the dialog to ACS, and return the relevant response to Diameter.

Refer to the following:

- Configuration file parameter screeningService (on page 63) in the Services section
- ACS Control Plan for Screening (on page 124)

Configuration

Overview

Introduction

This chapter explains how to configure the Oracle Communications Network Charging and Control (NCC) application.

In this chapter

This chapter contains the following topics. RAR Configuration......8 Prepaid Charging Configuration9 INAP Extensions 12

Configuration Overview

Introduction

This topic provides a high level overview of how the Diameter Control Agent (DCA) interface is configured.

There are configuration options which are added to the configuration files that are not explained in this chapter. These configuration options are required by the application and should not be changed.

Configuration Components

The Diameter Control Agent is configured by the following components:

Component	Locations	Description	Further Information
eserv.config	All SLC machines	DCA is configured by the DIAMETER section of eserv.config.	eserv.config Configuration (on page 6).
eserv.config	All SLC machines	DCA services mappings are configured in the ccsServiceLibrary section of eserv.config.	CCS Service Library configuration (on page 9).
SLEE.cfg	All SLC machines	The SLEE interface is configured to include the DCA	SLEE.cfg Configuration (on page 7) and SLEE Technical

Component	Locations	Description	Further Information
		service.	Guide.
acs.conf	All SLC machines	Configures the cc extension Digits/INAP extension mappings	acs.conf Configuration (on page 9)

eserv.config Configuration

Introduction

The **eserv.config** file is a shared configuration file, from which many Oracle Communications Network Charging and Control (NCC) applications read their configuration. Each NCC machine (SMS, SLC, and VWS) has its own version of this configuration file, containing configuration relevant to that machine. The **eserv.config** file contains different sections; each application reads the sections of the file that contains data relevant to it.

The eserv.config file is located in the /IN/service_packages/ directory.

The **eserv.config** file format uses hierarchical groupings, and most applications make use of this to divide the options into logical groupings.

Configuration File Format

To organize the configuration data within the **eserv.config** file, some sections are nested within other sections. Configuration details are opened and closed using either { } or [].

- Groups of parameters are enclosed with curly brackets { }
- An array of parameters is enclosed in square brackets []
- Comments are prefaced with a # at the beginning of the line

To list things within a group or an array, elements must be separated by at least one comma or at least one line break. Any of the following formats can be used, as in this example:

```
{ name="route6", id = 3, prefixes = [ "00000148", "0000473"] }
     { name="route7", id = 4, prefixes = [ "000001049" ] }
or
     { name="route6"
        id = 3
        prefixes = [
            "00000148"
             "0000473"
     { name="route7"
        id = 4
        prefixes = [
            "000001049"
    }
or
    { name="route6"
        id = 3
        prefixes = [ "00000148", "0000473" ]
    { name="route7", id = 4
        prefixes = [ "000001049" ]
```

eserv.config Files Delivered

Most applications come with an example eserv.config configuration in a file called eserv.config.example in the root of the application directory. The example file for DCA is:

/IN/service packages/eserv.config.dca.example

Warning: This file is not intended to be changed by the User. Please contact the Oracle support with your queries.

Editing the File

Open the configuration file on your system using a standard text editor. Do not use text editors, such as Microsoft Word, that attach control characters. These can be, for example, Microsoft DOS or Windows line termination characters (for example, ^M), which are not visible to the user, at the end of each row. This causes file errors when the application tries to read the configuration file.

Always keep a backup of your file before making any changes to it. This ensures you have a working copy to which you can return.

Loading eserv.config Changes

If you change the configuration file, you must restart the appropriate parts of the service to enable the new options to take effect.

Diameter eserv.config Configuration

The eserv.config file must be configured to enable the DCA to work. All necessary DCA configuration in eserv.config is done at installation time by the configuration script. However, you must manually map the service handles for services to the libdcaCcsSvcExtra.so library in the ccsPluginExtend section of ccsServiceLibrary. Refer to CCS Service Library configuration (on page 9).

Note: The DCA configuration options in eserv.config are explained in the section on the diameterControlAgent background process (on page 23).

SLEE.cfg Configuration

Introduction

The SLEE.cfg file must be configured to enable the DCA to work. All necessary SLEE configuration is done at installation time by the configuration script, this section is for information only.

The SLEE configuration file is located at /IN/service packages/SLEE/etc/SLEE.cfg.

For more information on SLEE configuration, see SLEE Technical Guide.

DCA SLEE Configuration

On installation, the following lines are added to the **SLEE.cfg** configuration file.

```
INTERFACE=dcaIf dca.sh /IN/service packages/DCA/bin EVENT
SERVICEKEY=INTEGER 1230 Dca Session
SERVICEKEY=INTEGER 1231 Dca DD
SERVICEKEY=INTEGER 1232 Dca RA
SERVICEKEY=INTEGER 1233 Dca CB
SERVICEKEY=INTEGER 1234 Dca PE
SERVICE=Dca Session 1 slee acs Dca Session
SERVICE=Dca DD 1 slee acs Dca DD
SERVICE=Dca RA 1 slee acs Dca RA
```

```
SERVICE=Dca_CB 1 slee_acs Dca_CB
SERVICE=Dca PE 1 slee acs Dca_PE
```

Note: It is essential for the correct operation of this application that the SLEE Interface type is always set to EVENT.

SERVICEKEY

The SERVICEKEY entries specify the SLEE service keys for the Diameter service.

During dcaScp installation the value of the service keys can be specified, or modified manually after installation, if necessary.

RAR Configuration

Diameter Charging Driver (DCD) can forward re-authorization requests (RARs) to DCA for forwarding on to network elements such as the Online Charging Server (OCS). You enable DCA to process RARs by setting the following parameter:

```
rarHandlingEnabled = true
```

When RAR processing is enabled in DCA, DCA informs DCD that it can process RAR messages, and DCD uses this information to pass on any RARs it receives from the OCS. DCA then forwards the reauthorization response that it receives back from the network to DCD, for DCD to forward on to the OCS. If DCD is not informed by DCA, then DCD will respond to a RAR with a re-authorization acknowledgement (RAA) containing the corresponding result code set in the rarResultCode parameter.

Add the following parameters to the DIAMETER configuration section in the **eserv.config** file to enable DCA to process RARs:

```
DIAMETER = {
DCAInstances = {

rarHandlingEnabled = true
rarClientTimeout = int
rarMaxRetry = int
}
}
```

See DCAInstances Parameters (on page 36) for more information.

You must also add service library entries to the CCS section of the **eserv.config** file using the following syntax:

```
CCS = {
  ccsServiceLibrary = {
  ccsPluginExtend = {
  library="libdcdCcsSvcExtra.so"
  handleName="Dca_Session"
  }
  }
}
```

where Dca Session is the name of the DCA session service.

Ensure the corresponding SERVICEKEY and SERVICE entries in the SLEE configuration file (**SLEE.cfg**) are present for the DCA session service. For example:

```
SERVICEKEY=INTEGER 1230 Dca_Session SERVICE=Dca Session 1 slee acs Dca Session
```

For more information on RAR processing in DCD, see the RAR configuration section in *Diameter Charging Driver Technical Guide*.

acs.conf Configuration

Introduction

The acs.conf file must be configured to enable the application to work. All necessary configuration is done at installation time by the configuration script; this section is for information only.

The ACS configuration file is located at /IN/service_packages/ACS/etc/acs.conf.

Refer to ACS Technical Guide for details on ACS configuration.

INAP Extension

The following values for cc extension Digits and INAP extension mappings and format are set in acs.conf on installation. You can change these, if required.

```
extensionNumber 3 506 asn1Integer value
extensionNumber 4 507 asn1Integer value
extensionNumber 5 501 asn1Integer value
extensionNumber 6 502 asn1Integer value
extensionNumber 7 503 asn1Integer value
extensionNumber 8 504 asn1Integer value
extensionNumber 9 505 octets value
```

Note: The extension Number n is displayed as CC Extension Digits n in the drop-down fields (for example, Number of Events) in the macro node configuration screens. See Control Plans (on page 117) for examples.

Prepaid Charging Configuration

CCS Service Library configuration

In order for the PRICE_ENQUIRY, DIRECT_DEBITING and REFUND_ACCOUNT services to work properly, you must manually map the service handles for these services to the libdcaCcsSvcExtra.so library in the CCS.ccsServiceLibrary.ccsPluginExtend section of the /IN/service_packages/eserv.config file. For example:

```
CCS = {
    ccsServiceLibrary = {
        ccsPluginExtend = [
            library="libdcaCcsSvcExtra.so"
            handleName="Dca PE"
            library="libdcaCcsSvcExtra.so"
            handleName="Dca DD"
            library="libdcaCcsSvcExtra.so"
            handleName="Dca RA"
```

]


Enabling Named Events

The DCA installation does as much as possible to be usable as soon as it is installed. However, you need to perform one manual procedure in Prepaid Charging before you try to use it first-off. You need to allow the use of the named events that are installed to whatever product types that you employ,

Here is an example of the procedure to follow to allocate product types to a DCA event set.

Step Action In the SMS main screen, open Services > Prepaid Charging > Rating Management. Result: The Rating Management screen will display. Select the Named Event tab.


3 From the Event Set drop-down box, select DCA Sample Events.



Action Step

4 From the Named Event grid, select Cent and click Edit.

Result: The Edit Named Event screen appears.



- 5 From the Available Named Event Catalogues field, select the named event catalogues for this event that will use DCA billing and click >> Add >>.
- 6 Click Save.
- 7 Repeat steps 4 through 6 for the Second named event.


Refer to CCS User's Guide, Named Event topic for details.

Feature Node Configuration

Named Event Node

The Named Event node must be configured as shown for the following fields:

- Event Class A Diameter (DCA) event class
- Number of Events Location Incoming Session Data



• Number of Events Field — CC Extension Digits 5

INAP Extensions

Introduction

As INAP is not designed to contain Diameter AVPs, these will be carried, where necessary, in INAP extensions in the InitialDP or the Connect. The following pre-defined INAP extension types are used, where appropriate.

Comments

Save

Cancel

The IDP extensions are used by the service loader plug-in to modify the CCS/ACS call context. Also, the control plans may access these extensions by means of suitable **acs.conf** configuration and by use of the ExtensionDigits[0-9] call context fields. See *Control Plans* (on page 117) for examples of control plans using these extensions.

In addition, inbound extension profiles may be set using the encodedExtension and extensionFormat parameters. This enables inbound AVPs within INITIAL or EVENT based Credit-Control-Request messages to be identified for mapping into the IDP passed to ACS. Multiple AVPs can be identified and passed to the target profile tags available within the inbound extensions block.

Note: While you can have multiple AVP mappings, you can have only three extension mappings from DCA to slee acs. You can create extension mappings either by specifying an encoded extension value. for example extensionType = 508, or by encoding as an extension profile block, which is extension type 701. Note that all profile tags go into one profile block and therefore use only one extension.

Therefore, if you define a profile encoded AVP, you have only 2 more user-defined extensions available. For example, you can have either three AVPs mapped directly to INAP extensions or two AVPs mapped directly to INAP extensions and multiple AVPs that are encoded in one profile block that is mapped to extension type 701.

IDP

The following standard INAP extensions are used in the IDP. This table also lists the mapping of the INAP extensions to the Call Content extension Digits profile buffers.

Extension	Description	Туре	cc extension Digits
501	Requested-Service-Units	Asn1Integer	5
502	Requested service unit type: • 1 = CC-Time • 2 = CC-Money • 3 = CC-Total-Octets • 4 = CC-Input-Octets • 5 = CC-Output-Octets • 6 = CC-Service-Specific-Units	Asn1Integer	6
503	Requested-action: • 0 = DIRECT_DEBITING • 1 = REFUND_ACCOUNT • 2 = CHECK_BALANCE • 3 = PRICE_ENQUIRY	Asn1Integer	7
504	Event-Timestamp	Asn1Integer	8
505	Subscription ID	Asn1OctetString	9
506	Currency	Asn1Integer. Value from ISO 4217, for example, 978 = Euro	3
507	Exponent	Asn1Integer. Currency exponent + 0x20. for example, 1E for -2	4
701	Multiple encoded AVPs	Inbound extension profile block	

Note: The cc extension Digits-INAP extension mappings are set in acs.conf on installation and can be changed, if required. See acs.conf Configuration (on page 9).

Connection

The following INAP extensions are used in the Connect operation.

Extension	Description	Туре
601	Granted service units	Asn1Integer
602	Granted service unit type: • 1 = CC-Time • 2 = CC-Money • 3 = CC-Total-Octets • 4 = CC-Input-Octets • 5 = CC-Output-Octets • 6 = CC-Service-Specific-Units	Asn1Integer
603	Cost information (in system currency) Asn1OctetString	

Parameter Mappings

Introduction

This topic describes the mappings between INAP parameters and Diameter AVPs.

CCR

This table describes the mappings for Credit-Control-Request AVPs.

AVP	Action	
Session-Id	Used to look up the correct StateMachine in sessionIdToStatemachine.	
Origin-Host	The stack code in the DIAMETER module handles this.	
Origin-Realm	The stack code in the DIAMETER module handles this.	
Destination-Realm	The stack code in the DIAMETER module handles this.	
Auth-Application- Id	Throw it out if not 4	
Service-Context- Id	Used as part of the key to look up the service.	
CC-Request-Type	Used as part of the key to look up the service.	
	Also used to determine the next state in the state machine.	
CC-Request-Number	Used in duplicate detection.	
Destination-Host	The stack code in the DIAMETER module handles this.	
User-Name	Ignored unless mapped to an IDP extension by the AVP mappings in eserv.config.	
CC-Sub-Session-Id	Ignored after copying from the request to the answer message.	
	We do not support multiple session IDs but some clients may set this anyway so we just ignore it.	
Acct-Multi-	Ignored after copying from the request to the answer message.	
Session-Id	We do not support multiple session IDs but some clients may set this anyway so we just ignore it.	
Origin-State-Id	Used to detect a client re-booting and wipe sessions for the host if it has rebooted.	

AVP	Action
Event-Timestamp	For EVENT_REQUEST messages, this gets copied into IDP extension type 504.
Subscription-Id	One or more Subscription-Id AVPs may be supplied. The first SIP or E164 type Subscription-Id is copied to: • CallingPartyNumber after applying the configured normalization rules and • IDP extension type 505.
	The first IMSI type Subscription-Id is copied to IMSI.
	Note: There must be an E164 or SIP type Subscription -Id present. Otherwise the message will be rejected.
Service- Identifier	Used as part of the key to look up the service.
Termination-Cause	Use cmnDebug() to trace this if this transaction is being traced. Otherwise, ignore.
Requested- Service-Unit	The type of the service unit (derived from which sub-AVP is contained within this one) is placed in IDP extension type 502. The value of the sub-AVP is placed in IDP extension type 501.
	Multiple unit types are supported. You can perform Basic and MSCC services, with the following provisos: • The units in Initial request are the units for the whole session, that is, you cannot add another unit mid-session.
	 If one unit fails to be granted, the entire service is denied. Multiple units are not suitable for use in event based credit control, because the call or dialog with ACS is a one-shot for each type (likely through a Named Event node). If multiple calls are opened to ACS and one of them happens to fail, it is too late for DCA to go back and revoke the successful cases.
Requested-Action	Used as part of the key to look up the service.
Used-Service-Unit	Also used to determine the next state in the state machine. The cumulative total of all the Used-Service-Unit AVPs is copied to ApplyChargingReport.timeNoTariffSwitch (multiplied by 10 to be in deciseconds if the unit type is Time). The variable dca::StateMachine:: totalUsedUnits is used for storing this information.
Multiple- Services- Indicator	If this is set to MULTIPLE_SERVICES_SUPPORTED then DCA will accept the incoming message and subsequent Multiple-Services-Credit-Control AVPs received in CCR/CCA update and final request messages.
	Note: This parameter will not be mapped to the InitialDP.
Multiple- Services-Credit- Control	This is a grouped AVP that can contain these AVPs: Requested-Service-Unit Used Service-Unit Service-Identifier Rating Group Requires that Multiple-Services-Indicator AVP has been received with value set to MULTIPLE_SERVICES_SUPPORTED.
	For multiple services credit control, a single session typically comprises multiple services. Each service is identified by either the Service-identifier

AVP	Action	
	or Rating-Group (where no Service-identifier). Requests received are handled as follows: • INITIAL-REQUEST – One IDP is sent for each service. The Diameter session will have multiple INAP dialogs with slee_acs. • UPDATE-REQUEST for a new Service-identifier/Rating-Group – Starts a new service within the session and causes DCA to send another IDP. • UPDATE-REQUEST with no requested-service-unit AVP – Ends a service within the session. • TERMINATION-REQUEST – Ends the whole session.	
	Note:	
	• If more than one unit type is received within this AVP, DCA will recognize the used-service-unit AVP in update and termination request messages and will extract the relevant unit used. Typically this will be the unit previously specified in the granted service unit.	
	If no relevant unit is found then DCA returns CCA (Multiple-Services-Credit-Control(result-Code = DIAMETER_INVALID_AVP_VALUE)).	
Service- Parameter-Info	Ignored unless mapped to an IDP extension by the AVP mappings in eserv.config.	
CC-Correlation-Id	Ignored unless mapped to an IDP extension by the AVP mappings in eserv.config.	
User-Equipment- Info	Ignored unless mapped to an IDP extension by the AVP mappings in eserv.config.	
Proxy-Info	The stack code in the DIAMETER module handles this.	
Route-Record	Ignored at present.	

CCA

This table describes the mappings for Credit-Control-Answer AVPs.

AVP	Set from
Session-Id	The Session-Id AVP of the first message in this transaction. (stored in dca::StateMachine:: sessionId
Result-Code	Set to DIAMETER_SUCCESS unless otherwise stated.
Origin-Host	The stack code in the DIAMETER module sets this.
Origin-Realm	The stack code in the DIAMETER module sets this.
Auth-Application- Id	Set to 4
CC-Request-Type	Leave as the stack default, that is, the value of CC-Request-Type from the corresponding request.
CC-Request-Number	Leave as the stack default, that is, the value of CC-Request-Number from the corresponding request.
User-Name	Not set
CC-Session- Failover	Not set (will default to FAILOVER-NOT-SUPPORTED according to <i>RFC 4006</i>)
CC-Sub-Session-Id	Set to the value from the corresponding request message, of present.
Acct-Multi-	Set to the value from the corresponding request message, of present.

AVP	Set from	
Session-Id		
Origin-State-Id	Set to dca::ControlAgent::originStateId.	
Event-Timestamp	Set to the value of the Event-Timestamp AVP from the corresponding request.	
Granted-Service- Unit	For session based services, this is ApplyCharging.maxDuration (divided by 10 if the unit type is Time). The unit type is obtained from the "DCA Unit Type" profile tag, if it is available in the ApplyCharging extension profile block. For Requested-Action type DIRECT_DEBIT, in the success case, this is the same as the Requested-Service-Unit AVP in the corresponding request. Otherwise, not present.	
Multiple- Services-Credit- Control	DCA will populate the MSCC AVPs in CCA messages with the following sub-AVPs where applicable:	
Cost-Information	For Request-Action type PRICE_ENQUIRY, success case, this comes from	
Final-Unit- Indication	the value of extension 603 in the INAP Connect. Otherwise, not set. Final-Unit-Action is set to REDIRECT or TERMINATE depending on the INAP operations received. Redirect-Server is set to the number matched in the redirectNumbers config list or TEL: <connect destinationroutingaddress="">@<configured host="" sip="">.</configured></connect>	
Check-Balance- Result	This is derived from the type of INAP operation received as described in the Check balance, with a result of enough credit (on page 20) scenario.	
Credit-Control- Failure-Handling	Set to TERMINATE.	
Direct-Debiting- Failure-Handling	Not set. (According to <i>RFC 4006</i> , it will default to TERMINATE_OR_BUFFER).	
Validity-Time	Set to the configured validity-time for the service in the graceful termination scenarios only. See the <i>Funds expiry, redirect, top-up and reconnect</i> (on page 21) scenario.	
Redirect-Host	Not set.	
Redirect-Host- Usage	Not set.	
Redirect-Max- Cache-Time	Not set.	
Proxy-Info	The stack code in the DIAMETER module sets this.	
Route-Record	Not set at the moment.	

AVP	Set from
	If we set this in the future, the stack code in the DIAMETER module will set this.
Failed-AVP	Set in some cases when Result-Code != success.

Business Scenarios

Introduction

This topic explains how the flow through the software achieves Diameter server services and also gives more details on the mapping between INAP operations/parameters and Diameter messages/AVPs.


The following scenarios are based on (and named after) the relevant appendixes in RFC 4006.

For each business scenario, a message sequence chart is given.

For sample message flows, refer also to the DCA Messages Flows chapter in Sample Message Flows Reference Guide.


Successful session-based charging, client terminates session

Here is an example successful session-based charging, client terminates session.




Multimedia messaging direct debit scenario

Here is an example multimedia messaging direct debit scenario.




Check balance, with a result of enough credit

Here is an example check balance, with a result of enough credit.




Price enquiry


Here is an example price enquiry.



Funds expiry, redirect, top-up and reconnect


Here is an example funds expiry, redirect, top-up and reconnect.





Multiple services credit control scenario

Here is an example multiple services credit control scenario.



Background Processes

Overview

Introduction

This chapter explains the process which runs automatically as part of the Oracle Communications Network Charging and Control (NCC) application. This process is started automatically by the SLEE.

In this chapter

This chapter contains the following topics.

diameterControlAgent Process

Purpose

The diameterControlAgent executable is a SLEE interface which converts between Diameter messages and CAP3 operations to enable a Diameter client to communicate with a CAP3 SCF.

Startup

This process is started automatically by the SLEE. For more information see SLEE.cfg Configuration (on page 7).

DIAMETER Configuration Structure

Here is the high-level structure of the DIAMETER configuration section of the eserv.config file.

```
DIAMETER = {
    DCADefaults = {
        DCADefaults parameters
    DCAInstances = [
    # First Instance
    NumberRules = [
        NumberRules_parameters
    ]
        DCAIinstances parameters
    ]
    RedirectNumberMappings = [
```

```
{
   RedirectNumberMappings parameters
Tracing = {
   Tracing parameters
   Services = [
        Services parameters
   DiameterServer = {
       DiameterServer_parameters
} # end of First Instance
] # end of DCAInstances section
PeerSchemes = [
# First Scheme
   schemeName = "SchemeA"
   Peers = [
       peerhost1 parameters
       peerhost2_parameters
    }
    schemeName = "SchemeB"
       SchemeB_parameters
1 # End of PeerSchemes section
```

Failure

If the diameterControlAgent fails, no Diameter messages will be processed.

DCADefaults Configuration Section

Example DCADefaults Configuration in eserv.config File

Here is an example DCADefaults section of the DIAMETER configuration in the eserv.config file.

```
DCADefaults = {
    sleeServiceKey = 1234
    inapServiceKey = 1234
    maxSessionLengthAfterFinalUnitIndicationsSeconds = 14340
    tcc = 3600
```

```
gracefulTerminationValidityTime = 300
   validityTime = 30
   systemErrorResultCode = 5012
   invalidMessageSequenceResultCode = 5012
   itc = "udi"
   AvpMappings = [
       AvpCodes = [
           avpCode = 1234
           mandatory = true
           vendorId = "16747"
        avpFormat = "OctetString"
        sipScheme = "sip"
       extensionType = 1234
       extensionFormat = "inapnumber"
        conversion = [
           { internal = 1, external = 5030 }
            { internal = 16, external = 2001 }
            { internal = 17, external = 3004 }
            { internal = 42, external = 5006 }
            { internal = 111, external = 3001 }
       mappingTypes = ["InitialRequest", "InitialResponse", "EventRequest",
        "EventResponse"]
   ]
}
```

DCADefaults Parameters

The following parameters are used as defaults if not specified in a Service. They are found within the DCADefaults = { } statement.

avpMappings

Syntax: avpMappings = [mappings parameters]

Description: The default service AVP mappings.

Optionality: Mandatory

Notes: See AvpMappings Parameters (on page 28).

gracefulTerminationValidityTime

gracefulTerminationValidityTime = seconds Syntax:

Description: The number of seconds granted for the user to top up the account during graceful

termination. Refer to RFC 4006 A.7.

Type: Integer Optionality: Optional Allowed: in seconds

Default:

Notes: Not present means no graceful termination.

Example: gracefulTerminationValidityTime = 300 inapServiceKey

Syntax: inapServiceKey = value

Description: The INAP Key value

Type: Integer

Optionality: Mandatory

Allowed: Any 32 bit integer

Example: inapServiceKey = 1234

invalidMessageSequenceResultCode

Syntax: invalidMessageSequenceResultCode = code

Description: The error code for an invalid message sequence result, for example, if

TERMINATION_REQUEST is the first message.

Type: Integer
Optionality: Mandatory

Allowed:

Default: 5012 [Diameter unable to comply]

Notes: See Part 7.1 of RFC 3588 and Part 9 of RFC 4006 for a list valid codes.

Example: invalidMessageSequenceResultCode = 5012

itc

Syntax: itc = infoTransferCapability

Description: The Bearer Capability Information Element (Q.931 section 4.5.5) contains an

Information Transfer Capability (ITC) field that is set automatically by DCA when

DCA triggers ACS.

This parameter overrides the ITC value within the Bearer Capability Information

Element.

For more details, please see itc (on page 62) parameter under the Services

section.

Type: Integer, or string

Optionality: Optional

Allowed:

Default:

Notes: If automatic setting of ITC is required, then this parameter should be absent.

Example: itc = 16

or

itc = "3.1kHzAudio"

or

itc = 0x10

mappingTypes

Syntax: mappingTypes = ["mapping_types"]

Description: Specifies the cases that the mapping applies to.

Type: String Array
Optionality: Optional

Allowed:

Default:

Notes: For more details, please see the mapping Types (on page 70) parameter under

the Services section.

Example: mappingTypes = ["InitialRequest", "UpdateRequest",

"EventRequest", "TerminateRequest"]

maxSessionLengthAfterFinalUnitIndicationsSeconds

Syntax: ${\tt maxSessionLengthAfterFinalUnitIndicationsSecon}$

ds = secs

Description: The maximum number of seconds that a session can last after

the Final-Unit-Indication AVP has been sent to the client.

Type: Integer

Optionality: Optional (default used if not set).

Allowed: A valid integer.

Default: 14340

 ${\tt maxSessionLengthAfterFinalUnitIndicationsSecon}$ Example:

ds = 14340

sleeServiceKey

sleeServiceKey = value Syntax

Description: The Service Key value

Type: Integer Optionality: Mandatory

Allowed: Refer to SLEE Technical Guide

Default: N/A

sleeServiceKey = 1234Example:

systemErrorResultCode

Syntax: systemErrorResultCode = code Description: The error code for a system error

Type: Integer Optionality: Mandatory

Allowed:

Default:

5012 [Diameter unable to comply]

Notes: See Part 7.1 of RFC 3588 and Part 9 of RFC 4006 for a list valid codes

Example: systemErrorResultCode = 5012

tcc

tcc = value Syntax:

Description: The Session supervision timer timeout

Type: Integer Optionality: Mandatory

number of seconds Allowed:

Default: 3600

Refer to RFC 4006. Notes:

Example: tcc = 3600

validityTime

Syntax: validityTime = seconds

Description: The validity time in seconds of granted units. Results in Validity-Time AVP being

placed in CCA.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: -1 (Not included)

Notes:

Example: validityTime = 30

AvpMappings Parameters

The following parameters are used for AVP mappings. They are all found within an AvpMappings = [array.

You can set up as many AVP mappings as required.

Within this section you can specify AVP codes for mapping. They are all found within an AvpCodes = [] array.

There MUST be one specified for the base AVP, plus list all extras for grouped AVPs.

AVP Format to Extension Type

This table shows the allowable conversion of AVP format to the Extension type.

AVP Format	Extension Type	Notes
OctetString	INAP Number	Not allowed
Time	INAP Number	Not allowed
String/OctetStrin	Integer	Must be ASCII digits
g		Converts to Integer
String	INAP Number	Must be Hex digits
Integer	String/Octets	Converts to string
Time	Integer	Number of seconds since 1 January 1970
Time	String/Octets	In format YYYYMMDDHH24mmss

AVP Casting

Casting between the AVP format and the encoded extension format is supported only for encoded extension formats with variable sizes. All other encoded extension formats are fixed in size and cannot be casted. In the eserv.config file, encoded extension formats are defined by the profileFormat parameter. See *profileFormat* (on page 69) for more information.

This table shows the profileFormat values that have variable sizes (which can be casted) versus fixed sizes (which cannot be casted).

Size Type	profileFormat Value
Variable size	LNSTRING, STRING, NSTRING, and RAW_DATA
Fixed size	INTEGER, INTEGER64, UINTEGER, UINTEGER64, TIME, BOOLEAN,

Size Type	profileFormat Value
	and ARRAY

For example, the following configuration casts an OctetString AVP format (1 byte) as a STRING encoded extension format (1 byte), which is supported:

```
AvpCodes = [
   {
      avpCode = 21 # RAT-Type
      mandatory = true
      vendorId = 10415
]
avpFormat = "OctetString"
encodedExtension = {
profileTag = 6760105
profileFormat = "STRING"
```

In contrast, the following configuration attempts to cast an OctetString AVP format (1 byte) as an INTEGER encoded extension format (4 bytes), which is not supported:

```
AvpCodes = [
   {
      avpCode = 21 # RAT-Type
      mandatory = true
      vendorId = 10415
]
avpFormat = "OctetString"
encodedExtension = {
profileTag = 6760105
profileFormat = "INTEGER"
```

avpCode

Syntax: avpCode = code

Description: The AVP code for this AVP.

Type: Integer Optionality: Mandatory

Notes: This parameter is an element of the AvpCodes parameter array.

avpCode = 1234Example:

AvpCodes

AvpCodes = [avpcodes] Syntax:

The AVP code[s] specifying the AVP. Description:

Array Type: Optional Optionality:

Allowed: Default:

Notes: FULLY-QUALIFIED AVP CODE:

If more than 1 element is specified in this array, the AvpCodes refer to a Fully-

Qualified "path" into the AVP hierarchy.

RELATIVE AVP CODE:

If only a single entry is specified and if this "AvpCodes" is used within the "AVPs" Array Section, each element in "AvpCodes" is relative and all the nested AVPs collectively form the complete "path" to specifying the AVP within the hierarchy.

Example: AvpCodes = [

{
 avpCode = 1234
 mandatory = true
 vendorId = "16747"
 }
}

avpFormat

Syntax: avpFormat = "format"

Description: The format of the AVP.

Type: String
Optionality: Mandatory

Allowed: Allowed values are:

- "OctetString"
 - "Integer32"
 - "Integer64"
 - "Unsigned32"
 - "Unsigned64"
 - "Address"
 - "Time"
 - "UTF8String"
 - "DiameterIdentity"
 - "DiameterURI"
 - "Enumerated"
 - "Grouped" Only valid if used in Service Specific AVP Mappings (on page 81)

Example: avpFormat = "OctetString"

conversion

Syntax: conversion = [mappings]

Description: For Integer type formats, you can use this parameter to define a conversion table

(for outbound mapping) for further mapping of internal (typically INAP cause, or

acsProfile values) to external (that is, Diameter AVP) values.

Type: Parameter array

Optionality: Optional

Allowed: Default: Notes: Example: This example is mapping from internal INAP Cause codes to its Diameter Result-

Code.

```
conversion = [
 { internal = 1, external = 5030 }
 { internal = 16, external = 2001 }
 { internal = 17, external = 3004 }
 { internal = 42, external = 5006 }
 { internal = 111, external = 3001 }
```

extensionFormat

Syntax: extensionFormat = "format"

Description: The format of the extension in ACS.

Type: String Optionality: Optional

"inapnumber" Allowed:

> "asn1integer" "octets"

"encoded" - Only valid if used in Service Specific AVP Mappings. See encodedExtension (on page 67).

Notes:

Example: extensionFormat = "inapnumber"

extensionType

Syntax: extensionType = typeDescription: The InitialDP extension type

Type: Integer Optionality: Mandatory

Notes: Cannot be a pre-defined INAP extension

nonProfile Encoded Extensions should be considered deprecated

Example: extensionType = 1234

external

Syntax: external = value

Description: The external value to be put into the AVP to be sent.

Type: Integer Optionality: Optional

Allowed: Default:

Notes: Member of the conversion section.

external = 5030Example:

internal

Syntax: internal = value

Description: The internal value (typically INAP cause or acsProfile values) from ACS.

Type: Integer Optionality: Optional

Allowed:

Default:

Notes: Member of the conversion section.

internal = 1Example:

mandatory

Syntax mandatory = true|false

Description: Whether the AVP code is mandatory

Type: Boolean Optionality: Optional Allowed: true, false Default: false

Notes: This parameter is an element of the AvpCodes parameter array.

mandatory = true Example:

noa

Syntax: noa = value

Description: The Nature of Address (NOA) for the INAP number. If a SIP Address AVP

telephone number is not international, the NOA of a mapped INAP Number will be

set to the value specified in this parameter.

Type: Integer

Optionality: Optional (default used if not set).

1 - Subscriber Allowed:

> 2 - Unknown 3 - National 4 - International

Default:

Notes: The NoA field of an INAP Number will be set to International (4) if the mapped

SIP address AVP telephone number begins with '+'.

Example: noa = 2

sipScheme

sipScheme = "sip scheme" Syntax:

Description: Indicates that the AVP contains a SIP address conforming to the URL scheme

configured.

Type: String

Optionality: Optional (default used if not present).

Allowed: Allowed values:

> "sip" "tel"

Default: parameter not present. No mapping done. Notes:

If specified, the SIP address (if found in the AVP) will be extracted and used in the mapped field sent to ACS. See sipScheme example configurations (on page 33).

The following parameter must be set:

avpFormat = "UTF8String" - if not set, AVP mapping will be ianored.

If a sipScheme is used, the destination is restricted. It can only be mapped to one of the following:

- inapField
- extensionFormat (of "inapnumber", or "octets")

If not specified, this indicates that the AVP does not contain a SIP address, so no address information will be extracted from the AVP.

Example:

```
sipScheme = "sip"
```

sipScheme example configurations

The following examples illustrate the use of the sipScheme parameter in the AvpMappings configuration, and the resulting mappings.

Example 1

Map AVP 1000 to the called Party Number field in IDP. For example, with "sip:+12125551212@phone2net.com;tag=887s", the digits+12125551212 are mapped to calledPartyNumber.

```
{
   AvpCodes = [
       {
            avpCode = 1001
    avpFormat = "UTF8String"
    sipScheme = "sip"
    inapField = ["calledPartyNumber"]
   mappingTypes = ["InitialRequest"]
```

Example 2

Map AVP 2000 to extension 7890 of type InapNumber. For example, with "tel:+358-555-1234567", the digits+358-555-1234567 are mapped to extension 7890.

```
AvpCodes = [
    {
        avpCode = 2000
avpFormat = "UTF8String"
sipScheme = "tel"
extensionFormat = "inapnumber"
extensionType = 7890
mappingTypes = ["InitialRequest"]
```

Example 3

Map AVP 2000 to extension 8000 of type InapNumber. For example, with "tel:555-1234567", the digits 555-1234567 are mapped to extension 8000. Because the number is not internationalized (no leading '+'), you must set the Nature of Address (noa parameter) to the configured value of 2.

vendorId

Syntax: vendorId = "id"

Description: The vendor specific AVP, if present.

Type: String
Optionality: Optional

Notes: This parameter is an element of the AvpCodes parameter array.

Example: vendorId = "16747"

DCAInstances Configuration Section

Introduction

Due to the size and complexity of the DCAInstances configuration, the description is broken down into the following topics:

- DCAInstances Parameters (on page 36)
- NumberRules Parameters (on page 43)
- RedirectNumberMappings Parameters (on page 45)
- Tracing Parameters (on page 46)
- DiameterServer parameters (on page 48)
- Services Configuration (on page 58)
- Service Specific AVP Mappings (on page 81)

DCAInstances configuration structure

Here is the high level structure of the configuration of an instance in the DCAInstances section of the DIAMETER configuration in the eserv.config file.

```
DCAInstances = [
# First Instance
{
NumberRules = [
    NumberRules_parameters
]
dummyDestination = "0000"
systemCurrencyCode = 978
systemCurrencyExponent = -2
multipleServicesRatingGroup = 0
```

```
allowDefaultRatingGroup = false
customDefaultUnits = false
dontDiscardRatingGroupInResponse = true
SIPDomain = "SIP Domain"
SIPPrefix = "SIP prefix"
ignoreRSU = true
rarHandlingEnabled = false
rarClientTimeout = 30
rarMaxRetry = None
RedirectNumberMappings = [
    RedirectNumberMappings parameters
]
Tracing = {
    Tracing parameters.
instanceName = "dcaIf"
scheme = "SchemeA"
systemErrorResultCode = 5012
invalidMessageSequenceResultCode = 5012
sessionBasedDuplicateDetection = true
returnServiceResultCodeInRoot = false
ggsnSupportsFinalUnitIndication = true
ccDuplicateStoreSize = 20
maxAnswerReorder = 2
roundingThreshold = "0.5"
roundingDetail = "ceil"
SubscriptionIdTypes = [
   Ο,
    2,
1
Services = [
    Services_parameters.
DiameterServer = {
    DiameterServer parameters
} # end of First Instance
] # end of Instances section
```

Note: Default settings are specified at installation time.

DCAInstances Parameters

Here are the parameters for the DCAInstances section.

allowDefaultRatingGroup

Syntax: allowDefaultRatingGroup = true|false Description: Whether or not to use the default Rating Group.

Type: Boolean

Optionality: Optional (default used if not set).

Allowed: If set to:

> and if no Service-Identifier AVP or Rating-Group AVP true is received in the initial request CCR, DCA will use

> > the Default Rating Group defined in multipleServicesRatingGroup.

DCA will not use the default Rating Group but instead

will wait for the Service-Identifier AVP or Rating-

Group AVP in the subsequent request.

Default: false

Notes:

Example: allowDefaultRatingGroup = false

ccDuplicateStoreSize

Syntax: ccDuplicateStoreSize = value

Description: The number of credit-control messages to maintain, when checking for

duplicates.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 20

Notes: Requires sessionBasedDuplicateDetection to be set to true.

Example: ccDuplicateStoreSize = 10

customDefaultUnits

Syntax: customDefaultUnits = true|false

Description: Applies only when multiple service credit control (MSCC) is in

use. Try to accommodate operator-specific ways of handling

default units in the following circumstances: An initial request with an MSCC having:

A Used-Service-Unit AVP containing CC-Time = 0

No Requested-Service-Unit AVP

An update request with an MSCC having:

An Used-Service-Unit AVP containing CC-Time =

<actual used>

No Requested-Service-Unit AVP

Type: Boolean

Optionality: Optional (default used if not set) Allowed:

- true DCA behaves as if the RSU had been specified with the unit type of CC-Time.
- false DCA behaves as it normally does if no RSU has been specified.

Default:

false

Notes:

Example: customDefaultUnits = true

dummyDestination

Syntax:

dummyDestination = "num"

Description:

Used as the Called Party Number in the InitialDP.

Type:

Number string

Optionality:

Mandatory

Allowed:

Digits

Default:

0000

Notes:

DCA requires a destination; however we do not use it.

Example:

dummyDestination = "0000"

dontDiscardRatingGroupInResponse

Syntax:

dontDiscardRatingGroupInResponse = true|false

Description:

If set to true, and a Service-Identifier AVP, and a Rating-Group AVP are both received in the request AVP (for MSCC),

then the Rating-Group AVP is returned in the CCA response.

Otherwise the Rating-Group AVP is not returned.

Type:

Boolean

Optionality: Optional (default used if not set).

Default:

Example:

dontDiscardRatingGroupInResponse = false

ggsnSupportsFinalUnitIndication

Syntax:

ggsnSupportsFinalUnitIndication = true|false Whether or not the GGSN supports final unit indication AVPs.

Description: Type:

Boolean

Optionality:

Optional (default used if not set).

Allowed:

true, false

Default:

true

Notes:

A false value implies a non-compliant GGSN.

Example:

ggsnSupportsFinalUnitIndication = true

ignoreRSU

Syntax:

ignoreRSU = true|false

Description:

Specifies whether DCA ignores any unit types in Requested-Service-Unit AVPs that are

included in a request. This parameter applies to session request types only.

Type:

Boolean

Optionality:

Optional (default used if not set)

Allowed:

- true DCA ignores any unit types in Requested-Service-Unit AVPs that are included in a request by treating them like empty RSUs.
- false DCA recognizes all Requested-Service-Unit AVPs in requests.

Default: false

Notes:

Example: ignoreRSU = true

instanceName

Syntax: instanceName = "name"

Description: The unique identifying name for this instance.

Type: String
Optionality: Mandatory

Allowed: This must match the interface name in SLEE.cfg. See SLEE.cfg Configuration (on

page 7).

Default: no default

Notes:

Example: instanceName = "dcaIf"

invalidMessageSequenceResultCode

Syntax: invalidMessageSequenceResultCode = code

Description: The error code for an invalid message sequence result, for example, if

TERMINATION_REQUEST is the first message.

Type: Integer
Optionality: Mandatory

Allowed:

Default: 5012 [Diameter unable to comply]

Notes: See Part 7.1 of *RFC* 3588 and Part 9 of *RFC* 4006 for a list valid codes.

Example: invalidMessageSequenceResultCode = 5012

maxAnswerReorder

Syntax: maxAnswerReorder = number

Description: The maximum number of answers to consider for reordering, before giving up,

and answering.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 10

Notes:

Example: maxAnswerReorder = 2

multipleServicesRatingGroup

Syntax: multipleServicesRatingGroup = value

Description: Rating Group value used to populate Rating Group AVPs in Multiple Services

Credit Control AVPs.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 0

Notes:

Example: multipleServicesRatingGroup = 3

originHostMustBeFQDN

Syntax: originHostMustBeFQDN = true

Description: Sets whether the Origin-Host needs to be a fully qualified domain name.

Type: Boolean

Optionality: Optional (default used if not set)

Allowed: true = DCA will reject messages

false = DCA will accept messages

Default: true

Notes: With this parameter set to true, DCA will reject messages from an Origin-Host which is

not a fully qualified domain name. If this parameter is set to false, DCA will accept

messages regardless of the Origin-Host parameter.

Example: originHostMustBeFQDN = true

rarClientTimeout

Syntax: rarClientTimeout = int

Description: Specifies the time, in seconds, that the DCA will wait for an RAA response from the

Diameter client

Type: Integer
Allowed: >=0
Default: 30

Notes: Set rarClientTimeout to 0 (zero) to disable timeouts.

Example: rarClientTimeout=30

rarHandlingEnabled

Syntax: rarHandlingEnabled = true|false

Description: Determines whether RAR Handling is enabled in DCD

Type: Boolean

Optionality: Optional (default used if not set)

Allowed: true, false
Default: false

Notes: When rarHandlingEnabled is set to false, the DCD responds to an RAR with an

RAA containing the corresponding result code set in the rarResultCode parameter

Example: rarHandlingEnabled = false

rarMaxRetry

Syntax: rarMaxRetry = int

Description: Specifies the maximum number of times that the DCA will attempt to re-transmit an

RAR to the Diameter client

Type: Integer Allowed: >=1

Default: None

Notes: A single re-transmit is allowed per timeout.

returnServiceResultCodeInRoot

Syntax: returnServiceResultCodeInRoot = true|false

Description: Whether or not service result codes should always be returned in the root level

(against the dictates of RFC 4006).

Type: Boolean

Optionality: Optional (default used if not set).

Allowed: true, false
Default: false

Notes: A true value implies a non-compliant GGSN.

Important: This can only apply (work sensibly) where there is a single service.

Example: returnServiceResultCodeInRoot = false

roundingThreshold

Syntax: roundingThreshold = "fraction"

Description: The threshold for rounding fractional unit values to integers.

Fractional parts less than this amount are rounded down, fractional parts greater

than this amount are rounded up.

Type: String containing a float

Optionality: Optional (default used if not set).

Allowed: Between 0.0 and 1.0

Default: "0.5"

Notes: If you want to truncate, set this to "1".

If you want to round all non-integers upwards, then set this to "0" and use "floor"

for roundingDetail parameter).

Example: roundingThreshold = "0.5"

roundingDetail

Syntax: roundingDetail = "rounding"

Description: The direction to round the number when the fractional part equals the

roundingThreshold.

Type: String

Optionality: Optional (default used if not set)

Allowed: Allowed values are:

"ceil" means upwards "floor" means downwards

Default: "ceil"

Notes:

Example: roundingDetail = "ceil"

scheme

Syntax: scheme = "name"

Description: The name of which scheme configuration this instance uses.

Type: String

Optionality:

Mandatory

Allowed:

This must be a SchemeName from the PeerSchemes section.

Default:

no default

Notes:

Example:

scheme = "SchemeA"

sessionBasedDuplicateDetection

Syntax:

sessionBasedDuplicateDetection = true|false

Description:

Whether to use CC-Request-Number and Session-Id for duplicate detection for session based services, as specified in RFC 4006. Otherwise the algorithm from

RFC 3588 is used.

Type:

Boolean

Optionality: Allowed:

Mandatory true, false

Default:

true

Notes:

Set to false if the clients do not implement this mechanism from RFC 4006.

Example:

sessionBasedDuplicateDetection = true

SIPDomain

Syntax:

SIPDomain= "domain"

Description:

The SIP domain for telephone redirections.

Type:

String

Optionality:

Mandatory

Allowed:

Default:

no default

Notes:

Used when no redirectNumberMapping exists for the given value.

Example:

SIPDomain = "oracle.com"

SIPPrefix

Syntax:

SIPPrefix= "prefix"

Description:

The SIP prefix for telephone redirections.

Type:

String

Optionality:

Mandatory

Allowed:

Default:

"tel+"

Notes:

Example:

Used in redirect-server-address when connect received from SLEE_acs. Used when no RedirectNumberMapping exists for the given value.

SIPDomain = "tel+"

SubscriptionIdTypes

Syntax:

SubscriptionIdTypes = [Ids]

Description:

If there is more than one Diameter Subscription-ID in the request, the

Subscription-ID with a Subscription-ID-Type nearest the top of this list is used.

Type:

Integer array

Optionality:

Optional (default used if not set).

Allowed: Subscription-ID-Types defined in *RFC 3588* are:

0 END USER E164

The identifier is in international E.164 format (for example, MSISDN), according to the ITU-T E.164 numbering plan defined in [E164] and [CE164].

1 END USER IMSI

The identifier is in international IMSI format, according to the ITU-T E.212 numbering plan as defined in

[E212] and [CE212].

2 END_USER_SIP_URI

The identifier is in the form of a SIP URI, as defined in [SIP].

3 END_USER_NAI

The identifier is in the form of a Network Access Identifier, as defined in [NAI].

4 END USER PRIVATE

The Identifier is a credit-control server private identifier.

Default: 0, 2, 1

Notes: If an entry in the list is not matched, then a Diameter error is returned.

Example: SubscriptionIdTypes = [

0, 2, 1

1

systemCurrencyCode

Syntax: systemCurrencyCode = code

Description: The ISO 4217 code of the currency.

Type: Integer
Optionality: Mandatory

Allowed: ISO 4217 code of the currency.

Default: 978 (Euro)

Notes:

Example: systemCurrencyCode = 978

systemCurrencyExponent

Syntax: systemCurrencyExponent = code

Description: The exponent value of small units for a big unit in the currency.

Type: Integer
Optionality: Mandatory

Allowed:

Default: -2 (100 small units for every big unit.)

Notes:

Example: systemCurrencyExponent = -2

systemErrorResultCode

Syntax: systemErrorResultCode = code

Description: The error code for a system error

Type: Integer Optionality: Mandatory

Allowed:

Default: 5012 [Diameter unable to comply]

Notes: See Part 7.1 of RFC 3588 and Part 9 of RFC 4006 for a list valid codes

Example: systemErrorResultCode = 5012

NumberRules Parameters

The following parameters define the number normalization rules for DCA. They are found within NumberRules = [].

This section is optional.

Example NumberRules configuration

Here is an example NumberRules section of the DCAInstances configuration.

```
NumberRules = [
   { prefix="25", fromNoa=3, min=8, max=9, remove=0, prepend="0" }
    { fromNoa=4, remove=0, prepend="00" }
   { prefix="027", min=9, remove=1, resultNoa=3 }
    { prefix="00", min=5, remove=2, prepend="", resultNoa=4 }
```

fromNoa

Syntax: fromNoa = int

Description: Used when attempting to match the nature of address (NoA) number contained in

a message. If there is a match, the fromNoa part of the number rule is evaluated.

Type: Integer Optionality: Required

2 - For unknown NoAs Allowed:

3 - For national NoAs

4 - For international NoAs

Notes: If you omit from Noa from the NumberRules parameter section, then no

matching rule will be found.

fromNoa = 3Example:

max

Syntax: max = num

Description: Specifies the maximum number of digits a number may contain. To meet the max

part of the number rule, the number of digits in the number must be equal to or

less than the value of max.

Type: Integer

Optionality: Optional (default used if not set)

Default: 999 Example: max = 9 min

Syntax: min = num

Description: Specifies the minimum number of digits a number may contain. To meet the min

part of the number rule, the number of digits in the number must be equal to or

greater than the value of min.

Type: Integer

Optionality: Optional (default used if not set)

Default: 0

Notes: The value of the min parameter must be greater than or equal to the value of the

remove (on page 44) parameter.

Example: min = 5

prefix

Syntax: prefix = "pref"

Description: Contains a digit or digits. Used to attempt to match the first digit or digits of a

prefix number with the specified value. If the digit or digits match, the prefix part of

the number rule is met.

Type: String
Optionality: Optional

Allowed: One or more decimal digits

Notes: This parameter is an element of the NumberRules parameter array.

Example: prefix = "25"

prepend

Syntax: prepend = "digits"

Description: Defines digits added to the beginning of a number.

Type: String
Optionality: Optional

Allowed: Any combination of decimal digits, or a null string ("")

Any combination of decimal digits, of a fidit string ()

• If the remove and prepend parameters are both used in the same number rule, "prepend" is added to the beginning of the number after

the number has been modified by the remove parameter.

• The prepend parameter is an element of the NumberRules parameter

array.

Example: prepend = "0"

remove

Notes:

Syntax: remove = num

Description: The number of digits stripped from the beginning of a number.

Type: Integer
Optionality: Required

Notes: The value of the remove parameter must be less than or equal to the value of the

min (on page 44) parameter.

Example: remove = 2

resultNoa

Syntax: resultNoa = noa

Description: A nature of address (NOA) sent to the network.

Type: Integer Optionality: Optional

A value is typically specified in demoralization rules Notes:

This parameter is an element of the NumberRules parameter array

Example: resultNoa = 4

RedirectNumberMappings Parameters

The following parameters are used to map the redirect number. They are found within RedirectNumberMappings = [].

This section in optional.

Example RedirectNumberMappings configuration

Here is an example RedirectNumberMappings section of the DCAInstances configuration.

```
RedirectNumberMappings = [
   prefix = "641234"
   destination = "oracle.com"
   type = "SIP URI"
```

destination

destination = "address" Syntax: The destination address string. Description:

Type:

Optionality: Mandatory if the RedirectNumberMappings section is included.

Allowed: See RFC 4006

Default: N/A

Example: destination = oracle.com

prefix

prefix = pref Syntax:

Description: A prefix of the destination Routing Address in the connect.

Type: Number string

Optionality: Mandatory if the RedirectNumberMappings section is included.

Allowed: **Digits** Default: N/A

prefix = 641234Example:

type

Syntax: type = "type" Description: The destination's type.

Type: String Optionality: Required if the RedirectNumberMappings section is included.

IPv4 Allowed:

IPv6 URL SIP URI

Default: N/A

Example: type = "SIP URI"

Tracing Parameters

The following parameters are used for tracing activities. They are all found within the Tracing = { } statement.

Example Tracing configuration

Here is an example Tracing section of the DCAInstances configuration.

```
Tracing = {
    enabled = true
    OrigAddress = [
        "a.b.c.com.0064212",
        "a.b.c.com.0064213",
        "a.b.c.com.0064214"
    ]
    destinationAddressAvp = 1234
    DestAddress = [
        "a.b.c.com.0064213",
        "a.b.c.com.0064214"
    ]
    traceDebugLevel = "all"
```

destAddress

destAddress = ["addr", "addr"] Syntax:

Description: List of destination addresses that are to be traced.

String array Type: Optionality: Optional

Any valid addresses Allowed:

Default:

Notes: "" = trace all known destination addresses.

destAddress is set to Dest-Realm. Subscription-Id.

Example values: destAddress = [

```
"a.b.c.com.0064213",
"a.b.c.com.0064214"
```

destinationAddressAvp

Syntax: destinationAddressAvp = avp

Description: The AVP to use in destination address as RFC 4006 does not specify this.

Type: Integer Optionality: Optional

Notes: If not specified, destinationAddress is hard-coded to 0000

destinationAddressAvp = 1234 Example:

enabled

Syntax: enabled = true|false **Description:** Switches tracing on or off.

Type: Boolean Optionality: Optional Allowed: true, false Default: false

Notes: If false, then the parameters in the Tracing section are ignored.

enabled = false Example:

origAddress

origAddress = ["addr", "addr"] Syntax:

List of originating addresses that are to be traced. **Description:**

Type: String array Optional Optionality:

Any valid addresses Allowed:

Default:

Notes: "" = trace all known originating addresses.

origAddress is set to <Origin-Realm>.<Subscription-Id.>

origAddrress = [**Example values:**

"a.b.c.com.0064212", "a.b.c.com.0064213", "a.b.c.com.0064214"

traceDebugLevel

traceDebugLevel = "level" Syntax:

Description: The debug level the tracing be at should.

Type: String Optionality: Mandatory

Notes: This is a string, with comma separation in it. See traceDebugLevel in ACS

Technical Guide.

Useful flags are cdaconfig, diameterControlAgent, cdaObjectCounts

Example: traceDebugLevel = "all"

DiameterServer Parameters

The following parameters are used for a Diameter Server. They are all found within DiameterServer = { }.

Example DiameterServer Configuration

Here is an example DiameterServer section in the DCAInstances configuration.

```
DiameterServer = {
   protocol = "both"
   sctpListenPort = "3868"
   tcpListenPort = "3868"
   tcpBindAddress = "192.168.1.1"
   sctpBindAddress = "192.168.1.2"
   Auth-Application-Id = [4, 34, 42]
   Acct-Application-Id = 21
   Vendor-Specific-Application-Identifier = [
           Vendor-Id = 111
           Auth-Application-Id = 1234
        {
           Vendor-Id = 111
           Acct-Application-Id = 4321
   localOriginHost = "creditcontrol.realm3.oracle.com"
   localOriginRealm = "realm3.oracle.com"
   productName = "oracle-dca"
   vendorId = 16247
   Supported-Vendor-Id = [16247, 10415]
   duplicateTime = 240
   duplicateBytes = 31457280
   connectionTimeout = 30
   watchdogPeriod = 30
   inBufferSize = 16384
   outBufferSize = 16384
   sendOriginStateId = false
   sendQuotaThreshold = true
   thirtyTwoBitQuotaThresholds = true
   percentTimeOuotaThreshold = 80
   percentVolumeQotaThreshold = 80
   commitGrantedOnTerminate = false
   allowMultiServiceIdentifier = false
   finalGrantUnused = false
   sessionLimit = 0
   throttleLimitError = 3004
   overLimitError = 3004
   counterLogInterval = 0
   throttleThreshold = 100
   throttleInterval = 100
   sendCreditLimitReachedOnSessionEnd = false
   chargeOnSessionTimeout = true
   sendAbortOnSessionTimeout = true
   commitGrantedOnSessionTimeout = true
   sessionFallbackTcc = 3600
} # End of DiameterServer section
```

Acct-Application-Id

syntax: Acct-Application-Id = [IDs]

Description: The Acct-Application-Id AVP values to include in the Capabilities Exchange

message.

Type: Integer - Single value, or array

Optionality: Optional

Notes: This array may have one or more values, or no value.

If there is only one value, brackets are not required.

If neither Auth-Application-Id, nor Acct-Application-Id is specified,

then Auth-Application-Id = 4.

Examples: Acct-Application-Id = 21

allowMultiServiceIdentifier

allowMultiServiceIdentifier = true|false Syntax:

Description: Whether or not more than one Service-Identifier is supported

for MSSC with a single multiple service credit control AVP.

Boolean Type:

Optionality: Optional (default used if not set).

true - More than one allowed. Triggers a service per Allowed:

Service-Identifier

false - More than one not permitted. Only use the first

Service Identifier

Default: false

Notes:

Example: allowMultiServiceIdentifier = true

Auth-Application-Id

svntax: Auth-Application-Id = [IDs]

Description: The Auth-Application-Id AVP values to include in the Capabilities Exchange

message.

Type: Integer - Single value, or array Optionality: Optional (default used if not set) Notes: For Credit control this is 4.

> This array may have one or more values, or no value. If there is only one value, brackets are not required.

The first Auth-Application-Id (or 4 if none) is placed in that AVP in the CCR

messages also.

If neither Auth-Application-Id, nor Acct-Application-Id is specified,

then Auth-Application-Id = 4.

Default: 4

Examples: Auth-Application-Id = [4, 34, 42]

Auth-Application-Id = 4

chargeOnSessionTimeout

Syntax: chargeOnSessionTimeout = true|false

Description: Indicates how DCA should manage a timeout with an access device (for example,

GGSN).

Type: Boolean

Optionality: Optional (default used if not set). Allowed: If set to true, DCA will attempt to finalize any sessions with ACS that are

associated with the timed-out session -

and..

there is an outstanding Apply

Charging

DCA will respond with an Apply Charging Report with

either the Total Granted Units

or Total Used Units

to ACS.

depending on configuration. we send ERBCSM(oAnswer)

a service's charging is via SMCB (armed to report

oAnswer; no outstanding

ACh)

Default: false

Notes:

Example: chargeOnSessionTimeout = true

commitGrantedOnSessionTimeout

Syntax: commitGrantedOnSessionTimeout = true|false

Description: Indicates whether DCA should request that the Total Granted Units or the Total

Used Units should be committed.

Type: Boolean

Optionality: Optional (default used if not set).

Allowed:

Default: false

Notes:

Example: commitGrantedOnSessionTimeout = false

commitGrantedOnTerminate

Syntax: commitGrantedOnTerminate = true|false

Description: Whether or not to commit granted funds on session terminate where the used

units are not specified.

Type: Boolean

Optionality: Optional (default used if not set).

• true – Commit granted (that is, charges for granted units)

false – Only commit reported used units (that is, does not charge)

Default: false

Notes:

Example: commitGrantedOnTerminate = true

connectionTimeout

Syntax: connectionTimeout = seconds

Description: How long to wait for a reply before considering there is a transport level problem

Type: Integer
Optionality: Mandatory
Allowed: Seconds

Default: 30

Example: connectionTimeout = 30

counterLogInterval

Syntax: counterLogInterval = secs

Description: The interval in seconds between sending request counts to the syslog file. Set to

0 (zero) if you do not want to log requests.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 600

Notes: This parameter is also used to control the frequency of notice messages that log

the number of requests received, and the frequency of warning messages that log

the number of throttled requests.

Example: counterLogInterval = 0

duplicateBytes

Syntax: duplicateBytes = bytes

Description: How many bytes to allocate to the duplicate detection buffer

Type: Integer Optionality: Mandatory

Default: 31457280 (30 MB)

Example: duplicateBytes = 31457280

duplicateTime

duplicateTime = seconds Syntax:

Description: How long to hold End-to-End Identifiers, when considering them for potential

duplicates.

Type: Integer Optionality: Mandatory Allowed: Seconds Default: 240

Example: duplicateTime = 240

finalGrantUnused

finalGrantUnused = true|false Syntax:

Whether or not to allow re-granting of unused units after a final unit indication is Description:

sent.

Type: Boolean

Optionality: Optional (default used if not set).

Allowed: true, false Default: false

Notes:

Example: finalGrantUnused = true

inBufferSize

inBufferSize = sizeSyntax:

Description: The size, in bytes, of inbound transport buffer. Type: Integer
Optionality: Mandatory

Allowed:

Default: 0 (kernel default)

Example: inBufferSize =16384

throttleLimitError

Syntax: throttleLimitError = Int

Description: The error code generated when a throttle limit is breached.

Type: Integer

Optionality: Optional (default used if not set)

Allowed:

Default: 3004 – Diameter too busy

Notes:

Example: throttleLimitError = 5006

overLimitError

Syntax: overLimitError = int

Description: Sets the error code to use in a throttle-generated CCA, and when rejecting a

session because the memory or session limit has been exceeded.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 3004 – Diameter too busy

Notes:

Example: overLimitError = 3004

protocol

Syntax: protocol = "protocol"

Description: The protocol for this server.

Type: String
Optionality: Mandatory
Allowed: "sctp"

"tcp""both"

Default: "tcp"

Example: protocol = "tcp"

sctpBindAddress

Syntax: sctpBindAddress = "addr"

Description: The SCTP port to listen on for this instance.

Type: String
Optionality: Mandatory

Default: 0 (that is, INADR_ANY)

Example: sctpBindAddress = "192.168.1.2"

sctpListenPort

Syntax: sctpListenPort = "port"

The SCTP port to listen on **Description:**

Type: String Optionality: Mandatory Default: "3868"

Example: sctpListenPort = "3868"

sessionLimit

sessionLimit = int Syntax:

Description: Limits the number of credit control sessions that may be created to the specified

value.

Type: Integer

Optionality: Optional (default used if not set).

Allowed: A positive value.

Default: 0 – Do not apply a limit.

Notes:

sessionLimit = 0Example:

tcpBindAddress

tcpBindAddress = "addr" Syntax:

Description: The TCP port to listen on for this instance.

Type: String Optionality: Mandatory

0 (that is, INADR_ANY) Default:

Example: tcpBindAddress = "192.168.1.1"

tcpListenPort

Syntax: tcpListenPort = "port" **Description:** The TCP port to listen on

Type: String Optionality: Mandatory Default: 3868

tcpListenPort = "3868" Example:

throttleThreshold

Syntax: throttleThreshold = int

Description: The number of initial or event requests to allow in a single interval. You set the length of

> the interval by using the throttleInterval parameter. The control agent counts the number of initial reservations or events received in the current interval and rejects new

requests once the count has gone above the threshold.

Type: Integer

Optionality: Optional (default used if not set)

Allowed:

Default: 0 - Allow all requests Notes:

Example: throttleThreshold = 50

throttleInterval

Syntax: throttleInterval = int

Description: The length, in milli-seconds, of each interval for which new requests will be counted and

checked against the threshold specified in throttleThreshold.

Type: Integer

Optionality: Optional (default used if not set)

Allowed: None Default: 100

Notes: If the value of the throttleInterval is set to any value other than 0 (zero), DCA

rejects new requests and reports an error until the time set by the

throttleInterval.

Example: throttleInterval = 100

localOriginHost

Syntax: localOriginHost = "hostname"

Description: The Origin-Host for messages sent out

Type: String
Optionality: Optional
Default: "hostname"

Notes: Recommended to keep the default value as the hostname of the target node, for

example the SLC.

Example: localOriginHost = "creditcontrol.realm3.oracle.com"

localOriginRealm

Syntax: localOriginRealm = "realmname"

Description: The Origin-Realm for messages sent out

Type: String
Optionality: Mandatory

Notes: Each realm may contain at most one SLC

Example: localOriginRealm = "realm3.oracle.com"

outBufferSize

Syntax: outBufferSize = size

Description: The size, in bytes, of inbound transport buffer.

Type: Integer
Optionality: Mandatory
Allowed: Bytes

Default: 0 (kernel default)

Example: outBufferSize = 16384

percentTimeQuotaThreshold

Syntax: percentTimeQuotaThreshold = percent

Description: The percentage of granted service units of the time quota threshold.

Type: Integer

Optionality: Optional (default used if not set).

0 to 100 per cent Allowed:

Default:

Notes:

Example: percentTimeQuotaThreshold = 80

percentVolumeOuotaThreshold

Syntax: percentVolumeQuotaThreshold = percent

Description: The percentage of granted service units of the volume quota threshold.

Type: Integer

Optionality: Optional (default used if not set).

Allowed: 0 to 100 percent

Default: 0

Notes:

Example: percentVolumeQuotaThreshold = 80

productName

Syntax: productName = "name"

Description: The product name used in Capabilities-Exchange-Answer

Type: String Optionality: Mandatory

Allowed:

Default: "esg-dca" (that is, Diameter Control Agent)

Notes:

Example: productName = "esq-dca"

sendAbortOnSessionTimeout

Syntax: sendAbortOnSessionTimeout = true|false

Description: Indicates whether DCA will send an abort session request to the access device

when the session with that device times out.

Boolean Type:

Optionality: Optional (default used if not set).

Allowed:

Default: false

Notes:

Example: sendAbortOnSessionTimeout = false

sendCreditLimitReachedOnSessionEnd

Syntax: sendCreditLimitReachedOnSessionEnd = true|false

Description: Indicates if we should reply to the final update request for a service (which DCA

> sometimes referred to as a sub-session) with a result code of DIAMETER_CREDIT_LIMIT_REACHED (4012), rather than

DIAMETER_SUCCESS (2001).

Type: Boolean Optionality: Optional (default used if not set).

Allowed: Default:

Notes: For the record, the last update request for a service contains an MSCC with used

service units but no requested-service-units AVP.

Example: sendCreditLimitReachedOnSessionEnd = false

sendOriginStateId

Syntax: sendOriginStateId = true|false

Description: To send or not send the origin state id flag.

Type: Boolean

Optionality: Optional (default used if not set).

Allowed: true, false

Default: true

Notes: Must be set to false if you do not want to send

Example: sendOriginStateId = false

sendQuotaThreshold

Syntax: sendQuotaThreshold = true|false

Description: Whether or not to send volume and quota threshold for MSCC.

Type: Boolean

Optionality: Optional (default used if not set).

Allowed: true, false

Default: true

Notes: Must be set to false if you do not want to send volume and quota threshold.

Example: sendQuotaThreshold = false

sessionFallbackTcc

Syntax: sessionFallbackTcc = seconds

Description: The session fallback tcc timer (in seconds).

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 3600

Notes: This value is used as the tcc timer for sessions that do not have an associated

service.

Example: sessionFallbackTcc = 3600

Supported-Vendor-Id

Syntax: Supported-Vendor-Id = [values]

Description: The Supported-Vendor-Id AVP values to include in the Capabilities Exchange

message.

Type: Integer – Single value, or array

Optionality: Optional

Allowed: Default:

Notes: This field may be specified as an array with either one or more values, or no

value.

If there is only one value, brackets are not required.

Supported-Vendor-Id = [16247, 10415] Example:

thirtyTwoBitQuotaThresholds

Syntax: thirtyTwoBitQuotaThresholds = true|false

Description: Whether to send the Time-Quota-Threshold and Volume-Quota-Threshold AVPs

as 32-bit integers (as supported by a Cisco Release 9 GGSN).

Type: Boolean

Optionality: Optional (default used if not set).

Allowed: true, false Default: true

Notes: If this is false it is sent as a 64-bit integer (as supported by a Cisco Release 7

GGSN).

thirtyTwoBitOuotaThresholds = true Example:

Vendor-Specific-Application-Identifier

Vendor-Specific-Application-Identifier = [values] Syntax:

Description: The Vendor-Specific-Application-Id AVP values

Type: Array Optional Optionality:

Allowed: Default:

Notes:

Vendor-Specific-Application-Identifier = [Example:

> Vendor-Id = 111Auth-Application-Id = 1234Vendor-Id = 111Auth-Application-Id = 4321

vendorId

Syntax: vendorId = id

Description: The Vendor ID to be supplied in the Capabilities-Exchange-Answer.

Type: Integer Optionality: Mandatory Allowed: A valid ID

Default: 0

Notes:

vendorId = 16247Example:

watchdogPeriod

Syntax: watchdogPeriod = seconds

Description: The period between sending out Device Watchdog messages to next-hop peer.

Type: Integer
Optionality: Mandatory
Allowed: Seconds
Default: 30

Example: watchdogPeriod =30

Services Configuration

Introduction

The Services section of the DCAInstances configuration allows you to select a specified service based upon one of the following:

- Service Context ID, Service Identifier, Rating Group, UnitType
- Configurable list of AVP values matched against the inbound message

If the <code>SelectionAVPs</code> is specified, then the <code>serviceContextId</code>, <code>serviceIdentifier</code>, <code>ratingGroup</code>, and <code>unitType</code> parameters cannot be specified.

Note: The service selection rules are tried in order. If you want the service configured by configurable AVPs to be used first, then put the parameters first in the Services section of the **eserv.config** file.

Services configuration structure

Here is the high-level structure of Services configuration section of the DIAMETER configuration in the eserv.config file.

```
Services = [
    serviceName = "<Service name>"
    serviceContextId = "<Service-Context-Id>"
    serviceIdentifier = "<Service-Identifier>"
    ratingGroup = "<Rating-Group>"
    screeningService = false
   unitType = "Time"
    selectionAVPsIsChargingKey = false
   conversionFactor = 1.0
    requestedAction="DIRECT DEBITING"
    sleeServiceKey = 1231
    inapServiceKey = 1231
    tcc = 3600
   gracefulTerminationValidityTime= 300
    itc = "udi"
   validityTime = 30
    sleeTimeout = 10
```

```
SelectionAVPs = [
    {
       AvpCodes = [ { avpCode=5, vendorId=16247 },
                     { avpCode=7, vendorId=16247 } ],
       avpType = "Unsigned64"
       avpValue = 123
        avpValue = "-0x5000000000"
        avpValue = "This Really Is A String"
       isChargingKey = false
    }
]
AVPMappings = [
    {
        base avpmappings
       basic arrayavpmappings
        key array avpmappings
        array_with_conditions_avpmappings
        array with context avpmappings
        conditional_avp_avpmappings
       prefix_tree_avpmappings
        timestamp_avpmappings
```

See Service Specific AVP Mappings (on page 81) for a description of the AVPMappings configuration and examples of specific configuration and mappings.

Services parameters

The following parameters are used for a service. They are all located within the Services array.

As many services as required can be set up.

AvpCodes

Syntax: AvpCodes = [avp codes]

Description: For a description of the AVPCodes parameters, see AvpCodes in the

DCADefaults section.

Type: Array Optionality: Optional

Allowed: Default:

Notes: AvpCodes may be included as a member of the following:

DCADefaults

- SelectionAVPs (on page 63)
- typeCriteria (on page 73)
- the base Service Specific AVP Mappings (on page 81)
- within AVP mappings of each level of a nested array

Example: AvpCodes = [

```
avpCode = 1234
mandatory = true
vendorId = "16747"
}
```

avpMappings

Syntax: avpMappings = [avpMappings parameters]

Description: The service-specific AVP mappings.

Optionality: Optional

Default: If not present, will use the avpMappings in the DCADefaults section.

Notes: See Service Specific AVP Mappings (on page 81).

avpType

Syntax: avpType = "type"

Description: The AVP datatype to match.

Type: String
Optionality: Optional

Allowed: Allowed values are:

Integer32Integer64Unsigned32Unsigned64UTF8String

Enumerated

Default:

Notes: This is a member of the SelectionAVPs array.

Example: paraMeter = "Integer32"

avpValue

Syntax: avpValue = "value" Description: The value to match.

Type: It may be specified either as a number or a quoted string.

Optionality: Optional

Allowed:

Default:

Notes: The config file supports only the signed 32-bit range for numbers. For numbers

outside of that range, put it in quotes.

This is a member of the SelectionAVPs array.

Example: avpValue = 123

avpValue = "-0x5000000000"

avpValue = "This Really Is A String"

conversionFactor

Syntax:

conversionFactor = unit

Description:

The conversion factor to use when communicating with ACS.

Multiplies the value received from ACS by this factor to calculate the

Granted-Service-Unit AVP.

Divides the Used-Service-Unit AVP by this value before sending it to

ACS.

Type: Optionality:

Mandatory

Float

Allowed:

Default:

Defaults to:

0.1 for time

1048576 for octets

1.0 for everything else

Notes: Ignored for CC-Time AVPs (always uses the default of 0.1)

Example: conversionFactor = 1.0

gracefulTerminationValidityTime

gracefulTerminationValidityTime = seconds Syntax:

Description: The number of seconds granted for the user to top up the account during graceful

termination. Refer to RFC 4006 A.7.

Type: Integer Optionality: Optional Allowed: in seconds

Default:

Notes: Not present means no graceful termination.

Example: gracefulTerminationValidityTime = 300

inapServiceKey

Syntax: inapServiceKey = value

Description: The INAP Key value

Type: Integer Optionality: Optional

Allowed: Any 32 bit integer

inapServiceKey = 1234Example:

isChargingKey

Syntax: isChargingKey = true|false

Description:

Type: Boolean

Optionality: Optional (default used if not set).

Allowed: true, false

Default:

Notes: If true, then we may match a Diameter CCR INITIAL_REQUEST, or

UPDATE REQUEST.

If false, then we may only match the INITIAL REQUEST (or if that is empty, then

the first UPDATE REQUEST).

This is a member of the SelectionAVPs array.

Example: isChargingKey = false

itc

Syntax: itc = infoTransferCapability

Description: The Bearer Capability Information Element (Q.931 section 4.5.5) contains an

Information Transfer Capability (ITC) field that is set automatically by DCA when

DCA triggers ACS.

This parameter overrides the ITC value within the Bearer Capability Information

Element.

Type: Integer or string

Optionality: Optional

Allowed: Allowed values are:

String	Integer	Hex	Description
"speech"	0	0x00	Speech
"udi"	8	0x08	Unrestricted Digital Information
"rdi"	9	0x09	Restricted Digital Information
"3.1kHzAudio"	16	0x10	3.1 kHz audio
"udiTA" or "7kHzAudio"	17	0x11	Unrestricted Digital Information with tones/ announcements
"video"	24	0x18	Video

Default: Defaults to one of the following:

• "speech" (0x00), if the Requested-Service-Unit AVP is set to CC-Time.

"udi" (0x08), if otherwise.

Notes: If automatic setting of ITC is required, then this parameter should be absent.

Example: itc = 16

or

itc = "3.1kHzAudio"

or

itc = 0x10

ratingGroup

Syntax: ratingGroup = "number"

Description: The number used to identify the rating group as part of a service triggering rule.

Type: String
Optionality: Optional

Allowed: The value in quotes must be a number.

Default:

Notes: This parameter must not be specified if SelectionAVPs is specified.

Example: ratingGroup = "2"

requestedAction

Syntax: requestedAction = "action"

Description: The action performed by the service

Type: String
Optionality: Optional

Allowed: • DIRECT_DEBITING

REFUND_ACCOUNTCHECK_BALANCEPRICE ENQUIRY

Default: not present

Not present indicates this service is for session based transactions.

See RFC 4006 Requested-Action AVP.

Example: requestedAction = "DIRECT_DEBITING"

screeningService

Syntax: screeningService = true|false

Description: If a screening service is not found for a particular service context ID, then DCA

assumes that no screening needs to take place, that is, the session is allowed.

Type: Boolean

Optionality: Optional (default used if not set).

Allowed: true, false
Default: false

Notes: If the screeningService flag is true, then serviceIdentifier and

 $\verb"ratingGroup" should be blank".$

Example: screeningService = false

SelectionAVPs

Syntax: SelectionAVPs = [selection_avps]

Description: Specifies the AVPs to be matched in an incoming request for the service to be

triggered.

Type: Array
Optionality: Optional

Allowed: Default: Notes: All of the selection AVPs must be matched in an incoming request for the service

to be triggered.

If SelectionAVPs is specified then none of serviceContextId, serviceIdentifier, ratingGroup, Or unitType can be specified.

Example: SelectionAVPs = [

```
{
   AvpCodes = [
   { avpCode=5, vendorId=16247 },
   { avpCode=7, vendorId=16247 } ],
   avpType = "Unsigned64"
   avpValue = 123
   avpValue = "-0x5000000000"
   avpValue = "This Really Is A String"
   isChargingKey = false
   }
}
```

selectionAVPsIsChargingKey

Syntax: selectionAVPsIsChargingKey = true|false

Description: Indicates whether this AVP is a charging key.

Type: Boolean

Optionality: Optional (default used if not set).

Optionally. Optional (default used if not set).

 true – Incoming UPDATE_REQUESTS messages matching this rule, for which there is no current session, will start a new session.

 false – Such messages will be rejected with a Diameter answer with an error result code.

Default: false

Notes:

Allowed:

Example: selectionAVPsIsChargingKey = false

serviceContextId

Syntax: serviceContextId = "id"

Description: The ID of the Service Context

Type: String

Optionality: Mandatory, if SelectionAVPs is not specified.

Notes: This parameter must not be specified if SelectionAVPs is specified.

You must specify both the ServiceContextId and serviceIdentifier to

identify the service. See RFC 4006.

Example: serviceContextId = "3"

serviceIdentifier

Syntax: serviceIdentifier = "Id"

Description: The service identifier number.

Type: Number string
Optionality: Optional

Notes: This parameter must not be specified if SelectionAVPs is specified.

You must specify both the ServiceContextId and serviceIdentifier to

identify the service. See RFC 4006.

serviceIdentifier = "3" Example:

serviceName

Syntax: serviceName = "name"

Description: The unique name of the service

Type: String Optionality: Mandatory Allowed: Any string

Default:

Example: serviceName = "DirectDebitService"

sleeServiceKey

Syntax: sleeServiceKey = value

Description: The Service Key value

Type: Integer Optionality: Optional

Allowed: The value specified in the SERVICEKEY entry in the SLEE.cfg file.

For more information about the SERVICEKEY configuration, see SLEE Technical

Guide

Default: no default

sleeServiceKey = 1234Example:

sleeTimeout

Syntax: sleeTimeout = seconds

Description: How long (in seconds) to wait for a response from the SLEE before the session

times out

Type: Integer

Optionality: Optional (default used if not set)

Allowed:

Default: 10

Notes:

sleeTimeout = 15Example:

tcc

tcc = secondsSyntax:

Description: The session supervision timer timeout

Type: Integer Optionality: Mandatory

Allowed: number of seconds

Default: 3600

Notes: Refer to RFC 4006

tcc = 3600Example:

unitType

Syntax: unitType = "type"

Description: The unit type used in the service

Type: String

Optionality: Mandatory, if SelectionAVPs is not specified.

Allowed: • "Time"

"Money"
 "Tatal Oa

"Total-Octets""Input-Octets""Output-Octets""Service-Specific"

Default: "Time"

Notes: This parameter must not be specified if SelectionAVPs is specified.

Example: unitType = "Time"

validityTime

Syntax: validityTime = seconds

Description: The validity time in seconds of granted units. Results in Validity-Time AVP being

placed in CCA.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: -1 (Not included)

Notes:

Example: validityTime = 30

Service Specific AVP Mappings parameters

The AVPMappings configuration in the Services section contains the following parameters that are used only in the Services section, not in other sections of the DIAMETER configuration.

For AVP parameters used throughout the DIAMETER configuration see *AvpMappings Parameters* (on page 28).

contextAVP

Syntax: contextAVP = true|false

Defines whether the avpCode in the specified AVPs array is the context AVP to

use in an Array with Context (on page 99)

Type: Boolean
Optionality: Optional.

Allowed: Default:

Notes: When only a single unique AVP is used to establish context, that AVP is typically

the key AVP associated with a data record. However DCA also allows more than 1 sub-AVPs in a hierarchy to be marked for inclusion for context. These multiple

AVPs which form the context are know as the Context AVP.

Context AVPs are typically used when possible key values are not well known, or unique, or the key might otherwise rely on multiple items from the hierarchy.

Example: contextAVP = true

encodedExtension

Syntax: encodedExtension= {profile parameters}

Description: This identifies the target tag and type in an incoming extension profile block for

this AVP, when extensionFormat = "encoded".

Parameter list Type:

Optionality: Optional

Allowed:

Default:

Notes: If encodedExtension is present and extensionFormat is absent,

extensionFormat = "encoded" is assumed. See extensionFormat (on page

31) for details.

RAW DATA profile mappings also have extra options (octetsStart and octetsLength) for specifying a part of the AVP (for inbound) or profile field (for

outbound) to extract.

encodedExtension = { Example:

```
profileTag = 99123
profileFormat = "INTEGER"
octetsStart = 3
octetsLength = 0
```

excludeIfMatches

Syntax: excludeIfMatches = [avpvalue]

Description: The value of the AVPs to exclude from the Type Criteria matching.

Type:

Optionality: Optional (default used if not set).

Allowed: Integer, string, hex string

Default:

Notes: This parameter can be used as part of the Base mapping outside AVPs = [...

1.

If used inside AVPs = [...] it must be used as part of the typeCriteria

section. See *typeCriteria* (on page 73) for an example.

Example: Example 1

excludeIfMatches = [101, 105]

Example 2

excludeIfMatches = ["SPAM"]

inapField

Syntax: inapField = [field1, field2, ...]

Description: Identifies the:

Target INAP field(s) for mapping from this AVP for Inbound Mapping

Source INAP field(s) for mapping to this AVP for Outbound Mapping

Type: String array Optionality: Optional

Allowed: The following INAP fields are allowed:

- "additionalCallingpartyId"
- "calledPartyBcdNumber"
- "calledPartyNumber"
- "callingPartyNumber"
- "cause"
- "destinationRoutingAddress"
- "imsi"
- "locationInformation" see note below
- "locationNumber"
- "maxCallDuration"
- "mscAddress"
- "originalCalledPartyId"
- "redirectingPartyId"
- "timelfNoTariffSwitch"

Default:

Notes: If the AVP mappings are to and from INAP Field(s), please do not configure or

specify parameters associated with acsProfile mapping (that is,

 $\verb|extensionFormat| \textbf{should} \ \textbf{not} \ \textbf{be} \ \textbf{set} \ \textbf{to} \ \textit{"encoded} \textit{"encoded} \textit{Extension} \ \textbf{should}$

be absent).

The location information in the AVP is an encoded field. In ACS the location information is split up, to populate the call context buffers of MCC, MNC, LAC, and Cell ID, for originating and terminating. Refer to the ACS Buffers topic in ACS

Feature Nodes User's Guide.

Example: inapField= ["CalledPartyNumber"]

includeIfMatches

Syntax: includeIfMatches = [avpvalue]

Description: The value of the AVPs to include in the Type Criteria matching.

Type: Array

Optionality: Optional (default used if not set).

Allowed: Integer, string, hex string

Default:

Notes: This parameter can be used as part of the Base mapping outside AVPs = [...

].

If used inside AVPs = [...] it must be used as part of the typeCriteria

section. See typeCriteria (on page 73) for an example.

Example: Example 1

includeIfMatches = [1, 10, 101, 1001, 10001]

Example 2

includeIfMatches = ["GoodNews!", "PrettyGoodNews"]

keyArray

Syntax: keyArray = true|false

Description: Defines whether the avpCode in the specified AVPs array is the key to use in a

Key Array (on page 86).

Type: Boolean

Optionality: Optional

Allowed: true, false

Default:

Notes:

Example: keyArray = true

literal

Syntax: literal = "value"

Description: Applies the literal value to the AVP when the outbound message matches the

types defined for that mapping.

String Type: Optionality: Optional

Default:

Notes: Outbound AVP only.

> If a mapping specifies both a literal and an IncludesIfMatches conditional AVP, then the literal will override the mapped value if the original value is found in

the IncludesIfMatches array.

Example: literal = "1"

profileFormat

Syntax: profileFormat = "format"

Description: The format of the profile.

Type: String Optionality: Optional

Allowed: The value given for this must be one of the valid storage formats for ACS profile

fields. The allowable values for this parameter are:

INTEGER

INTEGER64

UINTEGER

UINTEGER64

LNSTRING

NSTRING

STRING

TIME

BOOLEAN

ARRAY

RAW DATA

Default: **INTEGER**

Notes: See also the related parameter, profileTag.

Part of encodedExtension.

If the avpFormat parameter is set to "Grouped" for the AVPs array, then

profileFormat must be "ARRAY"

Example: profileFormat = "LNSTRING"

profileTag

Syntax: profileTag = num

Description: The profile tag.

Type: Integer Optionality: Optional

Notes: This parameter is used to identify the profile tag it will be stored into/retrieved

from. See also the related parameter, profileFormat.

Part of encodedExtension.

Example: profileTag = 999

mappingTypes

Syntax: mappingTypes = ["mapping types"]

Description: Defines the message types between DCA and ACS that the mapping applies to.

Type: String Array

Optionality: Optional (default used if not set).

Allowed: For Inbound:

"InitialRequest""UpdateRequest""EventRequest"

"TerminateRequest"

For Outbound:

"InitialResponse"

"UpdateResponse"

"EventResponse"

"TerminateResponse""FreeCallResponse" – See Notes.

One or more mapping types may be specified.

Note that the Configuration mappingType does not directly correspond to the CC-

Request-Type. See *Mapping categories* (on page 71).

Default: mappingTypes = ["InitialRequest", "InitialResponse",

"EventRequest", "EventResponse"]

Notes: If the configuration, within the AVPs array, for inbound is the same as for

outbound, include the inbound and outbound message types in the list.

Each inbound configuration "Request" mapping Type has a counterpart outbound

"Response" mappingType that (when defined) is applied to the outbound

Diameter message.

For example: If an inbound Diameter message has InitialRequest mappings applied, then InitialResponse mappings will be applied to the corresponding outbound Diameter answer. However, if a call is determined to be free, say after screening, or become free mid-session, then any mappings classified as "FreeCallResponse" (for the selected service) will be applied to the outbound

Diameter answer instead of the default response mapping type.

Example: mappingTypes = ["InitialRequest", "UpdateRequest",

"EventRequest", "TerminateRequest"]

Mapping categories

This table describes the relationship between CC-Request-Type and Configuration mapping Types for outbound request type mappings:

Diameter Message	CC-Request-Type	Credit Control	Service	Requested-Service- Unit	Used-Service-Unit	Configuration mappingTypes
CCR	INITIAL_REQ	MSCC	New	New	-	InitialRequest
CCR	INITIAL_REQ	Basic	New	New	-	InitialRequest
CCR	UPDATE_REQ	MSCC	New	New	-	InitialRequest
CCR	UPDATE_REQ	MSCC	Existin g	Existing UT	Existing UT	UpdateRequest
CCR	UPDATE_REQ	Basic	Existin g	Existing UT	Existing UT	UpdateRequest
CCR	UPDATE_REQ	MSCC	Existin g	-	Existing UT	TerminateRequest
CCR	TERM_REQ	MSCC	any	-	-	TerminateRequest
CCR	TERM_REQ	Basic	any	-	-	TerminateRequest
CCR	EVENT_REQ	-	-	-	-	EventRequest

Here are the abbreviations used in the table.

Abbreviation	Description
CCR	Credit-Control-Request
INITIAL_REQ	INITIAL_REQUEST
UPDATE_REQ	UPDATE_REQUEST
TERM_REQ	TERMINATION_REQUEST
EVENT_REQ	EVENT_REQUEST
MSCC	Multiple-Services-Credit-Control
Basic	Basic Credit-Control
Existing UT	Existing Unit Type

octetsLength

Syntax: octetsLength = num

Description: The number of octets to extract from the source data.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: O (copy all octets from octetsStart until the end of the field)

Notes: Part of encodedExtension.

> Used if profileFormat is RAW_DATA. Used in conjunction with octetsStart.

Example: See examples in octetsStart.

octetsStart

Syntax: octetsStart = num

Description: The offset within the source data (AVP or profile field) to start copying from.

Type: Integer Optionality: Optional (default used if not set).

Allowed:

Default: 0 (start copying from the beginning)

Notes: Negative values can be used to specify an offset from the end of the data.

Part of encodedExtension.

Used if profileFormat is RAW_DATA.

Used in conjunction with octetsLength.

Example: Example 1: Copy all data except for the first 3 octets.

octetsStart = 3
octetsLength = 0

Example 2: Copy the third-to-last and second-to-last octets.

octetsStart = -3
octetsLength = 2

repeating

Syntax: repeating = true|false

Description: Specifies whether the avpCode is repeating, that is the Diameter message

contains an array-like structure where the avpCode is used more than once.

Type: Boolean

Optionality: Optional (default used if not set).

Allowed: true, false

Default: false

Notes: For inbound mappings, the destination will need to be an Array, or Prefix Tree

type profile tag, in order to handle the complex structure.

Outbound mappings need to come from an Array or Prefix Tree.

Example: repeating = true

timestamp

Syntax: timestamp = "timestamp"

Description: The timestamp to record

Type: String
Optionality: Optional

Allowed: The available timestamps are:

"TIME_REQUEST_RECEIVED32""TIME_REQUEST_RECEIVED64"

"TIME_NOW32""TIME_NOW64"

Default:

Notes: 'NOW' refers to the time the mapping is processed. For an outbound mapping, it

will be as the reply is being created, hopefully immediately before it is sent.

'REQUEST_RECEIVED' is the time the request [that we are processing] entered

the Diameter stack.

See *Timestamp* (on page 114) for example usage.

Example: timestamp = "TIME REQUEST RECEIVED32"

typeCriteria

Syntax: typeCriteria = [criteria]

Description: Lists the criteria to match on, then specifies the AVP that is searched and, if a

match is found, mapped to a profile tag.

Type: Parameter section

Optionality: Optional (default used if not set).

Allowed: Default:

Notes:

Example: In this example, if the value of AVP of 1000.2000.3000 is 1, then map the value of each of the AVPs 1000.2000.3001 to array element as tag 100 in the sub-profile

block, as a string.

Note, the parent AvpCodes 1000.2000 are not shown in this example configuration fragment.

```
typeCriteria = [
includeIfMatches = [ 1 ]
AvpCodes = [
 \{ avpCode = 3000 \}
avpFormat = "Integer32"
 # What is included if match found
AVPs = [
AvpCodes = [
 \{ avpCode = 3001 \}
repeating = true
avpFormat = "UTF8String"
encodedExtension = {
profileTag = 100
profileFormat = "STRING"
 1
```

See the example mapping for this configuration in *Mapping* (on page 92).

See more examples in:

- Array with Conditions (on page 89)
- Conditional AVP (on page 104)

PeerSchemes Configuration Section

PeerSchemes configuration structure

Here is a high level structure of the configuration of a scheme in the PeerSchemes section.

```
PeerSchemes = [
```

```
{
    schemeName = "SchemeA"
    Peers = [
        name = "host1"
        protocol = "both"
        permittedOriginHosts = [
            "host1.realm1.oracle.com"
        RemoteAddresses = [
            "192.168.1.10"
        netmaskBits = 32
        netmask6Bits = 128
        permittedInstances = 0
        reqSctpInboundStreams = 8
        regSctpOutboundStreams = 8
    } # end of Peer host1
        peer host2 parameters
    } # end of Peer host2
} # End of Scheme A
    schemeName = "SchemeB"
        SchemeB parameters
    } # End of Scheme B
] # End of PeerSchemes section
```

Note: Default settings are specified at installation time.

PeerSchemes parameters

The following parameter is used in the PeerSchemes array.

schemeName

Syntax: schemeName = "name"

Description: The name identifying the scheme.

Type: String
Optionality: Mandatory

Example: schemeName = "SchemeA"

Peer host parameters

The following parameters are used for a peer host. They are members of the Peers array.

You can be set up as many peer hosts as required. A scheme can have no peers, in which case will accept all connections.

name

name = "name" Syntax:

Description: The name identifying either peer, or group of peers.

Type: String Optionality: Mandatory

name = "host1" Example:

netmaskBits

netmaskBits = bits Syntax:

Description: The number of bits for netmask.

Type: Integer Optionality: Mandatory

Default: 32 (bits for netmask, that is, a single machine (/32))

Example: netmaskBits = 32

netmask6Bits

netmask6Bits = bits Syntax:

Description: The number of bits for the IP version 6 prefix

Type: Integer Optionality: Mandatory

Default: 128 (bits for the address prefix, that is, a single machine (/128))

netmask6Bits = 128Example:

permittedInstances

Syntax: permittedInstances = num Description: The number of permitted instances.

Type: Integer Optionality: Mandatory

Notes: If set to 0 then allow all. Example: permittedInstances = 0

permittedOriginHosts

permittedOriginHosts = "host" Syntax:

Description: The list of peer names which will be checked against the OriginHost AVP, during

the capabilities exchange.

Type: String Optionality: Mandatory

Example value: permittedOriginHosts = "host1.realm1.oracle.com"

protocol

Syntax: protocol = "protocol" **Description:** The protocol for this host peer.

Type: String Optionality: Optional Allowed: • "sctp"

"tcp""both"

Default: If not specified, then it uses the protocol from the DiameterServer section. (on

page 48)

Example: protocol = "tcp"

RemoteAddresses

Syntax: remoteAddresses = ["ipaddress"]

Description: The list of remote IP addresses.

Type: Array of string parameters

Optionality: Mandatory

Notes: If an address becomes unavailable the list will be cycled through.

Example: remoteAddresses = [

"192.168.1.10"

regSctpInboundStreams

Syntax: reqSctpInboundStreams = num

Description: The number of requested inbound sctp streams.

Type: Integer
Optionality: Mandatory

Notes: There is no guarantee you will actually get these.

Example: reqSctpInboundStreams = 8

reqSctpOutboundStreams

Syntax: reqSctpOutboundStreams = num

Description: The number of requested outbound sctp streams.

Type: Integer
Optionality: Mandatory

Notes: There is no guarantee you will actually get these.

Example: reqSctpOutboundStreams = 8

Example PeerSchemes section

Here is an example PeerSchemes section of the DIAMETER configuration in the eserv.config file.

```
RemoteAddresses = [
           "192.168.1.10"
       netmaskBits = 32
       netmask6Bits = 128
       permittedInstances = 0
       reqSctpInboundStreams = 8
       reqSctpOutboundStreams = 8
    } # end of Peer host1
       name = "host2"
       protocol = "sctp"
       permittedOriginHosts = [
           "host1.realm1.oracle.com"
       RemoteAddresses = [
           "192.168.1.11"
       netmaskBits = 32
       netmask6Bits = 128
       permittedInstances = 0
       reqSctpInboundStreams = 8
       regSctpOutboundStreams = 8
    } # end of Peer host2
} # End of Scheme A
   schemeName = "SchemeB"
   Peers = [
       name = "host1"
       protocol = "both"
       permittedOriginHosts = [
            "host1.realm1.oracle.com"
       RemoteAddresses = [
           "192.168.1.10"
        ]
       netmaskBits = 32
       netmask6Bits = 128
       permittedInstances = 0
       reqSctpInboundStreams = 8
```

```
reqSctpOutboundStreams = 8
} # end of Peer host1

]
} # End of Scheme B
] # End of PeerSchemes section
```

Statistics Logged by diameterControlAgent

Introduction

Diameter statistics are generated by each SLC, and then transferred at periodic intervals to the Service Management System (SMS) for permanent storage and analysis.

An existing statistics system (smsStats) provides functions for the collection of basic statistical events. This is provided in the NCC SMS application. Refer to *SMS Technical Guide* for details.

DCA statistics

SMS statistics are logged with APPLICATION ID = 'DCA' (application number 96)

The following statistics are defined:

- DUPLICATES DETECTED
- INITIAL REQUESTS RECEIVED
- INITIAL_REQUESTS_ANSWERED
- UPDATE REQUESTS RECEIVED
- UPDATE_REQUESTS_REJECTED_ANSWERED
- TERMINATION REQUESTS RECEIVED
- TERMINATION REQUESTS ANSWERED
- DIRECT_DEBITS_RECEIVED
- DIRECT DEBITS ANSWERED
- ACCOUNT_REFUNDS_RECEIVED
- ACCOUNT REFUNDS ANSWERED
- BALANCE CHECKS RECEIVED
- BALANCE_CHECKS_ANSWERED
- PRICE ENQUIRIES RECEIVED
- PRICE ENQUIRIES ANSWERED
- UNSUPPORTED MESSAGES
- SESSIONS TIMED OUT
- GENERIC_ACTION_RECEIVED (Tracks requests for non-standard triggering)
- GENERIC_ACTION_ANSWERED (Tracks answers for non-standard triggering)
- RAR UNABLE TO BE DELIVERED (RAR cannot deliver RAR to the Diameter client)
- RAR_ERRORS_RECEIVED (RAR received error response to RAR)
- RAR TIMEOUT (RAR has timed out)
- RAR_SENT (RAR sent from DCA)
- RAR_ANSWERS_RECEIVED (RAA received in response to RAR)
- RAR_UNABLE_TO_COMPLY_RECIEVED (RAA received with UNABLE_TO_COMPLY)
- RAR_LIMITED_SUCCESS_RECEIVED (RAA received with LIMITED_SUCCESS)
- RAR_UNSOLICITED_ANSWER (Unexpected RAA received)

- RAA_EXCEPTION (RAA exception handling)
- RAA_UNKNOWN_SESSION_ID (RAA received with unknown session ID)

For all statistics, the Origin-Realm AVP from the message received is put into SMF_STATISTICS.DETAIL.

Reports

The following reports are available:

- DCA System Stats
- DCA System Stats by Realm

Reports are generated using the SMS Report Functions screen. Refer to the SMS User's Guide for details.

Example report

Here is an example DCA System Stats by Realm report.

```
DCA Statistics Listing by Realm
Start Date: 16 August 2007
Finish Date: 18 August 2007
Report Type: All Entries
Realm: realm2.oracle.com
28 August 2007, 22:50:56
```

Node Name	Statistics ID	Date	Value	
mtv-tst-scp10	DUPLICATES DETECTED	17 August	07 00:52	1
mtv-tst-scp10	DUPLICATES DETECTED	17 August	07 00:54	1
mtv-tst-scp10	INITIAL REQUESTS ANSWERED	16 August	07 00:02	1
mtv-tst-scp10	INITIAL REQUESTS ANSWERED	16 August	07 03:04	1
mtv-tst-scp10	INITIAL REQUESTS ANSWERED	16 August	07 22:34	1
mtv-tst-scp10	INITIAL REQUESTS ANSWERED	7 August	07 00:52	2
mtv-tst-scp10	INITIAL REQUESTS ANSWERED	17 August	07 00:54	2
mtv-tst-scp10	INITIAL REQUESTS ANSWERED	17 August	07 01:00	1
mtv-tst-scp10	INITIAL REQUESTS RECEIVED	16 August	07 00:02	1
mtv-tst-scp10	INITIAL REQUESTS RECEIVED	16 August	07 03:04	1
mtv-tst-scp10	INITIAL REQUESTS RECEIVED	16 August	07 22:34	1
mtv-tst-scp10	INITIAL_REQUESTS_RECEIVED	17 August	07 00:52	2
mtv-tst-scp10	INITIAL REQUESTS RECEIVED	17 August	07 00:54	2
mtv-tst-scp10	INITIAL REQUESTS RECEIVED	17 August	07 01:00	1
mtv-tst-scp10	SESSIONS_TIMED_OUT	17 August	07 00:54	1
mtv-tst-scp10	UPDATE_REQUESTS_ANSWERED	16 August	07 00:02	1
mtv-tst-scp10	UPDATE_REQUESTS_ANSWERED	16 August	07 03:04	1
mtv-tst-scp10	UPDATE REQUESTS ANSWERED	16 August	07 22:34	1
mtv-tst-scp10	UPDATE REQUESTS ANSWERED	17 August	07 00:52	2
mtv-tst-scp10	UPDATE_REQUESTS_ANSWERED	17 August	07 00:54	2
mtv-tst-scp10	UPDATE_REQUESTS_ANSWERED	17 August	07 01:00	1
mtv-tst-scp10	UPDATE_REQUESTS_RECEIVED	16 August	07 00:02	1
mtv-tst-scp10	UPDATE_REQUESTS_RECEIVED	16 August	07 03:04	1
mtv-tst-scp10	UPDATE REQUESTS RECEIVED	16 August	07 22:34	1
mtv-tst-scp10	UPDATE REQUESTS RECEIVED	17 August	07 00:52	2
mtv-tst-scp10	UPDATE_REQUESTS_RECEIVED	17 August	07 00:54	2
mtv-tst-scp10	UPDATE_REQUESTS_RECEIVED	17 August	07 01:00	1

Completed

Service Specific AVP Mappings

Overview

Introduction

This chapter explains the structure of the AVP mappings for a service.

In this chapter

This chapter contains the following topics. Introduction 81 Basic Array83 Key Array86 Array with Context 99

Introduction

Introduction

The AVP mappings within the Services parameter section are organized as shown in Services configuration structure (on page 58).

There are two types of configuration formats available:

- 'classic' format:
 - Base
- 'nested' format. These are configured within an array of format AVPs = []
 - Basic Array (on page 83)
 - Kev Array (on page 86)
 - Array with Conditions (on page 89)
 - Array with Context (on page 99)
 - Conditional AVP (on page 104)
 - Prefix Tree (on page 112)
 - Timestamp (on page 114)

Note: If you use classic format, you cannot use nested format in the eserv.config file.

Base example

Here is an example of the base AVP mappings in the Services AVPMappings section.

General Example 1 - Classic Format. Specify AVP code(s) for this AVP. There MUST be one specified for the base AVP, plus list all extras for grouped AVPs.

{

```
AvpCodes = [
        avpCode = 1234
       mandatory = true|false
       vendorId = "VendorID"
    1
    # The AVP data format.
   avpFormat =
   "OctetString|Integer32|Integer64|UInteger32|UInteger64|Unsigned32|Unsigned64|
   Address|Time|UTF8String|DiameterIdentity|DiameterURI|Enumerated|"
   extensionType = 1234
   extensionFormat = "inapnumber|asnlinteger|octets|encoded"
   encodedExtension= {
       profileTag = 99123
       profileFormat = "INTEGER | INTEGER64 | UINTEGER | UINTEGER64 | LNSTRING |
       NSTRING | STRING | TIME | BOOLEAN | RAW DATA"
       octetsStart = 3
       octetsLength = 0
inapField = [ field1, field2, ... ]
```

Simple conditional

Here is an example using includeIfMatches within Services AvpMappings section, that is, outside an AVPs array in a *typeCriteria* (on page 73) array.

Nested format

Nested formats are generally used to define arrays and conditional AVPs. Definitions are nested in the array formatted AVPs = [] and mirror the hierarchy of a Grouped AVP.

As groups can contain sub-groups, defined "AVPs" can contain sub-"AVPs".

Example nested format

The following example shows an AVP nested up to four levels deep:

- A root-level AVPs with one entry
- A first-level AVPs with one entry
- A second-level AVPs with two entries
- A third-level AVPs with two entries, which are part of the first entry of the second level AVPs.

Here is the configuration structure in the DIAMETER Services AvpMappings array of the example eserv.config.

```
AVPs = [ # Root-Level AVPs
    { # 1st Entry of Root-Level AVPs
        AvpCodes = [ ... ]
        AVPs = [ # 1st-Level AVPs
            { # 1st Entry of 1st-Level AVPs
                AvpCodes = [ ... ]
                AVPs = [ # 2nd-Level AVPs
                    { # 1st Entry of 2nd-Level AVPs
                        AvpCodes = [ ... ]
                        AVPs = [ # 3rd-Level AVPs
                            {  # 1st Entry of 3rd-Level AVPs
                                AvpCodes = [ ... ]
                                avpFormat = "..."
                                encodedExtension = {
                                 profileTag = 80301
                                 profileFormat = "..."
                            { # 2nd Entry of 3rd-Level AVPs
                                AvpCodes = [ ... ]
                                avpFormat = "..."
                                encodedExtension = {
                                 profileTag = 80303
                                 profileFormat = "..."
                            } # End of 2nd Entry of 3rd-Level AVPs
                        ] # End of 3rd-Level AVPs
                    } # End of 1st Entry of 2nd-Level AVPs
                    { # 2nd Entry of 2nd-Level AVPs (optional; specify if applicable)
                        AvpCodes = [ ... ]
                        avpFormat = "..."
                        encodedExtension = {
                            profileTag = 80302
                            profileFormat = "..."
                    } # End of 2nd Entry of 2nd-Level AVPs
                ] # End of 2nd-Level AVPs
                } # End of 1st Entry of 1st-Level AVPs
            ] # End of 1st-Level AVPs
        } # End of 1st Entry of Root-Level AVPs
    ] # End of Root-Level AVPs
avpFormat = "Grouped"
encodedExtension = {
    profileTag = 8234
    profileFormat = "ARRAY"
```

Basic Array

Introduction

Basic Arrays are also known as "simple repeating AVPs". In the simplest case, the repeating AVP is the one which requires mapping to an array in a profile block. DCA will need to establish multiple instances of the same AVP. However you only need define a single Basic Array type mapping definition. The mapping definition needs to establish:

That the target (or source) profile field is an array

- The format of the elements in the target array (for example, STRING)
- The format of the AVP (such as UTF8String)
- That the AVP code is repeating, that is, repeating = true. For a definition, see *repeating* (on page 72).

Note that in this case (unlike Paired-AVPs or Array with Conditions), there is no key or sub-AVPs to consider.

Basic Array configuration

Here is the example basic array configuration in the Services AVPMappings section of the eserv.config. In this example, the basic array contains a list of string-type (that is, profileFormat = "STRING") elements.

```
AVPs = [ # Root-Level AVPs
    { # 1st Entry in Root-Level AVPs
       AvpCodes = [
            {
                avpCode = 6000
        AVPs = [ # 1st Level AVPs
                AvpCodes = [
                    {
                            avpCode = 1000
                AVPs = [ # 2nd Level AVPs
                    {
                        AvpCodes = [
                                avpCode = 2000
                                repeating = true
                        avpFormat = "UTF8String"
                        encodedExtension = {
                            profileTag = 9998
                            profileFormat = "STRING"
                    }
                ] # End of 2nd Level AVPs
            }
        ] # End of 1st Level AVPs
    } # End of 1st Entry in Root-Level AVPs
] # End of Root-Level AVPs
# Specify mapping applies INBOUND only.
mappingTypes = ["InitialRequest", "UpdateRequest", "EventRequest",
"TerminateRequest"]
avpFormat = "Grouped"
encodedExtension = {
   profileTag = 8000
   profileFormat = "ARRAY"
```

Note: The parameter setting of avpFormat = "Grouped" can only be used in this place in the config file, that is, outside an "AVPs = [...]" array. Also an "AVPs = [...]" array must be defined because "Grouped" makes all the AVPs defined inside the "AVPs" = [...] " array as belonging to the one group. Because of this it makes no sense to put avpFormat = "Grouped" anywhere else except

Example Basic Array configuration

Here is a worked example of a basic array: inbound configuration.

```
AVPs = [
   {
       AvpCodes = [
           { avpCode = 1000 }
       AVPs = [
           {
                AvpCodes = [
                    { avpCode = 2000 # <-- 1000.2000
                    repeating = true # <-- 2000 is repeating
                1
                avpFormat = "UTF8String"
                encodedExtension {
                    profileTag = 9998 # Array element in sub-profile block
                    profileFormat = "STRING"
                }
            }
        1
    }
# Specify mapping applies INBOUND only.
mappingTypes = ["InitialRequest", "UpdateRequest", "EventRequest",
"TerminateRequest"
# AVPs above are encoded into an ARRAY-type in an ACS Profile Block.
encodedExtension = {
   profileTag = 8000
   profileFormat = "ARRAY"
```

The configuration for basic arrays: outbound is identical to above, except the mapping types are:

```
# Specify mapping applies OUTBOUND only.
mappingTypes = ["InitialResponse", "UpdateResponse", "EventResponse",
"TerminateResponse"]
```

Mapping

This table shows the mapping of Diameter AVPs to ACS profile blocks resulting from the worked example basic arrays configuration section above. This example is for inbound.

	Diameter A	VP		Profile Block						
Root AVP	1 st Level	Value	Profile (ARRAY)	Sub-Profile Block	Tag	Value				
1000	2000	"049772056"	8000	1	9998	"049772056"				
	2000	"6449016000"		2	9998	"6449016000"				
	2000	"0800500600"		3	9998	"0800500600"				

The mapping is a simple 1:1 mapping. For outbound, the mappings are the same, but in the reverse direction.

Key Array

Introduction

A key array is a set of records where one of the elements within each record can be identified as a key for accessing the record, using the parameter setting keyAVP = true.

Key Arrays configuration

Here is the example Key Array configuration in the Services AVPMappings section of the eserv.config. In this example, elements of the key array contain:

- an integer type Key AVP (avpCodes = 3000)
- three Data AVPs.

```
AVPs = [ # Root-Level AVPs
    { # 1st Entry in Root-Level AVPs
        AvpCodes = [
            {
                avpCode = 6100
        AVPs = [ # 1st-Level AVPs
            { # 1st Entry in 1st-Level AVPs
                AvpCodes = [
                        avpCode = 1000
                AVPs = [ # 2nd-Level AVPs
                    { # 1st Entry of 2nd-Level AVPs
                        AvpCodes = [
                            {
                              avpCode = 2000
                              repeating = true
                        AVPs = [ # 3rd-Level AVPs (Final Level)
                            { # Mapping for Key AVP
                              AvpCodes = [
                                  avpCode = 3000
                              1
                              keyAVP = true
                              avpFormat = "Integer32"
                              encodedExtension = {
                                 profileTag = 100
                                 profileFormat = "INTEGER"
                            } # End of Mapping for Key AVP
                            { # Mapping for 1st Data AVP
                              AvpCodes = [
                                 {
                                   avpCode = 3001
                                 }
```

```
avpFormat = "UTF8String"
                              encodedExtension = {
                                 profileTag = 101
                                profileFormat = "STRING"
                            } # End of Mapping for 1st Data AVP
                            { # Mapping for 2nd Data AVP
                              AvpCodes = [
                                   avpCode = 3002
                              avpFormat = "UTF8String"
                              encodedExtension = {
                                 profileTag = 102
                                 profileFormat = "STRING"
                            } # End of Mapping for 2nd Data AVP
                            { # Mapping for 3rd Data AVP
                              AvpCodes = [
                               {
                                  avpCode = 3003
                              avpFormat = "UTF8String"
                              encodedExtension = {
                                 profileTag = 103
                                 profileFormat = "STRING"
                            } # End of Mapping for 3rd Data AVP
                        ] # End of 3rd-Level AVPs
                    } # End of 1st entry of 2nd-Level AVPs
                ] # End of 2nd Level AVPs
           } # End of 1st Entry in 1st-Level AVPs
       ] # End of 1st-Level AVPs
    } # End of 1st Entry in Root-Level AVPs
] # End of Root-Level AVPs Mappings
# Specify mapping applies INBOUND only.
mappingTypes = ["InitialRequest", "UpdateRequest", "EventRequest",
"TerminateRequest"]
avpFormat = "Grouped"
encodedExtension = {
   profileTag = 8001
   profileFormat = "ARRAY"
```

Example Key Arrays configuration

}

Here is a worked example of Key Arrays: Inbound configuration.

```
AVPs = [
   {
        AvpCodes = [
            { avpCode = 1000 }
        AVPs = [
                AvpCodes = [
```

```
avpCode = 4400
repeating = true
                                                     # <-- 4400 is repeating
                    AVPs = [
                        {
                            AvpCodes = [
                                { avpCode = 4410  # <-- 1000.4400.4410
                            keyAVP = true
                                                       # <--
                                                                  4410 is the key,
                            others below are data AVPs.
                            avpFormat = "Integer32"
                            encodedExtension {
                                profileTag = 9998  # Array element in sub-profile
                                block
                                profileFormat = "INTEGER"
                        }
                            AvpCodes = [
                                { avpCode = 4420  # <-- 1000.4400.4420
                            avpFormat = "UTF8String"
                            encodedExtension {
                                profileTag = 9999  # Array element in sub-profile
                                block
                                profileFormat = "STRING"
                        }
                        {
                            AvpCodes = [
                                { avpCode = 4410  # <-- 1000.4400.4430
                            avpFormat = "UTF8String"
                            encodedExtension {
                                profileTag = 10000 # Array element in sub-profile
                                profileFormat = "STRING"
                        }
                   ]
               }
            ]
        }
    ]
    # Specify mapping applies INBOUND only.
    mappingTypes = ["InitialRequest", "UpdateRequest", "EventRequest",
    "TerminateRequest"
    encodedExtension = {
        profileTag = 8000
        profileFormat = "ARRAY"
The configuration for Key Arrays: Outbound is identical to above, except the mapping types are:
    # Specify mapping applies OUTBOUND only.
    mappingTypes = ["InitialResponse", "UpdateResponse", "EventResponse",
    "TerminateResponse"]
```

 $\{ avpCode = 4400 \}$

<-- 1000.4400

This table shows the mapping of Diameter AVPs to ACS profile blocks resulting from the worked example key array configuration section above. This example is for inbound.

	Dia	meter AVP		Profile Block				
Root AVP	1st Level	2 nd Level	Value	Profile Block (ARRAY)	Sub-Profile Block	Tag	Value	
1000	4400	4410	220	8000	1	9998	220	
		4420	"6449016000"			9999	"6449016000"	
		4430	"Chris"			10000	"Chris"	
	4400	4410	221		2	9998	221	
		4420	"123123123"			9999	"123123123"	
		4430	"Fred"			10000	"Fred"	

The mapping is a simple 1:1 mapping. For outbound, the mappings are the same, but in the reverse direction.

Array with Conditions

Introduction

In the case where the AVP to be mapped is the child of a repeating AVP, or where there are multiple mappings, to be made for different child AVPs, you may apply Array With Conditions mapping.

Array with conditions is a means of performing selective mapping based on the values of other AVPs, that is, not all AVPs are mapped, as DCA only considers or allows specific AVPs to be mapped if and only if a specified criterion is met.

Depending on the mapping type (inbound or outbound), the criteria involves matching the value of an AVP or an acsProfile against a list of known values.

Array with Conditions configuration

Here is the example Array with Conditions configuration in the Services AVPMappings section of the eserv.config.

```
{ # Array with Conditions Example
   AVPs = [ # Root-Level AVPs
           AvpCodes = [ # 1st Entry in Root-Level AVPs
                    avpCode = 7020
           AVPs = [ # 1st-Level AVPs
                { # 1st Entry in 1st-Level AVPs
                   AvpCodes = [
                        {
                            avpCode = 1000
                            repeating = true
                    AVPs = [ # 2nd-Level AVPs
                        { # 1st Entry in 2nd-Level AVPs
                           AvpCodes = [
                                {
                                    avpCode = 2000
                                    repeating = true
```

```
TypeCriteria = [
    {  # 1st Type Criterion
        includeIfMatches = [ 1, 11, 101 ]
        AvpCodes = [
                avpCode = 3000
        avpFormat = "Integer32"
        encodedExtension = {
            profileTag = 80100
            profileFormat = "INTEGER"
        }
        # AVPs below will be included if a match is found
    for 1st Type Criterion
        AVPs = [ # Conditional AVPs for 1st Type
    Criterion
               AvpCodes = [
                   {
                       avpCode = 3001
                       repeating = true
               avpFormat = "UTF8String"
               encodedExtension = {
                   profileTag = 80101
                   profileFormat = "STRING"
               }# End of Conditional AVPs for 1st Type
    Criterion
    } # End of 1st Type Criterion
    { # 2nd Type Criterion
      includeIfMatches = [ 2, 22, 202 ]
       AvpCodes = [
           {
               avpCode = 3000
       avpFormat = "Integer32"
       encodedExtension = {
           profileTag = 80100
           profileFormat = "INTEGER"
       # AVPs below will be included if a match is found
    for 2nd Type Criteria
       AVPs = [ # Conditional AVPs for 2nd Type Criterion
              AvpCodes = [
                      avpCode = 3001
                      repeating = true
             ]
               avpFormat = "UTF8String"
               encodedExtension = {
                  profileTag = 80101
                  profileFormat = "STRING"
```

```
] # End of Conditional AVPs for 2nd Type Criterion
                                } # End of 2nd Type Criterion
                            ] # End of TypeCriteria
                        } # End of 1st Entry of 2nd-Level AVPs
                    ] # End of 2nd-Level AVPs
                } # End of 1st Entry of 1st-Level AVPs
            ] # End of 1st-Level AVPs
        } # End of 1st Entry of Root-Level AVPs
    ] # End of Root-Level AVPs
    # Specify mapping applies INBOUND only.
    mappingTypes = ["InitialRequest", "UpdateRequest", "EventRequest",
    "TerminateRequest"]
    avpFormat = "Grouped"
    encodedExtension = {
        profileTag = 8020
        profileFormat = "ARRAY"
}
```

Array with Conditions - inbound - example 1

Here is a worked example of an array with conditions: inbound configuration.

Map only matching entry, not condition (AVP(3000)==1) inbound

```
AVPs = [
   {
        AvpCodes = [
            { avpCode = 1000 }
        AVPs = [
            {
                AvpCodes = [
                    { avpCode = 2000  # <-- 1000.2000 repeating = true # <-- 2000
                                                  # <-- 2000 is repeating
                TypeCriteria = [
                    {
                        includeIfMatches = [ 1 ]
                        AvpCodes = [
                            { avpCode = 3000  # <-- 1000.2000.3000 Inbound
                            Only
                             }
                        1
                        avpFormat = "Integer32" # <-- Inbound Only</pre>
                         # This is what is included if match found
                        AVPs = [
                            {
                                 AvpCodes = [
                                     { avpCode = 3001  # <-- 1000.2000.3001
                                       repeating = true # <--
                             repeating
                                 avpFormat = "UTF8String"
                                 encodedExtension = {
```

```
profileTag = 100  # Array element in sub-
                               profile block
                                       profileFormat = "STRING"
                           ]
                       }
                  ]
               }
           1
       }
   # Specify mapping applies INBOUND only.
   mappingTypes = ["InitialRequest", "UpdateRequest", "EventRequest",
   "TerminateRequest"]
   encodedExtension = {
       profileTag = 8020
       profileFormat = "ARRAY"
}
```

This table shows the mapping of Diameter AVPs to ACS profile blocks resulting from the worked example array with conditions configuration section above. This example is for inbound. For outbound the arrows are reversed.

	Dia	ameter AVP				Profil	e Block	
Root AVP	1 st Level	2 nd Level	Value		Profile Block (ARRAY)	Sub-Profile Block	Tag	Value
1000	2000	3000	1		8000	1	100	"6449016000"
		3001	"6449016000 <u>"</u>			2	100	"6449016001"
		3001	"6449016001"			3	100	"666666666"
	2000	3000	2					
		3001	"123123123"					
		3001	"6449016000"		200	ľ		
		3001	"6449016001"					
		3001	"6449016002"					
		3001	"6449016003"	٫ ا				
	2000	3000	1 /					
		3001	"666666666"					

Array with Conditions - Inbound - example 2

Here is an example of the array with conditions configuration in the Services AVPMappings section. Map both matching entry and condition.

```
TypeCriteria = [
                       includeIfMatches = [ 1 ]
                       AvpCodes = [
                           \{ avpCode = 3000 \}
                                              # <-- 1000.2000.3000 Inbound
                           Only
                           }
                       avpFormat = "Integer32" # <-- Inbound Only</pre>
                       # This is what is included if match found
                       AVPs = [
                           {
                               AvpCodes = [
                                   { avpCode = 3000  # <-- 1000.2000.3000
                               avpFormat = "Integer32"
                               encodedExtension = {
                                 profileTag = 99  # Array element in sub-
                           profile block
                                  profileFormat = "INTEGER"
                           }
                           {
                               AvpCodes = [
                                   { avpCode = 3001  # <-- 1000.2000.3001
                                     repeating = true # <--
                                                                      3001 is
                           repeating
                               avpFormat = "UTF8String"
                               encodedExtension = {
                                  profileTag = 100  # Array element in sub-
                           profile block
                                   profileFormat = "STRING"
                           }
                      ]
                  }
              ]
          }
       ]
   }
# Specify mapping applies INBOUND only.
mappingTypes = ["InitialRequest", "UpdateRequest", "EventRequest",
"TerminateRequest"]
encodedExtension = {
   profileTag = 8020
   profileFormat = "ARRAY"
```

}

This table shows the mapping of Diameter AVPs to ACS Profile Blocks resulting from the worked example array with conditions configuration section above. This example is for inbound.

	Dia	ameter AVP				Profile	e Block	
Root AVP	1 st Level	2 nd Level	Value		Profile Block (ARRAY)	Sub-Profile Block	Tag	Value
1000	2000	3000	1		8000	1	99	1
		3001	"6449016000"	}		├	100	"6449016000"
		3001	"6449016001"			2	99	1
	2000	3000	2	1			100	"6449016001"
		3001	"123123123"	1		3	99	1
		3001	"6449016000"	1			100	"666666666"
		3001	"6449016001"					
		3001	"6449016002"	1		1		
		3001	"6449016003"	1				
	2000	3000	1					
		3001	"666666666"					

Array with Conditions - outbound - example 1

Here is the example array with conditions: outbound configuration.

Map only profileTag100. No typeCriteria against a profileTag. Outgoing AVP 3000 is set using a literal.

```
AVPs = [
   {
       AvpCodes = [
          { avpCode = 1000 }
       AVPs = [
           {
               AvpCodes = [
                                             # <-- 1000.2000
                 \{ avpCode = 2000 \}
               # Just map as follows (no type Criteria specified)
               AVPs = [
                  {
                      AvpCodes = [
                          { avpCode = 3000 # <-- 1000.2000.3000
                      avpFormat = "Integer32"
                      literal = 1 # i.e. Outbound only (*not*
                      mapping from profileTag99)
                   {
                      AvpCodes = [
                          { avpCode = 3001  # <-- 1000.2000.3001
                           repeating = true # <-- 3001 is repeating
                      avpFormat = "UTF8String"
                      encodedExtension = {
                                           # Array element in sub-profile
                         profileTag = 100
                          block
                          profileFormat = "STRING"
```

```
]
               }
           ]
       }
   ]
   # Specify mapping applies OUTBOUND only.
   mappingTypes = ["InitialResponse", "UpdateResponse", "EventResponse",
   "TerminateResponse"]
   encodedExtension = {
       profileTag = 8000
       profileFormat = "ARRAY"
}
```

This table shows the mapping ACS profile blocks to AVPs in the example array with conditions configuration section in this topic. This example is for outbound.

	Profile Blo			Diameter AVP					
Profile Block (ARRAY)	Sub-Profile Block	Tag	Value	Root AVP	1 st Level AVP	2 nd Level AVP	Value		
8000	1	99	1	1000	2000	3000	1		
		100	"6449016000"	 		3001	"6449016000"		
		101	"something"			3001	"6449016001"		
	2	99	1		-	3001	"666666666"		
		100	"6449016001"						
		101	"something"						
		102	"else"						
	3	99	1 ,	 1					
		100	"66666666"						
		101	"other"						

Array with Conditions - outbound - example 2

Here is the example array with conditions: outbound configuration.

Map only profileTag 100. No typeCriteria against a profileTag. Outgoing AVP 3000 is set using a literal.

```
{
   AVPs = [
       {
           AvpCodes = [
               { avpCode = 1000 }
           AVPs = [
                {
                    AvpCodes = [
                       \{ avpCode = 2000 \}
                                                     # <-- 1000.2000
                         repeating = true
                                                     # <-- 2000 is repeating
                    ]
                    # Just map as follows (no type Criteria specified)
                    AVPs = [
                           AvpCodes = [
                                \{ avpCode = 3000 \}
                                                   # <-- 1000.2000.3000
```

```
1
                           avpFormat = "Integer32"
                           literal = 1  # i.e. Outbound only (*not*
                           mapping from profileTag99)
                           AvpCodes = [
                               { avpCode = 3001  # <-- 1000.2000.3001
                           avpFormat = "UTF8String"
                           encodedExtension = {
                              profileTag = 100
                                                  # Array element in sub-profile
                              block
                              profileFormat = "STRING"
                       }
                   ]
               }
           ]
       }
   # Specify mapping applies OUTBOUND only.
   mappingTypes = ["InitialResponse", "UpdateResponse", "EventResponse",
   "TerminateResponse"]
   encodedExtension = {
       profileTag = 8000
       profileFormat = "ARRAY"
   }
}
```

This table shows the mapping ACS profile blocks to AVPs in the example array with conditions configuration section in this topic. This example is for outbound.

				Dia	meter AVP			
Profile Block (ARRAY)	Sub-Profile Block	Tag	Value		Root AVP	1 st Level AVP	2 nd Level AVP	Value
8000	1	100	"6449016000"		1000	2000	3000	1
		101	"something"				3001	"6449016000"
		102	"else"			2000	3000	1
		103	"and more"				3001	"6449016001"
	2	100	"6449016001"			2000	3000	1
		101	"another"	1		>	3001	"666666666"
		102	"something"	1			•	
		103	"more"					
	3	100	"666666666"					
		100	"and"	1				
		101	"others"					

Array with Conditions - outbound - example 3

Here is the example array with conditions: outbound configuration.

Map only profileTag 100 with typeCriteria specified against profileTag 99. Outgoing AVP 3000 is set based on profileTag 99.

```
{ AVPs = [
```

```
AvpCodes = [
               { avpCode = 1000 }
           AVPs = [
               {
                   AvpCodes = [
                                               # <-- 1000.2000
                       {avpCode = 2000}
                   TypeCriteria = [
                       {
                           includeIfMatches = [ 1 ] # <-- Only profileTag(99)==1</pre>
                           are mapped
                           encodedExtension = {
                               profileTag = 99
                                               # Array element in sub-profile
                              block
                              profileFormat = "INTEGER"
                           # This is what is included if match found:
                           AVPs = [
                              {
                                   AvpCodes = [
                                      { avpCode = 3000  # <-- 1000.2000.3000
                                   1
                                   avpFormat = "Integer32"
                                   encodedExtension = {
                                      profileTag = 99
                                                         # Also include the matched
                               value(1) in outbound msg
                                       profileFormat = "INTEGER"
                                   }
                               }
                               {
                                   AvpCodes = [
                                       { avpCode = 3001 # <-- 1000.2000.3001
                                        repeating = true # <--
                                                                        3001 is
                               repeating
                                   ]
                                   avpFormat = "UTF8String"
                                   encodedExtension = {
                                      profileTag = 100
                                                        # Array element in sub-
                               profile block
                                      profileFormat = "STRING"
                              }
                          ]
                      }
                  1
              }
           ]
       }
   # Specify mapping applies OUTBOUND only.
   mappingTypes = ["InitialResponse", "UpdateResponse", "EventResponse",
   "TerminateResponse"]
   encodedExtension = {
       profileTag = 8000
       profileFormat = "ARRAY"
   }
}
```

This table shows the mapping ACS profile blocks to AVPs in the example array with conditions configuration section in this topic. This example is for outbound.

	Profile Blo	ock			Diameter AVP				
Profile Block (ARRAY)	Sub-Profile Block	Tag	Value	Root AVP	1 st Level AVP	2 nd Level AVP	Value		
8000	1	99	1	1000	2000	3000	1		
		100	"6449016000"	 	▶	3001	"6449016000"		
		101	"something"		_,▼	3001	"666666666"		
	2	99	2						
		100	"6449016001"						
		101	"something"						
		102	"else"						
	3	99	1						
		100	"666666666"						
		101	"others"						

Array with Conditions - outbound - example 4

Here is the example array with conditions: outbound configuration.

Map only profileTag 100 with typeCriteria specified against profileTag 99. No AVP 3000 in outgoing diameter message.

```
AVPs = [
   {
       AvpCodes = [
           { avpCode = 1000 }
       AVPs = [
           {
               AvpCodes = [
                  {avpCode = 2000  # <-- 1000.2000
               TypeCriteria = [
                   {
                       includeIfMatches = [ 1 ] # <-- Only profileTag(99) == 1</pre>
                       are mapped
                       encodedExtension = {
                           profileTag = 99
                                           # Array element in sub-profile
                           block
                           profileFormat = "INTEGER"
                       # This is what is included if match found:
                       AVPs = [
                               AvpCodes = [
                                   { avpCode = 3001  # <-- 1000.2000.3001
                                    repeating = true # <--
                                                                    3001 is
                           repeating
                               1
                               avpFormat = "UTF8String"
                               encodedExtension = {
                                                    # Array element in sub-
                                  profileTag = 100
                           profile block
                                  profileFormat = "STRING"
                               }
```

```
]
                      }
                  ]
               }
           ]
       }
   # Specify mapping applies OUTBOUND only.
   mappingTypes = ["InitialResponse", "UpdateResponse", "EventResponse",
   "TerminateResponse"]
   encodedExtension = {
       profileTag = 8000
       profileFormat = "ARRAY"
}
```

This table shows the mapping ACS profile blocks to AVPs in the example array with conditions configuration section in this topic. This example is for outbound.

	Profile Blo				Dia			
Profile Block (ARRAY)	Sub-Profile Block	Tag	Value		Root AVP	1 st Level AVP	2 nd Level AVP	Value
8000	1	99	1		1000	<u>20</u> 00▶	3001	"6449016000"
		100	"6449016000"			,,	3001	"666666666"
		101	"something"					
	2	99	2					
		100	"6449016001"					
		101	"something"					
		102	"else"	ر ا				
	3	99	1 /					
		100	"66666666"					
		101	"others"					

Array with Context

Introduction

A key array has a limitation in that it cannot handle the situation when the possible key values are not well known, for example, in cases when we may not have a unique key, or the key might otherwise rely on multiple items from the hierarchy. For these cases, you may use Array with Context mapping.

The key here is that DCA allows other sub-AVPs in a hierarchy to be marked as a Context AVP, using the parameter setting contextAVP = true. All AVPs marked as a Context AVP then collectively make the items which provide context.

Array with Context configuration

Here is the example Array with Context configuration in the Services AVPMappings section of the eserv.config.

```
{ # Array with Context Example
   AVPs = [ # Root-Level AVPs
        {  # 1st Entry of Root-Level AVPs
           AvpCodes = [
```

```
{
       avpCode = 7030
AVPs = [ # 1st-Level AVPs
    {  # 1st Entry of 1st-Level AVPs
       AvpCodes = [
           {
               avpCode = 1000
       AVPs = [ # 2nd-Level AVPs
            { # 1st Entry of 2nd-Level AVPs
               AvpCodes = [
                   {
                        avpCode = 2000
                        repeating = true
               AVPs = [ # 3rd-Level AVPs
                   { # Context AVP
                       AvpCodes = [
                                 avpCode = 3000 # This is AVP
                    7030.1000.2000.3000
                        contextAVP = true
                        avpFormat = "UTF8String"
                        encodedExtension = {
                           profileTag = 80301
                            profileFormat = "STRING"
                    {  # Data AVP
                        AvpCodes = [
                           {
                                avpCode = 3001  # This is AVP
                    7030.1000.2000.3001
                               repeating = true
                        ]
                        avpFormat = "UTF8String"
                        encodedExtension = {
                            profileTag = 80303
                            profileFormat = "STRING"
                    } # End of Data AVP
                ] # End of 3rd-Level AVPs
            } # End of 1st Entry of 2nd-Level AVPs
            { # 2nd Entry of 2nd-Level AVPs (Context AVP)
               AvpCodes = [
                    {
                        avpCode = 2001  # This is AVP 7030.1000.2001
                contextAVP = true
                avpFormat = "UTF8String"
               encodedExtension = {
                   profileTag = 80302
                   profileFormat = "STRING"
            } # End of 2nd Entry of 2nd-Level AVPs (Content AVP)
        ] # End of 2nd-Level AVPs
```

```
} # End of 1st Entry of 1st-Level AVPs
            ] # End 1st-Level AVPs
        } # End of 1st Entry of Root-Level AVPs
    ] # End of Root-Level AVPs
    # Specify mapping applies INBOUND only.
    mappingTypes = ["InitialRequest", "UpdateRequest", "EventRequest",
    "TerminateRequest"]
    avpFormat = "Grouped"
    encodedExtension = {
        profileTag = 8030
        profileFormat = "ARRAY"
} # End of Array with Context Example
```

Array with Context - inbound example

Here is an example of the Array with Context configuration in the Services AVPMappings section.

```
AVPs = [
   {
       AvpCodes = [
               avpCode = 1000
       AVPs = [
           {
               AvpCodes = [
                   {
                       avpCode = 2000 # <-- 1000.2000
                       repeating = true # <-- 2000 is repeating
               ]
               AVPs = [
                   {
                       AvpCodes = [
                           { avpCode = 3000 # <-- 1000.2000.3000
                       avpFormat = "UTF8String"
                       encodedExtension = {
                           profileTag = 101  # Array element in sub-profile
                           profileFormat = "STRING"
                       contextAVP = true
                   }
                       AvpCodes = [
                           { avpCode = 3001 # <-- 1000.2000.3001
                             repeating = true # <--
                                                            3001 is repeating
                       avpFormat = "UTF8String"
                       encodedExtension = {
                           profileTag = 102 # <-- Array element in sub-profile</pre>
                           profileFormat = "STRING"
                       }
```

```
}
                    1
                }
                {
                    AvpCodes = [
                        { avpCode = 2001  # <-- 1000.2001
                    avpFormat = "UTF8String"
                    encodedExtension = {
                       profileTag = 100 # <-- Array element in sub-profile block</pre>
                        profileFormat = "STRING"
                    contextAVP = true
                }
            ]
        }
   # Specify mapping applies INBOUND only.
   mappingTypes = ["InitialRequest", "UpdateRequest", "EventRequest",
   "TerminateRequest"]
   encodedExtension = {
       profileTag = 8000
       profileFormat = "ARRAY"
}
```

This table shows the mapping AVPs to ACS profile blocks in the example array with context configuration section in this topic. This example is for inbound.

Diameter Message					Profile Block			
Root AVP	1 st Level	2 nd Level	Value		Profile Block (ARRAY)	Sub-Profile Block	Tag	Value
1000	2000	3000	"ContextB"		8000	1	100	"RootContext"
		3001	"6449016000"				101	"ContextB"
		3001	"6449016001"				102	"6449016000"
	2001		"RootContext"]]		2	100	"RootContext"
	2000	3000	"ContextC"				101	"ContextB"
		3001	"123123123"			*	102	"6449016001"
						3	100	"RootContext"
							101	"ContextC"
							102	"123123123"

Array with Context - outbound example 1

Here is an example of the array with context outbound configuration in the Services AVPMappings section.

AVP 3001 is not repeating in the outbound Diameter message.

```
AVPs = [
               AvpCodes = [
                   {
                       avpCode = 2000 # <-- 1000.2000
                       repeating = true # <-- 2000 is repeating
               ]
               AVPs = [
                   {
                       AvpCodes = [
                          { avpCode = 3000 # <-- 1000.2000.3000
                       avpFormat = "UTF8String"
                       encodedExtension = {
                           profileTag = 101
                                            # Array element in sub-profile
                           block
                           profileFormat = "STRING"
                       contextAVP = true
                       AvpCodes = [
                           { avpCode = 3001  # <-- 1000.2000.3001 (not
                           repeating)
                       avpFormat = "UTF8String"
                       encodedExtension = {
                                             # <-- Array element in sub-profile
                           profileTag = 102
                           block
                           profileFormat = "STRING"
                       }
                   }
               ]
               AvpCodes = [
                   { avpCode = 2001  # <-- 1000.2001
               avpFormat = "UTF8String"
               encodedExtension = {
                   profileTag = 100  # <-- Array element in sub-profile block</pre>
                   profileFormat = "STRING"
               contextAVP = true
           }
       1
   }
# Specify mapping applies OUTBOUND only.
mappingTypes = ["InitialResponse", "UpdateResponse", "EventResponse",
"TerminateResponse"]
encodedExtension = {
   profileTag = 8000
   profileFormat = "ARRAY"
```

}

Mapping

AVP 3001 is not repeating in the outbound Diameter message.

	Profile Blo	ock			Dia	meter AVP	
Profile Block (ARRAY)	Sub-Profile Block	Tag	Value	Root AVP	1 st Level AVP	2 nd Level AVP	Value
8000	1	100	"RootContext"	1000	2000	3000	"ContextB"
		101	"ContextB"			_3001	"6449016000"
		102	"6449016000"	 	2000	3000	"ContextB"
	2	100	"RootContext"			3001	"6449016001"
		101	"ContextB"		.2000	3000	"ContextC"
		102	"6449016001"	 		3001	"123123123"
	3	100	"RootContext"		2001		"RootContext"
		101	"ContextC"	 			
		102	"123123123"				

Array with Context - outbound example 2

Adding repeating to the AVP 3001 configuration shown in *Array with Context - outbound example 1* (on page 102), produces the mapping shown in mapping example 2.

Mapping

AVP 3001 is repeating in the outbound Diameter message.

	Profile Blo	ock			Dia	meter AVP	
Profile Block (ARRAY)	Sub-Profile Block	Tag	Value	Root AVP	1 st Level AVP	2 nd Level AVP	Value
8000	1	100	"RootContext"	1000	2000	3000	"ContextB"
		101	"ContextB"			3001	"6449016000"
		102	"6449016000"	 		3001	"6449016001"
	2	100	"RootContext"		2000	3000	"ContextC"
		101	"ContextB"	 		3001	"123123123"
		102	"6449016001"		2001		"RootContext"
	3	100	"RootContext"				
		101	"ContextC"	 			
		102	"123123123"				

Conditional AVP

Introduction

Conditional AVP enables you to perform a mapping based on the value of another AVP. For example, we might want to map the Service-Parameter-Value AVP in a grouped Service-Parameter-Info AVP to a profile field, but only if its type (specified in the Service-Parameter-Type AVP) is one we are interested in. The conditional AVP includes the typeCriteria array to specify the condition to match.

For outbound mapping, conditional AVPs enable mapping to be performed based on the value:

- In a profile block, and/or
- Of another AVP in the outbound message being constructed

Conditional AVP configuration

Here is an example of the Conditional AVP configuration in the Services AVPMappings section of the eserv.config.

```
{
   AVPs = [ # Root-Level AVPs
       {  # 1st Entry of Root-Level AVPs
           AvpCodes = [
                   avpCode = 4000
            TypeCriteria = [
               {  # 1st Criterion
                   AvpCodes = [
                       {
                           avpCode = 4001
                   includeIfMatches = [ 1, 10, 101, 1001, 10001 ]
                   avpFormat = "Integer32"
                    # This is the AVP that is searched and map if a match is found
                   AVPs = [ # Conditional AVPs for 1st Criterion
                       {
                           AvpCodes = [
                               {
                                   avpCode = 4002
                           avpFormat = "UTF8String"
                           encodedExtension = {
                                profileTag = 99123
                               profileFormat = "STRING"
                   ] # End of Conditional AVPs for 1st Criterion
                } # End of 1st Criterion
                { # 2nd Criterion
                   AvpCodes = [
                       {
                           avpCode = 4001
                   includeIfMatches = [ 2, 20, 202, 2002, 20002 ]
                   avpFormat = "Integer32"
                    # This is the AVP that is searched and map if a match is found
                   AVPs = [ # Conditional AVPs for 2nd Criterion
                       {
                           AvpCodes = [
                               {
                                   avpCode = 4002
                            avpFormat = "UTF8String"
                           encodedExtension = {
                               profileTag = 99124
                               profileFormat = "STRING"
                    ] # End of Conditional AVPs for 2nd Criterion
```

```
} # End of 2nd Criterion
] # End of TypeCriteria
} # End of 1st Entry of Root-Level AVPs
] # End of Root-Level AVPs

# Specify mapping applies INBOUND only.
mappingTypes = ["InitialRequest", "UpdateRequest", "EventRequest",
"TerminateRequest"]

# Profile tag 99123 or 99124 is encoded as a child element inside an acsProfile Array.
encodedExtension = {
   profileTag = 8000
   profileFormat = "ARRAY"
}
} # End of Conditional AVP Example
```

Note: "Conditional AVPs" look similar to a non-repeating / non-ProfileArray case of "Array with Conditions". See *Array with Conditions - inbound - example 1* (on page 91).

If the avpCode being matched is not nested, you can map it without using typeCriteria, by configuring the condition outside AVPs = [...]. See Simple conditional (on page 82).

Conditional AVP - inbound example 1

Here is an example of the conditional AVP configuration in the Services AVPMappings section.

Service-Parameter-Info (440)

- Service-Parameter-Type (441)
- Service-Parameter-Value (442)

Map only matching entry, not condition.

In this example, no parent level (ARRAY-type) encoding format is specified here as encoding specified in leaf or child element of AVPs above are encoded at the root level of the ACS profile block.

```
AVPs = [
        AvpCodes = [
            {
                avpCode = 440
        TypeCriteria = [
            {  # Criteria for match value [ 1 ]
                includeIfMatches = [ 1 ]
                AvpCodes = [
                    \{ avpCode = 441 \}
                                             # <-- Inbound only: 441
                # or if specifying a fully qualified path:
                # AvpCodes = [
                # { avpCode = 440 }
                   \{ avpCode = 441 \}
                # 1
                avpFormat = "Integer32" # <-- Inbound only</pre>
                # This is what to include if match found:
                AVPs = [
                    {
                        AvpCodes = [
                             \{ avpCode = 442 \# < -- 440.442 \}
```

```
avpFormat = "UTF8String"
                           encodedExtension = {
                               profileTag = 99123 # Array element in sub-profile
                               profileFormat = "STRING"
                       }
                   ]
                  # Criteria for match value [ 2 ]
                   includeIfMatches = [ 2 ]
                   AvpCodes = [
                       \{ avpCode = 441 \}
                                                # <-- Inbound only: 441
                   avpFormat = "Integer32"
                                                # <-- Inbound only
                    # This is what to include if match found:
                   AVPs = [
                       {
                           AvpCodes = [
                               { avpCode = 442 # <-- 440.442
                           ]
                           avpFormat = "UTF8String"
                           encodedExtension = {
                               profileTag = 99124 # Array element in sub-profile
                               block
                               profileFormat = "STRING"
                       }
                  ]
              }
          ]
       }
   ]
   # Specify mapping applies INBOUND only.
   mappingTypes = ["InitialRequest", "UpdateRequest", "EventRequest",
   "TerminateRequest"]
}
```

Mapping example 1

This table shows the mapping AVPs to ACS profile blocks in the example conditional AVPs configuration section in this topic. This example is for inbound.

	Diameter A	VP	Profile Block		
Root AVP	1st Level	Value	Tag	Value	
440	441	1	99123	"Value for Type 1"	
	442	"Value for Type 1"			

			<u> </u>			
	Diameter A	VP		Profile Block		
Root AVP	1st Level	Value		Tag	Value	
440	441	2		99124	"Value for Type 2"	
	442	"Value for Type 2"				

Conditional AVP example 1

Here is an example of the conditional AVP configuration in the Services AVPMappings section.

Adding the following configuration to the AVPs to include if match is found to each criterion for match value produces the mapping shown in mapping example 2.

Map only matching entry, not condition.

"Value for Type 2"

Mapping example 2

440

This table shows the mapping AVPs to ACS profile blocks in the example conditional AVPs configuration section in this topic. This example is for inbound.

	Diameter A	VP		Profile Block		
Root AVP	1st Level	Value		Tag	Value	
440	441	1]	90001	1	
	442	"Value for Type 1"	1	99123	"Value for Type 1"	

	442	"Value for Type 1"	L	99123	"Value for Type
	Diameter A	VP	or	Pro	file Block
Root AVP		Value		Tag	Value

"Value for Type 2"

Conditional AVP example 3

441

442

Here is an example of the conditional AVP configuration in the Services AVPMappings section.

90001

99124

This is the same as *Conditional AVP - inbound example 1* (on page 106) but maps to an acsProfile ARRAY, by adding the following configuration to the end.

Map only matching entry, not condition, but map to an acsProfile ARRAY.

```
encodedExtension = {
    profileTag = 8000
    profileFormat = "ARRAY"
```

Mapping example 3

This table shows the mapping AVPs to ACS profile blocks in the example conditional AVPs configuration section in this topic. This example is for inbound.

Note similarity with the non-repeating array with conditions.

Diameter AVP				Profile Block					
Root AVP	1 st Level	Value		Profile Block (ARRAY)	Sub-Profile Block	Tag	Value		
440	441	1		80001	1	99123	"Value for Type 1"		
	442	"Value for Type 1"							

Diameter AVP			Profile Block				
Root AVP	1 st Level	Value		Profile Block (ARRAY)	Sub-Profile Block	Tag	Value
440	441	2		80001	2	99123	"Value for Type 2"
	442	"Value for Type 2"					

Conditional AVP - outbound example 1

Here is an example outbound conditional AVP configuration in the Services AVPMappings section.

No ACS profileTag conditions applicable when mapping to outbound Diameter message.

In this example, no parent level (ARRAY-type) encoding format is specified here as encoding specified in leaf or child element of AVPs above are encoded at the root level of the ACS Profile Block.

```
AVPs = [
   {
        AvpCodes = [
            {
                avpCode = 440
        TypeCriteria = [
                  # Criteria for match tag 99123
                includeIfMatches = [ ] # <-- Match any value as long as</pre>
                profileTag 99123 is present
                encodedExtension = {
                    profileTag = 99123
                                                 # <-- Outbound Only
                    profileFormat = "STRING"
                                                 # <-- Outbound Only
                # This is what to include if match found:
                AVPs = [
                    #Include type sub-AVP 1
                        AvpCodes = [
                            { avpCode = 441 # <-- 440.441
                        avpFormat = "UTF8String"
                        encodedExtension = {
                            profileTag = 99123 # Array element in sub-profile
                            block
                            profileFormat = "STRING"
                    }
                1
               # Criteria for match tag 99124
                includeIfMatches = [ ] # <-- Match any value as long as</pre>
                profileTag 99124 is present
```

```
encodedExtension = {
                   profileTag = 99124
                                              # <-- Outbound Only
                   profileFormat = "STRING" # <-- Outbound Only
                # This is what to include if match found:
               AVPs = [
                   #Include type sub-AVP 2
                   {
                       AvpCodes = [
                          { avpCode = 441 # <-- 440.441
                       ]
                       avpFormat = "Integer32"
                       literal = 2  # not mapped from a tag in the profile
                       block
                       }
                   }
                       AvpCodes = [
                           \{ avpCode = 442 \# < -- 440.442 \}
                       avpFormat = "UTF8String"
                       encodedExtension = {
                           profileTag = 99124 # Array element in sub-profile
                           block
                           profileFormat = "STRING"
                       }
                   }
              ]
          }
       ]
   }
]
# Specify mapping applies OUTBOUND only.
mappingTypes = ["InitialResponse", "UpdateResponse", "EventResponse",
"TerminateResponse"]
```

Mapping example 1 - conditional - outbound

This table shows the mapping ACS profile blocks to AVPs to in the example conditional AVPs configuration section in this topic. This example is for outbound.

Profile Block			Diameter AVP			
Tag	Value		Root AVP	1st Level	2 nd Level	
99123	"Value for Type 1"		440	441	1	
				442	"Value for Type 1"	

or

Profile Block			Diameter AVP				
Tag	Value		Root AVP	1 st Level	2 nd Level		
99124	"Value for Type 2"		440	441	2		
				442	"Value for Type 2"		

Conditional AVP - outbound example 2

Here is an example outbound conditional AVP configuration in the Services AVPMappings section.

Only the matching entries in ACS Profile Block are mapped in outbound Diameter message (Condition is "profileTag(90001) == 2")

In this example, no parent level (ARRAY-type) encoding format is specified here as encoding specified in leaf or child element of AVPs above are encoded at the root level of the ACS Profile Block.

```
AVPs = [
   {
       AvpCodes = [
            {
                avpCode = 440
        TypeCriteria = [
                # Criteria for match value [1] In this example, this is NOT the
            matching entry.
                includeIfMatches = [ 1 ]
                encodedExtension = {
                    profileTag = 90001
                                                # <-- Outbound Only
                    profileFormat = "STRING"
                                                # <-- Outbound Only
                # This is what to include if match found:
                AVPs = [
                    #Include type sub-AVP (the matching condition)
                    {
                        AvpCodes = [
                           { avpCode = 441 # <-- 440.441
                        avpFormat = "Integer32"
                        encodedExtension = {
                            profileTag = 90001 # Array element in sub-profile
                           block
                           profileFormat = "INTEGER"
                        }
                    }
                    {
                        AvpCodes = [
                            \{ avpCode = 442 \# < -- 440.442 \}
                        avpFormat = "UTF8String"
                        encodedExtension = {
                           profileTag = 99123 # Array element in sub-profile
                           block
                           profileFormat = "STRING"
                    }
                ]
            {  # Criteria for match value [2] In this example, this is the
            matching entry.
                includeIfMatches = [ 2 ]
                encodedExtension = {
                   profileTag = 90001
                                                # <-- Outbound Only
                    profileFormat = "INTEGER"
                                               # <-- Outbound Only
                 # This is what to include if match found:
                AVPs = [
```

```
#Include type sub-AVP (the matching condition)
                       AvpCodes = [
                           \{ avpCode = 441 \# < -- 440.441 \}
                        avpFormat = "Integer32"
                        encodedExtension = {
                           profileTag = 90001 # Array element in sub-profile
                           block
                           profileFormat = "INTEGER"
                    }
                       AvpCodes = [
                            { avpCode = 442 # <-- 440.442
                        avpFormat = "UTF8String"
                        encodedExtension = {
                            profileTag = 99124 # Array element in sub-profile
                           block
                           profileFormat = "STRING"
                        }
                   }
               ]
          }
       ]
   }
]
# Specify mapping applies OUTBOUND only.
mappingTypes = ["InitialResponse", "UpdateResponse", "EventResponse",
"TerminateResponse"]
```

Mapping example 2 - conditional - outbound

This table shows the mapping ACS profile blocks to AVPs to in the example conditional AVPs configuration section in this topic. This example is for outbound.

Profile Block			Diameter AVP			
Tag	Value		Root AVP	1 st Level	2 nd Level	
90001	2		440	441	2	
99124	"Value for Type 2"			442	"Value for Type 2"	

Prefix Tree

Introduction

Prefix Tree enables you to map repeating AVPs to and from a prefix tree ACS profile block, specified using profileFormat = "PREFIXTREE".

Prefix Tree configuration

Here is an example of the Prefix Tree configuration in the Services AVPMappings section of the eserv.config file.

```
{ AVPs = [ # Root-Level AVPs
```

```
AvpCodes = [
            {
               avpCode = 7100
               vendorId = "<Vendor ID>" # Optional. Vendor specific AVP, if
               present.
       AVPs = [ # 1st-Level AVPs
               AvpCodes = [
                    {
                       avpCode = 1000
                       [ # 2nd-Level AVPs
                AVPs =
                       AvpCodes = [
                                avpCode = 2000
                                repeating = true
                        1
                        avpFormat = "UTF8String"
                ] # End of 2nd-Level AVPs
        ] # End of 1st-Level AVPs
] # End of Root-Level AVPs
avpFormat = "Grouped"
encodedExtension = {
   profileTag = 8100
   profileFormat = "PREFIXTREE"
# Specify mapping applies INBOUND only.
mappingTypes = ["InitialRequest", "UpdateRequest", "EventRequest",
"TerminateRequest"]
# AVPs above are encoded into a PREFIXTREE-type in an ACS Profile Block.
encodedExtension = {
   profileTag = 7000
   profileFormat = "PREFIXTREE"
} # End of Prefix Tree example
```

Prefix Tree example

Here is an example of the prefix tree configuration in the Services AVPMappings section.

Note that the parent tag is specified outside of the AVPs array block. Parent tag 7000 has type "PREFIXTREE", hence profileTag and profileFormat for child elements are not applicable as this child AVP is encoded as entries within a prefix tree.

```
{
    AvpCodes = [
       avpCode = 1000
    AVPs = [
       {
           AvpCodes = [
```

```
{
               avpCode = 2000
                                          # <-- 1000.2000
               repeating = true
                                          # <-- 2000 is repeating
        ]
        avpFormat = "UTF8String"
    }
1
# Specify mapping applies INBOUND only.
mappingTypes = ["InitialRequest", "UpdateRequest", "EventRequest",
"TerminateRequest"]
encodedExtension = {
   profileTag = 7000
   profileFormat = "PREFIXTREE"
}
```

To specify outbound, the mappingTypes are specified as:

```
# Specify mapping applies OUTBOUND only.
mappingTypes = ["InitialResponse", "UpdateResponse", "EventResponse",
"TerminateResponse"]
```

Mapping

This table shows the mapping AVPs to ACS profile blocks in the example prefix tree configuration section in this topic. This example is for inbound. For outbound, the mapping direction is reversed.

	Diameter A	VP	Profile Block		
Root AVP	1 st Level	Value	Profile Block (Prefix Tree)	Value	
1000	2000	"049772"	7000	"049772"	
	2000	"644901"		"644901"	
	2000	"0800500"		"0800500"	

Timestamp

Introduction

The DCA interface on the SLC is able to record the time that the:

- Credit-Control-Request (CCR) was received (Time-In)
- Credit-Control-Answer (CCA) was ready to be assembled and sent (Time-Out)

This allows you to track processing time and, for example, identify bottle-necks.

You can map:

- The time a CCR was received into a configurable AVP in the CCA message
- The time a Credit-Control processing for a request was completed, into a configurable AVP in the CCA message

You can copy the timestamp from the incoming Diameter message to the outgoing Diameter message.

Timestamp example 1

This example copies a timestamp (the 3GPP eventtimestamp) from the incoming Diameter message to the outgoing Diameter message.

The data is copied through the profile tag 6291458; this is special cased to be copied from the incoming profile block to the outgoing one. It is an ARRAY tag, so that you can put whatever data you like in it.

```
mappingTypes = ["InitialRequest", "InitialResponse", "UpdateRequest",
    "UpdateResponse"]
    avpFormat = "Grouped"
    extensionFormat = "encoded"
    encodedExtension = {
       profileTag = 6291458
       profileFormat = "ARRAY"
    AVPs = [
       {
            AvpCodes = [
                {
                    avpCode = 833
                    vendorId = 10415
                    avpCode = 6
                    vendorId = 16247
                   repeating = True
            ]
            avpFormat = "Integer32"
            extensionFormat = "encoded"
            encodedExtension = {
               profileTag = 8192004
                profileFormat = "INTEGER"
       }
    ]
}
```

Timestamp example 2

This example places a received timestamp in the outgoing message. This uses the same repeating AVP as the previous example, so it gets appended to the group.

```
mappingTypes = [ "InitialResponse", "UpdateResponse" ]
# Any Integer/Unsigned 32/64 or OctetString may be used.
avpFormat = "Integer32"
timestamp = "TIME REQUEST RECEIVED32"
AvpCodes = [
    {
        avpCode = 833
        vendorId = 10415
    }
    {
        avpCode = 6
        vendorId = 16247
        repeating = True
    }
]
```

Note: See the timestamp (on page 72) parameter description for a list of values.

Timestamp example 3

This example places a replying timestamp in the outgoing message.

```
mappingTypes = [ "InitialResponse", "UpdateResponse" ]
```

Chapter 4

```
avpFormat = "Integer64"
timestamp = "TIME_NOW64"
AvpCodes = [
          avpCode = 833
          vendorId = 10415
          avpCode = 7
          vendorId = 16247
          repeating = True
]
```

Control Plans

Overview

Introduction

This chapter explains the example Control Plans that are shipped with Oracle Communications Network Charging and Control (NCC) Diameter Control Agent.

These are sufficient to run simple Diameter services. There are:

- for event based services:
 - CHECK BALANCE
 - DIRECT_DEBITING
 - PRICE_ENQUIRY
 - REFUND ACCOUNT
- for session based services:
 - Without redirect
 - With redirect to top-up-server functionality
 - Screening

In this chapter

This chapter contains the following topics.	
Check Balance	117
Direct Debiting	118
Price Enquiry	119
Refund Account	120
Session No Redirect	121
Session Redirect	122
Screening	124

Check Balance

Introduction

The Check Balance control plan determines if the user is able to reserve a specified number of units. It returns either a success or failure only; it does not return the number of units in the balance.


This control plan consists of a start node followed by two Named Event nodes and a terminate unchanged node, with Disconnect nodes as appropriate. The first Named Event node reserves an event type (the Reserve Event option selected), appropriate for this service. If the first Named Event node:

Fails to reserve the event, it goes to a Disconnect node with the reason set to the configured no funds cause.

Successfully reserves the event, the second Named Event node cancels the reservation (the Revoke Event option selected). Then, a Terminate Unchanged node sends an INAP Continue, which signals to diameterControlAgent that the balance check succeeded.

Check Balance control plan

Here is an example Check Balance control plan.



Direct Debiting

Introduction

This control plan starts with two profile branching nodes to determine if this is a time-based direct debit (through INAP extension 502) with an Event-Timestamp AVP (INAP extension 504).


- If it is, a DUCR node is used with the Debit option selected to debit the account.
- If it is not, a Named Event node is used with the <code>Direct Event</code> option selected to debit the account. The Named Event node reads its number of events from INAP extension 501 (Requested-Service-Units).

Failure branches are connected to Disconnect nodes with appropriate cause values to produce the correct Diameter Result-Code values.

Refer to INAP Extensions (on page 12) for details.

Direct Debiting control plan

Here is an example Direct Debiting control plan.



Price Enquiry

Introduction

This control plan has a Named Event node connected to:


- Disconnect nodes (for failures)
- An unconditional terminate node (for successes)

The Named Event node has the <code>Cost of event</code> option selected and is configured to store the cost of the event under a tag in the ACS temporary storage area. Then, the DCA service loader plug-in picks up this tag and puts it in INAP extension 603 in the Connect. The diameterControlAgent copies this into the Cost-information AVP.

Refer to INAP Extensions (on page 12) for details.

Price Enquiry control plan

Here is an example Price Enquiry control plan.




Refund Account

Introduction

The Refund Account control plan is identical to the *Direct Debiting* (on page 118) control plan, except, in the DUCR node, the **Credit** option is selected.

Refund Account control plan

Here is an example Refund Account control plan.



Session No Redirect


Introduction

The Session No Redirect control plan is a session based plan with no redirect to a top-up server.

This consists of a Start node connected to a UATB node. The exits of the UATB node are connected to an End node (Success cases) and to the Disconnect nodes with various release causes. The release causes in the Disconnect nodes are such as to cause diameterControlAgent to use the appropriate Result-Code.

Session No Redirect control plan

Here is an example Session No Redirect control plan.



eserv.config configuration

As shown in the notes with this control plan, you need to ensure that the following values are set in the CCS.ccsMacroNodes section of the eserv.config file.

```
CCS = {
    ccsMacroNodes = {
        UseDisconnectLeg = false
    }
}
```

Refer to the CCS Technical Guide for details.

Session Redirect

Introduction


This is the same as the control plan for *Session No Redirect* (on page 121), except the following exits of the UATB node are connected to an unconditional termination node which will contain a number mapped to the address of the top-up-server:

Declined No Funds

NSF (Disconnected)

Session Redirect control plan

Here is an example Session Redirect control plan.



eserv.config configuration

As shown in the notes with this control plan, you need to ensure that the following values are set in the CCS.ccsMacroNodes section of the eserv.config file.

```
CCS = {
    ccsMacroNodes = {
        UseDisconnectLeg = true
}
```

The switch configuration must also be set in the acsCharging.switchConfiguration section.

```
acsCharging = {
    switchConfiguration = [
        switchType = "internal"
        addDisconnectOrRelease = true
```

Refer to CCS Technical Guide for details.

Screening


Introduction

The Screening control plan denies service for voice but allows service for data, based on the bearer type received from DCA.

This consists of a Start node connected to a Transmission Type Branch node. The Transmission Type Branch node exits for voice (Exits 1 and 4) are connected to a Disconnect node with a release cause of 50. The exits for non-voice are connected to a Terminate Uncharged node.

Screening control plan

Here is an example Screening control plan.



eserv.config configuration

As shown in the notes with this control plan, for this example, you need to ensure that the following values are set in the DIAMETER Services section of the eserv.config file.

```
AvpMappings = [
```

```
AvpCodes = [
              {
                   avpCode = 268 # result_code
vendorId = 0
         mappingTypes = [
              "InitialResponse"
         inapField = [ "cause" ]
         avpFormat = "Unsigned32"
         conversion = [
              { internal = 50, external = 5003 } #Return
DIAMETER_AUTHORIZATION_REJECTED if screening failed
    }
]
```

About Installation and Removal

Overview

Introduction

This chapter provides information about the installed components for the Oracle Communications Network Charging and Control (NCC) application described in this guide. It also lists the files installed by the application that you can check for, to ensure that the application installed successfully.

In this Chapter

This chapter contains the following topics.	
Installation and Removal Overview	127
Checking the Installation	127

Installation and Removal Overview

Introduction

For information about the following requirements and tasks, see Installation Guide:

- NCC system requirements
- Pre-installation tasks
- Installing and removing NCC packages

DCA packages

An installation of Diameter Control Agent includes the following packages, on the:

- SMS:
 - dcaSms
- SLC:
 - dcaScp

Checking the Installation

Introduction

Refer to these check lists to ensure the Diameter Control Agent has been installed correctly.

DCA Scp directories and files

The DCA installation on the SLC creates the following directories:

- /IN/service_packages/DCA/bin
- /IN/service_packages/DCA/etc

- /IN/service_packages/DCA/lib
- /IN/service_packages/DCA/tmp

The DCA installation installs the following binaries and interfaces:

/IN/services_packages/DCA/bin/diameterControlAgent

The DCA installation installs the following example configuration file:

/IN/services_packages/eserv.config.dca.example

The DCA installation installs the following shared library:

/IN/services_packages/DCA/lib/libdcaCcsSvcExtra.so

DCA Sms directories

Check that the statistics and control plans have been installed correctly.

The DCA installation on the SMS creates the following directories:

- /IN/service_packages/DCA/db
- /IN/service_packages/DCA/lib

Diameter Charging Agent Call Flows

Call Flow Overview

Introduction

This chapter lists a sample set of DCA message flows.


In this chapter

Initial Request Success

Introduction

This example shows the flow for a successful initial request.

Call flow



Comments

This table provides additional comments on the call flow.

Operation	Comment
2	This operation contains a profile block encoded in extension 701, consisting of data mapped from AVPs.


Operation	Comment
	This operation contains a profile block encoded in extension 701, consisting of data mapped to AVPs.

Initial Request Release Call

Introduction

This example shows the flow for a release call.

Call flow



Comments

This table provides additional comments on the call flow.


Operation	Comment
2	This operation contains a profile block encoded in extension 701, consisting of data mapped from AVPs.
3	This operation contains a profile block encoded in extension 701, consisting of data mapped to AVPs.

Initial Request Multiple Requested Service Units

Introduction

This example shows the flow when multiple requests for service units (cash or time) are made.

Call flow



AVP Pass-Through DCA to DCD

Introduction

This example shows the flow when a simple pass through from DCA to DCD is made.

DCA Parameters

A large part of configuration for DCA are AVP to profile block definitions.

The following configuration is required to allow an AVP received by DCA from a CC-Client to be passed through to DCD.

 ACS is configured with an Inbound ARRAY-type profile tag, which is used to pass a repeating AVP to ACS.

Note: This may not be necessary if data is not going to be manipulated in a Control Plan, however this would risk having data corrupted if the chosen tag number already exists, and is used in the Control Plan.

- DCA is configured with an inbound mapping from a repeating AVP in a single grouped AVP to an ARRAY-type profile.
- DCD is configured with an outbound mapping from an ARRAY profile tag in the INCOMING_EXTENSIONS profile block.

The following configuration is required to allow an AVP received from a CC-Server by DCD to be passed through to DCA.


 ACS is configured with an Outbound ARRAY-type profile tag, which is used to pass data from ACS to DCA in the OUTGOING EXTENSIONS profile block.

Note: This may not be necessary if data is not going to be manipulated in a Control Plan, however this would risk having data corrupted if the chosen tag number already exists, and is used in the control Plan.

- DCD is configured with an inbound mapping to map a repeating AVP in a single grouped AVP to an ARRAY profile in the OUTGOING_EXTENSIONS profile block.
- DCA is configured with an outbound mapping to map an ARRAY profile tag to an AVP.

Call flow

This diagram shows the flow.




Comments

This table provides additional comments on the call flow.

Operation	Comment
1	CC-Client sends a CCR INITIAL_REQUEST to DCA.
2	DCA sends an InitialDP to ACS containing an ARRAY profile tag in the profile block encoded in the generic_extension_val_extended_os extension (id: 701), in the extensions argument.
3	Upon receipt of the operation, ACS copies the profile tags specified in the generic_extension_val_extended_os into the INCOMING_EXTENSIONS profile block. • The INCOMING_EXTENSIONS profile block is stored in tsMap->incomingExtensionsBlock in acsChassisContext. • In the case of an IDP, the whole generic_extension_val_extended_os extension buffer is re-assigned to tsMap->incomingExtensionsBlock; for an ACR, each profile tag in the extension is individually applied to tsMap->incomingExtensionsBlock.
4	A billing node in the invoked Control Plan results in the DCD actions library being invoked.
5	The DCD actions library:
6	The diameterBeClient sends the CCR request to the CC-Server.
7	CC-Server send a CCA INITIAL_REQUEST.
8	The diameterBeClient sends the response encoded in a DiameterSleeEvent back to ACS


Screening Successful

Call flow




Screening Call Disallowed

Call flow



Screening Failure

Call flow




Comments

The call flow shows DIAMETER_RATING_FAILED being returned. This is the default, however the actual returned Result-Code is configurable.

Update Request

Call flow




Comments

This table provides additional comments on the call flow.

Operation	Comment
2	This operation contains a profile block encoded in extension 701, consisting of data mapped from AVPs.
3	This operation contains a profile block encoded in extension 701, consisting of data mapped to AVPs.

Terminate Request

Call flow



Comments

This table provides additional comments on the call flow.

Operation	Comment
2	This operation contains a profile block encoded in extension 701, consisting of data mapped from AVPs.
3	This operation contains a profile block encoded in extension 701, consisting of data mapped to AVPs.

Glossary of Terms

AAA

Authentication, Authorization, and Accounting. Specified in Diameter RFC 3588.

ACS

Advanced Control Services configuration platform.

AVP

Attribute Value Pair, used in Diameter to represent properties of a particular request or answer.

Call Flow

The path that a caller into the system takes to perform various functions. Often represented diagrammatically as a flowchart or tree-like structure. This shows prompts that the user will hear, with decision points or menus represented by call states.

CAMEL

Customized Applications for Mobile network Enhanced Logic

This is a 3GPP (Third Generation Partnership Project) initiative to extend traditional IN services found in fixed networks into mobile networks. The architecture is similar to that of traditional IN, in that the control functions and switching functions are remote. Unlike the fixed IN environment, in mobile networks the subscriber may roam into another PLMN (Public Land Mobile Network), consequently the controlling function must interact with a switching function in a foreign network. CAMEL specifies the agreed information flows that may be passed between these networks.

CAP

CAMEL Application Part

CC

Country Code. Prefix identifying the country for a numeric international address.

CCA

Credit-Control-Answer, used in Diameter by the credit-control server to acknowledge a Credit-Control-Request (CCR) from the credit-control client.

CCR

Credit-Control-Request, used in Diameter by the credit-control client to request credit authorization from the credit-control server.

CCS

- 1) Charging Control Services component.
- 2) Common Channel Signalling. A signalling system used in telephone networks that separates signalling information from user data.

Diameter

A feature rich AAA protocol. Utilises SCTP and TCP transports.

DP

Detection Point

DTMF

Dual Tone Multi-Frequency - system used by touch tone telephones where one high and one low frequency, or tone, is assigned to each touch tone button on the phone.

FDA

First Delivery Attempt - the delivery of a short message directly to the SME rather than relaying it through the MC.

GPRS

General Packet Radio Service - employed to connect mobile cellular users to PDN (Public Data Network- for example the Internet).

GSM

Global System for Mobile communication.

It is a second generation cellular telecommunication system. Unlike first generation systems, GSM is digital and thus introduced greater enhancements such as security, capacity, quality and the ability to support integrated services.

HLR

The Home Location Register is a database within the HPLMN (Home Public Land Mobile Network). It provides routing information for MT calls and SMS. It is also responsible for the maintenance of user subscription information. This is distributed to the relevant VLR, or SGSN (Serving GPRS Support Node) through the attach process and mobility management procedures such as Location Area and Routing Area updates.

HPLMN

Home PLMN

IDP

INAP message: Initial DP (Initial Detection Point)

IMS

IP Multimedia Subsystem (3GPP) enables the use of multimedia services based on and built upon Internet applications, services and protocols. These protocols include SIP, which is used to manage the IP multimedia sessions.

IMSI

International Mobile Subscriber Identifier. A unique identifier allocated to each mobile subscriber in a GSM and UMTS network. It consists of a MCC (Mobile Country Code), a MNC (Mobile Network Code) and a MSIN (Mobile Station Identification Number).

The IMSI is returned by the HLR query (SRI-SM) when doing FDA. This tells the MSC exactly who the subscriber is that the message is to be sent to.

IN

Intelligent Network

INAP

Intelligent Network Application Part - a protocol offering real time communication between IN elements.

Initial DP

Initial Detection Point - INAP Operation. This is the operation that is sent when the switch reaches a trigger detection point.

IΡ

- 1) Internet Protocol
- 2) Intelligent Peripheral This is a node in an Intelligent Network containing a Specialized Resource Function (SRF).

IP address

Internet Protocol Address - network address of a card on a computer.

ISDN

Integrated Services Digital Network - set of protocols for connecting ISDN stations.

ITU

International Telecommunication Union

LAC

Location Area Code. This is an integer value specified as the third level of detail in the location area information. One LAC contains multiple Cell IDs or SAIs.

MC

Message Centre. Also known as SMSC.

MCC

Mobile Country Code. In the location information context, this is padded to three digits with leading zeros. Refer to ITU E.212 ("Land Mobile Numbering Plan") documentation for a list of codes.

MNC

Mobile Network Code. The part of an international address following the mobile country code (MCC), or at the start of a national format address. This specifies the mobile network code, that is, the operator owning the address. In the location information context, this is padded to two digits with a leading zero. Refer to ITU E.212 ("Land Mobile Numbering Plan") documentation for a list of codes.

MS

Mobile Station

MSC

Mobile Switching Centre. Also known as a switch.

MSIN

Mobile Station Identification Number.

MSISDN

Mobile Station ISDN number. Uniquely defines the mobile station as an ISDN terminal. It consists of three parts; the country code (CC), the national destination code (NDC) and the subscriber number (SN).

MT

Mobile Terminated

NOA

Nature Of Address - a classification to determine in what realm (Local, National or International) a given phone number resides, for the purposes of routing and billing.

PLMN

Public Land Mobile Network

RAA

Session message: Re-Auth Answer

RADIUS

Remote Authentication Dial-In User Service - a system of distributed security that secures remote access to networks and network services against unauthorised access.

RAR

Session message: Re-Auth Request

SCF

Service Control Function - this is the application of service logic to control functional entities in providing Intelligent Network services.

SCTP

Stream Control Transmission Protocol. A transport-layer protocol analogous to the TCP or User Datagram Protocol (UDP). SCTP provides some similar services as TCP (reliable, in-sequence transport of messages with congestion control) but adds high availability.

Session

Diameter exchange relating to a particular user or subscriber access to a provided service (for example, a telephone call).

SGSN

Serving GPRS Support Node

SIP

Session Initiation Protocol - a signaling protocol for Internet conferencing, telephony, event notification and instant messaging. (IETF)

SLC

Service Logic Controller (formerly UAS).

SLEE

Service Logic Execution Environment

SME

Short Message Entity - This is an entity which may send or receive short messages. It may be located in a fixed network, a mobile, or an SMSC.

SMS

Depending on context, can be:

- Service Management System hardware platform
- Short Message Service
- Service Management System platform
- NCC Service Management System application

SN

Service Number

SRF

Specialized Resource Function – This is a node on an IN which can connect to both the SSP and the SLC and delivers additional special resources into the call, mostly related to voice data, for example play voice announcements or collect DTMF tones from the user. Can be present on an SSP or an Intelligent Peripheral (IP).

SRI

Send Routing Information - This process is used on a GSM network to interrogate the HLR for subscriber routing information.

SSP

Service Switching Point

TCP

Transmission Control Protocol. This is a reliable octet streaming protocol used by the majority of applications on the Internet. It provides a connection-oriented, full-duplex, point to point service between hosts.

URI

Uniform Resource Identifier.

URL

Uniform Resource Locator. A standard way of specifying the location of an object, typically a web page, on the Internet.

VLR

Visitor Location Register - contains all subscriber data required for call handling and mobility management for mobile subscribers currently located in the area controlled by the VLR.

VWS

Oracle Voucher and Wallet Server (formerly UBE).

Index	CAMEL • 137 CAP • 137
۸	CC • 137
Α	CCA • 16, 137
AAA • 137	ccDuplicateStoreSize • 36 CCR • 14, 137
About Installation and Removal • 127	CCS • 137
About This Document • v	CCS Service Library configuration • 5, 7, 9
Acct-Application-Id • 48 ACS • 137	chargeOnSessionTimeout • 49
acs.conf Configuration • 6, 9, 14	Check Balance • 117
allowDefaultRatingGroup • 36	Check Balance control plan • 118
allowMultiServiceIdentifier • 49	Check balance, with a result of enough credit •
Array with Conditions • 73, 81, 89	17, 20 Chapting the Installation : 127
Array with Conditions - inbound - example 1 •	Checking the Installation • 127
91, 106	Comments • 129, 130, 133, 134, 135 commitGrantedOnSessionTimeout • 50
Array with Conditions - Inbound - example 2 •	commitGrantedOnTerminate • 50
92	Conditional AVP • 73, 81, 104
Array with Conditions - outbound - example 1 • 94	Conditional AVP - inbound example 1 • 106,
Array with Conditions - outbound - example 2 •	108
95	Conditional AVP - outbound example 1 • 109
Array with Conditions - outbound - example 3 •	Conditional AVP - outbound example 2 • 110
96	Conditional AVP configuration • 105
Array with Conditions - outbound - example 4 •	Conditional AVP example 1 • 107
98	Conditional AVP example 3 • 108 Configuration • 5
Array with Conditions configuration • 89	Configuration Components • 5
Array with Context • 66, 81, 99	Configuration File Format • 6
Array with Context - inbound example • 101	Configuration Overview • 5
Array with Context - outbound example 1 • 102, 104	Connection • 14
Array with Context - outbound example 2 • 104	connectionTimeout • 50
Array with Context configuration • 99	contextAVP • 66
Audience • v	Control Plans • 9, 12, 117
Auth-Application-Id • 49	conversion • 30 conversionFactor • 61
AVP • 137	Copyright • ii
AVP Casting • 28	counterLogInterval • 51
AVP Format to Extension Type • 28 AVP Pass-Through DCA to DCD • 132	customDefaultUnits • 36
avpCode • 29	
AvpCodes • 29, 59	D
avpFormat • 30	DCA Components • 3
avpMappings • 25, 60	DCA packages • 127
AvpMappings Parameters • 25, 28, 66	DCA Parameters • 132
avpType • 60	DCA Scp directories and files • 127
avpValue • 60	DCA SLEE Configuration • 7
В	DCA Sms directories • 128 DCA statistics • 78
Background Processes • 23	DCADefaults Configuration Section • 24
Base example • 81	DCADefaults Parameters • 25
Basic Array • 81, 83	DCAInstances Configuration Section • 34
Basic Array configuration • 84	DCAInstances configuration structure • 34 DCAInstances Parameters • 8, 34, 35
Business Scenarios • 18	destAddress • 46
C	destination • 45
Call flow • 129, 130, 131, 132, 133, 134, 135	destinationAddressAvp • 47
Call Flow • 137	Diagram • 3 Diameter • 138
Call Flow Overview • 129	Diameter - 190

diameterControlAgent Process • 7, 23 DiameterServer Parameters • 34, 48, 76 Direct Debiting • 118, 120 Direct Debiting • 138 DIMF • 138 N • 139 NAP Extension • 9	Diameter Charging Agent Call Flows • 129 DIAMETER Configuration Structure • 23	H
DiameterServer Parameters • 34, 48, 76 Direct Debiting • 118, 120 Direct Debiting • 118, 120 Document Conventions • vi dontDiscardRatingGroupInResponse • 37 DP • 138 DTMF • 139	Diameter eserv.config Configuration • 7	HLR • 138
Direct Debiting • 118, 120 Direct Debiting control plan • 119 Document Conventions • vi dontDiscardRatingGroupInResponse • 37 DP • 138 DTMF • 139 IMSI • 138 IN • 139 IMSI • 138 IN • 139 IMSI		HPLMIN • 138
Direct Debiting • 118, 120 Direct Debiting ontrol plan • 119 Document Conventions • vi dontDiscardRatingGroupInResponse • 37 DP • 138 DTMF • 13		I
Document Conventions • vi dontDiscardRatingGroupInResponse • 37 DP • 138 DTMF • 138 IMSI		
dontDiscardRatingGroupInResponse • 37 DP • 138 DTMF • 138 DTMF • 138 dummyDestination • 37 duplicateBytes • 51 duplicateBytes • 51 duplicateTime • 51 E Editing the File • 7 enabled • 47 Enabling Named Events • 10 encodedExtension • 31, 67 esserv.config Configuration • 122, 123, 124 eserv.config Configuration • 122, 123, 124 eserv.config Files Delivered • 7 Example Basic Array configuration • 85 Example DCADefaults Configuration in eserv.config File • 24 Example Example Resider Fire • 24 Example NumberRules configuration • 43 Example RedirectNumberMappings configuration • 48 Example PeerSchemes section • 76 Example RedirectNumberMappings configuration • 46 excludeIfMatches • 67 extensionType • 31 external • 31 F F K K Key Array • 68, 81, 86 Key Array • 68, 81, 86 Key Array • 68 L L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginRealm • 54 localOriginHost • 64 localOriginRealm • 54 localOriginRealm • 54 localOriginHost • 64 localOriginRealm • 54 localOriginHost • 64 localOriginRealm • 54 localOriginHost • 64 localOriginRealm • 54 loc		
DP + 138 DTMF + 138 dummybestination • 37 duplicateBytes • 51 duplicateTime • 51 E Editing the File • 7 enabled • 47 Enabling Named Events • 10 encodedExtension • 31, 67 eserv.config Configuration • 122, 123, 124 eserv.config Configuration • 125 example Basic Array configuration • 85 Example DCADefaults Configuration • 87 Example DCADefaults Configuration • 87 Example Rey Array configuration • 48 Example Rey Array configuration • 48 Example RedirectNumberMappings configuration • 45 Example RedirectNumberMappings configuration • 45 Example RedirectNumberMappings configuration • 46 excludeIfMatches • 67 extensionFormat • 31, 67 extensionFormat • 31 F F Editing the File • 7 enabled • 47 inapServiceKey • 26, 61 inauField • 67 inapServiceKey • 26, 61 inapServiceKey • 26, 61 inapServiceKey • 26, 61 inapServiceKey • 26, 61 inauField • 67 inapServiceKey • 26, 61 inauField • 67 inapServiceKey • 26, 61 inapSer		
DTMF*138 dummyDestination • 37 duplicateDytes • 51 duplicateTime • 51 Editing the File • 7 enabled • 47 Enabling Named Events • 10 encodedExtension • 31, 67 eserv.config Configuration • 122, 123, 124 eserv.config Configuration • 122, 123, 124 eserv.config Files Delivered • 7 Example Basic Array configuration • 85 Example DiameterServer Configuration • 85 Example DiameterServer Configuration • 87 Example Basic Array configuration • 87 Example BedirectNumberMappings configuration • 43 Example PeerSchemes section • 76 Example RedirectNumberMappings configuration • 45 Example RedirectNumberMappings configuration • 45 example RedirectNumberMappings configuration • 46 excludeIfMatches • 67 extensionType • 31 external • 31 F F F Key Array • 68, 81, 86 Key Array • 68 L AC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 mandatory	dontDiscardRatingGroupInResponse • 37	
dumyDestination • 37 duplicateBytes • 51 duplicateBytes • 51 duplicateTime • 51 E Editing the File • 7 enabled • 47 Enabling Named Events • 10 encodedExtension • 31, 67 eserv.config configuration • 122, 123, 124 eserv.config Configuration • 122, 123, 124 eserv.config Files Delivered • 7 Example DoADefaults Configuration • 85 Example DoADefaults Configuration • 87 Example DoADefaults Configuration • 48 Example Rey Array configuration • 87 Example DiameterServer Configuration • 48 Example Rey Array configuration • 48 Example Rey Array configuration • 47 Example DiameterServer Configuration • 48 Example Rey Array configuration • 48 Example RedirectNumberMappings configuration • 45 Example report • 79 Example Tracing configuration • 46 excludelfMatches • 67 extensionType • 31 external • 31 F F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 G M ggsnSupportsFinalUnitIndication • 37 GPRS • 138 ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61		
duplicateBytes • 51 duplicateTime • 51 E Editing the File • 7 enabled • 47 Enabling Named Events • 10 encodedExtension • 31, 67 eserv.config Configuration • 122, 123, 124 eserv.config Configuration • 5, 6 eserv.config Files Delivered • 7 Example Basic Array configuration • 85 Example DCADefaults Configuration • 85 Example DCADefaults Configuration • 87 Example NumberRules configuration • 48 Example NumberRules configuration • 43 Example PeerSchemes section • 76 Example PeerSchemes section • 76 Example Peoprt • 79 Example Tracing configuration • 46 excludelfMatches • 67 extensionType • 31 external • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G M ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61		
duplicateTime • 51 E Editing the File • 7 enabled • 47 Enabling Named Events • 10 encodedExtension • 31, 67 eserv.config Configuration • 122, 123, 124 eserv.config Configuration • 22, 123, 124 eserv.config Files Delivered • 7 Example Basic Array configuration • 85 Example DCADefaults Configuration • 85 Example DCADefaults Configuration • 87 Example DiameterServer Configuration • 87 Example DiameterServer Configuration • 87 Example PeerSchemes section • 76 Example RedirectNumberMappings configuration • 48 Example RedirectNumberMappings configuration • 45 Example RedirectNumberMappings configuration • 46 excludelfMatches • 67 extensionFormat • 31, 67 extensionFormat • 31, 67 extensionFormat • 31, 67 External • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G M ggsnSupportsFinalUnitIndication • 37 GPRS • 138 ggracefulTerminationValidityTime • 25, 61 INAP Extensions • 12, 118, 120 inapField • 67 inapServiceKey • 26, 61 inBufferSize • 51 includelfMatches • 68 Initial DP • 139 Initial Request Multiple Requested Service Units • 130 Initial Request Success • 129 Initial Request Multiple Requested Service Units • 130 Initial Request Success • 129 Initial Request Success • 129 Initial Request Success • 129 Initial Request Multiple Requested Service Units • 130 Initial Request Multiple Requested Service Units • 130 Initial Request Multiple Requested Service Units • 130 Initial Request Release Call • 130 Initial Request Release Call • 130 Initial Request Success • 129 Initial Request Multiple Requested Service Units • 130 Initial Request Multiple Requested Service Uni	•	
Editing the File • 7 enabled • 47 Enabling Named Events • 10 encoded Extension • 31, 67 eserv.config Configuration • 122, 123, 124 eserv.config Configuration • 122, 123, 124 eserv.config Files Delivered • 7 Example Basic Array configuration • 85 Example DoADefaults Configuration • 85 Example DiameterServer Configuration • 85 Example DiameterServer Configuration • 87 Example nested format • 82 Example NumberRules configuration • 43 Example RedirectNumberMappings configuration • 45 Example report • 79 Example racing configuration • 46 excludelfMatches • 67 extensionFormat • 31, 67 extensionFormat • 31, 67 extensionFype • 31 external • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G inapField • 67 inapServiceKey • 26, 61 inBufferSize • 51 includelfMatches • 68 Initial Pequest Multiple Requested Service Units • 130 Initial Request Multiple Requested Service Units • 130 Initial Request Release Call • 130 Initial Request Success • 129 Installation and Removal Overview • 127 instanceName • 38 internal • 31 Introduction • 1, 5, 6, 7, 9, 12, 14, 18, 34, 58, 78, 81, 83, 86, 89, 99, 104, 112, 114, 117, 118, 119, 120, 121, 122, 124, 127, 129, 131 132 invalidMessageSequenceResultCode • 26, 38 IP • 139 IP address • 139 itc • 26, 62 ITU • 139 K Key Array • 68, 81, 86 Key Array • 68 L L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61		
Editing the File • 7 enabled • 47 Enabling Named Events • 10 encodedExtension • 31, 67 eserv.config Configuration • 122, 123, 124 eserv.config Files Delivered • 7 Example Basic Array configuration in eserv.config File • 24 Example DCADefaults Configuration • 85 Example DCADefaults Configuration • 85 Example DiameterServer Configuration • 87 Example Mey Array configuration • 87 Example Rey Array configuration • 87 Example Rey Array configuration • 87 Example ReperSchemes section • 76 Example RedirectNumberMappings configuration • 45 Example Peort • 79 Example Tracing configuration • 46 excludelfMatches • 67 extensionType • 31 external • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G inapServiceKey • 26, 61 inBufferSize • 51 includelfMatches • 68 Initial Request Multiple Requested Service Units • 130 Initial Request Node Service Units • 130 Initial Request Node Service Units • 130 Initial Request Node Service Units • 130 Initial Request Release Call • 130 Initial Request Node Service Units • 130 Initial Request Node Sell-130 Initial Request Node Sell-13	duplicateTime • 51	
Editing the File • 7 enabled • 47 Enabling Named Events • 10 encoded Extension • 31, 67 eserv.config Configuration • 122, 123, 124 eserv.config Configuration • 122, 123, 124 eserv.config Files Delivered • 7 Example Basic Array configuration • 85 Example DoADefaults Configuration • 85 Example DiameterServer Configuration • 87 Example nested format • 82 Example NumberRules configuration • 43 Example PeerSchemes section • 76 Example RedirectNumberMappings configuration • 45 Example report • 79 Example Tracing configuration • 46 excludelfMatches • 67 extensionFormat • 31, 67 extensionFormat • 31, 67 extensionType • 31 external • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61	E	·
includelfMatches • 68 Initial DP • 139 Initial Request Multiple Requested Service Units • 130 Initial Request Multiple Requested Service Units • 130 Initial Request Release Call • 130 Initial Request Success • 129 Initial Request Release Call • 130 Initial Request Success • 129 Installation and Removal Overview • 127 InstanceName • 38 Internal • 31 Introduction • 1, 5, 6, 7, 9, 12, 14, 18, 34, 58, 78, 81, 83, 86, 89, 99, 104, 112, 114, 117, 118, 119, 120, 121, 122, 124, 127, 129, 130 Initial Request Release Call • 130 Initial Request R	L	·
enabled • 47 Enabling Named Events • 10 encodedExtension • 31, 67 eserv.config configuration • 122, 123, 124 eserv.config Files Delivered • 7 Example Basic Array configuration • 85 Example DiameterServer Configuration • 48 Example DiameterServer Configuration • 48 Example NumberRules configuration • 48 Example NumberRules configuration • 48 Example RedirectNumberMappings configuration • 45 Example Tracing configuration • 46 excludelfMatches • 67 extensionType • 31 external • 31 F Introduction • 1, 5, 6, 7, 9, 12, 14, 18, 34, 58, 78, 81, 83, 86, 89, 99, 104, 112, 114, 117, 118, 119, 120, 121, 122, 124, 127, 129, 130 Initial Request Multiple Requested Service Units • 130 Initial Request Success • 129 Installation and Removal Overview • 127 instanceName • 38 internal • 31 Introduction • 1, 5, 6, 7, 9, 12, 14, 18, 34, 58, 78, 81, 83, 86, 89, 99, 104, 112, 114, 117, 118, 119, 120, 121, 122, 124, 127, 129, 130 Initial Request Multiple Requested Service Units • 130 Initial Request Release Call • 130 Initial Request Multiple Requested Service Units • 130 Initial Request Release Call • 129 Installation and Removal Overview • 127 instanceName • 38 internal • 31 Introduction • 1, 5, 6, 7, 9, 12, 14, 18, 34, 58, 78, 81, 83, 86, 89, 99, 99, 104, 112, 114, 117, 119 Introduction • 1, 5, 6, 7, 9, 12, 14, 18, 34, 58, 78, 81, 183, 86, 89, 99, 99, 104, 112, 114, 117, 119 Introduction • 1, 5, 6, 7, 9, 12, 14, 1	Editing the File • 7	
Initial Request Multiple Requested Service encodedExtension • 31, 67 eserv.config configuration • 122, 123, 124 eserv.config Configuration • 122, 123, 124 eserv.config Files Delivered • 7 Example Basic Array configuration • 85 Example DCADefaults Configuration in eserv.config File • 24 Example DiameterServer Configuration • 48 Example NumberRules configuration • 48 Example NumberRules configuration • 43 Example PeerSchemes section • 76 Example RedirectNumberMappings configuration • 45 Example report • 79 Example Tracing configuration • 46 excludelfMatches • 67 extensionFormat • 31, 67 extensionType • 31 external • 31 F K	-	
encodedExtension • 31, 67 eserv.config configuration • 122, 123, 124 eserv.config Configuration • 5, 6 eserv.config Files Delivered • 7 Example Basic Array configuration • 85 Example DiameterServer Configuration • 48 Example NumberRules configuration • 48 Example PeerSchemes section • 76 Example PeerSchemes section • 76 Example RedirectNumberMappings configuration • 45 Example Tracing configuration • 46 excludelfMatches • 67 extensionTpornat • 31, 67 extensionTpornat • 31, 67 extensionTyoe • 31 external • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 frimalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61	Enabling Named Events • 10	
eserv.config Configuration • 122, 123, 124 eserv.config Configuration • 5, 6 eserv.config Files Delivered • 7 Example Basic Array configuration • 85 Example DCADefaults Configuration • 85 Example DiameterServer Configuration • 48 Example DiameterServer Configuration • 48 Example NumberRules configuration • 43 Example RedirectNumberMappings configuration • 45 Example RedirectNumberMappings configuration • 45 Example Tracing configuration • 46 excludelfMatches • 67 extensionType • 31 external • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61		
eserv.config Files Delivered • 7 Example Basic Array configuration • 85 Example DCADefaults Configuration in eserv.config File • 24 Example DiameterServer Configuration • 48 Example DiameterServer Configuration • 48 Example NumberRules configuration • 43 Example PeerSchemes section • 76 Example RedirectNumberMappings configuration • 45 Example report • 79 Example Tracing configuration • 46 excludelfMatches • 67 extensionType • 31 external • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 Initial Request Success • 129 Installation and Removal Overview • 127 instanceName • 38 internal • 31 Introduction • 1, 5, 6, 7, 9, 12, 14, 18, 34, 58, 78, 81, 83, 86, 89, 99, 104, 112, 114, 117, 118, 119, 120, 121, 122, 124, 127, 129, 130 132 invalidMessageSequenceResultCode • 26, 38 IP • 139 is ChargingKey • 62 ISDN • 139 is ChargingKey • 62 ISDN • 139 itc • 26, 62 ITU • 139 Iteral • 69 Loading eserv.config Changes • 7 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114		
eserv.config Files Delivered • 7 Example Basic Array configuration • 85 Example DCADefaults Configuration in eserv.config File • 24 Example DiameterServer Configuration • 48 Example Destraint • 24 Example nested format • 82 Example NumberRules configuration • 43 Example NumberRules configuration • 43 Example RedirectNumberMappings configuration • 45 Example report • 79 Example Tracing configuration • 46 excludelfMatches • 67 extensionType • 31 external • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61	eserv.config Configuration • 5, 6	
Example Basic Array configuration • 85 Example DCADefaults Configuration in eserv.config File • 24 Example DiameterServer Configuration • 48 Example NumberServer Configuration • 48 Example RedirectNumberMappings configuration • 45 Example RedirectNumberMappings configuration • 45 Example Tracing configuration • 46 excludelfMatches • 67 extensionFormat • 31, 67 extensionType • 31 external • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 Installation and Removal Overview • 127 instanceName • 38 internal • 31 Introduction • 1, 5, 6, 7, 9, 12, 14, 18, 34, 58, 78, 81, 83, 86, 89, 99, 104, 112, 114, 117, 118, 119, 120, 121, 122, 124, 127, 129, 130 132 invalidMessageSequenceResultCode • 26, 38 IP • 139 IP address • 139 isChargingKey • 62 ISDN • 139 itc • 26, 62 ITU • 139 K Key Array • 68, 81, 86 Key Array • 68, 81, 86 Key Array • 68 ID L LAC • 139 Loading eserv.config Changes • 7 LocalOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 104, 112, 114, 117, 118, 119, 120, 121, 122, 124, 127, 129, 130 132 invalidMessageSequenceResultCode • 26, 38 IP • 139 IR • 139 I		
eserv.config File • 24 Example DiameterServer Configuration • 48 Example Rey Arrays configuration • 48 Example NumberRules configuration • 43 Example PeerSchemes section • 76 Example RedirectNumberMappings configuration • 45 Example Tracing configuration • 46 excludelfMatches • 67 extensionFormat • 31, 67 extensionType • 31 external • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 internal • 31 Introduction • 1, 5, 6, 7, 9, 12, 14, 18, 34, 58, 78, 81, 83, 86, 89, 99, 104, 112, 112, 112, 112, 112, 112, 112, 11		
Example DiameterServer Configuration • 48 Example Key Arrays configuration • 87 Example NumberRules configuration • 87 Example nested format • 82 Example NumberRules configuration • 43 Example PeerSchemes section • 76 Example RedirectNumberMappings configuration • 45 Example RedirectNumberMappings configuration • 45 Example Tracing configuration • 46 excludelfMatches • 67 extensionFormat • 31, 67 extensionType • 31 external • 31 F F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61	Example DCADefaults Configuration in	
Example Key Arrays configuration • 87 Example NumberRules configuration • 43 Example PeerSchemes section • 76 Example RedirectNumberMappings configuration • 45 Example report • 79 Example Tracing configuration • 46 excludelfMatches • 67 extensionType • 31 external • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValiditityTime • 25, 61 78, 81, 83, 86, 89, 99, 104, 112, 114, 117, 118, 119, 120, 121, 122, 124, 127, 129, 130 132 78, 81, 83, 86, 89, 99, 104, 112, 114, 117, 118, 119, 120, 121, 122, 124, 127, 129, 130 132 133 78, 81, 83, 86, 89, 99, 104, 112, 114, 117, 118, 119, 120, 121, 122, 124, 127, 129, 130 132 InvalidMessageSequenceResultCode • 26, 38 IP • 139 IP • 139 IP address • 139 is ChargingKey • 62 ISDN • 139 itc • 26, 62 ITU • 139 K Key Array • 68, 81, 86 Key Array • 68 L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	eserv.config File • 24	
Example nested format • 82 Example NumberRules configuration • 43 Example PeerSchemes section • 76 Example RedirectNumberMappings configuration • 45 Example report • 79 Example Tracing configuration • 46 excludelfMatches • 67 extensionType • 31 external • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 118, 119, 120, 121, 122, 124, 127, 129, 130 132 invalidMessageSequenceResultCode • 26, 38 IP • 139 IP • 139 IP address • 139 isChargingKey • 62 ISDN • 139 itc • 26, 62 ITU • 139 K Key Array • 68, 81, 86 Key Arrays configuration • 86 keyArray • 68 L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	Example DiameterServer Configuration • 48	
Example NumberRules configuration • 43 Example PeerSchemes section • 76 Example RedirectNumberMappings configuration • 45 Example RedirectNumberMappings configuration • 45 Example report • 79 Example Tracing configuration • 46 excludelfMatches • 67 extensionFormat • 31, 67 extensionType • 31 external • 31 F K Key Array • 68, 81, 86 Key Arrays configuration • 86 keyArray • 68 Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61	Example Key Arrays configuration • 87	
Example PeerSchemes section • 76 Example RedirectNumberMappings configuration • 45 Example report • 79 Example Tracing configuration • 46 excludelfMatches • 67 extensionFormat • 31, 67 extensionType • 31 external • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 invalidMessageSequenceResultCode • 26, 38 IP • 139 IV • 139 It • 26, 62 ITU • 139 K Key Array • 68, 81, 86 Key Arrays configuration • 86 keyArray • 68 L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	Example nested format • 82	
Example RedirectNumberMappings configuration • 45 Example report • 79 Example Tracing configuration • 46 excludelfMatches • 67 extensionType • 31 external • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 IP • 139 IP address • 139 isChargingKey • 62 ISDN • 139 itc • 26, 62 ITU • 139 K Key Array • 68, 81, 86 Key Arrays configuration • 86 keyArray • 68 L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	Example NumberRules configuration • 43	_
Example report • 79 Example report • 79 Example Tracing configuration • 46 excludelfMatches • 67 extensionFormat • 31, 67 external • 31 F Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 IP address • 139 isChargingKey • 62 ISDN • 139 itt • 26, 62 ITU • 139 K Key Array • 68, 81, 86 Key Arrays configuration • 86 keyArray • 68 L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	Example PeerSchemes section • 76	· · · · · · · · · · · · · · · · · · ·
Example report • 79 Example Tracing configuration • 46 excludelfMatches • 67 extensionFormat • 31, 67 extensionType • 31 external • 31 F Key Array • 68, 81, 86 Key Arrays configuration • 86 Key Arrays configuration • 86 KeyArray • 68 Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 isChargingKey • 62 ISDN • 139 itc • 26, 62 ITU • 139 K Key Array • 68, 81, 86 Key Array • 68 L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	Example RedirectNumberMappings	
Example Tracing configuration • 46 excludelfMatches • 67 extensionFormat • 31, 67 extensionType • 31 external • 31 F K Key Array • 68, 81, 86 Key Arrays configuration • 86 Key Arrays configuration • 86 Key Array • 68 Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 ISDN • 139 itc • 26, 62 ITU • 139 K Key Array • 68, 81, 86 Key Arrays configuration • 86 keyArray • 68 L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	configuration • 45	
excludelfMatches • 67 extensionFormat • 31, 67 extensionType • 31 external • 31 F Key Array • 68, 81, 86 Key Arrays configuration • 86 Key Array • 68 Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 itc • 26, 62 ITU • 139 K Key Array • 68, 81, 86 Key Arrays configuration • 86 keyArray • 68 L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 91 102, 104, 114	Example report • 79	
extensionFormat • 31, 67 extensionType • 31 external • 31 F K Key Array • 68, 81, 86 Key Arrays configuration • 86 Key Array • 68 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 K Key Array • 68, 81, 86 Key Arrays configuration • 86 keyArray • 68 L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	Example Tracing configuration • 46	
extensionType • 31 external • 31 F Key Array • 68, 81, 86 Key Arrays configuration • 86 KeyArray • 68 Fillure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 K Key Array • 68, 81, 86 Key Arrays configuration • 86 keyArray • 68 L L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	excludelfMatches • 67	
external • 31 F Key Array • 68, 81, 86 Key Arrays configuration • 86 Key Array • 68 Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 Key Array • 68, 81, 86 Key Array • 68 L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 M M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114		110 • 139
Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 Key Array • 68, 81, 86 Key Arrays configuration • 86 keyArray • 68 L L L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	extensionType • 31	K
Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 Key Arrays configuration • 86 keyArray • 68 L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	external • 31	
Failure • 24 FDA • 138 Feature Node Configuration • 11 Features • 1 finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 keyArray • 68 L LAC • 139 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	C	
FDA • 138 Feature Node Configuration • 11 Features • 1 InalGrantUnused • 51 IfinalGrantUnused • 51 IfomNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G M ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 LAC • 139 Iiteral • 69 Loading eserv.config Changes • 7 IocalOriginHost • 54 IocalOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	•	
Feature Node Configuration • 11 Features • 1 InalGrantUnused • 51 Iteral • 69 Iteral • 69 Iteral • 69 Loading eserv.config Changes • 7 IocalOriginHost • 54 IocalOriginRealm • 54 M ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 LAC • 139 Iiteral • 69 Loading eserv.config Changes • 7 IocalOriginHost • 54 IocalOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	Failure • 24	keyArray • 68
Feature Node Configuration • 11 Features • 1 InalGrantUnused • 51 IfinalGrantUnused • 51 IfomNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 InalGrantUnused • 51 Iteral • 69 Loading eserv.config Changes • 7 IocalOriginHost • 54 IocalOriginRealm • 54 M InalGrantUnused • 51 Identify a continuation • 37 IocalOriginRealm • 54 InalGrantUnused • 51 Identify a continuation • 37 IocalOriginRealm • 54 InalGrantUnused • 51 Identify a continuation • 37 IocalOriginRealm • 54 InalGrantUnused • 51 Identify a continuation • 37 InalGrantUnused • 51 Identify a continuation • 37 InalGrantUnused • 51 Identify a continuation • 37 IocalOriginRealm • 54 InalGrantUnused • 51 Identify a continuation • 37 InalGrantUnused • 51 Identify a continuation • 37 InalGrantUnused • 51 Identify a continuation • 37 IocalOriginRealm • 54 InalGrantUnused • 51 Identify a continuation • 37 IocalOriginRealm • 54 InalGrantUnused • 51 Identify a continuation • 37 IocalOriginRealm • 54 InalGrantUnused • 51 Identify a continuation • 37 IocalOriginRealm • 54 InalGrantUnused • 51 Identify a continuation • 37 IocalOriginRealm • 54 InalGrantUnused • 51 Identify a continuation • 37 IocalOriginRealm • 54 InalGrantUnused • 51 Identify a continuation • 37 IocalOriginRealm • 54 InalGrantUnused • 51 Identify a continuation • 37 IocalOriginRealm • 54 IocalO	FDA • 138	I
finalGrantUnused • 51 fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 literal • 69 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	Feature Node Configuration • 11	
fromNoa • 43 Funds expiry, redirect, top-up and reconnect • 17, 21 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 Loading eserv.config Changes • 7 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	Features • 1	LAC • 139
Funds expiry, redirect, top-up and reconnect • localOriginHost • 54 localOriginRealm • 54 G ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 localOriginHost • 54 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	finalGrantUnused • 51	
17, 21 localOriginRealm • 54 M ggsnSupportsFinalUnitIndication • 37 GPRS • 138 gracefulTerminationValidityTime • 25, 61 localOriginRealm • 54 M mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114	fromNoa • 43	
M ggsnSupportsFinalUnitIndication • 37 mandatory • 32 GPRS • 138 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, 102, 104, 114 gracefulTerminationValidityTime • 25, 61 102, 104, 114	Funds expiry, redirect, top-up and reconnect •	
ggsnSupportsFinalUnitIndication • 37 mandatory • 32 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, gracefulTerminationValidityTime • 25, 61 102, 104, 114	17, 21	localOriginRealm • 54
GPRS • 138 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, gracefulTerminationValidityTime • 25, 61 102, 104, 114	G	M
GPRS • 138 Mapping • 73, 85, 89, 92, 94, 95, 96, 98, 99, gracefulTerminationValidityTime • 25, 61 102, 104, 114	ggsnSupportsFinalUnitIndication • 37	mandatory • 32
gracefulTerminationValidityTime • 25, 61 102, 104, 114		
11 0 0	GSM • 138	Mapping categories • 70, 71
Mapping example 1 • 107		Mapping example 1 • 107

Mapping example 1 - conditional - outbound • 110 Mapping example 2 • 108 Mapping example 2 - conditional - outbound • 112 Mapping example 3 • 108 mapping Types • 26, 27, 70 max • 43 maxAnswerReorder • 38 maxSessionLengthAfterFinalUnitIndicationsSec onds • 27 MC • 139 MCC • 139	Prefix Tree configuration • 112 Prefix Tree example • 113 Prepaid Charging Configuration • 9 prepend • 44 Prerequisites • v Price enquiry • 20 Price Enquiry • 119 Price Enquiry control plan • 120 productName • 55 profileFormat • 28, 69 profileTag • 70 protocol • 52, 75 Purpose • 23
min • 44 MNC • 139	R
MS • 140 MSC • 140 MSIN • 140 MSISDN • 140 MT • 140 Multimedia messaging direct debit scenario • 20 Multiple services credit control scenario • 22 multipleServicesRatingGroup • 38	RAA • 140 RADIUS • 140 RAR • 140 RAR Configuration • 8 rarClientTimeout • 39 rarHandlingEnabled • 39 rarMaxRetry • 39 ratingGroup • 63
N	RedirectNumberMappings Parameters • 34, 45 Refund Account • 120
name • 75 Named Event Node • 11 Nested format • 82 netmask6Bits • 75 netmaskBits • 75 noa • 32 NOA • 140 NumberRules Parameters • 34, 43	Refund Account control plan • 121 Related Documents • v RemoteAddresses • 76 remove • 44 repeating • 72, 84 Reports • 79 reqSctpInboundStreams • 76 reqSctpOutboundStreams • 76
0	requestedAction • 63 resultNoa • 45
octetsLength • 71 octetsStart • 71 origAddress • 47 originHostMustBeFQDN • 39	returnServiceResultCodeInRoot • 40 roundingDetail • 40 roundingThreshold • 40
outBufferSize • 54	005 440
overLimitError • 52 Overview • 1, 5, 23, 81, 117, 127	SCF • 140 scheme • 40
Р	schemeName • 74 Scope • v
Parameter Mappings • 14 Peer host parameters • 74 PeerSchemes Configuration Section • 73 PeerSchemes configuration structure • 73 PeerSchemes parameters • 74 percentTimeQuotaThreshold • 54 percentVolumeQuotaThreshold • 55 Per-Message Type AVP Mapping • 2, 4 permittedInstances • 75 permittedOriginHosts • 75 PLMN • 140 prefix • 44, 45 Prefix Tree • 81, 112	Screening • 4, 124 Screening Call Disallowed • 134 Screening control plan • 124 Screening Failure • 134 Screening Successful • 133 screeningService • 4, 63 SCTP • 140 sctpBindAddress • 52 sctpListenPort • 53 SelectionAVPs • 60, 63 selectionAVPslsChargingKey • 64 sendAbortOnSessionTimeout • 55 sendCreditLimitReachedOnSessionEnd • 55

sendOriginStateId • 56 throttleInterval • 54 sendQuotaThreshold • 56 throttleLimitError • 52 Service Specific AVP Mappings • 30, 34, 59, throttleThreshold • 53 timestamp • 72, 115 Service Specific AVP Mappings parameters • Timestamp • 72, 81, 114 Timestamp example 1 • 114 66 serviceContextId • 64 Timestamp example 2 • 115 serviceIdentifier • 64 Timestamp example 3 • 115 **SERVICEKEY • 8** traceDebugLevel • 47 serviceName • 65 Tracing Parameters • 34, 46 Services Configuration • 34, 58 type • 45 Services configuration structure • 58, 81 typeCriteria • 60, 67, 68, 73, 82 Services parameters • 59 Typographical Conventions • vi Session • 141 Session No Redirect • 121, 122 Session No Redirect control plan • 122 unitType • 66 Session Redirect • 122 Update Request • 135 Session Redirect control plan • 123 **URI • 142** sessionBasedDuplicateDetection • 41 **URL • 142** sessionFallbackTcc • 56 sessionLimit • 53 SGSN • 141 validityTime • 28, 66 Simple conditional • 82, 106 vendorld • 34, 57 SIP • 141 Vendor-Specific-Application-Identifier • 57 SIPDomain • 41 VLR • 142 SIPPrefix • 41 VWS • 142 sipScheme • 32 sipScheme example configurations • 33 SLC • 141 watchdogPeriod • 58 **SLEE • 141** What is Diameter Control Agent? • 1 SLEE.cfg Configuration • 5, 7, 23, 38 sleeServiceKey • 27, 65 sleeTimeout • 65 SME • 141 SMS • 141 SN • 141 SRF • 141 SRI • 141 SSP • 141 Startup • 23 Statistics Logged by diameterControlAgent • 78 SubscriptionIdTypes • 41 Successful session-based charging, client terminates session • 19 Supported-Vendor-Id • 56 System Overview • 1 systemCurrencyCode • 42 systemCurrencyExponent • 42 systemErrorResultCode • 27, 42 T tcc • 27, 65 TCP • 142 tcpBindAddress • 53 tcpListenPort • 53 Terminate Request • 135

thirtyTwoBitQuotaThresholds • 57