# 1 Energy in Thermal Physics

# 1.1 Thermal Equilibrium

The most familiar concept in thermodynamics is **temperature**. It's also one of the trickiest concepts—I won't be ready to tell you what temperature *really* is until Chapter 3. For now, however, let's start with a very naive definition:

Temperature is what you measure with a thermometer.

If you want to measure the temperature of a pot of soup, you stick a thermometer (such as a mercury thermometer) into the soup, wait a while, then look at the reading on the thermometer's scale. This definition of temperature is what's called an **operational definition**, because it tells you how to *measure* the quantity in question.

Ok, but why does this procedure work? Well, the mercury in the thermometer expands or contracts, as its temperature goes up or down. Eventually the temperature of the mercury equals the temperature of the soup, and the volume occupied by the mercury tells us what that temperature is.

Notice that our thermometer (and any other thermometer) relies on the following fundamental fact: When you put two objects in contact with each other, and wait long enough, they tend to come to the same temperature. This property is so fundamental that we can even take it as an alternative definition of temperature:

Temperature is the thing that's the same for two objects, after they've been in contact long enough.

I'll refer to this as the **theoretical definition** of temperature. But this definition is extremely vague: What kind of "contact" are we talking about here? How long is "long enough"? How do we actually ascribe a numerical value to the temperature? And what if there is more than one quantity that ends up being the same for both objects?

Before answering these questions, let me introduce some more terminology:

After two objects have been in contact long enough, we say that they are in thermal equilibrium.

The time required for a system to come to thermal equilibrium is called the relaxation time.

So when you stick the mercury thermometer into the soup, you have to wait for the relaxation time before the mercury and the soup come to the same temperature (so you get a good reading). After that, the mercury is in thermal equilibrium with the soup.

Now then, what do I mean by "contact"? A good enough definition for now is that "contact," in this sense, requires some means for the two objects to exchange energy spontaneously, in the form that we call "heat." Intimate mechanical contact (i.e., touching) usually works fine, but even if the objects are separated by empty space, they can "radiate" energy to each other in the form of electromagnetic waves. If you want to prevent two objects from coming to thermal equilibrium, you need to put some kind of thermal insulation in between, like spun fiberglass or the double wall of a thermos bottle. And even then, they'll eventually come to equilibrium; all you're really doing is increasing the relaxation time.

The concept of relaxation time is usually clear enough in particular examples. When you pour cold cream into hot coffee, the relaxation time for the contents of the cup is only a few seconds. However, the relaxation time for the coffee to come to thermal equilibrium with the surrounding room is many minutes.\*

The cream-and-coffee example brings up another issue: Here the two substances not only end up at the same temperature, they also end up blended with each other. The blending is not necessary for thermal equilibrium, but constitutes a second type of equilibrium—diffusive equilibrium—in which the molecules of each substance (cream molecules and coffee molecules, in this case) are free to move around but no longer have any tendency to move one way or another. There is also mechanical equilibrium, when large-scale motions (such as the expansion of a balloon—see Figure 1.1) can take place but no longer do. For each type of equilibrium between two systems, there is a quantity that can be exchanged between the systems:

Exchanged quantity	Type of equilibrium
energy	thermal
$\operatorname{volume}$	mechanical
particles	diffusive

Notice that for thermal equilibrium I'm claiming that the exchanged quantity is *energy*. We'll see some evidence for this in the following section.

When two objects are able to exchange energy, and energy tends to move spontaneously from one to the other, we say that the object that gives up energy is at

<sup>\*</sup>Some authors define relaxation time more precisely as the time required for the temperature difference to decrease by a factor of  $e \approx 2.7$ . In this book all we'll need is a qualitative definition.



Figure 1.1. A hot-air balloon interacts thermally, mechanically, and diffusively with its environment—exchanging energy, volume, and particles. Not all of these interactions are at equilibrium, however.

a higher temperature, and the object that sucks in energy is at a lower temperature. With this convention in mind, let me now restate the theoretical definition of temperature:

**Temperature** is a measure of the tendency of an object to spontaneously give up energy to its surroundings. When two objects are in thermal contact, the one that tends to spontaneously *lose* energy is at the *higher* temperature.

In Chapter 3 I'll return to this theoretical definition and make it much more precise, explaining, in the most fundamental terms, what temperature really is.

Meanwhile, I still need to make the *operational* definition of temperature (what you measure with a thermometer) more precise. How do you make a properly calibrated thermometer, to get a numerical *value* for temperature?

Most thermometers operate on the principle of thermal expansion: Materials tend to occupy more volume (at a given pressure) when they're hot. A mercury thermometer is just a convenient device for measuring the volume of a fixed amount of mercury. To define actual *units* for temperature, we pick two convenient temperatures, such as the freezing and boiling points of water, and assign them arbitrary numbers, such as 0 and 100. We then mark these two points on our mercury thermometer, measure off a hundred equally spaced intervals in between, and declare that this thermometer now measures temperature on the Celsius (or centigrade) scale, by definition!

Of course it doesn't have to be a mercury thermometer; we could instead exploit the thermal expansion of some other substance, such as a strip of metal, or a gas at fixed pressure. Or we could use an electrical property, such as the resistance, of some standard object. A few practical thermometers for various purposes are shown




Figure 1.2. A selection of thermometers. In the center are two liquid-in-glass thermometers, which measure the expansion of mercury (for higher temperatures) and alcohol (for lower temperatures). The dial thermometer to the right measures the turning of a coil of metal, while the bulb apparatus behind it measures the pressure of a fixed volume of gas. The digital thermometer at left-rear uses a thermocouple—a junction of two metals—which generates a small temperature-dependent voltage. At left-front is a set of three potter's cones, which melt and droop at specified clay-firing temperatures.

in Figure 1.2. It's not obvious that the scales for various different thermometers would agree at all the intermediate temperatures between 0°C and 100°C. In fact, they generally won't, but in many cases the differences are quite small. If you ever have to measure temperatures with great precision you'll need to pay attention to these differences, but for our present purposes, there's no need to designate any one thermometer as the official standard.

A thermometer based on expansion of a gas is especially interesting, though, because if you extrapolate the scale down to very low temperatures, you are led to predict that for any low-density gas at constant pressure, the volume should go to zero at approximately  $-273^{\circ}$ C. (In practice the gas will always liquefy first, but until then the trend is quite clear.) Alternatively, if you hold the volume of the gas fixed, then its pressure will approach zero as the temperature approaches  $-273^{\circ}$ C (see Figure 1.3). This special temperature is called absolute zero, and defines the zero-point of the absolute temperature scale, first proposed by William Thomson in 1848. Thomson was later named Baron Kelvin of Largs, so the SI unit of absolute temperature is now called the kelvin.\* A kelvin is the same size as a degree Celsius, but kelvin temperatures are measured up from absolute zero instead of from the freezing point of water. In round numbers, room temperature is approximately 300 K.

As we're about to see, many of the equations of thermodynamics are correct only when you measure temperature on the kelvin scale (or another absolute scale such as the Rankine scale defined in Problem 1.2). For this reason it's usually wise

<sup>\*</sup>The Unit Police have decreed that it is impermissible to say "degree kelvin"—the name is simply "kelvin"—and also that the names of all Official SI Units shall not be capitalized.




Figure 1.3. Data from a student experiment measuring the pressure of a fixed volume of gas at various temperatures (using the bulb apparatus shown in Figure 1.2). The three data sets are for three different amounts of gas (air) in the bulb. Regardless of the amount of gas, the pressure is a linear function of temperature that extrapolates to zero at approximately  $-280^{\circ}$ C. (More precise measurements show that the zero-point does depend slightly on the amount of gas, but has a well-defined limit of  $-273.15^{\circ}$ C as the density of the gas goes to zero.)

to convert temperatures to kelvins before plugging them into any formula. (Celsius is ok, though, when you're talking about the *difference* between two temperatures.)

**Problem 1.1.** The Fahrenheit temperature scale is defined so that ice melts at 32°F and water boils at 212°F.

- (a) Derive the formulas for converting from Fahrenheit to Celsius and back.
- (b) What is absolute zero on the Fahrenheit scale?

**Problem 1.2.** The Rankine temperature scale (abbreviated °R) uses the same size degrees as Fahrenheit, but measured up from absolute zero like kelvin (so Rankine is to Fahrenheit as kelvin is to Celsius). Find the conversion formula between Rankine and Fahrenheit, and also between Rankine and kelvin. What is room temperature on the Rankine scale?

Problem 1.3. Determine the kelvin temperature for each of the following:

- (a) human body temperature;
- (b) the boiling point of water (at the standard pressure of 1 atm);
- (c) the coldest day you can remember;
- (d) the boiling point of liquid nitrogen  $(-196^{\circ}\text{C})$ ;
- (e) the melting point of lead  $(327^{\circ}C)$ .

**Problem 1.4.** Does it ever make sense to say that one object is "twice as hot" as another? Does it matter whether one is referring to Celsius or kelvin temperatures? Explain.

**Problem 1.5.** When you're sick with a fever and you take your temperature with a thermometer, approximately what is the relaxation time?

6

**Problem 1.6.** Give an example to illustrate why you *cannot* accurately judge the temperature of an object by how hot or cold it feels to the touch.

**Problem 1.7.** When the temperature of liquid mercury increases by one degree Celsius (or one kelvin), its volume increases by one part in 5500. The fractional increase in volume per unit change in temperature (when the pressure is held fixed) is called the thermal expansion coefficient,  $\beta$ :

$$\beta \equiv \frac{\Delta V/V}{\Delta T}$$

(where V is volume, T is temperature, and  $\Delta$  signifies a change, which in this case should really be infinitesimal if  $\beta$  is to be well defined). So for mercury,  $\beta = 1/5500 \text{ K}^{-1} = 1.81 \times 10^{-4} \text{ K}^{-1}$ . (The exact value varies with temperature, but between 0°C and 200°C the variation is less than 1%.)

- (a) Get a mercury thermometer, estimate the size of the bulb at the bottom, and then estimate what the inside diameter of the tube has to be in order for the thermometer to work as required. Assume that the thermal expansion of the glass is negligible.
- (b) The thermal expansion coefficient of water varies significantly with temperature: It is  $7.5 \times 10^{-4} \text{ K}^{-1}$  at  $100^{\circ}\text{C}$ , but decreases as the temperature is lowered until it becomes zero at  $4^{\circ}\text{C}$ . Below  $4^{\circ}\text{C}$  it is slightly negative, reaching a value of  $-0.68 \times 10^{-4} \text{ K}^{-1}$  at  $0^{\circ}\text{C}$ . (This behavior is related to the fact that ice is less dense than water.) With this behavior in mind, imagine the process of a lake freezing over, and discuss in some detail how this process would be different if the thermal expansion coefficient of water were always positive.

Problem 1.8. For a solid, we also define the linear thermal expansion coefficient,  $\alpha$ , as the fractional increase in length per degree:

$$\alpha \equiv \frac{\Delta L/L}{\Delta T}.$$

- (a) For steel,  $\alpha$  is  $1.1 \times 10^{-5}$  K<sup>-1</sup>. Estimate the total variation in length of a 1-km steel bridge between a cold winter night and a hot summer day.
- (b) The dial thermometer in Figure 1.2 uses a coiled metal strip made of two different metals laminated together. Explain how this works.
- (c) Prove that the volume thermal expansion coefficient of a solid is equal to the sum of its linear expansion coefficients in the three directions:  $\beta = \alpha_x + \alpha_y + \alpha_z$ . (So for an isotropic solid, which expands the same in all directions,  $\beta = 3\alpha$ .)

## 1.2 The Ideal Gas

Many of the properties of a low-density gas can be summarized in the famous ideal gas law,

$$PV = nRT, (1.1)$$

where P = pressure, V = volume, n = number of moles of gas, R is a universal constant, and T is the temperature in kelvins. (If you were to plug a Celsius temperature into this equation you would get nonsense—it would say that the

volume or pressure of a gas goes to zero at the freezing temperature of water and becomes negative at still lower temperatures.)

The constant R in the ideal gas law has the empirical value

$$R = 8.31 \frac{J}{\text{mol} \cdot K} \tag{1.2}$$

in SI units, that is, when you measure pressure in  $N/m^2 = Pa$  (pascals) and volume in  $m^3$ . Chemists often measure pressure in atmospheres (1 atm =  $1.013 \times 10^5$  Pa) or bars (1 bar =  $10^5$  Pa exactly) and volume in liters (1 liter =  $(0.1 \text{ m})^3$ ), so be careful.

A mole of molecules is Avogadro's number of them,

$$N_{\rm A} = 6.02 \times 10^{23}.\tag{1.3}$$

This is another "unit" that's more useful in chemistry than in physics. More often we will want to simply discuss the number of molecules, denoted by capital N:

$$N = n \times N_{A}. \tag{1.4}$$

If you plug in  $N/N_A$  for n in the ideal gas law, then group together the combination  $R/N_A$  and call it a new constant k, you get

$$PV = NkT. (1.5)$$

This is the form of the ideal gas law that we'll usually use. The constant k is called **Boltzmann's constant**, and is tiny when expressed in SI units (since Avogadro's number is so huge):

$$k = \frac{R}{N_{\rm A}} = 1.381 \times 10^{-23} \text{ J/K.}$$
 (1.6)

In order to remember how all the constants are related, I recommend memorizing

$$nR = Nk. (1.7)$$

Units aside, though, the ideal gas law summarizes a number of important physical facts. For a given amount of gas at a given temperature, doubling the pressure squeezes the gas into exactly half as much space. Or, at a given volume, doubling the temperature causes the pressure to double. And so on. The problems below explore just a few of the implications of the ideal gas law.

Like nearly all the laws of physics, the ideal gas law is an approximation, never exactly true for a real gas in the real world. It is valid in the limit of low density, when the average space between gas molecules is much larger than the size of a molecule. For air (and other common gases) at room temperature and atmospheric pressure, the average distance between molecules is roughly ten times the size of a molecule, so the ideal gas law is accurate enough for most purposes.

**Problem 1.9.** What is the volume of one mole of air, at room temperature and 1 atm pressure?

Problem 1.10. Estimate the number of air molecules in an average-sized room.

**Problem 1.11.** Rooms A and B are the same size, and are connected by an open door. Room A, however, is warmer (perhaps because its windows face the sun). Which room contains the greater mass of air? Explain carefully.

**Problem 1.12.** Calculate the average volume per molecule for an ideal gas at room temperature and atmospheric pressure. Then take the cube root to get an estimate of the average distance between molecules. How does this distance compare to the size of a small molecule like  $N_2$  or  $H_2O$ ?

**Problem 1.13.** A mole is approximately the number of protons in a gram of protons. The mass of a neutron is about the same as the mass of a proton, while the mass of an electron is usually negligible in comparison, so if you know the total number of protons and neutrons in a molecule (i.e., its "atomic mass"), you know the approximate mass (in grams) of a mole of these molecules.\* Referring to the periodic table at the back of this book, find the mass of a mole of each of the following: water, nitrogen  $(N_2)$ , lead, quartz  $(SiO_2)$ .

**Problem 1.14.** Calculate the mass of a mole of dry air, which is a mixture of  $N_2$  (78% by volume),  $O_2$  (21%), and argon (1%).

**Problem 1.15.** Estimate the average temperature of the air inside a hot-air balloon (see Figure 1.1). Assume that the total mass of the unfilled balloon and payload is 500 kg. What is the mass of the air inside the balloon?

Problem 1.16. The exponential atmosphere.

- (a) Consider a horizontal slab of air whose thickness (height) is dz. If this slab is at rest, the pressure holding it up from below must balance both the pressure from above and the weight of the slab. Use this fact to find an expression for dP/dz, the variation of pressure with altitude, in terms of the density of air.
- (b) Use the ideal gas law to write the density of air in terms of pressure, temperature, and the average mass m of the air molecules. (The information needed to calculate m is given in Problem 1.14.) Show, then, that the pressure obeys the differential equation

$$\frac{dP}{dz} = -\frac{mg}{kT}P,$$

called the barometric equation.

(c) Assuming that the temperature of the atmosphere is independent of height (not a great assumption but not terrible either), solve the barometric equation to obtain the pressure as a function of height:  $P(z) = P(0)e^{-mgz/kT}$ . Show also that the density obeys a similar equation.

<sup>\*</sup>The precise definition of a mole is the number of carbon-12 atoms in 12 grams of carbon-12. The atomic mass of a substance is then the mass, in grams, of exactly one mole of that substance. Masses of individual atoms and molecules are often given in atomic mass units, abbreviated "u", where 1 u is defined as exactly 1/12 the mass of a carbon-12 atom. The mass of an isolated proton is actually slightly greater than 1 u, while the mass of an isolated neutron is slightly greater still. But in this problem, as in most thermal physics calculations, it's fine to round atomic masses to the nearest integer, which amounts to counting the total number of protons and neutrons.

(d) Estimate the pressure, in atmospheres, at the following locations: Ogden, Utah (4700 ft or 1430 m above sea level); Leadville, Colorado (10,150 ft, 3090 m); Mt. Whitney, California (14,500 ft, 4420 m); Mt. Everest, Nepal/Tibet (29,000 ft, 8850 m). (Assume that the pressure at sea level is 1 atm.)

**Problem 1.17.** Even at low density, real gases don't quite obey the ideal gas law. A systematic way to account for deviations from ideal behavior is the **virial** expansion,

 $PV = nRT\left(1 + \frac{B(T)}{(V/n)} + \frac{C(T)}{(V/n)^2} + \cdots\right),\,$ 

where the functions B(T), C(T), and so on are called the **virial coefficients**. When the density of the gas is fairly low, so that the volume per mole is large, each term in the series is much smaller than the one before. In many situations it's sufficient to omit the third term and concentrate on the second, whose coefficient B(T) is called the second virial coefficient (the first coefficient being 1). Here are some measured values of the second virial coefficient for nitrogen  $(N_2)$ :

T(K)	$B \text{ (cm}^3/\text{mol)}$
100	-160
200	-35
300	-4.2
400	9.0
500	16.9
600	21.3

- (a) For each temperature in the table, compute the second term in the virial equation, B(T)/(V/n), for nitrogen at atmospheric pressure. Discuss the validity of the ideal gas law under these conditions.
- (b) Think about the forces between molecules, and explain why we might expect B(T) to be negative at low temperatures but positive at high temperatures.
- (c) Any proposed relation between P, V, and T, like the ideal gas law or the virial equation, is called an equation of state. Another famous equation of state, which is qualitatively accurate even for dense fluids, is the van der Waals equation,

$$\Big(P + \frac{an^2}{V^2}\Big)(V - nb) = nRT,$$

where a and b are constants that depend on the type of gas. Calculate the second and third virial coefficients (B and C) for a gas obeying the van der Waals equation, in terms of a and b. (Hint: The binomial expansion says that  $(1+x)^p \approx 1 + px + \frac{1}{2}p(p-1)x^2$ , provided that  $|px| \ll 1$ . Apply this approximation to the quantity  $[1-(nb/V)]^{-1}$ .)

(d) Plot a graph of the van der Waals prediction for B(T), choosing a and b so as to approximately match the data given above for nitrogen. Discuss the accuracy of the van der Waals equation over this range of conditions. (The van der Waals equation is discussed much further in Section 5.3.)

## Microscopic Model of an Ideal Gas

In Section 1.1 I defined the concepts of "temperature" and "thermal equilibrium," and briefly noted that thermal equilibrium arises through the exchange of *energy* between two systems. But how, exactly, is temperature related to energy? The answer to this question is not simple in general, but it is simple for an ideal gas, as I'll now attempt to demonstrate.

I'm going to construct a mental "model" of a container full of gas.\* The model will not be accurate in all respects, but I hope to preserve some of the most important aspects of the behavior of real low-density gases. To start with, I'll make the model as simple as possible: Imagine a cylinder containing just one gas molecule, as shown in Figure 1.4. The length of the cylinder is L, the area of the piston is A, and therefore the volume inside is V = LA. At the moment, the molecule has a velocity vector  $\vec{v}$ , with horizontal component  $v_x$ . As time passes, the molecule bounces off the walls of the cylinder, so its velocity changes. I'll assume, however, that these collisions are always elastic, so the molecule doesn't lose any kinetic energy; its speed never changes. I'll also assume that the surfaces of the cylinder and piston are perfectly smooth, so the molecule's path as it bounces is symmetrical about a line normal to the surface, just like light bouncing off a mirror.  $\dagger$ 

Here's my plan. I want to know how the *temperature* of a gas is related to the kinetic *energy* of the molecules it contains. But the only thing I know about temperature so far is the ideal gas law,

$$PV = NkT (1.8)$$

(where P is pressure). So what I'll first try to do is figure out how the *pressure* is related to the kinetic energy; then I'll invoke the ideal gas law to relate pressure to temperature.

Well, what is the pressure of my simplified gas? Pressure means force per unit area, exerted in this case on the piston (and the other walls of the cylinder). What




Figure 1.4. A greatly simplified model of an ideal gas, with just one molecule bouncing around elastically.

<sup>\*</sup>This model dates back to a 1738 treatise by Daniel Bernoulli, although many of its implications were not worked out until the 1840s.

<sup>&</sup>lt;sup>†</sup>These assumptions are actually valid only for the *average* behavior of molecules bouncing off surfaces; in any *particular* collision a molecule might gain or lose energy, and can leave the surface at almost any angle.

is the pressure exerted on the piston by the molecule? Usually it's zero, since the molecule isn't even touching the piston. But periodically the molecule crashes into the piston and bounces off, exerting a relatively large force on the piston for a brief moment. What I really want to know is the *average* pressure exerted on the piston over long time periods. I'll use an overbar to denote an average taken over some long time period, like this:  $\overline{P}$ . I can calculate the average pressure as follows:

$$\overline{P} = \frac{\overline{F}_{x, \text{ on piston}}}{A} = \frac{-\overline{F}_{x, \text{ on molecule}}}{A} = -\frac{m(\overline{\Delta v_x})}{A}.$$
(1.9)

In the first step I've written the pressure in terms of the x component of the force exerted by the molecule on the piston. In the second step I've used Newton's third law to write this in terms of the force exerted by the piston on the molecule. Finally, in the third step, I've used Newton's second law to replace this force by the mass m of the molecule times its acceleration,  $\Delta v_x/\Delta t$ . I'm still supposed to average over some long time period; I can do this simply by taking  $\Delta t$  to be fairly large. However, I should include only those accelerations that are caused by the piston, not those caused by the wall on the opposite side. The best way to accomplish this is to take  $\Delta t$  to be exactly the time it takes for the molecule to undergo one round-trip from the left to the right and back again:

$$\Delta t = 2L/v_x. \tag{1.10}$$

(Collisions with the perpendicular walls will not affect the molecule's motion in the x direction.) During this time interval, the molecule undergoes exactly one collision with the piston, and the change in its x velocity is

$$\Delta v_x = (v_{x, \text{ final}}) - (v_{x, \text{ initial}}) = (-v_x) - (v_x) = -2v_x. \tag{1.11}$$

Putting these expressions into equation 1.9, I find for the average pressure on the piston

$$\overline{P} = -\frac{m}{A} \frac{(-2v_x)}{(2L/v_x)} = \frac{mv_x^2}{AL} = \frac{mv_x^2}{V}.$$
 (1.12)

It's interesting to think about why there are two factors of  $v_x$  in this equation. One of them came from  $\Delta v_x$ : If the molecule is moving faster, each collision is more violent and exerts more pressure. The other one came from  $\Delta t$ : If the molecule is moving faster, collisions occur more frequently.

Now imagine that the cylinder contains not just one molecule, but some large number, N, of identical molecules, with random\* positions and directions of motion. I'll pretend that the molecules don't collide or interact with each other—just with

<sup>\*</sup>What, exactly, does the word random mean? Philosophers have filled thousands of pages with attempts to answer this question. Fortunately, we won't be needing much more than an everyday understanding of the word. Here I simply mean that the distribution of molecular positions and velocity vectors is more or less uniform; there's no obvious tendency toward any particular direction.

the walls. Since each molecule periodically collides with the piston, the average pressure is now given by a sum of terms of the form of equation 1.12:

$$\overline{P}V = mv_{1x}^2 + mv_{2x}^2 + mv_{3x}^2 + \cdots.$$
 (1.13)

If the number of molecules is large, the collisions will be so frequent that the pressure is essentially continuous, and we can forget the overbar on the P. On the other hand, the sum of  $v_x^2$  for all N molecules is just N times the average of their  $v_x^2$  values. Using the same overbar to denote this average over all molecules, equation 1.13 then becomes

$$PV = Nm\overline{v_x^2}. (1.14)$$

So far I've just been exploring the consequences of my model, without bringing in any facts about the real world (other than Newton's laws). But now let me invoke the ideal gas law (1.8), treating it as an experimental fact. This allows me to substitute NkT for PV on the left-hand side of equation 1.14. Canceling the N's, we're left with

$$kT = m\overline{v_x^2}$$
 or  $\frac{1}{2}mv_x^2 = \frac{1}{2}kT$ . (1.15)

I wrote this equation the second way because the left-hand side is almost equal to the average translational **kinetic energy** of the molecules. The only problem is the x subscript, which we can get rid of by realizing that the same equation must also hold for y and z:

$$\overline{\frac{1}{2}mv_y^2} = \overline{\frac{1}{2}mv_z^2} = \frac{1}{2}kT. \tag{1.16}$$

The average translational kinetic energy is then

$$\overline{K}_{\text{trans}} = \frac{1}{2}mv^2 = \frac{1}{2}m(\overline{v_x^2 + v_y^2 + v_z^2}) = \frac{1}{2}kT + \frac{1}{2}kT + \frac{1}{2}kT = \frac{3}{2}kT.$$
(1.17)

(Note that the average of a sum is the sum of the averages.)

This is a good place to pause and think about what just happened. I started with a naive model of a gas as a bunch of molecules bouncing around inside a cylinder. I also invoked the ideal gas law as an experimental fact. Conclusion: The average translational kinetic energy of the molecules in a gas is given by a simple constant times the temperature. So if this model is accurate, the temperature of a gas is a direct measure of the average translational kinetic energy of its molecules.

This result gives us a nice interpretation of Boltzmann's constant, k. Recall that k has just the right units, J/K, to convert a temperature into an energy. Indeed, we now see that k is essentially a *conversion factor* between temperature and molecular energy, at least for this simple system. Think about the numbers, though: For an air molecule at room temperature (300 K), the quantity kT is

$$(1.38 \times 10^{-23} \text{ J/K})(300 \text{ K}) = 4.14 \times 10^{-21} \text{ J},$$
 (1.18)

and the average translational energy is 3/2 times as much. Of course, since molecules are so small, we would expect their kinetic energies to be tiny. The joule, though, is not a very convenient unit for dealing with such small energies. Instead

we often use the electron-volt (eV), which is the kinetic energy of an electron that has been accelerated through a voltage difference of one volt:  $1 \text{ eV} = 1.6 \times 10^{-19} \text{ J}$ . Boltzmann's constant is  $8.62 \times 10^{-5} \text{ eV/K}$ , so at room temperature,

$$kT = (8.62 \times 10^{-5} \text{ eV/K})(300 \text{ K}) = 0.026 \text{ eV} \approx \frac{1}{40} \text{ eV}.$$
 (1.19)

Even in electron-volts, molecular energies at room temperature are rather small.

If you want to know the average speed of the molecules in a gas, you can almost get it from equation 1.17, but not quite. Solving for  $\overline{v^2}$  gives

$$\overline{v^2} = \frac{3kT}{m},\tag{1.20}$$

but if you take the square root of both sides, you get not the average speed, but rather the square root of the average of the squares of the speeds (root-mean-square, or rms for short):

 $v_{\rm rms} \equiv \sqrt{\overline{v^2}} = \sqrt{\frac{3kT}{m}}. (1.21)$ 

We'll see in Section 6.4 that  $v_{\rm rms}$  is only slightly larger than  $\overline{v}$ , so if you're not too concerned about accuracy,  $v_{\rm rms}$  is a fine estimate of the average speed. According to equation 1.21, light molecules tend to move faster than heavy ones, at a given temperature. If you plug in some numbers, you'll find that small molecules at ordinary temperatures are bouncing around at *hundreds* of meters per second.

Getting back to our main result, equation 1.17, you may be wondering whether it's really true for real gases, given all the simplifying assumptions I made in deriving it. Strictly speaking, my derivation breaks down if molecules exert forces on each other, or if collisions with the walls are inelastic, or if the ideal gas law itself fails. Brief interactions between molecules are generally no big deal, since such collisions won't change the average velocities of the molecules. The only serious problem is when the gas becomes so dense that the space occupied by the molecules themselves becomes a substantial fraction of the total volume of the container. Then the basic picture of molecules flying in straight lines through empty space no longer applies. In this case, however, the ideal gas law also breaks down, in such a way as to precisely preserve equation 1.17. Consequently, this equation is still true, not only for dense gases but also for most liquids and sometimes even solids! I'll prove it in Section 6.3.

**Problem 1.18.** Calculate the rms speed of a nitrogen molecule at room temperature.

**Problem 1.19.** Suppose you have a gas containing hydrogen molecules and oxygen molecules, in thermal equilibrium. Which molecules are moving faster, on average? By what factor?

**Problem 1.20.** Uranium has two common isotopes, with atomic masses of 238 and 235. One way to separate these isotopes is to combine the uranium with fluorine to make uranium hexafluoride gas, UF<sub>6</sub>, then exploit the difference in the average thermal speeds of molecules containing the different isotopes. Calculate the rms speed of each type of molecule at room temperature, and compare them.

14

**Problem 1.21.** During a hailstorm, hailstones with an average mass of 2 g and a speed of 15 m/s strike a window pane at a 45° angle. The area of the window is 0.5 m<sup>2</sup> and the hailstones hit it at a rate of 30 per second. What average pressure do they exert on the window? How does this compare to the pressure of the atmosphere?

**Problem 1.22.** If you poke a hole in a container full of gas, the gas will start leaking out. In this problem you will make a rough estimate of the rate at which gas escapes through a hole. (This process is called **effusion**, at least when the hole is sufficiently small.)

- (a) Consider a small portion (area = A) of the inside wall of a container full of gas. Show that the number of molecules colliding with this surface in a time interval  $\Delta t$  is  $PA \Delta t/(2m\overline{v_x})$ , where P is the pressure, m is the average molecular mass, and  $\overline{v_x}$  is the average x velocity of those molecules that collide with the wall.
- (b) It's not easy to calculate  $\overline{v_x}$ , but a good enough approximation is  $(\overline{v_x^2})^{1/2}$ , where the bar now represents an average over all molecules in the gas. Show that  $(\overline{v_x^2})^{1/2} = \sqrt{kT/m}$ .
- (c) If we now take away this small part of the wall of the container, the molecules that would have collided with it will instead escape through the hole. Assuming that nothing enters through the hole, show that the number N of molecules inside the container as a function of time is governed by the differential equation

$$\frac{dN}{dt} = -\frac{A}{2V} \sqrt{\frac{kT}{m}} N.$$

Solve this equation (assuming constant temperature) to obtain a formula of the form  $N(t) = N(0)e^{-t/\tau}$ , where  $\tau$  is the "characteristic time" for N (and P) to drop by a factor of e.

- (d) Calculate the characteristic time for air at room temperature to escape from a 1-liter container punctured by a 1-mm<sup>2</sup> hole.
- (e) Your bicycle tire has a slow leak, so that it goes flat within about an hour after being inflated. Roughly how big is the hole? (Use any reasonable estimate for the volume of the tire.)
- (f) In Jules Verne's Round the Moon, the space travelers dispose of a dog's corpse by quickly opening a window, tossing it out, and closing the window. Do you think they can do this quickly enough to prevent a significant amount of air from escaping? Justify your answer with some rough estimates and calculations.

# 1.3 Equipartition of Energy

Equation 1.17 is a special case of a much more general result, called the equipartition theorem. This theorem concerns not just translational kinetic energy but all forms of energy for which the formula is a quadratic function of a coordinate or velocity component. Each such form of energy is called a degree of freedom. So far, the only degrees of freedom I've talked about are translational motion in the x, y, and z directions. Other degrees of freedom might include rotational motion, vibrational motion, and elastic potential energy (as stored in a spring). Look at

the similarities of the formulas for all these types of energy:

$$\frac{1}{2}mv_x^2$$
,  $\frac{1}{2}mv_y^2$ ,  $\frac{1}{2}mv_z^2$ ,  $\frac{1}{2}I\omega_x^2$ ,  $\frac{1}{2}I\omega_y^2$ ,  $\frac{1}{2}k_sx^2$ , etc. (1.22)

The fourth and fifth expressions are for rotational kinetic energy, a function of the moment of inertia I and the angular velocity  $\omega$ . The sixth expression is for elastic potential energy, a function of the spring constant  $k_s$  and the amount of displacement from equilibrium, x. The equipartition theorem simply says that for each degree of freedom, the average energy will be  $\frac{1}{2}kT$ :

Equipartition theorem: At temperature T, the average energy of any quadratic degree of freedom is  $\frac{1}{2}kT$ .

If a system contains N molecules, each with f degrees of freedom, and there are no other (non-quadratic) temperature-dependent forms of energy, then its *total* thermal energy is

$$U_{\text{thermal}} = N \cdot f \cdot \frac{1}{2}kT. \tag{1.23}$$

Technically this is just the *average* total thermal energy, but if N is large, fluctuations away from the average will be negligible.

I'll prove the equipartition theorem in Section 6.3. For now, though, it's important to understand exactly what it says. First of all, the quantity  $U_{\rm thermal}$  is almost never the *total* energy of a system; there's also "static" energy that doesn't change as you change the temperature, such as energy stored in chemical bonds or the rest energies  $(mc^2)$  of all the particles in the system. So it's safest to apply the equipartition theorem only to *changes* in energy when the temperature is raised or lowered, and to avoid phase transformations and other reactions in which bonds between particles may be broken.

Another difficulty with the equipartition theorem is in counting how many degrees of freedom a system has. This is a skill best learned through examples. In a gas of monatomic molecules like helium or argon, only translational motion counts, so each molecule has three degrees of freedom, that is, f = 3. In a diatomic gas like oxygen  $(O_2)$  or nitrogen  $(N_2)$ , each molecule can also rotate about two different axes (see Figure 1.5). Rotation about the axis running down the length of the molecule doesn't count, for reasons having to do with quantum mechanics. The




Figure 1.5. A diatomic molecule can rotate about two independent axes, perpendicular to each other. Rotation about the third axis, down the length of the molecule, is not allowed.

same is true for carbon dioxide  $(CO_2)$ , since it also has an axis of symmetry down its length. However, most polyatomic molecules can rotate about all three axes.

It's not obvious why a rotational degree of freedom should have exactly the same average energy as a translational degree of freedom. However, if you imagine gas molecules knocking around inside a container, colliding with each other and with the walls, you can see how the average rotational energy should eventually reach some equilibrium value that is larger if the molecules are moving fast (high temperature) and smaller if the molecules are moving slow (low temperature). In any particular collision, rotational energy might be converted to translational energy or vice versa, but on average these processes should balance out.

A diatomic molecule can also *vibrate*, as if the two atoms were held together by a spring. This vibration should count as *two* degrees of freedom, one for the vibrational kinetic energy and one for the potential energy. (You may recall from classical mechanics that the average kinetic and potential energies of a simple harmonic oscillator are equal—a result that is consistent with the equipartition theorem.) More complicated molecules can vibrate in a variety of ways: stretching, flexing, twisting. Each "mode" of vibration counts as two degrees of freedom.

However, at room temperature many vibrational degrees of freedom do not contribute to a molecule's thermal energy. Again, the explanation lies in quantum mechanics, as we will see in Chapter 3. So air molecules ( $N_2$  and  $O_2$ ), for instance, have only five degrees of freedom, not seven, at room temperature. At higher temperatures, the vibrational modes do eventually contribute. We say that these modes are "frozen out" at room temperature; evidently, collisions with other molecules are sufficiently violent to make an air molecule rotate, but hardly ever violent enough to make it vibrate.

In a solid, each atom can vibrate in three perpendicular directions, so for each atom there are six degrees of freedom (three for kinetic energy and three for potential energy). A simple model of a crystalline solid is shown in Figure 1.6. If we let N stand for the number of atoms and f stand for the number of degrees of freedom  $per\ atom$ , then we can use equation 1.23 with f=6 for a solid. Again, however, some of the degrees of freedom may be "frozen out" at room temperature.

Liquids are more complicated than either gases or solids. You can generally use the formula  $\frac{3}{2}kT$  to find the average translational kinetic energy of molecules in a




Figure 1.6. The "bed-spring" model of a crystalline solid. Each atom is like a ball, joined to its neighbors by springs. In three dimensions, there are six degrees of freedom per atom: three from kinetic energy and three from potential energy stored in the springs.

liquid, but the equipartition theorem doesn't work for the rest of the thermal energy, because the intermolecular potential energies are not nice quadratic functions.

You might be wondering what practical consequences the equipartition theorem has: How can we *test* it, experimentally? In brief, we would have to add some energy to a system, measure how much its temperature changes, and compare to equation 1.23. I'll discuss this procedure in more detail, and show some experimental results, in Section 1.6.

**Problem 1.23.** Calculate the total thermal energy in a liter of helium at room temperature and atmospheric pressure. Then repeat the calculation for a liter of air.

**Problem 1.24.** Calculate the total thermal energy in a gram of lead at room temperature, assuming that none of the degrees of freedom are "frozen out" (this happens to be a good assumption in this case).

**Problem 1.25.** List all the degrees of freedom, or as many as you can, for a molecule of water vapor. (Think carefully about the various ways in which the molecule can vibrate.)

## 1.4 Heat and Work

Much of thermodynamics deals with three closely related concepts: **temperature**, **energy**, and **heat**. Much of students' difficulty with thermodynamics comes from confusing these three concepts with each other. Let me remind you that temperature, fundamentally, is a measure of an object's tendency to spontaneously give up energy. We have just seen that in many cases, when the energy content of a system increases, so does its temperature. But please don't think of this as the *definition* of temperature—it's merely a statement *about* temperature that happens to be true.

To further clarify matters, I really should give you a precise definition of energy. Unfortunately, I can't do this. Energy is the most fundamental dynamical concept in all of physics, and for this reason, I can't tell you what it is in terms of something more fundamental. I can, however, list the various forms of energy—kinetic, electrostatic, gravitational, chemical, nuclear—and add the statement that, while energy can often be converted from one form to another, the total amount of energy in the universe never changes. This is the famous law of conservation of energy. I sometimes picture energy as a perfectly indestructible (and unmakable) fluid, which moves about from place to place but whose total amount never changes. (This image is convenient but wrong—there simply isn't any such fluid.)

Suppose, for instance, that you have a container full of gas or some other thermodynamic system. If you notice that the energy of the system increases, you can conclude that some energy came in from outside; it can't have been manufactured on the spot, since this would violate the law of conservation of energy. Similarly, if the energy of your system decreases, then some energy must have escaped and gone elsewhere. There are all sorts of mechanisms by which energy can be put into or taken out of a system. However, in thermodynamics, we usually classify these mechanisms under two categories: heat and work.

Heat is defined as any spontaneous flow of energy from one object to another, caused by a difference in temperature between the objects. We say that "heat" flows from a warm radiator into a cold room, from hot water into a cold ice cube, and from the hot sun to the cool earth. The *mechanism* may be different in each case, but in each of these processes the energy transferred is called "heat."

Work, in thermodynamics, is defined as any other transfer of energy into or out of a system. You do work on a system whenever you push on a piston, stir a cup of coffee, or run current through a resistor. In each case, the system's energy will increase, and usually its temperature will too. But we don't say that the system is being "heated," because the flow of energy is not a spontaneous one caused by a difference in temperature. Usually, with work, we can identify some "agent" (possibly an inanimate object) that is "actively" putting energy into the system; it wouldn't happen "automatically."

The definitions of heat and work are not easy to internalize, because both of these words have very different meanings in everyday language. It is strange to think that there is no "heat" entering your hands when you rub them together to warm them up, or entering a cup of tea that you are warming in the microwave. Nevertheless, both of these processes are classified as work, not heat.

Notice that both heat and work refer to energy in transit. You can talk about the total energy inside a system, but it would be meaningless to ask how much heat, or how much work, is in a system. We can only discuss how much heat entered a system, or how much work was done on a system.


I'll use the symbol U for the total energy inside a system. The symbols Q and W will represent the amounts of energy that enter a system as heat and work, respectively, during any time period of interest. (Either one could be negative, if energy leaves the system.) The sum Q + W is then the total energy that enters the system, and, by conservation of energy, this is the amount by which the system's energy changes (see Figure 1.7). Written as an equation, this statement is


$$\Delta U = Q + W, \tag{1.24}$$

the change in energy equals the heat added plus the work done.\* This equation is

Another notational issue concerns the fact that we'll often want  $\Delta U$ , Q, and W to be infinitesimal. In such cases I'll usually write dU instead of  $\Delta U$ , but I'll leave the symbols Q and W alone. Elsewhere you may see "dQ" and "dW" used to represent infinitesimal amounts of heat and work. Whatever you do, don't read these as the "changes" in Q and W—that would be meaningless. To caution you not to commit this crime, many authors put a little bar through the d, writing dQ and dW. To me, though, that d still looks like it should be pronounced "change." So I prefer to do away with the d entirely and just remember when Q and W are infinitesimal and when they're not.

<sup>\*</sup>Many physics and engineering texts define W to be positive when work-energy leaves the system rather than enters. Then equation 1.24 instead reads  $\Delta U = Q - W$ . This sign convention is convenient when dealing with heat engines, but I find it confusing in other situations. My sign convention is consistently followed by chemists, and seems to be catching on among physicists.





really just a statement of the law of conservation of energy. However, it dates from a time when this law was just being discovered, and the relation between energy and heat was still controversial. So the equation was given a more mysterious name, which is still in use: the first law of thermodynamics.

The official SI unit of energy is the **joule**, defined as  $1 \text{ kg} \cdot \text{m}^2/\text{s}^2$ . (So a 1-kg object traveling at 1 m/s has  $\frac{1}{2}$  J of kinetic energy,  $\frac{1}{2}mv^2$ .) Traditionally, however, heat has been measured in **calories**, where 1 cal was defined as the amount of heat needed to raise the temperature of a gram of water by 1°C (while no work is being done on it). It was James Joule (among others\*) who demonstrated that the same temperature increase could be accomplished by doing mechanical work (for instance, by vigorously stirring the water) instead of adding heat. In modern units, Joule showed that 1 cal equals approximately 4.2 J. Today the calorie is defined to equal exactly 4.186 J, and many people still use this unit when dealing with thermal or chemical energy. The well-known food calorie (sometimes spelled with a capital C) is actually a kilocalorie, or 4186 J.

Processes of heat transfer are further classified into three categories, according to the mechanism involved. Conduction is the transfer of heat by molecular contact: Fast-moving molecules bump into slow-moving molecules, giving up some of their energy in the process. Convection is the bulk motion of a gas or liquid, usually driven by the tendency of warmer material to expand and rise in a gravitational field. Radiation is the emission of electromagnetic waves, mostly infrared for objects at room temperature but including visible light for hotter objects like the filament of a lightbulb or the surface of the sun.

**Problem 1.26.** A battery is connected in series to a resistor, which is immersed in water (to prepare a nice hot cup of tea). Would you classify the flow of energy from the battery to the resistor as "heat" or "work"? What about the flow of energy from the resistor to the water?

**Problem 1.27.** Give an example of a process in which no heat is added to a system, but its temperature increases. Then give an example of the opposite: a process in which heat is added to a system but its temperature does not change.

<sup>\*</sup>Among the many others who helped establish the first law were Benjamin Thompson (Count Rumford), Robert Mayer, William Thomson, and Hermann von Helmholtz.

**Problem 1.28.** Estimate how long it should take to bring a cup of water to boiling temperature in a typical 600-watt microwave oven, assuming that all the energy ends up in the water. (Assume any reasonable initial temperature for the water.) Explain why no heat is involved in this process.

**Problem 1.29.** A cup containing 200 g of water is sitting on your dining room table. After carefully measuring its temperature to be 20°C, you leave the room. Returning ten minutes later, you measure its temperature again and find that it is now 25°C. What can you conclude about the amount of heat added to the water? (Hint: This is a trick question.)

Problem 1.30. Put a few spoonfuls of water into a bottle with a tight lid. Make sure everything is at room temperature, measuring the temperature of the water with a thermometer to make sure. Now close the bottle and shake it as hard as you can for several minutes. When you're exhausted and ready to drop, shake it for several minutes more. Then measure the temperature again. Make a rough calculation of the expected temperature change, and compare.

## 1.5 Compression Work

We'll deal with more than one type of work in this book, but the most important type is work done on a system (often a gas) by *compressing* it, as when you push on a piston. You may recall from classical mechanics that in such a case the amount of work done is equal to the force you exert dotted into the displacement:

$$W = \vec{F} \cdot \vec{dr}. \tag{1.25}$$

(There is some ambiguity in this formula when the system is more complicated than a point particle: Does dr refer to the displacement of the center of mass, or the point of contact (if any), or what? In thermodynamics, it is always the point of contact, and we won't deal with work done by long-range forces such as gravity. In this case the work-energy theorem tells us that the total energy of the system increases by W.\*)

For a gas, though, it's much more convenient to express the work done in terms of the pressure and volume. For definiteness, consider the typical cylinder-piston arrangement shown in Figure 1.8. The force is parallel to the displacement, so we can forget about dot products and just write


$$W = F \Delta x. \tag{1.26}$$

(I'm taking  $\Delta x$  to be positive when the piston moves inward.)

What I want to do next is replace F by PA, the pressure of the gas times the area of the piston. But in order to make this replacement, I need to assume that as the gas is compressed it always remains in internal equilibrium, so that its pressure is uniform from place to place (and hence well defined). For this to be the case, the

<sup>\*</sup>For a detailed discussion of different definitions of "work," see A. John Mallinckrodt and Harvey S. Leff, "All About Work," American Journal of Physics 60, 356–365 (1992).

Figure 1.8. When the piston moves inward, the volume of the gas changes by  $\Delta V$  (a negative amount) and the work done on the gas (assuming quasistatic compression) is  $-P\Delta V$ .



piston's motion must be reasonably slow, so that the gas has time to continually equilibrate to the changing conditions. The technical term for a volume change that is slow in this sense is **quasistatic**. Although perfectly quasistatic compression is an idealization, it is usually a good approximation in practice. To compress the gas non-quasistatically you would have to slam the piston very hard, so it moves faster than the gas can "respond" (the speed must be at least comparable to the speed of sound in the gas).

For quasistatic compression, then, the force exerted on the gas equals the pressure of the gas times the area of the piston.\* Thus,

$$W = PA \Delta x$$
 (for quasistatic compression). (1.27)


But the product  $A \Delta x$  is just minus the change in the volume of the gas (minus because the volume decreases when the piston moves in), so

$$W = -P \Delta V \qquad \text{(quasistatic)}. \tag{1.28}$$

For example, if you have a tank of air at atmospheric pressure  $(10^5 \text{ N/m}^2)$  and you wish to reduce its volume by one liter  $(10^{-3} \text{ m}^3)$ , you must perform 100 J of work. You can easily convince yourself that the same formula holds if the gas *expands*; then  $\Delta V$  is positive, so the work done on the gas is negative, as required.

There is one possible flaw in the derivation of this formula. Usually the pressure will change during the compression. In that case, what pressure should you use—initial, final, average, or what? There's no difficulty for very small ("infinitesimal") changes in volume, since then any change in the pressure will be negligible. Ah—but we can always think of a large change as a bunch of small changes, one after another. So when the pressure does change significantly during the compression, we need to mentally divide the process into many tiny steps, apply equation 1.28 to each step, and add up all the little works to get the total work.

<sup>\*</sup>Even for quasistatic compression, friction between the piston and the cylinder walls could upset the balance between the force exerted from outside and the backward force exerted on the piston by the gas. If W represents the work done on the gas by the piston, this isn't a problem. But if it represents the work you do when pushing on the piston, then I'll need to assume that friction is negligible in what follows.






Figure 1.9. When the volume of a gas changes and its pressure is constant, the work done on the gas is minus the area under the graph of pressure vs. volume. The same is true even when the pressure is not constant.

This procedure is easier to understand graphically. If the pressure is *constant*, then the work done is just minus the *area* under a graph of pressure vs. volume (see Figure 1.9). If the pressure is *not* constant, we divide the process into a bunch of tiny steps, compute the area under the graph for each step, then add up all the areas to get the total work. That is, the work is still minus the total area under the graph of P vs. V.

If you happen to know a formula for the pressure as a function of volume, P(V), then you can compute the total work as an integral:

$$W = -\int_{V_i}^{V_f} P(V) dV \qquad \text{(quasistatic)}. \tag{1.29}$$

This is a good formula, since it is valid whether the pressure changes during the process or not. It isn't always easy, however, to carry out the integral and get a simple formula for W.

It's important to remember that compression-expansion work is not the *only* type of work that can be done on thermodynamic systems. For instance, the chemical reactions in a battery cause *electrical* work to be done on the circuit it is connected to. We'll see plenty of examples in this book where compression-expansion work *is* the only kind of relevant work, and plenty of examples where it isn't.

**Problem 1.31.** Imagine some helium in a cylinder with an initial volume of 1 liter and an initial pressure of 1 atm. Somehow the helium is made to expand to a final volume of 3 liters, in such a way that its pressure rises in direct proportion to its volume.

- (a) Sketch a graph of pressure vs. volume for this process.
- (b) Calculate the work done on the gas during this process, assuming that there are no "other" types of work being done.
- $(\mathbf{c})$  Calculate the change in the helium's energy content during this process.
- (d) Calculate the amount of heat added to or removed from the helium during this process.
- (e) Describe what you might do to cause the pressure to rise as the helium expands.

**Problem 1.32.** By applying a pressure of 200 atm, you can compress water to 99% of its usual volume. Sketch this process (not necessarily to scale) on a PV diagram, and estimate the work required to compress a liter of water by this amount. Does the result surprise you?

**Problem 1.33.** An ideal gas is made to undergo the cyclic process shown in Figure 1.10(a). For each of the steps A, B, and C, determine whether each of the following is positive, negative, or zero: (a) the work done on the gas; (b) the change in the energy content of the gas; (c) the heat added to the gas. Then determine the sign of each of these three quantities for the whole cycle. What does this process accomplish?




Figure 1.10. PV diagrams for Problems 1.33 and 1.34.

**Problem 1.34.** An ideal diatomic gas, in a cylinder with a movable piston, undergoes the rectangular cyclic process shown in Figure 1.10(b). Assume that the temperature is always such that rotational degrees of freedom are active, but vibrational modes are "frozen out." Also assume that the only type of work done on the gas is quasistatic compression-expansion work.

- (a) For each of the four steps A through D, compute the work done on the gas, the heat added to the gas, and the change in the energy content of the gas. Express all answers in terms of  $P_1$ ,  $P_2$ ,  $V_1$ , and  $V_2$ . (Hint: Compute  $\Delta U$  before Q, using the ideal gas law and the equipartition theorem.)
- (b) Describe in words what is physically being done during each of the four steps; for example, during step A, heat is added to the gas (from an external flame or something) while the piston is held fixed.
- (c) Compute the net work done on the gas, the net heat added to the gas, and the net change in the energy of the gas during the entire cycle. Are the results as you expected? Explain briefly.

## Compression of an Ideal Gas

To get a feel for some of the preceding formulas, I'd like to apply them to the compression of an ideal gas. Since most familiar gases (such as air) are fairly close to ideal, the results we obtain will actually be quite useful.

When you compress a container full of gas, you're doing work on it, that is, adding energy. Generally this causes the temperature of the gas to increase, as you know if you've ever pumped up a bicycle tire. However, if you compress the gas very slowly, or if the container is in good thermal contact with its environment, heat

will escape as the gas is compressed and its temperature won't rise very much.\* The difference between fast compression and slow compression is therefore very important in thermodynamics.

In this section I'll consider two idealized ways of compressing an ideal gas: **isothermal compression**, which is so slow that the temperature of the gas doesn't rise at all; and **adiabatic compression**, which is so fast that no heat escapes from the gas during the process. Most *real* compression processes will be somewhere between these extremes, usually closer to the adiabatic approximation. I'll start with the isothermal case, though, since it's simpler.

Suppose, then, that you compress an ideal gas isothermally, that is, without changing its temperature. This almost certainly implies that the process is quasistatic, so I can use formula 1.29 to calculate the work done, with P determined by the ideal gas law. On a PV diagram, the formula P = NkT/V, for constant T, is a concave-up hyperbola (called an **isotherm**), as shown in Figure 1.11. The work done is minus the area under the graph:

$$W = -\int_{V_{i}}^{V_{f}} P \, dV = -NkT \int_{V_{i}}^{V_{f}} \frac{1}{V} \, dV$$
  
=  $-NkT \left( \ln V_{f} - \ln V_{i} \right) = NkT \ln \frac{V_{i}}{V_{f}}.$  (1.30)

Notice that the work done is positive if  $V_i > V_f$ , that is, if the gas is being compressed. If the gas expands isothermally, the same equation applies but with  $V_i < V_f$ , that is, the work done on the gas is negative.

As the gas is compressed isothermally, heat must be flowing out, into the environment. To calculate how much, we can use the first law of thermodynamics and the fact that for an ideal gas U is proportional to T:

$$Q = \Delta U - W = \Delta(\frac{1}{2}NfkT) - W = 0 - W = NkT \ln \frac{V_f}{V_i}.$$
 (1.31)




Figure 1.11. For isothermal compression of an ideal gas, the *PV* graph is a concave-up hyperbola, called an **isotherm**. As always, the work done is minus the area under the graph.

<sup>\*</sup>Scuba tanks are usually held under water as they are filled, to prevent the compressed air inside from getting too hot.

Thus the heat input is just minus the work done. For compression, Q is negative because heat *leaves* the gas; for isothermal expansion, heat must *enter* the gas so Q is positive.

Now let's consider adiabatic compression, which is so fast that no heat flows out of (or into) the gas. I'll still assume, however, that the compression is quasistatic. In practice this usually isn't a bad approximation.

If you do work on a gas but don't let any heat escape, the internal energy of the gas will increase:

$$\Delta U = Q + W = W. \tag{1.32}$$

If it's an *ideal* gas, U is proportional to T so the temperature increases as well. The curve describing this process on a PV diagram must connect a low-temperature isotherm to a high-temperature isotherm, and therefore must be steeper than either of the isotherms (see Figure 1.12).

To find an equation describing the exact shape of this curve, let me first use the equipartition theorem to write

$$U = \frac{f}{2}NkT,\tag{1.33}$$

where f is the number of degrees of freedom per molecule—3 for a monatomic gas, 5 for a diatomic gas near room temperature, etc. Then the energy change along any infinitesimal segment of the curve is

$$dU = \frac{f}{2}Nk \, dT. \tag{1.34}$$


Meanwhile, the work done during quasistatic compression is -P dV, so equation 1.32, applied to an infinitesimal part of the process, becomes

$$\frac{f}{2}Nk\,dT = -P\,dV. \tag{1.35}$$

This differential equation relates the changes in temperature and volume during the compression process. To solve the equation, however, we need to write the pressure P in terms of the variables T and V. The needed relation is just the ideal gas law; plugging in NkT/V for P and canceling the Nk gives

$$\frac{f}{2}\frac{dT}{T} = -\frac{dV}{V}. ag{1.36}$$

Figure 1.12. The PV curve for adiabatic compression (called an adiabat) begins on a lower-temperature isotherm and ends on a higher-temperature isotherm.



Now we can integrate both sides from the initial values  $(V_i \text{ and } T_i)$  to the final values  $(V_f \text{ and } T_f)$ :

$$\frac{f}{2}\ln\frac{T_f}{T_i} = -\ln\frac{V_f}{V_i}.\tag{1.37}$$

To simplify this equation, exponentiate both sides and gather the i's and f's. After a couple of lines of algebra you'll find

$$V_f T_f^{f/2} = V_i T_i^{f/2}, (1.38)$$

or more compactly,

$$VT^{f/2} = \text{constant.}$$
 (1.39)

Given any starting point and any final volume, you can now calculate the final temperature. To find the final pressure you can use the ideal gas law to eliminate T on both sides of equation 1.38. The result can be written

$$V^{\gamma}P = \text{constant}, \tag{1.40}$$

where  $\gamma$ , called the adiabatic exponent, is an abbreviation for (f+2)/f.

Problem 1.35. Derive equation 1.40 from equation 1.39.

**Problem 1.36.** In the course of pumping up a bicycle tire, a liter of air at atmospheric pressure is compressed adiabatically to a pressure of 7 atm. (Air is mostly diatomic nitrogen and oxygen.)

- (a) What is the final volume of this air after compression?
- (b) How much work is done in compressing the air?
- (c) If the temperature of the air is initially 300 K, what is the temperature after compression?

Problem 1.37. In a Diesel engine, atmospheric air is quickly compressed to about 1/20 of its original volume. Estimate the temperature of the air after compression, and explain why a Diesel engine does not require spark plugs.

Problem 1.38. Two identical bubbles of gas form at the bottom of a lake, then rise to the surface. Because the pressure is much lower at the surface than at the bottom, both bubbles expand as they rise. However, bubble A rises very quickly, so that no heat is exchanged between it and the water. Meanwhile, bubble B rises slowly (impeded by a tangle of seaweed), so that it always remains in thermal equilibrium with the water (which has the same temperature everywhere). Which of the two bubbles is larger by the time they reach the surface? Explain your reasoning fully.

Problem 1.39. By applying Newton's laws to the oscillations of a continuous medium, one can show that the speed of a sound wave is given by

$$c_s = \sqrt{\frac{B}{
ho}},$$

where  $\rho$  is the density of the medium (mass per unit volume) and B is the **bulk** modulus, a measure of the medium's stiffness. More precisely, if we imagine applying an increase in pressure  $\Delta P$  to a chunk of the material, and this increase results in a (negative) change in volume  $\Delta V$ , then B is defined as the change in pressure divided by the magnitude of the fractional change in volume:

$$B \equiv \frac{\Delta P}{-\Delta V/V}.$$

This definition is *still* ambiguous, however, because I haven't said whether the compression is to take place isothermally or adiabatically (or in some other way).

- (a) Compute the bulk modulus of an ideal gas, in terms of its pressure P, for both isothermal and adiabatic compressions.
- (b) Argue that for purposes of computing the speed of a sound wave, the adiabatic B is the one we should use.
- (c) Derive an expression for the speed of sound in an ideal gas, in terms of its temperature and average molecular mass. Compare your result to the formula for the rms speed of the molecules in the gas. Evaluate the speed of sound numerically for air at room temperature.
- (d) When Scotland's Battlefield Band played in Utah, one musician remarked that the high altitude threw their bagpipes out of tune. Would you expect altitude to affect the speed of sound (and hence the frequencies of the standing waves in the pipes)? If so, in which direction? If not, why not?

Problem 1.40. In Problem 1.16 you calculated the pressure of earth's atmosphere as a function of altitude, assuming constant temperature. Ordinarily, however, the temperature of the bottommost 10–15 km of the atmosphere (called the **troposphere**) decreases with increasing altitude, due to heating from the ground (which is warmed by sunlight). If the temperature gradient |dT/dz| exceeds a certain critical value, convection will occur: Warm, low-density air will rise, while cool, high-density air sinks. The decrease of pressure with altitude causes a rising air mass to expand adiabatically and thus to cool. The condition for convection to occur is that the rising air mass must remain warmer than the surrounding air despite this adiabatic cooling.

(a) Show that when an ideal gas expands adiabatically, the temperature and pressure are related by the differential equation

$$\frac{dT}{dP} = \frac{2}{f+2} \frac{T}{P}.$$

(b) Assume that dT/dz is just at the critical value for convection to begin, so that the vertical forces on a convecting air mass are always approximately in balance. Use the result of Problem 1.16(b) to find a formula for dT/dz in this case. The result should be a constant, independent of temperature and pressure, which evaluates to approximately  $-10^{\circ}$  C/km. This fundamental meteorological quantity is known as the dry adiabatic lapse rate.