std::byte

C++ now allows us to convert data types into bytes using std::byte.

C++17 is a significant update for the language, and it brings a lot of features in the Standard Library. So far this course has covered the most important aspects, but there are many more things to describe!

std::byte is a small type that gives you a view of bytes and bits rather than numeric/char values (like unsigned char).

In the Standard it's defined as enum:

```
enum class byte : unsigned char {}; // in <cstddef>
```

You can initialize byte from **unsigned char** with the syntax byte b{unsigned char}, which is in fact, another handy C++17 feature that allows you to init a scoped enum with the underlying type[^enumunder].

To convert from byte into a numeric type use std::to_integer().

```
[^enumunder]: Read more in P0138 - https://wg21.link/P0138
```

Let's see a basic example:

```
#include <iostream>
#include <cstddef>
using namespace std;

int main() {
    constexpr std::byte b{1};
    if(std::to_integer<int>(b) == 0x01){
        cout << "b is the byte form of 0x01" << endl;
    }

// shifts:
    constexpr auto b1 = b << 7;
    if(std::to_integer<int>(b1) == 0x80){
        cout << "b1 is the byte form of 0x80" << endl;
    }
</pre>
```

```
}
  // std::byte c{3535353}; // error: narrowing conversion from int
  constexpr std::byte c{255};
  if(std::to_integer<int>(c) == 0xff){
    cout << "c is the byte form of 0xff" << endl;</pre>
  // various bit operators, like &, |, &, etc
  constexpr auto c1 = b1 ^ c;
  if(std::to_integer<int>(c1) == 0x7f){
    cout << "c1 is the byte form of 0x7f" << endl;</pre>
  constexpr auto c2 = ~c1;
  if(std::to\_integer<int>(c2) == 0x80){
    cout << "c2 is the byte form of 0x80" << endl;</pre>
  if(c2 == b1){
    cout << "c2 == b1" << endl;
  /*static_assert(std::to_integer<int>(b) == 0x01);
  static_assert(std::to_integer<int>(b1) == 0x80);
  // various bit operators, like &, |, &, etc
  constexpr auto c1 = b1 ^ c;
  static_assert(std::to_integer<int>(c) == 0xff);
  static_assert(std::to_integer<int>(c1) == 0x7f);
  constexpr auto c2 = \sim c1;
  static_assert(std::to_integer<int>(c2) == 0x80);
  static_assert(c2 == b1);*/
}
```

The primary motivation behind std::byte is type-safety in the context of
memory/byte access.

Extra Info: See the reference paper P0298R3.

The next lesson will highlight the additions which have been made to map and set functionality.