# CS420: Operating Systems

## Virtual Memory

James Moscola Department of Physical Sciences York College of Pennsylvania



#### Background


- Code needs to be in memory to execute, but entire program rarely used
  - Error code, unusual routines, large data structures

- Want the ability to execute partially-loaded program
  - Programs no longer constrained by limits of physical memory
  - Program data no longer constrained by limits of physical memory

#### Background - Virtual Memory

- Virtual memory separation of user logical memory from physical memory
  - Only part of the program needs to be in memory for execution
  - Logical address space can therefore be much larger than physical address space
  - Allows physical address spaces to be shared by several processes
  - Allows for more efficient process creation
  - More programs running concurrently
  - Less I/O needed to load or swap processes
- In contrast to dynamic loading, virtual memory does not require programmer to do anything extra


### Virtual Memory that is Larger than Physical Memory



#### Virtual Address Space

- Enables sparse address spaces with holes left for growth, dynamically linked libraries, etc.
  - e.g. don't waste physical memory with empty space that is intended for the growth of the stack/heap


- System libraries can be shared by mapping them into virtual address space
- Can create shared memory by mapping pages into virtual address space
- Virtual memory allows pages to be shared during fork(), speeding up process creation



#### Demand Paging

- Could bring entire process into memory at load time
- Or load a page into memory only when it is needed, called demand paging
  - Pages that are never used are never loaded
    - Less I/O needed, no unnecessary I/O
    - Less memory needed
    - Faster response
  - Similar to page table system with swapping, but demand paging doesn't swap entire process into memory, instead uses a lazy swapper
- Lazy swapper never swaps a page into memory unless it will be needed
  - A swapper that deals with pages is called a pager

### Page Table Example




15

physical memory

Not all pages are always resident in physical memory

#### Valid-Invalid Bit

- Each page table entry includes a valid-invalid bit
  - If valid, then process is allowed to access that page, <u>AND</u> it is in physical memory
  - If invalid, process may not be allowed to access the requested page, or the page may not yet be in physical memory
- Initially valid-invalid bit is set to i on all entries




page table

#### Page Fault

- If requested page is memory resident, then process can operate normally
- If requested page not in physical memory (i.e. page is invalid in page table),
   then a page fault occurs
- If page fault occurs, first check to see if the requested page was an illegal request or if it just isn't in physical memory
  - If an illegal reference, the process terminates (seg fault, bus error, ...)
  - If simply not in memory:
    - Get a free frame of physical memory from the free-list
    - Swap page from disk into the frame via a scheduled disk operation
    - Update tables to indicate that the page is now in physical memory (i.e. set valid-invalid bit to 'v')
    - Restart the instruction that caused the page fault

### Steps in Handling a Page Fault



### Aspects of Demand Paging

- Extreme case of demand paging start a process with no pages in memory
  - Never bring a page into physical memory until it is needed
  - A page fault will occur each time a new page is requested, including on the very first page
  - The scheme is called pure demand paging
- Demand paging (and pure demand paging) require hardware support
  - Page table with valid / invalid bit
  - Secondary memory (swap device with swap space)
  - Ability to restart an instruction
- Performance of system can be severely impacted if too much page swapping is required (see example in OSC9 section 9.2.2, 40x slowdown!)


### Page Sharing - Copy-on-Write

- During process creation Copy-On-Write (COW) allows both parent and child processes to initially share the same pages in memory
  - If either process modifies a shared page, only then is the page copied
- COW allows more efficient process creation as only modified pages are copied
- Free pages are typically allocated from a pool of zero-fill-on-demand pages


- A variation of fork() exists called vfork() (virtual memory fork)
  - Parent suspends so child can use its memory address space
  - If child modifies parent's address space, those changes will be visible to parent (i.e. it does NOT use copy-on-write)
  - Designed to be used when child calls exec() immediately after fork()
  - Very efficient since no pages are copied during creation of child

### Example of Copy-on-Write

Memory before either process tries to write to shared pages



Memory after process<sub>1</sub> writes to page C



#### What Happens if There is no Free Frame?

- All frames used up by process pages and I/O buffers
  - How much memory should be allocated to I/O and how much to processes?


- Page replacement find some page in physical memory, but not really in use, page it out to swap space
  - Once a page is in physical memory, that doesn't mean it will always be in physical memory
  - Same page may be brought into physical memory several times
  - For performance reasons, want a page replacement algorithm which will result in minimum number of page faults

#### Page Replacement

- Must prevent over-allocation of physical memory by modifying page-fault service routine to include page replacement
  - If no free frame exists, must select a victim frame and write the page that it contains off to swap space
  - After writing page to swap space, must update pages tables accordingly
  - Required page can then be read into newly freed frame
  - Continue process by restarting instruction that caused the page-fault

- Use modify (dirty) bit to reduce overhead of page transfers
  - Only modified pages are written back to disk from physical memory
  - Without modify bit, unmodified pages may be unnecessarily written back to swap space

### Need For Page Replacement



#### Page and Frame Replacement Algorithms

- Frame-allocation algorithm determines
  - How many frames to give each process
- Page-replacement algorithm determines
  - Which frames to replace
  - Want lowest page-fault rate on both first access and re-access
- Evaluate algorithms by running them on a particular sequence of memory references (reference string) and computing the number of page faults on that sequence
  - Reference string is just page numbers, not full addresses
    - Example reference string: 7, 0, 1, 2, 0, 3, 0, 4, 2, 3, 0, 3, 0, 3, 2, 1, 2, 0, 1, 7, 0, 1
  - Repeated access to the same page does not cause a page fault
  - The more physical memory a system has, the more frames it has ... resulting in fewer page-faults

#### Page Replacement Algorithms

- Many different page replacement algorithms exist
  - FIFO Page Replacement
  - Optimal Page Replacement (theoretical best case)
  - Least-Recently Used (LRU) Page Replacement
  - Counting-Based Page Replacement

#### FIFO Page Replacement

#### A very simple page replacement algorithm

- When a page is brought into physical memory, insert a reference to that page into a FIFO
- When a page must be replaced, replace the oldest page first (i.e. the page at the head of the FIFO)


#### Pros:

- Very easy to understand and program

#### · Cons:

- Performance may not be very good
- May result in a high number of page faults

#### FIFO Page Replacement Example




#### Optimal Page Replacement

- An optimal page replacement algorithm can be described very simply:
  - Replace the page that will not be used for longest period of time

- Guarantees the lowest possible page-fault rate for a fixed number of frames
- Sadly, it is not possible to know which page won't be used for the longest period of time (can't see the future)
- Optimal algorithm is still very useful
  - Used for measuring how well other algorithm performs
  - How close are other algorithms to optimal?

### Optimal Page Replacement Example



#### Least Recently Used (LRU) Algorithm


- Interestingly, the same number of page-faults occur if a reference string is read either forwards or backwards and used to access pages
  - Because of this property, it is possible to use past knowledge of page use rather than future knowledge

- Least Recently Used (LRU) Replacement Algorithm:
  - Replace page that has not been used in the most amount of time (i.e. replace the page that is the least recently used page)
    - Associate time of last use with each page

Generally good algorithm and used frequently

#### Least Recently Used (LRU) Algorithm Example

A total of 12 pages faults; better than FIFO, but not optimal




replaced page 3 as it was least recently used

replaced page 2 as it was least recently used

#### Least Recently Used (LRU) Algorithm

- How should a least-recently-used algorithm be implemented?
  - Option #1 Counter implementation
    - Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
    - When a page needs to be replaced, look at the counters to find smallest value
      - Requires a potentially lengthy search through the page table (SLOW)
  - Option #2 Stack implementation
    - Keep a stack of page numbers in a doubly linked list
    - If a page is referenced, move it to the top of the stack (not a pure stack implementation)
      - Most recently used page is always at the top of the stack; the least recently used page is always at the bottom of the stack
    - Finding and moving page numbers in the stack takes time (updates to the stack must be done on *every* memory reference) (SLOW)

#### Stack Implementation



#### LRU Approximation Algorithms

- The LRU algorithm as described previous is too slow, even with specialized hardware
- Instead of finding exactly which page was least recently used, an approximation will do
- One possible approach for approximating the least recently used page is to use a reference bit
  - Associate a reference bit with each page, initially = 0
  - When page is referenced, set bit to 1
  - When it is time to replace a page, replace any that have reference bit = 0 (if one exists)
  - Can also use multiple reference bits to maintain a longer history and thus more closely approximate a true LRU algorithm

### Counting-Based Page Replacement

- Keep a counter of the number of references that have been made to each page
  - Not common

Least-frequently-used (LFU) algorithm: replaces the page with smallest count

- Most-frequently-used (MFU) algorithm: replaces the page with the largest count
  - Based on the argument that the page with the smallest count was probably just brought in and has yet to be used

#### Speeding Up Page Replacement

#### Always maintain a pool of free frames

- No need to search for a free frame when the page-fault occurs
- Load page into free frame and select victim to evict and add to free pool
- When convenient, evict victim
  - No longer have to wait for victim frame to get paged out before new page can get paged in

#### Possibly, keep list of modified pages

- When backing store is otherwise idle, write pages and set to non-dirty

#### Possibly, keep free frame contents intact and note what is in them

- If referenced again before reused, no need to load contents again from disk
- Generally useful to reduce penalty if wrong victim frame selected

#### Allocation of Frames

- Each process needs some minimum number of frames that it cannot run without
  - Even a single instruction may require more than a single frame of physical memory
- Example: IBM 370 6 pages to handle SS MOVE instruction:
  - Instruction is 6 bytes, and therefore might span 2 pages
  - 2 pages to handle for from
  - 2 pages to handle for to
- Maximum number of frames that can be allocated is the total number of frames in the system
- Two major allocation frame schemes
  - Fixed allocation
    - Equal allocation
    - Proportional allocation
  - Priority allocation

#### Types of Fixed Allocation

- Equal allocation every process in the system is allocated an equal share of the available frames
  - If the number of frames is m and the number of processes is n, each process is allocated m/n frames
  - For example, if there are 100 frames (after allocating frames for the OS) and 5 processes, give each process 100/5 = 20 frames
    - Maybe keep some as free frame buffer pool for faster paging
  - Pros: Easy to implement
  - Cons:
    - Why allocate 20 frames to a process that might actually only need 5?
    - Can be very wasteful
    - A higher priority process doesn't get any more frames than a lower priority process

#### Types of Fixed Allocation (Cont.)

- Proportional allocation Allocate available frames according to the size of a process
  - Larger processes are allocated more frames than smaller processes
  - Dynamic as degree of multiprogramming change

$$-s_i$$
 = size of process  $p_i$   $m = 64$   
 $-S = \sum s_i$   $s_1 = 10$   
 $-m$  = total number of frames  $s_2 = 127$   
 $-a_i$  = allocation for  $p_i = \frac{s_i}{S} \times m$   $a_1 = \frac{10}{137} \times 64 \approx 5$   
 $a_2 = \frac{127}{137} \times 64 \approx 59$ 

- Pros: Better allocation scheme than equal allocation
- Cons: A higher priority process doesn't get any more frames than a lower priority process

#### **Priority Allocation**

- Use a proportional allocation scheme using process priorities rather than process size
- If process P<sub>i</sub> generates a page fault,
  - Select for replacement one of its frames (local replacement)
  - Select for replacement a frame from a process with lower priority number (global replacement)

#### Global vs. Local Allocation


- Global replacement process selects a replacement frame from the set of ALL frames; one process can take a frame from another
  - Process execution time can vary greatly due to another process stealing frames
  - Tends to have greater throughput (the number of processes that complete execution per unit time)
  - More common than local replacement

- Local replacement each process selects a replacement frame from only its own set of allocated frames
  - Per-process performance is more consistent
  - But possibly underutilized memory

#### Thrashing

- If a process does not have "enough" pages, the page-fault rate is very high
  - Page fault to get page
  - Replace existing frame
  - But quickly need replaced frame back
  - This leads to:
    - Low CPU utilization
    - Operating system thinking that it needs to increase the degree of multiprogramming
    - Another process added to the system
- Thrashing = a process is busy swapping pages in and out (spends more time paging than executing)

### Thrashing (Cont.)



### Demand Paging and Thrashing

- Why does demand paging work?
   Locality model
  - Process migrates from one locality to another
  - Localities may overlap

- Why does thrashing occur?
   Σ size of locality > total memory size
  - Limit effects by using local or priority page replacement

### Locality In A Memory-Reference Pattern

