

Chapter 9B – Memory Management (Paging) Spring 2023



Overview

- Basic Method
- Hardware Support
- Protection
- Shared Pages
- Structure
- Swapping



- With paging, process space is no longer contiguous
- Used by most modern operating systems
- Partition the physical memory into fixed-size blocks called frames
- Partition the logical memory into same-sized fixed-size blocks called pages
 - There can be more pages than there are frames. This is virtual memory and will be covered in the next chapter.
- Use a Page Table for each process to translate logical addresses to physical addresses




- Processes use pages 0 to N so it <u>thinks</u> the memory is contiguous
- However, the physical location of each frame in memory is non-contiguous
- · Internal fragmentation is still possible & we all frames are used
- but or least all processes could
- · External fragmentation is avoided <= find a place to go.




- The logical address generated by the CPU is divided into a bitmap of length m. That's 2^m logical addresses with:
 - Page number (p) used as an index into a page table which contains base address of each page in physical memory. It is of length m-n or 2^{m-n} bits.
 - Page offset (d) combined with base address to define the physical memory address that is sent to the memory unit. It is length n or 2ⁿ bits. This is the size of each page.

page number	page offset	
р	d	
m -n	n	









- Example page numbers and page offsets
 - 3 bits $-2^1 \mid 2^2$ (2 pages, 4 page offsets each)

000	Page 0	Location 0
001	Page 0	Location 1
010	Page 0	Location 2
011	Page 0	Location 3
100	Page 1	Location 0
1 01	Page 1	Location 1
1 10	Page 1	Location 2
1 11	Page 1	Location 3



- Example page numbers and page offsets
 - 4 bits $-2^3 \mid 2^1$ (8 pages, 2 page offsets each)

0000	Page 0	Location 0
0001	Page 0	Location 1
0010	Page 1	Location 0
0011	Page 1	Location 1
0100	Page 2	Location 0
0101	Page 2	Location 1
0110	Page 3	Location 0
0111	Page 3	Location 1

1000	Page 4	Location 0
1001	Page 4	Location 1
1010	Page 5	Location 0
1011	Page 5	Location 1
1100	Page 6	Location 0
1101	Page 6	Location 1
1110	Page 7	Location 0
1111	Page 7	Location 1




- Example page numbers and page offsets
 - 4 bits $-2^2 \mid 2^2$ (4 pages, 4 page offsets each)

0000	Page 0	Location 0
0001	Page 0	Location 1
0010	Page 0	Location 2
0011	Page 0	Location 3
0100	Page 1	Location 0
0101	Page 1	Location 1
0110	Page 1	Location 2
0111	Page 1	Location 3

1000	Page 2	Location 0
1001	Page 2	Location 1
1010	Page 2	Location 2
1011	Page 2	Location 3
1100	Page 3	Location 0
11 01	Page 3	Location 1
11 10	Page 3	Location 2
1111	Page 3	Location 3



- Mapping pages to frames
 - length of each page.
 - 5 bits $-2^3 \mid 2^2$ (8 pages, 4 page offsets each)
 - Page 0, offset 0 (a) is at physical address 20
 - Page 0, offset 3 (d) is at physical address 23
 - Page 1, offset 0 (e) is at physical address 24
 - Page 3, offset 2 (n) is at physical address 9
- (Note: In this diagram, if a physical address is handled in 1-byte increments, there are 32 bytes of memory, a page is 4 bytes, and there are 8 pages/frames)





- Internal fragmentation
 - Consider a page size of 2048 bytes and process size is 72,766 bytes
 - 35 pages + 1,086 bytes
 - The last page is using 1,086 bytes with 962 bytes left over
 - A process could use n pages + 1 byte so n+1 frames in the worst case. Almost the entire frame is useless. On average, $\frac{1}{2}$ of the last frame is unused
 - Smaller page sizes minimizes the waste but adds overhead to the operating system
 - Larger page sizes make disk I/O to memory more efficient but adds more internal fragmentation



- Internal fragmentation
 - Most operating systems support two page sizes
 - 4KB or 8KB for regular processes
 - 2MB or 4MB or higher for processes that use a lot of memory




- External fragmentation
 - We have none. Any free frame can be allocated to a process as needed.



- Free frames
 - The operating system maintains a system-wide frame table
 - One entry per frame
 - Each entry has a flag indicating whether the frame is free or not
 - If it is not free, which process is using it



Free frames






- Due to the size of a process' page table, the table is kept in memory
 - The address of the page table is stored in the Page-table base register (PTBR)
 - The size of the page table is stored in the Page-table length register (PTLR)
 - Every instruction that accesses memory will trigger two memory accesses:
 - One to reference the page table itself and find the physical address
 - One to access the found address in memory
 - Solution: Cache the page table (Most systems have multiple levels)
 - This is called the Translation Look-aside Buffer (TLB)



- Some TLBs hold address-space identifiers (ASIDs) so processes can only use their own entries
 - Otherwise, the TLB will need to be reloaded at each context switch
- Typically small (e.g. 64 1024 entries). Some entries can be made permanent.
- If the page is found in the TLB (a hit), use the frame
- If the page is not found in the TLB (a miss)
 - Consult the page table in memory instead
 - Load it into the TLB so we can avoid a miss in the future (Use an algorithm like Least-recently used, round-robin, or random to replace existing entries)







- Effective memory-access time
 - The percentage of times the page number of interest is found in the TLB is the hit ratio
 - If it is not found in the TLB, we need to consult the page table (1 access)
 - Then we can use the address (1 access)

Effective Access Time =
$$(Hit) \bullet Access Time + (1 - Hit) \bullet 2(Access Time)$$

- Suppose a hit ratio of 80% and a memory access time of 10 nanoseconds, then effective access time is 0.80x10 + 0.2x20 = 12 nanoseconds
- A hit ratio of 99% is 10.1 nanoseconds




Protection

- Each entry in the page table can hold a protection bit to indicate whether the frame is read-only or read-write.
- To determine whether the frame is in the process' logical address space
 - Use a page-table length register
 - Each entry in the page table can hold a valid-invalid bit for all frames in the address space



Protection




0




Shared Pages


- Paging makes sharing address space easy
- These pages should be read-only
- Commonly used for DLLs





Page tables can be very large. We don't want to put this in one contiguous block







- Here are some examples using 64 bits
- More page tables means more memory accesses, so this strategy only goes so far

outer page	outer page inner page	
p_1	p_2	d
42	10	12


2nd outer page	outer page	inner page	offset
p_1	p_2	p_3	d
32	10	10	12



- Hashed Page Tables
 - Common in address spaces larger than 32 bits
 - Each entry in the page table holds
 - A hash of the page number
 - The frame
 - A pointer to the next hash
 - A logical address is hashed and then the matching hash is searched in the list



Hashed Page Tables






- Inverted Page Tables
 - Instead of one page table per process, one page table for all processes
 - One entry in the table for each frame in the system
 - This removes the need to maintain many page tables
 - This adds to the amount of time it takes to search the page table
 - Since pages to frames is one-to-one, shared memory will be regularly mapped and re-mapped



Inverted Page Tables






• In reality, modern operating systems will employ a mixture of these structures



Swapping

- A process can be temporarily swapped to a backing store (usually disk) and then brought back in
- Total memory space for processes can exceed the physical memory (oversubscribed)





Swapping

- The backing store needs to be reasonably fast
- Swapping entire processes is generally no longer used
- Modern operating systems may still swap pages
- Swapping pages due to low memory
 is an "emergency" situation and should be avoided
 - Terminate unnecessary processes
 - Get more memory

