

Table of Contents

Subnetting Basics








Subnetting Basics



 The process of taking an extensive network and splitting into smaller networks is known as subnetting



CLARUSWAY®

Why to use subnetting?

- Reduced Network Traffic
- Optimized Network Performance
- Simplified Management Easier to identify and isolate network problems
- Facilitated Spanning of Large Geographical Distances -Connecting multiple smaller networks makes the system more efficient


CLARUSWAY®

ı

Subnetting Basics



- IPv4 address is divided into network ID and host ID by using octets
- In subnetting we can borrow some bits from host ID to use as subnetwork



CLARUSWAY®

ш



Subnetting IPv4 Address:

- A Class A. B. or C TCP/IP network can be further divided, or subnetted, by a system administrator
- For example, you have 150 hosts on three networks that are connected by a router
- You are allocated a **Class C** address:

192.168.123 Network ID Host ID

You can use from 192.168.123 .1 to | 192.168.123 (Just remember that the first and last address in any network or subnet cannot be assigned to any individual host, so you cannot use 192.168.123.0 and 192.168.123.255) CLARUSWAY®

Subnetting Basics



Subnetting IPv4 Address:

- With the allocated Class C IP address we can map 254 hosts on one network
- But our 150 hosts are located on **three** separate networks
- Instead of requesting more address blocks for each network, we can divide our block into three subnets





Subnetting IPv4 Address:

- Remember we can create subnets by borrowing bits from Host ID
- We need 3 subnets in total, so if we borrow 1 bit we will get 2 subnets which is not enough
- So we need more bits, if we borrow 2 bits we will get 4 subnets and our subnet mask will be:



1

Subnetting Basics



Subnetting IPv4 Address:

- Since we borrowed 2 bits, there are only 6 bits left for Host ID which makes 2⁶ 2 = 62 hosts (first and last numbers are reserved)
- Our company has **3 networks** and **50 hosts** on each network
- We have **4 subnets**, and **62 host IDs** for each subnet (that means 1 subnet with 62 host IDs will be reserved for future use)



Subnetting IPv4 Address:

- Using subnet mask 255.255.255.192, our 192.168.123.0 network will become 4 networks:
 - 192.168.123.0111111111111111111111111111100 0000000

 - 192.168.123.128 1111111111111111111111111111 0000000
 - 0 192.168.123.192 1111111111111111111111111 000000
- Valid host addresses will be:

 192.168.123.1-62
 192.168.123.129-190

 192.168.123.65-126
 192.168.123.193-254

(Remember, again, that binary host addresses with all 1s or all 0s are reserved, so you cannot use addresses with the last octet of 0, 63, 64, 127, 128, 191, 192, and 255)

CLARUSWAY®

WAY TO REINVENT YOURSELF

4

Subnetting Basics



Let's see how this works:

- Assume we have two IP addresses:
 - o 192.168.123.71 and 192.168.123.133
- If we used default subnet mask of Class C which is 255.255.255.0 both addresses should be on the same network
- However we use subnet mask of 255.255.255.192 so
 - o 192.168.123.71 host will be on the 192.168.123.64 network
 - o 192.168.123.133 host will be on the 192.168.123.128 network



Well done!

Default gateways


- If a host needs to communicate with a host on another network, it will communicate through a router
- A router specified on a host is called default gateway
- So how does TCP/IP knows if the destination host is on the same network or not?



Subnetting Basics

Default gateways

When a host wants to communicate with another device, it performs a comparison process using the defined subnet mask with the destination IP address and its own IP address



CLARUSWAY®

14

Source host :192.168.123.72 Subnet mask 255.255.255.192 Destination host 192.168.123.109

Source IP :11000000.10101000.01111011.01001000 Logical Subnet mask: 11111111.1111111.1111111.11000000 AND Network ID **11000000.10101000.01111011.01000000**(192.168.123.64)

Destination IP: 11000000.10101000.01111011.01101101 Logical Subnet mask: 11111111.1111111.1111111.11000000 AND Network ID 11000000.10101000.01111011.01000000 192.168.123.64)

Same result! Two hosts are on the same network.

CLARUSWAY®

Subnetting Basics

Source host :192.168.123.46 Subnet mask 255.255.255.192 Destination host 192,168,123,202

Source IP :11000000.10101000.01111011.00101110 Logical Subnet mask : 11111111.1111111.1111111.11000000 AND Network ID 11000000.10101000.01111011.00000000 (192.168.123.0)

Destination IP: 11000000.10101000.01111011.11001010 Subnet mask: 11111111.1111111.1111111.11000000

Network ID **11000000.10101000.01111011.11000000** (192.168.123.192)

Logical AND

Not the same! Two hosts are on different networks.

CLARUSWAY®

Classless Inter-Domain Routing (CIDR)

- In order to reduce the wastage of IP addresses, a new concept of CIDR is introduced
- CIDR provides the flexibility of borrowing bits of Host part of the IP address
- By using subnetting, one single Class A address can be used to have smaller sub-networks which provides better network management capabilities

CLARUSWAY®

a

Subnetting Basics

• CIDR notation examples:

IP address: 192.168.1.142

Subnet mask: 255.255.255.0 or 111111111.11111111.1111111.000000000


IP address: 172.16.56.140

28 turned on bits (1s)

CIDR: 172.16.56.140 /28

CLARUSWAY®

18





- 15