# NINTENDO NITRO-System

# fontcvtr

**Operation Manual** 

Version 0.1.1

The contents of this document are strictly confidential and the document should be handled accordingly.

© 2004-2005 Nintendo NTR-06-0370-001-A1





# **Contents**

1	Intro	duction	7
	1.1	About fontcvtr	7
	1.2	What fontcvtr Can Do	7
	1.3	Font Licenses	7
2	File S	Structure	8
3	Expla	anation of Operations	9
	3.1	GUI	9
	3.2	Converting Fonts	10
	3.2.1	Basic Operations	10
	3.2.2	The Flow for Creating a Font Resource	10
	3.3	Input Specifications	11
	3.3.1	BMP	11
	3.3.2	NITRO Font	11
	3.3.3	Windows Font	12
	3.3.4	LC Font	13
	3.4	Output Specifications	14
	3.4.1	BMP	14
	3.4.2	NITRO Font	15
	3.5	Filter Specification	17
1	Char	acter Filter Files	18
	4.1	Overview	18
	4.2	Structure	18
	4.3	Document Type Definition	19
	4.4	How to Use	19
5	Lette	r Order Files	20
	5.1	Overview	20
	5.2	The Included Letter Order Files	20
	5.3	Structure	21
	5.4	DTD	
	5.5	How to Use	
	D145	June 20 Format	00
)		Image Format	
	6.1	The Structure of BMP Images	23



6.1.1 BI	ock	23
6.1.1.1	Grid Area	24
6.1.1.2	Margin Area	24
6.1.1.3	Cell	24
6.1.1.4	Width Line Region	24
6.1.2 C	ells and Width Lines	24
6.1.2.1	Glyph Image	25
6.1.2.2	Width Line	25
6.1.2.3	Glyphs With NoOutput	26
6.1.3 Ba	aseline	26
6.2 BMP	Fonts that Are Output	27
6.3 BMP	Fonts that Can Be Input	27
7 Precaution	ns	28
7.1 Prec	autions About Converting Windows Fonts	28
7.2 Unic	ode Inside fontcvtr	28
7.3 Prec	autions when Describing Letter Order File	29
	ode in the Letter Order File	
8 Warning a	nd Error Messages	30
8.1 Warr	ning Messages	30
8.2 Error	Messages	30
Codes		
Code 4-1	sample.xlit	18
Code 5-1	cp1252.xlor	21
Tables		
Table 4-1	Character Filter Definition Elements	19
Table 5-1	Included Letter Order Files	20
Table 5-2	Letter Order Definition Elements	22
Table 7-1	Places Where Character Codes are Converted	28
Table 7-2	The 2:1 Relationship of Characters Converted from Shift_JIS to Unicode	29
Table 8-1	Explanation of Warning Messages	30
Table 8-2	Explanation of Error Categories	31
Table 8-3	Descriptions of Error Messages	31

4



# **Figures**

Figure 1-1 Relationships Among Font-Related Resources	7
Figure 2-1 File Structure	8
Figure 3-1 Main Dialog Box of fontcvtr	9
Figure 3-2 The Basic Flow for Creating a Font Resource	10
Figure 3-3 Input: BMP	11
Figure 3-4 Input: NITRO Font	11
Figure 3-5 Input: Windows Font	12
Figure 3-6 Input: LC Font	13
Figure 3-7 Output: BMP	14
Figure 3-8 Specifying Cell Size and Glyph Output Position	15
Figure 3-9 Output: NITRO Font	16
Figure 3-10 Filter Specification	17
Figure 6-1 Example of BMP Image (Number of Blocks: 16x9)	23
Figure 6-2 Schematic Pattern Diagram of Block	24
Figure 6-3 Schematic Patter Diagram of Cell and Width Line	25
Figure 6-4 Left and Right Placement in Cell	25
Figure 6-5 Position of Baseline	26
Figure 6-6 Font Height	27



# **Revision History**

Version	Revision Date	Description	
0.1.1	07/11/2005	Corrected a misnamed function	
0.1.0	5/25/2005	Initial version	



#### Introduction 1

#### 1.1 About fontcvtr

fontcvtr is a Windows tool for creating NITRO fonts. Using NITRO fonts with the NITRO-System G2D Character Drawing Library, character strings can be easily drawn on Nintendo DS (DS).

#### 1.2 What fontcytr Can Do

fontcvtr converts Windows and Sharp LC fonts into NITRO fonts. This tool can also be used to write non-NITRO fonts out as BMP files. Because BMP files can be loaded and converted into NITRO fonts, the non-NITRO fonts can first be converted into and fine-tuned as BMP files before converting the BMP files into NITRO fonts. With fontcvtr, you can use glyph data from BMP files to create unique NITRO fonts. These relationships are shown in Figure 1-1.

In each step of the conversion, you can create only the fonts that you need by extracting the needed text characters from the original font set.




Figure 1-1 Relationships Among Font-Related Resources

#### 1.3 **Font Licenses**

fontcytr can convert any font installed on a PC to a NITRO font for us on the DS. However, a user license is required to use these non-NITRO fonts in game software that will be sold. You need to obtain licenses for each game software title.

fontcvtr and NITRO-System do not come with licenses for any fonts.



# 2 File Structure

fontcvtr files are located in NitroSystem/tools/win/fontcvtr. The user manual is located in NitroSystem/docs/G2D.

The file structure of all the fontcvtr related folders and files are shown in Figure 2-1.




Figure 2-1 File Structure

For more details, see chapters 4 - Character Filter Files and 5 - Letter Order Files.

This fontcvtr manual covers topics shared by the fontcvtr (GUI) and fontcvtrc (the command line), as well as topics unique to fontcvtr. To read topics unique to the command-line version, read the fontcvtrc manual.

When you start fontcvtr, a settings file called fontcvtr.ini is created in the same directory as fontcvtr.exe. (Note that fontcvtr.ini is not shown in **Error! Reference source not found.**.) The display state of fontcvtr is automatically stored in this settings file so the display is in the same state the next time fontcvtr runs.

NTR-06-0370-001-A1 8 © 2004-2005 Nintendo



# 3 Explanation of Operations

# 3.1 **GUI**

Figure 3-1shows a screen shot from fontcvtr (henceforth referred to as fontcvtr).

The GUI of fontcytr is a dialog-box, and all operations can be performed from the dialog box.




Figure 3-1 Main Dialog Box of fontcvtr

The main dialog box can be divided into four components: Input Specifications at the top, Output Specifications at the bottom, Filter Specification in the middle, and Status Display at the very bottom of the dialog box. The Input Specifications is used to set the resource and options for the font-conversion source. The Output Specifications is used to specify the font-conversion target. Once the settings have been specified, click **Convert** and fontcvtr executes the font conversion process.

The Status Display shows the status of the process in a progress bar.

All fontcvtr operations support file drag and drop into fields where files can be specified.



# 3.2 Converting Fonts

# 3.2.1 Basic Operations

Follow these procedures when using fontcvtr to convert fonts:

- 1. Open the tab for the conversion-source resource and set the input resource. For further detail, see section 3.3 Input Specifications.
- 2. Open the tab for the output-target resource and set the output resource. For further detail, see section 3.4 Output Specifications.
- 3. Specify a filter as necessary. If you are not going to use a filter, clear the **Use Filter** box. For further detail, see section 3.5 Filter Specification.
- 4. Click Convert.
- 5. The conversion process executes. If there is a problem in the input resource, output resource, or either of their settings, a warning message window is displayed. If fontcvtr cannot compensate for the problem, an error displays in the message window and the conversion fails. If it is only a warning or nothing is displayed, then the conversion process is a success. For further details, see chapter 8 Warning and Error Messages.

# 3.2.2 The Flow for Creating a Font Resource

The Windows or LC font is first converted to a BMP file and creates the base font. Adjustments are made if necessary, and then converted from a BMP file to a NITRO font. A filter can now be used so that only text characters needed by the application are stored in the NITRO font.




Figure 3-2 The Basic Flow for Creating a Font Resource

NTR-06-0370-001-A1 10 © 2004-2005 Nintendo



# 3.3 Input Specifications

#### 3.3.1 BMP

Figure 3-3 shows the BMP tab of the Input Specifications. Use this tab to specify a BMP file as the input source, explained further in Chapter 6 - BMP Image Format.




Figure 3-3 Input: BMP

#### Bitmap File

Specifies the conversion source BMP file.

### Glyph Order

Selects the letter order of the BMP file. For further detail, see Chapter 5 - Letter Order Files.

#### Colors

Specifies the valid number of colors in the BMP file. Also specifies the number of colors in the font that is output. If you use more colors than those specified, those additional colors will be treated as transparent colors. For example, if you specify 4 for the drop-down **Colors** box, the BMP color palette output will be color numbers 0-3, and all color numbers above 4 will be treated as transparent colors.

#### 3.3.2 NITRO Font

Figure 3-4 shows the NITRO font tab of Input Specifications. Use this tab to specify a NITRO font that has been created by fontcvtr as the input source.




Figure 3-4 Input: NITRO Font

#### NITRO Font

Specifies a NITRO font as the conversion source.



#### 3.3.3 Windows Font

#### Figure 3-5 Input: Windows Font

shows the Windows Font tab of the Input Specifications. Use this tab to specify one of the fonts that is installed in Windows as the input source.

Note that when a Windows font is entered as the input source, the text characters of that font in the entire Unicode range are passed to the output. If BMP has been specified for the output, then the output text characters are restricted by the Letter Order file. But if NITRO font has been specified for the output but a Letter Order file has not been specified, then all text characters for that font will be output. Depending on the font, the output could result in tens of thousands of text characters;, therefore, be careful.

In the initial state, the Windows Font tab only shows a font **Name** and **Size** drop-down list box. But by clicking on the green triangle, show or hide other fields.




Figure 3-5 Input: Windows Font

#### Name

Specify the Windows font name to use as the conversion source. Click to view a list of all fonts installed on the PC. Fonts shown with a yellow background are raster fonts (bitmap fonts) while those shown with a white background are vector fonts (outline fonts).

#### Size

Specify the conversion source font size in units of pixels. Depending on the font, the value might not adhere strictly to the size. Especially with raster fonts, the difference might be striking if a small font size is specified.

#### Levels of Gray

Specify the number of levels in the gray scale output. If a value is set to 2, the output will be black and white only. This option is not available for raster fonts because they are always set to 2.

#### Glyph Width

Specify if the text character width of the output font will include a blank space on either side of the Windows font. When set to *glyph on*ly, this blank space is not included, and the text character width is the same as the glyph width. To include blank spaces, set **Glyph Width** to *include margin*. If set to *fixed width*, all text characters are output with the text character width set in **Fixed Width** (described in section 3.3.4 - LC Font). This options is the default value.

#### Fixed Width

Specify the text character width in units of pixels. This setting can only be configured when **Glyph Width** is set to *fixed width*.



#### 3.3.4 LC Font

Figure 3-6 shows the LC Font tab of the Input Specifications. This tab is used to specify LC Font as the input.

If you would like to LC Fonts, contact the Nintendo Licensing Department.




Figure 3-6 Input: LC Font

## LC Font File (default mapping)

Specifies the conversion source LC Font file.

### LC Font File (Half Width mapping)

Specify the conversion source LC Font file. This setting is different from the default mapping because LC font stores full width character codes and the full width text characters are replaced by the half width character codes for use as the conversion source. The character code replacement is done so LC Font letters and numbers can be used with ASCII character codes.

If default mapping and Half Width mapping are both specified, the two fonts will be combined into a single font for conversion. By using default mapping for the full-width LC Font and Half Width mapping for the half-width LC Font, you can cover all text characters from ASCII to level 2 Japanese kanji characters (corresponding to the Letter Order file JIS X0201 X0208 012.xco).

#### **Fixed Width**

All LC Font text characters have the same text character width, but if **Fixed Width** is unchecked, the spaces on either side of the glyphs are removed during the conversion process and the font is output as a proportional font. This setting has the same effect as selecting glyph only for Glyph Width when converting a Windows font. However, in the case of the LC Font, every text character has a 1-pixel space attached to its left side in order to prevent letters from touching.



# 3.4 Output Specifications

In the initial state, each tab in Output Specifications displays only the settings that need to be configured. Click the green triangle to toggle show and hide other options.

#### 3.4.1 BMP

Figure 3-7 shows the BMP tab of Output Specifications. The input source font data is output as a BMP file based on the image settings described in chapter 6 - BMP Image Format. This BMP file output can be used as a BMP entry in the Input Specifications.




Figure 3-7 Output: BMP

### Bitmap File

Specify the conversion-destination BMP file.

#### Glyph Order

Select the order to output the text characters in the BMP files. For further detail, see chapter 5 - Letter Order Files.

#### • Size/Offset or Margin

Specify **Size/Offset** and then specify the cell size and glyph output position with the parameters shown on the left in Figure 3-8; otherwise, specify **Margin** and then specify the cell size and glyph output position with the parameters shown on the right in Figure 3-8.






Figure 3-8 Specifying Cell Size and Glyph Output Position

#### Place center

Check to center the glyph in the cell. The *Left* and *Top* values are set automatically. This feature is available when **Size/Offset** has been selected.

#### Right=Left, Bottom=Top

Check to make the values of *Right* and *Left* and *Bottom* and *Top* the same. This feature is available when **Margin** has been selected.

#### Left, Top, Right, Bottom

Specify the parameters shown on the right in Figure 3-8 when **Margin** has been selected. When **Size/Offset** has been selected, these parameters change to *Width, Height, Left, Top*.

#### Draw Grid

Check to draw a grid.

#### Rotation

Select None, Clockwise, or CounterClockwise to rotate the output text character. To output the text character without rotation, specify None. If set to Clockwise, the text character rotates clockwise by 90 degrees. If set to CounterClockwise, the text character is rotated counterclockwise by 90 degrees.

#### 3.4.2 NITRO Font

Figure 3-9 shows the NITRO Font tab of Output Specifications. This tab configures the settings to convert the input source font data into a font resource to be used by the Character Drawing Library. Ultimately, font data is output in this format.






Figure 3-9 Output: NITRO Font

#### NITRO Font

Specify the output target NITRO font file.

#### Alternate Char

Specify which alternate text characters the Character Drawing Library should display if the font is not supported. Enter the character code or the text character itself. Character codes are entered according to C-language rules in octal, decimal, or hexadecimal. If only one text character is entered, it is assumed that this single text character maps directly to the alternate text character. When *Use Default* is selected, the text character with the lowest character code is used as the alternate text character. (In most cases, this alternate text character is half-width.)

#### Line Height

Specify the height of one line. Value ranges from 0 to 255. The Character Drawing Library uses this value for the basic line height. If *Use Default* is selected, the value is set to the height of the font.

#### Default Left Space

Specify the default width of the left space for text characters that do not have their own left space. Values range from -128 to 127. When *Use Default* is selected, the value is set to 0.

#### Default Width

Specify the default glyph width for text characters that do not have their own glyph width. Value ranges from 0 to the largest glyph width possible for the font. When *Use Default* is selected, the value is set to the largest glyph width possible.

#### Default Right Space

Specify the default width of the right space for text characters that do not have their own right space. When *Use Default* is selected, the value is set to 0.

#### Use Default

The *Use Default* checkbox is to the right of each option field. Check this box to set the option to its default value. The default values for each option is explained above. However, note that if a NITRO font is entered as the input, then the default values correspond to the values configured in the NITRO font.

#### Encoding

Specify the text character encoding format that corresponds to the output font.



#### 3.5 **Filter Specification**

Figure 3-10 shows the filter specification field on the dialog box. If a text character filter file is specified, text characters not included in the file are not output. The filter provides a method to create a compact NITRO font that includes only the necessary set of text characters. If a character filter file is not specified, then all text characters that belong to the font entered as input are passed to the output. For further detail, see chapter 4 - Character Filter Files.



Figure 3-10 Filter Specification

**Use Filter** 

Check this box to use apply a filter during the conversion process.



# 4 Character Filter Files

### 4.1 Overview

The character filter file specifies which text characters fontcvtr will output. You can use this file so the game program only includes necessary text characters in the NITRO font.

Character filter files are written in XML and have the \*.xllt extension.

## 4.2 Structure

The XML structure of the character filter file complies with the protocol for NITRO-System XML files (NNSXML protocol). To learn more about the NNSXML protocol, see

NitroSystem/docs/Readme/DataFormatRule.pdf. This section explains the character filter file structure that is not defined by the NNSXML protocol. Specifically, the section describes the internal structure of the *root* element and the *body* element of the character filter file.

The sample character filter file sample.xllt is shown in Code 4-1. When fontcvtr is run using this character filter file, a total of only 19 text characters are output, including the letters fontcvtr, the kana characters あいうえかきくけ, the kanji characters 任天堂, and a half-width space.

```
<?xml version="1.0" encoding="UTF-8" ?>
<!DOCTYPE letter-list SYSTEM "letter-list.dtd">
<letter-list version="1.0">
      <head>
              <create user="hatamoto minoru" date="2005-02-18T10:51:13" />
              <title>xllt sample</title>
              <comment>Character Filter file sample</comment>
      </head>
      <body>
              <letter>
                      font.cvt.r
                      あいうえかきくけ
                      任天堂
              </letter>
      </body>
</letter-list>
```

#### Code 4-1 sample.xllt

The root element of the text character filter is *letter-list*, and this filter contains only two elements: the *head* element defined by the NNSXML protocol and the *body* element. The *head* element and the incorporated elements are all defined by the NNSXML protocol, and therefore, they will not be explained. The *body* element incorporates the *letter* element, and the *letter* element contains all the

NTR-06-0370-001-A1 18 © 2004-2005 Nintendo



text characters that will be output. Note that blank-space text characters in the *letter* element (e.g., the half-width space and the tab characters) are ignored, and the letters that are output always include a half-width space. This information is described below in Table 4-1 Character Filter Definition Elements.

**Table 4-1 Character Filter Definition Elements** 

Element	Includable Elements	Description	
	Attribute		
letter-list	head, body	Defines the text character filter. This element is the root element of the	
	version (required)	character filter file. The required attribute version is specified currently as 1.0.	
letter	None	Defines the text characters in the NITRO font. Characters are specified	
	None	by entering the text characters you want to include directly.	

# 4.3 Document Type Definition

The Document Type Definition (DTD) describes the structural rules for an XML document. It is written as shown in Table 4-1 Character Filter Definition Elements. The DTD for the character filter file is shown in letter-list.dtd and is located in the same folder as fontcvtr.exe inside the xllt folder.

# 4.4 How to Use

See chapter 3.5 - Filter Specification to learn how to use character filter files.



# 5 Letter Order Files

### 5.1 Overview

The letter order file defines the text character order in the input and output of the BMP files by fontcvtr. The letter order file defines the number of text characters on the horizontal and vertical axis in the BMP image and also the order in which the characters are drawn. Since characters not defined in the letter order file are not output, this file can also operate as a character filter.

Letter order files are written in XML and named with the \*.xlor extension.

# 5.2 The Included Letter Order Files

fontcvtr comes with four letter order files (see Table 5-1). Except for the output text characters, these files share the same specifications. Text characters are output in the order of their character code with 16 characters on the horizontal axis.

Because a letter order file only specifies character codes, it cannot handle shape differences in characters for each font. For example, if a Japanese font is selected in the Windows Font tab as the input and cp1252.xlor is selected in the BMP tab for the letter order file as the output, then the yen sign (Y) will be output t even though backslashes should be output.

Table 5-1 Included Letter Order Files

Filename	Displayed by fontcvtr	Description
cp1252.xlor	European Language (CodePage 1252 / Latin-1)	Outputs alphanumeric and some European language characters. This file is called Windows code page 1252; it includes ISO 8859-1 (Latin-1) and all ASCII characters.
ds_ipl.xlor	DS-IPL font table	Outputs the same characters as the IPL font of the Nintendo DS. In addition to cp1252.xlor and JIS_X0201_X0208_01.xlor, it has a non-Unicode character region for pictographs.
JIS_X0201_X0208_01.xlor	Japanese Level 1 (JIS X 0208)	Outputs Japanese characters, including all level 1 kanji. This also includes half-width alphanumeric characters and half-width kana characters.
JIS_X0201_X0208_012.xlor	Japanese Level 1,2 (JIS X 0208)	Outputs level 2 kanji in addition to the level 1 kanji of JIS_X0201_X0208_01.xlor.

NTR-06-0370-001-A1 20 © 2004-2005 Nintendo



#### 5.3 Structure

As with character filter files, the XML structure of letter order files complies with the NNSXML protocol. Table 5-1 shows a section of the letter order file cp1252.xlor.

```
<?xml version="1.0" encoding="UTF-8" standalone="no" ?>
<!DOCTYPE letter-order SYSTEM "letter-order.dtd">
<letter-order version="1.0">
     <head>
             <create user="hatamoto minoru" date="2005-02-18T10:51:13" />
             <title>European Language (CodePage 1252 / Latin-1)</title>
             <comment>Windows Code ~(omitted)~ 8859-1 (Latin-1)./comment>
     </head>
     <body>
             <area width="16" />
             <order>
                    <sp/> ! &quot; # $ % &amp; &apos; ( ) * + , - . /
                    0 1 2 3 4 5 6 7 8 9 : ; < = &gt; ?
                    @ A B C D E F G H I J K L M N O
                    PQRSTUVWXYZ[¥]^
                    `abcdefghijklmno
                    pqrstuvwxyz{|}~<null/>
                    € <null/> ~(omitted)~ &#x00FE; &#x00FF;
             </order>
     </body>
</letter-order>
```

#### Code 5-1 cp1252.xlor

The root element in the letter order definition is *letter-order*, and this definition contains only two elements: the head element defined by the NNSXML protocol and the body element. The head element and incorporated elements are all defined by the NNSXML protocol, and therefore, they will not be explained. The body element incorporates the area element, and specifies the number of characters on the vertical and horizontal axis of the BMP image and the order element that specifies the drawing order of the characters.

The area element has no content but has two attributes: height and width; height and width define the number of characters on the vertical and horizontal axis. Both of these attributes can be omitted. When width is omitted, the default value is 16 text characters. When height is omitted, the default value is set so that all characters are output.

The order element arranges the text characters, and the same order is used to make the letter order in the BMP image. The first text character is placed in the upper-left corner of the BMP image, and the second text character follows immediately to the right. Using the specified letter order, his left-to-right order is used to position the rest of the text characters to fill the first line to the right edge of the BMP image and then moving to the second line. The blank-space characters (the half-width and the tab spaces) are ignored in the order element so you must use the sp element in order to output a half-width space. In addition, you can use the null element to skip ahead one space in the output. These different elements are listed in Table 5-2.



**Table 5-2 Letter Order Definition Elements** 

Element	Includable Elements	Description
	Attribute	
letter-order	head, body  version (required)	Defines the order of text characters. This element is the root element of the letter order file.  The required attribute <i>version</i> is presently specified as 1.0.
area	None  width (can be omitted)  height (can be omitted)	Defines the number of characters to output on the vertical and horizontal axis of the BMP image. The <i>width</i> attribute defines the number of characters on the horizontal axis. When it is omitted, the default value is 16 text characters. The <i>height</i> attribute defines the number of text characters on the horizontal axis. When it is omitted, the default value is set to output all characters specified in the <i>order</i> element.
order	sp, null None	Defines the output characters and output order. Specify text characters by arranging them in the output order. The same character should not appear more than once.
sp	None None	Specify a half-width space inside the <i>order</i> element. You need to use this element to output a half-width space because direct descriptions of half-width spaces are ignored.
null	None None	Specify no text character output. Provides a way to skip a character' space.

### 5.4 DTD

The DTD for the letter order file is letter-order.dtd and is located in the same folder as fontcvtr.exe, inside the xlor folder.

### 5.5 How to Use

When fontcvtr starts, it reads the files with the \*.xlor extension (xlor/\*.xlor) from the xlor folder (the same folder which contains fontcvtr.exe) and treats them as letter order files, showing the *title* element content in each file as a list item in **Glyph Order**. Therefore, in order to use a letter order file, you must give the file a \*.xlor extension and save it in the xlor folder.

If you start fontcvtr after adding a new letter order file to the xlor folder, the new file will appear as a list item in **Glyph Order**. If you select the newly added file for an input and output BMP file, the new letter order file will be used to input and output BMP files.

If the new letter order file fails to load at startup because of a syntax error or for another reason, the new file will not display in **Glyph Order** and cannot be used. The error message that displays will assist you in troubleshooting the problem in the file.



# 6 BMP Image Format

# 6.1 The Structure of BMP Images

The BMP images handled by fontcvtr have a block and cell structure. The BMP image comprises a grid of blocks, and each block comprises a cell. There are no spaces between blocks.

### 6.1.1 Block

The BMP image blocks are arranged without any spaces between the blocks. The number of blocks in the horizontal and vertical axes is defined in the letter order file (see Figure 6-1 Example of BMP Image (Number of Blocks: 16x9)

).





Figure 6-1 Example of BMP Image (Number of Blocks: 16x9)

Each block includes a cell and a width line. The block shown in Figure 6-2 has a width of 14 pixels and a height of 16 pixels. The thick solid line shows the boundaries of the block and the thin dashed lines show the boundaries of each pixel.





### Figure 6-2 Schematic Pattern Diagram of Block

#### 6.1.1.1 Grid Area

The border of 1-pixel squares around the inside of the block boundary is called the grid area. In Figure 6-2, this area is shaded in dark gray.

If **Draw Grid** has been checked,, grid area Fills with black when the BMP file is output, which makes **Draw Grid** look like there is a 2-pixel grid neighboring blocks. If **Draw Grid** is not checked, this grid area will be filled with white.

When BMP is input, this grid area is simply ignored.

#### 6.1.1.2 Margin Area

The 1-pixel squares around the inside of the grid area is called the margin area. This area is set so the grid and cell and width lines do not touch. There is also a 1-pixel margin area between the cell and the width line.

When the BMP file is output, if **Draw Grid** has been checked the margin area will be filled with dim green. If **Draw Grid** is not checked, this area will be filled with white.

When BMP is input, this area is checked to see if it is filled with a single color. A warning message will display if it is filled with more than two colors.

#### 6.1.1.3 Cell

The larger block contained by the margin area is called the cell. The glyph image is drawn in cell the area. Because the height of the width line is set to 1 pixel, the cell size follows:

Cell width = Block width - 4 pixels Cell height = Block height - 6 pixels

### 6.1.1.4 Width Line Region

The width line is the smaller area within the margin area and has a height of 1 pixel that extends horizontally. It defines the width of the text character and the relative location of the glyph image.

# 6.1.2 Cells and Width Lines

Figure 6-3(left) shows the pattern diagram of a width line area and a representative cell with a width of 10 pixels and a height of 10 pixels.

NTR-06-0370-001-A1 24 © 2004-2005 Nintendo






Figure 6-3 Schematic Patter Diagram of Cell and Width Line

#### 6.1.2.1 Glyph Image

The glyph image is the only thing placed inside the cell. fontcvtr searches inside the cell for the smallest rectangle that contains dots that are not white, and treats this as the glyph image. Thus, white parts around the glyph image are ignored and do not affect the output font. In Figure 6-3, the glyph image on the left outputs as the rectangular image on the right, with a width of 5 pixels and a height of 7 pixels.

If the glyph image is located in the same relative location as the width line, then it does not matter whether it is located on the left or right side of the cell. In both cases shown in Figure 6-4, the font will be output just like the font shown in Figure 6-3.




Figure 6-4 Left and Right Placement in Cell

#### **6.1.2.2** Width Line

A single line is drawn in the width line area. If the line is broken into two segments, an error will occur.

The width line prescribes both the width of the character and the width of the empty space to the left and right of the character.

Because the length of the width line defines the text character width, the text character width can be set to be narrower than the glyph image. When the text character width is reduced, the text character appears to overlap preceding text characters. The left text character shown in Figure 6-3 has a text character width of 7 pixels.



The left space width is the difference between the left end of the width line and the left edge of the glyph image. When text characters are drawn with the Character Drawing Library, the glyphs are drawn with a spacing equal to this left space width. The left text character shown in Figure 6-3 has a 1 pixel left space width; therefore, when the text character is drawn, the glyph is drawn with a 5 pixel width and is shifted by 1 pixel to the right from the specified coordinate.

Like the left space width, the right space width is the difference between the right end of the width line and the right edge of the glyph image. The right text character shown in Figure 6-3 has a right space width of 1 pixel.

### 6.1.2.3 Glyphs With NoOutput

If the cell contains nothing but white dots and the width line is 0, then the glyph is not passed to output. This method can be used to control glyph output without using a text character filter. However, if a text character is specified but not passed to output, a warning message displays.

#### 6.1.3 Baseline




Figure 6-5 Position of Baseline

As shown in Figure 6-5, the BMP image includes 1 pixel that indicates the baseline position. This point is located on the left side of the grid area in this block and appears in white if the grid is drawn and black if the grid is not drawn. The upper boundary of this pixel defines the baseline position. In other words, the baseline is the space between pixels. The baseline is in the same position in the BMP image in all blocks.

The font height is the total of the highest ascender and lowest descender from the baseline for a particular font. For example, the font height for the two characters shown in Figure 6-6 is 9 pixels.






Figure 6-6 Font Height

#### 6.2 BMP Fonts that Are Output

fontcvtr outputs an index color BMP with 8 bits per pixel (256 colors).

The BMP color palette is output as gray scale from white to black in the gradation levels of the font. For example, if the font has a four-level gradation, the color palette is created with the values set in the following order: 0xFFFFFF, 0xAAAAAA, 0x555555, and 0x000000. The output for the color that will be used to fill margins follows the gradation levels.

#### 6.3 **BMP Fonts that Can Be Input**

For input fontcvtr accepts index color BMP with 1, 4, or 8 bits per pixel (2, 16, or 256 colors). Additional requirements include:

Block width \* number of blocks in horizontal direction = BMP width Block height \* number of blocks in vertical direction = BMP height

In other words, there must be no spaces between blocks in the BMP and no margins.

In actuality, the number of blocks on the horizontal axis is determined by the letter order file, and the BMP width (height) is determined by the BMP file. The block width and height are calculated once these values have been determined. Both the width and the height must be integer values.

fontcvtr ignores all color information contained in the BMP file. The only relevant color information is the color index, and when the BMP image is read, the color index is passed on as-is by the glyph image contained in the NITRO font. To get the same BMP image output on the Nintendo DS, you must draw the text characters using a color palette with the same colors and order as the color palette of the BMP image. The exception is white; when the BMP is read, white is replaced by the 0th color of the color index. fontcvtr treats white as a transparent color, whereas with the Nintendo DS, the 0th color of the color index displays a transparent color.



# 7 Precautions

# 7.1 Precautions About Converting Windows Fonts

Both Windows 2000 and XP have automatic font linking, which automatically displays text characters in another font when the text characters are unsupported. For example, Tahoma font ,which is a standard font in Windows 2000 and XP does not support Japanese characters. But you can still display Japanese characters in Notepad even when Tahoma is set as the default font. The feature is useful for normal PC applications, but be careful about unlicensed fonts accidentally appearing in your game software.

This risk can be avoided because fontcvtr disables the automatic font linking feature and only outputs text characters included in the specified font. As a result, a font that does not support Japanese like Tahoma will not output the text characters correctly.

# 7.2 Unicode Inside fontcvtr

fontcvtr uses Unicode for the internal processing of character codes, and cannot handle text characters not supported by Unicode. Windows features are used to convert the various types of encoding; therefore, the process must follow Windows conversion rules. Although the JIS character code 0x8160 for "~" is defined in Unicode as U+301C, because the Windows convention defines it as U+FF5E, fontcvtr handles it as U+FF5E. Table 7-1 shows the character code conversions that fontcvtr generates for the various inputs and outputs.

Table 7-1 Places Where Character Codes are Converted

Place	Description of Conversion Process
Input BMP	References the letter order file and allocates from cell position to Unicode.
Input NITRO	Converts from the encoding stored in NITRO font to Unicode.
Input Windows	Outputs characters in Unicode from U+0000 to U+FFFF.
Input LC	Converts from Shift_JIS to Unicode.
Output BMP	References the letter order file and allocates from Unicode to cell position.
Output NITRO	Converts from Unicode to specified encoding.
Character Filter file	Converts to Unicode when loaded.
Letter Order file	Converts to Unicode when loaded.



# 7.3 Precautions when Describing Letter Order File

If you create a letter order file that specifies the same text character multiple times and run the conversion process with BMP as the input source, only the glyph for one of the assigned cells will be read, and the glyphs in the rest of the cells will be ignored. This situation can cause a bug that is difficult to pinpoint—even rewriting the glyph in the ignored cell will not reflect the change in the font.

To help you find duplicate cells, fontcvtr displays a warning message if the same text character appears more than once in the letter order file and has a different glyph for each occurrence. To avoid these problems, try not to define the same character multiple times in the letter order file.

## 7.4 Unicode in the Letter Order File

Because fontcvtr uses Unicode for internal processing, the text characters in the letter order file are also converted internally with Unicode. If the conversion involves a non-Unicode character set, text characters that have been assigned different character codes will be assigned a single Unicode character code. For example, each of the nine characters in Table 7-2 are assigned two different Shift\_JIS character codes for use with Windows, but when they are converted into Unicode, each is assigned just a single Unicode character code.

Even though all the character codes in the letter order file might appear to be different, sometimes the font will not reflect the changes made to the glyph in a cell. Because all occurrences of the same text character are grouped and assigned a single Unicode value, all the glyphs for that text character become the same glyph. You can avoid this by using single characters once.

fontcvtr displays a warning message when the same character is specified more than once in the letter order file, but the warning is displayed after the Unicode conversion. Thus, the warning will be displayed even in the case described above.

Table 7-2 The 2:1 Relationship of Characters Converted from Shift\_JIS to Unicode

Character	Character Code Normally	Shift_JIS Character Codes in Machine-	Unicode
	Used by Shift_JIS	Dependent Character Region	
U	0x81BE	0x879C	U+222A
Λ	0x81BF	0x879B	U+2229
_	0x81DA	0x8797	U+2220
Τ	0x81DB	0x8796	U+22A5
=	0x81DF	0x8791	U+2261
≒	0x81E0	0x8790	U+2252
$\checkmark$	0x81E3	0x8795	U+221A
:	0x81E6	0x879A	U+2235
ſ	0x81E7	0x8792	U+222B



# 8 Warning and Error Messages

# 8.1 Warning Messages

Table 8-1 lists the warning messages displayed by fontcvtr. In addition to the messages in this table, fontcvtr will also display an error message if it fails to read the letter order file at startup.

The warnings only indicate a possible problem, so fontcvtr will continue the conversion process.

**Table 8-1 Explanation of Warning Messages** 

Warning message	Explanation
A character ('{character}': U+{character code}) included in the Filter is not included in the INPUT font.	{Character} is specified for output in the character filter but is not present in the font at input. For this reason, the character output will not be included.
A character code ('{character}': U+{character code}) has multiple glyphs. Second and later glyphs are ignored.	{Character} corresponds to more than one glyph. All glyphs after the first are ignored. The cause is multiple definitions for the same character it the letter order file. For details, see chapter 7.3 Precautions when Describing Letter Order File.
BMP position ({coordinate x}, {coordinate y}) is <null></null> in {Letter Order file's path}, but the cell includes non-white color.	The BMP cell with the specified coordinates is <null></null> in the letter order file, but has a non-white color. The drawing of the glyph might protrude.
Can't represent output character('{character}': U+{character code }) in the specified character set.	{Character} could not be represented with the specified encoding so it was not output. To output {Character} you need to use some other encoding.
More than one color detected in margin area at ({coordinate x}, {coordinate y}).	Two or more colors were detected in the margin of the cell with the coordinates in the BMP. The drawing of the glyph might protrude.

# 8.2 Error Messages

The error messages displayed by fontcvtr can be divided into five categories. Table 8-2 lists the error categories and **Error! Reference source not found.** explains the error messages that are not part of the Internal Error category. In **Error! Reference source not found.**, the text enclosed in brackets is replaced in the actual error messages.

When an error occurs, the conversion process stops and there is no output.

NTR-06-0370-001-A1 30 © 2004-2005 Nintendo



**Table 8-2 Explanation of Error Categories** 

Error category	Description	
BMP Error	Error in a file specified as a BMP file.	
NFTR Error	Error in a file specified as a NITRO font file.	
XML Error	Error in a file specified as an XML file (Letter Order file, Character Filter file).	
Parameter Error	Errors due to some other invalid input parameter.	
Internal Error	These errors usually do not occur. They indicate that there might be a bug in fontcvtr.	

**Table 8-3 Descriptions of Error Messages** 

Error message	Description
BMP Error:	The BMP does not contain baseline information.
BMP has no baseline info.	For details, see chapter 6 - BMP Image Format.
BMP Error:  BMP height ({BMP height}) is not a multiple of vertical number of blocks ({Number of blocks in vertical direction})	The height of the BMP image is not multiples of the number of vertical blocks specified in the letter order file.  For details, see chapter 6 BMP Image Format.
BMP Error:	The height of the BMP image is too small.
BMP height ({BMP height}) too small. Must be >= {Min. value of BMP in vertical direction}	For details, see chapter 6 - BMP Image Format.
BMP Error:  BMP width ({BMP width}) is not multiply of horizontal number of blocks ({Number of blocks in horizontal direction})	The width of the BMP image is not multiples of the number of horizontal blocks specified in the letter order file.  For details, see chapter 6 BMP Image Format.
BMP Error:	The width of the BMP image is too small.
BMP width ({BMP width}) too small. Must be >= ({Min. value of BMP in horizontal direction})	For details, see chapter 6 - BMP Image Format.
BMP Error:  Two or more width line found at ({Coordinate x}, {Coordinate y})	The width line of the cell in the mentioned coordinates is broken into two or more line segments.  For details, see chapter 6 - BMP Image Format.
BMP Error: Unsupported BMP bpp ({BMP's bpp}).	The bpp (bits per pixel) value for the BMP image is not supported.
	fontcvtr supports only 1, 4, and 8 bpp.
BMP Error:	There is no white color in the BMP image.
Color white not found in BMP.	fontcvtr treats white as transparent color, so the BMP image must include the color white.
Can not open a file ({File path}).	The file cannot be opened. Check to see that the displayed file path is correct.
Can not read from a file ({File path}).	Cannot read the file. Some other application might have locked the file.



Error message	Description
Can not write to a file ({File path}).	The file cannot be written to. Some other application might have locked the file.
Input file ({File path}) has illegal image size({BMP data size} (expect {Expected BMP data size})).	The image data stored in the BMP file is an illegal size. The BMP file might be corrupt or the file might not be a BMP file.
Input file ({File path}) has illegal image size ({BMPwidth} x {BMP height}).	The image stored in the BMP file has an illegal width and height size. The BMP file might be corrupt or the file might not be a BMP file.
Input file ({File path}) has unsupported bpp ({BMP's bpp}).	The BMP file does not have a valid bpp (bits per pixel) value. The BMP file might be corrupt or the file might not be a BMP file.
Input file ({File path}) is not bmp file.	The file that has been specified as a BMP file is not a BMP file.
Input file ({File path}) is unsupported BMP.	The specified BMP file is in a format that fontcvtr cannot handle.
	fontcvtr does not support compressed BMP and BMP that has multiple planes.
NFTR File Error:	The NITRO font file's byte order mark indicates big-endian.
Little-endian byte order support only	fontcvtr supports only little-endian order. The NITRO font file might be corrupt or the file might not be a NITRO font file.
NFTR File Error:	The file specified as a NITRO font file is not a NITRO font
The file is not NFTR file	file.
NFTR File Error:	The NITRO font file has an invalid header size.
Unknown header size (={File's header size}, must be {Correct header size})	The NITRO font file might be corrupt or the file might not be a NITRO font file.
NFTR File Error:	This is an unsupported version of Nitro font.
Unsupported version (={File version}, supports {Supported version})	
NFTR File Error:	The NITRO font file has an invalid number of blocks. The
Number of blocks is too small (={Number of data blocks in file})	NITRO font file might be corrupt or the file might not be a NITRO font file.
NFTR File Error:	The NITRO font includes a character that cannot be
Can't represent input character (0x{Character code}) in the Unicode character set.	represented by Unicode.
	fontcvtr cannot handle characters that cannot be represented by Unicode. The problem might instead be that the character code table in the NITRO font is different from the current local character set.
Parameter Error:	An LC Font file has not been specified.
	1



Error message	Description
Parameter Error:  Can't represent AlternateChar ('{Alternate character}':  U+{Unicode character code of alternate character}) in the local character set.	The character specified as the alternate character cannot be represented by the local character code. Output the NITRO font in Unicode, or specify an alternate character.
Please use Unicode character set or other AlternateChar.	
Parameter Error:	The character specified as the alternate character is not
Can't represent AlternateChar (0x{Character code of alternate character}) in the Unicode character set.	included in Unicode.  fontcvtr cannot handle characters that cannot be represented
Please use other AlternateChar.	by Unicode. Specify an alternate character.
Parameter Error:  DefaultLeftSpace (={Input value}) out of range[-128 ~ 127]	The default left-space width exceeds the range that can be specified. The value should be set between -128 and 127.
Parameter Error:  DefaultWidth (={Input value}) out of range [{Min. value} ~ {Max. value}]	The default character width exceeds the range that can be specified. The value should be set between {Min. value} and {Max. value}.
Parameter Error:  DefaultRightSpace (={Input value}) out of range [{Min. value} ~ {Max. value}]	The default right-space width exceeds the range that can be specified. The value should be set between {Min. value} and {Max. value}.
Parameter Error: Directory ({Directory path}) not exists.	The path specified for the input file or for the output file does not exist.
Parameter Error: File not specified	No file has been specified.
Parameter Error: File ({File path}) not exists.	The specified file does not exist. Check that the path is correct.
Parameter Error: Invalid Font Size ({Specified font size})	An invalid font size has been specified.
Parameter Error: Invalid alternate character (0x0000)	0x0000 cannot be specified for the alternate character.
Parameter Error: Invalid fixed width ({Specified character width})	An invalid monospace character width has been specified.
Parameter Error: LineHeight (={Specified value}) out of range [0 - 255]	An invalid line height has been specified. The value should be set between 0 and 255.
Parameter Error:  Max glyph width (={Glyph width}) over 255.	The glyph width exceeds 255 pixels. It must be no larger than 255 pixels.
Parameter Error:  Max char width (={Character width}) over 255.	The character width exceeds 255 pixels. It must be no larger than 255 pixels.
Parameter Error: Font height (={Font height}) over 255.	The font height exceeds 255 pixels. It must be no larger than 255 pixels.



Error message	Description
Parameter Error:	The baseline position exceeds 127 pixels. It should be set
Baseline position (={Baseline position}) over 127.	between -128 and 127.
Parameter Error:	The baseline position is set below -128 pixels. It should be
Baseline position (={Baseline position }) under -128.	set between -128 and 127.
Parameter Error: No glyphs in output.	There are no glyphs for output. Either there were no characters in the input source or all characters in the input source have been filtered out. Here are two possible reasons: (1) the system was configured to output only Japanese characters using a Western font, or (2) the characters in the letter order file are completely different from the characters in the character filter file.
Parameter Error:	The specified alternate character is not included in the font.
Specified AlternateChar ('{ Specified alternate character}' : {Character code (local)}) is not included in the Font	The character specified as the alternate character must be part of the font being output.
Parameter Error:	The specified alternate character is not included in the font.
Specified AlternateChar ('{Specified alternate character}' : {Character code (Unicode)}) is not included in the Font	The character specified as the alternate character must be part of the font being output.
Parameter Error:	The file specified for output has been configured as a read-
Specified file ({File path}) is read only.	only file, so data cannot be written to it.
Parameter Error:	A directory was specified where a file should have been
Specified path ({File path}) indicates directory.	specified.
Parameter Error:	The specified filter file does not exit. Check the path to see if
Filter file ({File path}) not exists	it is correct.
Parameter Error:	The file that was specified as a LC Font file is not an LC Font
Input file ({File path}) is not LC Font file.	file.
Parameter Error:	The cell width must be specified as a value larger than 0.
Cell Width (={Specified value}) must be > 0.	
Parameter Error:	The cell height must be specified as a value larger than 0
Cell Height (={Specified value}) must be => 0.	
Parameter Error:	The cell's left margin must be specified as a value of 0 or
Cell Margin Left (={Specified value}) must be => 0.	larger.
Parameter Error:	The cell's right margin must be specified as a value of 0 or
Cell Margin Right (={Specified value}) must be => 0.	larger.
Parameter Error:	The top margin of the cell must be specified as a value of 0 or larger.
Cell Margin Top (={Specified value}) must be => 0.	
Parameter Error:	The bottom margin of the cell must be specified as a value of
Cell Margin Bottom (={Specified value}) must be => 0.	0 or larger.
Parameter Error:	No Letter Order file has been selected.
Order file is not selected.	



Error message	Description
Parameter Error:	Use Filter has been checked, but no path has been entered
"Use Filter" checked, but filter file path not specified.	for the Character Filter file.
Parameter Error:	No encoding has been selected for the NITRO font that will
Output encoding is not selected	be output.
XML Error:	This is an invalid Character Filter file.
Invalid filter file	
XML Error:	This is an invalid Letter Order file.
Invalid order file.	
XML Error:	An invalid height has been specified by the Letter Order file.
Invalid order height (={The height specified in the Letter Order file}).	
XML Error:	An invalid width has been specified by the Letter Order file.
Invalid order width (={The width specified in the Letter Order file}).	





This converter uses software developed by Apache Software Foundation (http://www.apache.org/)

The Apache Software License, Version 1.1

Copyright (c) 1999 The Apache Software Foundation. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment: "This product includes software developed by the Apache Software Foundation (http://www.apache.org/)." Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear.
- 4. The names "Xerces" and "Apache Software Foundation" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org.
- 5. Products derived from this software may not be called "Apache", nor may "Apache" appear in their name, without prior written permission of the Apache Software Foundation.

THIS SOFTWARE IS PROVIDED "AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES: LOSS OF USE, DATA, OR PROFITS: OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation and was originally based on software copyright (c) 1999,

International Business Machines, Inc., http://www.ibm.com.

For more, information on the Apache Software Foundation, please see <a href="http://www.apache.org/">http://www.apache.org/</a>.



Microsoft and Windows are registered trademarks or trademarks of Microsoft Corporation in the U.S. and other countries.

LC Font is a registered trademark of Sharp Corp.

All other company names and product names in this document are the registered trademarks or trademarks of those companies.

### © 2005 Nintendo

The contents of this document cannot be duplicated, copied, reprinted, transferred, distributed or loaned in whole or in part without the prior approval of Nintendo Co. Ltd.