Chapter 1

Code generation

1.1 Stack machines

A stack machine uses only a stack as storage. When executing an instruction $r = F(a_1, \ldots, a_n)$, it pops n operands from the stack, computes the operation F using the operands, and pushes the result r back on the stack. For example, when computing 7+5, the stack will change from s-7-5 to s-12.

Consider two instructions: push i (push integer i on the stack) and add (add two integers). Then we have the program to computer 7 + 5:

push 7 push 5 add

An important property of stack machines is that location of the operands/result is not explicitly stated because they are always at the top of the stack. This is different from register machine in which the locations have to be specified. We have add instead of $add \, r_1, r_2, r_3$, which produces more compact programs. This is one of the reasons why JAVA bytecodes uses stack evaluation.

Stack machine produces compact programs, but register machine executes faster. There is an intermediate point between the two kinds of machines called an **n-register stack machine**. As the name reveals, the top n positions of the pure stack machine's stack are held in registers. It turns out that even one single register can provide considerable performance improvement, which is the case of **1-register stack machine**. The resgister is called the **accumulator**.

In a pure stack machine, an add does 3 memory operations: two reads and one write. But in a 1-register stack machine, what add does is $acc \leftarrow acc + top_of_stack$. In general, consider an arbitrary expression $op(e_1, \ldots, e_n)$. For each subexpression $e_i(1 \le i \le n-1)$, we will compute e_i , store the result in acc and then push the result on the stack. For e_n , we will have its result remain in acc. Then we will pop n-1 values from the stack to compute op, and store the result in acc. If we follow this procedure, obviously after evaluating an

expression e, acc holds the value of e, and the stack is unchanged. In other words, **expression evaluation preserves the stack.**

Consider the calculation of 3 + (7 + 5). We will have the following process:

Code	Acc	Stack
$acc \leftarrow 3$	3	<init $>$
push acc	3	3,<init $>$
$acc \leftarrow 7$	7	3,<init $>$
push acc	7	7,3,<init $>$
$acc \leftarrow 5$	5	7,3,<init $>$
$acc\leftarrow acc + top_of_stack$	12	7,3,<init $>$
pop	12	3,<init $>$
$acc\leftarrow acc + top_of_stack$	15	3,<init $>$
pop	15	<init $>$

1.2 Basic MIPS instructions

In our discussion of code generation, we will focus on generating code for a stack machine with accumulator. The resulting code should be able to run on an MIPS processor (or simulator). Thus we have to simulate stack machine instructions using MIPS instructions and registers.

We choose to keep the accumulator in MIPS register \$a0. The stack is kept in memory and grows towards lower addresses, which is a standard convention in MIPS. The address of the next location on the stack is kept in MIPS register \$sp (which stands for stack pointer), and the top of the stack is at address \$sp ± 4

MIPS is an old structure with a relatively simple instruction set (prototypical reduced instruction set computer, or RISC). Most MIPS operations use registers for operands and results. Load and store instructions are used to move values to and from memory. There are 32 general purpose registers (32 bits each) in MIPS, and we will use only \$a0, \$sp and \$t1 (temp register used for operations that take two arguments).

Here are the first set of MIPS instructions that we introduce.

```
lw reg1 offset(reg2): Load 32-bit word from address reg2 + offset into reg1.
sw reg1 offset(reg2): Store 32-bit word in reg1 at address reg2 + offset.
add reg1 reg2 reg3: reg1 ← reg2 + reg3
addiu reg1 reg2 imm: reg1 ← reg2 + imm. u means that overflow is not checked.
li reg imm: reg ← imm.
move reg1 reg2 reg1 ← reg2.
```

The stack machine code for 7 + 5 is:

1.3 Code generation for a simple language

In this section we will take a look at code generation for higher level languages rather than a simple stack machine in the previous section.

Condiser a language for integer operations. Its grammar depicts a list of function definitions:

```
\begin{split} \mathsf{P} &\to \mathsf{D}; \, \mathsf{P} \mid \mathsf{D} \\ \mathsf{D} &\to \mathsf{def} \; \mathsf{id}(\mathsf{ARGS}) = \mathsf{E}; \\ \mathsf{ARGS} &\to \mathsf{id}, \, \mathsf{ARGS} \mid \mathsf{id} \\ \mathsf{E} &\to \mathsf{int} \mid \mathsf{id} \mid \mathsf{if} \, \mathsf{E}_1 = \mathsf{E}_2 \; \mathsf{then} \; \mathsf{E}_3 \; \mathsf{else} \; \mathsf{E}_4 \mid \mathsf{E}_1 + \mathsf{E}_2 \mid \mathsf{E}_1 - \mathsf{E}_2 \mid \mathsf{id}(\mathsf{E}_1, \dots, \mathsf{E}_n) \end{split}
```

The first function definition f is the entry point, i.e. the main routine. This language is enough to write a program that computes the Fibonacci numbers:

$$\begin{aligned} \text{def fib}(x) &= \text{if } x = 1 \text{ then } 0 \text{ else} \\ &\quad \text{if } x = 2 \text{ then } 1 \text{ else} \\ &\quad \text{fib}(x - 1) + \text{fib}(x - 2) \end{aligned}$$

For each expression e, we want to generate MIPS code that **computers the** value of e in \$a0 and preserves \$sp and the content of the stack. We will define a function cgen(e) whose return value if the code generated for e.

1.3.1 Constants

For constants, we need to simply load it into the accumulator:

$$cgen(i) = li $a0 i$$

1.3.2 Addition

For addition:

```
cgen(e1 + e2) =
    cgen(e1)
    sw $a0 0($sp)
    addiu $sp $sp -4
    cgen(e2)
    lw $t1 4($sp)
    add $a0 $t1 $a0
    addiu $sp $sp 4
```

Here we use different colors to emphasize the fact that MIPS code is **generated** at compile time and **executed** at run time. Code in red color is what happens at compile time: the generation, while code in black is what happens at run time: the execution. More precisely, we should write sw \$a0 0(\$sp) as something like print sw \$a0 0(\$sp), which indicates that the MIPS code is generated at compile time and saved somewhere, maybe in an intermediate file, and does not get executed until run time.

It seems that the piece of code above could be optimized: why don't we save the value of e1 directly in \$t1, rather than saving it in the memory and then retrieve it into \$t1? The code will look like:

```
cgen(e1 + e2) = cgen(e1)

move $t1 $a0

cgen(e2)

add $a0 $t1 $a0
```

Unfortunately, this neat piece of code is wrong. We can convince ourselves by simply condisering the code generated for 1 + (2 + 3). In short, the value of \$t1 will be modified during cgen(e2), and is no longer the value of e1 when the execution comes to add \$a0 \$t1 \$a0.

The simple example of code generation for addition demonstrates a few universal properties of code generation. The code generated for e1 + e2 is a template with "holes" for code generated to evaluate e1 and e2. Stack machine code generation is actually recursive. The code generation process can be written as a recursive descent of the AST, at least for expressions.

1.3.3 Subtration

By introducing another MIPS instruction sub:

```
sub reg1 reg2 reg3 reg1\leftarrowreg2 - reg3
```

we can generate the code for e1 - e2:

```
cgen(e1 - e2) =
    cgen(e1)
    sw $a0 0($sp)
    addiu $sp $sp -4
    cgen(e2)
    lw $t1 4($sp)
    sub $a0 $t1 $a0
    addiu $sp $sp 4
```

1.3.4 If-then-else

In order to generate code for if-then-else expressions, we need to introduce a couple of new instructions:

```
\mathbf{beq} \ \mathbf{reg1} \ \mathbf{reg2} \ \mathbf{label} \ \mathbf{branch} \ \mathbf{to} \ \mathbf{label} \ \mathbf{if} \ \mathbf{reg1} = \mathbf{reg2}
```

b label Unconditional jump to label

1.3.5 Function calls & definitions, variable references

Code for function calls and function definitions depends on the layout of the activation record, thus they need to be designed together. For this simple language, a very simple AR is sufficient.

• Since the result is always in the accumulator, there is no need to store the result in AR.

- The AR should hold the actual parameters, thus for $f(x_1, \ldots, x_n)$, we need to push x_n, \ldots, x_1 on the stack. These are the only variables in this language.
- The stack discipline guarantees that \$sp is preserved after a function call. Thus there is no need for a control link: the previous activation can be found directly; and we do not need to look at another activation during the function call because there is no non-local variable.
- We need the return address.
- A pointer to the **current** activation is useful. It lives in register \$fp (frame pointer).

To summarize, for this simple language, an AR will contain the caller's frame pointer, the actual parameters and the return address. The caller's frame pointer should be contained because f will be probably overwritten during the execution of the function (by other functions called during the execution). Consider a call to f(x, y). Before its body gets executed, its AR looks like Figure 1.1.




Figure 1.1: AR of f(x,y)

The **calling sequence** is the instructions (of both the caller and the callee) to set up a function invocation. Here we introduce a new instruction

jal label Jump to label, and save the address of the next instruction in \$ra (meaning return address). jal means jump and link.

Now we can actually generate the code for function call expressions.

```
cgen(f(e1,e2,...,en)) =
   sw $fp 0($sp)
   addiu $sp $sp -4
   cgen(en)
   sw $a0 0($sp)
   addiu $sp $sp -4
   ...
   cgen(e1)
   sw $a0 0($sp)
   addiu $sp $sp -4
   jal f_entry
```

For f(e1,e2,...,en), we first save the frame pointer of the caller, then save the arguments one by one (from en to e1). Up to now we've completed the calling sequence on the caller side. Next we can use jal to jump to the entry point of function f. The return address is now in \$ra. The AR so far is 4*n+4 bytes long.

We introduce another instruction

jr reg Jump to the address in register reg.

Now we can discuss the callee side of the calling sequence.

```
cgen(def f(x1,x2,...,xn) = e) =
  f_entry:
    move $fp $sp
    sw $ra 0($sp)
    addiu $sp $sp -4
    cgen(e)
    lw $ra 4($sp)
    addiu $sp $sp 4n + 8
    lw $fp 0($sp)
    ir $ra
```

First we set up the frame pointer by saving the current stack pointer into \$fp. Then the return address is saved in memory. Now we can generate code for the function body. The stack pointer will be reserved, thus we can load the return address back into \$ra. Next we can pop the return address, all arguments and the old fp out of the stack (totally 4*n+8 bytes). We restore the value of the old fp, and finally jump back to the return address.

Variables in this language are just the function arguments. They are all pushed into the AR by the caller. But since the stack grows when intermediate results are saved, the variables are not at fixed offsets from \$sp. That's when \$fp should be used. The offset of xi from \$fp is 4*i. Thus we can generate the code for variable reference.

$$cgen(xi) = lw $a0 4*i($fp)$$

1.3.6 **Summary**

To summarize, the AR must be designed together with the code generator. Code generation can be completed by a recursive traversal of the AST. Such an approach using a stack machine is a wise choice to implement the COOL code generator.

Production compilers are for sure different from the example here. They emphasize keeping values in registers, especially the current stack frame, for the code to run faster. Also, intermediate results are laid out in the AR rather than pushed and popped from the stack.

1.3.7 Example

In this section we will generate code for the following example program:

```
sumto_entry:
  move $fp $sp
                      //set up frame pointer
  sw $ra $sp
                      //return address
  addiu $sp $sp -4
  lw $a0 4($fp)
                      //start generation for if-then-else. load x from AR.
  sw $a0 0($sp)
                      //save value of x (1st arg of comparison)
  addiu $sp $sp -4
  li $a0 0
                      //immediately load 0
  lw $t1 4($sp)
                      //load x (1st arg of comparison) into $t1
  addiu $sp $sp 4
                      //pop x
  beg $t1 $a0 true1
                      //compare and branch
false1:
  lw $a0 4($fp)
                      //load x from AR
  sw $a0 0($sp)
                      //save value of x (1st arg of addition)
  addiu $sp $sp -4
  sw $fp 0($sp)
                      //save frame pointer of caller
  addiu $sp $sp -4
```

```
lw $a0 4($fp)
                      //load x from AR
  sw $a0 0($sp)
                      //save value of x (1st arg of subtraction)
  addiu $sp $sp -4
  li $a0 1
                      //immediately load 1
  lw $t1 4($sp)
                      //load x (1st arg of subtraction into $t1)
  sub $a0 $t1 $a0
                      //subtraction
  addiu $sp $sp 4
                      //pop x
  sw $a0 0($sp)
                      //save value of x-1 (arg of sumto(x-1))
  addiu $sp $sp -4
 jal sumto_entry
                      //jump and link
  lw $t1 4($sp)
                      //load x (1st arf of addition) into $t1
  add $a0 $t1 $a0
                      //addition (x+sumto(x-1))
  addiu $sp $sp 4
                      //pop x. up to now finished x+sumto(x-1)
  b end_if1
true1:
  li $a0 0
                      //immediately load 0
end_if1
                      //up to now finished if-then-else
  lw $ra 4($sp)
                      //load return address
  addiu $sp $sp 12
                      //pop ra, argument(x) and old fp
  lw $fp 0($sp)
                      //restore old fp
  jr $ra
```

1.4 Temporaries