

Configure event collection from NagiosXI

- Release version: Australia
-
- Updated March 12, 2026
-
- ⌚ 3 minutes to read

Configure the NagiosXI connector instance to receive events from the Nagios Core monitor.

Before you begin

Supported version: 5.5.2.

The NagiosXI connector instance requires a credential that lets the instance access NagiosXI accounts. You can use an existing credential or create a new one. For more information, see [Create Nagios XI server credentials](#).

Role required: evt_mgmt_admin

Procedure

1. Navigate to All > Event Management > Integrations > Connector Instances.
2. Click New.
3. On the form, fill in the fields.

Field	Description
Name	Descriptive name for the Nagios connector.
Description	Description for the use of the NagiosXI event collection instance.
Host IP	Specify the Nagios XI IP address.
Credential	Select the credential with basic authentication that you created for this connector. For more information, see Create Nagios XI server credentials . Ensure that the user password contains the NagiosXI user API key, for example 04lquEPqf4JimWCm8RWbJokOpW8LYBUfEvJp9OSHSRYe4QDrHPFndYbWcCHapBpk.
Event collection last run time	The last run time value is automatically updated.

Field	Description
Last event collection status	The last run time status is automatically updated.
Event collection schedule (seconds)	The frequency, in seconds, that the system checks for new events from Nagios. The default value is 120 seconds.
Last error message	The last error message is automatically updated.
Connector Definition	Select NagiosXI.
MID Servers (MID Server for Connectors section)	Optional. Name of a MID Server. If no MID Server is specified, an available MID Server that has a matching IP range is used. In the MID Servers for Connectors section, specify a MID Server that is up and valid. You can configure several MID Servers. If the first is down, the next MID Server is used. If that MID Server is not available, the next is selected, and so on. MID Servers are sorted according to the order that their details were entered into the MID Server for Connectors section.

4. Right-click the form header and select Save.

The connector instance values are added to the form and the parameters that are relevant to the connector appear.

5. In the Connector Instance Values section, specify the Nagios values.

- `initial_sync_in_days`. Specify the number of days for which events must be collected at the first collection cycle. Default value 7 days.
- `port`. Default value 80.
- `protocol`. The default protocol type is `http`.
- `time_zone`. The default time zone is `GMT`; update this value to the Nagios timezone. For example, if Nagios is sending the events according to the EDT time zone, update this value to `GMT-04:00` (abbreviations such as EDT are not supported).
- `severity_by_state_type`. The default value is `false`. When set to `true`, the `state_type` is used along with the `state` to determine the severity which creates less critical events as shown in the following mapping table.

Table 1. Mapping Table

<code>_state_type</code> (Connector definition parameter)	State (Nagios JSON payload attribute)	State_type (Nagios JSON payload attribute)	ServiceNow Severity
false	2	0/1	1 (Critical)
false	1	1	1(Critical)

_state_type(Connector definition parameter)	State (Nagios JSON payload attribute)	State_type (Nagios JSON payload attribute)	ServiceNow Severity
false	1	0	2(Major)
false	0	0/1	5(OK)
true	0	0/1	5(OK)
true	1	0	4 (Warning-soft -> Warning)
true	2	0	2(Critical-soft -> Major)
true	3	0	4(Unknown-soft-> Warning)
true	1	1	3(Warning-hard -> Minor)
true	2	1	1(Critical-hard -> Critical)
true	3	1	3(Unknown-hard -> Minor)

6. Right-click the form header and select Save.

7. Click Test Connector to verify the connection between the MID Server and the connector.

8. If the test fails, follow the instructions that the error issues to correct the problem and then run another test.

If this message appears: `Connection test failed: Failed to connect to Nagios on test connector. Invalid API Key`, then enter the API Key for the specific user to be able to read the Nagios events.

Note:

Use a network tool, such as ping, to verify credential correctness and network connectivity from the MID Server to the Nagios Core monitor.

9. After a successful test, select the Active check box and then click Update.

- **Create Nagios XI server credentials**

Create credentials to access Nagios XI server.