batch script language manual

by hank (or yupeng)*

Version 1.0

December 3, 2011

Contents

1	\mathbf{sum}	mary
2	how	to install
	2.1	Download the source code
	2.2	Build from source code
	2.3	Run a crash session
	2.4	Use the "extend" command load batch.so file to crash
	2.5	Write a script to test whether it can work \hdots
3	\mathbf{The}	syntax of batch script
	3.1	variable
	3.2	loop
	3.3	if
	3.4	$comment \dots \dots$
4	buil	d in function
	4.1	call
	4.2	get
	4.3	lines
	4.4	len
	4.5	generic math calculate and logic function

1 summary

You can find crash here:

[&]quot;batch" is a crash extension.

^{*}If you have any question or advice, you can send email to one of these address: pyu@redhat.com or yupeng0921@gmail.com

```
http://people.redhat.com/anderson/crash_whitepaper
```

"batch" is an interpreter. It give crash the ability to run script. It support a C like style script language. Generally you can call a crash command, and store the command output to a variable. Then get a part of the command output, transfer it to another crash command. For example, you know a super_block address is "ffff81087d829400", and you want to know the gendisk address corresponding to the super block. First, you should find the block device address:

```
\begin{array}{lll} crash> \ struct \ super\_block.s\_bdev \ ffff81087d829400 \\ s \ bdev = 0xffff81087e1fbb80 \ , \end{array}
```

Then, you find the gendisk from the block device:

```
\begin{array}{lll} crash> \ struct & block\_device.bd\_disk & 0xffff81087e1fbb80 \\ bd & disk & = 0xffff81087f70e400 \ , \end{array}
```

Use batch, you can write it as a script:

"call" and "get" are buildin functions. "cmd", "callret", and "getret" are variables, and their type are string. Transfer a string to "call" function, it will exectute it as a crash command, and return the crash command output as a string. In our example, we set the cmd variable to a string:

```
cmd = "struct super block.s bdev " + "ffff81087d829400";
```

It will set the "cmd" varaible to string:

```
"struct super block.s bdev ffff81087d829400"
```

Then run the "call" function:

```
callret = call(cmd);
```

It will run the crash command:

```
struct super block.s bdev ffff81087d829400
```

And store the output to variable "callret". So after run that line, the value of "callret" will be:

```
" s bdev = 0xffff81087e1fbb80, "
```

"get" function can get a substring of a string. It has 4 parameters, the first one is the input string, the second one specify which lines of the string, as the string may has many lines. The third parameter specify we get the substring from which characters on that line, and the fourth parameter specify how many characters we want to get.

So this line:

```
getret = get(callret, 0, 11, 18);
```

means we get the first line (0 means first line, 1 means second line, and so on), from the 11th character, and get total 18 characters.

The "callret" variable only has one line, that is line 0. Its 11th character is "0", from that character, we get 18 characters, the result will be:

"0xffff81087e1fbb80"

It will be store to "getret" variable.

This line will print the string in variable getret:

```
print getret;
```

The "print" function can print a string or number to screen.

2 how to install

2.1 Download the source code

2.2 Build from source code.

Here is an article explain how to build a crash extention:

http://people.redhat.com/anderson/crash_whitepaper/#SHARED_LIBRARY Generall, if you run crash on a x86 64 system, you can run:

gcc -nostartfiles -shared -rdynamic -o batch.so batchcmd.c -fPIC -DX86_64 -D_FIL

2.3 Run a crash session

crash vmcore vmlinux

2.4 Use the "extend" command load batch.so file to crash

copy the "batch.so" file to the current directory of crash session, then use the "extend" command load the "batch.so" file.

```
crash> extend batch.so
./batch.so: shared object loaded
```

2.5 Write a script to test whether it can work

For example, you create a file named "test.cr", and write one line to that file: print "hello world";

Then call "batch" command, and pass the script file name as parameter:

```
crash> batch test.cr
hello world
```

3 The syntax of batch script

The batch script is a very simple C-like language, each statement stop with a ';'.

3.1 variable

Identifiers for variables are alphanumeric sequences, and may include the underscore (_) characters. They may not start with a plain digit. The batch script support two kind of variable, the "long" type and the "string" type.

Create a "long" type variable:

```
a_long_variable = 10;
Create a "string" type variable:
a_string_variable = "hello world";
```

3.2 loop

```
general syntax:
while (exp) stmt
   example:
count = 0;
total = 0;
while (count < 10) {
        total = total + count;
        count = count + 1;
}</pre>
```

Note: until now, the loop don't support "break" or "continue".

3.3 if

3.4 comment

Both of "#" and "//" are OK.

4 build in function

4.1 call

```
prototype
c all:string(command name:string)
```

The "call" function need a string type parameter, then run this string as a crash command. The return value of "call" function is a string, it is the output of the crash command.

example:

```
a = call("sys");
```

After run the "call" function, the output of the crash "sys" will be store in variable "a". It may be something like this:

```
KERNEL: vmlinux
    DUMPFILE: localhost vmcore [PARTIAL DUMP]
        CPUS: 16
        DATE: Tue Nov 1 19:22:45 2011
      UPTIME: 28 days, 00:48:26
LOAD AVERAGE: 1.11, 1.11, 1.12
       TASKS: 886
   NODENAME: localhost
     RELEASE: 2.6.18 - 194.26.1. el5
     VERSION: #1 SMP Fri Oct 29 14:21:16 EDT 2010
     MACHINE: x86 64
                      (2266 \text{ Mhz})
      MEMORY: 63.1 GB
       PANIC: "SysRq : Trigger a crashdump"
                         COMMAND: "bash"
         PID: 24446
        TASK: ffff810cf4b33820
                                [THREAD INFO: ffff810da301e000]
         CPU: 8
       STATE: TASK RUNNING (SYSRQ)
```

4.2 get

```
prototype
```

```
get:string(command output:string, lines:long, start:long, len:long)
```

The "get" function can return a substring of an input string. Generally, it is used to get a part of a crash command's output. "command_output" is a string, "lines" specific which line of the string. "start" is specific we get the

substring from which characters on the specific line, "len" specific we get how many characters. If "len" is -1, means get until the end of this line.

example:

```
a = call("sys");

b = get(a, 4, 14, 23);
```

Thus, the string "Tue Nov 1 19:22:45 2011" will be stored in variable b.

4.3 lines

prototype

```
lines:long(command_output:string)
```

Input a string, then return how many lines the string contains.

4.4 len

prototype

```
len:long(command output:string)
```

Return the length of the input string.

4.5 generic math calculate and logic function