Manual of plotastrodata

Yusuke Aso

1 Read Data

The data class AstroData can take a fits file.

```
from plotastrodata.analysis_utils import AstroData
d = AstroData(fitsimage='file_name.fits')
```

AstroData can take more arguments, such as Tb and sigma. Tb=True means the data values will be converted from flux densities in the unit of Jy beam⁻¹ to brightness temperatures in the unit of K. sigma specifies how to measure the noise level of the data values: for example, the default option of 'hist' means to use the histgram of the data values. The argument of pvpa is the position angle of the PV cut direction in the unit of degree, which will be used to calculate the spatial resolution of the PV diagram.

The data class AstroFrame is necessary to form the AstroData instance in a useful format. AstroFrame can take quantities related to coordinate ranges.

vmin, vmax, and vsys are in the unit of km s⁻¹. rmax is in the unit of arcsec. Instead of rmax, other arguments (xmin, xmax, ymin, ymax, xoff, yoff) can be used to adjust the x and y ranges in more detail. When an argument of fitsimage is given, the central coordinates center is read from the given fits file; the rest frequency is also read from the fits file, which is used for the frequency-velocity conversion. Moreover, an argument of dist can specifies the distance used to change the unit of spatial coordinates from arcsec to au. An argument of swapxy is used to swap the x and y coordinates. An argument of pv must be True when the AstroData instance to be read is a position-velocity (PV) diagram, i.e., the first and second axes are the spatial and velocity coordinates. When quadrants=True, the first and third (or second and fourth) quadrants of the PV diagram will be averaged. xflip and yflip will be used to determine the plotting direction of the x and y axes, respectively; these have a meaning only when a figure is made from the data set.

Forming the AstroData instance needs the following command.

```
f.read(d)
```

After this command, the AstroData instance has useful attributes in the format of numpy array: a 1D array of d.x (as well as d.y and d.v), a 2D or 3D array of d.data, a 1D array of d.beam, and a float of d.sigma. d.x and d.y are the relative coordinates in the unit of arcsec from the

given center. Similarly, d.v is the relative coordinate in the unit of km s⁻¹ from the given vsys. d.beam is the beam components array([bmaj, bmin, bpa]), where bmaj and bmin are in the unit of arcsec, while bpa is in the unit of degree. When Tb=True above, the data values are converted to the brightness temperature and stored as d.data. d.sigma is the noise level measured in the way specified above in the same unit as d.data. AstroData can take two more arguments, restfreq and cfactor. restfreq is used to explicitly set the rest frequency in the unit of Hz, which is used to convert frequency to velocity and Jy beam⁻¹ to K. When this argument is zero (restfreq=0), the frequency axis is not converted to velocity. When the unit of the frequency/velocity axis in the input fits header is m/s, f.read(d) divides the coordinate by 1000. The argument cfactor specifies a constant factor that d.data is multiplied by. This will be useful when one wants to change the intensity unit from Jy beam⁻¹ to mJy beam⁻¹.

In addition to the input attributes, f.read(d) adds three attributes to the AstroData instance d: fitsimage_org, sigma_org, and fitsheader. fitsimage_org saves the input fitsimage, while fitsimage is updated to None after f.read(d). Similarly, sigma_org saves the input sigma, which may be a string, while sigma is updated to the calculated value. fitsheader is the fits header in the format of astropy.io.fits.open(fitsimage)[0].

When pv=True in AstroFrame, the read method changes the beam attribute of the AstroData instance. The first element will be the velocity resolution. The second element of beam will be $1/\sqrt{\cos^2(\mathrm{bpa}-\mathrm{pvpa})/\mathrm{bmaj}^2+\sin^2(\mathrm{bpa}-\mathrm{pvpa})/\mathrm{bmin}^2}$. This is calculated from the intersection of the beam ellipse and the PV cut line. The third element will be 0. The original beam will be stored in beam_org.

2 Analyze Data

AstroData also has handy methods to analyze the 2D/3D data.

The binning method rebins the 2D/3D data with a given width for each coordinate.

```
d.binning(width=[5, 4, 2])
```

This command takes an average over 5 channels in the velocity direction, 4 pixels in the y direction, and 2 pixels in the x direction. The number of channels and pixels are decreased accordingly after this method. If the length of width is 2, the two values are regarded as the widths for the y and x directions.

The centering method sets the coordinates so that the spatial center and the systemic velocity have the exact zero coordinates by interpolation.

```
d.centering(includexy=True, includev=False)
```

This command adjusts the x and y coordinates but does not adjust the velocity coordinate. This method will be useful when one wants to quickly get a radial profile along a line passing the center or a PV diagram (using the rotate method together).

The circularbeam method makes the beam shape circular by additional 2D Gaussian convolution. This method takes no argument.

```
d.circularbeam()
```

The new beam has the major and minor axes same as the old major axis. This method also updates the attribute of d.beam accordingly.

The deproject method deprojects the 2D/3D data with a given position angle (P.A.) and inclination angle.

```
d.deproject(pa=45, incl=45)
```

pa is the position angle from the north to the east in the unit of degree. incl is the inclination angle; incl=0 means the face-on configuration and thus no deprojection. This command replaces d.data and d.beam with the deprojected data and the deprojected beam, respectively.

The fit2d method performs MCMC fitting to the 2D image of d.data or d.data[chan], where chan is the channel number, by using emcee or ptemcee through the class of plotastrodata.fitting_utils.EmceeCorner.

model is a function with the shape of model(par, x, y), where par is the list of parameters. bounds is the 2D list of the parameter boundary in the shape of $[[p_{0,\min},p_{1,\min},...],[p_{0,\max},p_{1,\max},...]]$ kwargs_fit and kwargs_plotcorner are the arguments for the methods of EmceeCorner.fit and EmceeCorner.plotcorner, respectively. nsteps includes the number the burn-in steps. The output res is a dictionary consisting of popt, plow, pmid, phigh, model, and residual. The first four keys provide the best, lower percentile, 50 percentile, and higher percentile parameters. The last two keys provide the model and residual 2D images.

The histogram method returns the bins and the histogram in the bins of the attribute of d.data by using numpy.histogram().

```
hbin, hist = d.histogram(bins=10)
```

The arguments are the same as those for numpy.histogram(). The bins (hbin) have the same length as the histogram (hist), which is different from the original numpy.histogram.

The gaussfit2d method performs the 2D Gaussian fitting to the 2D image of d.data or d.data[chan], where chan is the channel number, by using scipy.optimize.curve_fit.

```
res = d.gaussfit2d(chan=12)
```

This command performs the fitting to the channel of 12 in d.data. For 2D data, the chan argument can be omitted. The output (res here) is a dictionary having keys of popt, pcov, model, and residual. popt and pcov are the optimized parameters (peak intensity, central x, central y, major FWHM, minor FWHM, and P.A.) and their covariance. The model and residual are 2D arrays with the same shape of the fitted 2D array.

The mask method puts numpy nan on pixels that satisfies a given condition.

```
d.mask(dataformask=d2.data, includepix=[1e-3, 100], excludepix=[50, 200])
```

This command puts numpy.nan on pixels of d.data where d2.data is outside [1e-3, 100] or inside [50, 200], where d2 is an AstroData instance different from d. This method will be useful when one wants to put a mask on a moment 1 map using the values of a moment 0 map.

The profile method makes line profiles at given spatial positions.

```
v, f, g = d.profile(xlist=[-0.5, 0.2], ylist=[1, 0.8], ellipse=[0.3, 0.2, 45])
```

This command makes line profiles at (x,y)=(-0.5,1) and (0.2,0.8) in the unit of arcsec. The intensity of each profile is an average over a boxcar ellipse with the major axis of 0.3 arcsec, the minor axis of 0.2 arcsec, and the P.A. of 45 degrees. Instead of xlist and ylist, coordinate strings can be input using an argument of coords: coords=['00h00m00.0s 00d00m00.0s', '11h11m11.1s 11d11m11.1s']. When ellipse is omitted, the profile is made by picking up the values at the closest pixel to the given position. When the ellipse size is not so large compared to the pixel size, the integer argument ninterp may be useful; this makes the pixel size ninterp times finer by interpolartion. When the boolian argument flux is True, the output profile has the unit of Jy. Additionally, when the boolian argument gaussfit is True, the profiles will be fitted with a 1D Gaussian function. The output v above is d.v. The output f above is a list of 1D-array profiles, i.e., 2D array. The output g is a list of dictionaries; each dictionary has keys of best and error (square root of the diagonal components of the covarience).

The rotate method rotates the attribute d.data by the given angle in the unit of degrees by interpolation.

```
d.rotate(pa=45)
```

When a pixel refers to a position outside the original image, this pixel has numpy.nan after this method.

The slice method makes a radial profile for a 2D image or a PV diagram for a 3D image along a given direction and length by interpolation.

```
r, f = d.slice(length=3, pa=45, dx=0.2)
```

This commands makes a radial profile (or PV diagram) along a cut with a length of 3 arcsec at P.A.=45 degrees with a separation of 0.2 arcsec. The output r and f are both 1D arrays of the positional offsets and the intensity at the positions. When the separation dx is omitted, the absolute value of the x pixel size is adopted.

The todict method returns the attributes as a dictionary.

```
a = d.todict()
```

This output includes keys of data, x, y, v, fitsimage, beam, Tb, restfreq, cfactor, sigma, and center. This dictionary can be input to methods of PlotAstroData as **a.

The writetofits method exports the instance as a fits file.

```
d.writetofits(fitsimage='new_file_name.fits')
```

The output fits file reuses the header components of the fits file used to make the AstroData instance ('file_name.fits' above); some header components are updated properly after the above-mentioned methods for analysis, such as CDELT1.

3 Plot Data

The class PlotAstroData can take an AstroData instance through the method of d.todict().

```
from plotastrodata.plot_utils import PlotAstroData

p = PlotAstroData(rmax=3.0)
p.add_color(**d.todict())
```

```
p.add_scalebar(length=50 / 140, label='50 au')
p.set_axis()
p.savefig('figure_name.png')
```

These commands make a color map using the AstroData instance d. PlotAstroData can take the same arguments as AstroFrame to define the plotting ranges; particularly rmax is necessary. The method p.add_color() can take a fits file directly instead of the AstroData instance, as p.add_color(fitsimage='file_name.fits'). This method can actually take the same arguments as AstroData to specify the data to be plotted as a color map; **d.todict() does this indirectly. The command p.add_scalebar() can be omitted if the map does not need to show a scale bar. The command p.set_axis() (or p.set_axis_radec()) is necessary even without any argument. More detailed usage can be found in the example.py file and https://plotastrodata.readthedocs.io/en/latest/#. The following is the explanation of each method (each type of maps).

The add_color method plots the given data in the format of a color map.

The stretch argument can be 'linear', 'log', 'asinh', or 'power'. The Arcsin hyperbolic stretch can be adjusted by another argument of stretchscale as asinh(data / stretchscale). The power-law stretch can be adjusted by another argument of stretchpower as ((data / vmin)^(1 - stretchpower) - 1) / (1 - stretchpower) / ln(10), where vmin is a given minimum value. The arguments starting with 'cb' adjust the colorbar. In addition, two arguments, xskip and yskip, can be used to skip spatial pixels in this method as well as add_contour, add_segment, and add_rgb. Similarly, show_beam and beamcolor can be used in these four methods.

The add_contour method plots the given data in the format of a contour map.

```
p.add_contour(**d.todict(), levels=[-3, 3, 6, 9])
```

The levels argument spedifies the contour levels in the unit of d.sigma.

The add_rgb method plots the given data in the format of three-color maps. The input three data sets are mixed as Red, Green, and Blue.

```
p.add_rgb(**d.todict(), stretch=['linear', 'log', 'linear'])
```

For this method, the input is a combination of three data sets, and thus d.data here must be a list of three numpy arrays. In the same way as add_color, stretchscale and stretchpower are available in this method.

The add_segment method plots the given data in the format of a segment map, as is often used for polarization maps.

The input format of the data is different from that for add_color and add_contour. One of the following pairs must be given: (ampfits, angfits), (Qfits, Ufits), (amp, ang), or (stQ, stU). The latter two pairs are supposed to be in the numpy.array format. The ampfactor argument can be used to adjust the segment length. When angonly=True, the segment length is set to be uniform. The rotation can be used to rotate the segments in the unit of degrees. The cutoff argument specifies the intensity threshold to calculate the amplitude and angle from the Stokes Q and U intensities.