Discussion 2: Threads, I/O

February 3, 2023

Contents

1	'hreads	2
	1 pthreads Party	2
2	/0	4
	.1 Concept Check	ϵ
	2 File Descriptor Fun	7
	3 Echo Server	

1 Threads

Threads are single unique execution contexts with their own set of registers and stack. Threads are sometimes referred to as "lightweight processes".

Thread Control Block

Components that are shared between threads in the same process (e.g. heap, global variables) do not need to be persisted by each individual thread. However, each thread still needs to persist its registers and stack in the **thread control block (TCB)**.

Syscalls

POSIX defines a pthread library which consists of syscalls for threads similar to the process syscalls.

Starts a new thread in the calling process. The thread starts execution by invoking start_routine that takes in arg as its sole argument.

```
void pthread_exit(void *retval)
```

Terminates the calling thread and stores a value in retval that is available to another thread in the same process that joins. Similar to how a return from main will implicitly call exit for processes, a return from start_routine will implicitly call pthread_exit.

```
int pthread_yield(void)
```

Calling thread relinquishes the CPU and is put at the end of the run queue.

```
int pthread_join(pthread_t thread, void **retval)
```

Calling thread waits for thread to terminate. For a non-NULL retval, the exit status of thread (i.e. the one from pthread_exit) is made available in retval.

1.1 pthreads Party

1. What are the possible outputs of the following program? How can you change the program to make it print "HELPER" before "MAIN"?

```
void *helper(void *arg) {
printf("HELPER");
return NULL;
}
int main() {
pthread_t thread;
pthread_create(&thread, NULL, &helper, NULL);
pthread_yield();
printf("MAIN");
return 0;
}
```

 $pthread_order.c$

```
print MAIN or output morbe MAINHEIPER or HELPERMAIA

Yield does not guarantee helper will finish
```

change line 8 to pthread_join (thread, NULL

2. What does the following program print?

```
void *helper(void *arg) {
  int *num = (int*) arg;
  *num = 2;
  return NULL;
  }
  int main() {
  int i = 0;
  pthread_t thread;
  pthread_create(&thread, NULL, &helper, &i);
  pthread_join(thread, NULL);
  printf("i is %d", i);
  return 0;
}
```

pthread_stack.c

i is \(\) threads (an alless each other's stock since they share same address space

3. What does the following program print?

```
void *helper(void *arg) {
    char *message = (char *) arg;
    strcpy(message, "I am the helper");
    return NULL;
5 }
6 int main() {
  char *message = malloc(100);
    strcpy(message, "I am the main");
    pthread_t thread;
10
    pthread_create(&thread, NULL, &helper, message);
    printf("%s", message);
11
    pthread_join(thread, NULL);
12
   return 0;
13
14 }
```

pthread_heap.c

I'm the main or I'm the helpst
join is called after the prints

2 I/O

The operating system must be able to interface with a wide variety of **input/output** (I/O) devices including but not limited to keyboard, mouse, disk, USB port, WiFi. While there are many different types of devices, POSIX unifies all of them behind a single common interface.

Design Philosophy

POSIX has a set of design philosophies that define the standard for UNIX-based operating systems.

Uniformity

All I/O is regularized behind a single common interface under the idea that "everything is a file". This means all I/O (e.g. file operations, interprocess communications) use the same set of syscalls: open, close, read, write.

Open Before Use

Before any I/O operation, the "device" must be opened before using. This allows the operating system to perform various checks (e.g. access control permissions) and bookkeeping of metadata. For instance, a device might only be allowed to be opened by one application.

Byte Oriented

All data from devices are addressed in bytes even for devices with different block sizes.

Kernel Buffered Read/Writes

Data from devices are stored in a kernel buffer and returned to the application on request. Similarly, outgoing data is stored in a kernel buffer until the device is ready to be written to. Kernel buffering allows for same interface between devices with different read block sizes and different write speeds.

Explicit Close

An application must explicitly call close when it's done with the device. Similar to open, this allows the operating system to perform bookkeeping and garbage collection.

Low-Level API

Low-level API operates directly with file descriptors which are indices into a file descriptor table (FDT). Each process has its own FDT stored in kernel memory, where each entry points to a file description which represents an open file or device and keeps track of metadata (e.g. offset position). This means that the same file descriptor can correspond to different file descriptions across different processes.

Specifically, file descriptors 0, 1, and 2 are initialized to standard input (stdin), standard output (stdout), and standard error (stderr), respectively. However, they can be redefined (see dup and dup2).

Select methods from the low-level API are listed below. All low-level methods are syscalls, meaning they occur entirely in kernel space.

int open(const char* pathname, int flags)

Opens a file specified by pathname with access control permissions flags. Returns a file descriptor or -1 on an error.

int close(int fd)

Closes a file descriptor, so that it no longer refers to any file and may be reused. If fd is the last file descriptor referring to the file description, the resources associated with the open file description are freed. Returns 0 on success or -1 on an error.

ssize_t read(int fd, void *buf, size_t count)

Attempts to read up to count bytes from file descriptor fd into the buffer starting at buf. Returns the number of bytes read on success or -1 on an error.

ssize_t write(int fd, const void *buf, size_t count)

Attempts to write count bytes to file descriptor fd from the buffer starting at buf. Returns number of bytes written on success or -1 on an error.

off_t lseek(int fd, off_t offset, int whence)

Repositions the file offset of the open file description associated with the file descriptor fd to the argument offset according to the directive whence.

int dup(int oldfd)

Allocates the next available file descriptor to point to the same file description as oldfd.

int dup2(int oldfd, newfd)

Same as dup but with a specific file descriptor newfd.

A particular note about read and write is that these methods are not guaranteed to fully succeed, meaning read and write might read and write less bytes than specified. However, this isn't considered an error.

High-Level API

High-level API operates on **streams** of data, which are unformatted sequences of bytes with a position. Streams can encompass any data type from raw binaries to text. An open stream is represented by a pointer to FILE, which contain information pertaining to an open stream such as the file descriptor. For example, FILE *stdout, and FILE* stderr respectively correspond to file descriptors 0, 1, and 2.

High-level API buffers data in *user memory* in larger chunks (e.g. 1024 bytes). This is different from the kernel buffered philosophy since not every invocation of the high-level API requires a syscall. For instance, a fread with size = 100 will still fetch the data in a larger chunk (e.g. 1024 bytes), meaning there will not be a syscall when fread is called a second time with size = 100.

Select methods from the high-level API are listed below.

FILE *fopen(const char *pathname, const char *mode)

Opens the file associated with pathname and associates a stream with it. Returns a FILE * or NULL on an error.

int fclose(FILE *stream)

Flushes the stream pointed to by **stream** and closes the underlying file descriptor. Returns 0 on success or **EOF** on an error.

int fread(void *ptr, size_t size, size_t nmemb, FILE *stream)

Reads nmemb items of data, each size bytes long, from the stream pointed to by stream, storing them at the location given by ptr. Return the number of *items* read.

```
int fwrite(void *ptr, size_t size, size_t nmemb, FILE *stream)
```

Writes nmemb items of data, each size bytes long, to the stream pointed to by stream, obtaining them from the location given by ptr. Returns the number of *items* written.

int fflush(FILE *stream)

Forces a write of all data in the user space buffer to stream.

```
int fprintf(FILE *stream, const char *format, ...)
```

Prints to stream according to format.

```
int fscanf(FILE *stream, const char *format, ...)
```

Scans from stream according to format.

Contrary to read and write, fread and fwrite guarantee that they will read and write the specified amount. If fread and fwrite return an amount less than the specified amount, it is considered an error.

In general, high-level APIs provide a more expressive way of interacting with devices. For instance, fprintf allows printing with a specific format whereas write can only write raw sequences of bytes. There are also

different API methods defined for character-oriented devices (e.g. fputc) and block-oriented devices (e.g. fread).

Interprocess Communication

In theory, processes can communicate using files, where one process writes to a file and another reads from a file. However, this is a painfully slow process due to the overhead of disk speeds. **Interprocess communication (IPC)** provide mechanisms to communicate between processes to manage shared data. Oftentimes, this communication will be facilitated using memory instead of disk.

Pipes are one-way communication channels between processes on the same physical machine. A pipe can be thought of as a single queue where you can read from one end and write to another. When opened, each end of the queue corresponds to its own file descriptor. You can use the int pipe(int pipedfd[2]) syscall to create a pipe.

Sockets are two-way communication channels between processes. These processes can be on the same or different machines. Sockets can be thought of as using two queues, one in each direction.

For a connection to to be established, the server needs to be able to accept a request connection from the client. The steps to do this are

- 1. Create server socket using socket syscall.
- 2. Bind the server socket to a specific address using bind syscall.
- 3. Start listening for connections using listen syscall.

Once these steps succeed, the server can accept new connections using the accept syscall. When the client wants to make a connection request, it sends a 5-Tuple that uniquely identifies a connection. In the 5-Tuple are

- 1. Source IP Address
- 2. Destination IP Address
- 3. Source Port Number
- 4. Destination Port Number
- 5. Protocol (e.g. TCP)

2.1 Concept Check

1. What's the difference between fopen and open?

2. What will the test.txt file look like after this program is run? You may assume read and write fully succeed (i.e. read/write the specified number of bytes).

For reference, SEEK_SET will set the offset to offset bytes, while SEEK_CUR will set the offset to its current location plus offset bytes. Seeking past the end of a file will set the bytes to 0.

```
int main() {
char buffer[200];
memset(buffer, 'a', 200);
int fd = open("test.txt", O_CREAT|O_RDWR);
write(fd, buffer, 200);
lseek(fd, 0, SEEK_SET);
read(fd, buffer, 100);
```

```
8 lseek(fd, 500, SEEK_CUR);
9 write(fd, buffer, 100);
10 }
```

lseek_test.c

```
test, txf will contain 200 a and 400 NULL and then 100 a
```

2.2 File Descriptor Fun

1. Consider a method that copies n bytes from src file to dest file. You may assume both files are already created, and src is at most 100 bytes long. This method has been written in two different ways, one using the high-level API and low-level API.

```
void copy_high(const char* src, const char* dest) {
    char buffer[100];
    FILE* rf = fopen(src, "r");
    int buf_size = fread(buffer, 1, sizeof(buffer), rf);
    fclose(rf);
    FILE* wf = fopen(dest, "w");
    fwrite(buffer, 1, buf_size, wf);
    fclose(wf);
9 }
10
void copy_low(const char* src, const char* dest) {
    char buffer[100];
    int rfd = open(src, O_RDONLY);
    int buf_size = 0;
    while ((bytes_read = read(rfd, &buffer[buf_size], sizeof(buffer) - buf_size)) > 0)
      buf_size += bytes_read;
16
    close(rfd);
18
    int bytes_written = 0;
19
    int wfd = open(dest, O_WRONLY);
    while (bytes_written < buf_size)</pre>
      bytes_written += write(wfd, &buffer[bytes_written], buf_size - bytes_written);
22
    close(wfd);
24
25 }
```

copy.c

What is the purpose of the while loops in copy_low?

```
open only operates bytes, while loop is used to read bytes

one by one read and write are not quoranteed to read

2. What does the following program print to standard output? and write the specified

int main(int argc, char **argv) {

int fd;

if ((fd = open("out.txt", O_CREAT|O_TRUNC|O_WRONLY, 0644)) < 0)

need to while loop

7 to make Sure desired

Number of bytes are re-
```

```
4    exit(1);
5
6    printf("The last digit of pi is ...");
7    fflush(stdout);
8
9    dup2(fd, 1);
10    printf("five");
11    exit(0);
12 }
```

dup_pi.c

```
The last digit of pi is ... \five fluch replace 1 (stdout) with out the so five will go to out that
```

2.3 Echo Server

Consider a server implementation that echoes back the bytes that the client sent. Each connection needs to be handled in its own thread. Threads should be allowed to handle connections concurrently. For simplicity, assume read and write do not return short.

```
#define BUF_SIZE 1024
3 struct addrinfo* setup_address(char* port) {
    struct addrinfo* server;
    struct addrinfo hints;
    memset(&hints, 0, sizeof(hints));
    hints.ai_family = AF_UNSPEC;
    hints.ai_socktype = SOCK_STREAM;
    hints.ai_flags = AI_PASSIVE;
9
10
    int rv = getaddrinfo(NULL, port, &hints, &server);
11
12
    if (rv != 0) {
      printf("getaddrinfo failed: %s\n", gai_strerror(rv));
14
      return NULL;
15
    }
16
    return server;
17 }
18
19 void* serve_client(void* client_socket_arg) {
    int client_socket = (int) client_socket_arg;
    char buf[BUF_SIZE];
21
    ssize_t n;
22
23
    while ((n = read(client_socket, buf, BUF_SIZE)) > 0) {
24
      buf [n] = ' \setminus 0';
25
      printf("Client Sent: %s\n", buf);
26
      28
29
          _pthyeud__exit(NUU)
30
31
32
                                - cluse c client-socket)
```

```
35 }
36
  int main(int argc, char** argv) {
37
    if (argc < 2) {
      printf("Usage: %s <port>\n", argv[0]);
39
      return 1;
40
41
42
    struct addrinfo* server = setup_address(argv[1]);
43
    if (server == NULL)
      return 1;
    int server_socket = $\int \text{lkf} \text{server->ai_family, server->ai_socktype, server->ai_protocol);}
46
    if (server_socket == -1)
47
     return 1;
48
    if (black (server_socket, server->ai_addr, server->ai_addrlen) == -1)
49
      return 1;
50
    if ( | server_socket, 1) == -1)
51
      return 1;
52
53
    while (1) {
      int connection_socket = accept(server_socket, NULL, NULL);
55
      if (connection_socket == -1)
56
        pthread_exit(NULL);
     59
60
61
62
      pthread_detach(handler_thread);
63
    }
64
65 }
```

echo_server.c

1. What are the first three steps that a server needs to perform to be able to accept new connections? Specify the specific syscalls that need to be used.

```
socket bind listen
```

2. What function should each thread start at (i.e. start_routine argument in pthread_create)?

```
serve_client
```

3. What should the server do when it's finished with a client according to POSIX design philosophies?

```
close Cunneltium socket
```

4. What are the dangers of this approach compared to making a new process for each connection?

```
each connection could attack the sent because each connection is handled in the same process
```