Virtual Memory II


CSE 351 Spring 2019

Instructor:

Ruth Anderson

Teaching Assistants:

Gavin Cai
Jack Eggleston
John Feltrup
Britt Henderson
Richard Jiang
Jack Skalitzky
Sophie Tian
Connie Wang
Sam Wolfson
Casey Xing
Chin Yeoh



WHY EVERYTHING I HAVE IS BROKEN


https://xkcd.com/1495/

Administrivia

- Homework 4, due TONIGHT Wed (5/22) NO LATES
 - Structs, Caches
- Lab 4, due Fri (5/24)
 - Lab 4 Pre-Lab quiz is due Fri 5/24 NO LATES
- Homework 5, coming soon!
 - Processes and Virtual Memory




Page hit: VM reference is in physical memory



CSE351, Spring 2019

Page Fault

Page fault: VM reference is NOT in physical memory




Page Fault Exception

This is a fixable error: just have to move this page from disk into main memory first!

- User writes to memory location
- That portion (page) of user's memory is currently on disk

```
int a[1000];
int main ()
{
    a[500] = 13;
}
```


```
80483b7: c7 05 10 9d 04 08 0d movl $0xd,0x8049d10
```



- Page fault handler must load page into physical memory
- Returns to faulting instruction: mov is executed again!
 - Successful on second try

Handling a Page Fault


Page miss causes page fault (an exception)



PP 3


Handling a Page Fault

- Page miss causes page fault (an exception)
- Page fault handler selects a victim to be evicted (here VP 4)




Handling a Page Fault

- Page miss causes page fault (an exception)
- Page fault handler selects a victim to be evicted (here VP 4)



Handling a Page Fault

- Page miss causes page fault (an exception)
- Page fault handler selects a victim to be evicted (here VP 4)
- Offending instruction is restarted: page hit!
 e.g. from slide 7, restart the move operation!



Peer Instruction Question

- How many bits wide are the following fields?

$$p = 14 \text{ bits}$$

- 16 KiB pages p = 14 bits VPO =PPO so both these take up 14 bits. But the Virtual address space may be larger than the physical address space n = 48 bits Circle VPO =PPO so both these take up 14 bits. But the Virtual address space may be larger than the physical address space n = 48 bits Circle VPO =PPO so both these take up 14 bits. But the Virtual address space may be larger than the physical address space n = 48 bits Circle Virtual memory n = 34 bits TiB virtual memory n = 34 bits
- Vote at: http://pollev.com/rea

	VPN	PPN
(A)	34	24
(B)	32	18
(C)	30	20
(D)	34	20

VPN =
$$n-p=34$$
 bits $\iff 2^{34}$ pages in virtual address space
PPN = $m-p=20$ bits $\iff 2^{20}$ pages in physical address space


PPN =
$$m - \rho = 20bAs \longleftrightarrow 2^{20}$$
 pages in physical address space

Virtual Memory (VM)

- Overview and motivation
- VM as a tool for caching
- Address translation
- VM as a tool for memory management
- VM as a tool for memory protection

VM for Managing Multiple Processes

- Key abstraction: each process has its own virtual address space
 - It can view memory as a simple linear array (e.g. seems like data is contiguous)
- With virtual memory, this simple linear virtual address space need not be contiguous in physical memory
 - Process needs to store data in another VP? Just map it to any PP!



Simplifying Linking and Loading

Linking

- Each program has similar virtual address space
- Code, Data, and Heap always start at the same addresses


Loading

- execve allocates virtual pages
 for .text and .data sections
 & creates PTEs marked as invalid
- The .text and .data sections are copied, page by page, on demand by the virtual memory system
 0x400000

Memory invisible to Kernel virtual memory user code User stack (created at runtime) %rsp (stack pointer) Memory-mapped region for shared libraries brk Run-time heap (created by malloc) Read/write segment Loaded (.data, .bss) from the executable Read-only segment file (.init, .text, .rodata) Unused

VM for Protection and Sharing

- The mapping of VPs to PPs provides a simple mechanism to protect memory and to share memory between processes
 - Sharing: map virtual pages in separate address spaces to the same physical page (here: PP 6)
 - Protection: process can't access physical pages to which none of its virtual pages are mapped (here: Process 2 can't access PP 2)




Memory Protection Within Process

VM implements read/write/execute permissions

Extend page table entries with permission bits (management

MMU checks these permission bits on every memory access

 If violated, raises exception and OS sends SIGSEGV signal to process (segmentation fault)




Review Question

What should the permission bits be for pages from the following sections of virtual memory?


	Section	Read	Write	Execute	
	Stack	1	1	0	
static in size	Неар	1	1_	0	
	→Static Data	1		\bigcirc	
	Literals	1	O (constants)	0	
	Instructions	1	O (don't atter)	1 (only instruction should be exact	ions duble

Address Translation: Page Hit (page does live in physical mom)



- 1) Processor sends virtual address to MMU (memory management unit)
- 2-3) MMU fetches PTE from page table in cache/memory (Uses PTBR to find beginning of page table for current process)
- 4) MMU sends physical address to cache/memory requesting data
- 5) Cache/memory sends data to processor

Address Translation: Page Fault (page is NOT in physical mem)



- 1) Processor sends virtual address to MMU
- 2-3) MMU fetches PTE from page table in cache/memory
- 4) Valid bit is zero, so MMU triggers page fault exception
- 5) Handler identifies victim (and, if dirty, pages it out to disk)
- 6) Handler pages in new page and updates PTE in memory
- 7) Handler returns to original process, restarting faulting instruction

Hmm... Translation Sounds Slow

- The MMU accesses memory twice: once to get the PTE for translation, and then again for the actual memory request
 - The PTEs may be cached in L1 like any other memory word
 - But they may be evicted by other data references
 - And a hit in the L1 cache still requires 1-3 cycles
- What can we do to make this faster?
 - **Solution:** add another cache! 🤾

Speeding up Translation with a TLB

- Translation Lookaside Buffer (TLB):
 - Small hardware cache in MMU
 - Maps virtual page numbers to physical page numbers
 - Contains complete page table entries for small number of pages
 - Modern Intel processors have 128 or 256 entries in TLB
 - Much faster than a page table lookup in cache/memory

e.g. for frequently used pages... The TLB is a cache for PTEs
(quickly get the conversion between virtual and physical address.

Still got to get page data from memory.

TLB

VPN


PTE

VPN

PTE


VPN

PTE



A TLB hit eliminates a memory access!

don't have to look in memory for the page table that maps virtual --> physical address, just to extract the needed page.



- A TLB miss incurs an additional memory access (the PTE)
 - Fortunately, TLB misses are rare

Fetching Data on a Memory Read


1) Check TLB

- Input: VPN, Output: PPN
- TLB Hit: Fetch translation, return PPN
- TLB Miss: Check page table (in memory)
 - Page Table Hit: Load page table entry into TLB
 - Page Fault: Fetch page from disk to memory, update corresponding page table entry, then load entry into TLB

2) Check cache

- Input: physical address, <u>Output</u>: data
- Cache Hit: Return data value to processor
- Cache Miss: Fetch data value from memory, store it in cache, return it to processor

Address Translation



Context Switching Revisited

- What needs to happen when the CPU switches processes?
 - Registers:
 - Save state of old process, load state of new process
 - Including the Page Table Base Register (PTBR)
 - Memory:
 - Nothing to do! Pages for processes already exist in memory/disk and protected from each other
 - TLB:
 - Invalidate all entries in TLB mapping is for old process' VAs
 - Cache:
 - Can leave alone because storing based on PAs good for shared data

Summary of Address Translation Symbols

Basic Parameters

UNIVERSITY of WASHINGTON

- $N = 2^n$ Number of addresses in virtual address space
- $M = 2^m$ Number of addresses in physical address space
- $P = 2^p$ Page size (bytes)
- Components of the virtual address (VA)
 - VPO Virtual page offset
 - Virtual page number VPN
 - TIB index TLBI
 - TLB tag TLBT
- Components of the physical address (PA)
 - Physical page offset (same as VPO) PPO
 - Physical page number PPN

Virtual Memory Summary

- Programmer's view of virtual memory
 - Each process has its own private linear address space
 - Cannot be corrupted by other processes
- System view of virtual memory
 - Uses memory efficiently by caching virtual memory pages
 - Efficient only because of locality
 - Simplifies memory management and sharing
 - Simplifies protection by providing permissions checking

Memory System Summary

- Memory Caches (L1/L2/L3)
 - Purely a speed-up technique
 - Behavior invisible to application programmer and (mostly) OS
 - Implemented totally in hardware
- Virtual Memory
 - Supports many OS-related functions
 - Process creation, task switching, protection
 - Operating System (software)
 - Allocates/shares physical memory among processes
 - Maintains high-level tables tracking memory type, source, sharing
 - Handles exceptions, fills in hardware-defined mapping tables
 - Hardware
 - Translates virtual addresses via mapping tables, enforcing permissions
 - Accelerates mapping via translation cache (TLB)