

Page table

One page table per process
Stores corresponding page frame # for a page #

And stores page permissions:
Read-only
No-execute
Dirty (modified)
Referenced
Others (e.g., secure or privileged mode access)

Page table is selected by setting a page table base register with the address of the table

Improving look-up performance: TLB

Cache frequently-accessed pages
Translation lookaside buffer (TLB)
Associative memory: key (page #) and value (frame #)

TLB is on-chip & fast ... but small (64 – 1,024 entries)
TLB miss: result not in the TLB
Need to do page table lookup in memory
Hit ratio = % of lookups that come from the TLB
Address Space Identifier (ASID): share TLB among address spaces

Page-Based Virtual Memory Benefits

Simplify memory management for multiprogramming

Allow discontiguous allocation

MMU give the illusion of contiguous allocation

Allow a process to feel that it has more memory than it really has

Also: process can have greater address space than system memory

Memory Protection

Each process' address space is separate from others

MMU allows pages to be protected:

Writing, execution, kernel vs. user access


Real-Time Considerations Avoid page table lookup Or run CPU without virtual addressing Pin high-priority real-time process memory into TLB (if possible)


Accessing memory Process makes *virtual* address references for all memory access MMU converts to physical address via a per-process page table Page number → Page frame number Basic info stored in a PTE (page table entry): Valid? Is the page mapped? Page frame number Permissions (read-only, read-write, execute-only, ...) Modified? Page fault if not a valid reference Most CPUs support: Virtual addressing mode and Physical addressing mode CPU starts in physical mode ... someone has to set up page tables Divide address space into user & kernel spaces


Page allocator With VM, processes can use non-contiguous pages Sometimes you need contiguous allocation E.g., DMA logic ignores paging If we rely on DMA, we need contiguous pages


Page allocator • Linux kernel support for contiguous buffers - free_area: keep track of lists of free pages - 1st element: free single pages - 2nd element: free blocks of 2 contiguous pages - 3nd element: free blocks of 4 contiguous pages - ... - 10nd element: free blocks of 512 contiguous pages


Buddy System Try to get the best usable allocation unit If not available, get the next biggest one & split Coalesce upon free Example We want 8 contiguous pages Do we have a block of 8? Suppose no. Do we have a block of 16? Suppose no. Do we have a block of 32? Suppose yes. Split the 32 block into two blocks of 16. Back up. Do we have a block of 16? Yes! Split one of the 16 blocks into two blocks of eight. Back up. Do we have a block of 8? Yes!



























Multilevel (Hierarchical) page tables


• Most processes use only a small part of their address space


• Keeping an entire page table is wasteful


• E.g., 32-bit system with 4KB pages: 20-bit page table


– 1,048,576 entries in a page table









































Memory Protection & Control

Omain

Clients execute & access data within a domain. Each access is checked against access permissions for each memory block

Memory region attributes

Execute newe

Read-only, read/write, no access
Privileged read-only, privileged & user read-only
Privileged read-only, privileged & user read-only
Privileged read-only, privileged & user read-only
Sharable (is this secure memory or not?)

Sharable (is this memory shared with other processors)

Strongly ordered (memory accesses must occur in program order)

Device/shared, device/non-shared

Normal/shared, normal/non-shared

Signal Memory Abort if permission is not valid for access

MMU Example: x86-64

IA-32 Memory Models

Flat memory model

Linear address space
Single, contiguous address space

Segmented memory model
Memory appears as a group of independent address spaces: segments (code, data, stack, etc.)

Logical address = {segment selector, offset}

16,383 segments; each segment can be up to 232 bytes

Real mode

8086 model
Segments up to 64KB in size
maximum address space: 220 bytes

Segments

• Each segment may be up to 4 GB

• Up to 16 K segments per process

• Two partitions per process

• Local: private to the process

• Up to 8 K segments

• Info stored in a Local Descriptor Table (LDT)

• Global: shared among all processes


• Up to 8 K segments


• Info stored in a Global Descriptor Table (GDT)


• Logical address is (segment selector, offset)


• Segment selector = 16 bits:


• 13 bits segment number + 1 bit LDT/GDT ID + 2 bits protection



























Example: TLBs on the Core i7 4 KB pages Instruction TLB: 128 entries per core Data TLB: 64 entries Core 2 Duo: 16 entries TLB0; 256 entries TLB1 Atom: 64-entry TLB, 16-entry PDE Second-level unified TLB 512 entries



Recap

- Fragmentation is a non-issue
- · Page table
- Page table entry (PTE)
- Multi-level page tables
- · Inverted page table
- · Segmentation
- · Segmentation + Paging
- · Memory protection
 - Isolation of address spaces
 - Access control defined in PTE

Demand Paging

Executing a program

- Allocate memory + stack and load the entire program from memory (including linked libraries)
- · Then execute it

Executing a program

- Allocate memory + stack and load the entire program from memory (including linked libraries)
- · Then execute it

We don't need to do this!

Demand Paging


- · Load pages into memory only as needed
 - On first access
 - Pages that are never used never get loaded
- Use valid/invalid bit in page table entry
 - Valid: the page is in memory ("valid" mapping)
 - Invalid: out of bounds access or page is not in memory
 - Have to check the process' memory map in the PCB to find out
- Invalid memory access generates a page fault


Demand Paging: At Process Start

- · Open executable file
- Set up memory map (stack & text/data/bss)
 - But don't load anything!
- Load first page & allocate initial stack page
- Run it!

Memory Mapping • Executable files & libraries must be brought into a process' virtual address space - File is mapped into the process' memory - As pages are referenced, page frames are allocated & pages are loaded into them • If we ever run out of memory, we may need to save some modified pages into a swap file and load those in later on demand. • vm_area_struct - Defines regions of virtual memory - Used in setting page table entries - Start of VM region, end of region, access rights • Several of these are created for each mapped image - Executable code, initialized data, uninitialized data

Demand Paging: Page Fault Handling Soon the process will access an address without a valid page OS gets a page fault from the MMU What happens? Kernel searches a tree structure of memory allocations for the process to see if the faulting address is valid If not valid, send a SEGV signal to the process Is the type of access valid for the page? Send a signal if not We have a valid page but it's not in memory





Page Replacement A process can run without having all of its memory allocated It's allocated on demand If the {address space used by all processes + OS} ≤ physical memory then we're ok Otherwise: Make room: discard or store a page onto the disk If the page came from a file & was not modified Discard ... we can always get it If the page is dirty, it must be saved in a swap file Swap file: a file (or disk partition) that holds excess pages

Cost Handle page fault exception: ~ 400 usec Disk seek & read: ~ 10 msec Memory access: ~ 100 ns Page fault degrades performance by around 100,000!! Avoid page faults! If we want < 10% degradation of performance, we can have just one page fault per 1,000,000 memory accesses

Page replacement

We need a good replacement policy for good performance

FIFO Replacement

- · First In, First Out
- Good
 - May get rid of initialization code or other code that's no longer used
- Bad
 - May get rid of a page holding frequently used global variables

Least Recently Used (LRU)

- · Timestamp a page when it is accessed
- When we need to remove a page, search for the one with the oldest timestamp
- · Nice algorithm but...
 - Timestamping is a pain we can't do it with the MMU!

Not Frequently Used Replacement

- Approximate LRU
- Each PTE has a reference bit
- · Keep a counter for each page frame
- · At each clock interrupt:
 - Add the reference bit of each frame to its counter
 - Clear reference bit
- To evict a page, choose the frame with the lowest counter
- Problem
 - No sense of time: a page that was used a lot a long time ago may still have a high count
 - Updating counters is expensive

70

Clock (Second Chance)

- Arrange physical pages in a logical circle (circular queue)
 - Clock hand points to first frame
- Paging hardware keeps 1 reference bit per frame
 - Set reference bit on memory reference
 - If it's not set then the frame hasn't been used for a while
- On page fault:
 - Advance clock hand
 - Check reference bit
 - If 1, it's been used recently clear & advance
 - If 0, evict this page

Enhanced Clock (Second Chance)

- Use the reference and modify bits of the page
- Choices for replacement (reference, modify):
 - (0, 0): not referenced recently or modified
 - Good candidate for replacement
 - (0, 1): not referenced recently but modified.
 - The page will have to be saved before replacement
 - (1, 0): recently used.
 - Less ideal will probably be used again
 - (1, 1): recently used and modified
 - Least ideal will probably be used again AND we'll have to save it to a swap file if we replace it.
- Algorithm: like clock but replace the first page in the lowest non-empty class

72

Nth Chance Replacement Similar to Second Chance Maintain a counter along with a reference bit On page fault: Advance clock hand Check reference bit If 1, clear and set counter to 0 If 0, increment counter. If counter < N, go on. Else evict Better approximation of LRU

Kernel Swap Daemon kswapd on Linux Anticipate problems Decides whether to shrink caches if page count is low Page cache, buffer cache Evict pages from page frames

Demand paging summary Allocate page table Map kernel memory Initialize stack Memory-map text & date from executable program (& libraries) But don't load! Load pages on demand (first access) When we get a page fault

Summary: If we run out of free page frames

Free some page frames

Discard pages that are mapped to a file or

Move some pages to a swap file

Clock algorithm

Anticipate need for free page frames


kswapd – kernel swap dæmon

Multitasking Considerations

Supporting multitasking

Multiple address spaces can be loaded in memory
A CPU register points to the current page table
OS changes the register set when context switching
Performance increased with Address Space ID in TLB

Working Set Keep active pages in memory A process needs its working set in memory to perform well Working set = set of pages that have been referenced in the last window of time Spatial locality Size of working set varies during execution More processes in a system: Good: increase throughput; chance that some process is available to run Bad: thrashing: processes do not have enough page frames available to run without paging



Resident Set Management

- Resident set = set of a process' pages in memory
- · How many pages of a process do we bring in?
- Resident set can be fixed or variable
- Replacement scope: global or local
 - Global: process can pick a replacement from all frames
- · Variable allocation with global scope:
 - Simple
 - Replacement policy may not take working sets into consideration
- · Variable allocation with local scope
 - More complex
 - Modify resident size to approximate working set size

Working Set Model

- Approximates locality of a program
- Δ: working set window:
 - Amount of elapsed time while the process was actually executing (e.g., count of memory references)
- WSS_i: working set size of process P_i
 - WSS_i = set of pages in most recent Δ page references
- System-wide demand for frames $D = \sum WSS_i$
- If D > total memory size, then we get thrashing

Page fault frequency

- Too small a working set causes a process to thrash
- Monitor page fault frequency per process
 - If too high, the process needs more frames
 - If too low, the process may have too many frames

Dealing with thrashing

- · If all else fails ...
- Suspend a process(es)
 - Lowest priority, Last activated, smallest resident set, …?
- Swapping:
 - Move an entire process onto the disk: no pages in memory
 - Process must be re-loaded to run

© 2012 Paul Krzyzanowski

