```
** Documentation
Below are two sample programs using OpenSSL's BIGNUM library.
You can find OpenSSL's documentation at the following URL by scrolling
down to the functions that begin "BN_". Not all functions are listed, so
sometimes you need to click on a related function and find it on that page.
https://www.openssl.org/docs/man1.1.1/man3/
The Google documentation is easier to find things and read, but is not 100%
compatible with the 1.1.1 documentation given above. Since testing will be on
a 1.1.1 system, do not use any function not listed in the above documentation.
https://commondatastorage.googleapis.com/chromium-boringssl-docs/bn.h.html
** Compiling
Be sure to #include <openssl/bn.h>
Read https://krovetz.net/152/openssl.html for information on compiling.
==== EXAMPLE 1: GCD
#include <openssl/bn.h>
#include <stdio.h>
void gcd(BIGNUM *r, BIGNUM *a, BIGNUM *b, BN_CTX *ctx)
{
    BIGNUM *c = BN_new();
    BIGNUM *d = BN new();
    BIGNUM *td = BN new();
    BN_copy(c,a);
    BN_copy(d,b);
    while ( ! BN_is_zero(d) ) {
        BN copy(td,d);
                                 // td = d
        BN_{mod}(d, c, td, ctx); // d = c%d
                                 // c=d
        BN_copy(c,td);
    }
    // Copy results
                                // r = c
    BN_copy(r, c);
    BN_free(c);
    BN_free(d);
    BN_free(td);
int main()
{
    unsigned char a[20] = {0xff,};
    unsigned char b[20] = \{0xee,\};
    BN_CTX *ctx = BN_CTX_new();
    BIGNUM *bna = BN_bin2bn(a, sizeof(a), NULL);
    BIGNUM *bnb = BN bin2bn(b, sizeof(b), NULL);
    BIGNUM *r me = BN new();
    BIGNUM *r_ssl = BN_new();
```

```
gcd(r me, bna, bnb, ctx);
    BN gcd(r ssl, bna, bnb, ctx);
    if (BN_cmp(r_ssl, r_me) != 0)
        printf("Not equal!\n");
    char *as = BN bn2dec(bna);
    char *bs = BN bn2dec(bnb);
    char *rs = BN bn2dec(r me);
    printf("GCD of\n%s\nand\n%s\nis\n%s\n",as,bs,rs);
   return 0;
}
/* Output:
GCD of
1455792646560079078679451688838485039110401556480
1358739803456073806767488242915919369836374786048
97052843104005271911963445922565669274026770432
==== EXAMPLE 2: I/O
#include <openssl/bn.h>
#include <stdio.h>
int main() {
    char a[100], b[100], c[100];
    scanf("%99s %99s %99s", a, b, c);
    BN CTX *ctx = BN CTX new();
    BIGNUM *x = BN new();
    BIGNUM *y = BN new();
    BIGNUM *z = BN_new();
    BIGNUM *r = BN new();
                            // BN dec2bn wants BIGNUM ** instead of BIGNUM *
    BN dec2bn(&x, a);
    BN dec2bn(&y, b);
    BN dec2bn(&z, c);
    BN_mul(x, x, y, ctx);
    BN_nnmod(r, x, z, ctx);
    char *res = BN bn2dec(r);
    printf("%s\n", res);
    free(res);
    BN CTX free(ctx);
    BN free(x);
    BN free(y);
    BN free(z);
    BN_free(r);
    return 0;
}
```