Chapter 8:

Subnetting IP networks

Introduction to Networks v5.1



Chapter Outline

- 8.0 Introduction
- 8.1 Subnetting an IPv4 Network
- 8.2 Addressing Schemes
- 8.3 Design Considerations for IPv6
- 8.4 Summary

Section 8.1: Subnet an IPv4 Network

Upon completion of this section, you should be able to:


- Explain how subnetting segments a network to enable better communication.
- Explain how to calculate IPv4 subnets for a /24 prefix.
- Explain how to calculate IPv4 subnets for a /16 and /8 prefix.
- Given a set of requirements for subnetting, implement an IPv4 addressing scheme.
- Explain how to create a flexible addressing scheme using variable length subnet masking (VLSM).

Topic 8.1.1: Network Segmentation



Broadcast Domains

Each router interface connects a *broadcast domain* and broadcasts are only propagated within its specific broadcast domain.




Problems with Large Broadcast Domains

 Slow network operations due to the significant amount of broadcast traffic.


Slow device operations because a device must accept and

process each broadcast packet.




Problems with Large Broadcast Domains (cont.)

- Solution -reduce the size of the network to create smaller broadcast domains in a process called subnetting.
- These smaller network spaces are called subnets.




Reasons for Subnetting

Network administrators can group devices and services into subnets that are determined by: Location




Reasons for Subnetting (cont.)

Network administrators can group devices and services into subnets that are determined by: Organizational unit.



Reasons for Subnetting (cont.)

Network administrators can group devices and services into subnets that are determined by: Device type.



Topic 8.1.2: Subnetting an IPv4 Network



Subnet a Network Address

Method:


Borrowing host bits and turning them into network bits.

Example:

Network Address: Provided by network ISP

Subnetted Address: Eight bits are borrowed to increase the number of network bits

A Note About IP Addresses



IP Address in Network Computer Readable Format

Dots are added only to made IP addresses readable by people. Subnet Arithmetic needs to be done per octet.

Octet Boundaries

Subnetting Networks on the Octet Boundary

Prefix Length	Subnet Mask	Subnet Mask in Binary (n = network, h = host)	# of hosts
/8	255.0.0.0	nnnnnnn . hhhhhhhh . hhhhhhhh . hhhhhhhh	16,777,214
/16	255.255.0.0	nnnnnnn . nnnnnnnn . hhhhhhhh . hhhhhhhh	65,534
/24	255.255.255.0	nnnnnnn . nnnnnnnn . nnnnnnnn . hhhhhhhh	254

Class B IP Address Subnet Example

Network Address: Provided by network ISP 172.16.0.0/16

Borrow 8 bits from host for subnet to create /24

172.16.0.0/24

Specific Subnets

172.16.<u>0</u>.0/24

172.16.1.0/24

172.16.<u>2</u>.0/24

172.16.255.0/24

Class B IP Address Subnet Example cont'd

Specific Subnets s=8; no. of subnets=256 172.16.<u>0</u>.0/24

172.16.1.0/24

172.16.2.0/24

2^S Subnets

s: # subnet bits

172.16.<u>255</u>.0/24

Host Addresses per Subnet h=8; no. of hosts=254

172.16.5.<u>1</u>

172.16.5.2

172.16.5.<u>3</u>

172.16.6.<u>254</u>

2^h- 2 Hosts

h: # host bits

Subnetting on the Octet Boundary

Subnetting 10.x.0.0/16

Subnet Address (256 Possible Subnets)	Host Range (65,534 possible hosts per subnet)	Broadcast
<u>10.0</u> .0.0/16	<u>10.0</u> .0.1 - <u>10.0</u> .255.254	<u>10.0</u> .255.255
10.2.0.0/16	<u>10.2</u> .0.1 - <u>10.2</u> .255.254	<u>10.2</u> .255.255
<u>10.3</u> .0.0/16	<u>10.3</u> .0.1 - <u>10.3</u> .255.254	<u>10.3</u> .255.255
<u>10.4</u> .0.0/16	<u>10.4</u> .0.1 - <u>10.4</u> .255.254	<u>10.4</u> .255.255
<u>10.5</u> .0.0/16	<u>10.5</u> .0.1 - <u>10.5</u> .255.254	<u>10.5</u> .255.255
<u>10.6</u> .0.0/16	<u>10.6</u> .0.1 - <u>10.6</u> .255.254	<u>10.6</u> .255.255
<u>10.7</u> .0.0/16	<u>10.7</u> .0.1 - <u>10.7</u> .255.254	<u>10.7</u> .255.255
<u>10.255</u> .0.0/16	<u>10.255</u> .0.1 - <u>10.255</u> .255.254	<u>10.255</u> .255.255

Subnetting 10.x.x.0/24

Subnet Address (65,536 Possible Subnets)	Host Range (254 possible hosts per subnet)	Broadcast		
<u>10.0.0</u> .0/24	<u>10.0.0</u> .1 - <u>10.0.0</u> .254	<u>10.0.0</u> .255		
<u>10.0.1</u> .0/24	<u>10.0.1</u> .1 - <u>10.0.1</u> .254	<u>10.0.1</u> .255		
<u>10.0.2</u> .0/24	<u>10.0.2</u> .1 - <u>10.0.2</u> .254	<u>10.0.1</u> .255		
10.0.255.0/24	<u>10.0.255</u> .1 - <u>10.0.255</u> .254	<u>10.0.255</u> .255		
<u>10.1.0</u> .0/24	<u>10.1.0</u> .1 - <u>10.1.0</u> .254	<u>10.1.0</u> .255		
<u>10.1.1</u> .0/24	<u>10.1.1</u> .1 - <u>10.1.1</u> .254	<u>1.1.1.0</u> .255		
<u>10.1.2</u> .0/24	<u>10.1.2</u> .1 - <u>10.1.2</u> .254	<u>10.1.2.0</u> .255		
<u>10.100.0</u> .0/24	<u>10.100.0</u> .1 - <u>10.100.0</u> .254	<u>10.100.0</u> .255		
10.255.255.0/24	<u>10.255.255</u> .1 - <u>10.255.255</u> .254	<u>10.255.255</u> .255		

Classless Subnetting

- /25 Borrowing 1 bit from the fourth octet creates 2 subnets supporting 126 hosts each.
- /26 Borrowing 2 bits creates 4 subnets supporting 62 hosts each.
- /27— Borrowing 3 bits creates 8 subnets supporting 30 hosts each.
- /28 Borrowing 4 bits creates 16 subnets supporting 14 hosts each.
- /29 Borrowing 5 bits creates 32 subnets supporting 6 hosts each.
- /30— Borrowing 6 bits creates 64 subnets supporting 2 hosts each.

Prefix Length	Subnet Mask	Subnet Mask in Binary (n = network, h = host)	# of subnets	# of hosts
/25	255.255.255.128	nnnnnnn.nnnnnnnn.nnnnnnn.nhhhhhh 11111111.11111111.11111111.10000000	2	126
/26	255.255.255.192	nnnnnnn . nnnnnnnn . nnnnnnnn . nnhhhhhh 11111111 . 11111111 . 11111111 . 11000000	4	62
/27	255.255.255.224	nnnnnnn.nnnnnnnn.nnnnnnn.nnnhhhhh 11111111.11111111.11111111.11100000	8	30
/28	255.255.255.240	nnnnnnn.nnnnnnnn.nnnnnnn.nnnhhhh 11111111.11111111.11111111.11110000	16	14
/29	255.255.255.248	nnnnnnn.nnnnnnnn.nnnnnnn.nnnnhhh 11111111.11111111.11111111.11111000	32	6
/30	255.255.255.252	nnnnnnn.nnnnnnnn.nnnnnnn.nnnnnhh 11111111.11111111.11111111.11111100	64	2

Classless IP Address Subnet Example

Network Address: Provided by network ISP 192.168.1.0/24

Borrow 2 bits from host for subnet to create /26

Specific Subnets (4 subnets)

$$192.168.1.0/26$$
 (ss=00)
 $192.168.1.64/26$ (ss=01)
 $192.168.1.128/26$ (ss=10)
 $192.168.1.192/26$ (ss=11)

Classless IP Address Subnet Example

Specific Subnets (4 subnets)

192.168.1.0/26

192.168.1.64/26

192.168.1.128/26

192.168.1.192/26

 2^2 = 4 Subnets s=2: # subnet bits

Host Addresses per Subnet 172.16.1.65

172.16.1.66

172.16.1.67

172.16.1.126


 $2^6 - 2 = 62 \text{ Hosts}$

h=6: # host bits

Classless Subnetting Example

192.168.1.0/25 Network

Borrow 1 bit from the host portion of the address.



The borrowed bit value is 0 for the Net 0 address.




The new subnets have the SAME subnet mask.

Mask 255. 255. 255. 1 000 0000

Classless Subnetting Example (cont.)


Dotted Decimal Addresses

Borrow 1 bit from the host portion of the address.



Creating 2 Subnets

/25 Subnetting Topology



Creating 2 Subnets (cont.)


Address Range for 192.168.1.0/25 Subnet

Address Range for 192.168.1.128/25 Subnet

Networl	Address						Networ	k Address					
192.	168.	1.	0	000	0000	= 192.168.1.0	192.	168.	1.	1	000	0000	= 192.168.1.128
First Ho	st Addres	s					First Ho	st Addres	S				
192.	168.	1.	0	000	0001	= 192.168.1.1	192.	168.	1.	1	000	0001	= 192.168.1.129
Last Ho	Last Host Address					Last Host Address							
192.	168.	1.	0	111	1110	= 192.168.1.126	192.	168.	1.	1	111	1110	= 192.168.1.254
Broadca	ast Addres	ss					Broadc	ast Addres	SS				
192.	168.	1.	0	111	1111	= 192.168.1.127	192.	168.	1.	1	111	1111	= 192.168.1.255


Creating 4 Subnets

/26 Subnetting Topology




Creating 4 Subnets (cont.)

Borrowing 2 Bits



Creating 4 Subnets (cont.)

Calculate Number of Hosts



Address Range for 192.168.1.0/26 Subnet



Creating 4 Subnets (cont.)

Address Ranges Nets 0 - 2

	Network	192.	168.	1.	00	00	0000	192.168.1.0
Net 0	First	192.	168.	1.	00	00	0001	192.168.1.1
Net 0	Last	192.	168.	1.	00	11	1110	192.168.1.62
	Broadcast	192.	168.	1.	00	11	1111	192.168.1.63
	Network	192.	168.	1.	01	00	0000	192.168.1.64
Net 1	First	192.	168.	1.	01	00	0001	192.168.1.65
Net I	Last	192.	168.	1.	01	11	1110	192.168.1.126
	Broadcast	192.	168.	1.	01	11	1111	192.168.1.127
	Network	192.	168.	1.	10	00	0000	192.168.1.128
N-+ O	First	192.	168.	1.	10	00	0001	192.168.1.129
Net 2	Last	192.	168.	1.	10	11	1110	192.168.1.190
	Broadcast	192.	168.	1.	10	11	1111	192.168.1.191

Topic 8.1.3: Subnetting a /16 and a /8 Prefix



Creating Subnets with a /16 prefix

					T/
Prefix Length	Subnet Mask	Network Address (n = network, h = host)	# of subnets	# of hosts	ľ
/17	255.255.128.0	nnnnnnn.nnnnnnn.nhhhhhhh.hhhhhhhh 11111111.11111111.10000000.00000000	2	32564	
/18	255.255.192.0	nnnnnnn.nnnnnnn.nnhhhhhh.hhhhhhhh 11111111.11111111.11000000.00000000	4	16282	
/19	255.255.224.0	nnnnnnn.nnnnnnn.nnhhhhhhhhhhhh 11111111.11111111.11100000.00000000	8	8190	
/20	255.255.240.0	nnnnnnn.nnnnnnn.nnnhhhh.hhhhhhh 11111111.11111111.11110000.00000000	16	4094	
/21	255.255.248.0	nnnnnnn.nnnnnnnn.nnnnhhh.hhhhhhh 11111111.11111111.11111000.00000000	32	2046	l
/22	255.255.252.0	nnnnnnn.nnnnnnn.nnnnnhh.hhhhhhh 11111111.11111111.1111100.00000000	64	1022	l
/23	255.255.254.0	nnnnnnn.nnnnnnn.nnnnnnh.hhhhhhhh 11111111.11111111.1111110.00000000	128	510	l
/24	255.255.255.0	nnnnnnn.nnnnnnnn.nnnnnnn.hhhhhhh 11111111.11111111.11111111.00000000	256	254	l
/25	255.255.255.128	nnnnnnn.nnnnnnnn.nnnnnnn.nhhhhhhh 11111111.11111111.11111111.10000000	512	126	ŀ
/26	255.255.255.192	nnnnnnn.nnnnnnnn.nnnnnnnn.nnhhhhhh 11111111.11111111.11111111.11000000	1024	62	
/27	255.255.255.224	nnnnnnn.nnnnnnnn.nnnnnnnn.nnnhhhhh 11111111.11111111.111111111.11100000	2048	30	ļ

Creating 100 Subnets with a /16 Network

172 . 16 . 0 . 0

nnnnnnn.nnnnnnn.hhhhhhhh.hhhhhhh

```
2<sup>1</sup> = 2 <--
  Borrowing 1 bit:
 Borrowing 2 bits:
                           2^2 = 4 <--
 Borrowing 3 bits:
                           2^3 = 8 <--
 Borrowing 4 bits:
                         2^4 = 16 <--
 Borrowing 5 bits:
                         2^5 = 32 <--
                         2^6 = 64 <--
 Borrowing 6 bits:
 Borrowing 7 bits:
                        2<sup>7</sup> = 128 <--
 Borrowing 8 bits:
                        2<sup>8</sup> = 256 <
 Borrowing 9 bits:
                        2<sup>9</sup> = 512 <--
Borrowing 10 bits:
                     2^10 = 1024 <--
Borrowing 11 bits:
                     2<sup>11</sup> = 2048 <del><---</del>
Borrowing 12 bits: 2^12 = 4096 -
Borrowing 13 bits: 2^13 = 8192 -
Borrowing 14 bits: 2^14 = 16384 <--
```


Creating 100 Subnets with a /16 Network (cont.)

Resulting /23 Subnets



Calculating the Hosts

Hosts = 2ⁿ (where n = host bits remaining)



 $2^9 = 512$ hosts per subnet $2^9 - 2 = 510$ valid hosts per subnet

Address Range for 172.16.0.0/23 Subnet

Network Address

172. 16. 00 00 00 00. 0000 0000 = 172.16.0.0/23

First Host Address

172. 16. 00 00 00 00. 0000 0001 = 172.16.0.1/23

Last Host Address

172. 16. 00 00 00 01. 1111 1110 = 172.16.1.254/23

Broadcast Address


172. 16. 00 00 00 01. 1111 1111 = 172.16.1.255/23

Creating 1000 Subnets with a /8 Network



Creating 1000 Subnets with a /8 Network (cont.)

Calculating Hosts



Address Range for 10.0.0.0/18 Subnet

Netw	ork Address			
10.	00 00 00 00.	0000 0000.	0000 0000	= 10.0.0.0/18
First H	lost Address			
10.	00 00 00 00.	0000 0000.	0000 0001	= 10.0.0.1/18
Last H	lost Address			
10.	00 00 00 00.	0011 1111.	1111 1110	= 10.0.63.254/18
Broad	cast Address			
		0011 1111		- 40 0 00 055/40
10.	00 00 00 00.	0011 1111.	1111 1111	= 10.0.63.255/18

Topic 8.1.4: Subnetting to Meet Requirements



Subnetting Based on Host Requirements

Two considerations when planning subnets:


- The number of host addresses required for each network.
- The number of individual subnets needed.

Prefix Length	Subnet Mask	Subnet Mask in Binary (n = network, h = host)	# of subnets	# of hosts
/25	255.255.255.128	nnnnnnn . nnnnnnnn . nnnnnnnn . nhhhhhhh 11111111 . 11111111 . 11111111 . 10000000	2	126
/26	255.255.255.192	nnnnnnn . nnnnnnnn . nnnnnnnn . nnhhhhhh 11111111 . 11111111 . 11111111 . 11000000	4	62
/27	255.255.255.224	nnnnnnn . nnnnnnnn . nnnnnnnn . nnnhhhhh 11111111 . 11111111 . 11111111 . 11100000	8	30
/28	255.255.255.240	nnnnnnn . nnnnnnnn . nnnnnnnn . nnnnhhhh 11111111 . 11111111 . 11111111 . 11110000	16	14
/29	255.255.255.248	nnnnnnn . nnnnnnnn . nnnnnnnn . nnnnnhhh 11111111 . 11111111 . 11111111 . 11111000	32	6
/30	255.255.255.252	nnnnnnn . nnnnnnnn . nnnnnnnn . nnnnnnhh 11111111 . 11111111 . 11111111 . 11111100	64	2

The more bits borrowed to create subnets, the fewer host bits available.

Subnetting Based on Network Requirements

Subnets Based on Organizational Structure



Corporate Network

Network Requirement Example

Corporate Network
Base Network Address: 172.16.0.0/22

LAN1 (Engineering) LAN3 (Sales) LAN2 (Human Resources) 30 hosts 40 hosts 23 hosts LAN4 (Technical Support) LAN5 (Exec 35 hosts Management) 10 hosts

Select Subnet Parameters

- 1. Base Network Address: 172.16.0.0/22 which has 10 host bits
- 2. Select number of host bits per subnet:

 Maximum number of hosts per subnet = 40

$$2^6$$
- 2 = 62 Hosts h=6: # host bits

$$2^{5}$$
 - 2 = 30 Hosts

h=5: # host bits

Therefore required number host bits = 6


3. Number of remaining bits for subnet = 4
Number of subnets with 4 bits = 16
Number of required subnets = 5

$$2^4$$
 = 16 Subnets

s=4: # subnet bits

New subnet mask is /26


Network Requirement Example (cont.)



4 bits borrowed from host portion to create subnets

Network Requirement Example (cont.)


172.16.0.0/22




Topic 8.1.5: Benefits of Variable Length Subnetting Masking




Traditional Subnetting Wastes Addresses





Traditional Subnetting Wastes Addresses (Cont.)

Unused Addresses on WAN Subnets




Variable Length Subnet Masks

Traditional Subnetting Creates Equal Sized Subnets

Subnets of Varying Sizes

One subnet was further divided to create 8 smaller subnets of 4 hosts each



Section 8.2: Addressing Schemes

Upon completion of this section, you should be able to:

Implement a VLSM addressing scheme.

Section 8.3: Design Considerations for IPv6

Upon completion of this section, you should be able to:

Explain how to implement IPv6 address assignments in a business network.


Topic 8.3.1: Subnetting an IPv6 Network



The IPv6 Global Unicast Address

The IPv6 global unicast address normally consists of a /48 global routing prefix, a 16 bit subnet ID, and a 64 bit interface ID.

IPv6 Global Unicast Address Structure



A/48 routing prefix + 16 bit Subnet ID = /64 prefix

Subnetting Using the Subnet ID

Address Block: 2001:0DB8:ACAD::/48


Increment subnet ID to create 65,536 subnets 2001:0DB8:ACAD:0000::/64 2001:0DB8:ACAD:0001::/64 2001:0DB8:ACAD:0002::/64 2001:0DB8:ACAD:0003::/64 2001:0DB8:ACAD:0004::/64 2001:0DB8:ACAD:0005::/64 2001:0DB8:ACAD:0006::/64 2001:0DB8:ACAD:0007::/64 2001:0DB8:ACAD:0008::/64 2001:0DB8:ACAD:0008::/64 2001:0DB8:ACAD:0008::/64 2001:0DB8:ACAD:0008::/64

Subnets 13 - 65,534 not shown

2001:0DB8:ACAD:FFFF::/64

IPv6 Subnet Allocation

Example Topology



IPv6 Subnet Allocation (cont.)


Address Block: 2001:0DB8:ACAD::/48

5 subnets allocated from 65,536 available subnets

```
2001:0DB8:ACAD:0000::/64
2001:0DB8:ACAD:0001::/64
2001:0DB8:ACAD:0002::/64
2001:0DB8:ACAD:0003::/64
2001:0DB8:ACAD:0004::/64
2001:0DB8:ACAD:0005::/64
2001:0DB8:ACAD:0006::/64
2001:0DB8:ACAD:0007::/64
2001:0DB8:ACAD:0008::/64
2001:0DB8:ACAD:FFFF::/64
```

IPv6 Subnet Allocation (cont.)

IPv6 Subnet Allocation



Section 8.4: Summary

Chapter Objectives:

- Implement an IPv4 addressing scheme to enable end-to-end connectivity in a small to medium-sized business network.
- Given a set of requirements, implement a VLSM addressing scheme to provide connectivity to end users in a small to medium-sized network.
- Explain design considerations for implementing IPv6 in a business network.

Thank you.

CISCO Cisco Networking Academy
Mind Wide Open