

PH-214 Modern Physics Notes

Useful Math

Taylor series expansions:

$$\sin x = \sum_{n=0}^{\infty} (-1)^n \frac{x^{2n+1}}{(2n+1)!} = x - \frac{x^3}{3!} + \frac{x^5}{5!} - \frac{x^7}{7!} + \dots$$

$$\cos x = \sum_{n=0}^{\infty} (-1)^n \frac{x^{2n}}{(2n)!} = 1 - \frac{x^2}{2!} + \frac{x^4}{4!} - \frac{x^6}{6!} + \dots$$

$$\tan x = \sum_{n=1}^{\infty} \frac{B_{2n}(-4)^n(1-4^n)}{(2n)!} x^{2n-1} = x + \frac{x^3}{3} + \frac{2x^5}{15} + \frac{17x^7}{315} + \dots$$

$$(1+x)^m = \sum_{n=0}^{\infty} \binom{m}{n} x^n = 1 + mx + \frac{m(m-1)}{2} x^2 + \frac{m(m-1)(m-2)}{6} x^3 + \dots$$

Note: For small x , higher order terms reduce to zero

Euler's Identity:

Use complex exponentials to manipulate complicated trig functions and complex amplitudes.

$$e^{ix} = \cos x + i \sin x$$

Visualizing propagating plane waves:

A 1D plane wave propagating in the $+z$ direction can be mathematically represented as:

$$\psi = f(kz - \omega t) \iff f(z - vt), \quad v = \frac{\omega}{k}$$

Where:

- $(kz - \omega t)$ [rad]:

The argument represents the **phase** of the wave. A change in phase simply moves the wave forward or backward in space and time, without changing its shape, there are a few ways to see this which we will look at later.

- k [rad/m]:

is the **wave number**, representing the spatial frequency of the wave, or how *spread out* the wave is in space. Since k scales the spatial variable z , a larger k means the wave advances through the same phase over a smaller change in z .


- ω [rad/s]:

is the **angular frequency**, representing the temporal frequency of the wave, or how *spread out* the wave is in time. As in rotational kinematics, ω scales time t , and a larger ω means the wave advances through the same phase over a smaller change in t .

A plane wave is special in that it represents a wave whose shape is fixed as it propagates through space and time, with its shape represented by the function f .

Global View

As mentioned before, there are two ways to visualize how the phase $(kz - \omega t)$ represents a propagating wave. The first is a *global* view, looking at how z and t change relative to each other for a fixed phase, tracking a specific point on the wave.



When we track a specific point on the wave, f must give the same value at different positions and times, meaning the phase must stay constant. This shows that as t increases, z must also increase to maintain the phase (the wave moves rightward!). Vice versa, as z increases, t must increase too to keep the phase constant (again, moving rightward!).


Note: This intuition applies to *any* point on the wave! Thus, by tracking all points, we can clearly see a propagating plane wave.

Local View

The second is a *local* view, looking at how the phase changes at a fixed position as time changes, or at a fixed time as position changes. For this, we will look at a sinusoidal wave, to better show oscillation: $\psi = \cos(kz - \omega t)$

1. Fixing z , letting t vary:


Imagine we are at a fixed position $z = z_1$. As time increases, we are effectively watching a cross-section of the wave at that point, seeing only a single point along the wave moving up and down like riding the “surface” of the wave.



2. Fixing t , letting z vary:

Now imagine we are at a fixed time $t = t_1$. Moving along the z axis, and plotting the

wave's amplitude, we see the full shape of the wave at that instant (ωt_1 becomes a constant phase shift).



3. Letting z and t vary together:

When we looked at z and t separately, we saw only a *part* of the wave's behavior. For a fixed z , we observed how a single point moves over time, capturing the wave's temporal variation. For a fixed t , we saw the spatial variation, revealing the full shape of the wave at that instant. When both z and t vary together, we can see the wave's complete behavior, watching how its shape propagates through space and time.

Note: This intuition will become very useful when we study electromagnetic polarization, where the plane wave is a 2D wave. In our cross-sectional view, the single point along the wave will move along the xy plane instead of just up and down.

Vector Calculus

- **Del Operator:**

$$\vec{\nabla} = \frac{\partial}{\partial x} \hat{x} + \frac{\partial}{\partial y} \hat{y} + \frac{\partial}{\partial z} \hat{z}$$

- **Laplacian Operator:**

$$\nabla^2 = \vec{\nabla} \cdot \vec{\nabla} = \frac{\partial^2}{\partial x^2} + \frac{\partial^2}{\partial y^2} + \frac{\partial^2}{\partial z^2} \quad (\text{in cartesian})$$

- **Divergence:** Dot product of del operator with a vector field $\vec{A}$, giving a scalar field that represents how much $\vec{A}$ spreads (diverges) out from a point.

$$\vec{\nabla} \cdot \vec{A} = \frac{\partial A_x}{\partial x} + \frac{\partial A_y}{\partial y} + \frac{\partial A_z}{\partial z}$$

Note: A positive divergence indicates a source, while a negative divergence indicates a sink.

- **Curl:** Cross product of del operator with a vector field $\vec{A}$, giving a vector field that represents how much $\vec{A}$ curls around a point.

$$\begin{aligned}\vec{\nabla} \times \vec{A} &= \begin{vmatrix} \hat{x} & \hat{y} & \hat{z} \\ \frac{\partial}{\partial x} & \frac{\partial}{\partial y} & \frac{\partial}{\partial z} \\ A_x & A_y & A_z \end{vmatrix} \\ &= \underbrace{\left(\frac{\partial A_z}{\partial y} - \frac{\partial A_y}{\partial z} \right)}_{\text{curl about } x\text{-axis}} \hat{x} + \underbrace{\left(\frac{\partial A_x}{\partial z} - \frac{\partial A_z}{\partial x} \right)}_{\text{curl about } y\text{-axis}} \hat{y} + \underbrace{\left(\frac{\partial A_y}{\partial x} - \frac{\partial A_x}{\partial y} \right)}_{\text{curl about } z\text{-axis}} \hat{z}\end{aligned}$$

Note: A positive curl indicates a counterclockwise rotation, while a negative curl indicates a clockwise rotation about the respective axis.

- **Vector Identities:**

$$\vec{\nabla} \cdot (\vec{A} \times \vec{B}) = \vec{B} \cdot (\vec{\nabla} \times \vec{A}) - \vec{A} \cdot (\vec{\nabla} \times \vec{B}) \quad (\text{Product Rule})$$



$$\vec{\nabla} \times (\vec{\nabla} v) = 0 \quad (\text{Curl of a gradient is always zero})$$

$$\vec{\nabla} \cdot (\vec{\nabla} \times \vec{A}) = 0 \quad (\text{Divergence of a curl is always zero})$$

Divergence Theorem

Relates the flux of a vector field $\vec{F}$ through a closed surface S to the divergence of $\vec{F}$ within the volume V enclosed by S .

$$\underbrace{\int_V (\vec{\nabla} \cdot \vec{F}) d\tau}_{\text{how field spreads inside the volume}} = \underbrace{\oint_S \vec{F} \cdot d\vec{a}}_{\text{flux of field through the surface}}$$



Stokes Theorem

States that inside a surface A bounded by a closed curve P , if a vector field $\vec{F}$ has a non-zero curl about $\vec{A}$ (the normal to the surface), then there will be a non-zero circulation of $\vec{F}$ around the curve P .

$$\underbrace{\int_A (\vec{\nabla} \times \vec{F}) \cdot d\vec{a}}_{\text{flux of the curl of } \vec{F}} = \underbrace{\oint_P \vec{F} \cdot d\vec{l}}_{\text{circulation of } \vec{F}}$$



Key Electricity and Magnetism Laws

- Coulomb's Law

$$\vec{F}_e = \frac{1}{4\pi\epsilon_0} \frac{q_1 q_2}{r^2} \hat{r}$$

- Magnetic Force

$$\vec{F}_b = q\vec{v} \times \vec{B}$$

- Electric Field of a Point Charge

$$\vec{E} = \frac{1}{4\pi\epsilon_0} \frac{q}{r^2} \hat{r}$$

- Biot-Savart Law

$$\vec{B} = \int \frac{\mu_0}{4\pi} \frac{i d\vec{s} \times \hat{r}}{r^2}$$

Unit 1: Electromagnetic Waves

Maxwell's Equations

1. Gauss's Law for Electricity

Relates the electric flux through a closed 3D Gaussian surface to the total charge enclosed within that surface.

$$\oint_S \vec{E} \cdot d\vec{a} = \frac{q_{\text{enc}}}{\epsilon_0}$$

There exists a diverging electric field if there exists a non-zero charge density at that point.

$$\vec{\nabla} \cdot \vec{E} = \frac{\rho}{\epsilon_0}$$

2. Gauss's Law for Magnetism

Any 3D Gaussian surface will have zero net magnetic flux (no magnetic monopoles).

$$\oint_S \vec{B} \cdot d\vec{a} = 0$$

There exists no diverging magnetic field at any point in space because there are no magnetic monopoles.

$$\vec{\nabla} \cdot \vec{B} = 0$$

3. Faraday's Law of Induction

Relates the electric circulation around a closed Faradian loop to the changing magnetic flux through the surface bounded by the loop.

$$\oint_P \vec{E} \cdot d\vec{l} = -\frac{d\Phi_B}{dt}, \quad \Phi_B = \oint_S \vec{B} \cdot d\vec{a}$$

Note: For coils with N turns, multiply the flux by N .

A changing magnetic field induces a circulating (curling) electric field.

$$\vec{\nabla} \times \vec{E} = -\frac{\partial \vec{B}}{\partial t}$$

4. **Ampere-Maxwell Law**

Relates the magnetic circulation around a closed Amperian loop to the enclosed current and changing electric flux through the surface bounded by the loop.

$$\oint_P \vec{B} \cdot d\vec{l} = \mu_0 I_{\text{enc}} + \mu_0 \varepsilon_0 \frac{d\Phi_E}{dt}, \quad \Phi_E = \oint_S \vec{E} \cdot d\vec{a}$$

Both a changing electric field and a non-zero current density induce a circulating (curling) magnetic field.

$$\vec{\nabla} \times \vec{B} = \mu_0 \vec{J} + \mu_0 \varepsilon_0 \frac{\partial \vec{E}}{\partial t}, \quad I_{\text{enc}} = \oint_S \vec{J} \cdot d\vec{a}$$