Common

- Smart pointers are located in header <memory>
- unique ptr and shared ptr have access operators * and -> overloaded so a smart pointer can be dereferenced like a normal raw pointer.
- Use .get() (on unique ptr and shared ptr) to access the raw, underlying pointer.
- .get() is useful when you want to pass a pointer to a function to "observe" the managed object void foo(MyType* pObj) { } foo(mySmartPytr.get());
- unique ptr (since C++11) and shared ptr (since C++17) have template specialization for arrays (delete[] will be called on clean up). This might be helpful when you get a pointer to an array from some third-party library or a legacy system. Still, if possible, it's better to use some standard containers like std::vector or std::array.
- Reminder: don't use auto_ptr! It has been deprecated since C++11 and removed in C++17. Replace it with unique_ptr.
- In C++17, for smart pointers, there is no class template argument deduction from pointer type because it is impossible to distinguish a pointer obtained from an array and non-array forms of new.

std::unique ptr

A lightweight smart pointer that has the unique ownership of a managed object.

- Unique pointer destroys the underlying object when it goes out of scope, its reset() method is called or is assigned with a new pointer/object.
- unique ptr is movable, but not copyable.
- Usually, it's the size of a native pointer (depending on the type of deleter used).

Creation

```
Advised with auto and std::make unique
auto pObj = make unique<MyType>(...)'
or with explicit new:
unique_ptr<MyType> pObject(new MyType(...))
but the type occurs twice here
```

Custom deleters

A deleter can be any callable type: std::function, function pointer, stateless functor, stateful functor, lambda. Example:

```
struct DelFunctor {
    void operator()(MyType * p) {
        p->SpecialDelete();
        delete p;
};
using my spec ptr = unique ptr<MyType,
                          DelFunctor>;
```

- Deleter is not called when pointer is null
- get_deleter() can return a non const reference to the deleter, so it can be used to replace it

Passing to functions

unique ptr is movable only, so it should be passed with std::move to explicitly express the ownership transfer:

```
auto pObj = make unique<MyType>(...);
func(std::move(p0bj));
// pObj is invalid after the call!
```

Other

- reset() resets the pointer (deletes the old one)
- unique ptr is also useful in "pimpl" idiom implementation
- unique ptr is usually the first candidate to return from factory functions. If factories gets more complicated (like when adding caches), you might then use shared_ptr (or weak_ptr)

std::shared ptr

Multiple shared pointers can point to the same object, sharing the ownership. When the last shared pointer to an object goes out of scope, it is destroyed. This functionality is implemented with a reference counting mechanism

- shared_ptr is copyable and movable
- it's usually the size of two native pointers.

Creation

```
Advised method is through std::make shared():
auto pObj = make shared<MyType>(...)
make_shared will usually allocate the control block
next to the Object, so there's better memory locality.
```

Custom deleters

A deleter is stored in a control block and can be passed during creation (not with make shared()). Deleter is not part of the type so it can be anything callable.

```
void DeleteFunc(MyType* p) {
   if (p) p->SpecialDelete ();
    delete p;
shared_ptr<MyType> ptr(new MyType(),
                        DeleteFunc);
```

- A custom deleter must cope with potential null pointer values. Deleter is called also when the pointer is empty.
- get deleter() (non-member function) returns a non const pointer to the deleter

Passing to functions

Usually it's good enough to pass the shared pointer by value. Shared pointer is copyable so the reference counter will be correctly updated, it's also guite lightweight operation. std::move can be also used to transfer the ownership.

Other

- The reference counter is managed atomically but the pointer access is not thread-safe.
- Use shared from this() to return a shared pointer to *this. The class must derive from std::enable_shared_from_this.
- Casting between pointer types can be done using dynamic pointer cast, static pointer cast or reinterpret pointer cast.
- shared ptr might create cyclic dependencies and mem leaks when two pointers point to each other.

std::weak ptr

Non-owning smart pointer that holds a "weak" reference to an object that is managed by std::shared ptr. It must be converted to std::shared ptr to access the referenced object via lock() method.

- One example where weak pointers are useful is caching. Such system distributes only weak pointers, and before any use, the client is responsible for checking if the resource is still alive.
- A weak pointer is also used to break cycles in shared

Creation

A weak pointer is created from a shared_ptr, but before using it, you have to convert it to shared_ptr

```
weak_ptr pWeak = pSharedPtr;
if (auto observe = pWeak.lock()) {
    // the object is alive
} else {
   // shared ptr was deleted
```

A weak pointer created from a shared pointer will increase 'weak reference counter' that is stored in the control block of the shared pointer. Even if all shared pointers (referring to a single object) are dead, but one weak pointer has a weak reference (to that object) the control block might still be present in the memory. This might be a problem when the control block is allocated together with the object (like when using make_shared). In that case, the destructor of the object is called, but memory is not released.

Other

- use count() returns the number of shared pointers sharing the same managed object.
- Use expired() to check if the managed object is still present.
- The weak pointer doesn't have * and -> operators overloaded, so you cannot dereference underlying pointer before converting to shared_ptr (via lock()).

cplusplus.com/reference/memory

References

cppreference.com/cpp/memory CppCoreGuidelines/Resource