iWGS - version 0.8

in silico Whole Genome Sequencer

Xiaofan Zhou

2014/11/23

Contents

Introduction	1
Pre-requisites/Supported tools	2
Reads simulator	2
QC tools	2
Assembler	3
Evaluation	4
Additional tools	5
Installation	6
iWGS	6
Pre-compiled tools	6
Installation reminders/tips for other tools	7
Running iWGS	11
Command line options	11
Control file	12
Advanced configuration files	15
Output	17
Examples	17
References	20
Appendices	22
Appendix A. One complete control file	22
Appendix B. Exemplar configuration files	25

Introduction

To be completed

Pre-requisites/Supported tools

This section contains information on all tools supported by iWGS, including the latest supported version and the homepage.

Reads simulator

ART (v03.11.14) [1]:

http://www.niehs.nih.gov/research/resources/software/biostatistics/art/

pIRS (v2.0.0) [2]: https://code.google.com/p/pirs/

PBSIM (v1.0.3) [3]: https://code.google.com/p/pbsim/

* The PBSIM package distributed with iWGS has been modified (based on version 1.0.3) to model the distribution of per read quality scores using the Weibull distribution instead of the default normal distribution. It also carries a new quality model profile learned from more recent datasets generated by RSII P5/C3 sequencing chemistry

(https://github.com/PacificBiosciences/DevNet/wiki/Arabidopsis-lyrata).

Table 1: iWGS will choose the simulator automatically depending on the target read type and read length.

	SE	PE	MP	НМР	PacBio CLR
ART		> 100bp	> 100bp	> 100bp	
pIRS		≤ 100bp	≤ 100bp	≤ 100bp	
PBSIM					

Color key:

Supported
Unsupported

QC tools

Trimmomatic (v0.32) [4]:

http://www.usadellab.org/cms/index.php?page=trimmomatic

NextClip (v1.3) [5]: https://github.com/richardmleggett/nextclip/

Table 2: The compatibility between QC tools and read types.

		SE	PE	MP	НМР	PacBio CLR
Tuing many many tile	Quality trimming					
Trimmomatic	Adapter trimming					
NextClip	Adapter trimming					
Quake	Error correction					

Color key:

Supported
Unsupported

<u>Assembler</u>

ABYSS (v1.5.2) [7]: http://www.bcgsc.ca/platform/bioinfo/software/abyss/

ALLPATHS-LG (r51298) [8, 9]: http://www.broadinstitute.org/software/allpaths-lg/blog/

Celera Assembler (v8.2) [10, 11]: http://sourceforge.net/projects/wgs-assembler/

DISCOVAR *de novo* (r51321) [12]:

http://www.broadinstitute.org/software/discovar/blog/

MaSuRCA (v2.3.2) [13]: http://www.genome.umd.edu/masurca.html

Minia (v1.6906) [14]: http://minia.genouest.org/

SGA (v0.10.13) [15]: https://github.com/jts/sga

SOAPdenovo2 (v2.0.4) [16]:

http://sourceforge.net/projects/soapdenovo2/files/SOAPdenovo2/

(dip)SPAdes (v3.1.1) [17]: http://bioinf.spbau.ru/spades/

Velvet (v1.2.10) [18]: http://www.ebi.ac.uk/~zerbino/velvet/

Table 2: The compatibility between assemblers and read types.

	SE	PE	MPª	HMP⁵	PacBio CLR
ABYSS					
ALLPATHS-LG		overlapping			
Celera Assembler ^c					
DISCOVAR de novo		(near) overlapping			
MaSuRCA					
Minia					
SGA					
SOAPdenovo2					
(dip)SPAdes					
Velvet					

Color key:

	Require all of these		
	Require at least one of these		
Supported			
	Unsupported		

^aAlthough ABYSS, CA, MaSuRCA, Minia, SGA, SOAPdenovo2, (dip)SPAdes, and Velvet can perform *de novo* assembly using only MP libraries, it is highly recommended that only high-quality MP ("HMP") data should be used in such cases;

^bABYSS, CA (illumina only assembly), and MaSuRCA will only use HMP libraries for scaffolding;

^cIt is recommend to have at least 50x coverage CLR reads for a PacBio only assembly, or at least 20x coverage CLR reads for a hybrid assembly.

Evaluation

QUAST (v2.3): http://bioinf.spbau.ru/quast/

Additional tools

AMOS (v3.1.0) [19]: http://sourceforge.net/projects/amos/

* the "bank-transact" included in the AMOS package is required for Celera Assembler to perform hybrid assembly using both high-quality short reads (e.g. Illumina) and PacBio CLR reads.

BLASR [20]: https://github.com/PacificBiosciences/blasr/

PBDAGCON: https://github.com/PacificBiosciences/pbdagcon/

* BLASR and PBDAGCON are both required for Celera Assembler to run with the slower but more sensitive consensus module "pbdagcon". If either one is missing, the faster module "falcon_sense" will be used instead.

picard.jar (v1.125): http://broadinstitute.github.io/picard/

* FastqToSam.jar is part of the Picard package; it is required by DISCOVAR *de novo* to convert FastQ files to BAM format.

BWA (v0.7.10) [21]: http://sourceforge.net/projects/bio-bwa/

SAMtools (v 1.1) [22]: http://www.htslib.org/

* BWA and SAMtools are both required for SGA to perform scaffolding.

KmerGenie (v1.6741) [23]: http://kmergenie.bx.psu.edu/

* KmerGenie can be invoked to estimate the "best" k-mer length for assembly protocols that involve one of these assemblers: ABYSS, SOAPdenovo2, (dip)SPAdes, and Velvet.

Installation

This section contains information on how to install the iWGS pipeline and its prerequisites.

iWGS

The main iWGS pipeline does not require any installation, and can be run on Linux or Mac OS. To obtain and run iWGS, type:

- 1) wget [github link missing currently]
- 2) tar xvf iwgs-[version].tar.gz
- 3) cd iwgs-[version]
- 4) ./iWGS

Pre-compiled tools

Pre-compiled binaries for Linux and/or Mac OS are available for some of the supported tools. We thus include these pre-compile tools with the iWGS package so there is no need to install these tools separately:

Reads simulator:

ART: Linux, Mac OS

pIRS: Linux

* The pre-complied binary has a bug, which hopefully will get fixed in future. For now, you will have to compile from source code.

PBSIM: Linux

* The pre-compiled binary is only available for the original version. The source code of the modified version is provided separately.

QC tools:

Trimmomatic: Linux, Mac OS

Assembler:

Celera Assembler: Linux, Mac OS

MaSuRCA Linux

SOAPdenovo2: Linux, Mac OS (dip)SPAdes: Linux, Mac OS

Evaluation:

QUAST: Linux, Mac OS

Additional tools:

BWA Linux

picard.jar Linux, Mac OS

SAMtools Linux

Installation reminders/tips for other tools

For other tools, please follow their respective instructions for proper installation. Some reminders/tips are provided here to facilitate a smooth installation (and execution).

Potential dependencies:

BamTools: https://github.com/pezmaster31/bamtools

Boost: http://www.boost.org/

gtest: https://code.google.com/p/googletest/

HDF5: http://www.hdfgroup.org/HDF5/

jemalloc: http://www.canonware.com/jemalloc/

Jellyfish: http://www.cbcb.umd.edu/software/jellyfish/

log4cpp: http://log4cpp.sourceforge.net/

sparsehash: https://code.google.com/p/sparsehash/

zlib: http://www.zlib.net/

Reads simulator:

pIRS:

- 1) modify the <pirs-dir>/src/pirs/Makfile:
 - a. on the first line, replace "/usr/local/share/pirs" with <pirs-dir>/src/Profiles;
 - b. requires zlib: if you do not have zlib already, install zlib first, and add the following to the sixth line ("CFLAGS += -static"):

-L<zlib-lib-dir> -l<zlib-include-dir>.

- 2) modify the <pirs-dir>/src/stator/gcContCvgBias/Makefile:
 - a. requires zlib: if you do not have zlib already, install zlib first, and add the following to the fourth line ("CFLAGS += -static"):

-L<zlib-lib-dir> -l<zlib-include-dir>.

QC tools:

NextClip:

1) simply "make all".

Quake:

- 1) requires Boost: if you do not have Boost already, install Boost, and update the second line ("CFLAGS") in <quake-dir>/src/Makefile;
- 2) requires Jellyfish (use version 1.* only; Quake is not compatible with v2.0 or above): install Jellyfish and place a link of jellyfish binary to the <quake-dir>/bin folder;
- 3) install VGAM library in R.

Assembler:

ABYSS:

- requires Boost: if you do not have Boost already, install Boost, and add the "--with-boost=<boost-include-dir>" option while running the "configure" script;
- 2) requires sparsehash: install sparsehash, and add the "CPPFLAGS=l<sparsehash-include-dir>" option while running the "configure" script;
- 3) to enable the use of multi-threads, add the "--with-mpi=<openmpi-dir>" option while running the "configure" script; the exact <openmpi-dir> may vary depending on your environment: e.g. /usr/local/openmpi/latest/x86_64/gcc46 (ACCRE); /usr/lib/openmpi (my PC);
- 4) by default, ABYSS accepts k-mer sizes up to 64; to allow larger k-mer sizes, add the "--enable-maxk=<value>" (<value> should be a multiple of 32) option while running the "configure" script.

ALLPATHS-LG:

- requires GCC version ≥ 4.7.0 to compile and run (make sure you have the right GCC version when ALLPATHS-LG is executed!);
- 2) if you do not have access to GCC version ≥ 4.7.0, please use the ALLPATHS-LG version 44837 or earlier;
- 3) keep in mind that the memory consumption of ALLPATHS-LG will be extremely high when using PacBio data.

DISCOVAR de novo:

- 1) requires GCC version ≥ 4.7.0 to compile and **run** (make sure you have the right GCC version when DISCOVAR *de novo* is executed!);
- 2) unfortunately, there is no version of DISCOVAR *de novo* that is compatible with GCC version < 4.7.0;
- 3) requires jemalloc; if you do not have jemalloc already, install jemalloc (version \geq 3.6.0), and add the "--with-jemalloc=<jemalloc-lib-dir>" option while running the "configure" script.

SGA:

- 1) requires sparsehash: install sparsehash, and add the "--with-sparsehash=<sparsehash-dir>" option while running the "configure" script;
- requires BamTools: install BamTools, and add the "--withbamtools=<bamtools -dir>" option while running the "configure" script;
- 3) requires zlib;
- 4) suggests jemalloc: if you do not have jemalloc already, install jemalloc (version ≥ 3.6.0), and add the "--with-jemalloc=<jemalloc-lib-dir>" option while running the "configure" script.

Velvet:

- by default, Velvet accepts up to two datasets ("categories"); to allow more than two datasets, add the "CATEGORIES=<value>" option while running the "make" command;
- 2) by default, Velvet accepts k-mer sizes up to 31; to allow larger k-mer sizes, add the "MAXKMERLENGTH=<value>" option while running the "make" command.
- 3) to allow the assembly of datasets with more than 2.2 billion reads, add the option "BIGASSEMBLY=1" option while running the "make" command;
- 4) to enable the use of multi-threads, add the "OPENMP=1" option while running the "make" command.

Evaluation tools:

OUAST:

1) Run "quast.py -test" before the first use.

Additional tools:

AMOS:

1) an error encountered when trying to compile with GCC (version \geq 4.9.0); earlier GCC versions (e.g. 4.6) seem work fine.

BLASR:

- 1) requires HDF5:
 - a. it is recommended to have a fresh installation of HDF5 (version
 1.8.10 or above tested, add the "--enable-cxx" option while running the "configure" script);
 - b. modify the \$path_to_blasr/common.mk file to change "HDF5INCLUDEDIR" (fifth line) and "HDF5LIBDIR" (sixth line) accordingly;
 - c. if errors related to hdf5lib occur, add \$path_to_hdf5/lib to the \$LD_LIBRARY_PATH environmental variable.

PBDAGCON:

- 1) use the same GCC version for all the following dependencies (version 4.6.1 tested);
- 2) requires Boost (version 1.47 tested; version 1.46 is also compatible according to the manual);
- 3) requires log4cpp (version 1.0 or 1.1);
- 4) requires gtest (version 1.3.0 or above);
- 5) do the following:
 - a. unzip pbdagcon-master.zip
 - b. cd pbdagcon-master
 - c. git clone https://github.com/pbjd/alignment.git
 - d. git clone https://github.com/pbjd/pbdata.git
 - e. modify "src/cpp/pbi.mk" to change "BOOST", "LOG4CPP", "GTEST", "INCDIRS", and "LIBDIRS" accordingly
 - f. make
 - g. the binary file of pbdagcon will be generated in src/cpp

KmerGenie:

- 1) by default, KmerGenie evaluates k-mer sizes up to 121; to allow the evaluation of larger k-mer sizes, do the following:
 - a. make clean
 - b. make k=<value>

Running iWGS

iWGS uses both command line options and a control file to collect all information it needs to carry out an analysis.

Command line options

Basic options:

-s settings <string></string>	the control file that contains all information for a iWGS run (see the "control file" section for detailed explanation)
-g genome <string></string>	the reference genome sequence in FASTA format
-t threads <int></int>	the number of threads to use (default: 1)
-m memory <int></int>	the number of GBs of memory to use (default: 8)
-o out_dir <string></string>	the directory to store all outputs, will be created if not
	already exists (default: ./)
-p price <string></string>	provide pricing information to calculate the cost of each
	library and assembly protocol
-c cleanup	whether to remove simulated reads and files generated
	by assemblers after the iWGS run
-r overwrite	whether to redo the simulation/QC/assembly if the
	corresponding files already exist
-v verify	verify the settings and quit

Advanced options:

Advanced options:		
Mode	1:	iWGS can run in three modes: (default: 1) get parameters from command line / control file, and finish all steps (reads simulation, assembly, and evaluation) in a single run
	2:	get parameters from command line / control file, and generate three configuration files for library, assembly protocol, and miscellaneous options, respectively, which would allow each library / assembly protocol to have different parameters (see the "advanced configuration files" section for detailed explanation)
Conf	3:	restart from the configuration files generated in Mode 2 the configuration files for library, assembly protocol, and miscellaneous options, separated by comma; to be used in Mode 3
Real		run iWGS with real datasets

Control file

The control file consists of the following sections (see Appendix for the complete control file):

General options:

These general options in the control file are the same as corresponding command line options, and will override the command line options if both are specified.

genome = out_dir = threads = memory =

Library options:

Each library option line starts with the key word "library" and contains the information for a library to be simulated, in the format of four to six parameters separated by comma. The number and meaning of the parameters needed for a library vary with different read types:

	1 st	2 nd	3 rd	4 th	5 th	6 th
	parameter	parameter	parameter	parameter	parameter	parameter
SE						
PE	Library	Dood tupo	Coverage	Read length	Average	SD of
MP	name	Read type	Coverage		insert size	insert size
CLR				Average	SD of	
CLIN				accuracy	accurary	

Note: there is no need to specify the reads simulator; iWGS will make the choice automatically based on the read type and other specifics of the library.

Example 1: a 100bp SE library "L001" with 50x coverage. library = L001,SE,50,100

Example 2: a 100bp PE library "L002" with 50x coverage, average insert size of 180bp, and SD of insert size of 9bp.

library = L002,PE,50,100,180,9

Example 3: a 100bp MP library "L003" with 50x coverage, average insert size of 2000bp, and SD of insert size of 100bp.

library = L003,MP,50,100,2000,100

Example 4: a 100bp HMP library "L004" with 50x coverage, average insert size of 5000bp, and SD of insert size of 250bp.

library = L004,HMP,50,100,5000,250

Example 5: a PacBio CLR library "L005" with 50x coverage, average read accuracy of 0.85, and SD of read accuracy of 0.02.

library = L005, CLR, 50, 0.85, 0.02

Simulator options:

Each simulator option line starts with a keyword in the format of: "[name_of_simulator].[option_of_simulator]". These options are used to set parameters for read simulators. Leave the options blank to use the default values.

Note: these parameters are applied universally to all libraries simulated by the corresponding simulator.

Example 1: set the substitution error rate for pIRS pIRS.error rate =

Example 2: set the amount to shift every first-read quality score for ART ART.qual_shift1 =

Example 3: set the maximum read accuracy for PBSIM PBSIM.accuracy_max =

Quality control options:

The option QC takes a list of library names (separated by comma) or the word "all" to perform preprocessing of selected or all of the libraries. Leave the option blank to skip the QC step for all libraries.

OC =

Each QC tool option line starts with a keyword in the format of:

"[name_of_tool].[option_of_tool]". These options are used to set parameters for QC tools. Leave the options blank to use the default values.

Note: these parameters are applied universally to all libraries that will be processed by the corresponding QC tools.

Example 1: set the quality trimming threshold for Trimmomatic Trimmomatic.trailing =

Example 2: set the adapter sequence for NextClip NextClip.adapter =

Example 3: set the k-mer size for Quake

Quake.kmer =

Assembly protocol options:

Each assembly protocol option line starts with the key word "protocol" and contains the information for an assembly protocol, in the format of three or more parameters separated by comma. The number and meaning of the parameters needed for an assembly protocol are shown below:

1 st parameter 2 nd parameter		3 rd n th parameters		
Protocol name	Assembler name	Names of libraries to be included		

Example 1: an assembly protocol "P002" using the assembler ALLPAHTS-LG, and libraries L002 (overlapping PE), L003 (MP), L004 (HMP), and L005 (PacBio CLR). Protocol = P002,ALLPATHS,L002,L003,L004,L005

Example 2: an assembly protocol "P010" using the assembler SOAPdenovo2, and libraries L001 (SE), L002 (PE), L003 (MP), and L004 (HMP). protocol = P010,SOAPdenovo2,L001,L002,L003,L004

Assembler options:

Each assembler option line starts with a keyword in the format of: "[name_of_assembler].[option_of_assembler]". These options are used to set parameters for *de novo* genome assemblers. Leave the options blank to use the default values.

Note: these parameters are applied universally to all assembly protocols using the genome assembler.

Example 1: set the k-mer size to be used for SOAPdenovo2; the default value ("0") indicates that the k-mer size is to be estimated.

SOAPdenovo2.kmer = 0

Example 2: set additional options for SPAdes; the text between quotation marks will be passed to the assembler.

SPAdes.option = "--only-assembler"

Evaluation options:

Each evalution option line starts with a keyword in the format of: "[name_of_evaluator].[option_of_evaluator]". These options are used to set parameters for genome assembly assessment tools. Leave the options blank to use the default values.

Example 1: whether the genome to evaluate is eukaryotic QUAST.eukaryote = 1

Example 2: whether to run QUAST in "GAGE" mode QUAST.gage = 1

Example 3: to provide a gene annotation file for QUAST (only effective in full evaluation mode)

QUAST.gene =

Executable options:

Each executable option line starts with a keyword in the format of: "bin.[name_of_executable]". These options are used to set path information for needed executables. Leave the options blank if the executables are available in PATH environmental variable.

Example 1: set the path to the pIRS executable, "pirs" bin.pIRS =

Example 2: set the path to SPAdes executable, "spades.py" bin.SPAdes =

Example 3: set the path to QUAST executable, "quast.py" bin.QUAST =

Advanced configuration files

One limitation of the control file is that the simulator/assembler related parameters will be applied universally to all relevant libraries / assembly protocols. iWGS allows advanced users to set parameters specific to each library / assembly protocol in the following way:

- run iWGS in Mode 2 (advanced option); iWGS will collect information from command line options and/or the control file, and generate three configuration files for library, assembly protocol, and miscellaneous options, respectively;
- 2) modify the configuration files to set library /assembly protocol specific parameters;
- 3) run iWGS in Mode 3 to resume the analysis from the modified configuration files.

The three configuration files are explained as below (see Appendix for exemplar configuration files):

Library configuration file: (default name: libraries.conf)

This file contains one section for each library, and all keywords are in the format of: "[library_name].[option_name]".

All libraries have three common options: (using L001 as example)

```
L001.read_type = SE
L001.simulator = ART
L001.depth = 50
```

Note: the "read_type" and "simulator" options are for users' reference only, please do not modify.

Other available options vary depend on the read type, simulator, and QC settings; for example:

```
L001.qual_shift1 =

L001.qual_profile1 =

L001.ins_rate1 =

L001.del_rate1=

L001.QC = 1

L001.tm-trailing = 3

L001.tm-minlen = 25

L001.qk-kmer = 0

L001.qk-minlen = 25
```

Since L001 is a SE library, only the ART parameters for the first-read are available. Trimmomatic quliaty-trimming and Quake error-correction will also be performed on L001.

Assembly protocol configuration file: (default name: protocols.conf)

This file contains one section for each assembly protocol, and all keywords are in the format of: "[protocol_name].[option_name]".

All protocols have two common options: (using P010 as example)

```
P010.library = L001,L002,L003,L004
P010.assembler = SOAPdenovo2
```

Note: the "assembler" options are for users' reference only, please do not modify.

Other available options vary depend on the assembler; for example:

```
P001.kmer = 0
P001.option = "-F -R -E -w -u"
```

The default value for "option" (the extra command to pass to the assembler: SOAPdenovo2) is taken from the recipes of GAGE-B project [24].

Miscellaneous option configuration file: (default name: misc.conf)

This file contains all the general options, evaluation options, and executable options, which are in the same format as in the control file.

Output

iWGS will create five directories under the "out dir" directory:

- \$out_dir/libraries/ this directory contains all simulated reads; each simulated library will be stored in a separate subdirectory with the same name as the library; this folder will be removed if the "cleanup" command line option is turned on;
- \$out_dir/preprocessed/ this directory contains all reads after preprocessing; each library will be stored in a separate subdirectory with the same name as the library; this folder will be removed if the "cleanup" command line option is turned on;
- 3) \$out_dir/protocols/ this directory contains the results of all assembly protocols; files generated by each assembly protocol will be stored in a separate subdirectory with the same name as the protocol; this folder will be removed if the "cleanup" command line option is turned on;
- 4) \$out_dir/logs/ this directory contains log files for all library simulation, assembly, and evaluation steps;
- 5) \$out_dir/assemblies/ this directory contains copies of all successfully assembled contig/scaffold files;
- 6) \$out_dir/evaluation/ this directory contains the results of QUAST evaluations; copies of the main evaluation reports can be found in this directory; two subdirectores, "contigs/" and "scaffolds/", will be created to store the detailed evaluation results on assembled contigs and scaffolds, respectively.

Examples

A quick and simple iWGS analysis:

A quick and simple iWGS analysis can be carried out without using a control file, in which case the only required option is the reference genome ("-g"). iWGS will simulate the following two libraries:

Name	Read type	Simulator	Read length	Coverage	Average insert size	SD of insert size
L001	PE	pIRS	100bp	50x	180bp	9bp

		L002	MP	pIRS	100bp	50x	3000bp	150bp
--	--	------	----	------	-------	-----	--------	-------

and evaluate the following two assembly protocols:

Name	Assembler	Libraries	Note
P001	SOAPdenovo2	L001, L002	k-mer size to be estimated
P002	ALLPATHS-LG	L001, L002	

iWGS will behave in the same way in cases where a control file is provided but no library and assembly protocol is specified.

Exemplar command:

iWGS -g Kazachestania_africana.fa -t 8 -m 32 -o K_africana

Run with library / assembly protocol specific parameters:

- 1) collect information from the control file and generate configuration files: iWGS -s K africana.ctl --Mode 2
- 2) modify the configuration files;
- 3) resume the analysis:

iWGS --Mode 3 --Conf libraries.conf,protocols.conf,misc.conf

Using iWGS to analyze real datasets:

iWGS can also be used to analyze real datasets, providing a convenient way for users to try multiple assembler/parameter combinations on their own data and evaluate the resulting assemblies.

- create the output directory (\$out_dir) and the "real_data" subdirectory (\$out_dir/real_data);
- 2) under the "real_data" directory, create a subdirectory for each real dataset to place the corresponding data file(s); the names of the subdirectory the data files should follow the naming convention of iWGS:

Read type	Subdirectory name	Data file name	
SE, PacBio CLR	[libuan a paga]a	[library_name].fq	
PE, MP	[library_name] ^a	[library_name]_1.fq, [library_name]_2.fq	

^athe [library name] can be any legitimate name for the library.

- 3) in the iWGS control file, create a library option line for each real dataset; real specs (e.g. coverage, read length) of the libraries should be provided;
- 4) run iWGS with the "Real" option:# Exemplar command:

iWGS -s real_data.ctl -r 0 -c 0 --Real

Note: similarly, with proper library options in the control file, iWGS can analyze real datasets together with simulated data. The users can use this feature to evaluate the potential improvements additional datasets may have on existing real data.

References

- 1. Huang, W., et al., *ART: a next-generation sequencing read simulator.* Bioinformatics, 2012. **28**(4): p. 593-4.
- 2. Hu, X., et al., *pIRS: Profile-based Illumina pair-end reads simulator*. Bioinformatics, 2012. **28**(11): p. 1533-5.
- 3. Ono, Y., K. Asai, and M. Hamada, *PBSIM: PacBio reads simulator--toward accurate genome assembly.* Bioinformatics, 2013. **29**(1): p. 119-21.
- 4. Bolger, A.M., M. Lohse, and B. Usadel, *Trimmomatic: a flexible trimmer for Illumina sequence data*. Bioinformatics, 2014. **30**(15): p. 2114-20.
- 5. Leggett, R.M., et al., *NextClip: an analysis and read preparation tool for Nextera Long Mate Pair libraries*. Bioinformatics, 2014. **30**(4): p. 566-8.
- 6. Kelley, D.R., M.C. Schatz, and S.L. Salzberg, *Quake: quality-aware detection and correction of sequencing errors.* Genome Biol, 2010. **11**(11): p. R116.
- 7. Simpson, J.T., et al., *ABySS: a parallel assembler for short read sequence data.* Genome Res, 2009. **19**(6): p. 1117-23.
- 8. Gnerre, S., et al., *High-quality draft assemblies of mammalian genomes from massively parallel sequence data*. Proc Natl Acad Sci U S A, 2011. **108**(4): p. 1513-8.
- 9. Ribeiro, F.J., et al., *Finished bacterial genomes from shotgun sequence data*. Genome Res, 2012. **22**(11): p. 2270-7.
- 10. Myers, E.W., et al., *A whole-genome assembly of Drosophila*. Science, 2000. **287**(5461): p. 2196-204.
- 11. Koren, S., et al., *Reducing assembly complexity of microbial genomes with single-molecule sequencing.* Genome Biol, 2013. **14**(9): p. R101.
- 12. Weisenfeld, N.I., et al., *Comprehensive variation discovery in single human genomes*. Nat Genet, 2014.
- 13. Zimin, A.V., et al., *The MaSuRCA genome assembler*. Bioinformatics, 2013. **29**(21): p. 2669-77.
- 14. Salikhov, K., G. Sacomoto, and G. Kucherov, *Using cascading Bloom filters to improve the memory usage for de Brujin graphs*. Algorithms for Molecular Biology, 2014. **9**.
- 15. Simpson, J.T. and R. Durbin, *Efficient de novo assembly of large genomes using compressed data structures*. Genome Res, 2012. **22**(3): p. 549-56.
- 16. Luo, R., et al., SOAPdenovo2: an empirically improved memory-efficient short-read de novo assembler. Gigascience, 2012. **1**(1): p. 18.
- 17. Bankevich, A., et al., SPAdes: a new genome assembly algorithm and its applications to single-cell sequencing. J Comput Biol, 2012. **19**(5): p. 455-77.
- 18. Zerbino, D.R. and E. Birney, *Velvet: algorithms for de novo short read assembly using de Bruijn graphs*. Genome Res, 2008. **18**(5): p. 821-9.
- 19. Schatz, M.C., et al., *Hawkeye and AMOS: visualizing and assessing the quality of genome assemblies.* Brief Bioinform, 2013. **14**(2): p. 213-24.

- 20. Chaisson, M.J. and G. Tesler, *Mapping single molecule sequencing reads using basic local alignment with successive refinement (BLASR): application and theory.* BMC Bioinformatics, 2012. **13**: p. 238.
- 21. Li, H. and R. Durbin, *Fast and accurate short read alignment with Burrows-Wheeler transform*. Bioinformatics, 2009. **25**(14): p. 1754-60.
- 22. Li, H., et al., *The Sequence Alignment/Map format and SAMtools*. Bioinformatics, 2009. **25**(16): p. 2078-9.
- 23. Chikhi, R. and P. Medvedev, *Informed and automated k-mer size selection for genome assembly*. Bioinformatics, 2014. **30**(1): p. 31-7.
- 24. Magoc, T., et al., *GAGE-B*: an evaluation of genome assemblers for bacterial organisms. Bioinformatics, 2013. **29**(14): p. 1718-25.

Appendices

Appendix A. One complete control file

```
# General options
################################
genome = /home/xiaofan/iWGS/example/Kazachstania_africana.fa # the reference genome sequence
in fasta format
                                                    # all outputs will be written to the folder ./K african
out dir = K africana
threads = 4
                                                    # number of CPUs to use (default: 1)
memory = 32
                                                    # number of GBs of memory to use (default: 8)
##################################
# Library options
####################################
                                                    # Illumina 100bp SE library "L001" - coverage: 50x
library = L001, SE, 50, 100
                                                    # Illumina 100bp PE library "L002" - coverage: 50x;
library = L002,PE,50,100,180,9
average insert size: 180bp; SD of insert size: 9bp
library = L003,MP,50,100,2000,100
                                                    # Illumina 100bp MP library "L003" - coverage: 50x;
average insert size: 5000bp; SD of insert size: 250bp
library = L004,HMP,50,100,5000,250
                                                    # Illumina 100bp MP library "L003" - coverage: 50x;
average insert size: 5000bp; SD of insert size: 250bp
library = L005,CLR,50,0.85,0.02
                                                    # PacBio CLR library "L003" - coverage: 50x; average
read accuracy: 0.85; SD of read accuracy: 0.02
library = L006,PE,50,250,450,23
                                                    # Illumina 250bp PE library "L005" - coverage: 50x;
average insert size: 450bp; SD of insert size: 23bp
# Simulator options
#################################
pIRS.error_rate =
                                                    # substitution error rate: 0, 1, or 0.0001-0.63
(default: 1 - indicate that the default setting of pIRS should be used)
pIRS.error profile =
                                                    # the base-calling profile for simulating
substitution-error and quality score (default: the default profile of pIRS)
pIRS.gc =
                                                    # whether to simulate GC bias: 1 - yes; 0 - no
(default: 1)
pIRS.gc_profile =
                                                    # the GC content-coverage file for simulating GC
bias (default: the default profile of pIRS)
pIRS.indel =
                                                    # whether to simulate indel errors: 1 - yes; 0 - no
(default: 1)
pIRS.indel_profile =
                                                    # the InDel-error profile for simulating InDel-error
(default: the default profile of pIRS)
ART.qual shift1 =
                                                    # the amount to shift the quality score of all first-
reads (default: 0)
ART.qual shift2 =
                                                    # the amount to shift the quality score of all second-
reads (default: 0)
ART.qual_profile1 =
                                                    # the quality profile of first-reads (default: the
default profile of ART)
```

```
ART.qual_profile2 =
                                                    # the quality profile of second-reads (default: the
default profile of ART)
                                                    # the insertion rate of first-reads (default: 0.00009)
ART.ins_rate1 =
                                                    # the insertion rate of second-reads (default:
ART.ins rate2 =
0.00015)
ART.del rate1 =
                                                    # the deletion rate of first-reads (default: 0.00011)
                                                    # the deletion rate of second-reads (default:
ART.del rate2 =
0.00023)
PBSIM.model_qc =
                                                    # the model of quality code for simulating read
accuracy (default: the default profile of PBSIM)
PBSIM.ratio =
                                                    # the ratio of substitution:insertion:deletion errors
(default: 10:60:30)
PBSIM.accuracy_max =
                                                    # the maximum read accuracy (default: 0.90)
PBSIM.accuracy_min =
                                                    # the minimum read accuracy (default: 0.75)
PBSIM.length_mean =
                                                    # the mean of read length (default: 3000)
PBSIM.length_sd =
                                                    # the standard deviation of read length (default:
2300)
PBSIM.length max =
                                                    # the maximum read length (default: 25000)
PBSIM.length min =
                                                    # the minimum read length (default: 100)
####################################
# Quality control options
###################################
QC = L001,L002,L003,L004
                                                    # provide a list of library names (or "all") to perform
quality control on selected (or all) libraries
Trimmomatic.trailing =
                                                    # default: 3; the threshold for quality trimming from
3'-end of reads
Trimmomatic.adapters =
                                                    # a file containing adapter sequence files for each
library to perform adapter trimming
Trimmomatic.minlen =
                                                    # default: 25; minimum read length after
Trimmomatic trimming
NextClip.adapter =
                                                    # default: "CTGTCTCTTATACACATCT"; adapter
sequence for adapter trimming
NextClip.minlen =
                                                    # minimum read length after NextClip trimming
Ouake.kmer =
                                                    # default 0 - to estimate based on genome size
Ouake.minlen =
                                                    # minimum read length after Quake error-
correction
#################################
# Assembly protocol options
####################################
protocol = P001,ABYSS,L001,L002,L003,L004
                                                    # assembly protocol "P001" that uses the ABYSS
assembler and libraries "L001", "L002", "L003", and "L004"
protocol = P002,ALLPATHS,L002,L003, L004
                                                    # assembly protocol "P002" that uses the
ALLPATHS-LG assembler and libraries "L002", "L003", and "L004"
```

```
protocol = P003,CA,L001,L002,L003,L004
                                                  # assembly protocol "P003" that uses the Celera
Assembler and libraries "L001", "L002", "L003", and "L004" - assembly of only illumine data
protocol = P004,CA,L001,L002,L004,L005
                                                  # assembly protocol "P004" that uses the Celera
Assembler and libraries "L001", "L002", "L003", and "L005" - hybrid assembly of illumine and PacBio data
protocol = P005,CA,L005
                                                   # assembly protocol "P005" that uses the Celera
Assembler and the library "L005" - assembly of only PacBio data
protocol = P006,DISCOVAR,L006
                                                   # assembly protocol "P006" that uses the DISCOVAR
de novo assembler and the library "L006"
protocol = P007,MaSuRCA,L001,L002,L003,L004
                                                   # assembly protocol "P007" that uses the MaSuRCA
assembler and libraries "L001", "L002", "L003", and "L004"
protocol = P008, Minia, L001, L002, L004
                                                   # assembly protocol "P008" that uses the Minia
assembler and libraries "L001", "L002", and "L004"
protocol = P009,SGA,L001,L002,L003,L004
                                                  # assembly protocol "P009" that uses the SGA
assembler and libraries "L001", "L002", "L003", and "L004"
protocol = P010,SOAPdenovo2,L001,L002,L003,L004
                                                           # assembly protocol "P010" that uses the
SOAPdenovo2 assembler and libraries "L001", "L002", "L003", and "L004"
protocol = P011,SPAdes,L001,L002,L003,L004,L005 # assembly protocol "P011" that uses the SPAdes
assembler and libraries "L001", "L002", "L003", "L004", and "L005"
protocol = P012, Velvet, L001, L002, L003, L004
                                                  # assembly protocol "P012" that uses the Velvet
assembler and libraries "L001", "L002", "L003", and "L004"
# Assembler options
####################################
ABYSS.kmer =
                                                  # default: 0 - to be estimated using KmerGenie
ABYSS.option = "l=1 n=5 s=100"
                                                  # GAGE-B recipe
ALLPATHS.ploidy =
                                                  # default: 1; set to 2 for heterozygous assembly
= 2N2da.A2
                                                   # default 1; set to 0 to use "pbdagcon" instead of
"falcon"
CA.sensitive =
                                                   # default: 0; set to 1 for lower-quality PacBio data
MaSuRCA.kmer =
                                                   # default: 0 - to be selected automatically
Minia.kmer =
                                                   # default: 0 - to be estimated using KmerGenie
Minia.min-abundance =
                                                  # default: 0 - to be estimated using KmerGenie
SGA.kmer =
                                                   # default: 31; the k-mer size for the "correct"
module
SGA.min-overlap =
                                                  # default: 45; the overlap size for the "overlap"
module
SGA.assemble-overlap =
                                                   # default: 75; the overlap size for the "assemble"
module
SPAdes.kmer =
                                                   # default: 0 - to be estimated using KmerGenie
SPAdes.multi-kmer =
                                                   # default: 1 - to use multiple k-mer sizes
SPAdes.option = "--only-assembler"
                                                   # set it empty (i.e. "") to enable the error-correction
module
```

```
SOAPdenovo2.kmer =
                                                                                           # default: 0 - to be estimated using KmerGenie
SOAPdenovo2.option = "-F -R -E -w -u"
                                                                                           # GAGE-B recipe
Velvet.kmer =
                                                                                           # default: 0 - to be estimated using KmerGenie
                                                                                           # GAGE-B recipe
Velvet.option = "-exp_cov auto -scaffolding yes"
###################################
# Evaluation options
################################
QUAST.eukaryote =
                                                                                           # whether the reference genome is eukaryotic: 1 -
yes; 0 - no (default: 1)
QUAST.gage =
                                                                                           # whether to generate GAGE report: 1 - yes; 0 - no
(default: 1)
QUAST.gene = example/Kazachstania_africana.genes
                                                                                                         # gene annotations to be used for
evaluation (default: NA)
###############################
# Executable options
################################
bin.pIRS = /home/xiaofan/iWGS/tools/pIRS/pirs
bin.ART =/home/xiaofan/iWGS/tools/ART/art illumina
bin.PBSIM = /home/xiaofan/iWGS/tools/PBSIM/bin/pbsim
bin. Trimmo matic = /home/xia of an/iWGS/tools/Trimmo matic/trimmo matic. jar and the following properties of th
bin.NextClip = /home/xiaofan/iWGS/tools/NextClip/bin/nextclip
bin.Quake = /home/xiaofan/iWGS/tools/Quake/bin/quake.py
bin.KmerGenie = /home/xiaofan/iWGS/tools/kmergenie/kmergenie
bin.ABYSS = /home/xiaofan/iWGS/tools/ABYSS/bin/abyss-pe
bin.ALLPATHS = /home/zhoux8/usr/bin/allpathslg/bin/RunAllPathsLG
bin.PBcR = /home/xiaofan/iWGS/tools/CA/Linux-amd64/bin/PBcR
bin.runCA = /home/xiaofan/iWGS/tools/CA/Linux-amd64/bin/runCA
bin.DISCOVAR = /home/xiaofan/iWGS/tools/Discovar/bin/DiscovarExp
bin.MaSuRCA = /home/xiaofan/iWGS/tools/MaSuRCA/bin/masurca
bin.Minia = /home/xiaofan/iWGS/tools/Minia/minia
bin.SGA = /home/xiaofan/iWGS/tools/SGA/bin/sga
bin.SOAPdenovo2 = /home/xiaofan/iWGS/tools/SOAPdenovo2
bin.SPAdes = /home/xiaofan/iWGS/tools/SPAdes/bin/spades.py
bin.dipSPAdes = /home/xiaofan/iWGS/tools/SPAdes/bin/dipspades.py
bin.velvetg = /home/xiaofan/iWGS/tools/Velvet/velvetg
bin.velveth = /home/xiaofan/iWGS/tools/Velvet/velveth
bin.QUAST = /home/xiaofan/iWGS/tools/QUAST/quast.py
bin.AMOS = /home/xiaofan/iWGS/tools/dependencies/bank-transact
bin.BLASR = /home/xiaofan/iWGS/tools/dependencies/blasr
bin.BWA = /home/xiaofan/iWGS/tools/dependencies/bwa
bin.PBDAGCON = /home/xiaofan/iWGS/tools/dependencies/pbdagcon
bin.Picard = bin.AMOS = /home/xiaofan/iWGS/tools/dependencies/picard.jar
bin.SAMtools = /home/xiaofan/iWGS/tools/dependencies/samtools
```

Appendix B. Exemplar configuration files

Library configuration file: (one example for each read type)

```
# Library options
#################################
# parameters for the library L001
L001.read_type = SE
L001.depth = 50
L001.simulator = ART
L001.read length = 100
L001.qual\_shift1 = 0
L001.qual_profile1 =
L001.ins rate1 = 0.00009
L001.del rate1 = 0.00011
L001.QC = 1
L001.tm-trailing = 3
L001.tm-adapter = /home/xiaofan/iWGS/example/TruSeq-SE.fa
L001.tm-minlen = 25
L001.qk-kmer = 15
L001.qk-minlen = 25
# parameters for the library L002
L002.read type = PE
L002.depth = 50
L002.simulator = pIRS
L002.read_length = 100
L002.frag_mean = 180
L002.frag_sd = 9
L002.error_rate = 1
L002.error profile =
L002.gc = 1
L002.gc_profile =
L002.indel = 1
L002.indel profile =
L002.QC = 1
L002.tm-trailing = 3
L002.tm-adapter = /home/xiaofan/iWGS/example/TruSeq-PE.fa
L002.tm-minlen = 25
L002.qk-kmer = 15
L002.qk-minlen = 25
# parameters for the library L003
L003.read_type = MP
L003.depth = 50
L003.simulator = pIRS
L003.read_length = 100
L003.frag mean = 2000
L003.frag_sd = 100
L003.error_rate = 1
L003.error_profile =
L003.gc = 1
```

##################################

L003.gc_profile =
L003.indel = 1
L003.indel_profile =
L003.QC = 1
L003.tm-trailing = 3
L003.tm-minlen = 25
L003.nc-adapter = CTGTCTCTTATACACATCT
L003.nc-minlen = 25

parameters for the library L004

 $L004.read_type = HMP$

L004.depth = 50

L004.simulator = pIRS

 $L004.read_length = 100$

 $L004.frag_mean = 5000$

 $L004.frag_sd = 250$

L004.error_rate = 1

L004.error_profile =

L004.gc = 1

L004.gc_profile =

L004.indel = 1

L004.indel_profile =

L004.QC = 1

L004.tm-trailing = 3

L004.tm-minlen = 25

L004.nc-adapter = CTGTCTCTTATACACATCT

L004.nc-minlen = 25

L004.qk-kmer = 15

L004.qk-minlen = 25

parameters for the library L005

L005.read_type = CLR

L005.depth = 50

L005.simulator = PBSIM

 $L005.accuracy_mean = 0.85$

 $L005.accuracy_sd = 0.02$

 $L005.accuracy_max = 0.90$

L005.accuracy_min = 0.75

 $L005.model_qc = /home/xiaofan/iWGS/tools/PBSIM/data/model_qc_clr$

L005.ratio = 10:60:30

 $L005.length_mean = 3000$

 $L005.length_sd = 2300$

L005.length max = 25000

 $L005.length_min = 100$

L005.QC = 0

parameters for the library L006

L006.read_type = PE

L006.depth = 50

L006.simulator = ART

```
L006.read_length = 250
L006.frag_mean = 450
L006.frag_sd = 23
L006.qual\_shift1 = 0
L006.qual\_shift2 = 0
L006.qual_profile1 =
L006.qual_profile2 =
L006.ins_rate1 = 0.00009
L006.ins\_rate2 = 0.00015
L006.del rate1 = 0.00011
L006.del_rate2 = 0.00023
L006.QC = 0
Protocol configuration file: (one example for each assembler)
####################################
# Assembly protocol options
####################################
# parameters for the assembly protocol P001
P001.library = L001,L002,L003,L004
P001.assembler = ABYSS
P001.kmer = 0
P001.option = "I=1 n=5 s=100"
# parameters for the assembly protocol P002
P002.library = L002,L003,L004
P002.assembler = ALLPATHS
P002.ploidy = 1
# parameters for the assembly protocol P003
P003.library = L001,L002,L003,L004
P003.assembler = CA
P003.pbCNS = 1
P003.sensitive = 0
# parameters for the assembly protocol P004
P004.library = L001,L002,L004,L005
P004.assembler = CA
P003.pbCNS = 1
P004.sensitive = 0
# parameters for the assembly protocol P005
P005.library = L005
P005.assembler = CA
P003.pbCNS = 1
P005.sensitive = 0
# parameters for the assembly protocol P006
```

P006.library = L006

P006.assembler = DISCOVAR

```
# parameters for the assembly protocol P007
P007.library = L001,L002,L003,L004
P007.assembler = MaSuRCA
P007.kmer = 0
# parameters for the assembly protocol P008
P008.library = L001,L002,L004
P008.assembler = Minia
P008.kmer = 0
P008.min-abundance = 0
# parameters for the assembly protocol P009
P009.library = L001,L002,L003,L004
P009.assembler = SGA
P009.kmer = 31
P009.min-overlap = 45
P009.assemble-overlap = 75
# parameters for the assembly protocol P010
P010.library = L001,L002,L003,L004
P010.assembler = SOAPdenovo2
P010.kmer = 0
P010.option = "-F -R -E -w -u"
# parameters for the assembly protocol P011
P011.library = L001,L002,L003,L004,L005
P011.assembler = SPAdes
P011.kmer = 0
P011.multi-kmer = 1
P011.option = "--only-assembler"
# parameters for the assembly protocol P012
P0012.library = L001,L002,L003,L004
P0012.assembler = Velvet
P0012.kmer = 0
P0012.option = "-exp_cov auto -scaffolding yes"
Miscellaneous options configuration file:
####################################
# General options
###################################
genome = /home/xiaofan/iWGS/example/Kazachstania_africana.fa
threads = 4
memory = 32
```

#####################################

out_dir = /home/xiaofan/iWGS/example/K_africana

Evaluation options

################################

QUAST.eukaryote = 1

QUAST.gage = 1

QUAST.gene = /home/xiaofan/iWGS /example/Kazachstania_africana.genes

###################################

Executable options

################################

bin.pIRS = /home/xiaofan/iWGS/tools/pIRS/pirs

bin.ART =/home/xiaofan/iWGS/tools/ART/art_illumina

bin.PBSIM = /home/xiaofan/iWGS/tools/PBSIM/bin/pbsim

bin.Trimmomatic = /home/xiaofan/iWGS/tools/Trimmomatic/trimmomatic.jar

bin.NextClip = /home/xiaofan/iWGS/tools/NextClip/bin/nextclip

bin.Quake = /home/xiaofan/iWGS/tools/Quake/bin/quake.py

bin.KmerGenie = /home/xiaofan/iWGS/tools/kmergenie/kmergenie

bin.ABYSS = /home/xiaofan/iWGS/tools/ABYSS/bin/abyss-pe

bin. A LLPATHS = /home/zhoux8/usr/bin/allpathslg/bin/RunAllPathsLG

bin.PBcR = /home/xiaofan/iWGS/tools/CA/Linux-amd64/bin/PBcR

bin.runCA = /home/xiaofan/iWGS/tools/CA/Linux-amd64/bin/runCA

bin.DISCOVAR = /home/xiaofan/iWGS/tools/Discovar/bin/DiscovarExp

bin.MaSuRCA = /home/xiaofan/iWGS/tools/MaSuRCA/bin/masurca

bin.Minia = /home/xiaofan/iWGS/tools/Minia/minia

bin.SGA = /home/xiaofan/iWGS/tools/SGA/bin/sga

bin.SOAPdenovo2 = /home/xiaofan/iWGS/tools/SOAPdenovo2

bin.SPAdes = /home/xiaofan/iWGS/tools/SPAdes/bin/spades.py

bin.dipSPAdes = /home/xiaofan/iWGS/tools/SPAdes/bin/dipspades.py

bin.velvetg = /home/xiaofan/iWGS/tools/Velvet/velvetg

bin.velveth = /home/xiaofan/iWGS/tools/Velvet/velveth

bin.QUAST = /home/xiaofan/iWGS/tools/QUAST/quast.py

bin.AMOS = /home/xiaofan/iWGS/tools/dependencies/bank-transact

bin.BLASR = /home/xiaofan/iWGS/tools/dependencies/blasr

bin.BWA = /home/xiaofan/iWGS/tools/dependencies/bwa

bin.PBDAGCON = /home/xiaofan/iWGS/tools/dependencies/pbdagcon

bin.Picard = bin.AMOS = /home/xiaofan/iWGS/tools/dependencies/picard.jar

bin.SAMtools = /home/xiaofan/iWGS/tools/dependencies/samtools