```
#define N 100
                                       /* number of slots in the buffer */
typedef int semaphore:
                                       /* semaphores are a special kind of int */
                                       /* controls access to critical region */
semaphore mutex = 1:
semaphore\ empty = N;
                                       /* counts empty buffer slots */
semaphore full = 0;
                                       /* counts full buffer slots */
void producer(void)
    int item;
    while (TRUE) {
                                       /* TRUE is the constant 1 */
                                       /* generate something to put in buffer */
        item = produce_item();
        down(&empty);
                                       /* decrement empty count */
                                       /* enter critical region */
        down(&mutex);
        insert_item(item);
                                       /* put new item in buffer */
        up(&mutex);
                                       /* leave critical region */
                                       /* increment count of full slots */
        up(&full);
    }
void consumer(void)
    int item;
    while (TRUE) {
                                       /* infinite loop */
        down(&full);
                                       /* decrement full count */
        down(&mutex);
                                       /* enter critical region */
        item = remove_item();
                                       /* take item from buffer */
        up(&mutex);
                                       /* leave critical region */
                                       /* increment count of empty slots */
        up(&empty);
        consume_item(item);
                                       /* do something with the item */
    }
Fig. 2-24. The producer-consumer problem using semaphores.
```