
MATLAB® Object-Oriented Programming



MATLAB®



How to Contact MathWorks



Latest news: www.mathworks.com

Sales and services: www.mathworks.com/sales_and_services

User community: www.mathworks.com/matlabcentral

Technical support: www.mathworks.com/support/contact_us

7

Phone: 508-647-7000



The MathWorks, Inc. 3 Apple Hill Drive Natick, MA 01760-2098

Object-Oriented Programming

© COPYRIGHT 1984-2015 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Revision History

March 2008	Online only	New for MATLAB 7.6 (Release 2008a)
October 2008	Online only	Revised for MATLAB 7.7 (Release 2008b)
March 2009	Online only	Revised for MATLAB 7.8 (Release 2009a)
September 2009	Online only	Revised for MATLAB 7.9 (Release 2009b)
March 2010	Online only	Revised for MATLAB 7.10 (Release 2010a)
September 2010	Online only	Revised for Version 7.11 (Release 2010b)
April 2011	Online only	Revised for Version 7.12 (Release 2011a)
September 2011	Online only	Revised for Version 7.13 (Release 2011b)
March 2012	Online only	Revised for Version 7.14 (Release 2012a)
September 2012	Online only	Revised for Version 8.0 (Release 2012b)
March 2013	Online only	Revised for Version 8.1 (Release 2013a)
September 2013	Online only	Revised for Version 8.2 (Release 2013b)
March 2014	Online only	Revised for Version 8.3 (Release 2014a)
October 2014	Online only	Revised for Version 8.4 (Release 2014b)
March 2015	Online only	Revised for Version 8.5 (Release 2015a)

Video Demo of MATLAB Classes MATLAB Programmer Without Object-Oriented Programming Experience MATLAB Programmer with Object-Oriented Programming Experience Why Use Object-Oriented Design Approaches to Writing MATLAB Programs When Should You Start Creating Object-Oriented Programs Class Diagram Notation 1. Handle Objects 1. What Is a Handle Object? Copying Handles 1. Modifying Handle Objects in Functions 1. How to Determine If an Object Is a Handle Deleted Handle Objects 1. Basic Examp A Simple Class Define a Simple Class	Using Object-Oriented Design in MAT	LAB
Video Demo of MATLAB Classes MATLAB Programmer Without Object-Oriented Programming Experience MATLAB Programmer with Object-Oriented Programming Experience Why Use Object-Oriented Design Approaches to Writing MATLAB Programs When Should You Start Creating Object-Oriented Programs Class Diagram Notation 1. Handle Objects 1. What Is a Handle Object? 1. Copying Handles 1. Modifying Handle Objects in Functions 1. How to Determine If an Object Is a Handle 1. Deleted Handle Objects 1. Basic Examp A Simple Class Define a Simple Class		
Experience MATLAB Programmer with Object-Oriented Programming Experience Why Use Object-Oriented Design Approaches to Writing MATLAB Programs When Should You Start Creating Object-Oriented Programs Class Diagram Notation 1- Handle Objects 1- Copying Handle Object? 1- Copying Handles 1- Modifying Handle Objects in Functions 1- How to Determine If an Object Is a Handle Deleted Handle Objects 1- Deleted Handle Objects 1- Basic Examp A Simple Class Define a Simple Class	Video Demo of MATLAB Classes	1-2 1-2
Experience Why Use Object-Oriented Design Approaches to Writing MATLAB Programs When Should You Start Creating Object-Oriented Programs Class Diagram Notation 1. Handle Objects What Is a Handle Object? Copying Handles Modifying Handle Objects in Functions How to Determine If an Object Is a Handle Deleted Handle Objects Basic Examp A Simple Class Define a Simple Class	Experience	1-2
Approaches to Writing MATLAB Programs When Should You Start Creating Object-Oriented Programs Class Diagram Notation Handle Objects What Is a Handle Object? Copying Handles Modifying Handle Objects in Functions How to Determine If an Object Is a Handle Deleted Handle Objects Basic Examp A Simple Class Define a Simple Class	•	1-2
When Should You Start Creating Object-Oriented Programs Class Diagram Notation 1. Handle Objects 1. What Is a Handle Object? 1. Copying Handles 1. Modifying Handle Objects in Functions 1. How to Determine If an Object Is a Handle 1. Deleted Handle Objects 1. Basic Examp A Simple Class 1. Define a Simple Class 1.		1-8
Handle Objects		1-3 1-7
What Is a Handle Object? 1. Copying Handles 1. Modifying Handle Objects in Functions 1. How to Determine If an Object Is a Handle 1. Deleted Handle Objects 1. Basic Examp A Simple Class Define a Simple Class	Class Diagram Notation	1-14
Copying Handles		1-16
Modifying Handle Objects in Functions		1-16
How to Determine If an Object Is a Handle		1-16 1-17
Deleted Handle Objects		1-17
A Simple Class		1-19
Define a Simple Class	Basic Exan	nple
Define a Simple Class		
1		2-2
Create an Object		2-2
•	•	2-3
*	±	2-3
		2-3 2-4

	MATLAB Classes Overv
	guage
Some Basic Relationships	
	al Workflow
	nts
	ementation
	Manager Class
	tManager Class
	ynopsis
Using BankAccount Object	ts
	les
	n Object
	ass
Using Filewriter Objects.	
	ed Data
	s
	ssign Data
	eific Values
	vith a Constructor
	o Objects
	Strain
	osis

2-5

2-6

dlnode Class Design	
Create Doubly Linked List	
Why a Handle Class for Linked Lists?	
dlnode Class Synopsis	
Specialize the dlnode Class	
Class for Graphing Functions	
Class Definition Block	
Using the topo Class	
Behavior of the Handle Class	
Class Definition—Syntax R	efei
Class Files and Folders	
Options for Class Folders	
Options for Class Files	
Grouping Classes with Package Folders	
Class Components	
Class Building Blocks	
Class Definition Block	
Properties Block	
Methods Block	
Events Block	
Enumeration Block	
Related Information	
Classdef Block	
Specifying Attributes and Superclasses	
Assigning Class Attributes	
Specifying Superclasses	
Properties	
What You Can Define	
Initializing Property Values	
Defining Default Values	
Assigning Property Values from the Constructor	
Initializing Properties to Unique Values	
Property Attributes	

Property Access Methods	4-14
Referencing Object Properties Using Variables	4-15
Methods and Functions	4-16
The Methods Block	4-16
Method Calling Syntax	4-16
Private Methods	4-18
More Detailed Information On Methods	4-18
Class-Related Functions	4-18
Overloading Functions and Operators	4-19
Methods In Separate Files	4-20
Methods In Class Folders	4-20
Define Method in Function File	4-21
Specify Method Attributes in classdef File	4-21
Methods That You Must Define In the classdef File	4-22
Events and Listeners	4-24
Define and Trigger Events	4-24
Listen for Events	4-24
Attribute Specification	4-26
Attribute Syntax	4-26
Attribute Descriptions	4-26
Attribute Values	4-27
Simpler Syntax for true/false Attributes	4-27
Call Superclass Methods on Subclass Objects	4-29
Calling Superclass Constructor	4-29
Calling Superclass Methods	4-30
Representative Class Code	4-31
Class Calculates Area	4-31
Description of Class Definition	4-33
MATLAB Code Analyzer Warnings	4-36
Syntax Warnings and Property Names	4-36
Warnings Caused by Variable/Property Name Conflicts	4-36
Exception to Variable/Property Name Rule	4-37
Objects In Switch Statements	4-38
Evaluating the Switch Statement	4-38
Defining the eq Method	4-40

Referring to Class Files Automatic Updates for Modified Classes When MATLAB Loads Class Definitions Results of Automatic Update Result of Changes to Class Definitions Actions That Do Not Trigger Updates When Updates to Classes Fail Potential Side Effects from Class Updates When Updates of Existing Objects Are Not Possible Updates to Property Definitions Updates to Method Definitions Updates to Event Definitions
Functions to Query Class Components Using the Editor and Debugger with Classes Referring to Class Files Automatic Updates for Modified Classes When MATLAB Loads Class Definitions Results of Automatic Update Result of Changes to Class Definitions Actions That Do Not Trigger Updates When Updates to Classes Fail Potential Side Effects from Class Updates When Updates of Existing Objects Are Not Possible Updates to Property Definitions Updates to Method Definitions Updates to Event Definitions Updates to Event Definitions New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
Referring to Class Files Automatic Updates for Modified Classes When MATLAB Loads Class Definitions Results of Automatic Update Result of Changes to Class Definitions Actions That Do Not Trigger Updates When Updates to Classes Fail Potential Side Effects from Class Updates When Updates of Existing Objects Are Not Possible Updates to Property Definitions Updates to Method Definitions Updates to Event Definitions Updates to Event Definitions New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
Automatic Updates for Modified Classes When MATLAB Loads Class Definitions Results of Automatic Update Result of Changes to Class Definitions Actions That Do Not Trigger Updates When Updates to Classes Fail Potential Side Effects from Class Updates When Updates of Existing Objects Are Not Possible Updates to Property Definitions Updates to Method Definitions Updates to Event Definitions Updates to Event Definitions New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
Automatic Updates for Modified Classes When MATLAB Loads Class Definitions Results of Automatic Update Result of Changes to Class Definitions Actions That Do Not Trigger Updates When Updates to Classes Fail Potential Side Effects from Class Updates When Updates of Existing Objects Are Not Possible Updates to Property Definitions Updates to Method Definitions Updates to Event Definitions Updates to Event Definitions New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
When MATLAB Loads Class Definitions Results of Automatic Update Result of Changes to Class Definitions Actions That Do Not Trigger Updates When Updates to Classes Fail Potential Side Effects from Class Updates When Updates of Existing Objects Are Not Possible Updates to Property Definitions Updates to Method Definitions Updates to Event Definitions Compatibility with Previous Versions New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
When MATLAB Loads Class Definitions Results of Automatic Update Result of Changes to Class Definitions Actions That Do Not Trigger Updates When Updates to Classes Fail Potential Side Effects from Class Updates When Updates of Existing Objects Are Not Possible Updates to Property Definitions Updates to Method Definitions Updates to Event Definitions Compatibility with Previous Versions New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
Result of Changes to Class Definitions Actions That Do Not Trigger Updates When Updates to Classes Fail Potential Side Effects from Class Updates When Updates of Existing Objects Are Not Possible Updates to Property Definitions Updates to Method Definitions Updates to Event Definitions Compatibility with Previous Versions New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
Actions That Do Not Trigger Updates When Updates to Classes Fail Potential Side Effects from Class Updates When Updates of Existing Objects Are Not Possible Updates to Property Definitions Updates to Method Definitions Updates to Event Definitions Compatibility with Previous Versions New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
When Updates to Classes Fail Potential Side Effects from Class Updates When Updates of Existing Objects Are Not Possible Updates to Property Definitions Updates to Method Definitions Updates to Event Definitions Compatibility with Previous Versions New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
Potential Side Effects from Class Updates When Updates of Existing Objects Are Not Possible Updates to Property Definitions Updates to Method Definitions Updates to Event Definitions Compatibility with Previous Versions New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
When Updates of Existing Objects Are Not Possible Updates to Property Definitions Updates to Method Definitions Updates to Event Definitions Compatibility with Previous Versions New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
Updates to Property Definitions Updates to Method Definitions Updates to Event Definitions Updates to Event Definitions Compatibility with Previous Versions New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
Updates to Method Definitions Updates to Event Definitions Compatibility with Previous Versions New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
Updates to Event Definitions Compatibility with Previous Versions New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
Compatibility with Previous Versions New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
New Class-Definition Syntax Introduced with MATLAB Software Version 7.6 Changes to Class Constructors New Features Introduced with Version 7.6
Software Version 7.6
New Features Introduced with Version 7.6
New Features Introduced with Version 7.6
Examples of Old and New
Comparing MATLAB with Other OO Languages
Common Object-Oriented Techniques
Some Differences from C++ and Java Code
Defining and Organizing C

Constructing Objects 5-3 Class Hierarchies 5-3 Class Definition 5-4 classdef Syntax 5-4 Class Attributes 5-5 Specifying Class Attributes 5-5 Specifying Attributes 5-5 Expressions in Class Definitions 5-8 Basic Knowledge 5-8 Where to Use Expressions in Class Definitions 5-8 How MATLAB Evaluates Expressions 5-10 When MATLAB Evaluates Expressions 5-10 Samples of Expression Evaluation 5-10 Class and Path Folders 5-10 Class and Path Folders 5-14 Class And Path Folders 5-14 Class Folders 5-14 Access to Functions Defined in Private Folders 5-14 Class Precedence 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Internal Packages 5-19	Attributes for Class Members	5-2
Constructing Objects 5-3 Class Hierarchies 5-3 Class Definition 5-4 classdef Syntax 5-4 Class Attributes 5-5 Specifying Class Attributes 5-5 Specifying Attributes 5-5 Expressions in Class Definitions 5-8 Basic Knowledge 5-8 Where to Use Expressions in Class Definitions 5-8 How MATLAB Evaluates Expressions 5-10 Samples of Expression Evaluation 5-10 Class and Path Folders 5-10 Class and Path Folders 5-14 Class Access to Functions Defined in Private Folders 5-14 Class Precedence 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Internal Packages 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members From Outside the Package 5-21	Kinds of Classes	5-3
Class Definition 5-3 classdef Syntax 5-4 classdef Syntax 5-4 Class Attributes 5-5 Specifying Class Attributes 5-5 Specifying Attributes 5-6 Expressions in Class Definitions 5-8 Basic Knowledge 5-8 Where to Use Expressions in Class Definitions 5-8 How MATLAB Evaluates Expressions 5-10 When MATLAB Evaluates Expressions 5-10 Samples of Expression Evaluation 5-10 Class and Path Folders 5-14 Class and Path Folders 5-14 Class Folders 5-14 Class Folders 5-14 Access to Functions Defined in Private Folders 5-15 Class Precedence 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-19 Packages Create Namespaces 5-19 Internal Packages 5-19 Referencing Package Members Within Packages <		5-3
class Attributes 5-5 Specifying Class Attributes 5-5 Specifying Attributes 5-6 Expressions in Class Definitions 5-8 Basic Knowledge 5-8 Where to Use Expressions in Class Definitions 5-8 How MATLAB Evaluates Expressions 5-10 When MATLAB Evaluates Expressions 5-10 Samples of Expression Evaluation 5-10 Class and Path Folders 5-14 Class and Path Folders 5-14 Class Folders 5-14 Access to Functions Defined in Private Folders 5-15 Class Precedence and MATLAB Path 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Internal Packages 5-19 Package Folders 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members From Outside the Package 5-21 Packages and the MATLAB Path 5		5-3
class Attributes 5-5 Specifying Class Attributes 5-5 Specifying Attributes 5-6 Expressions in Class Definitions 5-8 Basic Knowledge 5-8 Where to Use Expressions in Class Definitions 5-8 How MATLAB Evaluates Expressions 5-10 When MATLAB Evaluates Expressions 5-10 Samples of Expression Evaluation 5-10 Class and Path Folders 5-14 Class and Path Folders 5-14 Class Folders 5-14 Access to Functions Defined in Private Folders 5-15 Class Precedence and MATLAB Path 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Internal Packages 5-19 Package Folders 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members From Outside the Package 5-21 Packages and the MATLAB Path 5	Class Definition	5-4
Specifying Class Attributes 5-5 Specifying Attributes 5-6 Expressions in Class Definitions 5-8 Basic Knowledge 5-8 Where to Use Expressions in Class Definitions 5-8 How MATLAB Evaluates Expressions 5-10 When MATLAB Evaluates Expressions 5-10 Samples of Expression Evaluation 5-10 Class and Path Folders 5-14 Class and Path Folders 5-14 Class Ploders 5-14 Access to Functions Defined in Private Folders 5-14 Class Precedence and MATLAB Path 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Internal Packages 5-19 Package Folders 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members from Outside the Package 5-21 Packages and the MATLAB Path 5-22		5-4
Specifying Class Attributes 5-5 Specifying Attributes 5-6 Expressions in Class Definitions 5-8 Basic Knowledge 5-8 Where to Use Expressions in Class Definitions 5-8 How MATLAB Evaluates Expressions 5-10 When MATLAB Evaluates Expressions 5-10 Samples of Expression Evaluation 5-10 Class and Path Folders 5-14 Class and Path Folders 5-14 Class Ploders 5-14 Access to Functions Defined in Private Folders 5-14 Class Precedence and MATLAB Path 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Internal Packages 5-19 Package Folders 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members from Outside the Package 5-21 Packages and the MATLAB Path 5-22	Class Attributes	5-5
Specifying Attributes 5-6 Expressions in Class Definitions 5-8 Basic Knowledge 5-8 Where to Use Expressions in Class Definitions 5-8 How MATLAB Evaluates Expressions 5-10 When MATLAB Evaluates Expressions 5-10 Samples of Expression Evaluation 5-10 Class and Path Folders 5-14 Class and Path Folders 5-14 Class Folders 5-14 Class Folders 5-14 Class Folders 5-15 Class Precedence and MATLAB Path 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Unferior Classes Attribute 5-17 Inferior Classes Attribute 5-19 Packages Create Namespaces 5-19 Internal Packages 5-19 Package Folders 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members From Outside the Package 5-21 Packages and the MATLAB Path 5-22 Importing Classes 5-24		5-5
Basic Knowledge 5-8 Where to Use Expressions in Class Definitions 5-8 How MATLAB Evaluates Expressions 5-10 When MATLAB Evaluates Expressions 5-10 Samples of Expression Evaluation 5-10 Class and Path Folders 5-14 Class and Path Folders 5-14 Path Folders 5-14 Class Folders 5-14 Class Folders 5-14 Access to Functions Defined in Private Folders 5-15 Class Precedence and MATLAB Path 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Internal Packages 5-19 Package Folders 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members From Outside the Package 5-21 Packages and the MATLAB Path 5-22 Importing Classes 5-24		5-6
Basic Knowledge 5-8 Where to Use Expressions in Class Definitions 5-8 How MATLAB Evaluates Expressions 5-10 When MATLAB Evaluates Expressions 5-10 Samples of Expression Evaluation 5-10 Class and Path Folders 5-14 Class and Path Folders 5-14 Path Folders 5-14 Class Folders 5-14 Class Folders 5-14 Access to Functions Defined in Private Folders 5-15 Class Precedence and MATLAB Path 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Internal Packages 5-19 Package Folders 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members From Outside the Package 5-21 Packages and the MATLAB Path 5-22 Importing Classes 5-24	Expressions in Class Definitions	5-8
Where to Use Expressions in Class Definitions How MATLAB Evaluates Expressions Samples of Expression Evaluation Class and Path Folders Class and Path Folders Class and Path Folders Class Folders Class Folders Class Folders Class Folders Class Precedence and MATLAB Path Class Precedence Basic Knowledge Why Mark Classes as Inferior InferiorClasses Attribute Packages Create Namespaces Internal Packages Folders Referencing Package Members Within Packages Referencing Package Members from Outside the Package Folders		
How MATLAB Evaluates Expressions 5-10 When MATLAB Evaluates Expressions 5-10 Samples of Expression Evaluation 5-10 Class and Path Folders 5-14 Class and Path Folders 5-14 Path Folders 5-14 Class Folders 5-14 Access to Functions Defined in Private Folders 5-15 Class Precedence and MATLAB Path 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Internal Packages 5-19 Package Folders 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members from Outside the Package 5-21 Packages and the MATLAB Path 5-22 Importing Classes 5-24		
When MATLAB Evaluates Expressions 5-10 Samples of Expression Evaluation 5-10 Class and Path Folders 5-14 Class and Path Folders 5-14 Path Folders 5-14 Class Folders 5-14 Access to Functions Defined in Private Folders 5-15 Class Precedence and MATLAB Path 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Internal Packages 5-19 Package Folders 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members from Outside the Package 5-21 Packages and the MATLAB Path 5-22 Importing Classes 5-24	•	
Samples of Expression Evaluation 5-10 Class and Path Folders 5-14 Class and Path Folders 5-14 Path Folders 5-14 Class Folders 5-14 Class Folders 5-14 Access to Functions Defined in Private Folders 5-15 Class Precedence and MATLAB Path 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Internal Packages 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members from Outside the Package 5-21 Packages and the MATLAB Path 5-22 Importing Classes 5-24	<u>*</u>	
Class and Path Folders 5-14 Path Folders 5-14 Class Folders 5-14 Access to Functions Defined in Private Folders 5-15 Class Precedence and MATLAB Path 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Package Folders 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members from Outside the Package 5-21 Packages and the MATLAB Path 5-22 Importing Classes 5-24		5-10 5-10
Class and Path Folders 5-14 Path Folders 5-14 Class Folders 5-14 Access to Functions Defined in Private Folders 5-15 Class Precedence and MATLAB Path 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Package Folders 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members from Outside the Package 5-21 Packages and the MATLAB Path 5-22 Importing Classes 5-24	Class and Path Folders	5-14
Path Folders 5-14 Class Folders 5-14 Access to Functions Defined in Private Folders 5-15 Class Precedence and MATLAB Path 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 Inferior Classes Attribute 5-17 Packages Create Namespaces 5-19 Package Folders 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members from Outside the Package 5-21 Packages and the MATLAB Path 5-22 Importing Classes 5-24		5-14
Class Folders		
Access to Functions Defined in Private Folders Class Precedence and MATLAB Path Class Precedence Basic Knowledge S-17 Why Mark Classes as Inferior InferiorClasses Attribute 5-17 Packages Create Namespaces Internal Packages Package Folders Package Folders Referencing Package Members Within Packages F-20 Referencing Package Members from Outside the Package F-21 Packages and the MATLAB Path F-22 Importing Classes 5-15 5-16 5-17 5-17 5-17 5-17 5-18 5-19 6-19 6-19 6-19 6-19 6-19 6-19 6-19 6		
Class Precedence 5-15 Class Precedence 5-17 Basic Knowledge 5-17 Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Internal Packages 5-19 Package Folders 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members from Outside the Package 5-21 Packages and the MATLAB Path 5-22 Importing Classes 5-24		
Basic Knowledge		5-15
Basic Knowledge	Class Precedence	5-17
Why Mark Classes as Inferior 5-17 InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Internal Packages 5-19 Package Folders 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members from Outside the Package 5-21 Packages and the MATLAB Path 5-22 Importing Classes 5-24		
InferiorClasses Attribute 5-17 Packages Create Namespaces 5-19 Internal Packages 5-19 Package Folders 5-19 Referencing Package Members Within Packages 5-20 Referencing Package Members from Outside the Package 5-21 Packages and the MATLAB Path 5-22 Importing Classes 5-24	Why Mark Classes as Inferior	
Internal Packages	InferiorClasses Attribute	5-17
Internal Packages	Packages Create Namesnaces	5-19
Package Folders		
Referencing Package Members Within Packages		
Referencing Package Members from Outside the Package		
Packages and the MATLAB Path		
1 0		5-21 5-22
1 0	Importing Classes	5-24
	Syntax for Importing Classes	5-24

${\bf Value\ or\ Handle\ Class-Which\ to\ Use}$

	4	ı	١
1			١
	٠	=	١
		_	•

Comparing Handle and Value Classes Basic Difference	6-2 6-2 6-2
Behavior of MATLAB Built-In Classes	6-3 6-4
Which Kind of Class to Use	6-9
Examples of Value and Handle Classes	6-9
When to Use Handle Classes	6-9
When to Use Value Classes	6-10
The Handle Superclass	6-11
Building on the Handle Class	6-11
Handle Class Methods	6-12
Relational Methods	6-12
Testing Handle Validity	6-12
When MATLAB Destroys Objects	6-14
Handle Class Destructor	6-16
Basic Knowledge	6-16
Syntax of Class Destructor Method	6-16
When to Define a Destructor Method	6-17
Destructors in Class Hierarchies	6-17
Object Lifecycle	6-18
Restrict Explicit Object Deletion	6-20
Nondestructor Delete Methods	6-20
Finding Handle Objects and Properties	6-22
Finding Handle Objects	6-22
Finding Handle Object Properties	6-22
Implementing a Set/Get Interface for Properties	6-23
The Standard Set/Get Interface	6-23
Subclass matlab.mixin.SetGet	6-23
Get Method Syntax	6-23
Set Method Syntax	6-24
Class Darived from matlah mixin SatGat	6_95

Controlling the Number of Instances	6- 6-
	_
Properties — Storing Class	Da
How to Use Properties	,
What Are Properties	
Types of Properties	
Defining Properties	. '
Property Definition Block	
Access Property Values	
Inheritance of Properties	
Specify Property Attributes	•
Property Attributes	
Specifying Property Attributes	
Table of Property Attributes	
Mutable and Immutable Properties	7
Set Access to Property Values	7
Property Access Methods	7
Property Setter and Getter Methods	7
Set and Get Method Execution and Property Events	7
Access Methods and Properties Containing Arrays	7
Modify Property Values with Access Methods	7
Property Set Methods	7
Overview of Property Access Methods	7
Property Set Method Syntax	7
Validate Property Set Value	7
Set Method Behavior	7
Property Get Methods	7
Overview of Property Access Methods	7
Property Get Method Syntax	7
Errors Not Returned from Get Method	7
Get Method Behavior	7

Access Methods for Dependent Properties	7-24
Set and Get Methods for Dependent Properties	7-24
Get Method for Dependent Property	7-25
When to Use Set Methods with Dependent Properties	7-25
When to Use Private Set Access with Dependent Properties	7-26
when to Ose I rivate Set Access with Dependent I roperties	7-20
Properties Containing Objects	7-28
Assigning to Read-Only Properties Containing Objects	7-28
Assignment Behavior	7-28
Oynamic Properties — Adding Properties to an Instance .	7-30
What Are Dynamic Properties	7-30
	7-30 7-31
Defining Dynamic Properties	
Responding to Dynamic-Property Events	7-32
Defining Property Access Methods for Dynamic Properties.	7-34
Dynamic Properties and ConstructOnLoad	7-35
Methods — Defining Class Operat	ions
Methods — Defining Class Operat	ions
low to Use Methods	8-2
ow to Use Methods	8-2 8-2
How to Use Methods	8-2
How to Use Methods Class Methods Method Naming	8-2 8-2
How to Use Methods Class Methods Method Naming Method Attributes	8-2 8-2 8-3
How to Use Methods Class Methods Method Naming Method Attributes Specifying Method Attributes	8-2 8-2 8-3 8-5 8-5
How to Use Methods Class Methods Method Naming Method Attributes	8-2 8-2 8-3
How to Use Methods Class Methods Method Naming Method Attributes Specifying Method Attributes Table of Method Attributes Ordinary Methods	8-2 8-2 8-3 8-5 8-5 8-5
How to Use Methods Class Methods Method Naming Method Attributes Specifying Method Attributes Table of Method Attributes	8-2 8-2 8-3 8-5 8-5 8-5
Iow to Use Methods	8.
How to Use Methods Class Methods Method Naming Method Attributes Specifying Method Attributes Table of Method Attributes Ordinary Methods	8-2 8-2 8-3 8-5 8-5 8-7 8-7
ow to Use Methods Class Methods Method Naming ethod Attributes Specifying Method Attributes Table of Method Attributes rdinary Methods Defining Methods Multi-File Classes	8-2 8-2 8-3 8-5 8-5 8-7 8-7
ow to Use Methods Class Methods Method Naming ethod Attributes Specifying Method Attributes Table of Method Attributes rdinary Methods Defining Methods Multi-File Classes	8-2 8-2 8-3 8-5 8-5 8-7 8-7 8-8
Iow to Use Methods Class Methods Method Naming Iethod Attributes Specifying Method Attributes Table of Method Attributes Ordinary Methods Defining Methods Multi-File Classes Iethod Invocation Determining Which Method Is Invoked	8-2 8-2 8-3 8-5 8-5 8-7 8-7 8-8 8-9
How to Use Methods Class Methods Method Naming Method Attributes Specifying Method Attributes Table of Method Attributes Ordinary Methods Defining Methods Multi-File Classes Method Invocation Determining Which Method Is Invoked Referencing Names with Expressions—Dynamic Reference	8-2 8-3 8-5 8-5 8-7 8-7 8-8 8-9 8-9 8-11
How to Use Methods Class Methods Method Naming Method Attributes Specifying Method Attributes Table of Method Attributes Ordinary Methods Defining Methods Multi-File Classes Method Invocation Determining Which Method Is Invoked Referencing Names with Expressions—Dynamic Reference Controlling Access to Methods	8-2 8-3 8-5 8-5 8-7 8-7 8-8 8-9 8-9 8-11 8-12
How to Use Methods Class Methods Method Naming Method Attributes Specifying Method Attributes Table of Method Attributes Ordinary Methods Defining Methods Multi-File Classes Method Invocation Determining Which Method Is Invoked Referencing Names with Expressions—Dynamic Reference Controlling Access to Methods Invoking Superclass Methods in Subclass Methods	8-2 8-3 8-5 8-5 8-5 8-7 8-7 8-8 8-9 8-9 8-11 8-12 8-13
How to Use Methods Class Methods Method Naming Method Attributes Specifying Method Attributes Table of Method Attributes Ordinary Methods Defining Methods Multi-File Classes Method Invocation Determining Which Method Is Invoked Referencing Names with Expressions—Dynamic Reference Controlling Access to Methods	8-2 8-3 8-5 8-5 8-5 8-7 8-7 8-8 8-9 8-9 8-11 8-12

Class Constructor Methods	8-15
Rules for Constructors	8-15
Related Information	8-16
Initializing Objects In Constructor	8-16
No Input Argument Constructor Requirement	8-17
Constructing Subclasses	8-18
Errors During Class Construction	8-20
Basic Structure of Constructor Methods	8-21
Static Methods	8-23
Why Define Static Methods	8-23
Calling Static Methods	8-23
Overload Functions for Your Class	8-25
Overloading MATLAB Functions	8-25
Rules for Naming to Avoid Conflicts	8-27
Class Support for Array-Creation Functions	8-28
Extend Array-Creation Functions for Your Class	8-28
Which Syntax to Use	8-29
Implement Support for Array-Creation Functions	8-30
Object Precedence in Methods	8-37
Specifying Precedence of User-Defined Classes	8-37
Dominant Argument in Overloaded Plotting Functions	8-39
Graphics Object Precedence	8-39
Dominant Argument	8-39
Defining Class Precedence	8-39
Calls to Inferior-Class Methods	8-41
Class Methods for Graphics Callbacks	8-42
Referencing the Method	8-42
Syntax for Method Callbacks	8-42
How to Use a Class Method for a Slider Callback	8-43

()
	7	

Create Object Arrays	9-2
Basic Knowledge	9-2
Build Arrays in the Constructor	9-2
Referencing Property Values in Object Arrays	9-3
Related Information	9- 4
Initialize Object Arrays	9-5
Calls to Constructor	9-5
Initial Value of Object Properties	9-6
Empty Arrays	9-8
Creating Empty Arrays	9-8
Assigning Values to an Empty Array	9-8
Initialize Arrays of Handle Objects	9-10
	9-11
Object Arrays with Dynamic Properties	9-18
Concatenating Objects of Different Classes	9-15
Basic Knowledge	9-15
	9-15
Concatenating Objects	9-15
Calling the Dominant-Class Constructor	9-16
	9-18
Heterogeneous Arrays	9-21
Why Heterogeneous Arrays	9-21
Heterogeneous Array Concepts	9-21
Nature of Heterogeneous Arrays	9-22
Unsupported Hierarchies	9-25
	9-26
	9-27

${\bf Events-Sending\ and\ Responding\ to\ Messages}$

10

Learn to Use Events and Listeners	10-2
Why Use Events and Listeners	10-2
Events and Listeners Basics	10-2
Events and Listeners Syntax Overview	10-3
Class with Custom Event Data	10-5
Class to Observe Property Changes	10-7
Class to Observe Troperty Changes	10 ,
Property Set Listener	10-9
PushButton Class Design	10-9
Events and Listeners — Concepts	10-12
The Event Model	10-12
Default Event Data	10-13
Events Only in Handle Classes	10-14
Property-Set and Query Events	10-14
Listeners	10-15
Institution of the contract of	10 10
Event Attributes	10-17
Specifying Event Attributes	10-17
Events and Listeners — Syntax and Techniques	10-19
Name Events	10-19
Trigger Events	10-19
Listen to Events	10-20
Define Event-Specific Data	10-22
1	
Listener Lifecycle	10-2 3
Control Listener Lifecycle	10-23
Temporarily Deactivating Listeners	10-24
Permanently Deleting Listeners	10-25
Function Handle for Listener Callbacks	10-26
Specify Listener Callbacks	10-26
Callback Execution	10-28
Listen for Changes to Property Values	10-29
Creating Property Listeners	10-29
Property Event and Listener Classes	10-31
Aborting Set When Value Does Not Change	10-32

Example Overview	10-36
<u> •</u>	10-36
Techniques Demonstrated in This Example	10-37
Summary of feneval Class	10-37 10-38
Summary of fcnview Class	10-38
Using the fcneval and fcnview Classes	10-40
Implementing the UpdateGraph Event and Listener	10-40
The PostSet Event Listener	10-42
Enabling and Disabling the Listeners	10-40
@fcneval/fcneval.m Class Code	10-49
@fcnview/fcnview.m Class Code	10-50
Puilding on Other (loggog
Building on Other 0	lasses
Hierarchies of Classes — Concepts	
Classification	. 11-2
Developing the Abstraction	. 11-3
Developing the Abstraction	. 11-3 . 11-4
Developing the Abstraction	. 11-3 . 11-4 11-4
Developing the Abstraction	. 11-3 . 11-4 11-4
Developing the Abstraction	. 11-3 11-4 11-4 11-5 . 11-7
Developing the Abstraction Designing Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Creating Subclasses — Syntax and Techniques Defining a Subclass	. 11-3 . 11-4 . 11-5 . 11-7 . 11-7
Developing the Abstraction Designing Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Creating Subclasses — Syntax and Techniques Defining a Subclass Initializing Superclasses from Subclasses	. 11-3 . 11-4 . 11-5 . 11-7 . 11-7
Developing the Abstraction Designing Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Creating Subclasses — Syntax and Techniques Defining a Subclass Initializing Superclasses from Subclasses Calling Superclass Constructor Explicitly	. 11-3 . 11-4 . 11-5 . 11-7 . 11-7 . 11-9
Developing the Abstraction Designing Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Creating Subclasses — Syntax and Techniques Defining a Subclass Initializing Superclasses from Subclasses Calling Superclass Constructor Explicitly Constructor Arguments and Object Initialization	. 11-3 11-4 11-5 . 11-7 . 11-7 . 11-9 11-9
Developing the Abstraction Designing Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Creating Subclasses — Syntax and Techniques Defining a Subclass Initializing Superclasses from Subclasses Calling Superclass Constructor Explicitly Constructor Arguments and Object Initialization Call Only Direct Superclass from Constructor	. 11-3 . 11-4 . 11-5 . 11-7 . 11-7 . 11-9 . 11-9 . 11-10
Developing the Abstraction Designing Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Creating Subclasses — Syntax and Techniques Defining a Subclass Initializing Superclasses from Subclasses Calling Superclass Constructor Explicitly Constructor Arguments and Object Initialization	. 11-3 11-4 11-5 . 11-7 . 11-7 . 11-9 11-9
Developing the Abstraction Designing Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Creating Subclasses — Syntax and Techniques Defining a Subclass Initializing Superclasses from Subclasses Calling Superclass Constructor Explicitly Constructor Arguments and Object Initialization Call Only Direct Superclass from Constructor	. 11-3 . 11-4 . 11-5 . 11-7 . 11-7 . 11-9 . 11-9 . 11-10
Developing the Abstraction Designing Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Creating Subclasses — Syntax and Techniques Defining a Subclass Initializing Superclasses from Subclasses Calling Superclass Constructor Explicitly Constructor Arguments and Object Initialization Call Only Direct Superclass from Constructor Subclass Alias for Existing Class	. 11-3 11-4 11-5 . 11-7 . 11-7 . 11-9 11-9 11-10 11-11
Developing the Abstraction Designing Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Creating Subclasses — Syntax and Techniques Defining a Subclass Initializing Superclasses from Subclasses Calling Superclass Constructor Explicitly Constructor Arguments and Object Initialization Call Only Direct Superclass from Constructor Subclass Alias for Existing Class Sequence of Constructor Calls in Class Hierarchy	. 11-3 . 11-4 . 11-5 . 11-7 . 11-7 . 11-9 . 11-10 . 11-11
Developing the Abstraction Designing Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Creating Subclasses — Syntax and Techniques Defining a Subclass Initializing Superclasses from Subclasses Calling Superclass Constructor Explicitly Constructor Arguments and Object Initialization Call Only Direct Superclass from Constructor Subclass Alias for Existing Class Sequence of Constructor Calls in Class Hierarchy Modify Superclass Methods	. 11-3 . 11-4 . 11-5 . 11-7 . 11-7 . 11-9 . 11-10 . 11-11
Developing the Abstraction Designing Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Creating Subclasses — Syntax and Techniques Defining a Subclass Initializing Superclasses from Subclasses Calling Superclass Constructor Explicitly Constructor Arguments and Object Initialization Call Only Direct Superclass from Constructor Subclass Alias for Existing Class Sequence of Constructor Calls in Class Hierarchy Modify Superclass Methods When to Modify Superclass Methods	. 11-3 11-4 11-5 . 11-7 . 11-7 . 11-7 . 11-9 . 11-10 . 11-11 . 11-13

Modify Superclass Properties	11-18
Allowed Superclass Property Modification	11-18
Private Local Property Takes Precedence in Method	11-18
Subclassing Multiple Classes	11-20
Class Member Compatibility	11-20
Using Multiple Inheritance	11-21
Specify Allowed Subclasses	11-22
Basic Knowledge	11-22
Why Control Allowed Subclasses	11-22
Specify Allowed Subclasses	11-22
Define a Sealed Hierarchy of Classes	11-24
Control Access to Class Members	11-25
Basic Knowledge	11 - 25
Applications for Access Control Lists	11-26
Specify Access to Class Members	11-26
Properties with Access Lists	11-28
Methods with Access Lists	11-28
Abstract Methods with Access Lists	11-32
Property Access List	11-33
Method Access List	11-34
Event Access List	11-35
Supporting Both Handle and Value Subclasses	11-36
Basic Knowledge	11-36
Handle Compatibility Rules	11-36
Defining Handle-Compatible Classes	11-37
Subclassing Handle-Compatible Classes	11-39
Methods for Handle Compatible Classes	11-41
Handle-Compatible Classes and Heterogeneous Arrays	11-42
Subclassing MATLAB Built-In Types	11-44
MATLAB Built-In Types	11-44
Built-In Types You Cannot Subclass	11-44
Why Subclass Built-In Types	11-45
Which Functions Work With Subclasses of Built-In Types.	11-45
Behavior of Built-In Functions with Subclass Objects	11-45

Behavior of Inherited Built-In Methods	11-48
Subclass double	11-48
Built-In Data Value Methods	11-49
Built-In Data Organization Methods	11-50
Built-In Indexing Methods	11-51
Built-In Concatenation Methods	11-51
Built-In Subclass Without Properties	11-53
A Class to Manage uint8 Data	11-53
Using the DocUint8 Class	11-54
Built-In Subclass With Properties	11-61
Subclasses with Properties	11-61
Property Added	11-61
Methods Implemented	11-61
Class Definition Code	11-62
Use ExtendDouble	11-63
Indexed Reference for ExtendDouble	11-64
Concatenating ExtendDouble Objects	11-65
Understanding size and numel	11-67
size and numel	11-67
Subclasses Inherited Behavior	11-68
Classes Not Derived from Built-In Classes	11-69
Changing the Behavior of size	11-71
Avoid Overloading numel	11-71
Class to Represent Hardware	11-73
Class Objective	11-73
Why Derive from int32	11-73
Class Definition	11-73
Methods of int32	11-74
Determine Array Class	11-76
Querying the Class Name	11-76
Testing for Class	11-76
Testing for Specific Types	11-77
Testing for Most Derived Class	11-78
Abstract Classes	11-80
Abstract Classes	11-80
Declaring Classes as Abstract	11-81
Determine If a Class Is Abstract	11-82

Find Inherited Abstract Properties and Methods	
Interfaces	
Interfaces and Abstract Classes	
An Interface for Classes Implementing Graphs	• • • •
Saving and Loadin	ag Obi
Saving and Loadin	ig Obj
Save and Load Process	
Save and Load Objects	
What Information Is Saved?	
How Is the Property Data Loaded?	
Errors During Load	• • • • •
Reduce MAT-File Size for Saved Objects	
Default Values	
Dependent Properties	
Transient Properties	
Avoid Saving Unwanted Variables	
Save Object Data to Recreate Graphics Objects	
What to Save	
Regenerate When Loading	
Change to a Stairstep Chart	
Improve Version Compatibility with Default Values .	
Version Compatibility	
Using a Default Property Value	• • • •
Avoid Property Initialization Order Dependency	
Control Property Loading	
Dependent Property with Private Storage	
Property Value Computed from Other Properties	• • •
Modify the Save and Load Process	
When to Modify the Save and Load Process	
· ·	
How to Modify the Save and Load Process	
· ·	

	A Typical saveobj and loadobj Pattern	12 - 15
	Regenerating from Object or struct	12-16
	Related Examples	12-17
	Maintain Class Compatibility	12-18
	Rename Property	12-18
	Update Property When Loading	12 - 20
	Maintaining Compatible Versions of a Class	12-21
	Version 2 of the PhoneBookEntry Class	12-22
	Initialize Objects	12-25
	Calling Constructor When Loading Objects	12 - 25
	Initializing Objects in the loadobj Method	12-25
	Save and Load Objects from Class Hierarchies	12-27
	Saving and Loading Subclass Objects	12 - 27
	Reconstruct the Subclass Object from a Saved struct	12-27
	Restore Listeners	12-30
	Create Listener with loadobj	12-30
	Use Transient Property to Load Listener	12 - 30
	Using the BankAccount and AccountManager Classes	12-32
	Save and Load Dynamic Properties	12-33
	Saving Dynamic Properties	12 - 33
	When You Need saveobj and loadobj Methods	12 - 33
	Implementing saveobj and loadobj Methods	12-33
	Enumera	tions
13		
	Defining Named Values	13-2
	Kinds of Predefined Names	13-2
	Working with Enumerations	13-3
	Basic Knowledge	13-3
	Using Enumeration Classes	13-4
	Defining Methods in Enumeration Classes	13-8
	Defining Properties in Enumeration Classes	13-9
	Array Expansion Operations	13-10

	Constructor Calling Sequence	13-10
	Restrictions Applied to Enumeration Classes	13-12
	Techniques for Defining Enumerations	13-12
	Enumerations Derived from Built-In Types	13-14
	Basic Knowledge	13-14
	Why Derive Enumerations from Built-In Types	13-14
	Aliasing Enumeration Names	13-16
	Superclass Constructor Returns Underlying Value	13-17
	Default Converter	13-18
	Mutable (Handle) vs. Immutable (Value) Enumeration	
	Members	13-20
	Basic Knowledge	13-20
	Selecting Handle- or Value-Based Enumerations	13-20
	Value-Based Enumeration Classes	13-20
	Handle-Based Enumeration Classes	13-22
	Using Enumerations to Represent a State	13-25
	Enumerations That Encapsulate Data	13-27
	Basic Knowledge	13-27
	Store Data in Properties	13-27
	Saving and Loading Enumerations	13-31
	Basic Knowledge	13-31
	Built-In and Value-Based Enumeration Classes	13-31
	Simple and Handle-Based Enumeration Classes	13-31
	Causes: Loading as Struct Instead of Object	13-32
		, •
11	Constant Prop	erties
14		
	Properties with Constant Values	14-2
	Defining Named Constants	14-2
	Constant Property Assigned a Handle Object	14-4
	Constant Property Assigned Any Class Instance	14-4

Tı	nform	ation	from	Class	Meta	data
		avivii	11 (/11)	11055	\mathbf{v}	uata

	Class Metadata	15-2
	What Is Class Metadata?	15-2
	The meta Package	15-2
	Metaclass Objects	15-3
	·	
	Inspecting Class and Object Metadata	15-5
	Inspecting a Class	15-5
	Metaclass EnumeratedValues Property	15-7
	Finding Objects with Specific Values	15-8
	Find Handle Objects	15-8
		15-0 15-9
	Find by Attribute Settings	19-9
	Getting Information About Properties	15-12
	The meta.property object	15-12
	How to Find Properties with Specific Attributes	15-15
		15 10
	Find Default Values in Property Metadata	15-18
	meta.property Object	15-18
	meta.property Data	15-18
16	Specializing Object Beha	avior
		100
	Methods That Modify Default Behavior	16-2
	How to Customize Class Behavior	16-2
	Which Methods Control Which Behaviors	16-2
	Overloading and Overriding Functions and Methods	16-3
	Overloading numel, subsref, and subsasgn	16-5
	Considerations for Overloading	16-5
	Syntax to Overload numel, subsref, and subsasgn	16-5
	Concatenation Methods	16-7
	Default Concatenation	16-7
	Methods to Overload	16-7
	Memous to Overtoau	10-7

Object Converters	16-8
Why Implement a Converter	16-8
Converters for Package Classes	16-8
Converters and Subscripted Assignment	16-9
Object Array Indexing	16-11
Default Indexed Reference and Assignment	16-11
What You Can Modify	16-12
When to Modify Indexing Behavior	16-13
Built-In subsref and subsasgn Called In Methods	16-13
Avoid Overriding Access Attributes	16-15
Indexed Reference	16-17
Understanding Indexed Reference	16-17
Compound Indexed References	16-18
Writing subsref	16-19
Indexed Assignment	16-21
Understanding Indexed Assignment	16-21
Indexed Assignment to Objects	16-23
Compound Indexed Assignments	16-23
Object end Indexing	16-25
Define end Indexing for an Object	16-25
The end Method	16-26
Objects In Index Expressions	16-27
Using Objects as Indices	16-27
Scenarios for Implementing Objects as Indices	16-27
subsindex Implementation	16-28
Class with Modified Indexing	16-29
Modify Class Indexing	16-29
Class Description	16-29
Specialize Subscripted Reference — subsref	16-31
Specialize Subscripted Assignment — subsasgn	16-31
Implementing Addition for Object Data — double and plus	16-32
MyDataClass.m	16-34
Class Operator Implementations	16-37
Defining Operators	16-37
MATIAR Operators and Associated Functions	16-37

17

Custom Display Interface	17-2
Default Object Display	17-2
CustomDisplay Class	17-8
Methods for Customizing Object Display	17-8
Methods for edistormating object Display	1,
How CustomDisplay Works	17-7
Steps to Display an Object	17-7
Methods Called for a Given Object State	17-8
Role of size Function in Custom Displays	17-9
How size Is Used	17-9
Precautions When Overloading size	17-9
r recautions when overloading size	17-8
Customize Display for Heterogeneous Arrays	17-10
Class with Default Object Display	17-12
The EmployeeInfo Class	17-12
Default Display — Scalar	17-18
Default Display — Scalar	17-18
Default Display — Fronty Object Arrey	17-14
Default Display — Empty Object Array	
Default Display — Handle to Deleted Object	17-15
Default Display — Detailed Display	17-18
Choose a Technique for Display Customization	17-16
Ways to Implement a Custom Display	17-16
Sample Approaches Using the Interface	17-17
cample ripproactics come the interface	_, _,
Customize Property Display	17-19
Change the Property Order	17-19
Change the Values Displayed for Properties	17-20
Customize Header, Property List, and Footer	17-22
Design of Custom Display	17-22
getHeader Method Override	17-24 17-24
getPropertyGroups Override	17-24 $17-25$
getFooter Override	17-25
Customize Display of Scalar Objects	17-28
Dosign Of Custom Display	17_99

	displayScalarObject Method Override getPropertyGroups Override	17-29 17-30
	Customize Display of Object Arrays	17-32 17-32
	Design of Custom Display	17-32 17-33
	The displayNonScalarObject Override	17-33 17-34
	Overload the disp Function	17-37 17-37
	Implement disp or disp and display	17-37
	Relationship Between disp and display	17-37
18	Implementing a Class for Polynon	nials
	Class Design for Polynomials	18-2
	Object Requirements	18-2
	DocPolynom Class Members	18-2
	DocPolynom Class Synopsis	18-4
	The DocPolynom Constructor	18-13
	Remove Irrelevant Coefficients	18-14
	Convert DocPolynom Objects to Other Types	18-15
	Overload disp for DocPolynom	18-17
	Display Evaluated Expression	18-18
	Redefine Indexed Reference	18-18
	Define Arithmetic Operators	18-21
10	Designing Related Cla	asses
17	A Simple Class Hierarchy Shared and Specialized Properties Designing a Class for Financial Assets	19-2 19-2 19-3
	DocAsset Class Definition	19-4 19-4
	The DocAsset Constructor Method	19-4 19-5
	The Docasset Constructor Method	19-9

The DocAsset Display Method	19-6
Designing a Class for Stock Assets	19-7
DocStock Class Definition	19-7
Summary of the DocStock Class	19-7
Designing a Class for Bond Assets	19-10
DocBond Class Definition	19-10
Summary of the DocBond Class	19-10
Designing a Class for Savings Assets	19-14
DocSavings Class Definition	19-14
Summary of the DocSavings Class	19-14
DocAsset Class Code Listing	19-17
DocStock Class Code Listing	19-17
DocBond Class Code Listing	19-18
DocSavings Class Code Listing	19-19
Containing Assets in a Portfolio	19-20
Kinds of Containment	19-20
Designing the DocPortfolio Class	19-20
Displaying the Class Files	19-21
Summary of the DocPortfolio Class	19-21
The DocPortfolio Constructor Method	19-23
The DocPortfolio disp Method	19-24
The DocPortfolio pie3 Method	19-24
Visualizing a Portfolio	19-25
DocPortfolio Class Code Listing	19-26

Using Object-Oriented Design in MATLAB

- "Begin Using Object-Oriented Programming" on page 1-2
- "Why Use Object-Oriented Design" on page 1-3
- "Class Diagram Notation" on page 1-14
- "Handle Objects" on page 1-16

Begin Using Object-Oriented Programming

In this section...

"Video Demo of MATLAB Classes" on page 1-2

"MATLAB Programmer Without Object-Oriented Programming Experience" on page 1-2

"MATLAB Programmer with Object-Oriented Programming Experience" on page 1-2

Video Demo of MATLAB Classes

You can watch a brief presentation on MATLAB class development by clicking this link:

Play video

MATLAB Programmer Without Object-Oriented Programming Experience

If you create MATLAB programs, but are not defining classes to accomplish your tasks, start with the following sections:

- "Why Use Object-Oriented Design" on page 1-3
- "Classes in the MATLAB Language" on page 3-2
- · "Sample Classes"
- "Some Basic Relationships"

MATLAB Programmer with Object-Oriented Programming Experience

If have experience with both MATLAB programming and object-oriented techniques, start with the following sections:

- "Class Syntax Fundamentals"
- "Class Files and Folders"
- "Compatibility with Previous Versions"
- "Comparing MATLAB with Other OO Languages"

Why Use Object-Oriented Design

In this section...

"Approaches to Writing MATLAB Programs" on page 1-3

"When Should You Start Creating Object-Oriented Programs" on page 1-7

Approaches to Writing MATLAB Programs

Creating software applications typically involves designing how to represent the application data and determining how to implement operations performed on that data. Procedural programs pass data to functions, which perform the necessary operations on the data. Object-oriented software encapsulates data and operations in objects that interact with each other via the object's interface.

The MATLAB language enables you to create programs using both procedural and object-oriented techniques and to use objects and ordinary functions in your programs.

Procedural Program Design

In procedural programming, your design focuses on steps that must be executed to achieve a desired state. You typically represent data as individual variables or fields of a structure and implement operations as functions that take the variables as arguments. Programs usually call a sequence of functions, each one of which is passed data, and then returns modified data. Each function performs an operation or perhaps many operations on the data.

Object-Oriented Program Design

The object-oriented program design involves:

- · Identifying the components of the system or application that you want to build
- Analyzing and identifying patterns to determine what components are used repeatedly or share characteristics
- · Classifying components based on similarities and differences

After performing this analysis, you define classes that describe the objects your application uses.

Classes and Objects

A class describes a set of objects with common characteristics. Objects are specific instances of a class. The values contained in an object's properties are what make an object different from other objects of the same class (an object of class double might have a value of 5). The functions defined by the class (called methods) are what implement object behaviors that are common to all objects of a class (you can add two doubles regardless of their values).

Using Objects in MATLAB Programs

The MATLAB language defines objects that are designed for use in any MATLAB code. For example, consider the try/catch programming construct.

If the code executed in the try block generates an error, program control passes to the code in the catch block. This behavior enables your program to provide special error handling that is more appropriate to your particular application. However, you must have enough information about the error to take the appropriate action.

MATLAB provides detailed information about the error by passing an MException object to functions executing the try/catch blocks.

The following try/catch blocks display the error message stored in an MException object when a function (surf in this case) is called without the necessary arguments:

```
try
    surf
catch ME
    disp(ME.message)
end
Not enough input arguments.
```

In this code, ME is an object of the MException class, which is returned by the catch statement to the function's workspace. Displaying the value of the object's message property returns information about the error (the surf function requires input arguments). However, this is not all the information available in the MException object.

You can list the public properties of an object with the properties function:

```
properties(ME)
Properties for class MException:
```

```
identifier
message
cause
stack
```

Objects Organize Data

The information returned in an MException object is stored in properties, which are much like structure fields. You reference a property using dot notation, as in ME.message. This reference returns the value of the property. For example,

```
class(ME.message)
ans =
char
```

shows that the value of the message property is an array of class char (a text string). The stack property contains a MATLAB struct:

ME.stack

```
ans =
  file: [1x90 char]
  name: 'surf'
  line: 50
```

You can simply treat the property reference, ME.stack as a structure and reference its fields:

```
ME.stack.file
ans =
D:\myMATLAB\matlab\toolbox\matlab\graph3d\surf.m
```

The file field of the struct contained in the stack property is a character array:

```
class(ME.stack.file)
ans =
char
```

You could, for example, use a property reference in MATLAB functions:

```
strcmp(ME.stack.name, 'surf')
```

```
ans =
```

methods(ME)

Object properties can contain any class of value and can even determine their value dynamically. This provides more flexibility than a structure and is easier to investigate than a cell array, which lacks fieldnames and requires indexing into various cells using array dimensions.

Objects Manage Their Own Data

You could write a function that generates a report from the data returned by MException object properties. This function could become quite complicated because it would have to be able to handle all possible errors. Perhaps you would use different functions for different try/catch blocks in your program. If the data returned by the error object needed to change, you would have to update the functions you have written to use the new data.

Objects provide an advantage in that objects define their own operations. A requirement of the MException object is that it can generate its own report. The methods that implement an object's operations are part of the object definition (i.e., specified by the class that defines the object). The object definition might be modified many times, but the interface your program (and other programs) use does not change. Think of your program as a client of the object, which isolates your code from the object's code.

To see what methods exist for MException objects, use the methods function:

```
Methods for class MException:

addCause getReport ne throw eq isequal rethrow throwAsCaller

Static methods:
```

You can use these methods like any other MATLAB statement when there is an MException object in the workspace. For example:

```
ME.getReport
ans =
Error using ==> surf
Not enough input arguments.
```

Objects often have methods that overload (redefined for the particular class of the object) MATLAB functions (e.g., isequal, fieldnames, etc.). This enables you to use objects just like other values. For example, MException objects have an isequal method. This method enables you to compare these objects in the same way you would compare variables containing doubles. If ME and ME2 are MException objects, you can compare them with this statement:

```
isequal(ME, ME2)
```

However, what really happens in this case is MATLAB calls the MException isequal method because you have passed MException objects to isequal.

Similarly, the eq method enables you to use the == operator with MException objects:

```
ME == ME2
```

Of course, objects should support only those methods that make sense. For example, it would probably not make sense to multiply MException objects so the MException class does not implement methods to do so.

When Should You Start Creating Object-Oriented Programs

Objects are well integrated into the MATLAB language, regardless of whether you are writing simple functions, working interactively in the command window, or creating large applications.

Simple programming tasks are easily implemented as simple functions, but as the magnitude and complexity of your tasks increase, functions become more complex and difficult to manage.

As functions become too large, you might break them into smaller functions and pass data from one to the other. However, as the number of functions becomes large, designing and managing the data passed to functions becomes difficult and error prone. At this point, you should consider moving your MATLAB programming tasks to object-oriented designs.

Understanding a Problem in Terms of Its Objects

Thinking in terms of things or objects is simpler and more natural for some problems. You might think of the nouns in your problem statement as the objects you need to define and the verbs as the operations you must perform.

For example, consider performing an analysis of economic institutions. It would be difficult to represent the various institutions as procedures even though they are all actors in the overall economy. Consider banks, mortgage companies, credit unions. You can represent each institution as an object that performs certain actions and contains certain data. The process of designing the objects involves identifying the characteristics of these institutions that are important to your application.

Identify Commonalities

All of these institutions belong in the general class of lending institutions, so all objects might provide a loan operation and have a Rate property that stores the current interest rate.

Identify Differences

You must also consider how each institution differs. A mortgage company might provide only home mortgage loans. Therefore, the loan operation might need be specialized for mortgage companies to provide fixRateLoan and varRateLoan methods to accommodate two loan types.

Consider Interactions

Institutions can interact, as well. For example, a mortgage company might sell a mortgage to a bank. To support this activity, the mortgage company object would support a sellMortgage operation and the bank object would support a buyMortgage operation.

You might also define a loan object, which would represent a particular loan. It might need Amount, Rate, and Lender properties. When the loan is sold to another institution, the Lender property could be changed, but all other information is neatly packaged within the loan object.

Add Only What Is Necessary

It is likely that these institutions engage in many activities that are not of interest to your application. During the design phase, you need to determine what operations and data an object needs to contain based on your problem definition.

Managing Data

Objects encapsulate the model of what the object represents. If the object represents a kind of lending institution, all the behaviors of lending institutions that are necessary for your application are contained by this object. This approach simplifies the management of data that is necessary in a typical procedural program.

Objects Manage Internal State

In the simplest sense, objects are data structures that encapsulate some internal state, which you access via its methods. When you invoke a method, it is the object that determines exactly what code to execute. In fact, two objects of the same class might execute different code paths for the same method invocation because their internal state is different. The internal workings of the object need not be of concern to your program — you simply use the interface the object provides.

Hiding the internal state from general access leads to more robust code. If a loan object's Lender property can be changed only by the object's newLender method, then inadvertent access is less likely than if the loan data were stored in a cell array where an indexing assignment statement could damage the data.

Objects provide a number of useful features not available from structures and cell arrays. For example, objects provide the ability to:

- Constrain the data assigned to any given property by executing a function to test values whenever an assignment is made
- Calculate the value of a property only when it is queried and thereby avoid storing data that might be dependent on the state of other data
- Broadcast notices when any property value is queried or changed, to which any number of listeners can respond by executing functions
- Restrict access to properties and methods

Reducing Redundancy

As the complexity of your program increases, the benefits of an object-oriented design become more apparent. For example, suppose you need to implement the following procedure as part of your application:

- 1 Check inputs
- 2 Perform computation on the first input argument
- **3** Transform the result of step 2 based on the second input argument
- 4 Check validity of outputs and return values

This simple procedure is easily implemented as an ordinary function. But now suppose you need to use this procedure again somewhere in your application, except that step 2 must perform a different computation. You could simply copy and paste the first implementation, and then rewrite step 2. Or you could create a function that accepted an

option indicating which computation to make, and so on. However, these options lead to more and more complicated code.

An object-oriented design could result in a simpler solution by factoring out the common code into what is called a base class. The base class would define the algorithm used and implement whatever is common to all cases that use this code. Step 2 could be defined syntactically, but not implemented, leaving the specialized implementation to the classes that you then derive from this base class.

```
Step 1
function checkInputs()
   % actual implementation
end
Step 2
function results = computeOnFirstArg()
   % specify syntax only
end
Step 3
function transformResults()
   % actual implementation
end
Step 4
function out = checkOutputs()
   % actual implementation
end
```

The code in the base class is not copied or modified, it is inherited by the various classes you derive from the base class. This reduces the amount of code to be tested, and isolates your program from changes to the basic procedure.

Defining Consistent Interfaces

The use of a class as the basis for similar, but more specialized classes is a useful technique in object-oriented programming. This class is often called an interface class. Incorporating this kind of class into your program design enables you to:

- · Identify the requirements of a particular objective
- · Encode these requirements into your program as an interface class

For example, suppose you are creating an object to return information about errors that occur during the execution of specific blocks of code. There might be functions that return

special types of information that you want to include in an error report only when the error is generated by these functions.

The interface class, from which all error objects are derived, could specify that all error objects must support a getReport method, but not specify how to implement that method. The class of error object created for the functions returning special information could implement its version of the getReport method to handle the different data.

The requirement defined by the interface class is that all error objects be able to display an error report. All programs that use this feature can rely on it being implement in a consistent way.

All of the classes derived from the interface class can create a method called getReport without any name conflicts because it is the class of the object that determines which getReport is called.


Reducing Complexity

Objects reduce complexity by reducing what you need to know to use a component or system. This happens in a couple of ways:

- Objects provide an interface that hides implementation details.
- · Objects enforce rules that control how objects interact.

To illustrate these advantages, consider the implementation of a data structure called a doubly linked list. See "Class to Implement Linked Lists" on page 3-36 for the actually implementation.

Here is a diagram of a three-element list:




To add a new node to the list, it is necessary to disconnect the existing nodes in the list, insert the new node, and reconnect the nodes appropriately. Here are the basic steps:

First disconnect the nodes:

- 1 Unlink n2.Prev from n1
- 2 Unlink n1.Next from n2

Now create the new node, connect it, and renumber the original nodes:

- 1 Link new.Prev to n1
- 2 Link new.Next to n3 (was n2)
- 3 Link n1.Next to new (will be n2)
- 4 Link n3.Prev to new (will be n2)



The details of how methods perform these steps are encapsulated in the class design. Each node object contains the functionality to insert itself into or remove itself from the list.

For example, in this class, every node object has an insertAfter method. To add a new node to a list, create the node object and then call its insertAfter method:

```
nnew = NodeConstructor;
nnew.insertAfter(n1)
```

Because the node class defines the code that implements these operations, this code is:

- Implemented in an optimal way by the class author
- · Always up to date with the current version of the class
- Well tested
- Can automatically update old-versions of the objects when they are loaded from MATfiles.

The object methods enforce the rules for how the nodes interact. This design removes the responsibility for enforcing rules from the applications that use the objects. It also means the application is less likely to generate errors in its own implementation of the process.

Fostering Modularity

As you decompose a system into objects (car -> engine -> fuel system -> oxygen sensor), you form modules around natural boundaries. These objects provide interfaces by which they interact with other modules (which might be other objects or functions). Often the data and operations behind the interface are hidden from other modules to segregate implementation from interface.

Classes provide three levels of control over code modularity:

- Public Any code can access this particular property or call this method.
- Protected Only the object's own methods and those of the object's whose class has been derived from this object's class can access this property or call this method.
- · Private Only the object's own methods can access this property or call this method.

Overloaded Functions and Operators

When you define a class, you can overload existing MATLAB functions to work with your new object. For example, the MATLAB serial port class overloads the fread function to read data from the device connected to the port represented by this object. You can define various operations, such as equality (eq) or addition (plus), for a class you have defined to represent your data.

Reduce Code Redundancy

Suppose your application requires a number of dialog windows to interact with users. By defining a class containing all the common aspects of the dialog windows, and then deriving the specific dialog classes from this base class, you can:

- Reuse code that is common to all dialog window implementations
- · Reduce code testing effort due to common code
- Provide a common interface to dialog developers
- Enforce a consistent look and feel
- · Apply global changes to all dialog windows more easily

Learning More

See "Classes in the MATLAB Language" on page 3-2 to learn more about writing object-oriented MATLAB programs.

Class Diagram Notation

The diagrams representing classes that appear in this documentation follow the conventions described in the following legend.

Concept	Graphical representation	Example
Object		BankAccount Properties AccountNumber AccountBalance
Class		Employee Properties Name Address
is_a	4	Asset
has_a	<>── (aggregation)	FileReader FileID
ilas_a	(composition)	Car Tire

Handle Objects

In this section... "What Is a Handle Object?" on page 1-16 "Copying Handles" on page 1-16 "Modifying Handle Objects in Functions" on page 1-17 "How to Determine If an Object Is a Handle" on page 1-19

What Is a Handle Object?

"Deleted Handle Objects" on page 1-19

Certain kinds of MATLAB objects are *handles*. When a variable holds a handle, it actually holds a reference to the object.

Handle objects enable more than one variable to refer to the same information. Handleobject behavior affects what happens when you copy handle objects and when you pass them to functions.

Copying Handles

All copies of a handle object variable refer to the same underlying object. This means that if h identifies a handle object, then,

```
h2 = h;
```

Creates another variable, h2, that refers to the same object as h.

For example, the MATLAB audioplayer function creates a handle object that contains the audio source data to reproduce a specific sound segment. The variable returned by the audioplayer function identifies the audio data and enables you to access object functions to play the audio.

MATLAB software includes audio data that you can load and use to create an audioplayer object. This sample load audio data, creates the audio player, and plays the audio:

```
load gong Fs y
gongSound = audioplayer(y,Fs);
```

```
play(gongSound)
```

Suppose you copy the gongSound object handle to another variable (gongSound2):

```
gongSound2 = gongSound;
```

The variables gongSound and gongSound2 are copies of the same handle and, therefore, refer to the same audio source. Access the audioplayer information using either variable.

For example, set the sample rate for the gong audio source by assigning a new value to the SampleRate property. First get the current sample rate and then set a new sample rate:

You can use gongSound2 to access the same audio source:

```
gongSound2.SampleRate
```

```
ans = 16384
```

Play the gong sound with the new sample rate:

```
play(gongSound2)
```

Modifying Handle Objects in Functions

When you pass an argument to a function, the function copies the variable from the workspace in which you call the function into the parameter variable in the function's workspace.

Passing a nonhandle variable to a function does not affect the original variable that is in the caller's workspace. For example, myFunc modifies a local variable called var, but when the function ends, the local variable var no longer exists:

```
function myFunc(var)
```

```
var = var + 1;
end

Define a variable and pass it to myfunc:
x = 12;
myFunc(x)

The value of x has not changed after executing myFunc(x):
x
x = 12
```

The myFunc function can return the modified value, which you could assign to the same variable name (X) or another variable.

```
function out = myFunc(var)
  out = var + 1;
end

Modify a value in myfunc:

x = 12;
x = myFunc(x)

x =
```

When the argument is a handle variable, the function copies only the handle, not the object identified by that handle. Both handles (original and local copy) refer to the same object.

When the function modifies the data referred to by the object handle, those changes are accessible from the handle variable in the calling workspace without the need to return the modified object.

For example, the modifySampleRate function changes the audioplayer sample rate:

```
function modifySampleRate(audioObj,sr)
  audioObj.SampleRate = sr;
end
```

Create an audioplayer object and pass it to the modifySampleRate function:

```
load gong Fs y
gongSound = audioplayer(y,Fs);
gongSound.SampleRate
ans =
    8192
modifySampleRate(gongSound,16384)
gongSound.SampleRate
ans =
    16384
```

The modifySampleRate function does not need to return a modified gongSound object because audioplayer objects are handle objects.

How to Determine If an Object Is a Handle

Handle objects are members of the handle class. Therefore, you can always identify an object as a handle using the isa function. isa returns logical true (1) when testing for a handle variable:

```
load gong Fs y00
gongSound = audioplayer(y,Fs);
isa(gongSound, 'handle')
ans =
```

To determine if a variable is a valid handle object, use isa and isvalid:

```
if isa(gongSound, 'handle') && isvalid(gongSound)
...
end
```

Deleted Handle Objects

When a handle object has been deleted, the handle variables that referenced the object can still exist. These variables become invalid because the object they referred to no

longer exists. Calling delete on the object removes the object, but does not clear handle variables.

For example, create an audioplayer object:

```
load gong Fs y
gongSound = audioplayer(y,Fs);
```

The output argument, gongSound, is a handle variable. Calling delete deletes the object along with the audio source information it contains:

```
delete(gongSound)
```

However, the handle variable still exists:

gongSound

```
gongSound =
  handle to deleted audioplayer
```

The whos command shows gongSound as an audioplayer object:

whos

Name	Size	Bytes	Class	Attributes
Fs	1x1	8	double	
gongSound	1x1	104	audioplayer	
У	42028x1	336224	double	

The handle gongSound no longer refers to a valid object:

isvalid(gongSound)

```
ans = 0
```

You cannot call functions on the invalid handle variable:

play(gongSound)

```
Invalid or deleted object.
```

You cannot access properties with the invalid handle variable:

gongSound.SampleRate

Invalid or deleted object.

To remove the variable, gongSound, use clear:

clear gongSound whos

Name	Size	Bytes	Class	Attributes
Fs V	1x1 42028x1	8 336224	double	

Basic Example

A Simple Class

```
In this section...

"Define a Simple Class" on page 2-2

"Create an Object" on page 2-3

"Access Properties" on page 2-3

"Call Methods" on page 2-3

"Add a Constructor" on page 2-4

"Vectorize Methods" on page 2-5

"Overloading Functions" on page 2-6

"BasicClass Code Listing" on page 2-6
```

Define a Simple Class

The basic purpose of a class is to define an object that encapsulates data and the operations performed on that data. For example, BasicClass defines a property and two methods that operate on the data in that property:

- · Value Property that contains the data stored in an object of the class
- roundOff Method that rounds the value of the property to two decimal places
- multiplyBy Method that multiplies the value of the property by the specified number

Here is the definition of BasicClass:

```
classdef BasicClass
  properties
    Value
  end
  methods
    function r = roundOff(obj)
        r = round([obj.Value],2);
  end
    function r = multiplyBy(obj,n)
        r = [obj.Value] * n;
  end
  end
end
```

To use the class, create an object of the class, assign the class data, and call operations on that data.

Related Information

For more information on defining classes, see classdef.

Create an Object

Create an object of the class using the class name:

```
a = BasicClass
a =
BasicClass with properties:
    Value: []
```

Initially, the property value is empty.

Access Properties

Assign a value to the OriginalValue property using the object variable and a dot before the property name:

```
a.Value = pi/3;
```

To access a property value, use dot notation without the assignment:

a.Value

```
ans = 1.0472
```

Related Information

For more information on class properties, see "Defining Properties"

Call Methods

Call the roundOff method on object a:

```
a = BasicClass(pi/3);
roundOff(a)
ans =
1.0500
```

Pass the object as the first argument to a method that takes multiple arguments:

```
multiplyBy(a,3)
ans =
    3.1416
```

You can also call a method using dot notation:

```
a.multiplyBy(3)
```

It is not necessary to pass the object explicitly as an argument when using dot notation. The notation uses the object to the left of the method name.

Related Information

For more information on class methods, see "Ordinary Methods"

Add a Constructor

Classes can define a special method to create objects, called a constructor. Constructor methods enable you to validate and assign property values. Here is a constructor for the BasicClass class:

```
methods
  function obj = BasicClass(val)
    if nargin > 0
        if isnumeric(val)
            obj.Value = val;
        else
            error('Value must be numeric')
        end
        end
        end
        end
        end
end
```

The constructor enables you to create an object in one step:

```
a = BasicClass(pi/3)
a =
BasicClass with properties:
    Value: 1.0472
```

This constructor also performs type checking on the input argument. For example:

```
a = BasicClass('A character array')
Error using BasicClass (line 11)
Value must be numeric
```

Related Information

For more information on constructors, see "Class Constructor Methods"

Vectorize Methods

MATLAB enables you to vectorize operations. For example, you can add a number to a vector:

```
[1 2 3] + 2
ans =
```

MATLAB adds the number 2 to each of the elements in the array [1 2 3]. To vectorize the arithmetic operator methods, enclose the Value property reference in brackets.

```
[obj.Value] + 2
```

By using vector notation, a can be an array:

```
a(1) = BasicClass(2.7984);
a(2) = BasicClass(sin(pi/3));
a(3) = BasicClass(7);
roundOff(a)
ans =
    2.8000    0.8700    7.0000
```

Overloading Functions

Classes can implement existing functionality, such as addition, by defining a method with the same name as the existing MATLAB function. For example, suppose you want to add two BasicClass object. It makes sense to add the values of the ObjectValue properties of each object.

Here is an overload of the MATLAB plus function. It defines addition for this class as adding the property values:

```
method
  function r = plus(o1,o2)
    r = [o1.Value] + [o2.Value];
  end
end
```

By implementing a method called plus, you can use the "+" operator with objects of BasicClass.

```
a = BasicClass(pi/3);
b = BasicClass(pi/4);
a + b
ans =
1.8326
```

Related Information

For information on overloading functions, see "Overload Functions for Your Class".

For information on overloading operators, see "Class Operator Implementations".

BasicClass Code Listing

Here is the BasicClass definition after adding the features discussed in this topic:

```
classdef BasicClass
  properties
    Value
  end
  methods
    function obj = BasicClass(val)
```

```
if nargin == 1
            if isnumeric(val)
               obj.Value = val;
            else
               error('Value must be numeric')
            end
         end
      end
      function r = roundOff(obj)
         r = round([obj.Value],2);
      function r = multiplyBy(obj,n)
         r = [obj.Value] * n;
      function r = plus(01,02)
         r = [o1.Value] + [o2.Value];
      end
   end
end
```

MATLAB Classes Overview

- "Classes in the MATLAB Language" on page 3-2
- "Developing Classes Typical Workflow" on page 3-8
- "Class to Manage Writable Files" on page 3-19
- "Class to Represent Structured Data" on page 3-24
- "Class to Implement Linked Lists" on page 3-36
- "Class for Graphing Functions" on page 3-54

Classes in the MATLAB Language

```
In this section...

"Classes" on page 3-2

"Some Basic Relationships" on page 3-4
```

Classes

In the MATLAB language, every value is assigned to a class. For example, creating a variable with an assignment statement constructs a variable of the appropriate class:

```
a = 7;
b = 'some text';
s.Name = 'Nancy';
s.Age = 64;
whos
whos
                                                Attributes
  Name
             Size
                              Bytes
                                    Class
             1x1
                                     double
  а
  b
             1x9
                                 18
                                      char
             1 x 1
                                370 struct
```

Basic commands like whos display the class of each value in the workspace. This information helps MATLAB users recognize that some values are characters and display as text while other values are double precision numbers, and so on. Some variables can contain different classes of values like structures.

Predefined Classes

MATLAB defines fundamental class that comprise the basic types used by the language. For more information, see "Fundamental MATLAB Classes".

User-Defined Classes

You can create your own MATLAB classes. For example, you could define a class to represent polynomials. This class could define the operations typically associated with MATLAB classes, like addition, subtraction, indexing, displaying in the command window, and so on. These operations would need to perform the equivalent of polynomial addition, polynomial subtraction, and so on. For example, when you add two polynomial objects:

p1 + p2

the plus operation must be able to add polynomial objects because the polynomial class defines this operation.

When you define a class, you can overload special MATLAB functions (such as plus.m for the addition operator). MATLAB calls these methods when users apply those operations to objects of your class.

See "Class Design for Polynomials" on page 18-2 for an example that creates just such a class.

MATLAB Classes — Key Terms

MATLAB classes use the following words to describe different parts of a class definition and related concepts.

- Class definition Description of what is common to every instance of a class.
- Properties Data storage for class instances
- Methods Special functions that implement operations that are usually performed only on instances of the class
- Events Messages that are defined by classes and broadcast by class instances when some specific action occurs
- Attributes Values that modify the behavior of properties, methods, events, and classes
- Listeners Objects that respond to a specific event by executing a callback function
 when the event notice is broadcast
- Objects Instances of classes, which contain actual data values stored in the objects' properties
- Subclasses Classes that are derived from other classes and that inherit the methods, properties, and events from those classes (subclasses facilitate the reuse of code defined in the superclass from which they are derived).
- Superclasses Classes that are used as a basis for the creation of more specifically defined classes (i.e., subclasses).
- · Packages Folders that define a scope for class and function naming

These are general descriptions of these components and concepts. This documentation describes all of these components in detail.

Some Basic Relationships

This section discusses some of the basic concepts used by MATLAB classes.

Classes


A class is a definition that specifies certain characteristics that all instances of the class share. These characteristics are determined by the properties, methods, and events that define the class and the values of attributes that modify the behavior of each of these class components. Class definitions describe how objects of the class are created and destroyed, what data the objects contain, and how you can manipulate this data.

Class Hierarchies

It sometimes makes sense to define a new class in terms of existing classes. This enables you to reuse the designs and techniques in a new class that represents a similar entity. You accomplish this reuse by creating a subclass. A subclass defines objects that are a subset of those defined by the superclass. A subclass is more specific than its superclass and might add new properties, methods, and events to those inherited from the superclass.

Mathematical sets can help illustrate the relationships among classes. In the following diagram, the set of Positive Integers is a subset of the set of Integers and a subset of Positive numbers. All three sets are subsets of Real numbers, which is a subset of All Numbers.

The definition of Positive Integers requires the additional specification that members of the set be greater than zero. Positive Integers combine the definitions from both Integers and Positives. The resulting subset is more specific, and therefore more narrowly defined, than the supersets, but still shares all the characteristics that define the supersets.



The "is a" relationship is a good way to determine if it is appropriate to define a particular subset in terms of existing supersets. For example, each of the following statements makes senses:

- A Positive Integer is an Integer
- · A Positive Integer is a Positive number

If the "is a" relationship holds, then it is likely you can define a new class from a class or classes that represent some more general case.

Reusing Solutions

Classes are usually organized into taxonomies to foster code reuse. For example, if you define a class to implement an interface to the serial port of a computer, it would probably be very similar to a class designed to implement an interface to the parallel port. To reuse code, you could define a superclass that contains everything that is common to the two types of ports, and then derive subclasses from the superclass in which you implement only what is unique to each specific port. Then the subclasses would inherit all of the common functionality from the superclass.

Objects

A class is like a template for the creation of a specific instance of the class. This instance or object contains actual data for a particular entity that is represented by the class. For example, an instance of a bank account class is an object that represents a specific bank account, with an actual account number and an actual balance. This object has built into it the ability to perform operations defined by the class, such as making deposits to and withdrawals from the account balance.

Objects are not just passive data containers. Objects actively manage the data contained by allowing only certain operations to be performed, by hiding data that does not need to be public, and by preventing external clients from misusing data by performing operations for which the object was not designed. Objects even control what happens when they are destroyed.

Encapsulating Information

An important aspect of objects is that you can write software that accesses the information stored in the object via its properties and methods without knowing anything about how that information is stored, or even whether it is stored or calculated when queried. The object isolates code that accesses the object from the internal implementation of methods and properties. You can define classes that hide both data and operations from any methods that are not part of the class. You can then implement whatever interface is most appropriate for the intended use.

References

- [1] Shalloway, A., J. R. Trott, Design Patterns Explained A New Perspective on Object-Oriented Design.. Boston, MA: Addison-Wesley 2002.
- [2] Gamma, E., R. Helm, R. Johnson, J. Vlissides, Design Patterns Elements of Reusable Object-Oriented Software. Boston, MA: Addison-Wesley 1995.
- [3] Freeman, E., Elisabeth Freeman, Kathy Sierra, Bert Bates, *Head First Design Patterns*. Sebastopol, CA 2004.

Related Examples

- "A Simple Class"
- "Developing Classes Typical Workflow" on page 3-8

- "Class to Represent Structured Data" on page 3-24
- "Class to Manage Writable Files" on page 3-19
- "Class to Implement Linked Lists" on page 3-36

External Web Sites

• Object Oriented Programming

Developing Classes — Typical Workflow

In this section...

"Formulating a Class" on page 3-8

"Specifying Class Components" on page 3-9

"BankAccount Class Implementation" on page 3-10

"Formulating the AccountManager Class" on page 3-14

"Implementing the AccountManager Class" on page 3-15

"AccountManager Class Synopsis" on page 3-15

"Using BankAccount Objects" on page 3-17

Formulating a Class

This example discusses how to approach the design and implementation of a class. The objective of this class is to represent a familiar concept (a bank account). However, you can apply the same approach to most class designs.

To design a class that represents a bank account, first determine the elements of data and the operations that form your abstraction of a bank account. For example, a bank account has:

- · An account number
- An account balance
- A status (open, closed, etc.)

You must perform certain operations on a bank account:

- Create an object for each bank account
- Deposit money
- Withdraw money
- Generate a statement
- Save and load the BankAccount object

If the balance is too low and you attempt to withdraw money, the bank account broadcasts a notice. When this event occurs, the bank account broadcasts a notice to other entities that are designed to listen for these notices. In this example, a simplified version of an account manager program performs this task.

In this example, an account manager program determines the status of all bank accounts. This program monitors the account balance and assigns one of three values:

- open Account balance is a positive value
- overdrawn Account balance is overdrawn, but by \$200 or less.
- closed Account balance is overdrawn by more than \$200.

These features define the requirements of the BankAccount and AccountManager classes. Include only what functionality is required to meet your specific objectives. Support special types of accounts by subclassing BankAccount and adding more specific features to the subclasses. Extend the AccountManager as required to support new account types.

Specifying Class Components

Classes store data in properties, implement operations with methods, and support notifications with events and listeners. Here is how the BankAccount and AccountManager classes define these components.

Class Data

The class defines these properties to store the account number, account balance, and the account status:

- AccountNumber A property to store the number identifying the specific account.
 MATLAB assigns a value to this property when you create an instance of the class.
 Only BankAccount class methods can set this property. The SetAccess attribute is private.
- AccountBalance A property to store the current balance of the account. The
 class operation of depositing and withdrawing money assigns values to this property.
 Only BankAccount class methods can set this property. The SetAccess attribute is
 private.
- AccountStatus The BankAccount class defines a default value for this property.
 The AccountManager class methods change this value whenever the value of the AccountBalance falls below 0. The Access attribute specifies that only the AccountManager and BankAccount classes have access to this property.
- AccountListener Storage for the InsufficentFunds event listener. Saving a BankAccount object does not save this property because you must recreate the listener when loading the object.

Class Operations

These methods implement the operations defined in the class formulation:

- BankAccount Accepts an account number and an initial balance to create an
 object that represents an account.
- deposit Updates the AccountBalance property when a deposit transaction occurs
- withdraw Updates the AccountBalance property when a withdrawal transaction occurs
- getStatement Displays information about the account
- loadobj Recreates the account manager listener when you load the object from a
 MAT-file.

Class Events

The account manager program changes the status of bank accounts that have negative balances. To implement this action, the BankAccount class triggers an event when a withdrawal results in a negative balance. Therefore, the triggering of the InsufficientsFunds event occurs from within the withdraw method.

To define an event, specify a name within an events block. Trigger the event by a call to the notify handle class method. Because InsufficientsFunds is not a predefined event, you can name it with any string and trigger it with any action.

BankAccount Class Implementation

It is important to ensure that there is only one set of data associated with any object of a BankAccount class. You would not want independent copies of the object that could have, for example, different values for the account balance. Therefore, implement the BankAccount class as a handle class. All copies of a given handle object refer to the same data.

BankAccount Class Synopsis

BankAccount Class	Discussion
classdef BankAccount < handle	Handle class because there should be only one copy of any instance of

BankAccount Class	Discussion
	BankAccount."Comparing Handle and Value Classes"
<pre>properties (SetAccess = private) AccountNumber AccountBalance end properties (Transient)</pre>	AccountStatus property access by AccountManager class methods.
AccountListener end	AccountNumber and AccountBalance properties have private set access.
	AccountListener property is transient so the listener handle is not saved.
	See "Specify Property Attributes".
events InsufficientFunds end	Class defines event called InsufficentFunds. withdraw method triggers event when account balance becomes negative.
	For information on events and listeners, see "Events" .
methods	Block of ordinary methods. See "Methods and Functions" for syntax.
<pre>function BA = BankAccount(AccountNumber,InitialBalanc BA.AccountNumber = AccountNumber; BA.AccountBalance = InitialBalance; BA.AccountListener = AccountManager.addAccount(BA)</pre>	values with input arguments.
end	AccountManager.addAccount is static method of AccountManager class. Creates listener for InsufficientFunds event and stores listener handle in AccountListener property.

BankAccount Class

```
function deposit(BA,amt)
      BA.AccountBalance = BA.AccountBalance + amt;
      if BA.AccountBalance > 0
          BA.AccountStatus = 'open';
       end
   end
   function withdraw(BA,amt)
       if (strcmp(BA.AccountStatus, 'closed')&& ...
          BA.AccountBalance < 0)
          disp(['Account ',num2str(BA.AccountNumber),...
               has been closed.'])
          return
      end
      newbal = BA.AccountBalance - amt;
      BA.AccountBalance = newbal;
      if newbal < 0</pre>
          notify(BA,'InsufficientFunds')
      end
   end
   function getStatement(BA)
      disp(['Account: ',num2str(BA.AccountNumber)])
ab = sprintf('%0.2f',BA.AccountBalance);
      disp(['CurrentBalance: ',ab])
disp(['Account Status: ',BA.AccountStatus])
   end
end
methods (Static)
```

Discussion

deposit adjusts value of AccountBalance property.

If AccountStatus is closed and subsequent deposit brings AccountBalance into positive range, then AccountStatus is reset to open.

Updates AccountBalance property. If value of account balance is negative as result of the withdrawal, notify triggers InsufficentFunds event.

For more information on listeners, see "Events and Listeners — Syntax and Techniques".

Display selected information about the account.

End of ordinary methods block.

Beginning of static methods block. See "Static Methods"

BankAccount Class Discussion function obj = loadobj(s) loadobj method: if isstruct(s) accNum = s.AccountNumber; If the load operation fails, initBal = s.AccountBalance; create the object from a obj = BankAccount(accNum,initBal); obj.AccountListener = AccountManager.addAccount(s); end Recreates the listener end using the newly created BankAccount object as the source. For more information on saving and loading objects, see "Save and Load Process" end End of static methods block end End of classdef

Expand for Class Code

```
classdef BankAccount < handle</pre>
   properties (Access = ?AccountManager)
      AccountStatus = 'open';
   properties (SetAccess = private)
      AccountNumber
      AccountBalance
   end
   properties (Transient)
      AccountListener
   end
   events
      InsufficientFunds
   end
   methods
      function BA = BankAccount(accNum,initBal)
         BA.AccountNumber = accNum;
         BA.AccountBalance = initBal;
         BA.AccountListener = AccountManager.addAccount(BA);
      function deposit(BA,amt)
         BA.AccountBalance = BA.AccountBalance + amt;
```

```
if BA.AccountBalance > 0
           BA.AccountStatus = 'open';
        end
      end
      function withdraw(BA,amt)
        if (strcmp(BA.AccountStatus, 'closed')&& BA.AccountBalance <= 0)</pre>
           disp(['Account ',num2str(BA.AccountNumber),' has been closed.'])
           return
        end
        newbal = BA.AccountBalance - amt;
        BA.AccountBalance = newbal;
        if newbal < 0</pre>
           notify(BA,'InsufficientFunds')
        end
     end
      function getStatement(BA)
        disp('-----')
        disp(['Account: ',num2str(BA.AccountNumber)])
        ab = sprintf('%0.2f',BA.AccountBalance);
        disp(['CurrentBalance: ',ab])
        disp(['Account Status: ',BA.AccountStatus])
        disp('----')
     end
  end
  methods (Static)
     function obj = loadobj(s)
        if isstruct(s)
           accNum = s.AccountNumber;
           initBal = s.AccountBalance;
           obj = BankAccount(accNum,initBal);
           obj.AccountListener = AccountManager.addAccount(s);
        end
      end
  end
end
```

Formulating the AccountManager Class

The purpose of the AccountManager class is to provide services to accounts. For the BankAccount class, the AccountManager class listens for withdrawals that cause the balance to drop into the negative range. When the BankAccount object triggers the InsufficientsFunds event, the AccountManager resets the account status.

The AccountManager class stores no data so it does not need properties. The BankAccount object stores the handle of the listener object.

The AccountManager performs two operations:

- · Assign a status to each account as a result of a withdrawal
- Adds an account to the system by monitoring account balances.

Class Components

The AccountManager class implements two methods:

- assignStatus Method that assigns a status to a BankAccount object. Serves as the listener callback.
- addAccount Method that creates the InsufficientFunds listener.

Implementing the AccountManager Class

The AccountManager class implements both methods as static because there is no need for an AccountManager object. These methods operate on BankAccount objects.

The AccountManager is not intended to be instantiated. Separating the functionality of the AccountManager class from the BankAccount class provides greater flexibility and extensibility. For example, doing so enables you to:

- Extend the AccountManager class to support other types of accounts while keeping the individual account classes simple and specialized.
- Change the criteria for the account status without affecting the compatibility of saved and loaded BankAccount objects.
- Develop an Account superclass that factors out what is common to all accounts without requiring each subclass to implement the account management functionality

AccountManager Class Synopsis

AccountManager Class	Discussion
classdef AccountManager	This class defines the InsufficentFunds event
	listener and the listener callback.

AccountManager Class	Discussion
methods (Static)	There is no need to create an instance of this class so the methods defined are static. See "Static Methods".
<pre>function assignStatus(BA) if BA.AccountBalance < 0 if BA.AccountBalance < -200 BA.AccountStatus = 'closed'; else BA.AccountStatus = 'overdrawn'; end end end</pre>	The assignStatus method is the callback for the InsufficentFunds event listener. It determines the value of a BankAccount object AccountStatus property based on the value of the AccountBalance property. The BankAccount class constructor calls the AccountManager addAccount method to create and store this listener.
<pre>function lh = addAccount(BA) lh = addlistener(BA, 'InsufficientFunds', @(src, ~)AccountManager.assignStatus(src)); end</pre>	addAccount creates the listener for the InsufficentFunds event that the BankAccount class defines. See "Control Listener Lifecycle"
end end	end statements for methods and for classdef.

Expand for Class Code

```
classdef AccountManager
  methods (Static)
   function assignStatus(BA)
    if BA.AccountBalance < 0
        if BA.AccountBalance < -200
            BA.AccountStatus = 'closed';
        else
            BA.AccountStatus = 'overdrawn';
        end
   end</pre>
```

```
end
function lh = addAccount(BA)
    lh = addlistener(BA, 'InsufficientFunds', ...
    @(src, ~)AccountManager.assignStatus(src));
end
end
end
```

Using BankAccount Objects

The BankAccount class, while overly simple, demonstrates how MATLAB classes behave. For example, create a BankAccount object with an account number and an initial deposit of \$500:

```
BA = BankAccount(1234567,500)

BA =

BankAccount with properties:

AccountNumber: 1234567
AccountBalance: 500
AccountListener: [1x1 event.listener]
```

Use the getStatement method to check the status:

```
getStatement(BA)

Account: 1234567
CurrentBalance: 500.00
Account Status: open
```

Make a withdrawal of \$600, which results in a negative account balance:

The \$600 withdrawal triggered the InsufficientsFunds event. The current criteria defined by the AccountManager class results in a status of overdrawn.

Make another withdrawal of \$200:

```
withdraw(BA,200)
getStatement(BA)

Account: 1234567
CurrentBalance: -300.00
Account Status: closed
```

Now the AccountStatus has been set to closed by the listener and further attempts to make withdrawals are blocked without triggering the event:

```
withdraw(BA,100)
```

deposit(BA,700)

Account 1234567 has been closed.

If the AccountBalance is returned to a positive value by a deposit, then the AccountStatus is returned to open and withdrawals are allowed again:

```
getStatement(BA)

Account: 1234567

CurrentBalance: 400.00

Account Status: open
```

Class to Manage Writable Files

In this section...

"Flexible Workflow" on page 3-19

"Performing a Task with an Object" on page 3-19

"Defining the Filewriter Class" on page 3-19

"Using Filewriter Objects" on page 3-21

Flexible Workflow

The MATLAB language does not require you to define classes for all the code you write. You can use objects along with ordinary functions. This section illustrates the use of an object that implements the basic task of writing text to a file.

Performing a Task with an Object

One of the advantages of an object instead of writing a function to perform a task is that objects can encapsulate related data. For example, consider the task of writing data to a file. It involves the following steps:

- · Opening a file for writing and saving the file identifier
- Using the file identifier to write data to the file
- · Using the file identifier to close the file

Defining the Filewriter Class

This class writes text to a file. The advantage of using a class for this purpose is to:

- · Hide private data The caller does not need to manage the file identifier.
- Ensure only one file identifier is in use at any time Copies of handle objects reference the same file identifier as the original.
- Provide automatic file closing when the object is deleted the object's delete
 method takes care of cleanup without needing to be called explicitly.

The Filewriter class derives from the handle class. Therefore, a Filewriter object is a handle object. All copies of handle objects reference the same internal data. There is only one file identifier in use, even if you make copies of the object.

Also, handle classes define a delete method, which is called automatically when MATLAB destroys a handle object. This example overrides the delete method. This method closes the file before deleting the object and losing file identifier.

The Filewriter Class

```
classdef Filewriter < handle</pre>
   properties (Access = private)
      FileID
   end
   methods
      function obj = Filewriter(filename)
         obj.FileID = fopen(filename, 'a');
      end
      function writeToFile(obj,text_str)
         fprintf(obj.FileID, '%s\n', text str);
      end
      function delete(obj)
         fclose(obj.FileID);
      end
   end
end
```

Filewriter Class Synopsis

Filewriter Class	Discussion
classdef Filewriter < handle	This class derives from handle to provide a single reference to the file identifier and use the class destructor to close the file. For general information on class destructors, see "Handle Class Destructor"
properties (Access = private) FileID end	Only Filewriter class methods can access file identifier. "Property Attributes"

Filewriter Class	Discussion
methods	For method syntax, see "Methods and Functions"
<pre>function obj = Filewriter(filename) if nargin < 1 error('You must specify a filename') else obj.FileID = fopen(filename, 'a'); end end</pre>	Class constructor opens file for writing and saves file identifier in private property. See fopen and "Rules for Constructors"
<pre>function writeToFile(obj,text_str) fprintf(obj.FileID,'%s\n',text_str); end</pre>	Write a text string to open file. See ferror and fseek.
<pre>function delete(obj) fclose(obj.FileID); end</pre>	delete method closes file before destroying Filewriter object. See "Handle Class Destructor"
end end	end statements for methods and for classdef.

Using Filewriter Objects

Provides a file name to create a Filewriter object. Use the writeToFile method to write text to the file. The following statements create a file named mynewclass.m and write one line to it. The clear all command deletes the Filewriter object. Clearing the object variable calls its delete method, which closes the file.

```
fw = Filewriter('MyNewClass.m');
writeToFile(fw,'classdef < handle')
clear fw
type MyNewClass
classdef MyNewClass < handle</pre>
```

Filewriter objects provide functionality that you can use from functions and within other classes. You can create an ordinary function that uses this object, as the writeClassFile function does below.

This example creates only one simple class template, but another version could accept a cell array of attribute name/value pairs, method names, and so on.


```
function writeClassFile(classname, superclass)
```

```
fw = Filewriter([classname '.m']);
   if nargin > 1
      writeToFile(fw,['classdef ' classname ' < ' superclass])</pre>
   else
      writeToFile(fw,['classdef ' classname])
   end
                        properties ')
   writeToFile(fw, '
   writeToFile(fw,' ')
   writeToFile(fw,'
                        end')
   writeToFile(fw,
   writeToFile(fw, '
                        methods ')
                            function')
   writeToFile(fw,
   writeToFile(fw,' ')
   writeToFile(fw, '
                            end')
   writeToFile(fw, '
                        end')
   writeToFile(fw,'end')
end
```

To create a class file template, call writeClassFile with the name of the new class and its superclass. Use the type command to display the contents of the file:

```
writeClassFile('MyNewClass','handle')
edit MyNewClass
```

Here is the template file in the editor ready to add code:



See Also

fclose | fopen | fprintf

More About

· "Handle Class Destructor"

Class to Represent Structured Data

In this section...

"Objects As Data Structures" on page 3-24

"Structure of the Data" on page 3-24

"The TensileData Class" on page 3-25

"Create an Instance and Assign Data" on page 3-25

"Restrict Properties to Specific Values" on page 3-26

"Simplifying the Interface with a Constructor" on page 3-27

"Calculate Data on Demand" on page 3-28

"Displaying TensileData Objects" on page 3-29

"Method to Plot Stress vs. Strain" on page 3-30

"TensileData Class Synopsis" on page 3-31

Objects As Data Structures

This example defines a class for storing data with a specific structure. Using a consistent structure for data storage makes it easier to create functions that operate on the data. A MATLAB struct with field names describing the particular data element is a useful way to organize data. However, a class can define both the data storage (properties) and operations that you can perform on that data (methods). This example illustrates these advantages.

Background for the Example

For this example, the data represents tensile stress/strain measurements. These data are used to calculate the elastic modulus of various materials. In simple terms, stress is the force applied to a material and strain is the resulting deformation. Their ratio defines a characteristic of the material. While this is an over simplification of the process, it suffices for this example.

Structure of the Data

This table describes the structure of the data.

Data	Description
Material	Character string identifying the type of material tested
SampleNumber	Number of a particular test sample
Stress	Vector of numbers representing the stress applied to the sample during the test.
Strain	Vector of numbers representing the strain at the corresponding values of the applied stress.
Modulus	Number defining an elastic modulus of the material under test, which is calculated from the stress and strain data

The TensileData Class

This example begins with a simple implementation of the class and builds on this implementation to illustrate how features enhance the usefulness of the class.

The first version of the class provides only data storage. The class defines a property for each of the required data elements.

```
classdef TensileData
properties
Material
SampleNumber
Stress
Strain
Modulus
end
end
```

Create an Instance and Assign Data

The following statements create a TensileData object and assign data to it:

```
td = TensileData;
td.Material = 'Carbon Steel';
td.SampleNumber = 001;
td.Stress = [2e4 4e4 6e4 8e4];
td.Strain = [.12 .20 .31 .40];
td.Modulus = mean(td.Stress./td.Strain);
```

Advantages of a Class vs. a Structure

Treat the TensileData object (td in the statements above) much as you would any MATLAB structure. However, defining a specialized data structure as a class has advantages over using a general-purpose data structure, like a MATLAB struct:

• Users cannot accidentally misspell a field name without getting an error. For example, typing the following:

```
td.Modulis = ...
```

would simply add a new field to a structure, but returns an error when td is an instance of the TensileData class.

- A class is easy to reuse. Once you have defined the class, you can easily extend it with subclasses that add new properties.
- A class is easy to identify. A class has a name so that you can identify objects with the whos and class functions and the Workspace browser. The class name makes it easy to refer to records with a meaningful name.
- · A class can validate individual field values when assigned, including class or value.
- A class can restrict access to fields, for example, allowing a particular field to be read, but not changed.

Restrict Properties to Specific Values

Restrict properties to specific values by defining a property set access method. MATLAB calls the set access method whenever setting a value for a property.

Material Property Set Function

The Material property set method restricts the assignment of the property to one of the following strings: aluminum, stainless steel, or carbon steel.

Add this function definition to the methods block.

```
classdef TensileData
properties
Material
SampleNumber
Stress
Strain
```

```
Modulus
   end
   methods
      function obj = set.Material(obj,material)
         if (strcmpi(material, 'aluminum') ||...
               strcmpi(material, 'stainless steel') | |...
               strcmpi(material, 'carbon steel'))
            obj.Material = material;
         else
            error('Invalid Material')
         end
      end
   end
end
```

When there is an attempt to set the Material property, MATLAB calls the set.Material method before setting the property value.

If the value matches the acceptable values, the function set the property to that value. The code within set method can access the property directly to avoid calling the property set method recursively.

For example:

```
td = TensileData;
td.Material = 'brass';
```

Error using TensileData/set.Material Invalid Material

Simplifying the Interface with a Constructor

Simplify the interface to the TensileData class by adding a constructor that:

- Enables you to pass the data as arguments to the constructor
- Assigns values to properties

The constructor is a method having the same name as the class.

```
methods
```

```
function td = TensileData(material, samplenum, stress, strain)
   if nargin > 0
      td.Material = material;
```

```
td.SampleNumber = samplenum;
td.Stress = stress;
td.Strain = strain;
end
end
end
```

Create a TensileData object fully populated with data using the following statement:

```
td = TensileData('carbon steel',1,...
[2e4 4e4 6e4 8e4],...
[.12 .20 .31 .40]);
```

Calculate Data on Demand

If the value of a property depends on the values of other properties, define that property using the Dependent attribute. MATLAB does not store the values of dependent properties. The dependent property get method determines the property value when the property is queried.

Calculating Modulus

TensileData objects do not store the value of the Modulus property. The constructor does not have an input argument for the value of the Modulus property. The value of the Modulus:

- Is calculated from the Stress and Strain property values
- Needs to change if the value of the Stress or Strain property changes

Therefore, it is better to calculate the value of the Modulus property only when its value is requested. Use a property get access method to calculate the value of the Modulus.

Modulus Property Get Method

The Modulus property depends on Stress and Strain, so its Dependent attribute is true. Place the Modulus property in a separate properties block and set the Dependent attribute.

The get. Modulus method calculates and returns the value of the Modulus property.

```
properties (Dependent)
```

```
Modulus end
```

Define the property get method in a methods block using only default attributes.

```
methods
  function modulus = get.Modulus(obj)
    ind = find(obj.Strain > 0);
    modulus = mean(obj.Stress(ind)./obj.Strain(ind));
  end
end
```

This method calculates the average ratio of stress to strain data after eliminating zeros in the denominator data.

MATLAB calls the get. Modulus method when the property is queried. For example,

```
td = TensileData('carbon steel',1,...
       [2e4 4e4 6e4 8e4],...
       [.12 .20 .31 .40]);
td.Modulus
ans =
    1.9005e+005
```

Modulus Property Set Method

To set the value of a Dependent property, the class must implement a property set method. There is no need to allow explicit setting of the Modulus property. However, a set method enables you to provide a customized error message. The Modulus set method references the current property value and then returns an error:

```
methods
  function obj = set.Modulus(obj,~)
    fprintf('%s%d\n','Modulus is: ',obj.Modulus)
    error('You cannot set the Modulus property');
  end
end
```

Displaying TensileData Objects

The TensileData class overloads the disp method. This method controls object display in the command window.

The disp method displays the value of the Material, SampleNumber, and Modulus properties. It does not display the Stress and Strain property data. These properties contain raw data that is not easily viewed in the command window.

The disp method uses fprintf to display formatted text in the command window:

Method to Plot Stress vs. Strain

It is useful to view a graph of the stress/strain data to determine the behavior of the material over a range of applied tension. The TensileData class overloads the MATLAB plot function.

The plot method creates a linear graph of the stress versus strain data and adds a title and axis labels to produce a standardized graph for the tensile data records:


```
methods
  function plot(td,varargin)
    plot(td.Strain,td.Stress,varargin{:})
    title(['Stress/Strain plot for Sample',...
        num2str(td.SampleNumber)])
    ylabel('Stress (psi)')
    xlabel('Strain %')
  end
end
```

The first argument to this method is a TensileData object, which contains the data.

The method passes a variable list of arguments (varargin) directly to the built-in plot function. The TensileData plot method allows you to pass line specifier arguments or property name/value pairs.

For example:

```
td = TensileData('carbon steel',1,...
       [2e4 4e4 6e4 8e4],[.12 .20 .31 .40]);
plot(td,'-+b','LineWidth',2)
```



TensileData Class Synopsis

Discussion
Value class enables independent copies of object. For more information, see "Comparing Handle and Value Classes"
See "Structure of the Data" on page 3-24

Example Code Discussion properties (Dependent) Calculate Modulus when Modulus queried. For information about end this code, see "Calculate Data on Demand" on page 3-28 For general information, see "Access Methods for Dependent Properties" methods For general information about methods, see "Ordinary Methods" function td = TensileData(material, samplenum,... For information about this code, stress, strain) see "Simplifying the Interface if nargin > 0 with a Constructor" on page td.Material = material; td.SampleNumber = samplenum; 3-27 td.Stress = stress; td.Strain = strain; For general information end end about constructors, see "Class Constructor Methods" function obj = set.Material(obj,material) Restrict possible values for if (strcmpi(material, 'aluminum') ||... Material property. strcmpi(material, 'stainless steel') ||... strcmpi(material, 'carbon steel')) obj.Material = material; For information about this code, see "Restrict Properties error('Invalid Material') to Specific Values" on page end end 3-26.For general information about property set methods, see "Property Set Methods".

Example Code	Discussion
<pre>function m = get.Modulus(obj) ind = find(obj.Strain > 0); m = mean(obj.Stress(ind)./obj.Strain(ind));</pre>	Calculate Modulus property when queried.
end	For information about this code, see "Modulus Property Get Method" on page 3-28.
	For general information about property get methods, see "Property Get Methods".
<pre>function obj = set.Modulus(obj,~) fprintf('%s%d\n','Modulus is: ',obj.Modulus) error('You cannot set Modulus property); end</pre>	Add set method for Dependent Modulus property. For information about this code, see "Modulus Property Set Method" on page 3-29
	For general information about property set methods, see "Property Set Methods".
<pre>function disp(td) sprintf(1,'Material: %s\nSample Number: %g\nModulus: td.Material,td.SampleNumber,td.Modulus) end</pre>	Overload disp method to display certain properties.
	For information about this code, see "Displaying TensileData Objects"
	For general information about overloading disp, see "Overload the disp Function"
<pre>function plot(td,varargin) plot(td.Strain,td.Stress,varargin{:}) title(['Stress/Strain plot for Sample', num2str(td.SampleNumber)]) ylabel('Stress (psi)')</pre>	Overload plot function to accept TensileData objects and graph stress vs. strain.
xlabel('Strain %') end	"Method to Plot Stress vs. Strain"
end end	end statements for $\tt methods$ and for <code>classdef</code> .

Expand for Class Code

```
classdef TensileData
   properties
      Material
      SampleNumber
      Stress
      Strain
   end
   properties (Dependent)
      Modulus
   end
   methods
      function td = TensileData(material, samplenum, stress, strain)
         if nargin > 0
            td.Material = material;
            td.SampleNumber = samplenum;
            td.Stress = stress;
            td.Strain = strain;
         end
      end
      function obj = set.Material(obj,material)
         if (strcmpi(material, 'aluminum') ||...
               strcmpi(material, 'stainless steel') ||...
               strcmpi(material, 'carbon steel'))
            obj.Material = material;
         else
            error('Invalid Material')
         end
      end
      function m = get.Modulus(obj)
         ind = find(obj.Strain > 0);
         m = mean(obj.Stress(ind)./obj.Strain(ind));
      end
      function obj = set.Modulus(obj,~)
         fprintf('%s%d\n','Modulus is: ',obj.Modulus)
         error('You cannot set Modulus property');
      end
      function disp(td)
```

More About

· "Class Syntax Fundamentals"

Class to Implement Linked Lists

In this section...

"Class Definition Code" on page 3-36

"dlnode Class Design" on page 3-36

"Create Doubly Linked List" on page 3-37

"Why a Handle Class for Linked Lists?" on page 3-38

"dlnode Class Synopsis" on page 3-39

"Specialize the dlnode Class" on page 3-51

Class Definition Code

For the class definition code listing, see "dlnode Class Synopsis" on page 3-39.

To use the class, create a folder named @dlnode and save dlnode.m to this folder. The parent folder of @dlnode must be on the MATLAB path. Alternatively, save dlnode.m to a path folder.

d1node Class Design

dlnode is a class for creating doubly linked lists in which each node contains:

- · Data array
- · Handle to the next node
- · Handle to the previous node

Each node has methods that enables the node to be:

- Inserted before a specified node in a linked list
- Inserted after a specific node in a linked list
- · Removed from a list


Class Properties

The dlnode class implements each node as a handle object with three properties:

- Data Contains the data for this node
- Next Contains the handle of the next node in the list (SetAccess = private)

Prev — Contains the handle of the previous node in the list (SetAccess = private)

This diagram shows a list with three-nodes n1, n2, and n3. It also shows how the nodes reference the next and previous nodes.



Class Methods

The dlnode class implements the following methods:

- dlnode Construct a node and assign the value passed as an input to the Data property
- insertAfter Insert this node after the specified node
- insertBefore Insert this node before the specified node
- · removeNode Remove this node from the list and reconnect the remaining nodes
- clearList Remove large lists efficiently
- delete Private method called by MATLAB when deleting the list.

Create Doubly Linked List

Create a node by passing the node's data to the dlnode class constructor. For example, these statements create three nodes with data values 1, 2, and 3:

```
n1 = dlnode(1);
n2 = dlnode(2);
n3 = dlnode(3);
```

Build these nodes into a doubly linked list using the class methods designed for this purpose:

```
n2.insertAfter(n1) % Insert n2 after n1
n3.insertAfter(n2) % Insert n3 after n2
```

Now the three nodes are linked:

```
n1.Next % Points to n2
ans =
  dlnode with properties:
    Data: 2
    Next: [1x1 dlnode]
    Prev: [1x1 dlnode]
n2.Next.Prev % Points back to n2
ans =
  dlnode with properties:
    Data: 2
    Next: [1x1 dlnode]
    Prev: [1x1 dlnode]
n1.Next.Next % Points to n3
ans =
  dlnode with properties:
    Data: 3
    Next: []
    Prev: [1x1 dlnode]
n3.Prev.Prev % Points to n1
ans =
  dlnode with properties:
    Data: 1
    Next: [1x1 dlnode]
    Prev: []
```

Why a Handle Class for Linked Lists?

Each node is unique in that no two nodes can be previous to or next to the same node.

For example, a node object, node, contains in its Next property the handle of the next node object, node.Next. Similarly, the Prev property contains the handle of the previous node, node.Prev. Using the three-node linked list defined in the previous section, you can demonstrate that the following statements are true:

```
n1.Next == n2
n2.Prev == n1
```

Now suppose you assign n2 to x:

```
x = n2;
```

The following two equalities are then true:

```
x == n1.Next
x.Prev == n1
```

But each instance of a node is unique so there is only one node in the list that can satisfy the conditions of being equal to n1. Next and having a Prev property that contains a handle to n1. Therefore, x must point to the same node as n2.

This means there has to be a way for multiple variables to refer to the same object. The MATLAB handle class provides a means for both x and n2 to refer to the same node.

The handle class defines the eq method (use methods ('handle') to list the handle class methods), which enables the use of the == operator with all handle objects.

Related Information

For more information on handle classes, see "Comparing Handle and Value Classes" on page 6-2.

d1node Class Synopsis

This section describes the implementation of the dlnode class.

Example Code	Discussion
classdef dlnode < handle	"dlnode Class Design"
	"Why a Handle Class for Linked Lists?"
	"Comparing Handle and Value Classes"
properties	"dlnode Class Design" on page 3-36

Example Code	Discussion
Data end	
<pre>properties (SetAccess = private) Next = dlnode.empty; Prev = dlnode.empty; end</pre>	"Property Attributes": SetAccess. Initialize these properties to empty dlnode objects. For general information about properties, see "Defining Properties"
methods	For general information about methods, see "How to Use Methods"
<pre>function node = dlnode(Data) if (nargin > 0) node.Data = Data; end end</pre>	Creating an individual node (not connected) requires only the data. For general information about constructors, see "Rules for Constructors"
<pre>function insertAfter(newNode, nodeBefore) removeNode(newNode); newNode.Next = nodeBefore.Next; newNode.Prev = nodeBefore; if ~isempty(nodeBefore.Next)</pre>	Insert node into a doubly linked list after specified node, or link the two specified nodes if there is not already a list. Assigns the correct values for Next and Prev properties. "Insert Nodes"
<pre>function insertBefore(newNode, nodeAfter) removeNode(newNode); newNode.Next = nodeAfter; newNode.Prev = nodeAfter.Prev; if ~isempty(nodeAfter.Prev)</pre>	Insert node into doubly linked list before specified node, or link the two specified nodes if there is not already a list. This method assigns correct values for Next and Prev properties. See "Insert Nodes"

Example Code	Discussion
<pre>function removeNode(node) if ~isscalar(node) error('Nodes must be scalar') end prevNode = node.Prev; nextNode = node.Next; if ~isempty(prevNode) prevNode.Next = nextNode; end if ~isempty(nextNode) nextNode.Prev = prevNode; end node.Next = = dlnode.empty; node.Prev = dlnode.empty; end function clearList(node) prev = node.Prev; next = node.Next; removeNode(node) while ~isempty(next) node = next; next = node.Next; removeNode(node); end while ~isempty(prev) node = prev; prev = node.Prev; removeNode(node) end end</pre>	Remove node and fix the list so that remaining nodes are properly connected. node argument must be scalar. Once there are no references to node, MATLAB deletes it. "Remove a Node" Avoid recursive calls to destructor as a result of clearing the list variable. Loop through list to disconnect each node. When there are no references to a node, MATLAB calls the class destructor (see the delete method) before deleting it.
methods (Access = private) function delete(node) clearList(node) end	Class destructor method. MATLAB calls the delete method you delete a node that is still connected to the list.
end end	End of private methods and end of class definition.

Expand for Class Code

```
classdef dlnode < handle
  % dlnode A class to represent a doubly-linked node.
  % Link multiple dlnode objects together to create linked lists.
  properties
    Data
  end
  properties(SetAccess = private)
    Next = dlnode.empty;
    Prev = dlnode.empty;</pre>
```

```
end
methods
   function node = dlnode(Data)
      % Construct a dlnode object
      if nargin > 0
         node.Data = Data;
      end
   end
   function insertAfter(newNode, nodeBefore)
      % Insert newNode after nodeBefore.
      removeNode(newNode);
      newNode.Next = nodeBefore.Next;
      newNode.Prev = nodeBefore;
      if ~isempty(nodeBefore.Next)
         nodeBefore.Next.Prev = newNode;
      end
      nodeBefore.Next = newNode;
   end
   function insertBefore(newNode, nodeAfter)
      % Insert newNode before nodeAfter.
      removeNode(newNode);
      newNode.Next = nodeAfter;
      newNode.Prev = nodeAfter.Prev;
      if ~isempty(nodeAfter.Prev)
         nodeAfter.Prev.Next = newNode;
      end
      nodeAfter.Prev = newNode;
   end
   function removeNode(node)
      % Remove a node from a linked list.
      if ~isscalar(node)
         error('Input must be scalar')
      end
      prevNode = node.Prev;
      nextNode = node.Next;
      if ~isempty(prevNode)
         prevNode.Next = nextNode;
      end
      if ~isempty(nextNode)
         nextNode.Prev = prevNode;
```

```
end
         node.Next = dlnode.empty;
         node.Prev = dlnode.empty;
      end
      function clearList(node)
         % Clear the list before
         % clearing list variable
         prev = node.Prev;
         next = node.Next;
         removeNode(node)
         while ~isempty(next)
            node = next;
            next = node.Next;
            removeNode(node);
         end
         while ~isempty(prev)
            node = prev;
            prev = node.Prev;
            removeNode(node)
         end
      end
   end
   methods (Access = private)
      function delete(node)
         clearList(node)
      end
   end
end
```

Class Properties

Only dlnode class methods can set the Next and Prev properties because these properties have private set access (SetAccess = private). Using private set access prevents client code from performing any incorrect operation with these properties. The dlnode class methods perform all the operations that are allowed on these nodes.

The Data property has public set and get access, allowing you to query and modify the value of Data as required.

Here is how the dlnode class defines the properties:

```
properties
```

```
Data
end
properties(SetAccess = private)
  Next = dlnode.empty;
  Prev = dlnode.empty;
end
```

Construct a Node Object

To create a node object, specify the node's data as an argument to the constructor:

```
function node = dlnode(Data)
  if nargin > 0
     node.Data = Data;
  end
end
```

Insert Nodes

There are two methods for inserting nodes into the list — insertAfter and insertBefore. These methods perform similar operations, so this section describes only insertAfter in detail.

```
function insertAfter(newNode, nodeBefore)
  removeNode(newNode);
  newNode.Next = nodeBefore.Next;
  newNode.Prev = nodeBefore;
  if ~isempty(nodeBefore.Next)
        nodeBefore.Next.Prev = newNode;
  end
  nodeBefore.Next = newNode;
end
```

How insertAfter Works

First, insertAfter calls the removeNode method to ensure that the new node is not connected to any other nodes. Then, insertAfter assigns the newNode Next and Prev properties to the handles of the nodes that are after and before the newNode location in the list.

For example, suppose you want to insert a new node, nnew, after an existing node, n1, in a list containing n1-n2-n3.

First, create nnew:

```
nnew = dlnode(rand(3));
```

Next, call insertAfter to insert nnew into the list after n1:

```
nnew.insertAfter(n1)
```

The insertAfter method performs the following steps to insert nnew in the list between n1 and n2:

Set nnew.Next to n1.Next (n1.Next is n2):

```
nnew.Next = n1.Next;
```

Set nnew.Prev to n1


```
nnew.Prev = n1;
```

 If n1.Next is not empty, then n1.Next is still n2, so n1.Next.Prev is n2.Prev, which is set to nnew

```
n1.Next.Prev = nnew;
```

n1.Next is now set to nnew

```
n1.Next = nnew;
```



Remove a Node


The removeNode method removes a node from a list and reconnects the remaining nodes. The insertBefore and insertAfter methods always call removeNode on the node to insert before attempting to connect it to a linked list.

Calling removeNode ensures the node is in a known state before assigning it to the Next or Prev property:

```
function removeNode(node)
   if ~isscalar(node)
      error('Input must be scalar')
   end
   prevNode = node.Prev;
   nextNode = node.Next;
   if ~isempty(prevNode)
        prevNode.Next = nextNode;
   end
   if ~isempty(nextNode)
        nextNode.Prev = prevNode;
   end
   node.Next = dlnode.empty;
   node.Prev = dlnode.empty;
end
```

For example, suppose you remove n2 from a three-node list (n1-n2-n3):

n2.removeNode;



removeNode removes n2 from the list and reconnects the remaining nodes with the following steps:

```
n1 = n2.Prev;
n3 = n2.Next;
if n1 exists, then
    n1.Next = n3;
if n3 exists, then
```

```
n3.Prev = n1
```

The list is rejoined because n1 connects to n3 and n3 connects to n1. The final step is to ensure that n2.Next and n2.Prev are both empty (i.e., n2 is not connected):

```
n2.Next = dlnode.empty;
n2.Prev = dlnode.empty;
```

Removing a Node From a List

Suppose you create a list with ten nodes and save the handle to the head of the list:

```
head = dlnode(1);
for i = 10:-1:2
  new = dlnode(i);
  insertAfter(new,head);
end
```

Now remove the third node (Data property assigned the value 3):

```
removeNode(head.Next.Next)
```

Now the third node in the list has a data value of 4:

```
head.Next.Next
```

```
ans =
  dlnode with properties:
   Data: 4
   Next: [1x1 dlnode]
   Prev: [1x1 dlnode]
```


And the previous node has a Data value of 2:

head.Next

```
ans =
  dlnode with properties:
  Data: 2
  Next: [1x1 dlnode]
  Prev: [1x1 dlnode]
```

Delete a Node

To delete a node, call the removeNode method on that node. The removeNode method disconnects the node and reconnects the list before allowing MATLAB to destroy the removed node. MATLAB destroys the node once references to it by other nodes are removed and the list is reconnected.



Delete the List

When you create a linked list and assign a variable that contains, for example, the head or tail of the list, clearing that variable causes the destructor to recurse through the entire list. With large enough list, clearing the list variable can result in MATLAB exceeding its recursion limit.

The clearList method avoids recursion and improves the performance of deleting large lists by looping over the list and disconnecting each node. clearList accepts the handle of any node in the list and removes the remaining nodes.

```
function clearList(node)
  if ~isscalar(node)
```

```
error('Input must be scalar')
   end
   prev = node.Prev;
   next = node.Next;
   removeNode(node)
   while ~isempty(next)
      node = next;
      next = node.Next;
      removeNode(node);
   end
   while ~isempty(prev)
      node = prev;
      prev = node.Prev;
      removeNode(node)
   end
end
```

For example, suppose you create a list with a large number of nodes:

```
head = dlnode(1);
for k = 100000:-1:2
   nextNode = dlnode(k);
   insertAfter(nextNode,head)
end
```

The variable head contains the handle to the node at the head of the list:

head

```
head =
  dlnode with properties:
    Data: 1
    Next: [1x1 dlnode]
    Prev: []
head.Next
ans =
  dlnode with properties:
    Data: 2
    Next: [1x1 dlnode]
```

```
Prev: [1x1 dlnode]
```

You can call clearList to remove the whole list:

```
clearList(head)
```

The only nodes that have not been deleted by MATLAB are those for which there exists an explicit reference. In this case, those references are head and nextNode:

head

```
head =
  dlnode with properties:
    Data: 1
    Next: []
    Prev: []

nextNode

nextNode =
  dlnode with properties:
    Data: 2
    Next: []
    Prev: []
```

You can removed these nodes by clearing the variables:

```
clear head nextNode
```

The delete Method

The delete method simply calls the clearList method:

```
methods (Access = private)
  function delete(node)
     clearList(node)
  end
end
```

The delete method has private access to prevent users from calling delete when intending to delete a single node. MATLAB calls delete implicitly when the list is destroyed.

To delete a single node from the list, use the removeNode method.

Specialize the dlnode Class

The dlnode class implements a doubly linked list and provides a convenient starting point for creating more specialized types of linked lists. For example, suppose you want to create a list in which each node has a name.

Rather than copying the code used to implement the dlnode class, and then expanding upon it, you can derive a new class from dlnode (i.e., subclass dlnode). You can create a class that has all the features of dlnode and also defines its own additional features. And because dlnode is a handle class, this new class is a handle class too.

NamedNode Class Definition

To use the class, create a folder named <code>QNamedNode</code> and save <code>NamedNode.m</code> to this folder. The parent folder of <code>QNamedNode</code> must be on the MATLAB path. Alternatively, save <code>NamedNode.m</code> to a path folder.

The following class definition shows how to derive the NamedNode class from the dlnode class:

```
classdef NamedNode < dlnode
  properties
    Name = '';
  end
  methods
    function n = NamedNode (name,data)
        if nargin == 0
            name = '';
            data = [];
        end
        n = n@dlnode(data);
        n.Name = name;
  end
end
end</pre>
```

The NamedNode class adds a Name property to store the node name.

The constructor calls the class constructor for the dlnode class, and then assigns a value to the Name property.

Use NamedNode to Create a Doubly Linked List

Use the NamedNode class like the dlnode class, except that you specify a name for each node object. For example:

```
n(1) = NamedNode('First Node',100);
n(2) = NamedNode('Second Node',200);
n(3) = NamedNode('Third Node',300);
```

Now use the insert methods inherited from **dlnode** to build the list:

```
n(2).insertAfter(n(1))
n(3).insertAfter(n(2))
```

A single node displays its name and data when you query its properties:

```
n(1).Next
ans =
  NamedNode with properties:
    Name: 'Second Node'
    Data: 200
    Next: [1x1 NamedNode]
    Prev: [1x1 NamedNode]
n(1).Next.Next
ans =
  NamedNode with properties:
    Name: 'Third Node'
    Data: 300
    Next: []
    Prev: [1x1 NamedNode]
n(3).Prev.Prev
ans =
  NamedNode with properties:
    Name: 'First Node'
    Data: 100
```

```
Next: [1x1 NamedNode]
Prev: []
```

More About

• "The Handle Superclass"

Class for Graphing Functions

```
In this section...

"Class Definition Block" on page 3-54

"Using the topo Class" on page 3-55

"Behavior of the Handle Class" on page 3-56
```

The *class block* is the code that starts with the **classdef** key word and terminates with the **end** key word. The following example illustrated a simple class definition that uses:

- · Handle class
- Property set and get functions
- Use of a delete method for the handle object
- Static method syntax

Class Definition Block

The following code defines a class called topo. It is derived from handle so it is a handle class, which means it references the data it contains. See "Using the topo Class" on page 3-55 for information on how this class behaves.

```
classdef topo < handle
% topo is a subclass of handle
   properties
      FigHandle % Store figure handle
      FofXY % function handle
      Lm = [-2*pi 2*pi]; % Initial limits
   end % properties
   properties (Dependent, SetAccess = private)
   end % properties Dependent = true, SetAccess = private
      function obj = topo(fnc,limits)
      % Constructor assigns property values
         obj.FofXY = fnc;
         obj.Lm = limits;
      end % topo
      function set.Lm(obj,lim)
      % Lm property set function
         if \sim (\lim(1) < \lim(2))
            error('Limits must be monotonically increasing')
         else
```

```
obi.Lm = lim:
         end
      end % set.Lm
      function data = get.Data(obj)
      % get function calculates Data
      % Use class name to call static method
         [x,y] = topo.grid(obj.Lm);
         matrix = obj.FofXY(x,y);
         data.X = x;
         data.Y = y;
         data.Matrix = matrix;% Return value of property
      end % get.Data
      function surflight(obj)
      % Graph function as surface
         obj.FigHandle = figure;
         surfc(obj.Data.X,obj.Data.Y,obj.Data.Matrix,...
            'FaceColor',[.8 .8 0], 'EdgeColor',[0 .2 0],...
            'FaceLighting','gouraud');
         camlight left; material shiny; grid off
         colormap copper
      end % surflight method
      function delete(obj)
      % Delete the figure
         h = obj.FigHandle;
         if ishandle(h)
            delete(h);
         else
            return
         end
      end % delete
   end % methods
   methods (Static = true) % Define static method
     function [x,y] = grid(lim)
        inc = (\lim(2) - \lim(1))/35;
        [x,y] = meshgrid(lim(1):inc:lim(2));
     end % grid
   end % methods Static = true
end % topo class
```

Using the topo Class

This class is designed to display a combination surface/contour graph of mathematical functions of two variables evaluated on a rectangular domain of x and y. For example, any of the following functions can be evaluated over the specified domain (note that x and y have the same range of values in this example just for simplicity).

```
x.*exp(-x.^2 - y.^2); [-2 2]

sin(x).*sin(y); [-2*pi 2*pi]
```

```
sqrt(x.^2 + y.^2); [-2*pi 2*pi]
```

To create an instance of the class, passing a function handle and a vector of limits to the constructor. The easiest way to create a function handle for these functions is to use an anonymous function:


```
tobj = topo(@(x,y) x.*exp(-x.^2-y.^2),[-2 2]);
```

The class surflight method uses the object to create a graph of the function. The actual data required to create the graph is not stored. When the surflight method accesses the Data property, the property's get function performs the evaluation and returns the data in the Data property structure fields. This data is then plotted. The advantage of not storing the data is the reduced size of the object.

Behavior of the Handle Class


The topo class is defined as a handle class. This means that instances of this class are handle objects that reference the underlying data store created by constructing the object. For example, suppose you create an instance of the class and create a copy of the object:

```
tobj = topo(@(x,y) x.*exp(-x.^2-y.^2),[-2 2]);
a = tobj;
surflight(a)
```



Now suppose you change the FofXY property so that it contains a function handle that points to another function:

tobj.FofXY =
$$@(x,y)$$
 y.*exp(-x.^2-y.^2);
surflight(a)



Because a is a copy of the handle object tobj, changes to the data referenced by tobj also change the data referenced by a.

How a Value Class Differs

If topo were a value class, the objects tobj and a would not share data; each would have its own copy of the property values.

Class Definition—Syntax Reference

- · "Class Files and Folders" on page 4-2
- "Class Components" on page 4-5
- "Classdef Block" on page 4-9
- "Properties" on page 4-11
- "Methods and Functions" on page 4-16
- · "Methods In Separate Files" on page 4-20
- "Events and Listeners" on page 4-24
- "Attribute Specification" on page 4-26
- "Call Superclass Methods on Subclass Objects" on page 4-29
- "Representative Class Code" on page 4-31
- "MATLAB Code Analyzer Warnings" on page 4-36
- "Objects In Switch Statements" on page 4-38
- "Operations on Objects" on page 4-45
- "Using the Editor and Debugger with Classes" on page 4-49
- "Automatic Updates for Modified Classes" on page 4-50 $\,$
- "Compatibility with Previous Versions" on page 4-56
- "Comparing MATLAB with Other OO Languages" on page 4-59

Class Files and Folders

In this section...

"Options for Class Folders" on page 4-2

"Options for Class Files" on page 4-2

"Grouping Classes with Package Folders" on page 4-3

Options for Class Folders

There are two ways create folders that contain class-definition files:

- Path folder a folder that is on the MATLAB path.
- Class folder a folder that is in a path folder and is name with the @ character and the class name. For example:

@MyClass

Class folders are not directly on the MATLAB path. The path folder that contains the class folder is on the MATLAB path.

Options for Class Files


There are two ways to specify classes with respect to files and folders:

- · Create a single, self-contained class definition file in a path folder or a class folder
- Define a class in multiple files, which requires you to use a class folder inside a path folder

Creating a Single, Self-Contained Class Definition File


Create a single, self-contained class definition file in a folder on the MATLAB® path. The name of the file must match the class (and constructor) name and must have the .m extension. Define the class entirely in this file. You can put other single-file classes in this folder.

The following diagram shows an example of this folder organization. pathfolder is a folder on the MATLAB path.



Distributing the Class Definition to Multiple Files


If you use multiple files to define a class, put all the class-definition files (the file containing the classdef and all class method files) in a single @ClassName folder. That class folder must be inside a folder that is on the MATLAB path. You can define only one class in a class folder.



A path folder can contain classes defined in both class folders and single files without a class folder.

Grouping Classes with Package Folders

The parent folder to a package folder is on the MATLAB path, but the package folder is not. Package folders (which always begin with a + character) can contain multiple class definitions, package-scoped functions, and other packages. A package folder defines a new name space in which you can reuse class names. Use the package name to refer to classes and functions defined in package folders (for example, packagefld1.ClassNameA(), packagefld2.packageFunction()).



More About

- "Class and Path Folders" on page 5-14
- "Packages Create Namespaces" on page 5-19
- "Methods In Separate Files" on page 4-20

Class Components

In this section...

"Class Building Blocks" on page 4-5

"Class Definition Block" on page 4-5

"Properties Block" on page 4-6

"Methods Block" on page 4-6

"Events Block" on page 4-7

"Enumeration Block" on page 4-8

"Related Information" on page 4-8

Class Building Blocks

MATLAB organizes class definition code into modular blocks, delimited by keywords. All keywords have an associated end statement:

- classdef...end Definition of all class components
- properties...end Declaration of property names, specification of property attributes, assignment of default values
- methods...end Declaration of method signatures, method attributes, and function code
- events...end Declaration of event name and attributes
- enumeration...end Declaration of enumeration members and enumeration values

properties, methods, events, and enumeration are keywords only within a classdef block.

Class Definition Block

The classdef block contains the class definition within a file that starts with the classdef keyword and terminates with the end keyword.

classdef (ClassAttributes) ClassName < SuperClass</pre>

```
end ...
```

For example, this classdef defines a class called MyClass that subleasses the handle class, but cannot be used to derive subclasses:

```
classdef (Sealed) MyClass < handle
   ...
end</pre>
```

For more syntax information, see "Classdef Block" on page 4-9.

Properties Block

The properties block (one for each unique set of attribute specifications) contains property definitions, including optional initial values. The properties block starts with the properties keyword and terminates with the end keyword.

```
classdef ClassName
   properties (PropertyAttributes)
     ...
   end
   ...
end
```

For example, this class defines a property called Prop1 that has private access and has a default value equal to the output of the date function.

```
classdef MyClass
  properties (Access = private)
     Prop1 = date;
  end
  ...
end
```

For more information, see "Properties" on page 4-11.

Methods Block

The methods block (one for each unique set of attribute specifications) contains function definitions for the class methods. The methods block starts with the methods keyword and terminates with the end keyword.

```
classdef ClassName
  methods (MethodAttributes)
    ...
  end
  ...
end

For example:

classdef MyClass
  methods (Access = private)
    function obj = myMethod(obj)
    ...
  end
  end
end
end
```

For more information, see "Methods and Functions" on page 4-16.

Events Block

The events block (one for each unique set of attribute specifications) contains the names of events that this class declares. The events block starts with the events keyword and terminates with the end keyword.

```
classdef ClassName
  events (EventAttributes)
        EventName
  end
  ...
end
```

For example, this class defined an event called StateChange with a ListenAccess set to protected:

```
classdef EventSource
  events (ListenAccess = protected)
    StateChanged
  end
  ...
end
```

For more information, see "Events and Listeners" on page 4-24.

Enumeration Block

The enumeration block contains the enumeration members defined by the class. The enumeration block starts with the enumeration keyword and terminates with the end keyword.

```
classdef ClassName < SuperClass
  enumeration
        EnumerationMember
  end
  ...
end</pre>
```

For example, this class defines two enumeration members that represent logical false and true:

```
classdef Boolean < logical
   enumeration
    No (0)
    Yes (1)
   end
end</pre>
```

For more information, see "Working with Enumerations".

Related Information

"Class and Path Folders"

Classdef Block

In this section... "Specifying Attributes and Superclasses" on page 4-9 "Assigning Class Attributes" on page 4-9 "Specifying Superclasses" on page 4-10

Specifying Attributes and Superclasses

The classdef block contains the class definition. The classdef line is where you specify:

- Class attributes
- Superclasses

end

The classdef block contains the properties, methods, and events subblocks.

Assigning Class Attributes

Class attributes modify class behavior in some way. Assign values to class attributes only when you want to change their default value.

No change to default attribute values:

```
classdef ClassName
    ...
end

One or more attribute values assigned:
classdef (attribute1 = value,...)
    ...
end

For example, the TextString class specifies that it cannot be used to derive subclasses:
classdef TextString (Sealed)
```

For a list of attributes and a discussion of the behaviors they control, see "Class Attributes" on page 5-5 .

Specifying Superclasses

Derive a class from one or more other classes by specifying the superclasses on the classdef line:

```
classdef ClassName < SuperclassName
   ...
end</pre>
```

For example, the LinkedList class inherits from classes called Array and handle:

```
classdef LinkedList < Array & handle
   ...
end</pre>
```

For more information on superclasses, see "Creating Subclasses — Syntax and Techniques" on page 11-7

Properties

In this section...

- "What You Can Define" on page 4-11
- "Initializing Property Values" on page 4-11
- "Defining Default Values" on page 4-12
- "Assigning Property Values from the Constructor" on page 4-12
- "Initializing Properties to Unique Values" on page 4-13
- "Property Attributes" on page 4-13
- "Property Access Methods" on page 4-14
- "Referencing Object Properties Using Variables" on page 4-15

What You Can Define

You can control aspects of property definitions in the following ways:

- · Specify a default value for each property individually
- Assign property values in a class constructor
- · Assign property attribute values on a per block basis
- Define methods that execute when the property is set or queried

Note: Always use case sensitive property names in your MATLAB code. Properties cannot have the same name as the class.

Initializing Property Values

There are two basic approaches to initializing property values:

- In the property definition MATLAB evaluates the expression only once and assigns the same value to the property of every instance.
- In a class constructor MATLAB evaluates the assignment expression for each instance, which ensures that each instance has a unique value.

Defining Default Values

Within a properties block, you can control an individual property's default value. Default values can be constant values or MATLAB expressions. Expressions cannot reference variables. For example:

```
classdef ClassName
  properties
    Prop1 % No default value assigned
    Prop2 = 'some text';
    Prop3 = sin(pi/12); % Expression returns default value
  end
end
```

MATLAB sets property values not specified in the class definition to empty ([]).

Note: Evaluation of property default values occurs only when the value is first needed, and only once when MATLAB first initializes the class. MATLAB does not reevaluate the expression each time you create a class instance.

Related Information

For more information on the evaluation of expressions that you assign as property default values, see "When MATLAB Evaluates Expressions" on page 5-10 .

Assigning Property Values from the Constructor

To assign values to a property from within the class constructor, reference the object that the constructor returns (the output variable obj):

```
classdef MyClass
  properties
     Prop1
  end
  methods
     function obj = MyClass(intval)
        obj.Prop1 = intval;
  end
  end
end
```

When you assign a property in the class constructor, MATLAB evaluates the assignment statement for each object you create. Assign property values in the constructor if you want each object to contain a unique value for that property.

For example, suppose you want to assign a unique handle object to the property of another object each time you create one of those objects. Assign the handle object to the property in the constructor. Call the handle object constructor to create a unique handle object with each instance of your class.

Related Information

See "Referencing the Object in a Constructor" on page 8-17 for more information on constructor methods.

Initializing Properties to Unique Values

MATLAB assigns properties to the specified default values only once when MATLAB loads the class definition. Therefore, if you initialize a property value with a handle-class constructor, MATLAB calls this constructor only once and every instance references the same handle object. If you want a property value to be initialized to a new instance of a handle object each time you create an object, assign the property value in the constructor.

Property Attributes

All properties have attributes that modify certain aspects of the property's behavior. Specified attributes apply to all properties in a particular properties block. For example:

```
classdef ClassName
  properties (PropertyAttribute = value)
        Prop1
        Prop2
  end
end
```

For example, only methods in the same class definition can modify and query the Salary and Password properties.

```
classdef EmployeeInfo
  properties (Access = private)
     Salary
     Password
  end
end
```

This restriction exists because the class defines these properties in a properties block with the Access attribute set to private.

Property Attributes

For a description of property attributes, see "Property Attributes".

Property Access Methods

You can define methods that MATLAB calls whenever setting or querying a property value. Define property set access or get access methods in methods blocks that specify no attributes and have the following syntax:

methods

```
function obj = set.PropertyName(obj,value)
    ...
end

function value = get.PropertyName(obj)
    ...
end
end
```

MATLAB does not call the property set access method when assigning the default value specified in the property's definition block.

For example, the set.Password method tests the length of the character array assigned to a property named Password. If there are less than seven characters in the value assigned to the property, MATLAB returns the error. Otherwise, MATLAB assigns the specified value to the property.

```
function obj = set.Password(obj,pw)
  if numel(pw) < 7
     error('Password must have at least 7 characters')
  else
     obj.Password = pw;
end</pre>
```

Related Information

For more information on these methods, see "Property Access Methods".

Referencing Object Properties Using Variables

MATLAB can resolve a property name from a char variable using an expression of the form:

```
object.(PropertyNameVar)
```

where PropertyNameVar is a variable containing the name of a valid object property. Use this syntax when passing property names as arguments. For example, the getPropValue function returns the value of the KeyType property:

```
PropName = 'KeyType';
function o = getPropValue(obj,PropName)
   o = obj.(PropName);
end
```

More About

• "How to Use Properties"

Methods and Functions

```
In this section...

"The Methods Block" on page 4-16

"Method Calling Syntax" on page 4-16

"Private Methods" on page 4-18

"More Detailed Information On Methods" on page 4-18

"Class-Related Functions" on page 4-18

"Overloading Functions and Operators" on page 4-19
```

The Methods Block

Define methods as MATLAB functions within a methods block, inside the classdef block. The constructor method has the same name as the class and returns an object. You can assign values to properties in the class constructor. Terminate all method functions with an end statement.

```
classdef ClassName
  properties
        PropertyName
  end
methods
        function obj = ClassName(arg1,...)
        obj.PropertyName = arg1;
        ...
  end
        function ordinaryMethod(obj,arg1,...)
        ...
  end
end
methods (Static)
        function staticMethod(arg1,...)
        ...
  end
end
```

Method Calling Syntax

MATLAB differs from languages like C++ and Java® in that there is no special hidden class object passed to all methods. You must pass an object of the class explicitly to the

method. The left most argument does not need to be the class object, and the argument list can have multiple objects.

Note: Always use case sensitive method names in your MATLAB code.

Ordinary Methods

Call ordinary methods using MATLAB function syntax or dot notation. For example, suppose you have a class that defines ordinaryMethod. Pass an object of the defining class and whatever arguments are required.

```
classdef MyClass
   methods
     function out = ordinaryMethod(obj,arg1)
     ...
   end
  end
end
```

Call ordinaryMethod using the object obj of the class and either syntax:

```
obj = MyClass;
r = ordinaryMethod(obj,arg1);
r = obj.ordinaryMethod(arg1);
```

Static Methods

Static methods do not require an object of the class. To call a static method, prefix the method name with the class name so that MATLAB can determine what class defines the method.

```
classdef MyClass
  methods (Static)
    function out = staticMethod(arg1)
    ...
    end
  end
end
```

Call staticMethod using the syntax classname.methodname:

```
r = MyClass.staticMethod(arg1);
```

Related Information

For information on methods that do not require objects of their class, see "Static Methods" on page 8-23.

Private Methods

Use the Access method attribute to create a private method. You do not need to use a private folder.

See "Method Attributes" on page 8-5 for a list of method attributes.

More Detailed Information On Methods

"Methods"

Class-Related Functions

You can define functions that are not class methods in the file that contains the class definition (classdef). Define local functions outside of the classdef - end block, but in the same file as the class definition. Functions defined in classdef files work like local functions. You can call these functions from anywhere in the same file, but they are not visible outside of the file in which you define them.

Local functions in classdef files are useful for utility functions that you use only within that file. These functions can take or return arguments that are instances of the class but, it is not necessary, as in the case of ordinary methods. For example, the following code defines myUtilityFcn outside the classdef block:

```
classdef MyClass
  properties
    PropName
  end
  methods
    function obj = MyClass(arg1)
        obj.PropName = arg1;
    end
  end
end
end % End of classdef

function myUtilityFcn
```

end

You also can create package functions, which require the use of the package name when calling these functions.

Overloading Functions and Operators

Overload MATLAB functions for your class by defining a class method with the same name as the function that you want to overload. MATLAB dispatches to the class method when the function is called with an instance of the class.

You can overload MATLAB arithmetic, logical, relational, and indexing operators by defining class methods with the appropriate names.

See the handle class for a list of operations defined for that class, which are inherited by all classes deriving from handle.

More About

- "Packages Create Namespaces"
- "Class Operator Implementations"

Methods In Separate Files

In this section...

"Methods In Class Folders" on page 4-20

"Define Method in Function File" on page 4-21

"Specify Method Attributes in classdef File" on page 4-21

"Methods That You Must Define In the classdef File" on page 4-22

Methods In Class Folders

You can define class methods in files that are separate from the class definition file, with certain exceptions (see "Methods That You Must Define In the classdef File" on page 4-22).

To use multiple files for class definitions, put the class files in a folder having a name beginning with the @ character followed by the name of the class (this is called a class folder). Ensure that the parent folder of the class folder is on the MATLAB path.

If the class folder is contained in one or more package folders, then the top-level package folder must be on the MATLAB path.

For example, the folder @MyClass must contain the file MyClass.m (which contains the classdef block) and can contain other methods and function defined in files having a .m extension. The folder @MyClass can contain a number of files:

```
@MyClass/MyClass.m
@MyClass/subsref.m
@MyClass/subsasgn.m
@MyClass/horzcat.m
@MyClass/vertcat.m
@MyClass/myFunc.m
```

Note: MATLAB treats any .m file in the class folder as a method of the class. The base name of the file must be a valid MATLAB function name. Valid function names begin with an alphabetic character, and can contain letters, numbers, or underscores.

Define Method in Function File

To define a method in a separate file in the class folder, create the function in a file with the .m extension. Do not use the method-end keywords in that file. Name the file with the function name, as with any function.

In the myFunc.m file, implement the method:

```
function output = myFunc(obj,arg1,arg2)
   ...% code here
end
```

It is a good practice to declare the function signature in the classdef file in a methods block:

```
classdef MyClass
   methods
      output = myFunc(obj,arg1,arg2)
   end
   ...
end
```

If you want to use nondefault method attributes for a method implemented in a separate file, you must add the function signature to a methods block with the attribute specification.

Specify Method Attributes in classdef File

If you specify method attributes for a method that you define in a separate function file, include the method signature in a methods block in the classdef file. This methods block specifies the nondefault attributes that apply to the method.

For example, the following code shows a method with Access set to private in the methods block. The method implementation resides in a separate file. Do not include the function or end keywords in the methods block. Include only the function signature showing input and output arguments.

```
classdef MyClass
  methods (Access = private)
     output = myFunc(obj,arg1,arg2)
  end
end
```

In a file named myFunc.m, in the @MyClass folder, define the function:

```
function output = myFunc(obj,arg1,arg2)
   ...
end
```

If you specify nondefault attributes for a method, include the method signature in the file with the classdef block

Static Methods in Separate Files

To create a static method, set the method Static attribute to true and list the function signature in a static methods block in the classdef file. Include the input and output arguments with the function name. For example:

```
classdef MyClass
...
  methods (Static)
    output = staticFunc1(arg1,arg2)
    staticFunc2
  end
  ...
end
```

Define the functions in separate files using the same function signature. For example, in the file <code>QMyClass/staticFunc1.m</code>:

```
function output = staticFunc1(arg1,arg2)
...
end
and in @Myclass/staticFunc2.m:
function staticFunc2
...
end
```

Methods That You Must Define In the classdef File

You must define the following methods in the classdef file. You cannot defines these methods in separate files:

· Class constructor

- · Delete method
- All functions that use dots in their names, including:
 - Converter methods that must use the package name as part of the class name because the class is contained in packages
 - · Property set and get access methods

Related Information

- · "Converters for Package Classes".
- "Property Access Methods"

Related Examples

· "Update Graphs Using Events and Listeners"

Events and Listeners

```
In this section...

"Define and Trigger Events" on page 4-24

"Listen for Events" on page 4-24
```

Define and Trigger Events

To define an event, declare a name for the event in an events block. Trigger the event using the handle class notify method. Only classes derived from the handle class can define events.

For example, MyClass class:

- Subclasses handle
- Defines an event named StateChange
- Triggers the event using the inherited notify method in its upDateUI method.

```
classdef MyClass < handle
    events
        StateChange
    end
    ...
methods
    function upDateUI(obj)
        ...
    notify(obj,'StateChange');
    end
end</pre>
```

Listen for Events

Any number of objects can listen to the StateChange event. When notify executes, MATLAB calls all registered listener callbacks. MATLAB passes the handle of the object generating the event and event data to the callback functions. To create a listener, use the addlistener method of the handle class.

```
addlistener(event_obj, 'StateChange', @myCallback)
```

Related Examples

"Learn to Use Events and Listeners"

• "Events and Listeners — Syntax and Techniques"

Attribute Specification

In this section...

"Attribute Syntax" on page 4-26

"Attribute Descriptions" on page 4-26

"Attribute Values" on page 4-27

"Simpler Syntax for true/false Attributes" on page 4-27

Attribute Syntax

Attributes modify the behavior of classes and class components (properties, methods, and events). Attributes enable you to define useful behaviors without writing complicated code. For example, you can create a read-only property by setting its SetAccess attribute to private, but leaving its GetAccess attribute set to public:

```
properties (SetAccess = private)
   ScreenSize = getScreenSize;
end
```

All class definition blocks (classdef, properties, methods, and events) support specific attributes. All attributes have default values. Specify attribute values only in cases where you want to change from the default value to another predefined value.

Note: Specify the value of a particular attribute only once in any component block.

Attribute Descriptions

For lists of supported attributes, see:

- "Class Attributes" on page 5-5
- "Property Attributes" on page 7-7
- "Method Attributes" on page 8-5
- "Event Attributes" on page 10-17

Attribute Values

When you specify attribute values, those values affect all the components defined within the defining block. For example, the following property definition blocks set the:

- AccountBalance property SetObservable attribute to true
- SSNumber and CreditCardNumber properties' Hidden attribute to true and SetAccess attribute to private.

Defining properties with different attribute settings requires multiple properties blocks.

```
properties (SetObservable = true)
   AccountBalance
end
properties (SetAccess = private, Hidden = true)
   SSNumber
   CreditCardNumber
end
```

Specified multiple attributes in a comma-separated list, as shown in the previous example.

When specifying class attributes, place the attribute list directly after the classdef keyword:

```
classdef (AttributeName = attributeValue) ClassName
   ...
end
```

Simpler Syntax for true/false Attributes

You can use a simpler syntax for attributes whose values are true or false — the attribute name alone implies true and adding the not operator (~) to the name implies false. For example:

```
methods (Static)
...
end

Is the same as:
methods (Static = true)
```

end

Use the not operator before an attribute name to define it as false:

```
methods (~Static)
    ...
end

Is the same as:
methods (Static = false)
    ...
end
```

All attributes that take a logical value (that is, true or false) have a default value of false. Therefore, specify an attribute only if you want to set it to true.


Call Superclass Methods on Subclass Objects

In this section... "Calling Superclass Constructor" on page 4-29 "Calling Superclass Methods" on page 4-30

Calling Superclass Constructor

If you create a subclass object, MATLAB calls the superclass constructor to initialize the superclass part of the subclass object. By default, MATLAB calls the superclass constructor without arguments. If you want the superclass constructor called with specific arguments, explicitly call the superclass constructor from the subclass constructor. The call to the superclass constructor must come before any other references to the object.

The syntax for calling the superclass constructor uses an @ symbol:



In the following class, the MySub object is initialized by the MySuperClass constructor. The superclass constructor constructs the MySuperClass part of the object using the specified arguments.

```
classdef MySub < MySuperClass
  methods
    function obj = MySub(arg1,arg2,...)
        obj = obj@MySuperClass(SuperClassArguments);
        ...
end</pre>
```


```
end
end
```

See "Constructing Subclasses" on page 8-18 for more information.

Calling Superclass Methods

Subclass methods can call superclass methods if both methods have the same name. From the subclass, reference the method name and superclass name with the @ symbol.

This diagram illustrates how to call the superMethod defined by MySuperClass.



For example, a subclass can call a superclass disp method to implement the display of the superclass part of the object. Then the subclass adds code to display the subclass part of the object:

```
classdef MySub < MySuperClass
   methods
     function disp(obj)
          disp@MySuperClass(obj)
          ...
   end
  end
end</pre>
```

Related Information

For more information on when to call superclass methods, see ."Modify Superclass Methods"

Representative Class Code

```
In this section...

"Class Calculates Area" on page 4-31

"Description of Class Definition" on page 4-33
```

Class Calculates Area

The CircleArea class shows the syntax of a typical class definition. This class stores a value for the radius of a circle and calculates the area of the circle when you request this information. CircleArea also implements methods to graph, display, and create objects of the class.

To use the CircleArea class, copy this code into a file named CircleArea. M and save this file in a folder that is on the MATLAB path.

```
classdef CircleArea
   properties
      Radius
   end
   properties (Constant)
      P = pi;
   properties (Dependent)
   end
   methods
      function obj = CircleArea(r)
         if nargin > 0
            obj.Radius = r;
         end
      end
      function val = get.Area(obj)
         val = obj.P*obj.Radius^2;
      function obj = set.Radius(obj,val)
         if val < 0
            error('Radius must be positive')
         obj.Radius = val;
      function plot(obj)
```


```
r = obj.Radius;
         d = r*2;
         pos = [0 \ 0 \ d \ d];
         curv = [1 1];
         rectangle('Position',pos,'Curvature',curv,...
            'FaceColor',[.9 .9 .9])
         line([0,r],[r,r])
         text(r/2,r+.5,['r = ',num2str(r)])
         title(['Area = ',num2str(obj.Area)])
         axis equal
      end
      function disp(obj)
         rad = obj.Radius;
         disp(['Circle with radius: ',num2str(rad)])
      end
   end
   methods (Static)
      function obj = createObj
         prompt = {'Enter the Radius'};
         dlgTitle = 'Radius';
         rad = inputdlg(prompt,dlgTitle);
         r = str2double(rad{:});
         obj = CircleArea(r);
      end
   end
end
```

Use the CircleArea Class

Create an object using the dialog box:

```
ca = CircleArea.createObj
```

Add a value for radius and click **OK**.



Query the area of the defined circle:


ca.Area

ans =

164.2202

Call the overloaded plot method:

plot(ca)



Description of Class Definition

Class definition code begins with the classdef keyword followed by the class name: classdef CircleArea

Define the Radius property within the properties-end keywords. Use default attributes:

```
properties
Radius
end
```

Define the P property as Constant ("Properties with Constant Values"). Call the pi function only once when class is initialized.

```
properties (Constant)
   P = pi;
end
```

Define the Area property as Dependent because its value depends on the Radius property.

```
properties (Dependent)
Area
end
```

methods % Begin defining methods

The CircleArea class constructor method has the same name as the class and accepts the value of the circle radius as an argument. This method also allows no input arguments. ("Class Constructor Methods")

```
function obj = CircleArea(r)
  if nargin > 0
    obj.Radius = r;
  else
    obj.Radius = 0;
  end
end
```

Because the Area property is Dependent, it does not store its value. The get.Area method calculates the value of the Area property whenever it is queried. ("Access Methods for Dependent Properties")

```
function val = get.Area(obj)
  val = obj.P*obj.Radius^2;
end
```

The set.Radius method tests the value assigned to the Radius property to ensure the value is not less than zero. MATLAB calls set.Radius to assign a value to Radius. ("Property Set Methods".

```
function obj = set.Radius(obj,val)
  if val < 0
     error('Radius must be positive')
  end
  obj.Radius = val;
end</pre>
```

The CircleArea class overloads the plot function. The plot method uses the rectangle function to create a circle and draws the radius. ("Overload Functions for Your Class"

```
function plot(obj)
  r = obj.Radius;
  d = r*2;
  pos = [0 0 d d];
  curv = [1 1];
  rectangle('Position',pos,'Curvature',curv)
  line([0,r],[r,r])
  text(r/2,r+.5,['r = ',num2str(r)])
  axis equal
end
```

The CircleArea class overloads the disp function to change the way MATLAB displays objects in the command window.

```
function disp(obj)
    rad = obj.Radius;
    disp(['Circle with radius: ',num2str(rad)])
    end
end
methods (Static)
```

The CircleArea class defines a Static method that uses a dialog box to create an object. ("Static Methods"

```
function obj = createObj
  prompt = {'Enter the Radius'};
  dlgTitle = 'Radius';
  rad = inputdlg(prompt,dlgTitle);
  r = str2double(rad{:});
  obj = CircleArea(r);
end
```

End of Static methods block and end of classdef block.

```
end
end
```

MATLAB Code Analyzer Warnings

In this section... "Syntax Warnings and Property Names" on page 4-36 "Warnings Caused by Variable/Property Name Conflicts" on page 4-36 "Exception to Variable/Property Name Rule" on page 4-37

Syntax Warnings and Property Names

The MATLAB Code Analyzer helps you optimize your code and avoid syntax errors while you write code. It is useful to understand some of the rules that the Code Analyzer applies in its analysis of class definition code. This understanding helps you avoid situations in which MATLAB allows code that is undesirable.

Warnings Caused by Variable/Property Name Conflicts

The Code Analyzer warns about the use of variable names in methods that match the names of properties. For example, suppose a class defines a property called EmployeeName and in this class, there is a method that uses EmployeeName as a variable:

```
properties
    EmployeeName
end
methods
    function someMethod(obj,n)
        EmployeeName = n;
    end
end
```

While the previous function is legal MATLAB code, it results in Code Analyzer warnings for two reasons:

- The value of EmployeeName is never used
- EmployeeName is the name of a property that is used as a variable

If the function someMethod contained the following statement instead:

```
obj.EmployeeName = n;
```

The Code Analyzer generates no warnings.

If you change someMethod to:

```
function EN = someMethod(obj)
   EN = EmployeeName;
end
```

The Code Analyzer returns only one warning, suggesting that you might actually want to refer to the EmployeeName property.

While this version of someMethod is legal MATLAB code, it is confusing to give a property the same name as a function. Therefore, the Code Analyzer provides a warning suggesting that you might have intended the statement to be:

```
EN = obj.EmployeeName;
```

Exception to Variable/Property Name Rule

Suppose you define a method that returns a value of a property and uses the name of the property for the output variable name. For example:

```
function EmployeeName = someMethod(obj)
   EmployeeName = obj.EmployeeName;
end
```

The Code Analyzer does not warn when a variable name is the same as a property name when the variable is:

- · An input or output variable
- A global or persistent variable

In these particular cases, the Code Analyzer does not warn you that you are using a variable name that is also a property name. Therefore, a coding error like the following:

```
function EmployeeName = someMethod(obj)
  EmployeeName = EmployeeName; % Forgot to include obj.
end
```

does not trigger a warning from the Code Analyzer.

Objects In Switch Statements

In this section... "Evaluating the Switch Statement" on page 4-38 "Defining the eq Method" on page 4-40 "Enumerations in Switch Statements" on page 4-42

Evaluating the Switch Statement

MATLAB enables you to use objects in switch and case statements if the object's class defines an eq method. The eq method implements the == operation on objects of that class.

For objects, switch_expression == case_expression defines how MATLAB evaluates switch and cases statements.

Note: You do not need to define **eq** methods for enumeration classes. See "Enumerations in Switch Statements" on page 4-42.

Handle Objects in Switch Statements

All classes derived from the handle class inherit an eq method. The expression,

```
h1 == h2
```

is true if h1 and h2 are handles for the same object.

For example, the BasicHandle class derives from handle:

```
classdef BasicHandle < handle
  properties
    Prop1
end
methods
  function obj = BasicHandle(val)
    if nargin > 0
        obj.Prop1 = val;
  end
```

```
end
end

Create a BasicHandle object and use it in a switch statement:
h1 = BasicHandle('Handle Object');
h2 = h1;

Here is the switch statement code:

switch h1
    case h2
        disp('h2 is selected')
    otherwise
        disp('h2 not selected')
end

The result is:
h2 is selected
```

Object Must Be Scalar

The result is:

end

The switch statements work only with scalar objects. For example:

```
h1(1) = BasicHandle('Handle Object');
h1(2) = BasicHandle('Handle Object');
h1(3) = BasicHandle('Handle Object');
h2 = h1;

switch h1
   case h2
       disp('h2 is selected')
   otherwise
       disp('h2 not selected')
end
```

SWITCH expression must be a scalar or string constant.

In this case, h1 is not scalar. Use isscalar to determine if an object is scalar before entering a Switch statement.

Defining the eq Method

To enable the use of value-class objects in switch statements, implement an eq method for the class. Use the eq method to determine what constitutes equality of two object of the class.

Behave Like a Built-in Type

Some MATLAB functions also use the built-in == operator in their implementation. Therefore, your implementation of eq should be replaceable with the built-in eq to enable objects of your class work like built-in types in MATLAB code.

Design of eq

Implement the eq method to returns a logical array representing the result of the == comparison.

For example, the SwitchOnVer class implements an eq method that returns true for the == operation if the value of the Version property is the same for both objects. In addition, eq works with arrays the same way as the built-in eq. For the following expression:

```
obi1 == obi2
```

The eq method works like this:

- If both obj1 and obj2 are scalar, eq returns a scalar value.
- If both obj1 and obj2 are nonscalar arrays, then these arrays must have the same dimensions, and eq returns an array of the same size.
- If one input argument is scalar and the other is a nonscalar array, then eq treats the scalar object as if it is an array having the same dimensions as the nonscalar array.

Implementation of eq

Here is a class that implements an **eq** method. Ensure your implementation contains appropriate error checking for the intended use.

```
classdef SwitchOnVer
  properties
    Version
  end
  methods
    function obj = SwitchOnVer(ver)
    if nargin > 0
```

```
obj. Version = ver;
         end
      end
      function bol = eq(obj1,obj2)
         if ~strcmp(class(obj1),class(obj2))
            error('Objects are not of the same class')
         end
         s1 = numel(obj1);
         s2 = numel(obj2);
         if s1 == s2
            bol = false(size(obj1));
            for k=1:s1
               if obj1(k).Version == obj2(k).Version
                  bol(k) = true;
               else
                  bol(k) = false;
               end
            end
         elseif s1 == 1
            bol = scalarExpEq(obj2,obj1);
         elseif s2 == 1
            bol = scalarExpEq(obj1,obj2);
         else
            error('Dimension missmatch')
         end
         function ret = scalarExpEq(ns,s)
            % ns is nonscalar array
            % s is scalar array
            ret = false(size(ns));
            n = numel(ns);
            for kk=1:n
               if ns(kk).Version == s.Version
                  ret(kk) = true;
               else
                  ret(kk) = false;
               end
            end
         end
      end
   end
end
Use SwitchOnVer objects in switch statements:
```

% Create known versions of objects

```
ov1 = SwitchOnVer(1.0);
ov2 = SwitchOnVer(2.0);
ov3 = SwitchOnVer(3.0);
if isscalar(objIn)
      switch(objIn)
         case ov1
            disp('This is version 1.0')
         case ov2
            disp('This is version 2.0')
         case ov3
            disp('This is version 3.0')
         otherwise
            disp('There is no version')
      end
   else
      error('Input object must be scalar')
   end
```

Enumerations in Switch Statements

MATLAB enables you to use enumerations in switch statements without requiring an explicitly defined eq method for the enumeration class.

For example, the WeeklyPlanner class defines enumerations for five days of the week. The switch/case statements in the todaySchedule static method dispatch on the enumeration member corresponding to the current day of the week. The date and datestr functions return a character string with the name of the current day.

```
classdef WeeklyPlanner
  enumeration
    Monday, Tuesday, Wednesday, Thursday, Friday
end
methods (Static)
    function todaySchedule
        dayName = datestr(date,'dddd');
        dayEnum = WeeklyPlanner.(dayName);
        switch dayEnum
        case WeeklyPlanner.Monday
        disp('Monday schedule')
        case WeeklyPlanner.Tuesday
```

```
disp('Tuesday schedule')
case WeeklyPlanner.Wednesday
disp('Wednesday schedule')
case WeeklyPlanner.Thursday
disp('Thursday schedule')
case WeeklyPlanner.Friday
disp('Friday schedule')
end
end
end
end
```

Call todaySchedule to display today's schedule:

WeeklyPlanner.todaySchedule

Enumerations Derived from Built-In Types

Enumeration classes that derived from built-in types inherit the superclass eq method. For example, the FlowRate class derives from int32:

```
classdef FlowRate < int32
  enumeration
    Low (10)
    Medium (50)
    High (100)
  end
end</pre>
```

The switchEnum function switches on the input argument, which can be a FlowRate enumeration value.

```
function switchEnum(inpt)
    switch inpt
    case 10
        disp('Flow = 10 cfm')
    case 50
        disp('Flow = 50 cfm')
    case 100
        disp('Flow = 100 cfm')
    end
end
```

Call switchEnum with an enumerated value:

switchEnum(FlowRate.Medium)

Flow = 50 cfm

Operations on Objects

```
In this section...

"Object Operations" on page 4-45

"Help on Objects" on page 4-46


"Functions to Test Objects" on page 4-48

"Functions to Query Class Components" on page 4-48
```

Object Operations

Objects often define their own version of ordinary MATLAB functions that work with the object. For example, you can create a timeseries object and pass the object to plot:

```
ts = timeseries(rand(100,1),.01:.01:1,'Name','Data1');
plot(ts)
```



However, MATLAB does not call the standard plot function. MATLAB calls the timeseries plot method, which can extract the data from the timeseries object and create a customized graph.

Help on Objects

Suppose you use an audioplayer object to play audio with MATLAB. To do this, load audio data into MATLAB and create an audioplayer:

```
load('handel','Fs','y')
chorus = audioplayer(y,Fs);
```

The audioplayer function creates an object that you access using the object variable chorus. MATLAB stores the audio source and other information in the object properties.

Here are the properties and values for the chorus instance of the audioplayer:

chorus

```
chorus =
```

Click the link to get the documentation on audioplayer objects.

```
SampleRate: 8192
BitsPerSample: 16
NumberOfChannels: 1
DeviceID: -1
CurrentSample: 1
TotalSamples: 73113
Running: 'off'
StartFcn: []
StopFcn: []
TimerFcn: []
TimerPeriod: 0.0500
Tag: ''
UserData: []
Type: 'audioplayer'
```

The object's documentation discusses the purpose of the object and describes the properties and methods that you use when working with objects of that class.

You can also list the methods to see what operations you can perform. Pass the object to the methods function to see the list:

methods(chorus)

```
Methods for class audioplayer:

audioplayer getdisp pause resume stop
```

delete horzcat play set vertcat get isplaying playblocking setdisp

To play the audio, use the play method:

play(chorus)

Functions to Test Objects

These functions provide logical tests, which are useful when using objects in ordinary functions.

Function	Description
isa	Determine whether an argument is an object of specific class.
isequal	Determine if two objects are equal, which means both objects are of the same class and size and their corresponding property values are equal.
isobject	Determine whether input is a MATLAB object

Functions to Query Class Components

These functions provide information about object class components.

Function	Description
class	Return class of object.
enumeration	Display class enumeration members and names.
events	List event names defined by the class.
methods	List methods implemented by the class.
methodsview	List methods in separate window.
properties	List class property names.

Using the Editor and Debugger with Classes

Referring to Class Files

Define classes in files just like scripts and functions. To use the editor or debugger with a class file, use the full class name. For example, suppose the file for a class, myclass.m is in the following location:

```
+PackFld1/+PackFld2/@myclass/myclass.m
```

To open myclass.m in the MATLAB editor, you could reference the file using dotseparated package names:

```
edit PackFld1.PackFld2.myclass
```

You could also use path notation:

```
edit +PackFld1/+PackFld2/@myclass/myclass
```

If myclass.m is not in a class folder, then enter:

```
edit +PackFld1/+PackFld2/myclass
```

To refer to functions inside a package folder, use dot or path separators:

```
edit PackFld1.PackFld2.packFunction
edit +PackFld1/+PackFld2/packFunction
```

To refer to a function defined in its own file inside of a class folder, use:

```
edit +PackFld1/+PackFld2/@myclass/myMethod
```

Debugging Class Files

For debugging, dbstop accepts any of the file specifications used by the edit command.

See "Automatic Updates for Modified Classes" on page 4-50 for information about clearing class.

Automatic Updates for Modified Classes

In this section...

"When MATLAB Loads Class Definitions" on page 4-50

"Results of Automatic Update" on page 4-50

"Result of Changes to Class Definitions" on page 4-51

"Actions That Do Not Trigger Updates" on page 4-52

"When Updates to Classes Fail" on page 4-52

"Potential Side Effects from Class Updates" on page 4-52

"When Updates of Existing Objects Are Not Possible" on page 4-53

"Updates to Property Definitions" on page 4-53

"Updates to Method Definitions" on page 4-54

"Updates to Event Definitions" on page 4-55

When MATLAB Loads Class Definitions

MATLAB loads a class definition:

- The first time the class is referenced.
- Whenever the definition of a loaded class changes and MATLAB returns to the command prompt.

MATLAB allows only one definition for a class to exist at any time. Therefore, all existing objects of a class are updated automatically to conform to the new class definition. You do not need to call clear classes to remove existing objects when changing their defining class.

Note: Using an editor other than the MATLAB editor can result in delays to automatic updating.

Results of Automatic Update

MATLAB follows a set of basic rules when updating existing objects. An automatic update can result in existing objects being:

- Successfully updated to the new class definition.
- Converted to instances of matlab.lang.ObjectUpdateFailure if MATLAB cannot convert the objects to the new class definition.

Suppose you create an instance of a concrete class, and then edit the class definition to make the class abstract.

```
>> a = MyClass;
% Edit MyClass to make it Abstract
>> a
a =
ObjectUpdateFailure with no properties.
```

The object display provides information on the specific reason that the objects are not updated.

```
a =
```

This array was created with a previous version of the MyClass class. MATLAB is unable the new class is abstract which means objects must now belong to a concrete subclass.

Note: MATLAB does not update meta-class instances when you change the definition of a class. You need to retrieve new meta-class data after updating a class definition.

Result of Changes to Class Definitions

MATLAB updates existing objects when a class definition changes, including the following situations:

- Value to handle Existing objects become independent handles referring to different objects.
- Enumeration member added Existing objects preserve the enumeration members they had before, even if the underlying value has changed.
- Enumeration member removed Existing objects that are not using the removed member have the same enumeration members that they had previously. Existing

objects using the removed member have the removed member replaced with the default member of the enumeration.

- Enumeration block removed Enumeration members are removed from all existing objects.
- Superclass definition changed Changes applied to all subclasses of that superclass.
- Superclass added or removed Change of superclass applied to all existing objects.

Actions That Do Not Trigger Updates

Existing objects are not updated by these actions:

- Calling the class function on an out of date object does not cause an update.
- Assigning an out of date object to a variable does not cause an update.
- · Calling a method that does not access class data does not cause an update.

The Workspace browser does not display changes to an object class (for example, objects changed to matlab.lang.ObjectUpdateFailure) until after the update has been triggered.

Objects do not update until referenced in a way that exposes the change, such as invoking the object display. Updates do not occur incrementally. Updates conform to the latest version of the class.

When Updates to Classes Fail

Some class updates result in an invalid class definition. In these cases, objects do not update until the error is resolved. For example:

- · Adding a superclass can result in a property or method being defined twice.
- Changing a superclass to be Sealed when objects of one of its subclasses exists results in an invalid subclass definition.

Potential Side Effects from Class Updates

 Following an update, existing objects might not be fully compatible with the new class definition. For example, a newly added property might require execution of the constructor to be valid.

- Removing or renaming properties can lose the data held in the property. For example, if a property holds the only reference to another object and is removed from a class, the object is deleted because there are no references to it.
- Removing a class from a heterogeneous class hierarchy can result in invalid
 heterogeneous array elements. In this case, the default object for the heterogeneous
 hierarchy replaces these array elements.

When Updates of Existing Objects Are Not Possible

If MATLAB cannot update existing objects to conform to a modified class definition, then the existing objects of that class are converted to instances of matlab.lang.ObjectUpdateFailure. This conversion occurs when:

- An enumeration block is added to a non-enumeration class.
- A class is redefined to be Abstract.
- A class is removed from a heterogeneous hierarchy and there is no way to replace existing objects in a heterogeneous array with default objects.
- A class is updated to restrict array formation behavior, such as overloading array indexing and concatenation.
- · A handle class is redefined to be a value class.

Updates to Property Definitions

When you change the definition of class properties, MATLAB applies the changes in existing objects of the class.

If You Make This Change	Effect on Existing Objects of the Class
Add property	Adds the new property to existing objects of the class. Sets the property values to the default value (which is [] if the class definition does not specify a default).
Remove property	Removes the property from existing objects of the class. Attempts to access the removed property fail.
Change property default value	Does not apply the new default value to existing objects of the class.
Move property between subclass and superclass	Does not apply different default value when property definition moves between superclass and subclass.

If You Make This Change	Effect on Existing Objects of the Class
Change property attribute value	Applies changes to existing objects of the class. Some cases require transitional steps: • Abstract — Existing objects of a class that become abstract are converted to matlab.lang.ObjectUpdateFailure objects.
	• Access — Changes to the access lists do not change existing instances. However, if classes are added to the access list, instances of those classes have access to this property. If classes are removed from the access list, instances of those classes no longer have access to this property.
	• Dependent — If changed to true, existing objects no longer store property values. You must add a property get method for the property if you want to query the property value.
	• Transient — If changed to true, objects already saved reload this property value. If changed to false, objects already saved reload this property using the default value.

Updates to Method Definitions

When you change the definition of class methods, the affected class member is changed in existing objects as follows.

If You Make This Change	Effect on Existing Objects of the Class
Add method	New method is callable on existing objects of the class.
Modify method	Modifications are visible to existing objects.
Remove method	Deleted method is no longer callable on existing objects.
Change method attribute value	Apply changes to existing objects of the class. Some cases require transitional steps:

If You Make This Change	Effect on Existing Objects of the Class
	Abstract — Existing objects of a class that become abstract are converted to matlab.lang.ObjectUpdateFailure objects.
	• Access — Changes to the access lists do not change existing instances. However, if classes are added to the access list, instances of those classes have access to this method. If classes are removed from the access list, instances of those classes no longer have access to this method.
	• Sealed — If changed to true and existing subclasses already have defined the method, MATLAB returns an error because the new class definition cannot be applied to existing subclasses.

Updates to Event Definitions

If You Make This Change	Effect on Existing Objects of the Class
Add event	New event is supported on existing objects of the class.
Modify event	Modifications are visible to existing objects.
Remove event	Deleted event is no longer supported on existing objects.
Change event attribute value	Apply changes to existing objects of the class.
	Some cases require transitional steps:
	• ListenAccess — Changes to the access list does not change existing objects. However, if you add classes to the access list, objects of those classes can create listeners for this event. If you remove classes from the access list, objects of those classes are not allowed to create listeners for this event.
	• NotifyAccess — Changes to the access list does not change existing objects. However, if you add classes to the access list, instances of those classes can trigger this event. If you remove classes, objects of those classes are not able to trigger this event.

Compatibility with Previous Versions

In this section...

"New Class-Definition Syntax Introduced with MATLAB Software Version 7.6" on page 4-56

"Changes to Class Constructors" on page 4-57

"New Features Introduced with Version 7.6" on page 4-57

"Examples of Old and New" on page 4-58

New Class-Definition Syntax Introduced with MATLAB Software Version 7.6

MATLAB software Version 7.6 introduces a new syntax for defining classes. This new syntax includes:

- The classdef keyword begins a block of class-definitions code. An end statement terminates the class definition.
- Within the classdef code block, properties, methods, and events are also keywords delineating where you define the respective class members.

Cannot Mix Class Hierarchy

It is not possible to create class hierarchies that mix classes defined before Version 7.6 and current class definitions that use classdef. Therefore, you cannot subclass an old class to create a version of the new class.

Only One "@" Class Folder per Class

For classes defined using the new classdef keyword, a class folder shadows all class folders that occur after it on the MATLAB path. Classes defined in class folders must locate all class files in that single folder. However, classes defined in class folders continue to take precedence over functions and scripts having the same name, even those function and scripts that come before them on the path.

Private Methods

You do not need to define private folders in class folders in Version 7.6. You can set the method's Access attribute to private instead.

Changes to Class Constructors

Class constructor methods have two major differences. Class constructors:

- Do not use the class function.
- Must call the superclass constructor only if you want to pass arguments to its constructor. Otherwise, no call to the superclass constructor is necessary.

Example of Old and New Syntax

Compare the following two Stock constructor methods. The Stock class is a subclass of the Asset class, which requires arguments passed to its constructor.

Constructor Function Before Version 7.6

Write the same Stock class constructor as shown here. Define the inheritance on the classdef line and define the constructor within a methods block.

Constructor Function for Version 7.6

```
classdef Stock < Asset
   ...
  methods

   function s = Stock(description,num_shares,share_price)
% Call superclass constructor to pass arguments
        s = s@Asset(description,'stock',share_price*num_shares);
        s.NumShares = num_shares;
        s.SharePrice = share_price;
    end % End of function

end % End of methods block
end % End of classdef block</pre>
```

New Features Introduced with Version 7.6

- Properties: "How to Use Properties" on page 7-2
- · Handle classes: "Comparing Handle and Value Classes" on page 6-2
- Events and listeners: "Events and Listeners Concepts" on page 10-12
- Class member attributes: "Attribute Specification" on page 4-26
- Abstract classes: "Abstract Classes" on page 11-80
- Dynamic properties: "Dynamic Properties Adding Properties to an Instance" on page 7-30
- Ability to subclass MATLAB built-in classes: "Creating Subclasses Syntax and Techniques" on page 11-7
- Packages for scoping functions and classes: "Packages Create Namespaces" on page 5-19. MATLAB does not support packages for classes created before MATLAB Version 7.6 (that is, classes that do not use classdef).
- The JIT/Accelerator supports objects defined only by classes using classdef.

Examples of Old and New

The MATLAB Version 7.6 implementation of classes uses different syntax from previous releases. However, classes written in previous versions continue to work. Most of the code you use to implement the methods is likely to remain the same, except where you take advantage of new features.

The following sections reimplement examples using the latest syntax. The original MATLAB Classes and Objects documentation implemented these same examples and provide a comparison of old and new syntax.

"Class Design for Polynomials" on page 18-2

"A Simple Class Hierarchy" on page 19-2

"Containing Assets in a Portfolio" on page 19-20

Comparing MATLAB with Other OO Languages

In this section...

"Some Differences from C++ and Java Code" on page 4-59

"Modifying Objects" on page 4-60

"Common Object-Oriented Techniques" on page 4-64

Some Differences from C++ and Java Code

The MATLAB programming language differs from other object-oriented languages, such as C++ or Java in some important ways.

Public Properties

Unlike fields in C++ or the Java language, you can use MATLAB properties to define a public interface separate from the implementation of data storage. You can provide public access to properties because you can define set and get access methods that execute automatically when assigning or querying property values. For example, the following statement:

```
myobj.Material = 'plastic';
```

assigns the string plastic to the Material property of myobj. Before making the actual assignment, myobj executes a method called set.Material (assuming the class of myobj defines this method), which can perform any necessary operations. See "Property Access Methods" on page 7-14 for more information on property access methods.

You can also control access to properties by setting attributes, which enable public, protected, or private access. See "Property Attributes" on page 7-7 for a full list of property attributes.

No Implicit Parameters

In some languages, one object parameter to a method is always implicit. In MATLAB, objects are explicit parameters to the methods that act on them.

Dispatching

In MATLAB classes, method dispatching is not based on method signature, as it is in C+ + and Java code. When the argument list contains objects of equal precedence, MATLAB uses the left-most object to select the method to call.

However, if the class of an argument is superior to the class of the other arguments, MATLAB dispatches to the method of the superior argument, regardless of its position within the argument list.

See "Class Precedence" on page 5-17 for more information.

Calling Superclass Method

- In C++, you call a superclass method using the scoping operator: superclass::method
- In Java code, you use: superclass.method

The equivalent MATLAB operation is method@superclass.

Other Differences

In MATLAB classes, there is no equivalent to C++ templates or Java generics. However, MATLAB is weakly typed and it is possible to write functions and classes that work with different types of data.

MATLAB classes do not support overloading functions using different signatures for the same function name.

Modifying Objects

MATLAB classes can define public properties, which you can modify by explicitly assigning values to those properties on a given instance of the class. However, only classes derived from the handle class exhibit reference behavior. Modifying a property value on an instance of a value classes (classes not derived from handle), changes the value only within the context in which the modification is made.

The sections that follow describe this behavior in more detail.

Passing Objects to Functions

MATLAB passes all variables by value. When you pass an object to a function, MATLAB copies the value from the caller into the parameter variable in the called function.

However, MATLAB supports two kinds of classes that behave differently when copied:

- Handle classes a handle class instance variable refers to an object. A copy of a
 handle class instance variable refers to the same object as the original variable. If
 a function modifies a handle object passed as an input argument, the modification
 affects the object referenced by both the original and copied handles.
- Value classes the property data in an instance of a value class are independent of the property data in copies of that instance (although, a value class property could contain a handle). A function can modify a value object that is passed as an input argument, but this modification does not affect the original object.

See "Comparing Handle and Value Classes" on page 6-2 for more information on the behavior and use of both kinds of classes.

Passing Value Objects

When you pass a value object to a function, the function creates a local copy of the argument variable. The function can modify only the copy. If you want to modify the original object, return the modified object and assign it to the original variable name. For example, consider the value class, SimpleClass:

```
classdef SimpleClass
   properties
       Color
   end
   methods
      function obj = SimpleClass(c)
       if nargin > 0
        obj.Color = c;
      end
   end
   end
end
```

Create an instance of SimpleClass, assigning a value of red to its Color property:

```
obj = SimpleClass('red');
```

Pass the object to the function g, which assigns blue to the Color property:

```
function y = g(x)
    x.Color = 'blue';
    y = x;
end
```

```
y = g(obj);
```

The function **g** modifies its copy of the input object and returns that copy, but does not change the original object.

```
y.Color
ans =
    blue
obj.Color
ans =
    red
```

If the function g did not return a value, the modification of the object Color property would have occurred only on the copy of obj within the function workspace. This copy would have gone out of scope when the function execution ended.

Overwriting the original variable actually replaces it with a new object:

```
obj = g(obj);
```

Passing Handle Objects

When you pass a handle to a function, the function makes a copy of the handle variable, just like when passing a value object. However, because a copy of a handle object refers to the same object as the original handle, the function can modify the object without having to return the modified object.

For example, suppose you modify the SimpleClass class definition to make a class derived from the handle class:

```
classdef SimpleHandleClass < handle
  properties
        Color
  end
  methods
      function obj = SimpleHandleClass(c)
        if nargin > 0
            obj.Color = c;
        end
  end
end
```

end

Create an instance of SimpleHandleClass, assigning a value of red to its Color property:

```
obj = SimpleHandleClass('red');
```

Pass the object to the function g, which assigns blue to the Color property:

```
y = g(obj);
```

The function g sets the Color property of the object referred to by both the returned handle and the original handle:

```
y.Color
ans =
blue
obj.Color
ans =
blue
The variables y and obj refer to the same object:
y.Color = 'yellow';
obj.Color
ans =
yellow
```

The function **g** modified the object referred to by the input argument (**obj**) and returned a handle to that object in **y**.

MATLAB Passes Handles by Value

A handle variable is a reference to an object. MATLAB passes this reference by value.

Handles do not behave like references in C++. If you pass an object handle to a function and that function assigns a different object to that handle variable, the variable in the caller is not affected. For example, suppose you define a function g2:

```
function y = g2(x)
```

```
x = SimpleHandleClass('green');
y = x;
end

Pass a handle object to g2:
obj = SimpleHandleClass('red');
y = g2(obj);
y.Color
ans =
green
obj.Color
ans =
red
```

The function overwrites the handle passed in as an argument, but does not overwrite the object referred to by the handle. The original handle obj still references the original object.

Common Object-Oriented Techniques

This table provides links to sections that discuss object-oriented techniques commonly used by other object-oriented languages.

Technique	How to Use in MATLAB
Operator overloading	"Class Operator Implementations" on page 16-37
Multiple inheritance	"Subclassing Multiple Classes" on page 11-20
Subclassing	"Creating Subclasses — Syntax and Techniques" on page 11-7
Destructor	"Handle Class Destructor" on page 6-16
Data member scoping	"Property Attributes" on page 7-7
Packages (scoping classes)	"Packages Create Namespaces" on page 5-19
Named constants	See "Properties with Constant Values" on page 14-2 and "Defining Named Values" on page 13-2

Technique	How to Use in MATLAB	
Enumerations	"Working with Enumerations" on page 13-3	
Static methods	"Static Methods" on page 8-23	
Static properties	Not supported. See persistent variables. For the equivale of Java static final or C++ static const properties, use Constant properties. See "Properties with Constant Values on page 14-2	
Constructor	"Class Constructor Methods" on page 8-15	
Copy constructor	No direct equivalent	
Reference/reference classes	"Comparing Handle and Value Classes" on page 6-2	
Abstract class/Interface	"Abstract Classes" on page 11-80	
Garbage collection	"Object Lifecycle" on page 6-18	
Instance properties	"Dynamic Properties — Adding Properties to an Instance" on page 7-30	
Importing classes	"Importing Classes" on page 5-24	
Events and Listeners	"Events and Listeners — Concepts" on page 10-12	

Defining and Organizing Classes

- "User-Defined Classes" on page 5-2
- "Class Definition" on page 5-4
- "Class Attributes" on page 5-5
- "Expressions in Class Definitions" on page 5-8
- "Class and Path Folders" on page 5-14
- "Class Precedence" on page 5-17
- "Packages Create Namespaces" on page 5-19
- "Importing Classes" on page 5-24

User-Defined Classes

In this section...

"What is a Class Definition" on page 5-2

"Attributes for Class Members" on page 5-2

"Kinds of Classes" on page 5-3

"Constructing Objects" on page 5-3

"Class Hierarchies" on page 5-3

What is a Class Definition

A MATLAB class definition is a template whose purpose is to provide a description of all the elements that are common to all instances of the class. Class members are the properties, methods, and events that define the class.

MATLAB classes are defined in code blocks, with sub-blocks delineating the definitions of various class members. See "classdef Syntax" on page 5-4 for details on the classdef block.

Attributes for Class Members

Attributes modify the behavior of classes and the members defined in the class-definition block. For example, you can specify that methods are static or that properties are abstract, and so on. The following sections describe these attributes:

- "Class Attributes" on page 5-5
- "Method Attributes" on page 8-5
- "Property Attributes" on page 7-7
- "Event Attributes" on page 10-17

Class definitions can provide information, such as inheritance relationships or the names of class members without actually constructing the class. See "Class Metadata" on page 15-2.

See "Specifying Attributes" on page 5-6 for more on attribute syntax.

Kinds of Classes

There are two kinds of MATLAB classes—handle and value classes.

- Handle classes create objects that reference the data contained. Copies refer to the same data.
- Value classes make copies of the data whenever the object is copied or passed to a function. MATLAB numeric types are value classes.

See "Comparing Handle and Value Classes" on page 6-2 for a more complete discussion.

Constructing Objects

For information on class constructors, see "Class Constructor Methods" on page 8-15

For information on creating arrays of objects, see "Create Object Arrays" on page 9-2

Class Hierarchies


For more information on how to define class hierarchies, see "Hierarchies of Classes — Concepts".

Class Definition

classdef Syntax

Class definitions are blocks of code that are delineated by the classdef keyword at the beginning and the end keyword at the end. Files can contain only one class definition.

The following diagram shows the syntax of a classdef block. Only comments and blank lines can precede the classdef key word.



Related Examples

- · "A Simple Class"
- "Developing Classes Typical Workflow" on page 3-8
- "Class to Represent Structured Data" on page 3-24

Class Attributes

In this section...

"Specifying Class Attributes" on page 5-5

"Specifying Attributes" on page 5-6

Specifying Class Attributes

All classes support the attributes listed in the following table. Attributes enable you to modify the behavior of class. Attribute values apply to the class defined within the classdef block.

classdef (Attribute1 = value1, Attribute2 = value2,...) ClassName
 ...
end

For more information on attribute syntax, see "Attribute Specification".

Class Attributes

Attribute Name	Class	Description
Abstract	logical (default = false)	If specified as true, this class is an abstract class (cannot be instantiated). See "Abstract Classes" on page 11-80 for more information.
AllowedSubclasses	meta.class object or cell array of meta.class objects	List classes that can subclass this class. Specify subclasses as meta.class objects in the form: • A single meta.class object • A cell array of meta.class objects. An empty cell array, {}, is the same as a Sealed class (no subclasses). Specify meta.class objects using the ?ClassName syntax only. See "Specify Allowed Subclasses" on page 11-22 for more information.

Attribute Name	Class	Description
ConstructOnLoad	logical (default = false)	If true, MATLAB calls the class constructor when loading an object from a MAT-file. Therefore, you must implement the constructor so it can be called with no arguments without producing an error. See "Initialize Objects" on page 12-25 for more information.
HandleCompatible	logical (default = false) for value classes	If specified as true, this class can be used as a superclass for handle classes. All handle classes are HandleCompatible by definition. See "Supporting Both Handle and Value Subclasses" on page 11-36 for more information.
Hidden	logical (default = false)	If true, this class does not appear in the output of the superclasses or help functions.
InferiorClasses	meta.class object or cell array of meta.class objects	Use this attribute to establish a precedence relationship among classes. Specify a cell array of meta.class objects using the ? operator. The fundamental classes are always inferior to user-defined classes and do not show up in this list. See "Class Precedence" on page 5-17 and "Dominant Argument in Overloaded Plotting Functions" on page 8-39.
Sealed	logical (default = false)	If true, this class can not be subclassed.

Specifying Attributes

Attributes are specified for class members in the classdef, properties, methods, and events definition blocks. The particular attribute setting applies to all members defined within that particular block. This means that, for example, you might use multiple

properties definition blocks so you can apply different attribute setting to different properties.

Superclass Attributes Are Not Inherited

Class attributes are not inherited, so superclass attributes do not affect subclasses.

Attribute Syntax

Specify class attribute values in parentheses, separating each attribute name/attribute value pair with a comma. The attribute list always follows the classdef or class member key word, as shown below:

```
classdef (attribute-name = expression, ...) ClassName
  properties (attribute-name = expression, ...)
     ...
  end
  methods (attribute-name = expression, ...)
     ...
  end
  events (attribute-name = expression, ...)
     ...
  end
end
end
```

More About

• "Expressions in Attribute Specifications" on page 5-9

Expressions in Class Definitions

```
In this section...

"Basic Knowledge" on page 5-8

"Where to Use Expressions in Class Definitions" on page 5-8

"How MATLAB Evaluates Expressions" on page 5-10

"When MATLAB Evaluates Expressions" on page 5-10

"Samples of Expression Evaluation" on page 5-10
```

Basic Knowledge

The material presented in this section builds on an understanding of the following information:

- "Operators and Elementary Operations"
- "Properties" on page 4-11
- "Attribute Specification" on page 4-26

Where to Use Expressions in Class Definitions

An expression used in a class definition can be any valid MATLAB statement that evaluates to a single array. Use expressions to define property default values and in attribute specifications. Here are some examples used in a class definition:

MATLAB does not call property set methods when assigning the result of default value expressions to properties. (See "Property Access Methods" on page 7-14 for information about these special methods.)

Expressions in Attribute Specifications

Class definitions specify attribute values using an expression that assigns the desired value to the named attribute. For example, this assignment makes MyClass sealed (cannot be subclassed).

```
classdef MyClass (Sealed = true)
```

It is possible to use a MATLAB expression on the right side of the equals sign (=) as long as it evaluates to logical true or false. However, this expression *cannot* use any definitions from the class definition file, including any constant properties, static methods, and local functions.

While it is possible to use conditional expressions to specify attribute values, doing so can cause the class definition to change based on external conditions.

Note: The AllowedSubclasses and the InferiorClasses attributes require an explicit specification of a cell array of meta.class objects as their values. Other expression are not allowed.

See "Attribute Specification" on page 4-26 for more information on attribute syntax.

Expressions in Default Property Specifications

Property definitions allow you to specify default values for properties using any expression that has no reference to variables. For example, Myclass defines a constant property (Deg2Rad) and uses it in an expression that defines the default value of another property (PropA). The default value expression also uses a static method (getAngle) defined by the class:

```
classdef MyClass
  properties (Constant)
    Deg2Rad = pi/180;
end
properties
    PropA = sin(Deg2Rad*MyClass.getAngle([1 0],[0 1]));
end
...
methods (Static)
    function r = getAngle(vx,vy)
```

end end end

Expressions in Class Methods

Expression in class methods execute like expressions in any function — MATLAB evaluates an expression within the function's workspace only when the method executes. Therefore, expressions used in class methods are not considered part of the class definition and are not discussed in this section.

How MATLAB Evaluates Expressions

MATLAB evaluates the expressions used in the class definition without any workspace. Therefore, these expressions cannot reference variables of any kind.

MATLAB evaluates expressions in the context of the class file, so these expressions can access any functions, static methods, and constant properties of other classes that are on your path at the time MATLAB initializes the class. Expressions defining property default values can access constant properties defined in their own class.

When MATLAB Evaluates Expressions

MATLAB evaluates the expressions in class definitions only when the class is initialized. Initialization occurs before the class is first used.

After initialization, the values returned by these expressions are part of the class definition and are constant for all instances of the class. Each instance of the class uses the results of the initial evaluation of the expressions without reevaluation.

If you clear a class, then MATLAB reinitializes the class by reevaluating the expressions that are part of the class definition. (see "Automatic Updates for Modified Classes" on page 4-50)

Samples of Expression Evaluation

The following example shows how value and handle object behave when assigned to properties as default values. Suppose you have the following classes. ContClass defines the object that is created as a default property value, and ClassExp has a property that contains a ContClass object:

```
classdef ContClass
    properties
        TimeProp = datestr(now); % Assign current date and time
    end
end

classdef ClassExp
    properties
        ObjProp = ContClass;
    end
end
```

MATLAB creates an instance of the ContClass class when the ClassExp class is first used. MATLAB initializes both classes at this time. All instances of ClassExp include a copy of this same instance of ContClass.

```
a = ClassExp;
a.ObjProp.TimeProp
ans =
08-Oct-2003 17:16:08
```

The TimeProp property of the ContClass object contains the date and time when MATLAB initialized the class. Creating additional instances of the ClassExp class shows that the date string has not changed:

```
b = ClassExp;
b.ObjProp.TimeProp
ans =
08-Oct-2003 17:16:08
```

Because this example uses a value class for the contained object, each instance of the ClassExp has its own copy of the object. For example, suppose you change the value of the TimeProp property on the object contained by ClassExp objectb:

```
b.ObjProp.TimeProp = datestr(now)
ans =
08-Oct-2003 17:22:49
```

The copy of the object contained by object a is unchanged:

```
a.ObjProp.TimeProp
```

```
ans =
08-Oct-2003 17:16:08
Now consider the difference in behavior if the contained object is a handle object:
classdef ContClass < handle
    properties
        TimeProp = datestr(now);
    end
end</pre>
```

Creating two instances of the ClassExp class shows that MATLAB created an object when it initialized the ContClass and used a copy of the object *handle* for each instance of the ClassExp class. This means there is one ContClass object and the ObjProp property of each ClassExp object contains a copy of its handle.

Create an instance of the ClassExp class and note the time of creation:

```
a = ClassExp;
a.ObjProp.TimeProp
ans =
08-Oct-2003 17:46:01
```

Create a second instance of the ClassExp class. The ObjProp contains the handle of the same object:

```
b = ClassExp;
b.ObjProp.TimeProp
ans =

08-Oct-2003 17:46:01
Reassign the value of the contained object's TimeProp property:
b.ObjProp.TimeProp = datestr(now);
b.ObjProp.TimeProp
ans =

08-Oct-2003 17:47:34
```

Because the ObjProp property of object b contains a handle to the same object as the ObjProp property of object a, the value of the TimeProp property has changed on this object as well:

```
a.ObjProp.TimeProp
ans =
08-Oct-2003 17:47:34
```

See Also

datestr | now

More About

• "Comparing Handle and Value Classes" on page 6-2

Class and Path Folders

In this section...

"Class and Path Folders" on page 5-14

"Path Folders" on page 5-14

"Class Folders" on page 5-14

"Access to Functions Defined in Private Folders" on page 5-15

"Class Precedence and MATLAB Path" on page 5-15

Class and Path Folders

There are two types of folders that can contain class definitions.

- Path folders Folder name does not use an @ character and is itself on the MATLAB path. Use this type of folder when you want multiple classes in one folder.
- Class folders Folder name begins with an @ character followed by the class name. The folder is not on the MATLAB path, but its parent folder is on the path. Use this type of folder when you want to use multiple files for one class definition.

Path Folders

You can locate class definition files in folders that are on the MATLAB path. These classes are visible on the path like any ordinary function. Class definitions placed in path folders behave like any ordinary function with respect to precedence—the first occurrence of a name on the MATLAB path takes precedence over all subsequent occurrences.

The name of the file must match the name of the class, as specified with the classdef key word. Using a path folder eliminates the need to create a separate class folder for each class. However, the entire class definition, including all methods, must be contained within a single file (for example, MyClass1.m, MyClass2.m, and so on).

See the path function for information about the MATLAB path.

Class Folders

A class folder must be contained by a path folder, but is not itself on the MATLAB path. Place the class definition file inside the class folder, which can also contain separate

method files. The class definition file must have the same name as the class folder (without the @ character) and the class definition (beginning with the classdef key word) must appear in the file before any other code (white space and comments do not constitute code).

Define only one class per folder. All files must have a .m extension (for example, @MyClass/MyClass.m, @MyClass/myMethod.m, and so on).

You must use a class folder if you want to use more than one file for your class definition. Methods defined in separate files match the file name to the function name and must be declared in the classdef file. See for more information.

Access to Functions Defined in Private Folders

Private folders contain functions that are accessible only from functions defined in folders immediately above the private folder (See "Private Functions"). If a class folder contains a private folder, only the class (or classes) defined in that folder can access functions defined in the private folder. Subclasses do not have access to superclass private functions.

If you want a subclass to have access to the private functions of the superclass, define the private functions as protected methods of the superclass (that is, in a methods block with the Access attribute defined a protected).

No Class Definitions in Private Folders

You cannot put class definitions in private folders because doing so would not meet the requirements for class or path folders.

Class Precedence and MATLAB Path

When multiple class definition files with the same name exist, the precedence of a given file is determined by its location on the MATLAB path. All class definition files before it on the path (whether in a class folder or not) take precedence and it takes precedence over all class definition files occurring later on the path.

For example, consider a path with the following folders, containing the files indicated:

```
fldr1/foo.m % defines class foo
fldr2/foo.m % defines function foo
fldr3/@foo/foo.m % defines class foo
```

```
fldr4/@foo/bar.m % defines method bar
fldr5/foo.m % defines class foo
```

The MATLAB language applies the logic in the following list to determine which version of foo to call:

- Class fldr1/foo.m takes precedence over the class fldr3/@foo because it is before fldr3/@foo on the path.
- Class fldr3/@foo takes precedence over function fldr2/foo.m because it is a class in a class folder and fldr2/foo.m is not a class (classes in class folders take precedence over functions).
- Function fldr2/foo.m takes precedence over class fldr5/foo.m because it comes before class fldr5/foo.m on the path and because class fldr5/foo.m is not in a class folder. Classes not defined in class folders abide by path order with respect to functions.
- Class fldr3/@foo takes precedence over class fldr4/@foo; therefore, the method bar is not recognized as part of the foo class (which is defined only by fldr3/@foo).
- If fldr3/@foo/foo.m does not contain a classdef keyword (i.e., it is a MATLAB class prior to Version 7.6), then fldr4/@foo/bar.m becomes a method of the foo class defined in fldr3/@foo.

Previous Behavior of Classes Defined in Class Folders

In MATLAB Versions 5 through 7, class folders do not shadow other class folders having the same name, but residing in later path folders. Instead, the class is defined by the combination of methods from all class folders having the same name. This is no longer true.

Note that for backward compatibility, classes defined in class folders always take precedence over functions and scripts having the same name, even those that come before them on the path.

Class Precedence

In this section...

"Basic Knowledge" on page 5-17

"Why Mark Classes as Inferior" on page 5-17

"InferiorClasses Attribute" on page 5-17

Basic Knowledge

The material presented in this section builds on an understanding of the following information:

- "Class Metadata" on page 15-2
- "Attribute Specification" on page 4-26

Why Mark Classes as Inferior

When more than one class defines methods with the same name or when classes overload functions, MATLAB determines which method or function to call based on the dominant argument. Here is how MATLAB determines the dominant argument:

- · Determine the dominant argument based on the class of arguments.
- If there is a dominant argument, call the method of the dominant class.
- If arguments are of equal precedence, use the left-most argument as the dominant argument.
- If the class of the dominant argument does not define a method with the name of the called function, call the first function on the path with that name.

InferiorClasses Attribute

You can specify the relative precedence of user-defined classes using the class InferiorClasses attribute. Assign a cell array of class names (represented as meta.class objects) to this attribute to specify classes that are inferior to the class you are defining. For example, the following classdef declares that myClass is dominant over class1 and class2.

classdef (InferiorClasses = {?class1,?class2}) myClass

end

The ? operator combined with a class name creates a meta.class object. This syntax enables you to create a meta.class object without requiring you to construct an actual instance of the class.

MATLAB built-in classes are always inferior to user-defined classes and should not be used in this list.

The built-in classes include: double, single, char, logical, int64, uint64, int32, uint32, int16, uint16, int8, uint8, cell, struct, and function handle.

Dominant Class

MATLAB uses class dominance when evaluating expressions involving objects of more than one class. The dominant class determines:

- The methods of which class MATLAB calls when more than one class defines methods with the same names.
- The class of arrays that are formed by combining objects of different classes, assuming MATLAB can convert the inferior objects to the dominant class.

No Attribute Inheritance

Subclasses do not inherit a superclass InferiorClasses attribute. Only instances of the classes specified in the subclass InferiorClasses attribute are inferior to subclass objects.

More About

- "Class Precedence and MATLAB Path" on page 5-15
- "Dominant Argument in Overloaded Plotting Functions"

Packages Create Namespaces

In this section...

"Internal Packages" on page 5-19

"Package Folders" on page 5-19

"Referencing Package Members Within Packages" on page 5-20

"Referencing Package Members from Outside the Package" on page 5-21

"Packages and the MATLAB Path" on page 5-22

Internal Packages

MathWorks® reserves the use of packages named internal for utility functions used by internal MATLAB code. Functions that belong to an internal package are intended for MathWorks use only. Using functions or classes that belong to an internal package is strongly discouraged. These functions and classes are not guaranteed to work in a consistent manner from one release to the next. Any of these functions and classes might be removed from the MATLAB software in any subsequent release without notice and without documentation in the product release notes.

Package Folders

Packages are special folders that can contain class folders, function and class definition files, and other packages. Packages define the scope of the contents of the package folder (that is, a namespace within which names must be unique). This means function and class names need to be unique only within the package. Using a package provides a means to organize classes and functions and to select names for these components that other packages can reuse.

Note: Packages are not supported for classes created prior to MATLAB Version 7.6 (i.e., classes that do not use classdef).

Package folders always begin with the + character. For example,

+mypack

+mypack/pkfcn.m % a package function

```
+mypack/@myClass % class folder in a package
```

The top-level package folder's parent folder must be on the MATLAB path.

Listing the Contents of a Package

List the contents of a package using the help command:

help event

```
Contents of event:
```

```
EventData - event.EVENTDATA Base class for event data
```

PropertyEvent - event.PROPERTYEVENT Event data for object property

listener - event.LISTENER Listener object

proplistener - event.PROPLISTENER Listener object for property events.

You can also use the what command:

what event

```
Classes in directory Y:xxx\matlab\toolbox\matlab\lang\+event

EventData PropertyEvent listener proplistener
```

Referencing Package Members Within Packages

All references to packages, functions, and classes in the package must use the package name prefix, unless you import the package. (See "Importing Classes" on page 5-24.) For example, call a package function with this syntax:

```
z = mypack.pkfcn(x,y);
```

Note that definitions do not use the package prefix. For example, the function definition line of the pkfcn.m function would include only the function name:

```
function z = pkfcn(x,y)
```

Similarly, a package class would be defined with only the class name:

```
classdef myClass
```

but would be called with the package prefix:

```
obj = mypack.myClass(arg1,arg2,...);
```

Calling class methods does not require the package name because you have an instance of the class:

```
obj.myMethod(arg) or
myMethod(obj,arg)
```

A static method requires the full class name:

```
mypack.myClass.stMethod(arg)
```

Referencing Package Members from Outside the Package

Because functions, classes, and other packages contained in a package are scoped to that package, to reference any of the package members, you must prefix the package name to the member name, separated by a dot. For example, the following statement creates an instance of myClass, which is contained in mypack package.

```
obj = mypack.myClass;
```

Accessing Class Members — Various Scenarios

This section shows you how to access various package members from outside a package. Suppose you have a package mypack with the following contents:

```
+mypack
+mypack/myfcn.m
+mypack/@myfirstclass
+mypack/@myfirstclass/myfcn.m
+mypack/@myfirstclass/otherfcn.m
+mypack/@myfirstclass/myfirstclass.m
+mypack/@mysecondclass
+mypack/@mysecondclass/mysecondclass.m
+mypack/+mysubpack
+mypack/+mysubpack
+mypack/+mysubpack/myfcn.m
Invoke the myfcn function in mypack:
mypack.myfcn(arg)
Create an instance of each class in mypack:
obj1 = mypack.myfirstclass;
obj2 = mypack.mysecondclass(arg);
```

Invoke the myfcn function in mysubpack:

```
mypack.mysubpack.myfcn(arg1,arg2);
```

If mypack.myfirstclass has a method called myfcn, it is called as any method call on an object:

```
obj = mypack.myfirstclass;
myfcn(obj,arg);
```

If mypack.myfirstclass has a property called MyProp, it can be assigned using dot notation and the object:

```
obj = mypack.myfirstclass;
obj.MyProp = some value;
```

Packages and the MATLAB Path

You cannot add package folders to the MATLAB path, but you must add the package's parent folder to the path. Even if a package folder is the current folder, its parent folder must still be on the MATLAB path or the package members are not accessible.

Package members remain scoped to the package even if the package folder is the current folder. You must, therefore, always refer to the package members using the package name.

Package folders do not shadow other package folders that are positioned later on the path, unlike classes, which do shadow other classes.

Resolving Redundant Names

Suppose a package and a class have the same name. For example:

```
fldr1/+foo
fldr2/@foo/foo.m
```

A call to Which foo returns the path to the executable class constructor:

```
>> which foo
fldr2/@foo/foo.m
```

A function and a package can have the same name. However, a package name by itself is not an identifier so if a redundant name occurs alone, it identifies the function. Executing a package name alone returns an error.

If two or more packages have the same name, MATLAB treats them all as one package. If redundantly named packages in different path folders define the same function name, then MATLAB finds only one of these functions.

Package Functions vs. Static Methods

In cases where a package and a class have the same name, a static method takes precedence over a package function. For example:

```
fldr1/+foo/bar.m % bar is a function in package foo fldr2/@foo/bar.m % bar is a static method of class foo
```

A call to which foo.bar returns the path to the static method:

```
>> which foo.bar
fldr2/@foo/bar.m
```

In cases where a path folder contains both package and class folders with the same name, the class static method takes precedence over the package method:

```
fldr1/@foo/bar.m % bar is a static method of class foo fldr1/+foo/bar.m % bar is a function in package foo
```

A call to which foo.bar returns the path to the static method:

```
>> which foo.bar
fldr1/@foo/bar.m
```

More About

· "Class and Path Folders"

Importing Classes

Syntax for Importing Classes

You can import classes into a function to simplify access to class members. For example, suppose there is a package that contains a number of classes. You need to use only one of these classes in your function, or perhaps even just a static method from that class. Use the import command as follows:

```
function myFunc
  import pkg.cls1
  obj = cls1(arg,...); % call cls1 constructor
  obj.Prop = cls1.StaticMethod(arg,...); % call cls1 static method
end
```

You do not need to reference the package name (pkg) once you have imported the class (cls1). You can import all classes in a package using the syntax pkg.*:

```
function myFunc
  import pkg.*
  obj1 = cls1(arg,...); % call pkg.cls1 constructor
  obj2 = cls2(arg,...); % call pkg.cls2 constructor
  a = pkgFunction(); % call package function named pkgFunction
end
```

Importing Package Functions

Use import to import package functions:

```
function myFunc
  import pkg.pkfcn
  pkfcn(arg,...); % call imported package function
end
```

Package Function and Class Method Name Conflict

Suppose you have the following folder organization:

```
+pkg/timedata.m % package function
+pkg/@myclass/myclass.m % class definition file
+pkg/@myclass/timedata.m % class method
```

Import the package and call timedata on an instance of myclass:

```
import pkg.*
myobj = pkg.myclass;
timedata(myobj)
```

A call to timedata finds the package function, not the class method because MATLAB applies the import and finds pkg.timedata first. Do not use a package in cases where you have name conflicts and plan to import the package.

Clearing Import List

You can *not* clear the import list from a function workspace. To clear the *base workspace only*, use:

clear import

More About

"Packages Create Namespaces" on page 5-19

Value or Handle Class — Which to Use

- · "Comparing Handle and Value Classes" on page 6-2
- "Which Kind of Class to Use" on page 6-9
- "The Handle Superclass" on page 6-11
- "Handle Class Destructor" on page 6-16
- "Finding Handle Objects and Properties" on page 6-22
- "Implementing a Set/Get Interface for Properties" on page 6-23
- "Controlling the Number of Instances" on page 6-30

Comparing Handle and Value Classes

In this section...

"Basic Difference" on page 6-2

"Why Select Handle or Value" on page 6-2

"Behavior of MATLAB Built-In Classes" on page 6-3

"Behavior of User-Defined Classes" on page 6-4

Basic Difference

A *value* class constructor returns an instance that is associated with the variable to which it is assigned. If you reassign this variable, MATLAB creates a copy of the original object. If you pass this variable to a function, the function must return the modified object.

A *handle* class constructor returns a handle object that is a reference to the object created. You can assign the handle object to multiple variables or pass it to functions without causing MATLAB to make a copy of the original object. A function that modifies a handle object passed as an input argument does not need to return the object.

Note: All handle classes must subclass the abstract handle class.

"Modifying Objects" on page 4-60 compares handle and value object behavior when used as arguments to functions.

Why Select Handle or Value

MATLAB support two kinds of classes — handle classes and value classes. The kind of class you use depends on the desired behavior of the class instances and what features you want to use.

Use a handle class when you want to create a reference to the data contained in an object of the class, and do not want copies of the object to make copies of the object data. For example, use a handle class to implement an object that contains information for a phone book entry. Multiple application programs can access a particular phone book entry, but there can be only one set of underlying data.

The reference behavior of handles enables these classes to support features like events, listeners, and dynamic properties.

Use value classes to represent entities that do not need to be unique, like numeric values. For example, use a value class to implement a polynomial data type. You can copy a polynomial object and then modify its coefficients to make a different polynomial without affecting the original polynomial.

"Which Kind of Class to Use" on page 6-9 describes how to select the kind of class to use for your application.

Behavior of MATLAB Built-In Classes

If you create an object of the class int32 and make a copy of this object, the result is two independent objects having no data shared between them. The following code example creates an object of class int32 and assigns it to variable a, and then copies it to b. When you raise a to the fourth power and assign the value again to the variable a, MATLAB creates an object with the new data and assigns it to the variable a, overwriting the previous assignment. The value of b does not change.

```
a = int32(7);
b = a;
a = a^4;
b
7
```

MATLAB copies the value of a to b, which results in two independent versions of the original object. This behavior is typical of MATLAB numeric classes.

Handle Graphics[®] classes return a handle to the object created. A handle is a variable that references an instance of a class. If you copy the handle, you have another variable that refers to the same object. There is still only one version of the object data. For example, if you create a Handle Graphics line object and copy its handle to another variable, you can set the properties of the same line using either copy of the handle.

```
x = 1:10; y = sin(x);
h1 = line(x,y);
h2 = h1;
set(h2,'Color','red') % line is red
set(h1,'Color','green') % line is green
delete(h2)
set(h1,'Color','blue')
```

MATLAB returns an

Invalid or deleted object.

error in this case.

If you delete one handle, all copies are now invalid because you have deleted the single object to which all copies point.

Behavior of User-Defined Classes

Value class instances behave like built-in numeric classes and handle class instances behave like Handle Graphics objects, as illustrated in "Behavior of MATLAB Built-In Classes" on page 6-3.

Value Classes

MATLAB associates objects of value classes with the variables to which you assign them. When you copy a value object, MATLAB also copies the data contained by the object. The new object is independent of changes to the original object. Instances behave like standard MATLAB numeric and struct classes. Each property behaves essentially like a MATLAB array See "Memory Allocation for Arrays" for more information.

Value Class Behavior

Use value classes when assigning an object to a variable and passing an object to a function must make a copy of the function. Value objects are always associated with one workspace or temporary variable and go out of scope when that variable goes out of scope or is cleared. There are no references to value objects, only copies which are themselves objects.

For example, suppose you define a polynomial class whose Coefficients property stores the coefficients of the polynomial. Note how copies of these value-class objects are independent of each other:

```
p = polynomial([1 0 -2 -5]);
p2 = p;
p.Coefficients = [2 3 -1 -2 -3];
p2.Coefficients
ans =
    1 0 -2 -5
```

Creating a Value Class

All classes that are not subclasses of the handle class are value classes. Therefore, the following classdef creates a value class named myValueClass:

```
classdef myValueClass
    ...
end
```

Handle Classes

Objects of handle classes use a handle to reference objects of the class. A handle is a variable that identifies an instance of a class. When you copy a handle object, MATLAB copies the handle, but not the data stored in the object properties. The copy refers to the same data as the original handle. If you change a property value on the original object, the copied object reflects the same change.

All handle classes are subclasses of the abstract handle class. In addition to providing handle copy semantics, deriving from the handle class enables your class to:

- Inherit a number of useful methods ("Handle Class Methods" on page 6-12)
- Define events and listeners ("Events and Listeners Syntax and Techniques" on page 10-19)
- Define dynamic properties ("Dynamic Properties Adding Properties to an Instance" on page 7-30)
- Implement Handle Graphics type set and get methods ("Implementing a Set/Get Interface for Properties" on page 6-23)

Creating a Handle Class

Subclass the handle class explicitly to create a handle class:

```
classdef myClass < handle
   ...
end</pre>
```

See "The Handle Superclass" on page 6-11 for more information on the handle class and its methods.

Subclasses of Handle Classes

If you subclass a class that is itself a subclass of the handle class, your subclass is also a handle class. You do not need to specify the handle superclass explicitly in your class definition. For example, the employee class is a subclass of the handle class:

```
classdef employee < handle
...
end</pre>
```

Create a subclass of the employee class for engineer employees, which is also a handle class. You do not need to specify handle as a superclass in the classdef:

```
classdef engineer < employee
...
end</pre>
```

Handle Class Behavior

A handle is an object that references its data indirectly. When constructing a handle, the MATLAB runtime creates an object with storage for property values and the constructor function returns a handle to this object. When you assign the handle to a variable or when you pass the handle to a function, MATLAB copies the handle, but not the underlying data.

For example, suppose you have defined a handle class that stores data about company employees, such as the department in which they work:

```
classdef employee < handle
  properties
    Name = ''
    Department = '';
end
methods
  function e = employee(name,dept)
    e.Name = name;
    e.Department = dept;
end % employee
  function transfer(obj,newDepartment)
    obj.Department = newDepartment;
end % transfer
end
end</pre>
```

The transfer method in the previous code changes the employee's department (the Department property of an employee object). In the following statements, e2 is a copy of the handle object e. Notice that when you change the Department property of object e, the property value also changes in object e2.

```
e = employee('Fred Smith','QE');
```

```
e2 = e; % Copy handle object
transfer(e, 'Engineering')
e2.Department
ans =
Engineering
```

The variable e2 is an alias for e and refers to the same property data storage as e.

Initializing Properties to Handle Objects

See "Initializing Property Values" on page 4-11 for information on the differences between initializing properties to default values in the properties block and initializing properties from within the constructor. Also, see "Initialize Arrays of Handle Objects" on page 9-10 for related information on working with handle classes.

employee as a Value Class

If the employee class was a value class, then the transfer method would modify only its local copy of the employee object. In value classes, methods like transfer that modify the object must return a modified object to copy over the existing object variable:

```
function obj = transfer(obj,newDepartment)
  obj.Department = newDepartment;
end
```

When you call transfer, assign the output argument to create the modified object.

```
e = transfer(e, 'Engineering');
```

In a value class, the transfer method does not affect the variable e2, which is a different employee object. In this example, having two independent copies of objects representing the same employee is not a good design. Hence, implement the employee class as a handle class.

Deleting Handles

You can destroy handle objects before they become unreachable by explicitly calling the delete function. Deleting the handle of a handle class object makes all handles invalid. For example:

```
delete(e2)
e.Department
Invalid or deleted object.
```

6

Calling the delete function on a handle object invokes the destructor function or functions for that object. See "Handle Class Destructor" on page 6-16 for more information.

Which Kind of Class to Use

In this section...

"Examples of Value and Handle Classes" on page 6-9

"When to Use Handle Classes" on page 6-9

"When to Use Value Classes" on page 6-10

Examples of Value and Handle Classes

Handle and value classes are useful in different situations. For example, value classes enable you to create new array classes that have the same semantics as MATLAB numeric classes.

"Class Design for Polynomials" on page 18-2 and "Class to Represent Structured Data" on page 3-24 provides examples of value classes.

Handle classes enable you to create objects that more than one function or object can share. Handle objects allow more complex interactions among objects because they allow objects to reference each other.

"Class to Implement Linked Lists" on page 3-36 and "Developing Classes — Typical Workflow" on page 3-8 provides examples of a handle class.

When to Use Handle Classes

Use a handle class when:

- No two instances of a class can have the same state, making it impossible to have exact copies. For example:
 - A copy of a graphics object (such as a line) has a different position in its parents list of children than the object from which it was copied. Therefore, the two objects are not identical.
 - Nodes in lists or trees having specific connectivity to other nodes—no two nodes can have the same connectivity.
- The class represents physical and unique objects like serial ports or printers, in which
 the entity or state cannot exist in a MATLAB variable. However, a handle to such
 entity can be a variable.

- The class defines events and notifies listeners when an event occurs (notify is a handle class method).
- The class creates listeners by calling the handle class addlistener method.
- The class subclasses the dynamicprops class (a subclass of handle) so that instances can define dynamic properties.
- The class subclasses the matlab.mixin.SetGet class (a subclass of handle) so that it can implement a graphics object style set/get interface to access property values.
- You want to create a singleton class or a class in which you track the number of
 instances from within the constructor. MATLAB software never creates a unique
 handle without calling the class constructor. A copy of a handle object is not unique
 because both original and copy reference the same data.

When to Use Value Classes

Value class instances behave like normal MATLAB variables. A typical use of value classes is to define data structures. For example, suppose you want to define a class to represent polynomials. This class can define a property to contain a list of coefficients for the polynomial. It can implement methods that enable you to perform various common operations on the polynomial object. For example, implement addition and multiplication without converting the object to another class.

A value class is suitable because you can copy a polynomial object and have two objects that are identical representations of the same polynomial. See "Subclassing MATLAB Built-In Types" on page 11-44 for more information on value classes.

The Handle Superclass

In this section...

"Building on the Handle Class" on page $\overline{6-11}$

"Handle Class Methods" on page 6-12

"Relational Methods" on page 6-12

"Testing Handle Validity" on page 6-12

"When MATLAB Destroys Objects" on page 6-14

Building on the Handle Class

The handle class is an abstract class, which means you cannot create an instance of this class directly. Instead, you use this class as a superclass when you implement your own class. The handle class is the foundation of all classes that are themselves handle classes. When you define a class that is a subclass of handle, you have created a handle class. Therefore, all classes that follow handle semantics are subclasses of the handle class.

Handle Subclasses

There are two subclasses of the handle class that provide additional features when you derive your class from these subclasses:

- matlab.mixin.SetGet Provides set and get methods to access property values. See "Implementing a Set/Get Interface for Properties" on page 6-23 for information on subclassing matlab.mixin.SetGet.
- dynamicprops Provides the ability to define instance properties. See "Dynamic Properties — Adding Properties to an Instance" on page 7-30 for information on subclassing dynamicprops.

Deriving from subclasses of the handle class means that your class is a handle class. It inherits all the handle class methods, plus the special features provided by these subclasses.

Handle Class Methods

While the handle class defines no properties, it does define the methods discussed in this section. Whenever you create a handle class (that is, subclass the handle class), your subclass inherits these methods.

You can list the methods of a class by passing the class name to the methods function:

```
>> methods('handle')

Methods for class handle:

addlistener findobj gt lt
delete findprop isvalid ne
eq qe le notify
```

"Events and Listeners — Syntax and Techniques" on page 10-19 provides information on how to use the notify and addlistener methods, which are related to the use of events.

"Creating Subclasses — Syntax and Techniques" on page 11-7 provides general information on defining subclasses.

Relational Methods

```
function TF = eq(H1,H2)
function TF = ne(H1,H2)
function TF = lt(H1,H2)
function TF = le(H1,H2)
function TF = gt(H1,H2)
function TF = ge(H1,H2)
```

The handle class overloads these functions with implementations that allow for equality tests and sorting on handles. For each pair of input arrays, these functions return a logical array of the same size. Each element is an element-wise equality or comparison test result. The input arrays must be the same size or one (or both) can be scalar. The method performs scalar expansion as required.

Testing Handle Validity

Use the isvalid handle class method to determine if you have a valid handle object. For example, in this statement:

```
B = isvalid(H)
```

B is a logical array in which each element is true if, and only if, the corresponding element of H is a valid handle. B is always the same size as H.

Handle Class or Graphics Object Handle

Use the isa function to determine if a handle is of class handle, or is a Java or Handle Graphics handle. For example, consider the button class, which derives from the handle class:

Create a button object by passing a position vector to the button constructor:

```
h = button([50 20 50 20]);
```

Determine the difference between the graphics object handle (stored in the UiHandle property) and the handle class object, h. Use ishandle to test the validity of Handle Graphics object handles:

```
% The uicontrol is a graphics object handle
>> ishandle(h.UiHandle)
ans =
     1
If you close the figure, the ishandle function determines that the Handle Graphics
handle is not valid:
>> close
>> ishandle(h.UiHandle)
ans =
     0
h is still of class handle and is still a valid handle object:
>> isa(h,'handle')
ans =
>> isvalid(h)
ans =
h is also of class button:
>> isa(h,'button')
ans =
```

When MATLAB Destroys Objects

MATLAB destroys objects in the workspace of a function when the function:

- Reassigns an object variable to a new value
- Does not use an object variable for the remainder of a function

· Function execution ends

When MATLAB destroys an object, it also destroys values stored in the properties of the object and returns any computer memory associated with the object to MATLAB or the operating system.

You do not need to free memory in handle classes. However, there can be other operations that you want to perform when destroying an object. For example, closing a file or shutting down an external program that the object constructor started. You can define a delete method in your handle subclass for these purposes.

See "Handle Class Destructor" on page 6-16 for more information.

Handle Class Destructor

In this section...

"Basic Knowledge" on page 6-16

"Syntax of Class Destructor Method" on page 6-16

"When to Define a Destructor Method" on page 6-17

"Destructors in Class Hierarchies" on page 6-17

"Object Lifecycle" on page 6-18

"Restrict Explicit Object Deletion" on page 6-20

"Nondestructor Delete Methods" on page 6-20

Basic Knowledge

Terms and Concepts

Class destructor — a method named delete that MATLAB calls implicitly before destroying an object of the a handle class. User-defined code can also call delete explicitly to destroy a handle object.

Nondestructor – a method named **delete** that does not meet the syntax requirements of a valid destructor. Consequently, MATLAB does not call this method implicitly when destroying an object.

Table of method attributes: "Method Attributes" on page 8-5

Syntax of Class Destructor Method

When destroying an object, MATLAB implicitly calls the class destructor method, if the class defines one. Create a destructor method by implementing a method named delete. However, MATLAB recognizes a class method named delete as the class destructor only if you define delete as an ordinary method with the appropriate syntax.

To be a valid class destructor, the **delete** method:

- Must have one scalar input argument that is an object of the class.
- Must not define output arguments
- · Cannot be Sealed, Static, or Abstract

In addition, destructors should *not*:

- · Throw errors
- Create new handles to the object being destroyed

If you define a **delete** method that can be called with more than one input argument, or that returns any output arguments, then MATLAB does not recognize that method as the class destructor, and does not call it when destroying an object of the class.

Declare delete as an ordinary method:

```
methods
  function delete(obj)
    % obj is always scalar
  ...
  end
end
```

Calling Delete on an Array

MATLAB calls the destructor method element-wise on an array of objects. Because MATLAB calls the delete method separately for each element in an object array, each delete method is passed only one scalar argument.

When to Define a Destructor Method

Use a class destructor to perform any necessary cleanup operations before MATLAB destroys an object of the class.

For example, suppose an object opens a file for writing and you want to close the file in your delete method. This delete function calls fclose on a file identifier that the object's FileID property stores:

```
function delete(obj)
  fclose(obj.FileID);
end
```

For an example that uses this delete method, see "Class to Manage Writable Files".

Destructors in Class Hierarchies

If you create a hierarchy of classes, each class can define its own class destructor method. When destroying an object, MATLAB calls the destructor of each class in the hierarchy.

Therefore, defining a delete method in a handle subclass does not override the handle class delete method; the subclass delete methods augment the superclass delete methods.

Inheriting a Sealed Delete Method

You cannot define a valid destructor that is Sealed. MATLAB returns an error when you attempt to instantiate a class that defines a Sealed destructor.

Normally, declaring a method as Sealed prevents subclasses from overriding that method. However, because destructors must be named delete, an inherited method named delete that is Sealed does not prevent subclasses from defining valid destructors.

For example, if a superclass defines a method named delete that is not a valid destructor and is Sealed, then subclasses:

- · Can define valid destructors (which are always named delete).
- Cannot define methods named delete that are not valid destructors.

Destructors in Heterogeneous Hierarchies

Heterogeneous class hierarchies (matlab.mixin.Heterogeneous) require that all methods to which heterogeneous arrays are passed must be sealed. However, the rule does not apply to class destructor methods. Because destructor methods cannot be sealed, you can define a valid destructor in a heterogeneous hierarchy that is not sealed, but does function as a destructor.

Object Lifecycle

MATLAB invokes the destructor **delete** method when the lifecycle of an object ends. The lifecycle of an object ends when the object is:

- · No longer referenced anywhere
- · Explicitly deleted by calling delete on the handle

Inside a Function

The lifecycle of an object referenced by a local variable or input argument exists from the time the variable is assigned until the time it is reassigned, cleared, or no longer referenced within that function or any handle array.

A variable goes out of scope when you explicitly clear it or when its function ends. When a variable goes out of scope, if its value belongs to a handle class that defines a delete method, MATLAB calls that method. MATLAB defines no ordering among variables in a function. Do not assume that MATLAB destroys one value before another value when the same function contains multiple values.

Sequence During Handle Object Destruction

MATLAB invokes the delete methods in the following sequence when destroying an object:

- 1 The delete method for the class of the object
- 2 The delete method of each superclass class, starting with the immediate superclasses and working up the hierarchy to the most general superclasses

MATLAB invokes the delete methods of superclasses at the same level in the hierarchy in the order specified in the class definition. For example, the following class definition specifies supclass1 before supclass2 so MATLAB calls the delete function of supclass1 before the delete function of supclass2.

classdef myClass < supclass1 & supclass2

Superclass delete methods cannot call methods or access properties belonging to a subclass.

After calling each delete method, MATLAB destroys the property values belonging exclusively to the class whose method was called. The destruction of property values that contain other handle objects can cause MATLAB to call the delete methods for those objects, if there are no other references to those objects.

Destruction of Objects with Cyclic References

Consider a set of objects that reference other objects of the set such that the references form a cyclic graph. In this case, MATLAB:

- · Destroys the objects if they are referenced only within the cycle
- Does not destroy the objects as long as there is an external reference to any of the objects from a MATLAB variable outside the cycle

MATLAB destroys the objects in the reverse of the order of construction.

Restrict Explicit Object Deletion

You can destroy handle objects by explicitly calling delete on the object:

delete(obj)

A class can prevent explicit destruction of an object by setting its delete method Access attribute to private. MATLAB issues an error if you explicitly call delete on a handle object whose delete method is private. However, a method of the class can call the private delete method.

Similarly, if the class delete method Access attribute has a value of protected, only methods of the class and any subclasses can explicitly delete objects of that class.

However, when an object's lifecycle ends, MATLAB calls the object's delete method when destroying the object regardless of method's Access attribute setting. See "Object Lifecycle" on page 6-18 for information on when MATLAB destroys objects and "Sequence During Handle Object Destruction" on page 6-19 for information on how MATLAB calls object delete methods.

Inherited Private Delete Methods

Class destructor behavior differs from the normal behavior of an overridden method. MATLAB executes each delete method of each superclass of an object upon destruction, even if that delete method is not public.

When you explicitly call an object's delete method, MATLAB checks the delete method Access attribute in the class defining the object, but not in the superclasses of the object. Therefore, a superclass with a private delete method does not prevent the destruction of subclass objects.

Declaring a private delete method makes most sense for sealed classes. The reason for this is because, in the case where classes are not sealed, subclasses can define their own delete methods with public access, and MATLAB calls a private superclass delete method as a result of an explicit call to a public subclass delete method.

Nondestructor Delete Methods

A class can implement a method named delete that is not a valid class destructor, and therefore is not called implicitly by MATLAB when destroying an object. In this case, delete behaves like a normal method.

For example, if the superclass implements a Sealed method named delete that is not a valid destructor, then MATLAB does not allow subclasses to override this method.

A delete method defined by a value class cannot be a class destructor. See "Basic Difference" on page 6-2 for information on the difference between a value and handle class.

See "Syntax of Class Destructor Method" on page 6-16 for information on how to implement a delete method that is a valid destructor.

Finding Handle Objects and Properties

```
In this section...

"Finding Handle Objects" on page 6-22

"Finding Handle Object Properties" on page 6-22
```

Finding Handle Objects

The findobj method enables you to locate handle objects that meet certain conditions.

```
function HM = findobj(H, <conditions>)
```

The findobj method returns an array of handles matching the conditions specified.

Finding Handle Object Properties

The findprop method returns the meta.property object for the specified object and property.

```
function mp = findprop(h, 'PropertyName')
```

The findprop method returns the meta.property object associated with the *PropertyName* property defined by the class of h. The property can also be a dynamic property created by the addprop method of the dynamicprops class.

You can use the returned meta.property object to obtain information about the property, such as querying the settings of any of its attributes. For example, the following statements determine that the setting of the AccountStatus property's Dependent attribute is false.

```
ba = BankAccount(007,50,'open');
mp = findprop(ba,'AccountStatus'); % get meta.property object
mp.Dependent
ans =
    0
```

"Class Metadata" on page 15-2 provides more information on meta-classes.

Implementing a Set/Get Interface for Properties

In this section...

"The Standard Set/Get Interface" on page 6-23

"Subclass matlab.mixin.SetGet" on page 6-23

"Get Method Syntax" on page 6-23

"Set Method Syntax" on page 6-24

"Class Derived from matlab.mixin.SetGet" on page 6-25

The Standard Set/Get Interface

The MATLAB graphics system implements an interface based on set and get methods. These methods enable you to set or query the values of graphics object properties. The matlab.mixin.SetGet subclass of the handle class provides implementations of these methods. Derive your class from matlab.mixin.SetGet to obtain similar set and get functionality.

Note: The set and get methods referred to in this section are different from property set access and property get access methods. See "Property Access Methods" on page 7-14 for information on property access methods.

Subclass matlab.mixin.SetGet

Classes inherit set and get methods from matlab.mixin.SetGet:

classdef MyClass < matlab.mixin.SetGet</pre>

Because matlab.mixin.SetGet derives from the handle class, MyClass is also a handle class.

Get Method Syntax

Get the value of an object property using the object handle, h, and the property name:

```
v = get(h,'PropertyName');
```

If you specify an array of handles with a single property name, get returns the current property value for each object in H as a cell array of values, (CV):

```
CV = get(H, 'PropertyName');
```

The CV array is always a column regardless of the shape of H.

When prop is a cell array of string property names and H is an array of handles, get returns a cell array of values where each row in the cell corresponds to an object in H and each column in the cell corresponds to a property in prop. get returns the corresponding property values in an m-by-n cell array, where m = length(H) and n = length(prop)

```
prop = {'PropertyName1', 'PropertyName2'};
CV = get(H,prop);
```

If you specify a handle array, but no property names, get returns a struct array in which each structure in the array corresponds to an object in H. Each field in the structure corresponds to a property defined by the class of H. The value of each field is the value of the corresponding property. If you do not assign an output variable, then H must be scalar.

```
SV = get(H);
```

See "Using Handle Arrays with Get" on page 6-27 for an example.

Set Method Syntax

The set method assigns the value of the specified property for the object with handle H. If H is an array of handles, MATLAB assigns the property value to the named property for each object in the array H.

```
set(H, 'PropertyName', PropertyValue)
```

You can pass a cell array of property names and a cell array of property values to set:

```
set(H,{'PropertyName1','PropertyName2'},...
{Property1Value,Property2Value})
```

If length(H) is greater than one, then the property value cell array can have values for each property in each object. For example, if length(H) is 2 (two object handles), then you can use an expression like this:

```
set(H,{'PropertyName1','PropertyName2'},...
{Property11Value,Property12Value;Property21Value,Property22Value})
```

The preceding statement is equivalent to the follow two statements:

```
set(H(1), 'PropertyName1', Property11Value, 'PropertyName2', Property12Value)
set(H(2), 'PropertyName1', Property21Value, 'PropertyName2', Property22Value)
```

If you specify a scalar handle, but no property names, set returns a struct array with one field for each property in the class of H. Each field contains an empty cell array.

```
SV = set(h);
```

See "Class Derived from matlab.mixin.SetGet" on page 6-25 for an example.

Class Derived from matlab.mixin.SetGet

This sample class defines a set/get interface and illustrates the behavior of the inherited methods:

```
classdef LineType < matlab.mixin.SetGet</pre>
   properties
      Style = '-';
      Marker = 'o';
   properties (SetAccess = protected)
      Units = 'points';
   end
   methods
      function obj = LineType(s,m)
         if nargin > 0
            obj.Style = s;
            obj.Marker = m;
         end
      end % LineType
      function obj = set.Style(obj,val)
         if ~(strcmpi(val,'-') ||...
               strcmpi(val, '--') ||...
               strcmpi(val,'..'))
            error('Invalid line style ')
         end
      obj.Stvle = val;
      end % set.Style
      function obj = set.Marker(obj,val)
         if ~isstrprop(val, 'graphic')
            error('Marker must be a visible character')
         obj.Marker = val;
      end % set.Marker
   end % methods
```

```
end % classdef
```

Create an instance of the class and save its handle:

```
h = LineType('--','*');
```

Query the value of any object property using the inherited get method:

```
get(h,'Marker')
ans =
```

Set the value of any property using the inherited set method:

```
set(h,'Marker','Q')
```

Property Access Methods Are Called

MATLAB calls any property access methods (set.Style or set.Marker in the LineType class) when you use the set and get methods that are inherited from the matlab.mixin.SetGet class:

```
set(h,'Style','-.-')
Error using LineType>LineType.set.Style
Invalid line style
```

Using the set and get methods that are inherited from matlab.mixin.SetGet invokes any existing property access methods that would execute when assigning or querying property values using dot notation:

```
h.Style = '-.-';
Error using LineType>LineType.set.Style
Invalid line style
```

See "Property Access Methods" on page 7-14 for more information on property access methods.

Listing All Properties

You can create a struct containing object properties and their current values using get with only a handle array as input.

For example, the struct SV contains fields whose names correspond to property names. Each field contains the current value of the respective property.

```
% Create a LineType object and save its handle
h = LineType('--','*');
% Query the property values of object h
SV = get(h)
SV =

Style: '--'
Marker: '*'
Units: 'points'
```

Create a struct containing the properties that have public SetAccess using set with an object handle:

```
% Query setable property values
S = set(h)
S =
    Style: {}
    Marker: {}
```

The LineType class defines the Units property with SetAccess = protected. Therefore, S = set(h) does not create a field for this property in the struct S. set cannot return possible values for the properties.

Using Handle Arrays with Get

Suppose you create an array of LineType objects:

```
H = [LineType('...', 'z'), LineType('---', 'q')]
H =
    1x2 LineType with properties:
    Style
    Marker
    Units
```

When H is an array of handles, get returns a (length(H)-by-1) cell array of property values:

```
CV = get(H, 'Style')
CV =
```

```
' • • '
' - - '
```

When H is an array of handles and you do not specify a property name, get returns a struct array containing fields with name corresponding to property-names. You must assign the output of get to a variable when H is not scalar.

```
% Assign output of get for nonscalar H
SV = get(H)
SV =

2x1 struct array with fields:
    Style
    Marker
    Units
```

Get the value of the Marker property from the second array element in the SV struct array:

```
SV(2).Marker
ans =
```

Handle, Property Name, and Property Value Arrays

You can pass an array of handles, a cell array of property names, and a cell array of property values to set. The property value cell array must have one row of property values for each object in H and each row must have a value for each property in the property name array:

```
H = [LineType('..', 'z'),LineType('--', 'q')];
set(H, {'Style', 'Marker'}, {'..', 'o'; '--', 'x'})
The results of this call to set is:
H(1)
ans =
LineType with properties:
```

```
Style: '..'
Marker: 'o'
Units: 'points'

H(2)

ans =

LineType with properties:

Style: '--'
Marker: 'x'
Units: 'points'
```

Customizing the Property List

Customize the way property lists display by redefining the following methods in your subclass:

- setdisp When you call set with no output argument and a single scalar handle input, set calls setdisp to determine how to display the property list.
- getdisp When you call get with no output argument and a single scalar handle input, get calls getdisp to determine how to display the property list.

Controlling the Number of Instances

Limiting Instances

You can limit the number of instances of a class that can exist at any one time. For example, a *singleton* class can have only one instance and provides a way to access this instance. You can create a singleton class using these elements:

- · A persistent variable to contain the instance
- A sealed class (Sealed attribute set to true) to prevent subclassing
- A private constructor (Access attribute set to private)
- A static method to return the handle to the instance, if it exists, or to create the instance when needed.

Implementing a Singleton Class

The following skeletal class definition shows how you can approach the implementation of a class that allows you to create only one instance at a time:

```
classdef (Sealed) SingleInstance < handle
  methods (Access = private)
    function obj = SingleInstance
    end
end
methods (Static)
  function singleObj = getInstance
    persistent localObj
    if isempty(localObj) || ~isvalid(localObj)
        localObj = SingleInstance;
    end
    singleObj = localObj;
  end
end</pre>
```

The getInstance static method returns a handle to the object created, which the class stores in a persistent variable. getInstance creates an instance only the first time called in a session or when the object becomes invalid. For example:

```
sobj = SingleInstance.getInstance
sobj =
```

SingleInstance with no properties

As long as sobj exists as a valid handle, calling getInstance returns a handle to the same object. If you delete sobj, then calling getInstance creates an object and returns the handle.

```
delete(sobj)
isvalid(sobj)
ans =

     0
sobj = SingleInstance.getInstance;
isvalid(sobj)
ans =
     1
```

Properties — Storing Class Data

- "How to Use Properties" on page 7-2
- "Defining Properties" on page 7-4
- "Property Attributes" on page 7-7
- "Mutable and Immutable Properties" on page 7-13
- "Property Access Methods" on page 7-14
- "Property Set Methods" on page 7-19
- "Property Get Methods" on page 7-22
- "Access Methods for Dependent Properties" on page 7-24
- "Properties Containing Objects" on page 7-28
- "Dynamic Properties Adding Properties to an Instance" on page 7-30

How to Use Properties

In this section...

"What Are Properties" on page 7-2

"Types of Properties" on page 7-2

What Are Properties

Properties encapsulate the data that belongs to instances of classes. Data contained in properties can be public, protected, or private. This data can be a fixed set of constant values, or it can be dependent on other values and calculated only when queried. You control these aspects of property behaviors by setting property attributes and by defining property-specific access methods.

Flexibility of Object Properties

In some ways, properties are like fields of a struct object. However, storing data in an object property provides more flexibility. Properties can:

- Define a constant value that you cannot change outside the class definition. See "Properties with Constant Values" on page 14-2
- Calculate its value based on the current value of other data. See "Property Get Methods" on page 7-22
- Execute a function to determine if an attempt to assign a value meets a certain criteria. See "Property Set Methods" on page 7-19
- Trigger an event notification when any attempt is made to get or set its value. See "Property-Set and Query Events" on page 10-14
- Restrict access by other code to the property value. See the SetAccess and GetAccess attributes "Property Attributes" on page 7-7
- Control whether its value is saved with the object in a MAT-file. See "Save and Load Objects" on page 12-2

Types of Properties

There are two types of properties:

Stored properties — Use memory and are part of the object

 Dependent properties — No allocated memory and the get access method calculates the value when queried

Features of Stored Properties

- Can assign an initial value in the class definition
- · Property value is stored when you save the object to a MAT-file
- Can use a set access method to control possible values, but you are not required to use such methods.

When to Use Stored Properties

- You want to be able to save the property value in a MAT-file
- The property value is not dependent on other property values

Features of Dependent Properties

Dependent properties save memory because property values that depend on other values are calculated only when needed.

When to Use Dependent Properties

Define properties as dependent when you want to:

- Compute the value of a property from other values (for example, you can compute area from Width and Height properties).
- Provide a value in different formats depending on other values. For example, the size of a push button in values determined by the current setting of its Units property.
- Provide a standard interface where a particular property is or is not used, depending on other values. For example, different computer platforms can have different components on a toolbar).

Related Examples


- "Property Attributes"
- "Property Access Methods" on page 7-14

Defining Properties

In this section... "Property Definition Block" on page 7-4 "Access Property Values" on page 7-5 "Inheritance of Properties" on page 7-5 "Specify Property Attributes" on page 7-5

Property Definition Block

The following illustration shows a typical property specification. The properties and end keywords delineate a block of code that defines properties having the same attribute settings.



Note: Properties cannot have the same name as the class

Assigning a Default Value

The preceding example shows the Coefficients property specified as having a default value of [0 0 1].

You can initialize property values with MATLAB expressions. However, these expressions cannot refer to the class that you are defining in any way, except to call class static methods. MATLAB executes expressions that create initial property values only when initializing the class, which occurs just before first using the class. See "Defining Default Values" on page 4-12 for more information about how MATLAB evaluates default value expressions.

Access Property Values

Property access syntax is like MATLAB structure field syntax. For example, if obj is an object of a class, then you can get the value of a property by referencing the property name:

```
val = obj.PropertyName
```

Assign values to properties by putting the property reference on the left side of the equal sign:

```
obj.PropertyName = val
```

When you access a property, MATLAB executes any property set or get access method and triggering any enabled property events.

Inheritance of Properties

When you derive one class from another class, the derived (subclass) class inherits all the properties of the superclass. In general, subclasses define only properties that are unique to that particular class. Superclasses define properties that more than one subclass use.

Specify Property Attributes

Attributes specified with the properties keyword apply to all property definitions that follow in that block. If you want to apply attribute settings to certain properties only, reuse the properties keyword and create another property block for those properties.

For example, the following code shows the SetAccess attribute set to private for the IndependentVar and Order properties, but not for the Coefficients property:

See for a list of all property attributes.

More About

- "Properties"
- "Property Attributes" on page 7-7

Property Attributes

In this section... "Specifying Property Attributes" on page 7-7 "Table of Property Attributes" on page 7-7

Specifying Property Attributes

Assign property attributes on the same line as the properties keyword:

```
properties (Attribute1 = value1, Attribute2 = value2,...)
    ...
end
```

For example, give the Data property private access:

```
properties (Access = private)
   Data
end
```

For more information on attribute syntax, see "Attribute Specification".

Table of Property Attributes

Attributes enable you to modify the behavior of properties. All properties support the attributes listed in the following table.

Attribute values apply to all properties defined within the properties...end code block that specifies the nondefault values.

Property Attributes

Attribute Name	Class	Description
AbortSet	logical	If true, MATLAB does not set the property value if the new value is the same
	default = false	as the current value and does not call the property set method, if one exists.
		For handle classes, setting AbortSet to true also prevent the triggering of property PreSet and PostSet events.

Attribute Name	Class	Description
		See "Aborting Set When Value Does Not Change" on page 10-32
Abstract	logical default = false	If true, the property has no implementation, but a concrete subclass must redefine this property without Abstract being set to true.
		• Abstract properties cannot define set or get access methods. See "Property Access Methods" on page 7-14.
		• Abstract properties cannot define initial values. See "Assigning a Default Value" on page 7-5.
		 All subclasses must specify the same values as the superclass for the property SetAccess and GetAccess attributes.
		• Abstract=true use with the class attribute Sealed=false (the default).
Access	enumeration, default = public	public – unrestricted access
	meta.class objectcell array of	<pre>protected - access from class or subclasses</pre>
	meta.class objects	<pre>private - access by class members only (not subclasses)</pre>
		List of classes that have get and set access to this property. Specify classes as meta.class objects in the form:
		• A single meta.class object
		 A cell array of meta.class objects. An empty cell array, {}, is the same as private access.

Attribute Name	Class	Description
		See "Control Access to Class Members" on page 11-25
		Use Access to set both SetAccess and GetAccess to the same value. Query the values of SetAccess and GetAccess directly (not Access).
Constant	logical default = false	Set to true if you want only one value for this property in all instances of the class:
	default = Talse	• Subclasses inherit constant properties, but cannot change them.
		 Constant properties cannot be Dependent.
		• SetAccess is ignored.
		See "Properties with Constant Values" for more information.
Dependent	logical default = false	If false, property value is stored in object. If true, property value is not stored in object. The set and get functions cannot access the property by indexing into the object using the property name.
		MATLAB does not display in the command window the names and values of Dependent properties that do not define a get method (scalar object display only).
		• "Calculate Data on Demand" on page 3-28
		• "Property Get Methods"
		 "Avoid Property Initialization Order Dependency" on page 12-9
GetAccess	enumeration	public — unrestricted access
	default = public	

Attribute Name	Class	Description
		<pre>protected — access from class or subclasses</pre>
		<pre>private — access by class members only (not from subclasses)</pre>
		List classes that have get access to this property. Specify classes as meta.class objects in the form:
		· A single meta.class object
		 A cell array of meta.class objects. An empty cell array, {}, is the same as private access.
		See "Control Access to Class Members" on page 11-25
		MATLAB does not display in the command window the names and values of properties having protected or private GetAccess or properties whose Hidden attribute is true.
		The struct function defines fields for all properties when converting objects to structs.
GetObservable	logical	If true, and it is a handle class property,
	default = false	then you can create listeners for access to this property. The listeners are called whenever property values are queried. See "Property-Set and Query Events" on page 10-14
Hidden	logical default = false	Determines whether the property should be shown in a property list (e.g., Property Inspector, call to set or get, etc.).
		· · · · · · · · · · · · · · · · · · ·

Attribute Name	Class	Description
		MATLAB does not display in the command window the names and values of properties whose Hidden attribute is true or properties having protected or private GetAccess.
SetAccess	enumeration	public — unrestricted access
	default = public	<pre>protected — access from class or subclasses</pre>
		<pre>private — access by class members only (not from subclasses)</pre>
		<pre>immutable — property can be set only in the constructor.</pre>
		See "Mutable and Immutable Properties" on page 7-13
		List classes that have set access to this property. Specify classes as meta.class objects in the form:
		· A single meta.class object
		 A cell array of meta.class objects. An empty cell array, {}, is the same as private access.
		See "Control Access to Class Members" on page 11-25
SetObservable	logical	If true, and it is a handle class property,
	default = false	then you can create listeners for access to this property. The listeners are called whenever property values are modified. See "Property-Set and Query Events" on page 10-14
Transient	logical	If true, property value is not saved when object is saved to a file. See "Save and

Attribute Name	Class	Description
	default = false	Load Process" on page 12-2 for more
		about saving objects.

Mutable and Immutable Properties

Set Access to Property Values

The property SetAccess attribute enables you to determine under what conditions code can modify object property values. There are four levels of set access that provide varying degrees of access to object property values:

- SetAccess = public any code with access to an object can set public property values. There are differences between the behavior of handle and value classes with respect to modifying object properties.
- SetAccess = protected only code executing from within class methods or methods of subclasses can set property values. You cannot change the value of an object property unless the class or any of its subclasses defines a method to do so.
- SetAccess = private only the defining class can set property values. You can change the value of an object property only if the class defines a method to perform this action.
- SetAccess = immutable only the class constructor can set property values. You cannot change the value of an object property.

More About

"Modifying Objects"

Property Access Methods

In this section...

"Property Setter and Getter Methods" on page 7-14

"Set and Get Method Execution and Property Events" on page 7-16

"Access Methods and Properties Containing Arrays" on page 7-17

"Modify Property Values with Access Methods" on page 7-18

Property Setter and Getter Methods

Property access methods execute specific code whenever the associated property's value is queried or assigned a value. These methods enable you to perform a variety of operations:

- Execute code before assigning property values to perform actions such as:
 - Impose value range restrictions ("Restrict Properties to Specific Values" on page 3-26)
 - · Check for proper types and dimensions
 - · Provide error handling
- Execute code before returning the current values of properties to perform actions such as:
 - Calculate the value of properties that do not store values (for an example, see "Calculate Data on Demand" on page 3-28)
 - Change the value of other properties
 - Trigger events (for an example, see "Defining and Triggering an Event" on page 10-5)

Calling Access Methods

Note: You cannot call property access methods directly.

Property access methods execute automatically whenever you set or query the corresponding property values from outside the access method. MATLAB never calls the

set method for a property of a particular class if the property value is set from within that set method. Similarly, the get method for a property of a particular class is never called if the property is queried from within that get method.

You can obtain the function handle for the set and get access methods from the property's meta.property object. The meta.property SetMethod and GetMethod properties contain the function handles for these methods.

Restrictions on Access Methods

You can define property access methods only:

- For concrete properties (that is, properties that are not abstract)
- Within the class that defines the property (unless the property is abstract in that class, in which case the concrete subclass must define the access method).

MATLAB has no default set or get property access methods. Therefore, if you do not define property access methods, MATLAB software does not invoke any methods before assigning or returning property values.

Once defined, only the set and get methods can set and query the actual property values. See "Set Method Behavior" on page 7-20 for information on cases where MATLAB does not call property set methods.

Note: Property set and get access methods are not equivalent to user-callable set and get methods used to set and query property values from an instance of the class. See "Implementing a Set/Get Interface for Properties" on page 6-23 for information on user-callable set and get methods.

Access Methods Cannot Call Other Functions to Access Property Values

You can set and get property values only from within your property set or get access method. You cannot call another function from the set or get method and attempt to access the property value from that function.

For example, an anonymous function that calls another function to do the actual work cannot access the property value. Similarly, an access function cannot call another function to access the property value.

Defining Access Methods

Access methods have special names that include the property's name. Therefore, get. *PropertyName* executes whenever *PropertyName* is referenced and set. *PropertyName* executes whenever *PropertyName* is assigned a value.

Define property access methods in a methods block that specifies no attributes. You cannot call these methods directly. MATLAB calls these methods when any code accesses the properties.

Property access methods do not appear in the list of class methods returned by the methods command and are not included in the meta.class object's Methods property.

Access Method Function Handles

The property meta.property object contains function handles to the property's set and get methods. SetMethod property contains a function handle to the property's set method and the GetMethod property contains a function handle to the property's get method.

For example, if the class MyClass defines a set function for its Text property, you can obtain a function handle to this method from the meta.class object:

```
mc = ?ClassName;
mp = findobj(mc.PropertyList, 'Name', 'PropertyName');
fh = mp.GetMethod;
```

The returned value, fh, contains a function handle to the get method defined for the specified property name for the specified class.

"Class Metadata" on page 15-2 provides more information on using meta-classes.

Function handles discusses the use of function handles.

Set and Get Method Execution and Property Events

MATLAB software generates events before and after set and get operations. You can use these events to inform listeners that property values have been referenced or assigned. The timing of event generation is as follows:

- PreGet Triggered before calling the property get method
- PostGet Triggered after the property get method has returned its value

If a class computes a property value (Dependent = true), then the behaviors of its set events are like the get events:

- PreSet Triggered before calling the property set method
- PostSet Triggered after calling the property set method

If a property is not computed (Dependent = false, the default), then the assignment statement with the set method generates the events:

- · PreSet Triggered before assigning the new property value within the set method
- PostSet Triggered after assigning the new property value within the set method

For information about using property events, see "Creating Property Listeners" on page 10-29.

Access Methods and Properties Containing Arrays

You can use array indexing with properties that contain arrays without interfering with property set and get methods.

For indexed reference:

```
val = obj.PropName(n);
```

MATLAB calls the get method to get the referenced value.

For indexed assignment:

```
obj.PropName(n) = val;
```

MATLAB:

- Invokes the get method to get the property value
- · Performs the indexed assignment on the returned property
- Passes the new property value to the set method

MATLAB always passes scalar objects to set and get methods. When reference or assignment occurs on an array, MATLAB calls the set and get methods in a loop.

See "Assigning to Read-Only Properties Containing Objects" on page 7-28 for related information.

Modify Property Values with Access Methods

Property access methods are useful in cases where you want to perform some additional steps before assigning or returning a property value. For example, the Testpoint class uses a property set method to check the range of a value. It then applies scaling if it is within a particular range, and set it to NaN if it is not.

The property get methods applies a scale factor before returning its current value:

```
classdef Testpoint
   properties
      expectedResult = [];
   properties(Constant)
      scalingFactor = 0.001;
   end
   methods
      function obj = set.expectedResult(obj,erIn)
         if erIn >= 0 && erIn <= 100
            erIn = erIn.*obj.scalingFactor;
            obj.expectedResult = erIn;
         else
            obj.expectedResult = NaN;
         end
      end
      function er = get.expectedResult(obj)
         er = obj.expectedResult/obj.scalingFactor;
      end
   end
end
```

Property Set Methods

In this section... "Overview of Property Access Methods" on page 7-19 "Property Set Method Syntax" on page 7-19 "Validate Property Set Value" on page 7-20

Overview of Property Access Methods

"Set Method Behavior" on page 7-20

For an overview of property access methods, see "Property Access Methods" on page 7-14

Property Set Method Syntax

MATLAB calls a property's set method whenever a value is assigned to the property. Property set methods have the following syntax, where *PropertyName* is the name of the property.

For a value class:

```
methods
   function obj = set.PropertyName(obj,value)
    ...
end
```

- obj Object whose property is being assigned a value
- value The new value that is assigned to the property

Value class set functions must return the modified object to the calling function. Handle classes do not need to return the modified object.

For a handle class:

```
methods
   function set.PropertyName(obj,value)
    ...
end
```

You must use default method attributes for property set methods. The methods block defining the set method cannot specify attributes.

Validate Property Set Value

Use the property set method to validate the value being assigned to the property. The property set method can perform actions like error checking on the input value before taking whatever action is necessary to store the new property value.

```
classdef MyClass
  properties
    Prop1
  end
  methods
    function obj = set.Prop1(obj,value)
        if (value > 0)
            obj.Prop1 = value;
        else
            error('Property value must be positive')
        end
        end
        end
        end
        end
        end
end
```

For an example of a property set method, see "Restrict Properties to Specific Values" on page 3-26.

Set Method Behavior

If a property set method exists, MATLAB calls it whenever a value is assigned to that property. However, MATLAB does NOT call property set methods in the following cases:

- Assigning a value to a property from within its own property set method, to prevent recursive calling of the set method. However, property assignments made from functions called by a set method do call the set method.
- Initializing default values in class definitions when loading the class
- Assigning a property to its default value that is specified in the class definition
- Copying a value object (that is, not derived from the handle class). MATLAB does not call the set or get method when copying property values from one object to another.

• Assigning a property value that is the same as the current value when the property's AbortSet attribute is true. See "Aborting Set When Value Does Not Change" on page 10-32 for more information on this attribute.

A set method for one property can assign values to other properties of the object. These assignments do call any set methods defined for the other properties. For example, a graphics window object can have a Units property and a Size property. Changing the Units property can also require a change to the values of the Size property to reflect the new units.

Property Get Methods

In this section...

"Overview of Property Access Methods" on page 7-22

"Property Get Method Syntax" on page 7-22

"Errors Not Returned from Get Method" on page 7-22

"Get Method Behavior" on page 7-22

Overview of Property Access Methods

For an overview of property access methods, see "Property Access Methods" on page 7-14

Property Get Method Syntax

MATLAB calls a property's get method whenever the property value is queried.

Property get methods have the following syntax, where *PropertyName* is the name of the property. The function must return the property value.

```
methods
    function value = get.PropertyName(obj)
    ...
end
```

Errors Not Returned from Get Method

The MATLAB default object display suppresses error messages returned from property get methods. MATLAB does not allow an error issued by a property get method to prevent the display of the entire object.

Use the property set method to validate the property value. Performing validation when setting a property ensures the object is in a valid state. Use the property get method only to return the value that has been validated by set.

Get Method Behavior

MATLAB does NOT call property get methods in the following cases:

- Getting a property value from within its own property get method, which prevents recursive calling of the get method
- Copying a value object (that is, not derived from the handle class). Neither the set or get method is called when copying property values from one object to another.

Related Examples

• "Access Methods for Dependent Properties"

Access Methods for Dependent Properties

```
In this section...

"Set and Get Methods for Dependent Properties" on page 7-24

"Get Method for Dependent Property" on page 7-25

"When to Use Set Methods with Dependent Properties" on page 7-25

"When to Use Private Set Access with Dependent Properties" on page 7-26
```

Set and Get Methods for Dependent Properties

Dependent properties do not store data because the value of a dependent property depends on the current state of something else, like a concrete property value. Dependent properties must define a get method to determine the value for the property, when queried.

Typically, the property get method queries other property values to determine what value to return for the dependent property.

For example, the Account class returns a value for the dependent Balance property that depends on the value of the Currency property. The get.Balance method queries the Currency property before calculating a value for the Balance property.

MATLAB calls the get.Balance method when the Balance property is queried. You cannot call get.Balance explicitly.

Here is a partial listing of the class showing a dependent property and its get method:

```
classdef Account
  properties
        Currency
        DollarAmount
  end
  properties (Dependent)
        Balance
  end
    ...
  methods
    function value = get.Balance(obj)
        c = obj.Currency;
        switch c
```

```
case 'E'
    v = obj.DollarAmount / 1.3;
case 'P'
    v = obj.DollarAmount / 1.5;
otherwise
    v = obj.DollarAmount;
end
format bank
value = v;
end
end
end
```

Get Method for Dependent Property

One application of a property get method is to determine the value of a property only when you need it, and avoid storing the value. To use this approach, set the property's Dependent attribute to true:

```
properties (Dependent = true)
    PropertyName
end
```

Now the get method for the *PropertyName* property determines the value of that property and assigns it to the object from within the method:

```
function value = get.PropertyName(obj)
  value = calculateValue;
  ...
end
```

The get method calls a function or static method calculateValue to calculate the property value and returns Value to the code accessing the property. The property get method can take whatever action is necessary within the method to produce the output value.

"Calculate Data on Demand" on page 3-28 provide an example of a property get method.

When to Use Set Methods with Dependent Properties

While a dependent property does not store its value, there are situations in which you might want to define a set method for a dependent property.

For example, suppose you have a class that changes the name of a property from OldPropName to NewPropName. You want to continue to allow the use of the old name without exposing it to new users. You can make OldPropName a dependent property with set and get methods as show in the following example:

```
properties
   NewPropName
end
properties (Dependent, Hidden)
   OldPropName
end
methods
   function obj = set.OldPropName(obj,val)
        obj.NewPropName = val;
   end
   function value = get.OldPropName(obj)
        value = obj.NewPropName;
   end
end
```

There is no memory wasted by storing both old and new property values, and code that accesses OldPropName continues to work as expected.

It is sometimes useful for a set method of a dependent property to assign values to other properties of the object. Assignments made from property set methods cause the execution of any set methods defined for those properties. See "Calculate Data on Demand" on page 3-28 for an example.

When to Use Private Set Access with Dependent Properties

If you use a dependent property only to return a value, then do not define a set access method for the dependent property. Instead, set the SetAccess attribute of the dependent property to private. For example, consider the following get method for the MaxValue property:

```
methods
  function mval = get.MaxValue(obj)
       mval = max(obj.BigArray(:));
  end
end
```

This example uses the MaxValue property to return a value that it calculates only when queried. For this application, define the MaxValue property as dependent and private:

properties (Dependent, SetAccess = private)
 MaxValue
end

Properties Containing Objects

```
In this section...

"Assigning to Read-Only Properties Containing Objects" on page 7-28

"Assignment Behavior" on page 7-28
```

Assigning to Read-Only Properties Containing Objects

When a class defines a property with private or protected SetAccess, and that property contains an object which itself has properties, assignment behavior depends on whether the property contains a handle or a value object:

- Handle object you can set properties on handle objects contained in read-only properties
- Value object you cannot set properties on value object contained in read-only properties.

Assignment Behavior

These classes illustrate the assignment behavior:

- ReadOnlyProps class with two read-only properties. The class constructor assigns
 a handle object of type HanClass to the PropHandle property and a value object of
 type ValClass to the PropValue property.
- HanClass handle class with public property
- ValClass value class with public property

```
classdef ReadOnlyProps
  properties(SetAccess = private)
    PropHandle
    PropValue

end
  methods
    function obj = ReadOnlyProps
        obj.PropHandle = HanClass;
        obj.PropValue = ValClass;
    end
end
```

```
end
classdef HanClass < handle</pre>
   properties
      Hprop
   end
end
classdef ValClass
   properties
      Vprop
   end
end
Create an instance of the ReadOnlyProps class:
a = ReadOnlyProps
a =
 ReadOnlyProps with properties:
    PropHandle: [1x1 HanClass]
     PropValue: [1x1 ValClass]
Use the private PropHandle property to set the property of the HanClass object it
contains:
class(a.PropHandle.Hprop)
ans =
double
a.PropHandle.Hprop = 7;
Attempting to make an assignment to the value class object property is not allowed:
a.PropValue.Vprop = 11;
You cannot set the read-only property 'PropValue' of ReadOnlyProps.
```

More About

• "Mutable and Immutable Properties"

Dynamic Properties — Adding Properties to an Instance

In this section...

"What Are Dynamic Properties" on page 7-30

"Defining Dynamic Properties" on page 7-31

"Responding to Dynamic-Property Events" on page 7-32

"Defining Property Access Methods for Dynamic Properties" on page 7-34

"Dynamic Properties and ConstructOnLoad" on page 7-35

What Are Dynamic Properties

You can attach properties to objects without defining these properties in the class definition. These dynamic properties are sometimes referred to as instance properties. Use dynamic properties to attach temporary data to objects or assign data that you want to associate with a particular instance of a class, but not all objects of that class.

It is possible for more than one program to define dynamic properties on the same object so you must take care to avoid name conflicts. Dynamic property names must be valid MATLAB identifiers (see "Variable Names") and cannot be the same name as a method of the class.

Characteristics of Dynamic Properties

Once defined, dynamic properties behave much like class-defined properties:

- Set and query the values of dynamic properties using dot notation (see "Assigning Data to the Dynamic Property" on page 7-31)
- MATLAB saves and loads dynamic properties when you save and load the objects to which they are attached (see "Save and Load Dynamic Properties" on page 12-33 and "Dynamic Properties and ConstructOnLoad" on page 7-35)
- Define attributes for dynamic property (see "Setting Dynamic Property Attributes" on page 7-31).
- Add property set and get access methods (see "Defining Property Access Methods for Dynamic Properties" on page 7-34)
- Listen for dynamic property events (see "Responding to Dynamic-Property Events" on page 7-32)
- Access dynamic property values from object arrays, with restricted syntax (see "Object Arrays with Dynamic Properties" on page 9-13)

Defining Dynamic Properties

Any class that is a subclass of the dynamic properties using the addprop method. The syntax is:

```
P = addprop(H,'PropertyName')
```

where:

P is an array of meta. Dynamic Property objects

H is an array of handles

PropertyName is the name of the dynamic property you are adding to each object

Naming Dynamic Properties

Use only valid names when naming dynamic properties (see "Variable Names"). In addition, *do not* use names that:

- Are the same as the name of a class method
- Are the same as the name of a class event
- Contain a period (.)

Setting Dynamic Property Attributes

Use the meta.DynamicProperty object associated with the dynamic property to set property attributes. For example:

```
P.Hidden = true;
```

Remove the dynamic property by deleting its meta. Dynamic Property object:

```
delete(P);
```

The property attributes Constant and Abstract have no meaning for dynamic properties and setting the value of these attributes to true has no effect.

Assigning Data to the Dynamic Property

Suppose, you are using a predefined set of user interface widget classes (buttons, sliders, check boxes, etc.). You want to store the location of each instance of the widget class. Assume the widget classes are not designed to store location data for your particular

layout scheme. You want to avoid creating a map or hash table to maintain this information separately.

Assuming the button class is a subclass of dynamic property to store your layout data. Here is a simple class to create a uicontrol button:

```
classdef button < dynamicprops</pre>
   properties
      UiHandle
   end
   methods
      function obj = button(pos)
         if nargin > 0
             if length(pos) == 4
                obj.UiHandle = uicontrol('Position',pos,...
                    'Style', 'pushbutton');
             else
                error('Improper position')
             end
         end
      end
   end
end
```

Create an instance of the button class, add a dynamic property, and set its value:

```
b1 = button([20 40 80 20]);
b1.addprop('myCoord');
b1.myCoord = [2,3];
```

Access the dynamic property just like any other property, but only on the object on which you defined it:

```
b1.myCoord
ans =
2 3
```

Responding to Dynamic-Property Events

You can attach listeners to dynamic props objects to monitor the addition of dynamic properties to the object. You can also monitor the removal of dynamic properties, which occurs when you delete the object.

The dynamicprops class defines two events and inherits one from handle:

- ObjectBeingDestroyed Inherited from the handle class.
- PropertyAdded Triggered when you add a dynamic property to an object derived from the dynamicprops class.
- PropertyRemoved Triggered when you delete the meta.DynamicProperty object associated with the dynamic property.

Suppose you define a button object, as described in the previous section:

```
b2 = button([20 40 80 20]);
```

Create a function to attach listeners to the button object, b2, and a listener callback function:

```
function listenDynoEvent(obj)
  addlistener(obj, 'PropertyAdded', @eventPR);
  addlistener(obj, 'PropertyRemoved', @eventPR);
  function eventPR(src,evnt)
    mc = metaclass(src);
    fprintf(1, '%s %s \n', mc.Name, 'object');
    fprintf(1, '%s %s \n', 'Event triggered:', evnt.EventName);
  end
end
```

Triggering the PropertyAdded Event

Add the listeners to the button object, b2. Then, add a dynamic property, myCoord.

```
listenDynoEvent(b2)
mp = b2.addprop('myCoord');
```

The listener callback function, eventPR, executes and displays the object class and event name:

```
button object
Event triggered: PropertyAdded
```

Delete the dynamic property by deleting the meta. Dynamic Property object:

```
delete(mp)
button object
```

```
Event triggered: PropertyRemoved
```

Obtain the meta. Dynamic Property object for a dynamic property using the handle findprop method. Use findprop if you do not have the object returned by addprop:

```
mp = findprop(b2, 'myCoord');
```

Dynamic Properties and Ordinary Property Events

Dynamic properties support property set and get events so you can define listeners for these properties. Listeners are bound to the particular dynamic property for which you define them.

If you delete a dynamic property, and then create another one with the same name, the listeners do not respond to events generated by the new property, even though the property has the same name as the property for which the event was defined. Having a listener defined for a deleted dynamic property does not cause an error, but the listener callback is never executed.

"Property-Set and Query Events" on page 10-14 provides more information on how to define listeners for these events.

Defining Property Access Methods for Dynamic Properties

Dynamic properties enable you to add properties to class instances without modifying class definitions. You can also define property set access or get access methods without creating new class methods. See "Property Setter and Getter Methods" on page 7-14 for more on the purpose and techniques of these methods.

Note: You can set and get the property values only from within your property access methods. You cannot call another function from the set or get method and attempt to access the property value from that function.

Here are the steps for creating a property access method:

- Define a function that implements the desired operations you want to perform before
 the property set or get occurs. These methods must have the following signatures:
 mySet(obj,val) or val = myGet(obj)
- · Obtain the dynamic property's corresponding meta. Dynamic Property object.

 Assign a function handle pointing to your set or get property function to the meta.DynamicProperty object's GetMethod or SetMethod property. This function does not need to be a method of the class and you cannot use a naming scheme like set.PropertyName. Instead, use any valid function name.

Suppose you want to create a property set function for the button class dynamic property myCoord created previously. Write the function as follows:

```
function set_myCoord(obj,val)
  if ~(length(val) == 2)
     error('myCoords require two values')
  end
  obj.myCoord = val;
end
```

Because button is a handle class, the property set function does not need to return the object as an output argument. The function assigns the value to the property if the value is valid.

Use the handle class method findprop to get the meta. Dynamic Property object:

```
mb1 = b1.findprop('myCoord');
mb1.SetMethod = @set myCoord;
```

MATLAB calls the property set function whenever you set this property:

```
b1.myCoord = [1 2 3] % length must be two
Error using button.set_myCoord
myCoords require two values
```

Dynamic Properties and ConstructOnLoad

Setting the class ConstructOnLoad attribute to true causes MATLAB to call the class constructor when loading the class. MATLAB saves and restores dynamic properties when loading an object.

If you create dynamic properties from the class constructor, you can cause a conflict if you also set the class's ConstructOnLoad attribute to true. Here is the sequence:

- · A saved object saves the names and values of properties, including dynamic properties
- When loaded, a new object is created and all properties are restored to the values at the time the object was saved

- Then, the ConstructOnLoad attribute causes a call to the class constructor, which would create another dynamic property with the same name as the loaded property (see "Save and Load Objects" on page 12-2 for more on the load sequence)
- MATLAB prevents a conflict by loading the saved dynamic property, and does not
 execute addprop when calling the constructor.

If it is necessary for you to use ConstructOnLoad and you add dynamic properties from the class constructor (and want the constructor's call to addprop to be executed at load time) then set the dynamic property's Transient attribute to true. This setting prevents the property from being saved. For example:

```
classdef (ConstructOnLoad) MyClass < dynamicprops
  function obj = MyClass
    P = addprop(obj,'DynProp');
    P.Transient = true;
    ...
end
end</pre>
```

Methods — Defining Class Operations

- "How to Use Methods" on page 8-2
- "Method Attributes" on page 8-5
- "Ordinary Methods" on page 8-7
- "Method Invocation" on page 8-9
- "Class Constructor Methods" on page 8-15
- "Static Methods" on page 8-23
- "Overload Functions for Your Class" on page 8-25
- "Class Support for Array-Creation Functions" on page 8-28
- · "Object Precedence in Methods" on page 8-37
- "Dominant Argument in Overloaded Plotting Functions" on page 8-39
- "Class Methods for Graphics Callbacks" on page 8-42

How to Use Methods

In this section...

"Class Methods" on page 8-2

"Method Naming" on page 8-3

Class Methods

Methods are functions that implement the operations performed on objects of a class. Methods, along with other class members support the concept of encapsulation—class instances contain data in properties and class methods operate on that data. This allows the internal workings of classes to be hidden from code outside of the class, and thereby enabling the class implementation to change without affecting code that is external to the class.

Methods have access to private members of their class including other methods and properties. This enables you to hide data and create special interfaces that must be used to access the data stored in objects.

See "Methods That Modify Default Behavior" on page 16-2 for a discussion of how to create classes that modify standard MATLAB behavior.

See "Class Files and Folders" on page 4-2 for information on the use of @ and path directors and packages to organize your class files.

See "Methods In Separate Files" for the syntax to use when defining classes in more than one file.

Kinds of Methods

There are specialized kinds of methods that perform certain functions or behave in particular ways:

- Ordinary methods are functions that act on one or more objects and return some new
 object or some computed value. These methods are like ordinary MATLAB functions
 that cannot modify input arguments. Ordinary methods enable classes to implement
 arithmetic operators and computational functions. These methods require an object of
 the class on which to operate. See "Ordinary Methods" on page 8-7.
- Constructor methods are specialized methods that create objects of the class. A
 constructor method must have the same name as the class and typically initializes

property values with data obtained from input arguments. The class constructor method must return the object it creates. See "Class Constructor Methods" on page 8-15

- Destructor methods are called automatically when the object is destroyed, for example if you call delete(object) or there are no longer any references to the object. See "Handle Class Destructor" on page 6-16
- *Property access methods* enable a class to define code to execute whenever a property value is queried or set. See "Property Access Methods"
- Static methods are functions that are associated with a class, but do not necessarily operate on class objects. These methods do not require an instance of the class to be referenced during invocation of the method, but typically perform operations in a way specific to the class. See "Static Methods" on page 8-23
- Conversion methods are overloaded constructor methods from other classes that
 enable your class to convert its own objects to the class of the overloaded constructor.
 For example, if your class implements a double method, then this method is called
 instead of the double class constructor to convert your class object to a MATLAB
 double object. See "Object Converters" on page 16-8 for more information.
- Abstract methods serve to define a class that cannot be instantiated itself, but serves
 as a way to define a common interface used by a number of subclasses. Classes that
 contain abstract methods are often referred to as interfaces. See "Abstract Classes" on
 page 11-80 for more information and examples.

Method Naming

The name of a function that implements a method can contain dots (for example, set.PropertyName) only if the method is one of the following:

- Property set/get access method (see "Property Access Methods" on page 7-14)
- Conversion method that converts to a package-qualified class, which requires the use
 of the package name (see "Packages Create Namespaces" on page 5-19)

You cannot define property access or conversion methods as local functions, nested functions, or separately in their own files. Class constructors and package-scoped functions must use the unqualified name in the function definition; do not include the package name in the function definition statement.

See "Defining Methods" on page 8-7 for more information on how you can define methods.

See "Rules for Naming to Avoid Conflicts" on page 8-27 for related information.

Method Attributes

In this section...

"Specifying Method Attributes" on page 8-5

"Table of Method Attributes" on page 8-5

Specifying Method Attributes

Assign method attributes on the same line as the methods keyword:

```
methods (Attribute1 = value1, Attribute2 = value2,...)
   ...
end
```

For more information on attribute syntax, see "Attribute Specification".

Table of Method Attributes

Attributes enable you to modify the behavior of methods. All methods support the attributes listed in the following table.

Attribute values apply to all methods defined within the methods...end code block that specifies the nondefault values.

Method Attributes

Attribute Name	Class	Description
Abstract	logical Default = false	If true, the method has no implementation. The method has a syntax line that can include arguments, which subclasses use when implementing the method:
		• Subclasses are not required to define the same number of input and output arguments. However, subclasses generally use the same signature when implementing their version of the method.
		• The method can have comments after the function line.
		 The method does not contain function or end keywords, only the function syntax (e.g., [a,b] = myMethod(x,y))

Attribute Name	Class	Description
Access	 enumeration, default = public meta.class object cell array of meta.class objects 	 Determines what code can call this method: public — Unrestricted access protected — Access from methods in class or subclasses private — Access by class methods only (not from subclasses) List classes that have access to this method. Specify classes as meta.class objects in the form: A single meta.class object A cell array of meta.class objects. An empty cell array, {}, is the same as private access. See "Control Access to Class Members" on page 11-25
Hidden	logical Default = false	When false, the method name shows in the list of methods displayed using the methods or methodsview commands. If set to true, the method name is not included in these listings and ismethod does not return true for this method name.
Sealed	logical Default = false	If true, the method cannot be redefined in a subclass. Attempting to define a method with the same name in a subclass causes an error.
Static	logical Default = false	on an object of the class and does not require an object argument. Use the class name to call the method: classname.methodname or an instance of the class: obj.methodname
		"Static Methods" on page 8-23 provides more information.

Ordinary Methods

```
In this section...

"Defining Methods" on page 8-7

"Multi-File Classes" on page 8-8
```

Defining Methods

You can specify methods:

- · Inside of a class definition block
- In a separate file in the class folder (that is, @ClassName)

Methods Inside classdef Block

This example shows the definition of a method (the compute function in this example) within the classdef and methods blocks:

```
classdef ClassName
  methods (AttributeName = value,...)
    function x = compute(obj,inc)
        x = obj.y + inc;
    end % compute method
...
  end % methods block
...
end % classedf
```

Note: Nonstatic methods must include an explicit object variable in the function definition. The MATLAB language does not support an implicit reference in the method function definition.

Either of the following statements is correct syntax for calling a method where obj is an object of the class defining the compute method:

```
obj.compute(inc)
compute(obj,inc)
```

Method attributes apply only to that particular methods block, which is terminated by the end statement.

Multi-File Classes

You can define class methods in separate files within the class folder. In this case, create a function in a separate file having the same name as the function (i.e., <code>functionname.m</code>). If you want to specify attribute values for that method, you must declare the method signature within a methods block in the <code>classdef</code> block . For example:

```
classdef myClass
   methods (AttributeName = value,...)
     tdata = testdata(obj,arg1,arg2)
...
   end % methods
...
end % classdef
```

Do not use methods blocks in the separate files. Define the method as a function. Using the example above, the file testdata.m, must contain the definition of the testdata function. Note that the signatures must match.

```
function tdata = testdata(myClass_object,argument2,argument3)
   ...
end
```

The following limitations apply to methods defined in separate files:

- If you want to specify attributes for a method defined in a separate file, you must declare this method in a methods block (specifying attribute values) within the classdef block.
- The syntax declared in the methods block (if used) must match the method's function line.
- The separate file must be in the class folder.
- The constructor method must be defined within the classdef block and, therefore, cannot be in a separate file.
- Set and get property access methods must be defined within the classdef block and, therefore, cannot be in separate files.

More About

- "Methods In Separate Files"
- · "Determining Which Method Is Invoked"

Method Invocation

In this section...

"Determining Which Method Is Invoked" on page 8-9

"Referencing Names with Expressions—Dynamic Reference" on page 8-11

"Controlling Access to Methods" on page 8-12

"Invoking Superclass Methods in Subclass Methods" on page 8-13

"Invoking Built-In Functions" on page 8-14

Determining Which Method Is Invoked

When the MATLAB runtime invokes an ordinary method that has an argument list, it uses the following criteria to determine which method to call

- The class of the left-most argument whose class is not specified as inferior to any
 other argument's class is chosen as the dominant class and its method is invoked.
- If this class does not define the named method, then a function with that name on the MATLAB path is invoked.
- If no such function exists, MATLAB issues an error indicating that the dominant class does not define the named method

Dominant Argument

The dominant argument in a method's argument list determines which version of the method or function that the MATLAB runtime calls. Dominance is determined by the relative precedences of the classes of the arguments. In general, user-defined classes take precedence over built-in MATLAB classes. Therefore, the left most argument determines which method to call. However, user-defined classes can specify the relative dominance of specific classes.

For example, suppose classA defines classB as inferior and suppose both classes define a method called combine.

Calling the method with an object of classB and classA:

combine(B,A)

actually calls the combine method of classA because A is the dominant argument.

Dot Notation vs. Function Notation

MATLAB classes support both function and dot notation syntax for calling methods. For example, if setColor is a method of the class of object X, then calling setColor with function notation would be:

```
X = setColor(X, 'red');
```

The equivalent method call using dot notation is:

```
X = X.setColor('red')
```

However, in certain cases, the results for dot notation can differ with respect to how MATLAB dispatching works:

- If there is an overloaded subsref, it is invoked whenever using dot-notation. That is, the statement is first tested to see if it is subscripted assignment.
- If there is no overloaded subsref, then setColor must be a method of X. An ordinary function or a class constructor is never called using this notation.
- Only the argument X (to the left of the dot) is used for dispatching. No other
 arguments, even if dominant, are considered. Therefore dot notation can call only
 methods of X; methods of other argument are never called.

Case Where Result is Different

Here is an example of a case where dot and function notation can give different results. Suppose you have the following classes:

- classA defines a method called methodA that requires an object of classB as one of its arguments
- classB defines classA as inferior to classB

```
classdef classB (InferiorClasses = {?classA})
   ...
end
```

The methodA method is defined with two input arguments, one of which is an object of classB:

```
classdef classA
methods
  function methodA(obj,obj_classB)
```

```
end
end
```

classB does not define a method with the same name as methodA. Therefore, the following syntax causes the MATLAB runtime to search the path for a function with the same name as methodA because the second argument is an object of a dominant class. If a function with that name exists on the path, then MATLAB attempts to call this function instead of the method of classA and most likely returns a syntax error.

```
obj = classA(...);
methodA(obj,obj classB)
```

Dot notation is stricter in its behavior. For example, this call to methodA:

```
obj = classA(...);
obj.methodA(obj classB)
```

can call only methodA of the class of obj.

Referencing Names with Expressions – Dynamic Reference

You can reference an object's properties or methods using an expression in dotparentheses syntax:

```
obj.(expression)
```

The expression must evaluate to a string that is the name of a property or a method. For example, the following statements are equivalent:

```
obj.Property1
obj.('Property1')
```

In this case, **obj** is an object of a class that defines a property called **Property1**. Therefore, you can pass a string variable in the parentheses to reference to property:

```
propName = 'Property1';
obj.(propName)
```

You can call a method and pass input arguments to the method using another set of parentheses:

```
obj.(expression)(arg1,arg2,...)
```

Using this notation, you can make dynamic references to properties and methods in the same way you can create dynamic references to the fields of structs.

As an example, suppose an object has methods corresponding to each day of the week. These methods have the same names as the days of the week (Monday, Tuesday, and so on). Also, the methods take as string input arguments, the current day of the month (the date). Now suppose you write a function in which you want to call the correct method for the current day.

Use an expression created with the date and datestr functions:

```
obj.(datestr(date,'dddd'))(datestr(date,'dd'))
The expression datestr(date,'dddd') returns the current day as a string. For example:
datestr(date,'dddd')
ans =
Tuesday
The expression datestr(date,'dd') returns the current date as a string. For example:
datestr(date,'dd')
ans =
11
```

Therefore, the expression using dot-parentheses (called on Tuesday the $11^{\rm th}$) is the equivalent of:

```
obj.Tuesday('11')
```

Controlling Access to Methods

There might be situations where you want to create methods for internal computation within the class, but do not want to publish these methods as part of the public interface to the class. In these cases, you can use the Access attribute to set the access to one of the following options:

• public — Any code having access to an object of the class can access this method (the default).

- private Restricts method access to the defining class, excluding subclasses. Subclasses do not inherit private methods.
- protected Restricts method access to the defining class and subclasses derived from the defining class. Subclasses inherit this method.

Local and nested functions inside the method files have the same access as the method. Note that local functions inside a class-definition file have private access to the class defined in the same file.

Invoking Superclass Methods in Subclass Methods

A subclass can override the implementation of a method defined in a superclass. In some cases, the subclass method might need to execute some additional code instead of completely replacing the superclass method. To do this, MATLAB classes can use a special syntax for invocation of superclass methods from a subclass implementation for the same-named method.

The syntax to call a superclass method in a subclass class uses the @ symbol:

MethodName@SuperclassName

For example, the following disp method is defined for a Stock class that is derived from an Asset class. The method first calls the Asset class disp method, passing the Stock object so that the Asset components of the Stock object can be displayed. After the Asset disp method returns, the Stock disp method displays the two Stock properties:

```
classdef Stock < Asset
  methods
    function disp(s)
        disp@Asset(s) % Call base class disp method first
        fprintf(1,'Number of shares: %g\nShare price: %3.2f\n',...
        s.NumShares,s.SharePrice);
    end % disp
  end
end</pre>
```

Limitations of Use

The following restrictions apply to calling superclass methods. You can use this notation only within:

- · A method having the same name as the superclass method you are invoking
- · A class that is a subclass of the superclass whose method you are invoking

Invoking Built-In Functions

The MATLAB builtin function enables you to call the built-in version of a function that has been overloaded by a method.

Class Constructor Methods

In this section...

"Rules for Constructors" on page 8-15

"Related Information" on page 8-16

"Initializing Objects In Constructor" on page 8-16

"No Input Argument Constructor Requirement" on page 8-17

"Constructing Subclasses" on page 8-18

"Errors During Class Construction" on page 8-20

"Basic Structure of Constructor Methods" on page 8-21

Rules for Constructors

A constructor method is a special function that creates an instance of the class. Typically, constructor methods accept input arguments to assign the data stored in properties and always return an initialized object.

- The constructor has the same name as the class.
- · The only output argument from a constructor is the object constructed.
- The constructor can return only a single argument.
- Constructors must always return a valid instance of the class. Never return an empty object from a class constructor.
- If the class being created is a subclass, MATLAB calls the constructor of each
 superclass class to initialize the object. Implicit calls to the superclass constructor are
 made with no arguments. If superclass constructors require arguments, you must call
 them from the subclass constructor explicitly.
- If your constructor makes an explicit call to a superclass constructor, this call must occur before any other reference to the constructed object.
- A class does not need to define a constructor method unless it is a subclass of a superclass whose constructor requires arguments. In this case, you must explicitly call the superclass constructor with the required arguments. See "Constructing Subclasses" on page 8-18
- If a class does not define a constructor, MATLAB supplies a constructor that takes no arguments and returns a scalar object whose properties are initialized to empty or the

values specified as defaults in the property definitions. The constructor supplied by MATLAB also calls all superclass constructors with no arguments.

- If you create a class constructor, you should implement class constructors so that they can be called with no input arguments, in addition to whatever arguments are normally required See "No Input Argument Constructor Requirement" on page 8-17.
- Constructor functions must return an instance of the constructor's class. The constructor should avoid assigning to the constructor output argument because subclasses often call a superclass constructor in the process of creating an instance of the subclass.
- Calls to superclass constructors cannot be conditional. This means superclass
 construction calls cannot be placed in loops, conditions, switches, try/catch, or nested
 functions. See "No Conditional Calls to Superclass Constructors" on page 8-19 for
 more information.
- Restrict access to constructors using method attributes, as with any method.

Related Information

See "Constructor Calling Sequence" on page 13-10 for information specific to constructing enumerations.

Initializing Objects In Constructor

Constructor methods must return an initialized object as the only output argument. The output argument is created when the constructor executes, before executing the first line of code.

For example, the following constructor function can assign the value of the object's property A as the first statement because the object Obj has already been assigned to an instance of myClass.

```
function obj = myClass(a,b,c)
  obj.A = a;
end
```

You can call other class methods from the constructor because the object is already initialized.

The constructor also creates an object whose properties have their default values—either empty ([]) or the default value specified in the property definition block.

For example, the following code calls the class method CalculateValue to assign the value of the property Value.

```
function obj = myClass(a,b,c)
  obj.Value = obj.CalculateValue(a,b);
    ...
end
```

Referencing the Object in a Constructor

When initializing the object, for example, by assigning values to properties, you must use the name of the output argument to refer to the object within the constructor. For example, in the following code the output argument is **Obj** and the object is reference as **Obj**:

```
% obj is the object being constructed
function obj = myClass(arg)
  obj.propert1 = arg*10;
  obj.method1;
    ...
end
```

For more information on defining default property values, see "Defining Default Values" on page 4-12.

No Input Argument Constructor Requirement

There are cases where the constructor must be able to be called with no input argument:

- When loading objects into the workspace. If the class ConstructOnLoad attribute is set to true, the load function calls the class constructor with no arguments.
- When creating or expanding an object array such that not all elements are given specific values, the class constructor is called with no arguments to fill in unspecified elements, (for example, X(10,1) = myclass(a,b,c);). In this case, the constructor is called once with no arguments to populate the empty array elements with copies of this one object.

If there are no input arguments, the constructor creates an object using only default properties values. A good practice is to always add a check for zero arguments to the class constructor to prevent an error if either of the two cases above occur:

```
function obj = myClass(a,b,c)
  if nargin > 0
    obj.A = a;
    obj.B = b;
    obj.C = c;
    end
end
```

For ways to handle superclass constructors, see "Basic Structure of Constructor Methods" on page 8-21.

Constructing Subclasses

Subclass constructor functions must explicitly call superclass constructors if the superclass constructors require input arguments. The subclass constructor must specify these arguments in the call to the superclass constructor using the constructor output argument. Here is the syntax:

```
classdef MyClass < SuperClass
  function obj = MyClass(arg)
     obj@SuperClass(ArgumentList);
     ...
end
end</pre>
```

The class constructor must make all calls to superclass constructors before any other references to the object. These changes include assigning property values or calling ordinary class methods. Also, a subclass constructor can call a superclass constructor only once.

Reference Only Specified Superclasses

If the classdef does not specify the class as a superclass, the constructor cannot call a superclass constructor with this syntax .

```
classdef MyClass < SuperClass</pre>
```

MATLAB calls any uncalled constructors in the left-to-right order in which they are specified in the classdef line. MATLAB passes no arguments to these functions.

No Conditional Calls to Superclass Constructors

Calls to superclass constructors must be unconditional. There can be only one call for a given superclass. Initialize the superclass portion of the object by calling the superclass constructors before using the object (for example, to assign property values or call class methods).

If you must call superclass constructors with different arguments that depend on some condition, you can build a cell array of arguments and provide one call to the constructor.

For example, the Cube class constructor calls the superclass Shape constructor using default values when the Cube constructor is called with no arguments. If the Cube constructor is called with four input arguments, upvector and viewangle can be passed to the superclass constructor:

```
classdef Cube < Shape</pre>
   properties
      SideLength = 0;
      Color = [0 \ 0 \ 0];
   end
   methods
      function cubeObj = Cube(length,color,upvector,viewangle)
         if nargin == 0
            super args{1} = [0 \ 0 \ 1];
            super args{2} = 10;
         elseif nargin == 4
            super args{1} = upvector;
            super args{2} = viewangle;
         else
            error('Wrong number of input arguments')
         cubeObj@Shape(super args{:});
         if nargin > 0 % Use value if provided
            cubeObj.SideLength = length;
            cubeObj.Color = color;
         end
      end
   end
end
```

Zero or More Superclass Arguments

If you must support the syntax that calls the superclass constructor with no arguments, provide this syntax explicitly.

Suppose in the case of the Cube class example, all property values in the Shape superclass and the Cube subclass have default values specified in the class definitions. Then you can create an instance of Cube without specifying any arguments for the superclass or subclass constructors.

Here is how you can implement this behavior in the Cube constructor:

methods

```
function cubeObj = Cube(length,color,upvector,viewangle)
      if nargin == 0
         super args = {};
      elseif nargin == 4
         super args{1} = upvector;
         super args{2} = viewangle;
      else
         error('Wrong number of input arguments')
      end
      cubeObj@Shape(super args{:});
      if nargin > 0
         cubeObj.SideLength = length;
         cubeObj.Color = color;
      end
   end
end
```

More on Subclasses

See "Creating Subclasses — Syntax and Techniques" on page 11-7 for information on creating subclasses.

Errors During Class Construction

If an error occurs during the construction of a handle class, the MATLAB class system calls the class destructor on the object along with the destructors for any objects contained in properties and any initialized base classes.

For information on how objects are destroyed, see "Handle Class Destructor" on page 6-16.

Basic Structure of Constructor Methods

It is important to consider the state of the object under construction when writing your constructor method. Constructor methods can be structured into three basic sections:

- Pre-initialization Compute arguments for superclass constructors.
- Object initialization Call superclass constructors.
- Post initialization Perform any operations related to the subclass, including referencing and assigning to the object, call class methods, passing the object to functions, and so on.

This code illustrates the basic operations performed in each section:

```
classdef myClass < baseClass1</pre>
  properties
      ComputedValue
  end
  methods
      function obj = myClass(a,b,c)
%% Pre Initialization %%
% Any code not using output argument (obj)
         if nargin == 0
         % Provide values for superclass constructor
         % and initialize other inputs
            a = someDefaultValue;
            args{1} = someDefaultValue;
            args{2} = someDefaultValue;
         else
           % When nargin ~= 0, assign to cell array,
           % which is passed to supclass constructor
            args{1} = b;
            args{2} = c;
         compvalue = myClass.staticMethod(a);
5% Object Initialization
% Call superclass constructor before accessing object
% You cannot conditionalize this statement
         obj = obj@baseClass1(args{:});
%% Post Initialization %%
% Any code, including access to object
        obj.classMethod(...);
         obj.ComputedValue = compvalue;
     end
  end
end
```

See for information on creating object arrays in the constructor.

Related Examples

- "Simplifying the Interface with a Constructor" on page 3-27
- "Constructor Arguments and Object Initialization" on page 11-9

Static Methods

```
In this section...

"Why Define Static Methods" on page 8-23

"Calling Static Methods" on page 8-23
```

Why Define Static Methods

Static methods are associated with a class, but not with specific instances of that class. These methods do not perform operations on individual objects of a class and, therefore, do not require an instance of the class as an input argument, like ordinary methods.

Static methods are useful when you do not want to first create an instance of the class before executing some code. For example, you might want to set up the MATLAB environment or use the static method to calculate data needed to create class instances.

Suppose a class needs a value for pi calculated to particular tolerances. The class could define its own version of the built-in pi function for use within the class. This approach maintains the encapsulation of the class's internal workings, but does not require an instance of the class to return a value.

Defining a Static Method

To define a method as static, set the methods block **Static** attribute to **true**. For example:

```
classdef MyClass
    ...
    methods(Static)
        function p = pi(tol)
            [n d] = rat(pi,tol);
            p = n/d;
        end
    end
end
```

Calling Static Methods

Invoke static methods using the name of the class followed by dot (.), then the name of the method:

```
classname.staticMethodName(args,...)
```

Calling the pi method of MyClass in the previous section would require this statement:

```
value = MyClass.pi(.001);
```

You can also invoke static methods using an instance of the class, like any method:

```
obj = MyClass;
value = obj.pi(.001);
```

Inheriting Static Methods

Subclasses can redefine static methods unless the method's Sealed attribute is also set to true in the superclass.

Related Examples

"Implementing the AccountManager Class"

Overload Functions for Your Class

In this section...

"Overloading MATLAB Functions" on page 8-25

"Rules for Naming to Avoid Conflicts" on page 8-27

Overloading MATLAB Functions

Class methods can provide implementations of MATLAB functions that operate only on instances of the class. This is possible because MATLAB software can always identify to which class an object belongs.

MATLAB uses the dominant argument to determine which version of a function to call. If the dominant argument is an object, then MATLAB calls the method defined by the object's class, if one exists.

In cases where a class defines a method with the same name as a global function, the class's implementation of the function is said to *overload* the original global implementation.

To overload a MATLAB function:

- Define a method with the same name as the function you want to overload.
- Ensure the method argument list accepts an object of the class, which MATLAB uses to determine which version to call.
- Perform the necessary steps in the method to implement the function. For example, access the object properties to manipulate data, and so on.

Generally, the method that overloads a function produces results similar to the MATLAB function. However, there are no requirements with regard to how you implement the overloading method.

Note: MATLAB does not support overloading functions using different signatures for the same function name.

Overload the bar Function

It is convenient to overload commonly used functions to work with objects of your class. For example, suppose a class defines a property that stores data that you often graph. The MyData class overrides the bar function and adds a title to the graph:

```
classdef MyData
   properties
      Data
   end
   methods
      function obj = MyData(d)
         if nargin > 0
            obj.Data = d;
      end
      function bar(obj)
         y = obj.Data;
         bar(y, 'EdgeColor', 'r');
         title('My Data Graph')
      end
   end
end
```

The MyData bar method has the same name as the MATLAB bar function. However, the MyData bar method requires a MyData object as input. Because the method is specialized for MyData objects, it can extract the data from the Data property and create a specialized graph.

To use the bar method, create an object:

```
y = rand(1,10);
md = MyData(y);
```

Call the method using the object:

bar(md)

You can also use dot notation:

md.bar

Implementing MATLAB Operators

Classes designed to implement new MATLAB data types typically define certain operators, such as addition, subtraction, equality, and so on.

For example, standard MATLAB addition (+) cannot add two polynomials because this operation is not defined by simple addition. However, a polynomial class can define its own plus method that the MATLAB language calls to perform addition of polynomial objects when you use the + symbol:

p1 + p2

Rules for Naming to Avoid Conflicts

The names of methods, properties, and events are scoped to the class. Therefore, you should adhere to the following rules to avoid naming conflicts:

- You can reuse names that you have used in unrelated classes.
- You can reuse names in subclasses if the member does not have public or protected access. These names then refer to entirely different methods, properties, and events without affecting the superclass definitions
- Within a class, all names exist in the same name space and must be unique. A class cannot define two methods with the same name and a class cannot define a local function with the same name as a method.
- The name of a static method is considered without its class prefix. Thus, a static method name without its class prefix cannot match the name of any other method.

Related Examples

- "Define Arithmetic Operators" on page 18-21
- "Class Operator Implementations" on page 16-37
- "Methods That Modify Default Behavior" on page 16-2

Class Support for Array-Creation Functions

```
In this section...

"Extend Array-Creation Functions for Your Class" on page 8-28

"Which Syntax to Use" on page 8-29

"Implement Support for Array-Creation Functions" on page 8-30
```

Extend Array-Creation Functions for Your Class

There are a number of MATLAB functions that create arrays of a specific size and type, such as ones and zeros. User-defined classes can add support for array-creation functions without requiring the use of overloaded method syntax.

Class support for any of the array-creation functions enables you to develop code that you can share with built-in and user-defined data types. For example, the class of the variable x in the following code can be a built-in type during initial development, and then be replaced by a user-defined class that transparently overloads zeros:

```
cls = class(x);
zArray = zeros(m,n,cls);
```

Array-creation functions create arrays of a specific type in two ways:

- Class name syntax Specify class name that determines the type of array elements.
- Prototype object syntax Provide a prototype object that the function uses to determine the type and other characteristics of the array elements.

For example:

```
zArray = zeros(2,3,'uint8');

p = uint8([1 3 5 ; 2 4 6]);

zArray = zeros(2,3,'like',p);
```

After adding support for these functions to a class named MyClass, you can use similar syntax with that class:

```
zArray = zeros(2,3,'MyClass');
```

Or pass an object of your class:

```
p = MyClass(...);
zArray = zeros(size(p), 'like',p);
```

MATLAB uses these arguments to dispatch to the appropriate method in your class.

Array-Creation Functions That Support Overloading

The following functions support this kind of overloading.

Array-Creation Functions
ones
zeros
eye
nan (lower case)
inf
true
false
cast
rand
randn
randi

Which Syntax to Use

If you want to create an array of default objects, which require no input arguments for the constructor, then use the class name syntax.

If you need to create an array of objects with specific property values or if the constructor needs other inputs, use the prototype object to provide this information.

Classes can support both the class name and the prototype object syntax.

You can implement a class name syntax with the true and false functions even though these functions do not support that syntax by default.

Class Name Method Called If Prototype Method Does Not Exist

If your class implements a class name syntax, but does not implement a prototype object syntax for a particular function, you can still call both syntaxes. For example, if you implement a static zeros method only, you can call:

```
zeros(...,'like',MyClass(...))
```

In the case in which you call the prototype object syntax, MATLAB first searches for a method named zerosLike. If MATLAB cannot find this method, it calls for the zeros static method.

This feature is useful if you only need the class name to create the array. You do not need to implement both methods to support the complete array-creation function syntax. When you implement only the class name syntax, a call to a prototype object syntax is the same as the call to the class name syntax.

Implement Support for Array-Creation Functions

Use two separate methods to fully support an array-creation function. One method implements the class name syntax and the other implements the prototype object syntax.

For example, to support the zeros function:

Implement the class name syntax:

```
zeros(..., 'ClassName')
As a Static method:
methods (Static)
  function z = zeros(varargin)
    ...
  end
end
```

Implement the prototype object syntax:

```
zeros(..., 'like',obj)

As a Hidden method with the string 'Like' appended to the name.
```

```
methods (Hidden)
  function z = zerosLike(obj,varargin)
```

```
end
end
```

How MATLAB Interprets the Function Call

The special support for array-creation functions results from the interpretation of the syntax.

• A call to the zeros function of this form:

```
zeros(..., 'ClassName')
Calls the class static method like this:
ClassName.zeros(varargin{1:end-1})
• A call to the zeros function of this form:
zeros(..., 'like',obj)
Calls the class method like this:
zerosLike(obj,varargin{1:end-2})
```

Support All Function Inputs

The input arguments to an array-creation function can include the dimensions of the array the function returns and possibly other arguments. In general, there are three cases that your methods need to support:

· No dimension input arguments resulting in the return of a scalar. For example:

```
z = zeros('MyClass');
```

• One or more dimension equal to or less than zero, resulting in an empty array. For example:

```
z = zeros(2,0, 'MyClass');
```

Any number of valid array dimensions specifying the size of the array. For example:

```
z = zeros(2,3,5, 'MyClass');
```

When the array-creation function calls your class method, it passes the input arguments, excluding the class name or the literal 'like' and the object variable to your method. This enables you to implement your methods with signatures like these:

- · zeros(varargin) for "class name" methods
- · zeros(obj, varargin) for "like prototype object" methods

Sample Class

The Color class represents a color in a specific color space, such as RGB, HSV, and so on. The discussions in "Class Name Method Implementations" on page 8-32 and "Prototype Object Method Implementation" on page 8-34 use this class as a basis for the overloaded method implementations.

```
classdef Color
  properties
      ColorValues = [0,0,0];
      ColorSpace = 'RGB';
end
methods
    function obj = Color(cSpace,values)
      if nargin > 0
        obj.ColorSpace = cSpace;
        obj.ColorValues = values;
      end
    end
end
end
```

Class Name Method Implementations

The zeros function strips the final *ClassName* string and uses it to form the call to the static method in the Color class. The arguments passed to the static method are the array dimension arguments.

Here is an implementation of a zeros method for the Color class. This implementation:

- Defines the zeros method as Static (required)
- Returns a scalar Color object if the call to zeros has no dimension arguments
- Returns an empty array if the call to zeros has any dimensions arguments equal to 0.
- Returns an array of default Color objects. Use repmat to create an array of the dimensions specified by the call to zeros.

```
methods (Static)
  function z = zeros(varargin)
```

```
if (nargin == 0)
% For zeros('Color')
    z = Color;
elseif any([varargin{:}] <= 0)
% For zeros with any dimension <= 0
    z = Color.empty(varargin{:});
else
% For zeros(m,n,...,'Color')
% Use property default values
    z = repmat(Color,varargin{:});
end
end</pre>
```

The zeros method uses default values for the ColorValues property because these values are appropriate for this application. An implementation of a ones method might set the ColorValues property to [1,1,1].

Suppose you want to overload the randi function to achieve the following objectives:

- Define each ColorValue property as a 1-by-3 array in the range of 1 to a specified maximum value (for example, 1 to 255).
- · Accommodate scalar, empty, and multidimensional array sizes.
- Return an array of Color objects of the specified dimensions, each with random ColorValues.

```
methods (Static)
   function r = randi(varargin)
      if (nargin == 0)
         % For randi('ClassName')
         r = Color(RGB', randi(255, [1,3]));
      elseif any([varargin{2:end}] <= 0)</pre>
         % For randi with any dimension <= 0
         r = Color.empty(varargin{2:end});
      else
         % For randi(max,m,n,..., 'ClassName')
         if numel([varargin{:}]) < 2</pre>
            error('Not enough input arguments')
         end
         dims = [varargin{2:end}];
         r = zeros(dims, 'Color');
         for k = 1:prod(dims)
            r(k) = Color(RGB', randi(varargin\{1\}, [1,3]));
```

```
end
end
end
```

Prototype Object Method Implementation

The objective of a method that returns an array of objects that are "like a prototype object" depends on the requirements of the class. For the Color class, the zeroLike method creates objects that have the ColorSpace property value of the prototype object, but the ColorValues are all zero.

Here is an implementation of a zerosLike method for the Color class. This implementation:

- Defines the zerosLike method as Hidden
- Returns a scalar Color object if the call to the zeros function has no dimension arguments
- Returns an empty array if the call to the **zeros** function has any dimension arguments that are negative or equal to 0.
- Returns an array of Color objects of the dimensions specified by the call to the zeros function.

```
methods (Hidden)
   function z = zerosLike(obj,varargin)
      if nargin == 1
         % For zeros('like',obj)
         cSpace = obj.ColorSpace;
         z = Color;
         z.ColorSpace = cSpace;
      elseif any([varargin{:}] <= 0)</pre>
         % For zeros with any dimension <= 0
         z = Color.empty(varargin{:});
      else
         % For zeros(m,n,...,'like',obj)
         if ~isscalar(obj)
            error('Prototype object must be scalar')
         obj = Color(obj.ColorSpace,zeros(1,3,'like',obj.ColorValues));
         z = repmat(obj,varargin{:});
      end
   end
```

end

Full Class Listing

Here is the Color class definition with the overloaded methods.

Note: In actual practice, the Color class requires error checking, color space conversions, and so on. This overly simplified version illustrates the implementation of the overloaded methods.

```
classdef Color
   properties
      ColorValues = [0,0,0];
      ColorSpace = 'RGB';
   end
   methods
      function obj = Color(cSpace, values)
         if nargin > 0
            obj.ColorSpace = cSpace;
            obj.ColorValues = values;
         end
      end
   end
   methods (Static)
      function z = zeros(varargin)
         if (nargin == 0)
            % For zeros('ClassName')
            z = Color;
         elseif any([varargin{:}] <= 0)</pre>
            % For zeros with any dimension <= 0
            z = Color.empty(varargin{:});
         else
            % For zeros(m,n,..., 'ClassName')
            % Use property default values
            z = repmat(Color, varargin{:});
         end
      end
      function r = randi(varargin)
         if (nargin == 0)
            % For randi('ClassName')
            r = Color(RGB', randi(255, [1,3]));
         elseif any([varargin{2:end}] <= 0)</pre>
```

```
% For randi with any dimension <= 0
            r = Color.empty(varargin{2:end});
         else
            % For randi(max,m,n,..., 'ClassName')
            if numel([varargin{:}]) < 2</pre>
               error('Not enough input arguments')
            end
            dims = [varargin{2:end}];
            r = zeros(dims, 'Color');
            for k = 1:prod(dims)
               r(k) = Color(RGB', randi(varargin\{1\}, [1,3]));
            end
         end
      end
   end
   methods (Hidden)
      function z = zerosLike(obj,varargin)
         if nargin == 1
            % For zeros('like',obj)
            cSpace = obj.ColorSpace;
            z = Color;
            z.ColorSpace = cSpace;
         elseif any([varargin{:}] <= 0)</pre>
            % For zeros with any dimension <= 0
            z = Color.empty(varargin{:});
         else
            % For zeros(m,n,...,'like',obj)
            if ~isscalar(obj)
               error('Prototype object must be scalar')
            end
            obj = Color(obj.ColorSpace,zeros(1,3,'like',obj.ColorValues));
            z = repmat(obj,varargin{:});
         end
      end
   end
end
```

Object Precedence in Methods

Establishing an object precedence enables the MATLAB runtime to determine which of possibly many versions of an operator or function to call in a given situation.

For example, consider the expression

```
objectA + objectB
```

Ordinarily, objects have equal precedence and the method associated with the left-most object is called. However, there are two exceptions:

- User-defined classes have precedence over MATLAB fundamental classes (see "Fundamental MATLAB Classes") and certain built-in classes.
- User-defined classes can specify their relative precedence with respect to other userdefined classes using the InferiorClasses attribute.

In "Class Design for Polynomials" on page 18-2, the polynom class defines a plus method that enables the addition of DocPolynom objects. Given the object p:

calls the DocPolynom plus method (which converts the double, 1, to a DocPolynom object and then implements the addition of two polynomials). The user-defined DocPolynom class has precedence over the built-in double class.

Specifying Precedence of User-Defined Classes

You can specify the relative precedence of user-defined classes by listing inferior classes using a class attribute. The InferiorClasses property places a class below other classes in the precedence hierarchy. Define the InferiorClasses property in the classdef statement:

```
classdef (InferiorClasses = {?class1,?class2}) myClass
```

This attribute establishes a relative priority of the class being defined with the order of the classes listed.

Location in the Hierarchy

If objectA is above objectB in the precedence hierarchy, then the expression

objectA + objectB

calls @classA/plus.m. Conversely, if objectB is above objectA in the precedence hierarchy, then the MATLAB runtime calls @classB/plus.m.

More About

• "Rules for Naming to Avoid Conflicts" on page 8-27

Dominant Argument in Overloaded Plotting Functions

In this section...

"Graphics Object Precedence" on page 8-39

"Dominant Argument" on page 8-39

"Defining Class Precedence" on page 8-39

"Calls to Inferior-Class Methods" on page 8-41

Graphics Object Precedence

MATLAB graphics objects have the same precedence as user-defined objects. If you want to implement a method that accepts a graphics object as its first argument (for example, an axes handle), you must define the MATLAB graphics class as inferior to your class.

Dominant Argument

When evaluating expression involving objects of more than one class, MATLAB uses the dominant argument to determine which method or function to call.

Here is how MATLAB dispatches in response to a function call:

- · Determine the dominant argument based on the class of arguments.
- · If there is a dominant argument, call the method of the dominant class.
- If arguments are of equal precedence, use the left-most argument as the dominant argument.
- If the class of the dominant argument does not define a method with the name of the called function, call the first function on the path with that name.

Defining Class Precedence

Specify the relative precedence of MATLAB classes using the InferiorClasses class attribute. Here is the basic syntax:

```
classdef (InferiorClasses = {?class1,?class2}) ClassName
```

The following definition of the TemperatureData class implements a specialized version of plot to graph temperature data. The class plot method supports a variable number of input arguments to allow an axes handle as the first argument:

```
plot(obj)
plot(ax,obj)
```

obj is an instance of the TemperatureData class and ax is an axes handle.

MATLAB calls the plot method in both cases because the TemperatureData class specifies the matlab.graphics.axis.Axes as inferior.

```
classdef (InferiorClasses = {?matlab.graphics.axis.Axes}) TemperatureData
   properties
      Time
      Temperature
   end
   methods
      function obj = TemperatureData(x,y)
         obj.Time = x;
         obj.Temperature = y;
      end
      function plot(varargin)
         if nargin == 1
            obj = varargin{1};
            plot(obj.Time,obj.Temperature)
         elseif nargin == 2
            ax = varargin\{1\};
            obj = varargin{2};
            plot(ax,obj.Time,obj.Temperature)
         elseif nargin > 2
            ... % Implement additional syntax
         end
         xlabel('Time')
         ylabel('Temperature')
      end
   end
end
```

The following call to plot dispatches to the TemperatureData plot method, not the built-in plot function, because the TemperatureData object is dominant over the axes object.

```
x = 1:10;
y = rand(1,10)*100;
ax = axes;
td = TemperatureData(x,y);
plot(ax,td)
```

Calls to Inferior-Class Methods

When you declare a class as inferior to your class, and both classes define a method with the same name, MATLAB dispatches to your class method regardless of argument order.

Suppose the TemperatureData class that is described in the previous section defines a set method. If you attempt to assign an object of the TemperatureData class to the UserData property of an axes object:

```
td = TemperatureData(x,y);
set(gca, 'UserData',td)
```

The results is a call to the TemperatureData set method. MATLAB does not call the built-in set function.

To support the use of a **set** function with inferior classes, implement a **set** method in your class that calls the built-in **set** function when the first argument is an object of the inferior class.

```
function set(varargin)
  if isa(varargin{1}, 'matlab.graphics.axis.Axes')
     builtin('set', varargin{:})
  else
  ...
end
```

More About

• "Object Precedence in Methods" on page 8-37

Class Methods for Graphics Callbacks

In this section...

"Referencing the Method" on page 8-42

"Syntax for Method Callbacks" on page 8-42

"How to Use a Class Method for a Slider Callback" on page 8-43

Referencing the Method

To use an ordinary class method as callback for a graphics object, specify the callback property as a function handle referencing the method. For example,

```
uicontrol('Style', 'slider', 'Callback', @obj.sliderCallback)
```

Where your class defines a method called *sliderCallback* and *obj* is an instance of your class.

To use a static methods as a callback, specify the callback property as a function handle that includes the class name that is required to refer to a static method:

```
uicontrol('Style','slider','Callback',@MyClass.sliderCallback)
```

Syntax for Method Callbacks

For ordinary methods, use dot notation to ensure the first argument passed to the callback is an instance of the class defining the callback:

@obj.methodName

Define the callback method with the following input arguments:

- An instance of the defining class as the first argument
- Two arguments for the event source handle and the event data that MATLAB passes to the callback

The function signature would be of this form:

function methodName(obj,srcHandle,eventData)

For static methods, the required class name ensures MATLAB dispatches to the method of the specified class:

@MyClass.methodName

Define the static callback method with two input arguments — the event source handle and the event data that MATLAB passes to the callback

The function signature would be of this form:

function methodName(srcHandle, eventData)

Passing Additional Arguments

If you want to pass arguments to your callback in addition to the source and event data arguments passed by MATLAB, you can use an anonymous function. The basic syntax for an anonymous function that you assign to the graphic object's Callback property includes the object as the first argument:

```
@(src,event)method name(object,src,event,additional arg,...)
```

See "Anonymous Functions" for more information.

How to Use a Class Method for a Slider Callback

This example shows how to use a method of your class as a callback for a uicontrol slider.

The SeaLevelAdjuster class creates a slider that varies the color limits of an indexed image to give the illusion of varying the sea level.

Class Definition

Define SeaLevelAdjuster as a handle class with the following members:

- The class properties store graphics object handles and the calculated color limits.
- The class constructor creates the graphics objects and assigns the slider callback.
- The callback function for the slider accepts the three required arguments a class
 instance, the handle of the event source, and the event data. Because the class saves
 the handles of the graphics objects, the callback method does not use the source and
 event data arguments.
- The uicontrol callback uses dot notation to reference the callback method:
 ...'Callback',@slaObj.slider cb.

```
classdef SeaLevelAdjuster < handle
    properties
    Figure</pre>
```

```
Axes
      Image
      CLimit
      Slider
   end % properties
   methods
      function sla0bj = SeaLevelAdjuster(x,map)
         slaObj.Figure = figure('Colormap',map,...
            'Position',[100,100,560,580],...
            'Resize', 'off');
         slaObj.Axes = axes('DataAspectRatio',[1,1,1],...
            'XLimMode', 'manual', 'YLimMode', 'manual',...
            'Parent', slaObj.Figure);
         slaObj.Image = image(x,'CDataMapping','scaled',...
            'Parent', slaObj.Axes);
         slaObj.CLimit = get(slaObj.Axes, 'CLim');
         slaObj.Slider = uicontrol('Style', 'slider',...
            'Parent', slaObj.Figure,...
            'Max',slaObj.CLimit(2)-1,...
            'Min', slaObj.CLimit(1)-1,...
            'Value', slaObj.CLimit(1),...
            'Units','normalized',...
            'Position',[0.9286,0.1724,0.0357,0.6897],...
            'SliderStep',[0.002,0.005],...
            'Callback',@slaObj.slider cb);
      end % SeaLevelAdjuster
      function slider cb(sla0bj,~,~)
         % src and event arguments are not used
         min val = get(slaObj.Slider, 'Value');
         max val = max(max(get(slaObj.Image, 'CData')));
         slaObj.Axes.CLim = [min val max val];
         drawnow
      end % slider cb
   end % methods
end % classdef
```

Using the SeaLevelAdjuster Class


The class is designed to be used with the cape image that is included with the MATLAB product. To obtain the image data, use the load command:

```
load cape X map
```

After loading the data, create a ${\tt SeaLevelAdjuster}$ object for the image:

slaObj = SeaLevelAdjuster(X,map);

Move the slider to change the color mapping and visualize a rise in sea level.



More About

- "Ordinary Methods" on page 8-7
- "Static Methods" on page 8-23

• "Determining Which Method Is Invoked"

Object Arrays

- "Create Object Arrays" on page 9-2
- "Initialize Object Arrays" on page 9-5
- "Empty Arrays" on page 9-8
- "Initialize Arrays of Handle Objects" on page 9-10
- "Object Arrays with Dynamic Properties" on page 9-13
- "Concatenating Objects of Different Classes" on page 9-15
- "Heterogeneous Arrays" on page 9-21

Create Object Arrays

```
In this section...

"Basic Knowledge" on page 9-2

"Build Arrays in the Constructor" on page 9-2

"Referencing Property Values in Object Arrays" on page 9-3

"Related Information" on page 9-4
```

Basic Knowledge

The material presented in this section builds on an understanding of the information presented in the following sections.

Class Definitions

- "Class Syntax Fundamentals"
- "Class Constructor Methods" on page 8-15

Working with Arrays

- · "Matrix Indexing"
- · "Empty Matrices, Scalars, and Vectors"
- "Multidimensional Arrays"

Build Arrays in the Constructor

A class constructor can create an array by building the array and returning it as the output argument.

For example, the <code>ObjectArray</code> class creates an object array that is the same size as the input array. Then it initializes the <code>Value</code> property of each object to the corresponding input array value.

```
classdef ObjectArray
  properties
    Value
  end
  methods
```

```
function obj = ObjectArray(F)
    if nargin ~= 0
        m = size(F,1);
        n = size(F,2);
        obj(m,n) = ObjectArray;
        for i = 1:m
            for j = 1:n
                obj(i,j).Value = F(i,j);
        end
        end
        end
    end
end
end
end
```

To preallocate the object array, assign the last element of the array first. MATLAB fills the first to penultimate array elements with default <code>ObjectArray</code> objects.

After preallocating the array, assign each object Value property to the corresponding value in the input array F. To use the class:

- Create 5-by-5 array of magic square numbers
- Create a 5-by-5 object array

```
F = magic(5);
A = ObjectArray(F);
whos
Name Size
```

Name	Size	Bytes	Class	Attributes
A F	5x5 5x5		ObjectArray double	

Referencing Property Values in Object Arrays

Reference all values of the same property in an object array using the syntax:

```
objarray.PropName
```

For example, given the ObjProp class:

```
classdef ObjProp
   properties
   RegProp
```

```
end
methods
   function obj = ObjProp
      obj.RegProp = randi(100);
   end
end
end
```

Create an array of ObjProp objects and access the RegProp property of each object:

```
for k = 1:5
    a(k) = ObjProp;
end
a.RegProp

ans =
    91

ans =
    13

ans =
    92

ans =
    64

ans =
    10
```

Related Information

For information on array initialization, see "Initialize Object Arrays" on page 9-5.

For information specific to initialization of handle array, see "Initialize Arrays of Handle Objects" on page 9-10

Initialize Object Arrays

```
In this section...

"Calls to Constructor" on page 9-5

"Initial Value of Object Properties" on page 9-6
```

Calls to Constructor

During the creation of object arrays, MATLAB can call the class constructor with no arguments, even if the constructor does not build an object array. For example, suppose that you define the following class:

```
classdef SimpleValue
  properties
     Value
  end
  methods
     function obj = SimpleValue(v)
        obj.Value = v;
  end
  end
end
```

Execute the following statement to create an array:

```
a(1,7) = SimpleValue(7)
Error using SimpleValue (line 7)
Not enough input arguments.
```

This error occurs because MATLAB calls the constructor with no arguments to initialize elements 1 through 6 in the array.

Your class must support the no input argument constructor syntax. A simple solution is to test nargin and let the case when nargin == 0 execute no code, but not error:

```
classdef SimpleValue
  properties
    Value
  end
  methods
    function obj = SimpleValue(v)
```

Using the revised class definition, the previous array assignment statement executes without error:

```
a(1,7) = SimpleValue(7)
a =
  1x7 SimpleValue array with properties:
    Value
```

The object assigned to array element a(1,7) uses the input argument passed to the constructor as the value assigned to the property:

```
a(1,7)
ans =
   SimpleValue with properties:
   Value: 7
```

MATLAB created the objects contained in elements a(1,1:6) with no input argument. The default value for properties empty []. For example:

```
a(1,1)
ans =
   SimpleValue with properties:
   Value: []
```

MATLAB calls the SimpleValue constructor once and copies the returned object to each element of the array.

Initial Value of Object Properties

When MATLAB calls a constructor with no arguments to initialize an object array, one of the following assignments occurs:

- · If property definitions specify default values, MATLAB assigns these values.
- If the constructor assigns values in the absence of input arguments, MATLAB assigns these values.
- If neither of the preceding situations apply, MATLAB assigns the value of empty double (that is, []) to the property.

Empty Arrays

In this section...

"Creating Empty Arrays" on page 9-8

"Assigning Values to an Empty Array" on page 9-8

Creating Empty Arrays

Empty arrays have no elements, but are of a certain class. All nonabstract classes have a static method named empty that creates an empty array of the same class. The empty method enables you to specify the dimensions of the output array. However, at least one of the dimensions must be 0. For example:

```
ary = SimpleValue.empty(5,0);
creates a 5-by-0 empty array of class SimpleValue.
```

Calling empty with no arguments returns a 0-by-0 empty array.

Assigning Values to an Empty Array

An empty object defines the class of an array. To assign nonempty objects to an empty array, MATLAB calls the class constructor to create default instances of the class for every other array element. Once you assign a nonempty object to an array, all array elements must be nonempty objects.

Note: A class constructor must avoid returning empty objects by default.

For example, using the SimpleValue defined in the "Initialize Object Arrays" on page 9-5 section, create an empty array:

```
ary = SimpleValue.empty(5,0);
class(ary)
ans =
SimpleValue
```

ary is an array of class SimpleValue. However, it is an empty array:

```
ary(1)
```

Index exceeds matrix dimensions.

If you make an assignment to a property value, MATLAB calls the SimpleClass constructor to grow the array to the require size:

```
ary(5).Value = 7;
ary(5).Value
ans =
    7
ary(1).Value
ans =
[]
```

MATLAB populates array elements one through five with SimpleValue objects created by calling the class constructor with no arguments. Then MATLAB assigns the property value 7 to the object at ary(5).

Initialize Arrays of Handle Objects

When initializing an array of handle objects, MATLAB:

- · Calls the class constructor once to obtain an object
- Creates unique handles for each element in the array
- Copies the property values from the constructed object without calling the constructor again.

The InitHandleArray class illustrates this behavior.

```
classdef InitHandleArray < handle
  properties
    RandNumb
  end
  methods
    function obj = InitHandleArray
    obj.RandNumb = randi(100);
  end
  end
end</pre>
```

The property RandNumb contains a random number that the InitHandleArray constructor assigns.

Consider what happens when MATLAB initialize an array by first assigning to the last element in the array. (The last element is the one with the highest index values). For example, suppose the value of the RandNumb property of the InitHandleArray object assigned to the element A(4,5) is 59:

```
A(4,5) = InitHandleArray;
A(4,5).RandNumb
ans =
```

The element in the index location A(4,5) is an instance of the InitHandleArray class. Element A(1,1) is also an instance of the InitHandleArray class, but its RandNumb property is set to a different random number. MATLAB called the class constructor to create a single object, which MATLAB then copied to all the remaining array elements. Calling the constructor resulted in another call to the randi function, which returns a new random number:

```
A(1,1).RandNumb ans =
```

MATLAB copies this second instance to all remaining array elements:

```
A(2,2).RandNumb

ans =

10

A(2,3).RandNumb

ans =

10
```

When initializing an object array, MATLAB assigns a copy of a single object to the empty elements in the array. MATLAB gives each object a unique handle so that later you can assign different property values to each object. The objects are not equivalent:

```
A(1,1) == A(2,2)
ans =
```

That is, the handle A(1,1) does not refer to the same object as A(2,2). The creation of an array with a statement such as:

```
A(4,5) = InitHandleArray;
```

results in two calls to the class constructor. The first creates the object for array element A(4,5). The second creates a default object that MATLAB copies to all remaining empty array elements.

Related Information

See "Indexing Multidimensional Arrays" and "Reshaping Multidimensional Arrays" for information on array manipulation.

See "Initializing Properties to Unique Values" for information on assigning values to properties.

See "Object Array Indexing" for information on implementing subsasgn methods for your class.

Object Arrays with Dynamic Properties

You cannot reference all the dynamic properties in an object array using a single statement, as you can with ordinary properties. For example, suppose the <code>ObjectArrayDynamic</code> class subclasses the <code>dynamicprops</code> class, which enables you to add properties to objects of the <code>ObjectArrayDynamic</code> class:

```
classdef ObjectArrayDynamic < dynamicprops
  properties
    RegProp
  end
  methods
    function obj = ObjectArrayDynamic
       obj.RegProp = randi(100);
  end
  end
end</pre>
```

Create an object array and add dynamic properties to each member of the array.

Define elements 1 and 2 as ObjectArrayDynamic objects:

```
a(1) = ObjectArrayDynamic;
a(2) = ObjectArrayDynamic;
```

Add dynamic properties to each object and assign a value

```
a(1).addprop('DynoProp');
a(1).DynoProp = 1;
a(2).addprop('DynoProp');
a(2).DynoProp = 2;
```

Get the values of the ordinary properties, as with any array:

a.RegProp

```
ans = 4
ans = 85
```

MATLAB returns an error if you try to access the dynamic properties of all array elements using this syntax.

```
a.DynoProp
```

No appropriate method, property, or field 'DynoProp' for class 'ObjectArrayDynamic'.

Refer to each object individually to access dynamic property values:

```
a(1).DynoProp
ans =
     1
a(2).DynoProp
ans =
     2
```

For information about classes that can define dynamic properties, see "Dynamic Properties — Adding Properties to an Instance" on page 7-30.

Concatenating Objects of Different Classes

In this section...

"Basic Knowledge" on page 9-15

"MATLAB Concatenation Rules" on page 9-15

"Concatenating Objects" on page 9-15

"Calling the Dominant-Class Constructor" on page 9-16

"Converter Methods" on page 9-18

Basic Knowledge

The material presented in this section builds on an understanding of the information presented in the following sections.

- "Class Precedence" on page 5-17
- "Class Attributes" on page 5-5
- · "Create Object Arrays" on page 9-2
- · "Valid Combinations of Unlike Classes"

MATLAB Concatenation Rules

MATLAB follows these rules for concatenating objects:

- MATLAB always converts all objects to the dominant class.
- User-defined classes take precedence over built-in classes like double.
- If there is no defined dominance relationship between any two objects, then the leftmost object dominates (see "Class Precedence" on page 5-17).

Note: MATLAB does not convert objects to a common superclass unless those objects are part of a heterogeneous hierarchy. For more information, see "Heterogeneous Arrays" on page 9-21.

Concatenating Objects

Concatenation combines objects into arrays:

```
ary = [obj1,obj2,obj3,...,objn];
The size of ary is 1-by-n.
ary = [obj1;obj2;obj3;...;objn];
The size of ary is n-by-1.
```

The class of the arrays is the same as the class of the objects being concatenated. Concatenating objects of different classes is possible if MATLAB can convert objects to the dominant class. MATLAB attempts to convert unlike objects by:

- Calling the inferior object converter method, if one exists.
- Passing an inferior object to the dominant class constructor to create an object of the dominant class.

If conversion of the inferior object is successful, MATLAB returns an array that is of the dominant class. If conversion is not possible, MATLAB returns an error.

Calling the Dominant-Class Constructor

MATLAB calls the dominant class constructor to convert an object of an inferior class to the dominant class. MATLAB passes the inferior object to the constructor as an argument. If the class design enables the dominant class constructor to accept objects of inferior classes as input arguments, then concatenation is possible without implementing a separate converter method.

If the constructor simply assigns this argument to a property, the result is an object of the dominant class with an object of an inferior class stored in a property. If this assignment is not a desired result, then ensure that class constructors include adequate error checking.

For example, consider the class ColorClass and two subclasses, RGBColor and HSVColor:

```
classdef ColorClass
   properties
      Color
   end
end
```

The class RGBColor inherits the Color property from ColorClass. RGBColor stores a color value defined as a three-element vector of red, green, and blue (RGB) values.

The constructor does not restrict the value of the input argument. It assigns this value directly to the Color property.

```
classdef RGBColor < ColorClass
   methods
    function obj = RGBColor(rgb)
        if nargin > 0
            obj.Color = rgb;
        end
    end
end
end
```

The class HSVColor also inherits the Color property from ColorClass. HSVColor stores a color value defined as a three-element vector of hue, saturation, brightness value (HSV) values.

```
classdef HSVColor < ColorClass
   methods
    function obj = HSVColor(hsv)
        if nargin > 0
            obj.Color = hsv;
        end
    end
end
end
```

Create an instance of each class and concatenate them into an array. The RGBColor object is dominant because it is the leftmost object and neither class defines a dominance relationship:

```
crgb = RGBColor([1 0 0]);
chsv = HSVColor([0 1 1]);
ary = [crgb,chsv];
class(ary)
ans =
RGBColor
```

You can combine these objects into an array because MATLAB can pass the inferior object of class HSVColor to the constructor of the dominant class. However, notice that the Color property of the second RGBColor object in the array actually contains an HSVColor object, not an RGB color specification:

```
ary(2).Color
ans =
   HSVColor with properties:
    Color: [0 1 1]
```

Avoid this undesirable behavior by:

- Implementing converter methods
- Performing argument checking in class constructors before assigning values to properties

Converter Methods

If your class design requires object conversion, implement converter methods for this purpose.

The ColorClass class defines converter methods for RGBColor and HSVColor objects:

```
classdef ColorClass
   properties
      Color
   end
   methods
      function rgbObj = RGBColor(obj)
         if isa(obj, 'HSVColor')
            rgbObj = RGBColor(hsv2rgb(obj.Color));
         end
      end
      function hsv0bj = HSVColor(obj)
         if isa(obj,'RGBColor')
            hsv0bj = HSVColor(rgb2hsv(obj.Color));
         end
      end
   end
end
```

Create an array of RGBColor and HSVColor objects with the revised superclass:

```
crgb = RGBColor([1 0 0]);
chsv = HSVColor([0 1 1]);
```

```
ary = [crgb,chsv];
class(ary)
ans =
RGBColor
```

MATLAB calls the converter method for the HSVColor object, which it inherits from the superclass. The second array element is now an RGBColor object with an RGB color specification assigned to the Color property:

```
ary(2)
ans =
   RGBColor with properties:
    Color: [1 0 0]
ary(2).Color
ans =
   1 0 0
```

If the leftmost object is of class HSVColor, the array ary is also of class HSVColor, and MATLAB converts the Color property data to HSV color specification.

Defining a converter method in the superclass and adding better argument checking in the subclass constructors produces more predicable results. Here is the RGBColor class constructor with argument checking:

```
classdef RGBColor < ColorClass</pre>
   methods
      function obj = RGBColor(rgb)
         if nargin == 0
             rgb = [0 \ 0 \ 0];
         else
             if ~(isa(rgb, 'double')...
                   && size(rgb,2) == 3 ...
                   && max(rgb) <= 1 && min(rgb) >= 0
                error('Specify color as RGB values')
             end
         end
         obj.Color = rgb;
      end
   end
end
```

Your applications can require additional error checking and other coding techniques. The classes in these examples are designed only to demonstrate concepts.

More About

- "Object Converters"
- "Hierarchies of Classes Concepts"

Heterogeneous Arrays

In this section...

- "Why Heterogeneous Arrays" on page 9-21
- "Heterogeneous Array Concepts" on page 9-21
- "Nature of Heterogeneous Arrays" on page 9-22
- "Unsupported Hierarchies" on page 9-25
- "Default Object" on page 9-26
- "Conversion During Assignment and Concatenation" on page 9-27

Why Heterogeneous Arrays

A heterogeneous array is an array of objects that differ in their specific class, but which are all derived from or are instances of a common superclass. The common superclass forms the root of the hierarchy. The root superclass must derive directly from matlab.mixin.Heterogeneous.

By implementing a hierarchy of related classes as heterogeneous, you can create mixed class (heterogeneous) arrays of objects of those classes. Heterogeneous hierarchies are useful to:

- · Create arrays of objects that are of different classes, but part of a related hierarchy.
- · Call methods of the most specific common superclass on the array as a whole
- Access properties of the most specific common superclass using dot notation with the array
- Use common operators that are supported for object arrays
- Support array indexing (scalar or nonscalar) that returns arrays of the most specific class

Heterogeneous Array Concepts


• Heterogeneous array — An array in which two or more elements belong to different specific classes. All elements derive from the same root superclass.

- Root superclass Class derived directly from matlab.mixin.Heterogeneous. Only concrete subclasses of the root superclass can form heterogeneous arrays.
- Most specific common superclass The most specific class in the inheritance hierarchy from which all of the objects in a heterogeneous array derive. The most specific common superclass can be the root superclass or a more specific superclass shared by the objects currently in the array.
- Class of a heterogeneous array The most specific common superclass from which all objects in the heterogeneous array derive. Adding and removing objects from a heterogeneous array can change the most specific superclass shared by the instances. This change results in a change in the class of a heterogeneous array.

Nature of Heterogeneous Arrays

The heterogeneous hierarchy in this diagram illustrates the characteristics of heterogeneous arrays concerning:

- Array class
- Property access
- · Method invocation



Class of Heterogeneous Arrays

The class of a heterogeneous array is that of the most specific superclass shared by the objects of the array.

If these conditions are true, the concatenation and subscripted assignment operations return a heterogeneous array:

- \bullet $\,$ The objects on the right side of the assignment statement are of different classes
- All objects on the right side of the assignment statement derive from a common subclass of matlab.mixin.Heterogeneous

For example, form an array by concatenating objects of these classes The class of a1 is ClassA:

```
a1 = [SpecificA, SpecificB];
```

If the array includes an object of the class SpecificC, the class of a2 is RootSuperclass:

```
a2 = [SpecificA, SpecificB, SpecificC];
```

If you assigned an object of the class SpecificC to array a1 using indexing, the class of a1 becomes RootSuperclass:

```
a1(3) = SpecificC;
```

If the array contains objects of only one class, then the array is not heterogeneous. For example, the class of a is SpecificA.

```
a = [SpecificA, SpecificA];
```

Access Properties

Access array properties with dot notation when the class of the array defines the properties. The class of the array is the most specific common superclass, which ensures all objects inherit the same properties.

For example, suppose ClassA defines a property called Prop1.

```
a1 = [SpecificA, SpecificB];
a1.Prop1
```

Referring to Prop1 using dot notation returns the value of Prop1 for each object in the array.

Invoke Methods

To invoke a method on a heterogeneous array, the class of the array must define or inherit the method as Sealed. For example, suppose CommonSuperclass defines a Sealed method called superMethod.

Call the method on all objects in the array a2:


```
a2 = [SpecificA,SpecificB,SpecificC];
a2.superMethod
```

Sealing the method (so that it cannot be overridden in a subclass) ensures that there is no ambiguity in the method definition.

Unsupported Hierarchies


Heterogeneous hierarchies cannot have ambiguities when obtaining default objects and converting class objects to other types. Members of the hierarchy can derive from only one root superclass (that is, from only one direct subclass of matlab.mixin.Heterogeneous).

This diagram shows a hierarchy that is not allowed:



ClassA derives from two classes that are subclasses of matlab.mixin.Heterogeneous.

The next diagram shows two separate heterogeneous hierarchies. ClassA has only one root superclass (called OtherBaseClass). The heterogeneous hierarchy is no longer ambiguous:



Default Object

A default object is the object returned by calling the class constructor with no arguments. MATLAB uses default objects in these situations:

• Indexed assignment creates an array with gaps in array elements. For example, assign the first element of array h to index 5:

$$h(5) = ClassA(arg1,arg2);$$

MATLAB fills the unassigned positions with default objects.

 Loading a heterogeneous array from a MAT-file when the class definition of a specific object in the array is not available. MATLAB replaces the object with the default object. Heterogeneous hierarchies enable you to define the default object for that hierarchy. The matlab.mixin.Heterogeneous class provides a default implementation of a method called getDefaultScalarElement. This method returns an instance of the root class of the heterogeneous hierarchy, unless the root superclass is abstract.

If the root superclass is abstract or is not appropriate for a default object, override the getDefaultScalarElement method. Implement the getDefaultScalarElement override in the root superclass, which derives directly from matlab.mixin.Heterogeneous.

getDefaultScalarElement must return a scalar object that is derived from the root superclass. For specific information on how to implement this method, see getDefaultScalarElement.

Conversion During Assignment and Concatenation

If you specify a heterogeneous array that contains objects that are not derived from the same root superclass, MATLAB attempts to call a method called convertObject. Implement convertObject to convert objects to the appropriate class. There is no default implementation of this method.

If you want to support the formation of heterogeneous arrays using objects that are not part of the heterogeneous hierarchy, implement a convertObject method in the root superclass. The convertObject method must convert the nonmember object to a valid member of the heterogeneous hierarchy.

For details on implementing the convertObject method, see matlab.mixin.Heterogeneous.

Related Examples

"Handle-Compatible Classes and Heterogeneous Arrays"

Events — Sending and Responding to Messages

- "Learn to Use Events and Listeners" on page 10-2
- "Property Set Listener" on page 10-9
- "Events and Listeners Concepts" on page 10-12
- "Event Attributes" on page 10-17
- "Events and Listeners Syntax and Techniques" on page 10-19
- "Listener Lifecycle" on page 10-23
- "Function Handle for Listener Callbacks" on page 10-26
- "Listen for Changes to Property Values" on page 10-29
- "Update Graphs Using Events and Listeners" on page 10-36

Learn to Use Events and Listeners

In this section...

"Why Use Events and Listeners" on page 10-2

"Events and Listeners Basics" on page 10-2

"Events and Listeners Syntax Overview" on page 10-3

"Class with Custom Event Data" on page 10-5

"Class to Observe Property Changes" on page 10-7

Why Use Events and Listeners

Events are notices that objects broadcast in response to something that happens, such as a property value changing or a user interaction with an application program. Listeners execute functions when notified that the event of interest occurs. Use events to communicate things that happen to objects, and respond to these events by executing the listener's callback function.

See "Events and Listeners — Concepts" on page 10-12 for a more thorough discussion of the MATLAB event model.

Events and Listeners Basics

When using events and listeners:

- Only handle classes can define events and listeners.
- Call the handle notify method to trigger the event. The event notification broadcasts the named event to all listeners registered for this event.
- Use the handle addlistener method to associate a listener with an object that will be the source of the event.
- When adding a listener, pass a function handle for the listener callback function using a syntax such as the following:
 - addlistener(eventObject, 'EventName', @functionName) for an ordinary function.
 - addlistener(eventObject, 'EventName', @Obj.methodName) for a method of Obi.

- addlistener(eventObject, 'EventName', @ClassName.methodName) for a static method of the class ClassName.
- Listener callback functions must define at least two input arguments the event source object handle and the event data (See "Function Handle for Listener Callbacks" on page 10-26 for more information).
- You can modify the data passed to each listener callback by subclassing the event.EventData class.

Events and Listeners Syntax Overview

Define an event name in the events code block:

```
classdef ClassName < handle
   . . .
   events
      EventName
   end
end
For example, MyClass defines an event named StateChange:
classdef MyClass < handle</pre>
   events
      StateChange
   end
end
Trigger an event using the handle class notify method:
classdef ClassName < handle
   events
      EventName
   end
   . . .
   methods
      function anyMethod(obj)
          notify(obj,'EventName');
      end
end
```

Any function or method can trigger the event for a specific instance of the class defining the event. For example, the triggerEvent method calls notify to trigger the StateChange event:

```
classdef MyClass < handle
    events
        StateChange
    end
    methods
        function triggerEvent(obj)
            notify(obj,'StateChange')
    end
    end
end</pre>
```

Trigger the StateChange event with the triggerEvent method:

```
obj = MyClass;
obj.triggerEvent
```

Define a listener using the handle class addlistener method:

```
ListenerObject = addlistener(SourceOfEvent, 'EventName',@listenerCallback);
```

addlistener returns the listener object. The input arguments are:

- SourceOfEvent An object of the class defining the event on which the event occurred.
- EventName The name of the event defined in the class events code block.
- @listenerCallback a function handle referencing the function that executes in response to the event.

For example, create a listener object for the StateChange event:

```
function lh = createListener(src)
    lh = addlistener(src, 'StateChange', @handleStateChange)
end
```

Define the callback function for the listener. The callback function must accept as the first two arguments the event source object and an event data object:

```
function handleStateChange(src,eventData)
   ...
end
```

Class with Custom Event Data

Suppose you want to create a listener callback function that has access to specific information when the event occurs. This example shows how to do this by creating custom event data.

Events provide information to listener callback functions by passing an event data argument to the specified function. By default, MATLAB passes an event. EventData object to the listener callback. This object has two properties:

- EventName Name of the event triggered by this object.
- Source Handle of the object triggering the event.

Provide additional information to the listener callback by subclassing the event. EventData class.

- Define properties in the subclass to contain the additional data.
- Define a constructor that accepts the additional data as arguments.
- Set the ConstructOnLoad class attribute.
- Use the subclass constructor as an argument to the notify method to trigger the event.

Defining and Triggering an Event

The SimpleEventClass defines a property set method (see "Property Set Methods") from which it triggers an event if the property is set to a value exceeding a certain limit. The property set method performs these operations:

- · Saves the original property value
- · Sets the property to the specified value
- If the specified value is greater than 10, the set method triggers an ${\tt Overflow}$ event
- Passes the original property value, as well as other event data, in a SpecialEventDataClass object to the notify method.

```
classdef SimpleEventClass < handle
  properties
     Prop1 = 0;
end
events
     Overflow</pre>
```

```
end
methods
  function set.Prop1(obj,value)
    orgvalue = obj.Prop1;
    obj.Prop1 = value;
    if (obj.Prop1 > 10)
     % Trigger the event using custom event data
        notify(obj,'Overflow',SpecialEventDataClass(orgvalue));
    end
  end
end
end
```

Define the Event Data

Event data is always contained in an event. EventData object. The SpecialEventDataClass adds the original property value to the event data by subclassing event. EventData:

```
classdef (ConstructOnLoad) SpecialEventDataClass < event.EventData
    properties
        OrgValue = 0;
    end
    methods
        function eventData = SpecialEventDataClass(value)
            eventData.OrgValue = value;
    end
    end
end</pre>
```

Create a Listener for the Overflow Event

To listen for the Overflow event, attach a listener to an instance of the SimpleEventClass class. Use the addlistener method to create the listener. You also need to define a callback function for the listener to execute when the event is triggered.

The function setupSEC instantiates the SimpleEventClass class and adds a listener to the object. In this example, the listener callback function displays information that is contained in the eventData argument (which is a SpecialEventDataClass object).

```
function sec = setupSEC
  sec = SimpleEventClass;
  addlistener(sec,'Overflow',@overflowHandler)
  function overflowHandler(eventSrc,eventData)
```

```
disp('The value of Prop1 is overflowing!')
    disp(['Its value was: ' num2str(eventData.OrgValue)])
    disp(['Its current value is: ' num2str(eventSrc.Prop1)])
    end
end

Create the SimpleEventClass object and add the listener:

sec = setupSEC;
sec.Prop1 = 5;
sec.Prop1 = 15; % listener triggers callback

The value of Prop1 is overflowing!
Its value was: 5
Its current value is: 15
```

Class to Observe Property Changes

This example shows how to listen for changes to a property value. This examples uses:

- PostSet event predefined by MATLAB
- SetObservable property attribute to enable triggering the property PostSet event.
- addlistener handle class method to create the listener

```
classdef PropLis < handle</pre>
   % Define a property that is SetObservable
   properties (SetObservable)
      ObservedProp = 1;
   end
   methods
      function attachListener(obj)
         %Attach a listener to a PropListener object
         addlistener(obj, 'ObservedProp', 'PostSet', @PropLis.propChange);
      end
   end
   methods (Static)
      function propChange(metaProp,eventData)
         % Callback for PostSet event
         % Inputs: meta.property object, event.PropertyEvent
         h = eventData.AffectedObject;
         propName = metaProp.Name;
         disp(['The ',propName,' property has changed.'])
         disp(['The new value is: ',num2str(h.ObservedProp)])
```

```
disp(['Its default value is: ',num2str(metaProp.DefaultValue)])
  end
  end
end
```

The PropLis class uses an ordinary method (attachListener) to add the listener for the ObservedProp property. If the PropLis class defines a constructor, the constructor can contain the call to addlistener.

The listener callback is a static method (propChange). MATLAB passes two arguments when calling this function:

- metaProp a meta.property object for ObservedProp
- eventData an event.PropertyEvent object contain event specific data.

These arguments provide information about the property and the event.

Use the PropLis class by creating an instance and calling its attachListener method:

Related Examples

• "Property Set Listener" on page 10-9

Property Set Listener

This example shows how to define a listener for a property set event. This means the listener callback triggers when the value of a specific property changes. The class defined for this example uses a method for a push button callback and a static method for the listener callback. When the push button callback changes the value of a property, the listener executes its callback on the PreSet event.

This example defines a class (PushButton) with these design elements:

- ResultNumber Observable property
- uicontrol pushbutton Push button object used to generate a new graph when its callback executes
- A listener that responds to a change in the observable property

PushButton Class Design

The PushButton class creates figure, uicontrol, axes graphics objects and a listener object in the class constructor.


The push button's callback is a class method (named pressed). When the push button is activated, the following sequence occurs:

- 1 MATLAB executes the pressed method, which graphs a new set of data and increments the ResultNumber property.
- 2 Attempting to set the value of the ResultNumber property triggers the PreSet event, which executes the listener callback before setting the property value.
- 3 The listener callback uses the event data to obtain the handle of the callback object (an instance of the PushButton class), which then provides the handle of the axes object that is stored in its AxHandle property.
- **4** The listener callback updates the axes Title property, after the callback completes execution, MATLAB sets the ResultsNumber property to its new value.

```
classdef PushButton < handle
  properties (SetObservable)
    ResultNumber = 1;
  end
  properties</pre>
```

buttonObj = PushButton;

```
AxHandle
   end
   methods
      function buttonObj = PushButton
         myFig = figure;
         buttonObj.AxHandle = axes('Parent', myFig);
         uicontrol('Parent', myFig,...
             'Style','pushbutton',...
             'String', 'Plot Data',...
             'Callback',@(src,evnt)pressed(buttonObj));
         addlistener(buttonObj, 'ResultNumber', 'PreSet',...
            @PushButton.updateTitle);
      end
   end
   methods
      function pressed(obj)
         scatter(obj.AxHandle, randn(1,20), randn(1,20), 'p')
         obj.ResultNumber = obj.ResultNumber + 1;
      end
   end
   methods (Static)
      function updateTitle(~,eventData)
         h = eventData.AffectedObject;
         set(get(h.AxHandle, 'Title'), 'String',['Result Number: ',...
            num2str(h.ResultNumber)])
      end
   end
end
The scatter graph looks similar to this after three push-button clicks.
```



Related Examples

• "Listen for Changes to Property Values" on page 10-29

Events and Listeners — Concepts

In this section...

"The Event Model" on page 10-12

"Default Event Data" on page 10-13

"Events Only in Handle Classes" on page 10-14

"Property-Set and Query Events" on page 10-14

"Listeners" on page 10-15

The Event Model

Events represent changes or actions that occur within objects. For example,


- Modification of class data
- Execution of a method
- Querying or setting a property value
- Destruction of an object

Basically, any activity that you can detect programmatically can generate an event and communicate information to other objects.

MATLAB classes define a process that communicates the occurrence of events to other objects that need to respond to the events. The event model works this way:

- A handle class declares a name used to represent an event. "Name Events" on page 10-19
- After creating an object of the event-declaring class, attach listener to that object. "Control Listener Lifecycle" on page 10-23
- A call to the handle class notify method broadcasts a notice of the event to listeners. The class user determines when to trigger the event. "Trigger Events" on page 10-19
- Listeners execute a callback function when notified that the event has occurred. "Specify Listener Callbacks" on page 10-26
- You can bind listeners to the lifecycle of the object that defines the event, or limit listeners to the existence and scope of the listener object. "Control Listener Lifecycle" on page 10-23

The following diagram illustrates the event model.



Default Event Data

Events provide information to listener callbacks by passing an event data argument to the callback function. By default, MATLAB passes an event. EventData object to the listener callback. This object has two properties:

• EventName — The event name as defined in the class event block

Source — The object that is the source of the event

MATLAB passes the source object to the listener callback in the required event data argument. This enables you to access any of the object's public properties from within your listener callback function.

Customizing Event Data

You can create a subclass of the event. EventData class to provide additional information to listener callback functions. The subclass would define properties to contain the additional data and provide a method to construct the derived event data object so it can be passed to the notify method.

"Define Event-Specific Data" on page 10-22 provides an example showing how to customize this data.

Events Only in Handle Classes

You can define events only in handle classes. This restriction exists because a value class is visible only in a single MATLAB workspace so no callback or listener can have access to the object that triggered the event. The callback could have access to a copy of the object. However, accessing a copy is not generally useful because the callback cannot access the current state of the object that triggered the event or effect any changes in that object.

"Comparing Handle and Value Classes" on page 6-2 provides general information on handle classes.

"Events and Listeners — Syntax and Techniques" on page 10-19 shows the syntax for defining a handle class and events.

Property-Set and Query Events

There are four predefined events related to properties:

- PreSet Triggered just before the property value is set, before calling its set access method
- PostSet Triggered just after the property value is set
- PreGet Triggered just before a property value query is serviced, before calling its get access method

PostGet — Triggered just after returning the property value to the query

These events are predefined and do not need to be listed in the class events block.

When a property event occurs, the callback is passed an event.PropertyEvent object. This object has three properties:

- EventName The name of the event described by this data object
- Source The source object whose class defines the event described by the data object
- AffectedObject The object whose property is the source for this event (that
 is, AffectedObject contains the object whose property was either accessed or
 modified).

You can define your own property-change event data by subclassing the event. EventData class. Note that the event. PropertyEvent class is a sealed subclass of event. EventData.

See "Listen for Changes to Property Values" on page 10-29 for a description of the process for creating property listeners.

See "The PostSet Event Listener" on page 10-46 for an example.

See "Property Access Methods" on page 7-14 for information on methods that control access to property values.

Listeners

Listeners encapsulate the response to an event. Listener objects belong to the event.listener class, which is a handle class that defines the following properties:

- · Source Handle or array of handles of the object that generated the event
- EventName Name of the event
- Callback Function to execute when an enabled listener receives event notification
- Enabled Callback function executes only when Enabled is true. See "Enabling and Disabling the Listeners" on page 10-49 for an example.
- Recursive Allow listener to cause the same event that triggered the execution of the callback

Recursive is false by default. If the callback triggers its own event, the listener cannot execute recursively. Setting the Recursive to true can create a situation where infinite recursion reaches the recursion limit and triggers an error.

"Control Listener Lifecycle" on page 10-23 provides more specific information.

Event Attributes

Specifying Event Attributes

The following table lists the attributes you can set for events. To specify a value for an attribute, assign the attribute value on the same line as the event key word. For example, all the events defined in the following events block have protected ListenAccess and private NotifyAccess.

```
events (ListenAccess = 'protected', NotifyAccess = 'private')
     EventName1
     EventName2
end
```

To define other events in the same class definition that have different attribute settings, create another events block.

Event Attributes

Attribute Name	Class	Description
Hidden	logical Default = false	If true, event does not appear in list of events returned by events function (or other event listing functions or viewers).
ListenAccess	 enumeration, default = public meta.class object cell array of meta.class objects 	 Determines where you can create listeners for the event. public — Unrestricted access protected — Access from methods in class or subclasses private — Access by class methods only (not from subclasses) List classes that have listen access to this event. Specify classes as meta.class objects in the form: A single meta.class object A cell array of meta.class objects. An empty cell array, {}, is the same as private access. See "Control Access to Class Members" on page 11-25

Attribute Name	Class	Description
NotifyAccess	 enumeration, default = public meta.class object cell array of meta.class objects 	 Determines where code can trigger the event public — Any code can trigger event protected — Can trigger event from methods in class or derived classes private — Can trigger event by class methods only (not from derived classes) List classes that have notify access to this event. Specify classes as meta.class objects in the form: A single meta.class object A cell array of meta.class objects. An empty cell array, {}, is the same as private access. See "Control Access to Class Members" on page 11-25

Events and Listeners — Syntax and Techniques

```
In this section...

"Name Events" on page 10-19

"Trigger Events" on page 10-19

"Listen to Events" on page 10-20

"Define Event-Specific Data" on page 10-22
```

Name Events

Define an event by declaring an event name inside an events block. For example, the following class creates an event called ToggledState.

```
classdef ToggleButton < handle
  properties
     State = false
  end
  events
     ToggledState
  end
end</pre>
```

Trigger Events

The OnStateChange method calls notify to trigger the event. Pass the handle of the object that caused the event and the name of the event.

```
classdef ToggleButton < handle
  properties
     State = false
  end
  events
     ToggledState
  end
  methods
    function OnStateChange(obj,newState)
     if newState ~= obj.State
       obj.State = newState;
     notify(obj,'ToggledState');</pre>
```

```
end
end
end
```

Listen to Events

Once the call to notify triggers an event, MATLAB broadcasts a message to all listeners that are listening for that event on a specific object. To create a listener for an event, use the addlistener handle class method.

For example, the RespondToToggle class defines objects that listen for the ToggleState event defined in the class ToggleButton.

```
classdef RespondToToggle < handle
  methods
    function obj = RespondToToggle(toggle_button_obj)
        addlistener(toggle_button_obj, 'ToggledState', @RespondToToggle.handleEvnt);
    end
end
methods (Static)
    function handleEvnt(src,~)
        if src.State
            disp('ToggledState is true')
        else
            disp('ToggledState is false')
        end
end
end
end</pre>
```

The class RespondToToggle adds the listener from within its constructor. The class defines the callback (handleEvnt) as a static method that accepts the two standard arguments:

- src the handle of the object triggering the event (i.e., a ToggleButton object)
- evtdata an event.EventData object

The listener executes the callback when the specific ToggleButton object executes the notify method.

For example, create instances of both classes:

```
tb = ToggleButton;
rtt = RespondToToggle(tb);
```

Whenever you call the ToggleButton object's OnStateChange method, notify triggers the event:

```
tb.OnStateChange(true)
ToggledState is true
tb.OnStateChange(false)
ToggledState is false
```

Remove Listeners

You can remove a listener object by calling delete on its handle. For example, if the class RespondToToggle saved the listener handle as a property, you could delete the listener:

```
classdef RespondToToggle < handle</pre>
   properties
      ListenerHandle
   end
   methods
      function obj = RespondToToggle(toggle button obj)
         hl = addlistener(toggle_button_obj, 'ToggledState', @RespondToToggle.handleEvnt);
         obj.ListenerHandle = hl;
      end
   end
   methods (Static)
      function handleEvnt(src,~)
         if src.State
            disp('ToggledState is true')
            disp('ToggledState is false')
         end
      end
   end
end
```

With this code change, you can remove the listener from an instance of the RespondToToggle class. For example:

```
tb = ToggleButton;
rtt = RespondToToggle(tb);
```

At this point, the object rtt is listening for the ToggleState event triggered by object tb. To remove the listener, call delete on the property containing the listener handle:

```
delete(rtt.ListenerHandle)
```

You do not need to explicitly delete a listener. MATLAB automatically deletes the listener when the object's lifecycle ends (e.g., when the rtt object is deleted).

Define Event-Specific Data

Suppose that you want to pass the state of the toggle button as a result of the event to the listener callback. You can add more data to the default event data by subclassing the event. EventData class and adding a property to contain this information. You then can pass this object to the notify method.

Note: To save and load objects that are subclasses of event.EventData, such as ToggleEventData, enable the ConstructOnLoad class attribute for the subclass.

```
classdef (ConstructOnLoad) ToggleEventData < event.EventData
    properties
        NewState
    end

methods
    function data = ToggleEventData(newState)
        data.NewState = newState;
    end
end
end</pre>
```

The call to notify uses the ToggleEventData constructor to create the necessary argument.

```
notify(obj,'ToggledState',ToggleEventData(newState));
```

Related Examples

- "Property Set Listener" on page 10-9
- "Update Graphs Using Events and Listeners" on page 10-36

Listener Lifecycle

In this section...

"Control Listener Lifecycle" on page 10-23

"Temporarily Deactivating Listeners" on page 10-24

"Permanently Deleting Listeners" on page 10-25

Control Listener Lifecycle

There are two ways to create listeners:

- The addlistener method binds the listener to the lifecycle of the object(s) that generate the event. The listener object persists until MATLAB destroys the event object.
- The event.listener class constructor creates listeners that are not tied to the lifecycle of the object(s) generating the event. The listener is active as long as the listener object remains in scope and is not deleted.

Attach Listener to Event Source — Using addlistener

The following code defines a listener for the ToggleState event:

```
lh = addlistener(obj, 'ToggleState', @RespondToToggle.handleEvnt);
```

The arguments are:

- obj The object that is the source of the event
- ToggleState The event name passed as a string
- @RespondToToggle.handleEvnt A function handle to the callback function (static method)

The listener callback function must accept at least two arguments, which are automatically passed by the MATLAB runtime to the callback. The arguments are:

- The source of the event (that is, obj in the call to addlistener)
- An event.EventData object, or a subclass of event.EventData, such as the ToggleEventData object described earlier "Define Event-Specific Data" on page 10-22.

The callback function must be defined to accept these two arguments:

```
function callbackFunction(src,evnt)
    ...
end
```

In cases where the event data (evnt) object is user defined, it must be constructed and passed as an argument to the notify method. For example, the following statement constructs a ToggleEventData object and passes it to notify as the third argument:

```
notify(obj, 'ToggledState',ToggleEventData(newState));
```

"Specify Listener Callbacks" on page 10-26 provides more information on callback syntax.

Limiting Listener Scope — Constructing event.listener Objects Directly

You can also create listeners by calling the event.listener class constructor directly. When you call the constructor instead of using addlistener to create a listener, the listener exists only while the listener object you create is in scope (e.g., within the workspace of an executing function). It is not tied to the event-generating object's existence.

The event.listener constructor requires the same arguments as used by addlistener — the event-naming object, the event name, and a function handle to the callback:

```
lh = event.listener(obj, 'EventName',@callbackFunction)
```

For example, using the ToggleState event discussed previously:

```
lh = event.listener(obj, 'ToggleState', @RespondToToggle.handleEvnt)
```

If you want the listener to persist beyond the normal variable scope, you should use addlistener to create it.

Temporarily Deactivating Listeners

The addlistener method returns the listener object so that you can set its properties. For example, you can temporarily disable a listener by setting its Enabled property to false:

```
lh.Enabled = false;
```

To re-enable the listener, set Enabled to true.

Permanently Deleting Listeners

Calling delete on a listener object destroys it and permanently removes the listener: delete(1h)

Related Examples

• "Enabling and Disabling the Listeners" on page 10-49

Function Handle for Listener Callbacks

In this section...

"Specify Listener Callbacks" on page 10-26

"Callback Execution" on page 10-28

Specify Listener Callbacks

Callbacks are functions that execute when the listener receives notification of an event. Pass a function handle that references the function to addlistener or the event.listener constructor when creating the listener.

All callback functions must accept at least two arguments:

- The handle of the object that is the source of the event
- An event.EventData object or an object that is derived from the event.EventData class.

Function Handle Syntax

For a function:

@functionName

For an ordinary method called with an object of the class:

@obj.methodName

For a static method:

@ClassName.methodName

Defining a listener using an ordinary function as the callback uses this syntax:

lh = addlistener(eventSourceObj, 'EventName', @functionName)

Callback Function Syntax

Define the callback function to accept the required arguments:

```
function callbackFunction(src,evnt)
```

. . .

end

If you do not use the event source and event data arguments, you can define the function to ignore these inputs:

```
function callbackFunction(~,~)
    ...
end
```

Adding Arguments to a Callback Function

Ordinary class methods (i.e., not static methods) require a class object as an argument. Therefore, you need to add another argument to the callback function definition. If your listener callback is a method of the class of an object, Obj, then your call to addlistener would use this syntax:

```
lh = addlistener(eventSourceObj, 'EventName',@obj.callbackMethod)
```

Another option is to use an anonymous function.

Create a method to use as your callback function and reference this method as a function handle in a call to addlistener or the event.listener constructor:

```
lh = addlistener(eventSourceObj, 'EventName',@(src,evnt)callbackFunction(obj,src,evnt))
```

Then define the method in a method block as usual:

```
methods
   function callbackFunction(obj,src,evnt)
     ...
   end
end
```

You can specify additional arguments by extending the input argument list:

```
lh = addlistener(eventSourceObj, 'EventName',@(src,event)methodName(obj,src,event,arg1,
```

Define the method or function with a matching signature:

```
methods
   function callbackFunction(obj,src,evnt,arg1,...argn)
     ...
   end
end
```

For general information on anonymous functions, see "Anonymous Functions".

Callback Execution

Listeners execute their callback function when notified that the event has occurred. Listeners are passive observers in the sense that errors in the execution of a listener callback does not prevent the execution of other listeners responding to the same event, or execution of the function that triggered the event.

Callback function execution continues until the function completes. If an error occurs in a callback function, execution stops and control returns to the calling function. Then any remaining listener callback functions execute.

Listener Order of Execution

The order in which listeners callback functions execute after the firing of an event is undefined. However, all listener callbacks execute synchronously with the event firing.

The handle class notify method calls all listeners before returning execution to the function that called notify.

Callbacks That Call notify

Do not modify and reuse or copy and reuse the event data object that you pass to notify, which is then passed to the listener callback.

Listener callbacks can call notify to trigger events, including the same event that invoked the callback. When a function calls notify, MATLAB sets the property values of the event data object that is passed to callback functions. To ensure these properties have appropriate values for subsequently called callbacks, you should always create a new event data object if you call notify with custom event data.

Managing Callback Errors

If you want to control how your program responds to errors, use a try/catch statement in your listener callback function to handle errors.

Related Examples

· "Class Methods for Graphics Callbacks"

Listen for Changes to Property Values

In this section...

"Creating Property Listeners" on page 10-29

"Property Event and Listener Classes" on page 10-31

"Aborting Set When Value Does Not Change" on page 10-32

Creating Property Listeners

You can listen to the predeclared property events (named: PreSet, PostSet, PreGet, and PostGet) by creating a listener for those named events:

- Specify the SetObservable and/or GetObservable property attributes to add listeners for set or get events.
- Define a callback function
- Create a property listener by including the name of the property as well as the event in the call to addlistener (see "Add a Listener to the Property" on page 10-30.)
- Optionally subclass event.data to create a specialized event data object to pass to the callback function.
- Prevent execution of the callback if the new value is the same as the current value (see "Aborting Set When Value Does Not Change" on page 10-32).

Set Property Attributes to Enable Property Events

In the properties block, enable the SetObservable attribute:

```
properties (SetObservable)
% Can define PreSet and PostSet property listeners
% for properties defined in this block
   PropOne
   PropTwo
   ...
end
```

Define a Callback Function for the Property Event

The listener executes the callback function when MATLAB triggers the property event. You must define the callback function to have two specific arguments, which are passed to the function automatically when called by the listener:

- Event source a meta.property object describing the object that is the source of the property event
- Event data a event.PropertyEvent object containing information about the event

You can pass additional arguments if necessary. It is often simple to define this method as Static because these two arguments contain most necessary information in their properties.

For example, suppose the handlePropEvents function is a static method of the class creating listeners for two properties of an object of another class:

```
methods (Static)
function handlePropEvents(src,evnt)
switch src.Name
case 'PropOne'
% PropOne has triggered an event
...
case 'PropTwo'
% PropTwo has triggered an event
...
end
end
end
```

Another possibility is to use the event.PropertyEvent object's EventName property in the switch statement to key off the event name (PreSet or PostSet in this case).

"Class Metadata" on page 15-2 provides more information about the meta.property class.

Add a Listener to the Property

The addlistener handle class method enables you to attach a listener to a property without storing the listener object as a persistent variable. For a property events, use the four-argument version of addlistener.

If the call

```
addlistener(\texttt{EventObject}, \texttt{'PropOne'}, \texttt{'PostSet'}, @\textit{ClassName}. \\ handle \texttt{PropertyEvents});
```

The arguments are:

- EventObject handle of the object generating the event
- Prop0ne name of the property to which you want to listen

- PostSet name of the event for which you want to listen
- @ClassName.handlePropertyEvents function handle referencing a static method, which requires the use of the class name

If your listener callback is an ordinary method and not a static method, the syntax is:

```
addlistener(EventObject, 'PropOne', 'PostSet',@obj.handlePropertyEvents);
```

where *obj* is the handle of the object defining the callback method.

If the listener callback is a function that is not a class method, you pass a function handle to that function. Suppose the callback function is a package function:

```
addlistener(EventObject, 'PropOne', 'PostSet',@package.handlePropertyEvents);
```

See function handle for more information on passing functions as arguments.

Property Event and Listener Classes

The following two classes show how to create PostSet property listeners for two properties — PropOne and PropTwo.

Class Generating the Event

The PropEvent class enables property PreSet and PostSet event triggering by specifying the SetObservable property attribute. These properties also enable the AbortSet attribute, which prevents the triggering of the property events if the properties are set to a value that is the same as their current value (see "Aborting Set When Value Does Not Change" on page 10-32)

```
classdef PropEvent < handle
  properties (SetObservable, AbortSet)
     PropOne
     PropTwo
end
methods
  function obj = PropEvent(p1,p2)
     if nargin > 0
        obj.PropOne = p1;
        obj.PropTwo = p2;
     end
end
end
```

end

Class Defining the Listeners

The PropListener class defines two listeners:

- Property PropOne PostSet event
- Property PropTwo PostSet event

You could define listeners for other events or other properties using a similar approach and it is not necessary to use the same callback function for each listener. See the meta.property and event.PropertyEvent reference pages for more on the information contained in the arguments passed to the listener callback function.

```
classdef PropListener < handle</pre>
   % Define property listeners
   methods
      function obj = PropListener(evtobj)
         if nargin > 0
            addlistener(evtobj,'PropOne','PostSet',@PropListener.handlePropEvents);
            addlistener(evtobj, 'PropTwo', 'PostSet', @PropListener.handlePropEvents);
      end
   end
   methods (Static)
      function handlePropEvents(src,evnt)
         switch src.Name
            case 'PropOne'
               sprintf('PropOne is %s\n',num2str(evnt.AffectedObject.PropOne))
            case 'PropTwo'
               sprintf('PropTwo is %s\n',num2str(evnt.AffectedObject.PropTwo))
         end
      end
   end
end
```

Aborting Set When Value Does Not Change

By default, MATLAB triggers the property PreSet and PostSet events, invokes the property's set method (if defined), and sets the property value, even when the current value of the property is the same as the new value. You can prevent this behavior by setting the property's AbortSet attribute to true. When AbortSet is true, MATLAB does not:

- · Set the property value
- Trigger the PreSet and PostSet events

Call the property's set method, if one exists

When AbortSet is true, MATLAB gets the current property value to compare it to the value you are assigning to the property. This causes the property get method (get.Property) to execute, if one exists. However, MATLAB does not catch errors resulting from the execution of this method and these errors are visible to the user.

When to Use AbortSet

Consider using AbortSet only when the cost of setting a property value is much greater than the cost of always comparing the current value of the property with the new value being assigned.

How AbortSet Works

The following example shows how the AbortSet attribute works. The AbortTheSet class defines a property, PropOne, that has listeners for the PreGet and PreSet events and enables the AbortSet attribute. The behavior of the post set/get events is equivalent so only the pre set/get events are used for simplicity:

Note: Save the AbortTheSet class in a file with the same name in a folder on your MATLAB path.

```
classdef AbortTheSet < handle</pre>
   properties (SetObservable, GetObservable, AbortSet)
      PropOne = 7
   end
   methods
      function obj = AbortTheSet(val)
         obj.PropOne = val;
         addlistener(obj, 'PropOne', 'PreGet', @obj.getPropEvt);
         addlistener(obj, 'PropOne', 'PreSet', @obj.setPropEvt);
      end
      function propval = get.PropOne(obj)
         disp('get.PropOne called')
         propval = obj.PropOne;
      function set.PropOne(obj,val)
         disp('set.PropOne called')
         obj.PropOne = val;
      end
```

```
function getPropEvt(obj,src,evnt)
    disp ('Pre-get event triggered')
    % ...
end
function setPropEvt(obj,src,evnt)
    disp ('Pre-set event triggered')
    % ...
end
function disp(obj)
    % Overload disp to avoid accessing property
    disp (class(obj))
    end
end
end
```

The class specifies an initial value of 7 for the PropOne property. Therefore, if you create an object with the property value of 7, there is not need to trigger the PreSet event:

```
ats = AbortTheSet(7);
get.PropOne called
```

If you specify a value other than 7, then MATLAB triggers the PreSet event:

```
ats = AbortTheSet(9);
get.PropOne called
set.PropOne called
get.PropOne called
```

Similarly, if you set the PropOne property to the value 9, the AbortSet attribute prevents the property assignment and the triggering of the PreSet event. Notice also, that there is no PreGet event generated. Only the property get method is called:

```
ats.PropOne = 9;
get.PropOne called
```

If you query the property value, the PreGet event is triggered:

```
a = ats.PropOne
Pre-get event triggered
get.PropOne called
a =
```

9

If you set the PropOne property to a different value, MATLAB:

- Calls the property get method to determine if the value is changing
- Triggers the PreSet event
- · Calls the property set method to set the new value
- Calls the property get method again to determine if the result of calling the set method changed the value.

```
ats.PropOne = 11;
```

```
get.PropOne called
Pre-set event triggered
set.PropOne called
get.PropOne called
```

Because a property set method might modify the value that is actually assigned to a property, MATLAB must query the property value that would result from an assignment after a call the property's set method. This results in multiple calls to a property get method, if one is defined for that property.

Update Graphs Using Events and Listeners

In this section...

"Example Overview" on page 10-36

"Techniques Demonstrated in This Example" on page 10-37

"Summary of fcneval Class" on page 10-37

"Summary of fcnview Class" on page 10-38

"Methods Inherited from Handle Class" on page 10-40

"Using the feneval and fenview Classes" on page 10-40

"Implementing the UpdateGraph Event and Listener" on page 10-42

"The PostSet Event Listener" on page 10-46

"Enabling and Disabling the Listeners" on page 10-49

"@fcneval/fcneval.m Class Code" on page 10-50

"@fcnview/fcnview.m Class Code" on page 10-51

Example Overview


This example defines two classes:

- fcneval The function evaluator class contains a MATLAB expression and evaluates this expression over a specified range
- fcnview The function viewer class contains a fcneval object and displays surface graphs of the evaluated expression using the data contained in fcneval.

This class defines two events:

- A class-defined event that occurs when a new value is specified for the MATLAB function
- A property event that occurs when the property containing the limits is changed

The following diagram shows the relationship between the two objects. The fcnview object contains a fcneval object and creates graphs from the data it contains. fcnview creates listeners to change the graphs if any of the data in the fcneval object change.



Techniques Demonstrated in This Example

- · Naming an event in the class definition
- Triggering an event by calling notify
- Enabling a property event via the SetObservable attribute
- Creating listeners for class-defined events and property PostSet events
- Defining listener callback functions that accept additional arguments
- Enabling and disabling listeners

Summary of fcneval Class

The fcneval class evaluates a MATLAB expression over a specified range of two variables. The fcneval is the source of the data that objects of the fcnview class graph as a surfaces. fcneval is the source of the events used in this example. For a listing of the class definition, see "@fcneval/fcneval.m Class Code" on page 10-50

Property	Value	Purpose
FofXY	function handle	MATLAB expression (function of two variables).
Lm	two-element vector	Limits over which function is evaluated in both variables. SetObservable attribute set to true to enable property event listeners.
Data	structure with x, y, and z matrices	Data resulting from evaluating the function. Used for surface graph. Dependent attribute set to true, which means the get.Data method is called to determine property value when queried and no data is stored.

Event	When Triggered
	FOfXY property set function (set.FofXY) calls the notify method when a new value is specified for the MATLAB expression on an object of this class.

Method	Purpose
fcneval	Class constructor. Inputs are function handle and two-element vector specifying the limits over which to evaluate the function.
set.FofXY	FofXY property set function. Called whenever property value is set, including during object construction.
set.Lm	Lm property set function. Used to test for valid limits.
get.Data	Data property get function. This method calculates the values for the Data property whenever that data is queried (by class members or externally).
grid	A static method (Static attribute set to true) used in the calculation of the data.

Summary of fcnview Class

Objects of the fcnview class contain fcneval objects as the source of data for the four surface graphs created in a function view. fcnview creates the listeners and callback functions that respond to changes in the data contained in fcneval objects. For a listing of the class definition, see "@fcnview/fcnview.m Class Code" on page 10-51

Property	Value	Purpose
FcnObject	fcneval object	This object contains the data that is used to create the function graphs.
HAxes	axes handle	Each instance of a fcnview object stores the handle of the axes containing its subplot.
HLUpdateGraph	event.listener object for UpdateGraph event	Setting the event.listener object's Enabled property to true enables the listener; false disables listener.
HLLm	event.listener object for Lm property event	Setting the event.listener object's Enabled property to true enables the listener, false disables listener.
HEnableCm	uimenu handle	Item on context menu used to enable listeners (used to handle checked behavior)
HDisableCm	uimenu handle	Item on context menu used to disable listeners (used to manage checked behavior)
HSurface	surface handle	Used by event callbacks to update surface data.

Method	Purpose
fcnview	Class constructor. Input is fcneval object.
createLisn	Calls addlistener to create listeners for UpdateGraph and Lm property PostSet listeners.
lims	Sets axes limits to current value of fcneval object's Lm property. Used by event handlers.
updateSurfaceData	Updates the surface data without creating a new object. Used by event handlers.
listenUpdateGraph	Callback for UpdateGraph event.
listenLm	Callback for Lm property PostSet event
delete	Delete method for fcnview class.
createViews	Static method that creates an instance of the fcnview class for each subplot, defines the context menus that enable/disable listeners, and creates the subplots

Methods Inherited from Handle Class

Both the fcneval and fcnview classes inherit methods from the handle class. The following table lists only those inherited methods used in this example.

"Handle Class Methods" on page 6-12 provides a complete list of methods that are inherited when you subclass the handle class.

Methods Inherited from Handle Class	Purpose
addlistener	Register a listener for a specific event and attach listener to event-defining object.
notify	Trigger an event and notify all registered listeners.

Using the fcneval and fcnview Classes

This sections explains how to use the classes.

- Create an instance of the fcneval class to contain the MATLAB expression of a function of two variables and the range over which you want to evaluate this function
- Use the fcnview class static function createViews to visualize the function
- Change the MATLAB expression or the limits contained by the fcneval object and all the fcnview objects respond to the events generated.


You create a fcneval object by calling its constructor with two arguments—an anonymous function and a two-element, monotonically increasing vector. For example:

```
feobject = fcneval(@(x,y) x.*exp(-x.^2-y.^2),[-2 2]);
```


Use the createViews static method to create the graphs of the function. Note that you must use the class name to call a static function:


```
fcnview.createViews(feobject);
```

The createView method generates four views of the function contained in the fcneval object.




Each subplot defines a context menu that can enable and disable the listeners associated with that graph. For example, if you disable the listeners on subplot 221 (upper left) and change the MATLAB expression contained by the fcneval object, only the remaining three subplots update when the UpdateGraph event is triggered:





Similarly, if you change the limits by assigning a value to the feobject.Lm property, the feobject triggers a PostSet property event and the listener callbacks update the graph.

feobject.Lm = $[-8 \ 3];$




In this figure the listeners are re-enabled via the context menu for subplot 221. Because the listener callback for the property PostSet event also updates the surface data, all views are now synchronized

Implementing the UpdateGraph Event and Listener

The UpdateGraph event occurs when the MATLAB representation of the mathematical function contained in the fcneval object is changed. The fcnview objects that contain the surface graphs are listening for this event, so they can update the graphs to represent the new function.

Defining and Firing the UpdateGraph Event

The UpdateGraph event is a class-defined event. The fcneval class names the event and calls notify when the event occurs.



The fcnview class defines a listener for this event. When fcneval triggers the event, the fcnview listener executes a callback function that performs the follow actions:

- Determines if the handle of the surface object stored by the fcnview object is still valid (that is, does the object still exist)
- Updates the surface XData, YData, and ZData by querying the fcneval object's Data property.

The fcneval class defines an event name in an event block:

```
events
UpdateGraph
end
```

Determining When to Trigger the Event

The fcneval class defines a property set method for the FofXY property. FofXY is the property that stores the MATLAB expression for the mathematical function. This expression must be a valid MATLAB expression for a function of two variables.

The set.FofXY method:

- Determines the suitability of the expression
- If the expression is suitable:
 - Assigns the expression to the FofXY property
 - Triggers the UpdateGraph event

If fcneval.isSuitable does not return an MException object, the set.FofXY method assigns the value to the property and triggers the UpdateGraph event.

```
function set.FofXY(obj,func)
% Determine if function is suitable to create a surface
   me = fcneval.isSuitable(func);
   if ~isempty(me)
        throw(me)
   end
% Assign property value
   obj.FofXY = func;
% Trigger UpdateGraph event
   notify(obj,'UpdateGraph');
end
```

Determining Suitability of the Expression

The set.FofXY method calls a static method (fcneval.isSuitable) to determine the suitability of the specified expression. fcneval.isSuitable returns an MException object if it determines that the expression is unsuitable. fcneval.isSuitable calls the MException constructor directly to create more useful error messages for the user.

set.FofXY issues the exception using the MException.throw method. Issuing the exception terminates execution of set.FofXY and prevents the method from making an assignment to the property or triggering the UpdateGraph event.

Here is the fcneval.isSuitable method:

```
function isOk = isSuitable(funcH)
   v = [1 \ 1;1 \ 1];
   % Can the expression except 2 numeric inputs
      funcH(v,v);
   catch %#ok<CTCH>
      me = MException('DocExample:fcneval',...
         ['The function ',func2str(funcH),' Is not a suitable F(x,y)']);
      isOk = me;
      return
   end
   % Does the expression return non-scalar data
   if isscalar(funcH(v,v));
      me = MException('DocExample:fcneval',...
['The function ',func2str(funcH),'' Returns a scalar when evaluated']);
      isOk = me;
      return
   end
   is0k = [];
end
```

The fcneval.isSuitable method could provide additional test to ensure that the expression assigned to the FofXY property meets the criteria required by the class design.

Other Approaches

The class could have implemented a property set event for the FofXY property and would, therefore, not need to call notify (see "Listen for Changes to Property Values" on page 10-29). Defining a class event provides more flexibility in this case because you can better control event triggering.

For example, suppose you wanted to update the graph only if the new data is significantly different. If the new expression produced the same data within some tolerance, the set.FofXY method could not trigger the event and avoid updating the graph. However, the method could still set the property to the new value.

Defining the Listener and Callback for the UpdateGraph Event

The fcnview class creates a listener for the UpdateGraph event using the addlistener method:

```
obj.HLUpdateGraph = addlistener(obj.FcnObject,'UpdateGraph',...
@(src,evnt)listenUpdateGraph(obj,src,evnt)); % Add obj to argument list
```

The fcnview object stores a handle to the event.listener object in its HLUpdateGraph property, which is used to enable/disable the listener by a context menu (see "Enabling and Disabling the Listeners" on page 10-49).

The fcnview object (obj) is added to the two default arguments (src, evnt) passed to the listener callback. Keep in mind, the source of the event (src) is the fcneval object, but the fcnview object contains the handle of the surface object that is updated by the callback.

The listenUpdateGraph function is defined as follows:


```
function listenUpdateGraph(obj,src,evnt)
  if ishandle(obj.HSurface) % If surface exists
    obj.updateSurfaceData % Update surface data
  end
end
```

The updateSurfaceData function is a class method that updates the surface data when a different mathematical function is assigned to the fcneval object. Updating a graphics object data is generally more efficient than creating a new object using the new data:

```
function updateSurfaceData(obj)
% Get data from fcneval object and set surface data
    set(obj.HSurface,...
        'XData',obj.FcnObject.Data.X,...
        'YData',obj.FcnObject.Data.Y,...
        'ZData',obj.FcnObject.Data.Matrix);
end
```

The PostSet Event Listener

All properties support the predefined PostSet event (See "Property-Set and Query Events" on page 10-14 for more information on property events). This example uses the PostSet event for the fcneval Lm property. This property contains a two-element vector specifying the range over which the mathematical function is evaluated. Just after this property is changed (by a statement like obj.Lm = [-3 5];), the fcnview objects listening for this event update the graph to reflect the new data.



Sequence During the Lm Property Assignment

The fcneval class defines a set function for the Lm property. When a value is assigned to this property during object construction or property reassignment, the following sequence occurs:

- 1 An attempt is made to assign argument value to Lm property.
- 2 The set.Lm method executes to check whether the value is in appropriate range—if yes, it makes assignment, if no, it generates an error.
- **3** If the value of Lm is set successfully, the MATLAB runtime triggers a PostSet event.
- **4** All listeners execute their callbacks, but the order is nondeterministic.

The PostSet event does not occur until an actual assignment of the property occurs. The property set function provides an opportunity to deal with potential assignment errors before the PostSet event occurs.

Enabling the PostSet Property Event

To create a listener for the PostSet event, you must set the property's SetObservable attribute to true:

```
properties (SetObservable = true)
   Lm = [-2*pi 2*pi]; % specifies default value
end
```

The MATLAB runtime automatically triggers the event so it is not necessary to call notify.

"Specify Property Attributes" on page 7-5 provides a list of all property attributes.

Defining the Listener and Callback for the PostSet Event

The fcnview class creates a listener for the PostSet event using the addlistener method:

```
obj.HLLm = addlistener(obj.FcnObject,'Lm','PostSet',...
    @(src,evnt)listenLm(obj,src,evnt)); % Add obj to argument list
```

The fcnview object stores a handle to the event.listener object in its HLLm property, which is used to enable/disable the listener by a context menu (see "Enabling and Disabling the Listeners" on page 10-49).

The fcnview object (Obj) is added to the two default arguments (src, evnt) passed to the listener callback. Keep in mind, the source of the event (src) is the fcneval object, but the fcnview object contains the handle of the surface object that is updated by the callback.

The callback sets the axes limits and updates the surface data because changing the limits causes the mathematical function to be evaluated over a different range:

```
function listenLm(obj,src,evnt)
  if ishandle(obj.HAxes) % If there is an axes
      lims(obj); % Update its limits
    if ishandle(obj.HSurface) % If there is a surface
      obj.updateSurfaceData % Update its data
    end
end
```

end

Enabling and Disabling the Listeners

Each fcnview object stores the handle of the listener objects it creates so that the listeners can be enabled or disabled via a context menu after the graphs are created. All listeners are instances of the event.listener class, which defines a property called Enabled. By default, this property has a value of true, which enables the listener. If you set this property to false, the listener still exists, but is disabled. This example creates a context menu active on the axes of each graph that provides a way to change the value of the Enabled property.

Context Menu Callback

There are two callbacks used by the context menu corresponding to the two items on the menu:

- **Listen** Sets the **Enabled** property for both the **UpdateGraph** and **PostSet** listeners to **true** and adds a check mark next to the **Listen** menu item.
- **Don't Listen** Sets the **Enabled** property for both the **UpdateGraph** and **PostSet** listeners to **false** and adds a check mark next to the **Don't Listen** menu item.

Both callbacks include the fcnview object as an argument (in addition to the required source and event data arguments) to provide access to the handle of the listener objects.

The enableLish function is called when the user selects **Listen** from the context menu.

```
function enableLisn(obj,src,evnt)
  obj.HLUpdateGraph.Enabled = true; % Enable listener
  obj.HLLm.Enabled = true; % Enable listener
  set(obj.HEnableCm,'Checked','on') % Check Listen
  set(obj.HDisableCm,'Checked','off') % Uncheck Don't Listen
end
```

The disableLisn function is called when the user selects **Don't Listen** from the context menu.

```
function disableLisn(obj,src,evnt)
  obj.HLUpdateGraph.Enabled = false; % Disable listener
  obj.HLLm.Enabled = false; % Disable listener
  set(obj.HEnableCm,'Checked','off') % Unheck Listen
  set(obj.HDisableCm,'Checked','on') % Check Don't Listen
end
```

@fcneval/fcneval.m Class Code

```
classdef fcneval < handle</pre>
   properties
      FofXY
   end
   properties (SetObservable = true)
      Lm = [-2*pi 2*pi];
   end % properties SetObservable = true
   properties (Dependent = true)
      Data
   end
   events
      UpdateGraph
   end
   methods
      function obj = fcneval(fcn_handle,limits) % Constructor returns object
         if nargin > 0
            obj.FofXY = fcn_handle;
                                                      % Assign property values
            obj.Lm = limits;
         end
      end
      function set.FofXY(obj,func)
         me = fcneval.isSuitable(func);
         if ~isempty(me)
            throw(me)
         end
         obj.FofXY = func;
         notify(obj,'UpdateGraph');
      end
      function set.Lm(obj,lim)
         if \sim (\lim(1) < \lim(2))
            error('Limits must be monotonically increasing')
         else
            obj.Lm = lim;
         end
      end
```

```
function data = get.Data(obj)
         [x,y] = fcneval.grid(obj.Lm);
         matrix = obj.FofXY(x,y);
         data.X = x;
         data.Y = y;
         data.Matrix = real(matrix);
      end
   end % methods
   methods (Static = true)
      function [x,y] = grid(lim)
         inc = (\lim(2) - \lim(1))/20;
         [x,y] = meshgrid(lim(1):inc:lim(2));
      end % grid
      function is0k = isSuitable(funcH)
         v = [1 \ 1; 1 \ 1];
         try
            funcH(v,v);
         catch %#ok<CTCH>
            me = MException('DocExample:fcneval',...
               ['The function ',func2str(funcH),' Is not a suitable F(x,y)']);
            isOk = me;
            return
         end
         if isscalar(funcH(v,v));
            me = MException('DocExample:fcneval',...
               ['The function ',func2str(funcH),' Returns a scalar when evaluated']);
            isOk = me;
            return
         end
         is0k = [];
      end
   end
end
```

@fcnview/fcnview.m Class Code

```
classdef fcnview < handle</pre>
```

```
properties
                 % fcneval object
  FcnObject
                 % subplot axes handle
  HAxes
  HLUpdateGraph % UpdateGraph listener handle
  HLLm
                 % Lm property PostSet listener handle
               % "Listen" context menu handle
  HEnableCm
  HDisableCm % "Don't Listen" context menu handle
  HSurface
                 % Surface object handle
end
methods
  function obj = fcnview(fcnobj)
      if nargin > 0
         obj.FcnObject = fcnobj;
         obj.createLisn;
      end
   end
   function createLisn(obj)
      obj.HLUpdateGraph = addlistener(obj.FcnObject, 'UpdateGraph',...
         @(src,evnt)listenUpdateGraph(obj,src,evnt));
      obj.HLLm = addlistener(obj.FcnObject, 'Lm', 'PostSet',...
         @(src,evnt)listenLm(obj,src,evnt));
   end
   function lims(obj)
      lmts = obj.FcnObject.Lm;
      set(obj.HAxes,'XLim',lmts);
      set(obj.HAxes,'Ylim',lmts);
   end
   function updateSurfaceData(obj)
      data = obj.FcnObject.Data;
      set(obj.HSurface,...
         'XData',data.X,...
         'YData',data.Y,...
         'ZData', data. Matrix);
   end
   function listenUpdateGraph(obj,~,~)
      if ishandle(obj.HSurface)
         obj.updateSurfaceData
      end
   end
```

```
function listenLm(obj,~,~)
         if ishandle(obj.HAxes)
            lims(obj);
            if ishandle(obj.HSurface)
               obj.updateSurfaceData
            end
         end
      end
      function delete(obj)
         if ishandle(obj.HAxes)
            delete(obj.HAxes);
         else
            return
         end
      end
   end
   methods (Static)
      createViews(a)
   end
end
@fcnview/createViews
function createViews(fcnevalobj)
   p = pi; deg = 180/p;
   hfig = figure('Visible','off',...
      'Toolbar', 'none');
   for k=4:-1:1
      fcnviewobj(k) = fcnview(fcnevalobj);
      axh = subplot(2,2,k);
      fcnviewobj(k).HAxes = axh;
      hcm(k) = uicontextmenu;
      set(axh, 'Parent', hfig,...
         'FontSize',8,...
         'UIContextMenu', hcm(k))
      fcnviewobj(k).HEnableCm = uimenu(hcm(k),...
         'Label','Listen',...
         'Checked', 'on',...
         'Callback',@(src,evnt)enableLisn(fcnviewobj(k),src,evnt));
      fcnviewobj(k).HDisableCm = uimenu(hcm(k),...
         'Label', 'Don''t Listen',...
```

```
'Checked', 'off',...
         'Callback',@(src,evnt)disableLisn(fcnviewobj(k),src,evnt));
      az = p/k*deg;
      view(axh,az,30)
      title(axh,['View: ',num2str(az),' 30'])
      fcnviewobj(k).lims;
      surfLight(fcnviewobj(k),axh)
   end
   set(hfig, 'Visible', 'on')
end
function surfLight(obj,axh)
   obj.HSurface = surface(obj.FcnObject.Data.X,...
      obj.FcnObject.Data.Y,...
      obj.FcnObject.Data.Matrix,...
      'FaceColor',[.8 .8 0], 'EdgeColor',[.3 .3 .2],...
      'FaceLighting','phong',...
      'FaceAlpha',.3,...
      'HitTest','off',...
      'Parent', axh);
   lims(obj)
   camlight left; material shiny; grid off
   colormap copper
end
function enableLisn(obj,~,~)
   obj.HLUpdateGraph.Enabled = true;
   obj.HLLm.Enabled = true;
   set(obj.HEnableCm, 'Checked', 'on')
   set(obj.HDisableCm, 'Checked', 'off')
end
function disableLisn(obj,~,~)
   obj.HLUpdateGraph.Enabled = false;
   obj.HLLm.Enabled = false;
   set(obj.HEnableCm, 'Checked', 'off')
   set(obj.HDisableCm, 'Checked', 'on')
end
```

Building on Other Classes

- "Hierarchies of Classes Concepts" on page 11-2
- "Creating Subclasses Syntax and Techniques" on page 11-7
- "Sequence of Constructor Calls in Class Hierarchy" on page 11-13
- "Modify Superclass Methods" on page 11-15
- "Modify Superclass Properties" on page 11-18
- "Subclassing Multiple Classes" on page 11-20
- "Specify Allowed Subclasses" on page 11-22
- "Control Access to Class Members" on page 11-25
- "Property Access List" on page 11-33
- "Method Access List" on page 11-34
- "Event Access List" on page 11-35
- "Supporting Both Handle and Value Subclasses" on page 11-36 $\,$
- "Subclassing MATLAB Built-In Types" on page 11-44
- "Behavior of Inherited Built-In Methods" on page 11-48
- "Built-In Subclass Without Properties" on page 11-53
- "Built-In Subclass With Properties" on page 11-61
- "Understanding size and numel" on page 11-67
- "Class to Represent Hardware" on page 11-73
- "Determine Array Class" on page 11-76
- "Abstract Classes" on page 11-80
- "Interfaces" on page 11-84

Hierarchies of Classes — Concepts

In this section...

"Classification" on page 11-2

"Developing the Abstraction" on page 11-3


"Designing Class Hierarchies" on page 11-4

"Super and Subclass Behavior" on page 11-4

"Implementation and Interface Inheritance" on page 11-5

Classification

Organizing classes into hierarchies facilitates the reuse of code and the reuse of solutions to design problems that have already been solved. You can think of class hierarchies as sets — supersets (referred to as *superclasses* or *base classes*), and subsets (referred to as *subclasses* or *derived classes*). For example, the following picture shows how you could represent an employee database with classes.



At the root of the hierarchy is the Employees class. It contains data and operations that apply to the set of all employees. Contained in the set of employees are subsets whose members, while still employees, are also members of sets that more specifically define the type of employee. Subclasses like TestEngineer are examples of these subsets.

Developing the Abstraction

Classes are representations of real world concepts or things. When designing a class, form an abstraction of what the class represents. Consider an abstraction of an employee and what are the essential aspects of employees for the intended use of the class. Name, address, and department can be what all employees have in common.

When designing classes, your abstraction should contain only those elements that are necessary. For example, the employee hair color and shoe size certainly characterize the employee, but are probably not relevant to the design of this employee class. Their sales region is relevant only to some employee so this characteristic belongs in a subclass.

Designing Class Hierarchies

As you design a system of classes, put common data and functionality in a superclass, which you then use to derive subclasses. The subclasses inherit the data and functionality of the superclass and define only aspects that are unique to their particular purposes. This approach provides advantages:

- Avoid duplicating code that is common to all classes.
- Add or change subclasses at any time without modifying the superclass or affecting other subclasses.
- If the superclass changes (for example, all employees are assigned a number), then subclass automatically get these changes.

Super and Subclass Behavior

Subclass objects behave like objects of the superclass because they are specializations of the superclass. This fact facilitates the development of related classes that behave similarly, but are implemented differently.

A Subclass Object "Is A" Superclass Object

You can usually describe the relationship between an object of a subclass and an object of its superclass with a statement like:

The subclass is a superclass . For example: An Engineer is an Employee.

This relationship implies that objects belonging to a subclass have the same properties, methods, and events as the superclass, as well as any new features defined by the subclass. Test this relationship with the <code>isa</code> function.

Treat Subclass Objects Like Superclass Objects

You can pass a subclass object to a superclass method, but you can access only those properties that the superclass defines. This behavior enables you to modify the subclasses without affecting the superclass.

Two points about super and subclass behavior to keep in mind are:

- Methods defined in the superclass can operate on subclass objects.
- Methods defined in the subclass cannot operate on superclass objects.

Therefore, you can treat an Engineer object like any other Employees object, but an Employee object cannot pass for an Engineer object.

Limitations to Object Substitution

MATLAB determines the class of an object based on its most specific class. Therefore, an Engineer object is of class Engineer, while it is also an Employees object, as using the isa function reveals.

Generally, MATLAB does not allow you to create arrays containing a mix of superclass and subclass objects because an array can be of only one class. If you attempt to concatenate objects of different classes, MATLAB looks for a converter method defined by the less dominant class (usually, the left-most object in the expression is the dominant class).

See "Concatenating Objects of Different Classes" on page 9-15 for more information.

See matlab.mixin.Heterogeneous for information on defining heterogeneous class hierarchies.

See "Object Converters" on page 16-8 for information on defining converter methods.

Implementation and Interface Inheritance

MATLAB classes support both the inheritance of implemented methods from a superclass and the inheritance of interfaces defined by abstract methods in the superclass.

Implementation inheritance enables code reuse by subclasses. For example, an employee class can have a submitStatus method that all employee subclasses can use. Subclasses can extend an inherited method to provide specialized functionality, while reusing the common aspects. See "Modify Superclass Methods" on page 11-15 for more information on this process.

Interface inheritance is useful in cases where you want a group of classes to provide a common interface, but these classes create specialized implementations of methods and properties that define the interface.

Create an interface using an abstract class as the superclass. This class defines the methods and properties that you must implement in the subclasses, but does not provide an implementation.

The subclasses must provide their own implementation of the abstract members of the superclass. To create an interface, define methods and properties as abstract using their Abstract attribute.

See "Abstract Classes" on page 11-80 for more information and an example.

Creating Subclasses — Syntax and Techniques

In this section...

"Defining a Subclass" on page 11-7

"Initializing Superclasses from Subclasses" on page 11-7

"Calling Superclass Constructor Explicitly" on page 11-9

"Constructor Arguments and Object Initialization" on page 11-9

"Call Only Direct Superclass from Constructor" on page 11-10

"Subclass Alias for Existing Class" on page 11-11

Defining a Subclass

To define a class that is a subclass of another class, add the superclass to the classdef line after a < character:

```
classdef ClassName < SuperClass</pre>
```

When inheriting from multiple classes, use the & character to indicate the combination of the superclasses:

```
classdef ClassName < SuperClass1 & SuperClass2</pre>
```

See "Class Member Compatibility" on page 11-20 for more information on deriving from multiple superclasses.

Class Attributes

Subclasses do not inherit superclass attributes.

Initializing Superclasses from Subclasses

Use the following syntax to initialize the object for each superclass within the subclass constructor.

```
obj@SuperClass1(args,...);
...
obj@SuperclassN(args,...);
```

Where *obj* is the output of the constructor, *SuperClass...* is the name of a superclass, and *args* are any arguments required by the respective superclass constructor.

For example, the following segment of a class definition shows a class called **stock** that is a subclass of a class called **asset**.

```
classdef stock < asset
  methods
    function s = stock(asset_args,...)
    if nargin == 0
        ... % Assign values to asset_args
    end
    % Call asset constructor
    s@asset(asset_args);
    ...
  end
end
end</pre>
```

"Constructing Subclasses" on page 8-18 provides more information on creating subclass constructor methods.

Referencing Superclasses Contained in Packages

If a superclass is contained in a package, include the package name. For example:

```
classdef stock < financial.asset
  methods
    function s = stock(asset_args,...)
    if nargin == 0
        ...
    end
    % Call asset constructor
    s@financial.asset(asset_args);
    ...
  end
  end
end
end</pre>
```

Initializing Objects When Using Multiple Superclasses

To derive a class from multiple superclasses, initialize the subclass object with calls to each superclass constructor:

```
classdef stock < financial.asset & trust.member</pre>
```

Calling Superclass Constructor Explicitly

Explicitly calling each superclass constructor enables you to:

- Pass arguments to superclass constructors
- Control the order in which the superclass constructors are called

If you do not explicitly call the superclass constructors from the subclass constructor, MATLAB implicitly calls these constructors with no arguments. In this case, the superclass constructors must support no argument syntax.

In the case of multiple superclasses, MATLAB does not guarantee any specific calling sequence. If the order in which MATLAB calls the superclass constructors is important, you must explicitly call the superclass constructors from the subclass constructor.

Constructor Arguments and Object Initialization

You cannot conditionalize the object initialization calls to the superclass. Locate calls to superclass constructors outside any conditional code blocks.

Ensure that your class constructor supports the zero arguments syntax. Satisfy the need for a zero-argument syntax by assigning appropriate values to input argument variables before constructing the object:

For example, the Stock class constructor supports the no argument case with the if statement, but initializes the object for the superclass outside of the if code block.

```
classdef stock < financial.asset
  properties</pre>
```

```
SharePrice
   end
   methods
      function s = stock(name,pps)
         % Support no input argument case
         if nargin == 0
            name = '';
            pps = 0;
         end
         % Call superclass constructor
         s@financial.asset(name)
         % Assign property value
         s.SharePrice = pps;
      end
   end
end
```

Call Only Direct Superclass from Constructor

You cannot call an indirect superclass constructor from a subclass constructor. For example, suppose class B derives from class A and class C derives from class B. The constructor for class C cannot call the constructor for class A to initialize properties. Class B must make the call to initialize class A properties.

The following implementations of classes A, B, and C show how to design this relationship in each class.

Class A defines properties x and y, but assigns a value only to x:

Class B inherits properties x and y from class A. The class B constructor calls the class A constructor to initialize x and then assigns a value to y.

Class C accepts values for the properties X and Y, and passes these values to the class B constructor, which in turn calls the class A constructor:

Subclass Alias for Existing Class

You can refer to a class using a different name by creating an alias for that class. This technique is like the C++ typedef concept. To create an alias, create an empty subclass:

```
classdef NewClassName < OldClassName
end</pre>
```

The old class constructor must be callable with zero input arguments.

This technique is useful when reloading objects that you saved using the old class name. However, the class of the object reflects the new name. That is, this code returns the new class name.

```
class(obj)
```

Old Class Constructor Requires Arguments

If the old class constructor requires arguments, add a constructor to the new class:

```
classdef NewClass < OldClass
  methods</pre>
```

Related Examples


"No Input Argument Constructor Requirement"

Sequence of Constructor Calls in Class Hierarchy


MATLAB does not guarantee the sequence in which superclass constructors are called when constructing a subclass object. However, you can control the order in which class constructors are called by calling superclass constructors explicitly from the subclass constructor.

If you explicitly call a superclass constructor from the most specific subclass constructor, then MATLAB calls the most specific subclass constructor first. If you do not make an explicit call to a superclass constructor from the subclass constructor, MATLAB makes the implicit call before accessing the object.

Suppose you have a hierarchy of classes in which ClassC derives from ClassB, which derives from ClassA. The constructor for a subclass can call only direct superclasses. Therefore, each class constructor can call the direct superclass constructor:



In cases of multiple inheritance, the subclass constructor can call each superclass constructor. To ensure a specific superclass constructor calling sequence is followed, your most specific subclass constructor must explicitly call ALL superclass constructors:



If you do not explicitly call all direct superclass constructors, MATLAB does not guarantee the order in which the superclass constructors are called.

Related Examples

• "Class Constructor Methods"

Modify Superclass Methods

```
In this section...

"When to Modify Superclass Methods" on page 11-15

"Extend Superclass Methods" on page 11-15

"Completing Superclass Methods" on page 11-16

"Redefining Superclass Methods" on page 11-17
```

When to Modify Superclass Methods

An important concept in class design is that a subclass object is also an object of its superclass. Therefore, you can pass a subclass object to a superclass method and have the method execute properly. At the same time, you can apply special processing to the unique aspects of the subclass. Some useful techniques include:

- Calling a superclass method from within a subclass method
- Redefining in the subclass protected methods called from within a public superclass method
- Defining the same named methods in both super and subclass, but using different implementations

Extend Superclass Methods

Subclass methods can call superclass methods of the same name. This fact enables you to extend a superclass method in a subclass without completely redefining the superclass method. For example, suppose that both superclass and subclass defines a method called foo. The method names are the same so the subclass method can call the superclass method. However, the subclass method can also perform other steps before and after the call to the superclass method. It can operate on the specialized parts to the subclass that are not part of the superclass.

For example, this subclass defines a foo method, which calls the superclass foo method

```
classdef sub < super
  methods
    function foo(obj)
    % preprocessing steps
    foo@super(obj);</pre>
```

```
% postprocessing steps
    end
  end
end
```

Completing Superclass Methods

A superclass method can define a process that executes in a series of steps using a protected method for each step (Access attribute set to protected). Subclasses can then create their own versions of the protected methods that implement the individual steps in the process.

Implement this technique as shown here:

```
classdef super
  methods
    function foo(obj)
       step1(obj)
       step2(obj)
       step3(obj)
    end
end
methods (Access = protected)
    function step1(obj)
       % superclass version
    end
    ...
end
end
```

The subclass does not reimplement the foo method, it reimplements only the methods that carry out the series of steps (step1(obj), step2(obj), step3(obj)). That is, the subclass can specialize the actions taken by each step, but does not control the order of the steps in the process. When you pass a subclass object to the superclass foo method, MATLAB calls the subclass step methods because of the dispatching rules.

```
classdef sub < super
...
methods (Access = protected)
function step1(obj)
% subclass version
end
...</pre>
```

end end

Redefining Superclass Methods

You can completely redefine a superclass method. In this case, both the superclass and the subclass would define the same named method.

Related Examples

"Invoking Superclass Methods in Subclass Methods"

Modify Superclass Properties

```
In this section...

"Allowed Superclass Property Modification" on page 11-18

"Private Local Property Takes Precedence in Method" on page 11-18
```

Allowed Superclass Property Modification

There are two separate conditions under which you can redefine superclass properties:

- The value of the superclass property Abstract attribute is true
- The values of the superclass property SetAccess and GetAccess attributes are private

In the first case, the superclass is just requesting that you define a concrete version of this property to ensure a consistent interface. In the second case, only the superclass can access the private property, so the subclass is free to reimplement it in any way.

Private Local Property Takes Precedence in Method

When a subclass property has the same name as a superclass private property, and a method of the superclass references the property name, MATLAB always accesses the property defined by the calling method's class. For example, given the following classes, Super and Sub:

```
classdef Super
  properties (Access = private)
    Prop = 2;
end
methods
  function p = superMethod(obj)
    p = obj.Prop;
  end
end
end

classdef Sub < Super
  properties
    Prop = 1;
end</pre>
```

end

If you create an instance of the subclass and use it to call the superclass method, MATLAB access the private property of the method's class:

```
subObj = Sub
subObj =
   Sub with properties:
    Prop: 1
subObj.superMethod
ans =
   2
```

More About

• "Property Attributes"

Subclassing Multiple Classes

In this section...

"Class Member Compatibility" on page 11-20

"Using Multiple Inheritance" on page 11-21

Class Member Compatibility

When you create a subclass derived from multiple classes, the subclass inherits the properties, methods, and events defined by all specified superclasses. If more than one superclass defines a property, method, or event having the same name, there must be an unambiguous resolution to the multiple definitions. You cannot derive a subclass from any two or more classes that define incompatible class members.

There are various situations where you can resolve name and definition conflicts, as described in the following sections.

Property Conflicts

If two or more superclasses define a property with the same name, then at least one of the following must be true:

- All, or all but one of the properties must have their SetAccess and GetAccess attributes set to private
- The properties have the same definition in all superclasses (for example, when all superclasses inherited the property from a common base class)

Method Conflicts

If two or more superclasses define methods with the same name, then at least one of the following must be true:

- The method's Access attribute is private so only the defining superclass can access
 the method.
- The method has the same definition in all subclasses. This situation can occur when all superclasses inherit the method from a common base class and none of the superclasses override the inherited definition.
- The subclass redefines the method to disambiguate the multiple definitions across all superclasses. This means that the superclass methods must not have their Sealed attribute set to true.

- Only one superclass defines the method as Sealed, in which case, the subclass adopts
 the sealed method definition.
- The superclasses define the methods as Abstract and rely on the subclass to define the method.

Event Conflicts

If two or more superclasses define events with the same name, then at least one of the following must be true:

- The event's ListenAccess and NotifyAccess attributes must be private.
- The event has the same definition in all superclasses (for example, when all superclasses inherited the event from a common base class)

Using Multiple Inheritance

Resolving the potential conflicts involved when defining a subclass from multiple classes often reduces the value of this approach. For example, problems can arise when you enhance superclasses in future versions and introduce new conflicts.

Reduce potential problems by implementing only one unrestricted superclass. In all other superclasses, all methods are abstract and must be defined by a subclass or inherited from the unrestricted superclass.

In general, when using multiple inheritance, ensure that all superclasses remain free of conflicts in definition.

See "Defining a Subclass" on page 11-7 for the syntax used to derive a subclass from multiple superclasses.

See "Supporting Both Handle and Value Subclasses" on page 11-36 for techniques that provide greater flexibility when using multiple superclasses.

Specify Allowed Subclasses

In this section...

"Basic Knowledge" on page 11-22

"Why Control Allowed Subclasses" on page 11-22

"Specify Allowed Subclasses" on page 11-22

"Define a Sealed Hierarchy of Classes" on page 11-24

Basic Knowledge

The material presented in this section builds on an understanding of the following information:

- · "Class Metadata" on page 15-2
- · "Attribute Specification" on page 4-26

Why Control Allowed Subclasses

A class definition can specify a list of classes that it allows to subclass the class. Classes not in the list cannot subclass the class. Use the AllowedSubclasses class attribute to specify the allowed subclasses.

The AllowedSubclasses attribute provides a design point between Sealed classes, which do not allow subclassing, and the default behavior, which does not restrict subclassing.

By controlling the allowed subclasses, you can create a sealed hierarchy of classes. That is, a system of classes that enables a specific set of classes to derive from specific base classes, but that does not allow unrestricted subclassing.

See "Define a Sealed Hierarchy of Classes" on page 11-24 for more about this technique.

Specify Allowed Subclasses

Note: Specify attribute values explicitly, not as values returned from functions or other MATLAB expressions.

Specify a list of one or more allowed subclasses in the classdef statement by assigning meta.class objects to the AllowedSubclasses attribute. Create the meta.class object referencing a specific class using the ? operator and the class name:

```
classdef (AllowedSubclasses = ?ClassName) MySuperClass
...
end

Use a cell array of meta.class objects to define more than one allowed subclass:
classdef (AllowedSubclasses = {?ClassName1,?ClassName2,...?ClassNameN}) MySuperClass
...
end

Always use the fully qualified class name when referencing the class name:
classdef (AllowedSubclasses = ?Package.SubPackage.ClassName1) MySuperClass
...
end
```

Assigning an empty cell array to the AllowedSubclasses attribute is effectively the same as defining a Sealed class.

```
classdef (AllowedSubclasses = {}) MySuperClass
   ...
end
```

Note: Use only the ? operator and the class name to generate meta.class objects. Values assigned to the AllowedSubclasses attribute cannot contain any other MATLAB expressions, including functions that return either meta.class objects or cell arrays of meta.class objects.

Effect of Defining a Class as an Allowed Subclass

Including a class in the list of AllowedSubclasses does not define that class as a subclass or require you to define the class as a subclass. It just allows the referenced class to be defined as a subclass.

Declaring a class as an allowed subclass does not affect whether this class can itself be subclassed.

A class definition can contain assignments to the AllowedSubclasses attribute that reference classes that are not currently defined or available on the MATLAB path.

However, any referenced subclass that MATLAB cannot find when loading the class is effectively removed from the list without causing an error or warning.

Note: If MATLAB does not find any of the classes in the allowed classes list, the class is effectively Sealed. This is equivalent to AllowedSubclasses = {}.

Define a Sealed Hierarchy of Classes

The AllowedSubclasses attribute enables you to define a sealed class hierarchy by sealing the allowed subclasses:

```
classdef (AllowedSubclasses = {?SubClass1,?SubClass2}) SuperClass
...
end
```

Define the allowed subclasses as Sealed:

```
classdef (Sealed) SubClass1
    ...
end

classdef (Sealed) SubClass2
    ...
end
```

Sealed class hierarchies enable you to use the level of abstraction that your design requires while maintaining a closed systems of classes.

Related Examples

"Supporting Both Handle and Value Subclasses"

Control Access to Class Members

In this section...

- "Basic Knowledge" on page 11-25
- "Applications for Access Control Lists" on page 11-26
- "Specify Access to Class Members" on page 11-26
- "Properties with Access Lists" on page 11-28
- "Methods with Access Lists" on page 11-28
- "Abstract Methods with Access Lists" on page 11-32

Basic Knowledge

The material presented in this section builds on an understanding of the following information:

Related Topics

- "Class Metadata" on page 15-2
- "Attribute Specification" on page 4-26

Terminology and Concepts

- · Class members Properties, methods, and events defined by a class
- $Defining\ class$ The class defining the class member for which access is being specified
- Get access Permission to read the value of a property; controlled by the property GetAccess attribute
- Set access Permission to assign a value to a property; controlled by the property SetAccess attribute
- Method access Determines what other methods and functions can call the class method; controlled by the method Access attribute
- Listen access Permission to define listeners; controlled by the event ListenAccess attribute
- Notify access Permission to trigger events; controlled by the event NotifyAccess attribute

Possible Values for Access to Class Members

The following class member attributes can contain a list of classes:

- Properties Access, GetAccess, and SetAccess. For a list of all property attributes, see "Property Attributes" on page 7-7.
- Methods Access. For a list of all method attributes, see "Method Attributes" on page 8-5.
- Events ListenAccess and NotifyAccess. For a list of all event attributes, see "Event Attributes" on page 10-17.

These attributes accept the following possible values:

- public Unrestricted access
- protected Access by defining class and its subclasses
- private Access by defining class only
- Access list A list of one or more classes. Only the defining class and the classes in
 the list have access to the class members to which the attribute applies. If you specify
 a list of classes, MATLAB does not allow access by any other class (that is, access is
 private, except for the listed classes).

Applications for Access Control Lists

Access control lists enable you to control access to specific class properties, methods, and events, by specifying a list of classes to which you want to grant access to these class members.

This technique provides greater flexibility and control in the design of a system of classes. For example, use access control lists when you want to define parts of your class system in separate classes, but do not want to allow access to class members from outside the class system.

Specify Access to Class Members

Specify the classes that are allowed to access a particular class member in the member access attribute statement. For example:

```
methods (Access = {?ClassName1,?ClassName2,...})
```

Use the class meta.class object to refer to classes in the access list. To specify more than one class, use a cell array of meta.class objects. Use the package name when referring to classes that are in packages.

Note: You must specify the meta.class objects explicitly (created with the ? operator), not as values returned by functions or other MATLAB expressions.

How MATLAB Interprets Attribute Values

- Granting access to a list of classes restricts access to only:
 - The defining class
 - The classes in the list
 - · Subclasses of the classes in the list
- Including the defining class in the access list gives all subclasses of the defining class access.
- MATLAB resolves references to classes in the access list only when the class is loaded. If MATLAB cannot find a class that is included in the access list, that class is effectively removed from access.
- MATLAB replaces unresolved meta.class entries in the list with empty meta.class objects.
- An empty access list (that is, an empty cell array) is equivalent to private access.

Specifying Metaclass Objects

Use only the ? operator and the class name to generate the meta.class objects. Values assigned to the attributes cannot contain any other MATLAB expressions, including functions that return allowed attribute values:

- meta.class objects
- Cell arrays of meta.class objects
- The values public, protected, or private

You must specify these values explicitly, as shown in the example code in this section.

Properties with Access Lists

These sample classes show the behavior of a property that grants read access (GetAccess) to a class. The GrantAccess class gives GetAccess to the NeedAccess class for the Prop1 property:

```
classdef GrantAccess
  properties (GetAccess = ?NeedAccess)
     Prop1 = 7;
  end
end
```

The NeedAccess class defines a method that uses the value of the GrantAccess Prop1 value. The dispObj is defined as a Static method, however, it could be an ordinary method.

```
classdef NeedAccess
  methods (Static)
    function dispObj(GrantAccessObj)
        disp(['Prop1 is: ',num2str(GrantAccessObj.Prop1)])
    end
  end
end

Get access to Prop1 is private so MATLAB returns an error:

a = GrantAccess;
a.Prop1

Getting the 'Prop1' property of the 'GrantAccess' class is not allowed.

However, MATLAB allows access to Prop1 by the NeedAccess class:

NeedAccess.dispObj(a)

Prop1 is: 7
```

Methods with Access Lists

Classes granted access to a method can:

- Call the method using an instance of the defining class.
- Define their own method with the same name (if not a subclass).

• Override the method in a subclass only if the superclass defining the method includes itself or the subclass in the access list.

These sample classes show the behavior of methods called from methods of other classes that are in the access list. The class AcListSuper gives the AcListNonSub class access to itsm1 method:

```
classdef AcListSuper
  methods (Access = {?AcListNonSub})
    function obj = m1(obj)
        disp ('Method m1 called')
    end
end
```

Because AcListNonSub is in the access list of m1, its methods can call m1 using an instance of AcListSuper:

```
classdef AcListNonSub
   methods
      function obj = nonSub1(obj,AcListSuper Obj)
         % Call m1 on AcListSuper class
         AcListSuper Obj.m1;
      end
      function obj = m1(obj)
         % Define a method named m1
         disp(['Method m1 defined by ',class(obj)])
      end
   end
end
Create objects of both classes:
a = AcListSuper;
b = AcListNonSub;
Call the AcListSuper m1 method using an AcListNonSub method:
b.nonSub1(a);
Method m1 called
Call the AcListNonSub m1 method:
b.m1;
```

Method m1 defined by AcListNonSub

Subclasses Without Access

Including the defining class in the access list for a method grants access to all subclasses derived from that class. When you derive from a class that has a method with an access list and that list does *not* include the defining class in the access list:

- Subclass methods cannot call the superclass method because it is effectively private.
- Subclasses cannot override the superclass method.
- Subclass methods can call the superclass method indirectly using an instance of a class that is in the access list.
- Nonsubclass methods of classes in the superclass method access list can call the superclass method using an instance of a subclass that is not in the superclass method access list.

For example, AcListSub is a subclass of AcListSuper. The AcListSuper class defines an access list for method m1. However, this list does not include AcListSuper, which would implicitly include all subclasses of AcListSuper in the access list:

```
classdef AcListSub < AcListSuper
  methods
    function obj = sub1(obj,AcListSuper_Obj)
        % Access m1 via superclass object (NOT ALLOWED)
        AcListSuper_Obj.m1;
  end
  function obj = sub2(obj,AcListNonSub_Obj,AcListSuper_obj)
        % Access m1 via object that is in access list (is allowed)
        AcListNonSub_Obj.nonSub1(AcListSuper_Obj);
  end
  end
end</pre>
```

Attempting to call the superclass m1 method results in an error because subclasses are not in the access list for the method:

```
a = AcListSuper;
b = AcListNonSub;
c = AcListSub;
c.sub1(a);
Error using AcListSuper/m1
Cannot access method 'm1' in class 'AcListSuper'.
Error in AcListSub/sub1 (line 4)
```

```
AcListSuper Obj.m1;
```

The AcListSub sub2 method can call a method of a class that is on the access list for m1, and that method (nonSub1) does have access to the superclass m1 method:

```
c.sub2(b,a);
Method m1 called
```

When subclasses are not included in the access list for a method, those subclasses cannot define a method with the same name. This behavior is not the same as cases in which the method's Access is explicitly declared as private.

For example, adding the following method to the AcListSub class definition produces an error when you attempt to instantiate the class.

```
methods (Access = {?AcListNonSub})
  function obj = m1(obj)
    disp('AcListSub m1 method')
  end
end
```

If you attempt to instantiate the class, MATLAB returns an error:

```
c = AcListSub;
```

Error using AcListSub

Class 'AcListSub' is not allowed to override the method 'm1' because neither it nor its superclasses have been granted access to the method by class 'AcListSuper'.

The AcListNonSub class, which is in the m1 method access list, can define a method that calls the m1 method using an instance of the AcListSub class. While AcListSub is not in the access list for method m1, it is a subclass of AcListSuper.

For example, add the following method to the AcListNonSub class:

```
methods
   function obj = nonSub2(obj,AcListSub_Obj)
      disp('Call m1 via subclass object:')
      AcListSub_Obj.m1;
   end
end
```

Calling the nonSub2 method results in execution of the superclass m1 method:

```
b = AcListNonSub;
```

```
c = AcListSub;
b.nonSub2(c);
Call m1 via subclass object:
Method m1 called
```

This is consistent with the behavior of any subclass object, which can be substituted for an instance of its superclass.

Abstract Methods with Access Lists

A class containing a method declared as Abstract is an abstract class. It is the responsibility of subclasses to implement the abstract method using the function signature declared in the class definition.

When an abstract method has an access list, only the classes in the access list can implement the method. A subclass that is not in the access list cannot implement the abstract method so that subclass is itself abstract.

Property Access List

This class declares access lists for the property GetAccess and Access attributes:

```
classdef PropertyAccess
  properties (GetAccess = {?ClassA, ?ClassB}, SetAccess = private)
        Prop1
  end
  properties (Access = ?ClassC)
        Prop2
  end
end
```

The class PropertyAccess specifies the following property access:

- Gives the classes ClassA and ClassB get access to the Prop1 property.
- Gives all subclasses of ClassA and ClassB get access to the Prop1 property.
- Does not give get access to Prop1 from subclasses of PropertyAccess.
- Defines private set access for the Prop1 property.
- Gives set and get access to Prop2 for ClassC and its subclasses.

Related Examples

• "Properties with Access Lists"

Method Access List

This class declares an access list for the method Access attribute:

```
classdef MethodAccess
  methods (Access = {?ClassA, ?ClassB, ?MethodAccess})
    function listMethod(obj)
    ...
    end
  end
end
```

The MethodAccess class specifies the following method access:

- Access to listMethod from an instance of MethodAccess by methods of the classes ClassA and ClassB.
- Access to listMethod from an instance of MethodAccess by methods of subclasses of MethodAccess, because of the inclusion of MethodAccess in the access list.
- Subclasses of ClassA and ClassB are allowed to define a method named listMethod, and MethodAccess is allowed to redefine listMethod. However, if MethodAccess was not in the access list, its subclasses could not redefine listMethod.

Related Examples

"Methods with Access Lists"

Event Access List

This class declares an access list for the event ListenAccess attribute:

```
classdef EventAccess
  events (NotifyAccess = private, ListenAccess = {?ClassA, ?ClassB})
     Event1
     Event2
  end
end
```

The class EventAccess specifies the following event access:

- Limits notify access for Event1 and Event2 to EventAccess; only methods of the EventAccess can trigger these events.
- Gives listen access for Event1 and Event2 to methods of ClassA and ClassB. Methods of EventAccess, ClassA, and ClassB can define listeners for these events. Subclasses of MyClass cannot define listeners for these events.

Related Examples

"Events and Listeners — Syntax and Techniques"

Supporting Both Handle and Value Subclasses

In this section...

"Basic Knowledge" on page 11-36

"Handle Compatibility Rules" on page 11-36

"Defining Handle-Compatible Classes" on page 11-37

"Subclassing Handle-Compatible Classes" on page 11-39

"Methods for Handle Compatible Classes" on page 11-41

"Handle-Compatible Classes and Heterogeneous Arrays" on page 11-42

Basic Knowledge

The material presented in this section builds on knowledge of the following information.

- "Creating Subclasses Syntax and Techniques" on page 11-7
- "Subclassing Multiple Classes" on page 11-20
- · "Comparing Handle and Value Classes" on page 6-2

Key Concepts

Handle-compatible class is a class that you can combine with handle classes when defining a set of superclasses.

- All handle classes are handle-compatible.
- · All superclasses of handle-compatible classes must also be handle compatible.

HandleCompatible — the class attribute that defines nonhandle classes as handle compatible.

Handle Compatibility Rules

Handle-compatible classes (that is, classes whose HandleCompatible attribute is set to true) follow these rules:

· All superclasses of a handle-compatible class must also be handle compatible

- If a class explicitly sets its HandleCompatibility attribute to false, then none of the class's superclasses can be handle classes.
- If a class does not explicitly set its HandleCompatible attribute and, if any superclass is a handle, then all superclasses must be handle compatible.
- The HandleCompatible attribute is not inherited.

A class that does not explicitly set its HandleCompatible attribute to true is:

- A handle class if any of its superclasses are handle classes
- A value class if none of the superclasses are handle classes

Defining Handle-Compatible Classes

A class is handle compatible if:

- · It is a handle class
- Its HandleCompatible attribute is set to true

The HandleCompatible class attribute identifies classes that you can combine with handle classes when specifying a set of superclasses.

Handle compatibility provides greater flexibility when defining abstract superclasses, such as mixin and interface classes, in cases where the superclass is designed to support both handle and value subclasses. Handle compatibility removes the need to define both a handle version and a nonhandle version of a class.

A Handle Compatible Class

The Utility class is useful to both handle and value subclasses. In this example, the Utility class defines a method to reset property values to the default values defined in the respective class definition:

```
classdef (HandleCompatible) Utility
  methods
    function obj = resetDefaults(obj)
    mc = metaclass(obj);
    mp = mc.PropertyList;
    for k=1:length(mp)
        if mp(k).HasDefault && ~strcmp(mp(k).SetAccess, 'private')
            obj.(mp(k).Name) = mp(k).DefaultValue;
```

```
end
end
end
end
```

The Utility class is handle compatible. Therefore, you can use it in the derivation of classes that are either handle classes or value classes. See "Getting Information About Classes and Objects" for information on using meta-data classes.

Return Modified Objects

The resetDefaults method defined by the Utility class returns the object it modifies. When you call resetDefaults with a value object, the method must return the modified object. It is important to implement methods that work with both handle and value objects in a handle compatible superclass. See "Modifying Objects" on page 4-60 for more information on modifying handle and value objects.

Consider the behavior of a value class that subclasses the Utility class. The PropertyDefaults class defines three properties, all of which have default values:

```
classdef PropertyDefaults < Utility
  properties
    p1 = datestr(rem(now,1)); % Current time
    p2 = 'red'; % Character string
    p3 = pi/2; % Result of division operation
  end
end</pre>
```

Create a PropertyDefaults object. MATLAB evaluates the expressions assigned as default property values when the class is first loaded. MATLAB uses these same default values whenever you create an instance of this class in the current MATLAB session.

```
pd = PropertyDefaults
pd =
   PropertyDefaults with properties:
   p1: ' 4:42 PM'
   p2: 'red'
   p3: 1.5708
```

Assign new values that are different from the default values:

```
pd.p1 = datestr(rem(now,1));
pd.p2 = 'green';
pd.p3 = pi/4;
```

All pd object property values now contain values that are different from the default values originally defined by the class:

```
pd

pd =

   PropertyDefaults with properties:
:
   p1: ' 4:45 PM'
   p2: 'green'
   p3: 0.7854
```

Call the resetDefaults method, which is inherited from the Utility class. Because the PropertyDefaults class is not a handle class, return the modified object.

```
pd = pd.resetDefaults

pd =

PropertyDefaults with properties:

p1: ' 4:54 PM'
p2: 'red'
p3: 1.5708
```

If the PropertyDefaults class was a handle class, then you would not need to save the object returned by the resetDefaults method. To design a handle compatible class like Utility, ensure that all methods work with both kinds of classes.

Subclassing Handle-Compatible Classes

According to the rules described in "Handle Compatibility Rules" on page 11-36, when you combine a handle superclass with a handle-compatible superclass, the result is a handle subclass, which is handle compatible.

However, subclassing a handle-compatible class does not necessarily result in the subclass being handle compatible. Consider the following two cases, which demonstrate two possible results.

Combine Nonhandle Utility Class with Handle Classes

Suppose you define a class that subclasses a handle class, as well as the handle compatible Utility class discussed in "A Handle Compatible Class" on page 11-37. The HPropertyDefaults class has these characteristics:

- It is a handle class (it derives from handle).
- All of its superclasses are handle compatible (handle classes are handle compatible by definition).

```
classdef HPropertyDefaults < handle & Utility
    properties
        GraphPrim = line;
        Width = 1.5;
        Color = 'black';
    end
end

The HPropertyDefaults class is handle compatible:
hpd = HPropertyDefaults;
mc = metaclass(hpd);</pre>
```

```
hpd = HPropertyDefaults;
mc = metaclass(hpd);
mc.HandleCompatible
ans =
```

Nonhandle Subclasses of a Handle-Compatible Class

If you subclass a value class that is not handle compatible in combination with a handle compatible class, the subclass is a nonhandle compatible value class. The ValueSub class:

- Is a value class (It does not derive from handle.)
- One of its superclasses is handle compatible (the Utility class).

```
classdef ValueSub < MException & Utility
  methods
     function obj = ValueSub(str1,str2)
        obj = obj@MException(str1,str2);
    end
  end
end</pre>
```

The ValueSub class is a nonhandle-compatible value class because the MException class does not define the HandleCompatible attribute as true:

Methods for Handle Compatible Classes

Objects passed to methods of handle compatible classes can be either handle or value objects. There are two different behaviors to consider when implementing methods for a class that operate on both handles and values:

- If an input object is a handle object, then the method can alter the handle object and these changes are visible to all workspaces that have the same handle.
- If an input object is a value object, then changes to the object made inside the method affect only the value inside the method workspace.

Handle compatible methods generally do not alter input objects because the effect of such changes are not the same for handle and nonhandle objects.

See "Modifying Objects" on page 4-60 for information about modifying handle and value objects.

Identifying Handle Objects

Use the isa function to determine if an object is a handle object:

```
isa(obj,'handle')
```

Modifying Value Objects in Methods

If a method operates on both handle and value objects, the method must return the modified object. For example, the **setTime** method returns the object it modifies:

```
classdef (HandleCompatible) Util
% Utility class that adds a time stamp
properties
```

```
TimeStamp
end
methods
   function obj = setTime(obj)
    obj.TimeStamp = now;
end
end
end
```

Handle-Compatible Classes and Heterogeneous Arrays

A heterogeneous array contains objects of different classes. Members of a heterogeneous array have a common superclass, but might belong to different subclasses. See the matlab.mixin.Heterogeneous class for more information on heterogeneous arrays. The matlab.mixin.Heterogeneous class is a handle-compatible class.

Methods Must Be Sealed

You can invoke only those methods that are sealed by the common superclass on heterogeneous arrays (Sealed attribute set to true). Sealed methods prevent subclasses from overriding those methods and guarantee that methods called on heterogeneous arrays have the same definition for the entire array.

Subclasses cannot override sealed methods. In situations requiring subclasses to specialize methods defined by a utility class, you can employ the design pattern referred to as the template method.

Using the Template Technique

Suppose you need to implement a handle compatible class that works with heterogeneous arrays. This approach enables you to seal public methods, while providing a way for each subclass to specialize how the method works on each subclass instance. In the handle compatible class:

- Define a sealed method that accepts a heterogeneous array as input.
- · Define a protected, abstract method that each subclass must implement.
- Within the sealed method, call the overridden method for each array element.

Each subclass in the heterogeneous hierarchy implements a concrete version of the abstract method. The concrete method provides specialized behavior required by the particular subclass.

The Printable class shows how to implement a template method approach:

```
classdef (HandleCompatible) Printable
  methods(Sealed)
    function print(aryIn)
        n = numel(aryIn);
        for k=1:n
            printElement(aryIn(k));
        end
    end
    end
  methods(Access=protected, Abstract)
        printElement(objIn)
  end
end
```

More About

• "Heterogeneous Arrays"

Subclassing MATLAB Built-In Types

In this section...

"MATLAB Built-In Types" on page 11-44

"Built-In Types You Cannot Subclass" on page 11-44

"Why Subclass Built-In Types" on page 11-45

"Which Functions Work With Subclasses of Built-In Types" on page 11-45

"Behavior of Built-In Functions with Subclass Objects" on page 11-45

"Built-In Subclasses That Define Properties" on page 11-46

MATLAB Built-In Types

Built-in types represent fundamental kinds of data such as numeric arrays, logical arrays, and character arrays. Other built-in types contain data belonging to these fundamental types and other classes. For example, cell and struct arrays can contain instances of any class.

Built-in types define methods that perform operations on objects of these classes. For example, you can perform operations on numeric arrays, such as, sorting, rounding values, and element-wise and matrix multiplication. You can create an object of class double using an assignment statement, indexing expressions, or using converter functions.

See "Fundamental MATLAB Classes" for more information on MATLAB built-in classes.

Note: It is an error to define a class that has the same name as a built-in class.

Built-In Types You Cannot Subclass

You cannot subclass the following built-in MATLAB classes:

- char
- cell
- struct
- table

function_handle

In general, you cannot subclass any class that has its Sealed attribute set to true. Query the class meta-data to determine if the class is Sealed:

```
mc = ?ClassName;
mc.Sealed
```

A value of 0 indicates that the class is not Sealed and can be subclasses.

Why Subclass Built-In Types

Subclass a built-in type to extend the operations that you can perform on a particular class of data. For example, when you want to:

- · Define unique operations to perform on class data.
- Be able to use methods of the built-in class and other built-in functions directly
 with objects of the subclass. For example, you do not need to reimplement all the
 mathematical operators if you derived from a class such as double that defines these
 operators.

Which Functions Work With Subclasses of Built-In Types

Consider a class that defines enumerations. It can derive from an integer class and inherit methods that enable you to compare and sort values. For example, integer classes like int32 support all the relational methods (eq, ge, gt, le, lt, ne).

To see a list of functions that the subclass has inherited as methods, use the methods function:

```
methods('SubclassName')
```

Generally, you can use an object of the subclass with any:

- · Inherited methods
- Functions that normally accept input arguments of the same class as the superclass.

Behavior of Built-In Functions with Subclass Objects

When you define a subclass of a built-in class, the subclass inherits all built-in class methods. In addition, MATLAB provide a number of built-in functions as subclass methods.

However, built-in functions that work on built-in classes behave differently with subclasses. Their behavior depends on which function you are using and whether your subclass defines properties.

Behavior Categories

When you call an inherited method on a subclass of a built-in class, the result of that call depends on the nature of the operation performed by the method. The behaviors of these methods fit into several categories.

- Operations on data values return objects of the superclass. For example, if you subclass double and perform addition on two subclass objects, MATLAB adds the numeric values and returns a value of class double.
- Operations on the orientation or structure of the data return objects of the subclass.
 Methods that perform these kinds of operations include, reshape, permute, transpose, and so on.
- Converting a subclass object to a built-in class returns an object of the specified class.
 Functions such as uint32, double, char work with subclass objects the same as they work with built-in objects.
- Comparing objects or testing for inclusion in a specific set returns logical or built-in objects, depending on the function. Functions such as isequal, ischar, isobject work with subclass objects the same as they work with superclass objects.
- Indexing expressions return objects of the subclass. If the subclass defines properties, then default indexing no longer works. The subclass must define its own indexing methods.
- Concatenation returns an object of the subclass. If the subclass defines properties, then default concatenation no longer works and the subclass must define its own concatenation methods.

To list the built-in functions that work with a subclass of a built-in class, use the methods function.

Built-In Subclasses That Define Properties

When a subclass of a built-in class defines properties, MATLAB no longer provides support for indexing and concatenation operations. MATLAB cannot use the built-in functions normally called for these operations because subclass properties can contain any data.

The subclass must define what indexing and concatenation mean for a class with properties. If your subclass needs indexing and concatenation functionality, then the subclass must implement the appropriate methods.

Methods for Indexing

To support indexing operations, the subclass must implement these methods:

- · subsasgn Implement dot notation and indexed assignments
- subsref Implement dot notation and indexed references
- subsindex Implement object as index value

Methods for Concatenation

To support concatenation, the subclass must implement the following methods:

- horzcat Implement horizontal concatenation of objects
- vertcat Implement vertical concatenation of objects
- · cat Implement concatenation of object arrays along specified dimension

Behavior of Inherited Built-In Methods

```
In this section...

"Subclass double" on page 11-48

"Built-In Data Value Methods" on page 11-49

"Built-In Data Organization Methods" on page 11-50

"Built-In Indexing Methods" on page 11-51

"Built-In Concatenation Methods" on page 11-51
```

Subclass double

Most built-in functions used with built-in classes are actually methods of the built-in class. For example, the double and single classes both define a number of methods to perform arithmetic operations, indexing, matrix operation, and so on. All of these built-in class methods work with subclasses of the built-in class.

Subclassing double enables your class to use features without implementing the methods that a MATLAB built-in class define.

The DocSimpleDouble class subclasses the built-in double class.

```
classdef DocSimpleDouble < double
  methods
    function obj = DocSimpleDouble(data)
    if nargin == 0
        data = 0;
    end
    obj = obj@double(data);
  end
end
end</pre>
```

Create an instance of the class DocSimpleDouble.

```
sc = DocSimpleDouble(1:10)
sc =
   1x10 DocSimpleDouble:
   double data:
   1   2   3   4   5   6   7   8   9   10
```

Call a method inherited from class double that operates on the data, such as sum. sum returns a double and, therefore, uses the display method of class double:

```
sum(sc)
ans =
55
```

Index sc like an array of doubles. The returned value is the class of the subclass:

```
a = sc(2:4)
a =
  1x3 DocSimpleDouble:
  double data:
  2  3  4
```

Indexed assignment works the same as the built-in class. The returned value is the class of the subclass:

```
sc(1:5) = 5:-1:1
sc =
   1x10 DocSimpleDouble:
   double data:
   5      4      3      2      1      6      7      8      9      10
```

Calling a method that modifies the order of the data elements operates on the data, but returns an object of the subclass:

```
sc = DocSimpleDouble(1:10);
sc(1:5) = 5:-1:1;
a = sort(sc)

a =
    1x10 DocSimpleDouble:
    double data:
    1    2    3    4    5    6    7    8    9    10
```

Built-In Data Value Methods

When you call a built-in data value method on a subclass object, MATLAB uses the superclass part of the subclass object as inputs to the method, and the value returned is same class as the built-in class. For example:

```
sc = DocSimpleDouble(1:10);
a = sin(sc);
class(a)
ans =
double
```

Built-In Data Organization Methods

This group of built-in methods reorders or reshapes the input argument array. These methods operate on the superclass part of the subclass object, but return an object of the same type as the subclass.

```
sc = DocSimpleDouble(randi(9,1,10))
sc = DocSimpleDouble(randi(9,1,10))
sc =
 1x10 DocSimpleDouble:
 double data:
                           7
    6
                8
                     9
                                 7
                                      7
       1
b = sort(sc)
b =
 1x10 DocSimpleDouble:
 double data:
    1
          2
                4
                           6
                               7 7 7
                                                        9
```

Methods in this group include:

- reshape
- permute
- sort
- transpose
- ctranspose

Built-In Indexing Methods

Built-in classes use specially implemented versions of the subsref, subsasgn, and subsindex methods to implement indexing. When you index a subclass object, only the built-in data is referenced (not the properties defined by your subclass).

For example, indexing element 2 in the DocSimpleDouble subclass object returns the second element in the vector:

```
sc = DocSimpleDouble(1:10);
a = sc(2)
a =
   DocSimpleDouble
   double data:
   2
```

The value returned from an indexing operation is an object of the subclass. You cannot make indexed references if your subclass defines properties, unless your subclass overrides the default subsref method.

Assigning a new value to the second element in the **DocSimpleDouble** object operates only on the superclass data:

The subsref method also implements dot notation for methods.

Built-In Concatenation Methods

Built-in classes use the functions horzcat, vertcat, and cat to implement concatenation. When you use these functions with subclass objects of the same type, MATLAB concatenates the superclass data to form a new object. For example, you can concatenate objects of the DocSimpleDouble class:

```
sc1 = DocSimpleDouble(1:10);
sc2 = DocSimpleDouble(11:20);
[sc1,sc2]
```

```
1x20 DocSimpleDouble:
 double data:
 Columns 1 through 13
                                     7
                                                     10
                                                          11
                                                               12
                                                                      13
 Columns 14 through 20
       15
              16
                          18
                               19
                                     20
[sc1;sc2]
ans =
 2x10 DocSimpleDouble:
 double data:
                                                      10
   1 2
                     4
                          5
                                6
        12
                  14
                          15
                               16
                                     17
                                                      20
              13
                                           18
```

Concatenate two objects along a third dimension:

```
c = cat(3,sc1,sc2)
C =
  1x10x2 DocSimpleDouble:
  double data:
(:,:,1) =
     1
                                      6
                                             7
            2
                  3
                         4
                               5
                                                   8
                                                          9
                                                               10
(:,:,2) =
    11
          12
                 13
                        14
                              15
                                     16
                                           17
                                                  18
                                                         19
                                                               20
```

If the subclass of a built-in class defines properties, you cannot concatenate objects of the subclass. There is no way to determine how to combine properties of different objects. However, your subclass can define custom horzcat and vertcat methods to support concatenation in whatever way makes sense for your subclass.

Related Examples

- "Built-In Subclass Without Properties" on page 11-53
- "Built-In Subclass With Properties"

Built-In Subclass Without Properties

```
In this section...

"A Class to Manage uint8 Data" on page 11-53

"Using the DocUint8 Class" on page 11-54
```

A Class to Manage uint8 Data

This example shows a class derived from the built-in uint8 class. This class simplifies the process of maintaining a collection of intensity image data defined by uint8 values. The basic operations of the class include:

- Capability to convert various classes of image data to uint8 to reduce object data storage.
- A method to display the intensity images contained in the subclass objects.
- Ability to use all the methods that you can use on uint8 data (for example, Size, indexing (reference and assignment), reshape, bitshift, cat, fft, arithmetic operators, and so on).

The class data are matrices of intensity image data stored in the superclass part of the subclass object. This approach requires no properties.

The DocUint8 class stores the image data, which converts the data, if necessary:

```
classdef DocUint8 < uint8
  methods
  function obj = DocUint8(data)
    if nargin == 0
        data = uint8(0);
  end
    obj = obj@uint8(data);
  end
  function h = showImage(obj)
    data = uint8(obj);
    figure; colormap(gray(256))
    h = imagesc(data,[0 255]);
    axis image
    brighten(.2)
  end</pre>
```


end end

Using the DocUint8 Class

Create DocUint8 Objects

The DocUint8 class provides a method to display all images stored as DocUint8 objects in a consistent way. For example:

```
cir = imread('circuit.tif');
img1 = DocUint8(cir);
img1.showImage;
```



Because DocUint8 subclasses uint8, you can use any uint8 methods. For example,

```
size(img1)
ans =
```

280

returns the size of the image data.

Indexing Operations


272

Inherited methods perform indexing operations, but return objects of the same class as the subclass.

Therefore, you can index into the image data and call a subclass method:

```
showImage(img1(100:200,1:160));
```


Subscripted reference operations (controlled by the inherited subsref method) return a DocUint8 object.



You can assign values to indexed elements:

```
img1(100:120,140:160) = 255;
img1.showImage;
```


Subscripted assignment operations (controlled by the inherited ${\tt subsasgn}$ method) return a ${\tt DocUint8}$ object.



Concatenation Operations

Concatenation operations work on DocUint8 objects because this class inherits the uint8 horzcat and vertcat methods, which return a DocUint8 object:

showImage([img1 img1]);



Data Operations

Methods that operate on data values, such as arithmetic operators, always return an object of the built-in type (not of the subclass type). For example, multiplying <code>DocUint8</code> objects returns a <code>uint8</code> object:

```
a = img1.*1.8;
showImage(a);
```

Undefined function 'showImage' for input arguments of type 'uint8'.

To perform operations of this type, implement a subclass method to override the inherited method. The times method implements array (element-by-element) multiplication.

Add this method to the DocUint8 class:


```
function o = times(obj,val)
  u8 = uint8(obj).*val;
  o = DocUint8(u8);
end
```

When you override a uint8 method, MATLAB calls the subclass method, not the base class method. The subclass method must:

- · Call the uint8 times method on the DocUint8 object data.
- Construct a new DocUint8 object using the uint8 data.

After adding the times method to the DocUint8 class, the output of multiplication expressions is an object of the DocUint8 class:

```
showImage(img1.*1.8);
```



Related Examples

- "Class Operator Implementations"
- ${}^{\raisebox{3.5pt}{\text{\circle*{1.5}}}}$ "Built-In Subclass With Properties" on page 11-61

Built-In Subclass With Properties

In this section...

"Subclasses with Properties" on page 11-61

"Property Added" on page 11-61

"Methods Implemented" on page 11-61

"Class Definition Code" on page 11-62

"Use ExtendDouble" on page 11-63

"Indexed Reference for ExtendDouble" on page 11-64

"Concatenating ExtendDouble Objects" on page 11-65

Subclasses with Properties

When your subclass of a built-in class defines properties, default indexing and concatenation do not work. The default subsref, horzcat, and vertcat methods cannot work with unknown property types and values. Therefore, you must define these behaviors for the subclass.

This example subclasses the double class and defines a single property.

Property Added

The ExtendDouble class defines the DataString property to contain text that describes the data. The superclass part (double) of the class contains the data.

Methods Implemented

The following methods modify the behavior of the ExtendDouble class:

- ExtendDouble The constructor supports a no argument syntax that initializes properties to empty values.
- subsref Enables subscripted reference to the superclass part (double) of the subclass, dot notation reference to the DataString property, and dot notation reference the built-in data via the string Data (the double data property is hidden).
- horzcat Defines horizontal concatenation of ExtendDouble objects. concatenates
 the superclass part using the double class horzcat method and forms a cell array of
 the DataString properties.

- vertcat The vertical concatenation equivalent of horzcat (both are required).
- char A ExtendDouble to char converter used by horzcat and vertcat.
- disp ExtendDouble implements a disp method to provide a custom display for the object.

Class Definition Code

The ExtendDouble class extends double and implements methods to support subscripted reference and concatenation.

```
classdef ExtendDouble < double</pre>
   properties
      DataString
   end
   methods
      function obj = ExtendDouble(data,str)
         if nargin == 0
            data = 0;
            str = '':
         elseif nargin == 1
            str = '';
         end
         obj = obj@double(data);
         obj.DataString = str;
      end
      function sref = subsref(obj,s)
         switch s(1).type
            case '.'
                switch s(1).subs
                   case 'DataString'
                      sref = obj.DataString;
                   case 'Data'
                      sref = double(obj);
                      if length(s)>1 && strcmp(s(2).type, '()')
                         sref = subsref(sref,s(2:end));
                      end
                end
            case '()'
               sf = double(obj);
                if ~isempty(s(1).subs)
```

```
sf = subsref(sf,s(1:end));
               else
                  error('Not a supported subscripted reference')
               end
               sref = ExtendDouble(sf,obj.DataString);
         end
      end
      function newobj = horzcat(varargin)
         d1 = cellfun(@double, varargin, 'UniformOutput', false );
         data = horzcat(d1{:});
         str = horzcat(cellfun(@char,varargin,'UniformOutput',false));
         newobj = ExtendDouble(data,str);
      end
      function newobj = vertcat(varargin)
        d1 = cellfun(@double, varargin, 'UniformOutput', false );
        data = vertcat(d1{:});
        str = vertcat(cellfun(@char,varargin,'UniformOutput',false));
        newobj = ExtendDouble(data,str);
      end
      function str = char(obj)
         str = obj.DataString;
      end
      function disp(obj)
         disp(obj.DataString)
         disp(double(obj))
      end
   end
end
```

Use ExtendDouble

Create an instance of ExtendDouble and notice that the display is different from the default:

```
ed = ExtendDouble(1:10, 'One to ten')
ed =

One to ten
    1     2     3     4     5     6     7     8     9     10
```

The sum function continues to operate on the superclass part of the object:

```
sum(ed)
ans =
55
```

Subscripted reference works because the class implements a subsref method:

```
ed(10:-1:1)
ans =

One to ten
    10     9     8     7     6     5     4     3     2     1
```

However, subscripted assignment does not work because the class does not define a subsasgn method:

```
ed(1:5) = 5:-1:1

Error using ExtendDouble/subsasgn
Cannot use '(' or '{' to index into an object of class 'ExtendDouble' because
'ExtendDouble' defines properties and subclasses 'double'.
Click here for more information.
```

The sort function works on the superclass part of the object:

```
sort(ed(10:-1:1))
ans =

1  2  3  4  5  6  7  8  9  10
```

Indexed Reference for ExtendDouble

Subscripted reference (performed by subsref) requires the subclass to implement its own subsref method.

```
ed = ExtendDouble(15:20, 'fifteen to twenty');
a = ed(2)
a =
fifteen to twenty
```

16

whos

Name	Size	Bytes	Class	Attributes
a ed	1x1 1x6		ExtendDouble ExtendDouble	

Access the property data:

```
c = ed.DataString
c =
fifteen to twenty
```

whos

Name	Size	Bytes	Class	Attributes
а	1x1	146	ExtendDouble	
C	1x17	34	char	
ed	1x6	186	ExtendDouble	

Concatenating ExtendDouble Objects

Create these two objects:

```
ed1 = ExtendDouble([1:10], 'One to ten');
ed2 = ExtendDouble([10:-1:1], 'Ten to one');
```

Concatenate these objects along the horizontal dimension:

```
hcat = [ed1,ed2]
hcat =
```

```
roat =
   'One to ten' 'Ten to one'

Columns 1 through 13
   1   2   3   4   5   6   7   8   9   10   10   9   8

Columns 14 through 20
   7   6   5   4   3   2   1
```

wl	าด	S
----	----	---

Name	Size	Bytes	Class	Attributes
ed1 ed2 hcat	1x10 1x10 1x20	204	ExtendDouble ExtendDouble ExtendDouble	

Vertical concatenation works in a similar way:

```
vcat = [ed1;ed2]
vcat =
   'One to ten' 'Ten to one'
       2 3 4 5 6 7 8 9 10
9 8 7 6 5 4 3 2 1
```

Both horzcat and vertcat return a new object of the same class as the subclass.

Related Examples

"Built-In Subclass Without Properties" on page 11-53

Understanding size and numel

```
In this section...

"size and numel" on page 11-67

"Subclasses Inherited Behavior" on page 11-68

"Classes Not Derived from Built-In Classes" on page 11-69

"Changing the Behavior of size" on page 11-71

"Avoid Overloading numel" on page 11-71
```

size and numel

The size function returns the dimensions of an array. The numel function returns the number of elements in an array.

Other MATLAB functions use size and numel to perform their operations. Usually, you do not need to overload size and numel. The built-in size and numel functions behave consistently with user-defined classes.

When used with subclasses of built-in classes, the size and numel functions behave the same as they behave in the superclass.

Consider the built-in class double:

1 4

The double class defines these behaviors, including parentheses indexing.

Subclasses Inherited Behavior

Classes behave like their superclasses, unless the subclass explicitly overrides any given behavior. For example, SimpleDouble subclasses double, but defines no properties:

```
classdef SimpleDouble < double
  methods
    function obj = SimpleDouble(data)
    if nargin == 0
        data = 0;
    end
    obj = obj@double(data);
  end
end
end</pre>
```

Create an object and assign the values 1:10 to the superclass part of the object:

```
sd = SimpleDouble(1:10);
```

The size function returns the size of the superclass part:

```
size(sd)
ans =
```

The numel function returns the number of elements in the superclass part:

```
nume1(sd)
ans =
10
```

Object arrays return the size of the superclass arrays:

```
size([sd;sd])
```

The SimpleDouble class inherits the indexing behavior of the double class:

Classes Not Derived from Built-In Classes

Consider a simple value class. This class does not inherit the array-like behaviors of the double class. For example:

```
classdef VerySimpleClass
   properties
      Value
   end
end
```

Create an object and assign a ten-element vector to the Value property:

```
size([vs;vs])
ans =
     2
           - 1
numel([vs;vs])
ans =
     2
vs is a scalar object. The Value property is an array of doubles:
size(vs.Value)
ans =
     1
          10
Apply indexing expressions to the object property:
vssub = vs.Value(7:end);
size(vssub)
ans =
     1
            4
vs. Value is an array of class double:
class(vs.Value)
ans =
double
Creating an array of VerySimpleClass objects:
vsArray(1:10) = VerySimpleClass;
The Value property for array elements 2 through 10 is empty:
isempty([vsArray(2:10).Value])
ans =
```

1

MATLAB does not apply scalar expansion to object array property value assignment. Use the deal function for this purpose:

```
[vsArray.Value] = deal(1:10);
isempty([vsArray.Value])
ans =
```

The deal function assigns values to each Value property in the vsArray object array.

Indexing rules for object arrays are equivalent to those of arrays of struct:

```
vsArray(1).Value
ans =
    1    2    3    4    5    6    7    8    9    10
vsArray(1).Value(6)
ans =
    6
```

Changing the Behavior of size

Subclasses of built-in numeric classes inherit a Size method, which operates on the superclass part of the subclass object (this method is hidden). If you want Size to behave in another way, you can override it by defining your own Size method in your subclass.

Other MATLAB functions use the values returned by Size. If you change the way Size behaves, ensure that the values returned make sense for the intended use of your class.

Avoid Overloading numel

It is important to understand the significance of numel with respect to indexing. MATLAB calls numel to determine the number of elements returned by an indexed expression like:

A(index1,index2,...,indexn)

Both subsref and subsasgn use numel:

- subsref numel computes the number of expected outputs (nargout) returned subsref
- subsasgn numel computes the number of expected inputs (nargin) that MATLAB assigns as a result of a call to subsasgn

Subclasses of built-in classes always return scalar objects as a result of subscripted reference and always use scalar objects for subscripted assignment. The numel function returns the correct value for these operations and there is, therefore, no reason to overload numel.

If you define a class in which nargout for subsref or nargin for subsasgn is different from the value returned by the default numel, then overload numel for that class to ensure that it returns the correct values.

Class to Represent Hardware

```
In this section...

"Class Objective" on page 11-73

"Why Derive from int32" on page 11-73

"Class Definition" on page 11-73

"Methods of int32" on page 11-74
```

Class Objective

This example shows the implementation of a class to represent an optical multiplex card. These cards typically have a number of input ports, which this class represents by the port data rates and names. There is also an output port. The output rate of a multiplex card is the sum of the input port data rates.

Why Derive from int32

The MuxCard class derives from the int32 class because 32—bit integers represent the input port data rates. The MuxCard class inherits the methods of the int32 class, which simplifies the implementation of this subclass.

Class Definition

Here is the definition of the MuxCard class. Notice that the input port rates initialize the int32 portion of class.

```
classdef MuxCard < int32
  properties
        InPutNames
        OutPutName
  end

properties (Dependent = true)
        OutPutRate
  end

methods
    function obj = MuxCard(inptnames, inptrates, outpname)</pre>
```

```
obj = obj@int32(inptrates);
         obj.InPutNames = inptnames;
         obj.OutPutName = outpname;
      end
      function x = get.OutPutRate(obj)
         x = sum(obj);
      end
      function x = subsref(card, s)
         if strcmp(s(1).type, '.')
            base = subsref@int32(card, s(1));
            if isscalar(s)
               x = base;
            else
               x = subsref(base, s(2:end));
            end
         else
            x = subsref(int32(card), s);
         end
      end
   end
end
```

Methods of int32

The constructor takes three arguments:

```
    inptnames — Cell array of input port names
```

- inptrates Vector of input port rates
- outpname Name for the output port

```
omx = MuxCard({'inp1','inp2','inp3','inp4'},[3 12 12 48],'outp')
omx =

1x4 MuxCard array with properties:
    InPutNames: {'inp1' 'inp2' 'inp3' 'inp4'}
    OutPutName: 'outp'
    OutPutRate: 75

int32 data:
```

3 12 12 48

Use an DocMuxCard object like an int32. For example, this statement accesses the int32 data in the object to determine the names of the input ports that have a rate of 12:

```
omx.InPutNames(omx==12)
ans =
   'inp2' 'inp3'
```

Indexing the MuxCard object accesses the int32 vector of input port rates:

The OutPutRate property get access method uses sum to sum the output port rates:

omx.OutPutRate

```
ans = 75
```

Determine Array Class

```
In this section...

"Querying the Class Name" on page 11-76

"Testing for Class" on page 11-76

"Testing for Specific Types" on page 11-77

"Testing for Most Derived Class" on page 11-78
```

Querying the Class Name

Use the class function to determine the class of an array:

```
a = [2,5,7,11];
class(a)
ans =
double
str = 'Character array';
class(str)
ans =
char
```

Testing for Class

The isa function enables you to test for a specific class or a category of numeric class (numeric, float, integer):

```
a = [2,5,7,11];
isa(a,'double')
ans =
1
```

Floating-point values (single and double precision values):

```
isa(a,'float')
ans =
    1
```

Numeric values (floating-point and integer values):

```
isa(a,'numeric')
ans =
    1
```

isa Returns True for Subclasses

isa returns true for classes derived from the specified class. For example, the SubInt class derives from the built-in type int16:

```
classdef SubInt < int16
  methods
    function obj = SubInt(data)
    if nargin == 0
        data = 0;
    end
    obj = obj@int16(data);
  end
end
end</pre>
```

By definition, an instance of the SubInt class is also an instance of the int16 class:

```
aInt = SubInt;
isa(aInt, 'int16')
ans =
    1
```

Using the integer category also returns true:

```
isa(aInt,'integer')
ans =
    1
```

Testing for Specific Types

The class function returns the name of the *most derived* class of an object:

```
class(aInt)
ans =
SubInt
```

Use the **strcmp** function with the **class** function to check for a specific class of an object:

```
a = int16(7);
strcmp(class(a), 'int16')
ans =
1
```

Because the class function returns the class name as a character string, the inheritance of objects does not affect the result of the string comparison performed by strcmp:

```
aInt = SubInt;
strcmp(class(aInt),'int16')
ans =
```

Testing for Most Derived Class

If you define functions that require inputs that are:

- MATLAB built-in types
- · Not subclasses of MATLAB built-in types

Use the following techniques to exclude subclasses of built-in types from the input arguments.

- Define a cell array that contain the names of built-in types accepted by your function.
- · Call class and strcmp to test for specific types in a MATLAB control statement.

Test an input argument:

```
if strcmp(class(inputArg), 'single')
  % Call function
else
  inputArg = single(inputArg);
end
```

Testing for a Category of Types

Suppose you create a MEX-function, myMexFcn, that requires two numeric inputs that must be of type double or single:

```
outArray = myMexFcn(a,b)
```

Define a cell array that contains the character arrays double and single:

```
floatTypes = {'double','single'};
% Test for proper types
if any(strcmp(class(a),floatTypes)) && ...
    any(strcmp(class(b),floatTypes))
    outArray = myMexFcn(a,b);
else
    % Try to convert inputs to avoid error
    ...
end
```

Another Test for Built-In Types

Use isobject to separate built-in types from subclasses of built-in types. The isobject function returns false for instances of built-in types:

```
% Create a int16 array
a = int16([2,5,7,11]);
isobject(a)
ans =
0
```

Determine if an array is one of the built-in integer types:

```
if isa(a,'integer') && ~isobject(a)
   % a is a built-in integer type
   ...
end
```

Abstract Classes

In this section...

"Abstract Classes" on page 11-80

"Declaring Classes as Abstract" on page 11-81

"Determine If a Class Is Abstract" on page 11-82

"Find Inherited Abstract Properties and Methods" on page 11-83

Abstract Classes

Abstract classes are useful for describing functionality that is common to a group of classes, but requires unique implementations within each class.

Abstract Class Terminology

abstract class — A class that cannot be instantiated, but that defines class components used by subclasses.

abstract members — Properties or methods declared in an abstract class, but implemented in subclasses.

concrete members — Properties or methods that are fully implement by a class.

concrete class — A class that can be instantiated. Concrete classes contain no abstract members.

interface — An abstract class describing functionality that is common to a group of classes, but that requires unique implementations within each class. The abstract class defines the interface of each subclass without specifying the actual implementation.

An abstract class serves as a basis (that is, a superclass) for a group of related subclasses. An abstract class can define abstract properties and methods that subclasses must implement. Each subclass can implement the concrete properties and methods in a way that supports their specific requirements.

Abstract classes can define properties and methods that are not abstract, and do not need to define any abstract members. Abstract classes pass on their concrete members through inheritance.

Implementing a Concrete Subclass

A subclass must implement all inherited abstract properties and methods to become a concrete class. Otherwise, the subclass is itself an abstract class.

Declaring Classes as Abstract

A class is abstract when it declares:

- An abstract method
- An abstract property
- The Abstract class attribute

A subclass of an abstract class is itself abstract if it does not define concrete implementations for all inherited abstract methods or properties.

Abstract Methods

Define an abstract method:

```
methods (Abstract)
   abstMethod(obj)
end
```

For methods that declare the Abstract method attribute:

- Do not use a function...end block to define an abstract method, use only the method signature.
- Abstract methods have no implementation in the abstract class.
- Concrete subclasses are not required to support the same number of input and output arguments and do not need to use the same argument names. However, subclasses generally use the same signature when implementing their version of the method.

Abstract Properties

Define an abstract property:

```
properties (Abstract)
   AbsProp
end
```

For properties that declare the Abstract property attribute:

- Concrete subclasses must redefine abstract properties without the Abstract attribute, and must use the same values for the SetAccess and GetAccess attributes as those used in the abstract superclass.
- Abstract properties cannot define set or get access methods (see "Property Access Methods" on page 7-14) and cannot specify initial values. The subclass that defines the concrete property can create set or get access methods and specify initial values.

Abstract Class

Declare a class as abstract in the classdef statement:

```
classdef (Abstract) AbsClass
   ...
end
```

For classes that declare the Abstract class attribute:

- Concrete subclasses must redefine any properties or methods that are declared as abstract.
- The abstract class does not need to define any abstract methods or properties.

When you define any abstract methods or properties, MATLAB automatically sets the class Abstract attribute to true.

Determine If a Class Is Abstract

Determine if a class is abstract by querying the Abstract property of its meta.class object. For example, the AbsClass defines two abstract methods:

```
classdef AbsClass
  methods(Abstract, Static)
    result = absMethodOne
    output = absMethodTwo
  end
end
```

Use the logical value of the meta.class Abstract property to determine if the class is abstract:

```
mc = ?AbsClass;
if ~mc.Abstract
% not an abstract class
```

end

Display Abstract Member Names

Use the meta.abstractDetails function to display the names of abstract properties or methods and the names of the defining classes:

```
meta.abstractDetails('AbsClass');
Abstract methods for class AbsClass:
   absMethodTwo % defined in AbsClass
   absMethodOne % defined in AbsClass
```

Find Inherited Abstract Properties and Methods

The meta.abstractDetails function returns the names and defining class of any inherited abstract properties or methods that you have not implemented in your subclass. This can be useful if you want the subclass to be concrete and need to determine what abstract members the subclass inherits.

For example, suppose you subclass AbsClass, which is described in the "Determine If a Class Is Abstract" on page 11-82 section:

```
classdef SubAbsClass < AbsClass
% Failed to implement absMethodOne
% defined as abstract in AbsClass
   methods (Static)
     function out = absMethodTwo(a,b)
        out = a + b;
   end
  end
end</pre>
```

Determine if you implemented all inherited class members using meta.abstractDetails:

```
meta.abstractDetails(?SubAbsClass)

Abstract methods for class SubAbsClass:
   absMethodOne % defined in AbsClass
```

The SubAbsClass class itself is abstract because it has not implemented the absMethodOne defined in AbsClass.

Interfaces

In this section...

"Interfaces and Abstract Classes" on page 11-84

"An Interface for Classes Implementing Graphs" on page 11-84

Interfaces and Abstract Classes

The properties and methods defined by a class form the interface that determines how class users interact with objects of the class. When creating a group of related classes, define a common interface to all these classes, even though the actual implementations of this interface can differ from one class to another.

For example, consider a set of classes designed to represent various graphs (for example, line plots, bar graphs, pie charts, and so on). Suppose all classes must implement a Data property to contain the data used to generate the graph. However, the form of the data can differ considerably from one type of graph to another. Consequently, the way each class implements the Data property can be different.

The same differences apply to methods. All classes can have a draw method that creates the graph, but the implementation of this method changes with the type of graph.

The basic idea of an interface class is to specify the properties and methods that each subclass must implement without defining the actual implementation. This approach enables you to enforce a consistent interface to a group of related objects. As you add more classes in the future, the original interface remains.

An Interface for Classes Implementing Graphs

This example creates an interface for classes used to display specialized graphs. The interface is an abstract class that defines properties and methods that the subclasses must implement, but does not specify how to implement these components. This approach enforces the use of a consistent interface while providing the necessary flexibility to implement the internal workings of each specialized graph subclass differently.

In this example, the interface, derived subclasses, and a utility function are contained in a package folder:

+graphics/graph.m % abstract interface class

+graphics/linegraph.m % concrete subclass

Interface Properties and Methods

The graph class specifies the following properties, which the subclasses must define:

- Primitive Handle of the Handle Graphics object used to implement the specialized graph. The class user has no need to access these objects directly so this property has protected SetAccess and GetAccess.
- AxesHandle Handle of the axes used for the graph. The specialized graph objects can set axes object properties and also limit this property's SetAccess and GetAccess to protected.
- Data All specialized graph objects must store data, but the type of data varies so
 each subclass defines the storage mechanism. Subclass users can change the data so
 this property has public access rights.

The graph class names three abstract methods that subclasses must implement. The graph class also suggests in comments that each subclass constructor must accept the plot data and property name/property value pairs for all class properties.

- subclass_constructor Accept data and P/V pairs and return an object.
- draw Used to create a drawing primitive and render a graph of the data according to the type of graph implemented by the subclass.
- zoom Implementation of a zoom method by changing the axes CameraViewAngle property. The interface suggests the use of the camzoom function for consistency among subclasses. The zoom buttons created by the addButtons static method use this method as a callback.
- updateGraph Method called by the set.Data method to update the plotted data whenever the Data property changes.

Interface Guides Class Design

The package of classes that derive from the graph abstract class implement the following behaviors:

- Creating an instance of a specialized graph object (subclass object) without rendering the plot
- Specifying any or none of the object properties when you create a specialized graph object
- · Changing any object property automatically updates the currently displayed plot

 Allowing each specialized graph object to implement whatever additional properties it requires to give class users control over those characteristics.

Defining the Interface

The graph class is an abstract class that defines the methods and properties used by the subclasses. Comments in the abstract class suggest the intended implementation:

```
classdef graph < handle
% Abstract class for creating data graphs
% Subclass constructor should accept
% the data that is to be plotted and
% property name/property value pairs
   properties (SetAccess = protected, GetAccess = protected)
      Primitive % HG primitive handle
      AxesHandle % Axes handle
   end
   properties % Public access
      Data
   end
   methods (Abstract)
      draw(obj)
      % Use a line, surface,
      % or patch HG primitive
      zoom(obj,factor)
      % Change the CameraViewAngle
      % for 2D and 3D views
      % use camzoom for consistency
      updateGraph(obj)
      % Called by the set.Data method
      % to update the drawing primitive
      % whenever the Data property is changed
   end
   methods
      function set.Data(obj,newdata)
         obj.Data = newdata;
         updateGraph(obj)
      end
      function addButtons(gobj)
         hfig = get(gobj.AxesHandle,'Parent');
         uicontrol(hfig, 'Style', 'pushbutton', 'String', 'Zoom Out',...
            'Callback',@(src,evnt)zoom(gobj,.5));
         uicontrol(hfig, 'Style', 'pushbutton', 'String', 'Zoom In',...
            'Callback',@(src,evnt)zoom(gobj,2),...
            'Position',[100 20 60 20]);
      end
   end
end
```

The graph class implements the property set method (set.Data) to monitor changes to the Data property. An alternative is to define the Data property as Abstract and enable the subclasses to determine whether to implement a set access method for this

property. However, by defining the set access method that calls an abstract method (updateGraph, which each subclass must implement), the graph interface imposes a specific design on the whole package of classes, without limiting flexibility.

Method to Work with All Subclasses

The addButtons method adds push buttons for the zoom methods, which each subclass must implement. Using a method instead of an ordinary function enables addButtons to access the protected class data (the axes handle). Use the object's zoom method as the push button callback.

```
function addButtons(gobj)
  hfig = get(gobj.AxesHandle,'Parent');
  uicontrol(hfig,'Style','pushbutton','String','Zoom Out',...
    'Callback',@(src,evnt)zoom(gobj,.5));
  uicontrol(hfig,'Style','pushbutton','String','Zoom In',...
    'Callback',@(src,evnt)zoom(gobj,2),...
    'Position',[100 20 60 20]);
end
```

Deriving a Concrete Class — linegraph

This example defines only a single subclass used to represent a simple line graph. It derives from graph, but provides implementations for the abstract methods draw, zoom, updateGraph, and its own constructor. The base class (graph) and subclass are all contained in a package (graphics), which you must use to reference the class name:

```
classdef linegraph < graphics.graph</pre>
```

Adding Properties

The linegraph class implements the interface defined in the graph class and adds two additional properties—LineColor and LineType. This class defines initial values for each property, so specifying property values in the constructor is optional. You can create a linegraph object with no data, but you cannot produce a graph from that object.

```
properties
   LineColor = [0 0 0];
   LineType = '-';
end
```

The linegraph Constructor

The constructor accepts a struct with x and y coordinate data, as well as property name/property value pairs:

```
function gobj = linegraph(data,varargin)
  if nargin > 0
    gobj.Data = data;
  if nargin > 2
    for k=1:2:length(varargin)
        gobj.(varargin{k}) = varargin{k+1};
    end
  end
end
end
```

Implementing the draw Method

The linegraph draw method uses property values to create a line object. The linegraph class stores the line handle as protected class data. To support the use of no input arguments for the class constructor, draw checks the Data property to determine if it is empty before proceeding:

```
function gobj = draw(gobj)
  if isempty(gobj.Data)
    error('The linegraph object contains no data')
  end
  h = line(gobj.Data.x,gobj.Data.y,...
    'Color',gobj.LineColor,...
    'LineStyle',gobj.LineType);
  gobj.Primitive = h;
  gobj.AxesHandle = get(h,'Parent');
end
```

Implementing the zoom Method

The linegraph zoom method follows the comments in the graph class which suggest using the camzoom function. camzoom provides a convenient interface to zooming and operates correctly with the push buttons created by the addButtons method.

Defining the Property Set Methods

Property set methods provide a convenient way to execute code automatically when the value of a property changes for the first time in a constructor. (See "Property Set Methods".) The linegraph class uses set methods to update the line primitive data (which causes a redraw of the plot) whenever a property value changes. The use of property set methods provides a way to update the data plot quickly without requiring a call to the draw method. The draw method updates the plot by resetting all values to match the current property values.

Three properties use set methods: LineColor, LineType, and Data. LineColor and LineType are properties added by the linegraph class and are specific to the line primitive used by this class. Other subclasses can define different properties unique to their specialization (for example., FaceColor).


The graph class implements the Data property set method. However, the graph class requires each subclass to define a method called updateGraph, which handles the update of plot data for the specific drawing primitive used.

Using the linegraph Class

The linegraph class defines the simple API specified by the graph base class and implements its specialized type of graph:

```
d.x = 1:10;
d.y = rand(10,1);
lg = graphics.linegraph(d,'LineColor','b',...
    'LineType',':');
lg.draw;
lg.addButtons;
```


Clicking the **Zoom In** button shows the **ZOOM** method providing the callback for the button.



Changing properties updates the graph:

```
d.y = rand(10,1); % new set of random data for y
lg.Data = d;
lg.LineColor = [0.9,0.1,0.6]; % LineColor can be char or double
```

Now click **Zoom Out** and see the new results:



Saving and Loading Objects

- "Save and Load Process" on page 12-2
- "Reduce MAT-File Size for Saved Objects" on page 12-4
- · "Save Object Data to Recreate Graphics Objects" on page 12-5
- "Improve Version Compatibility with Default Values" on page 12-7
- "Avoid Property Initialization Order Dependency" on page 12-9
- "Modify the Save and Load Process" on page 12-13
- "Maintain Class Compatibility" on page 12-18
- "Initialize Objects" on page 12-25
- "Save and Load Objects from Class Hierarchies" on page 12-27
- "Restore Listeners" on page 12-30
- "Save and Load Dynamic Properties" on page 12-33

Save and Load Process

In this section...

"Save and Load Objects" on page 12-2

"What Information Is Saved?" on page 12-2

"How Is the Property Data Loaded?" on page 12-2

"Errors During Load" on page 12-3

Save and Load Objects

Use save and load to store and reload objects:

```
save filename object load filename object
```

What Information Is Saved?

Saving objects in MAT-files saves:

- · The full name of the object class, including any package qualifiers
- · Values of dynamic properties
- The names and values of all properties, except properties that have their Transient,
 Constant, or Dependent attributes set to true
 - Properties that have their Transient, Constant, or Dependent attributes set to true.

For a description of property attributes, see "Specify Property Attributes" on page 7-5

To save graphics objects, see savefig.

How Is the Property Data Loaded?

When loading objects from MAT-files, load restores the object. The load function:

- · Creates a new object.
- Assigns the values saved for each property.

- Calls the class constructor with no arguments *only* if the class ConstructOnLoad attribute is set to true. Otherwise, load does not call the class constructor.
- Assigns the saved property values to the object properties. These assignments result
 in calls to property set methods defined by the class (except in the case of Dependent
 properties, which are not saved or loaded).

You can use property set methods to ensure that property values are still valid in cases where the class definition has changed.

For information on property set methods, see "Property Set Methods".

Errors During Load

If a new version of a class removes or renames a property, load can generate an error when attempting to set the altered or deleted property.

In many cases, careful class design can prevent load problems when class definitions change between saved versions.

When an error occurs while an object is being loaded from a file, MATLAB does one of the following:

- If the class defines a loadobj method, MATLAB returns the saved values to the loadobj method in a struct.
- If the class does not define a loadobj method, MATLAB silently ignores the errors.
 The load function reconstitutes the object with property values that do not produce an error.

In the struct passed to the loadobj method, the field names correspond to the property names. The field values are the saved values for the corresponding properties.

If the saved object derives from multiple superclasses that have private properties with same name, the **struct** contains only the property value of the most direct superclass.

For information on how to implement saveobj and loadobj methods, see "Modify the Save and Load Process" on page 12-13.

Reduce MAT-File Size for Saved Objects

In this section...

"Default Values" on page 12-4

"Dependent Properties" on page 12-4

"Transient Properties" on page 12-4

"Avoid Saving Unwanted Variables" on page 12-4

Default Values

If a property often has the same value, define a default value for that property. When the user saves the object to a MAT-file, MATLAB does not save the default value, which reduces the size of the MAT-file.

For more information on how MATLAB evaluates default value expressions, see "Defining Default Values" on page 4-12.

Dependent Properties

Use a dependent property when the property value must be calculated at run time. A dependent property is not saved in the MAT-file when you save an object. Instances of the class do not allocate memory to hold a value for a dependent property.

Dependent is a property attribute (see "Property Attributes" on page 7-7 for a complete list.)

Transient Properties

MATLAB does not store the values of transient properties. Transient properties can store data in the object temporarily as an intermediate computation step or for faster retrieval. Use transient properties when you easily can reproduce the data at run time or when the data represents intermediate state that can be discarded.

Avoid Saving Unwanted Variables

Do not save variables that you do not want to load. Be sure that an object is still valid before you save it. For example, if you save a deleted handle object, MATLAB loads it as a deleted handle.

Save Object Data to Recreate Graphics Objects

In this section...

"What to Save" on page 12-5

"Regenerate When Loading" on page 12-5

"Change to a Stairstep Chart" on page 12-6

What to Save

Use transient properties to avoid saving what you can recreate when loading the object. For example, an object can contain component parts that you can regenerate from data that is saved. Regenerating these components also enables newer versions of the class to create the components in a different way.

Regenerate When Loading

The YearlyRainfall class illustrates how to regenerate a graph when loading objects of that class. YearlyRainfall objects contain a bar chart of the monthly rainfall for a given location and year. The Location and Year properties are ordinary properties whose values are saved when you save the object.

The Chart property contains the handle to the bar chart. When you save a bar chart, MATLAB also saves the figure, axes, and Bar object as well as the data required to create these graphics objects. The YearlyRainfall class design eliminates the need to save objects that it can regenerate:

- The Chart property is Transient so the graphics objects are not saved.
- ChartData is a private property that provides storage for the Bar object data (YData).
- The load function calls the set.ChartData method, passing it the saved bar chart data.
- The setup method regenerates the bar chart and assigns the handle to the Chart property. Both the class constructor and the set.ChartData method call setup.

```
classdef YearlyRainfall < handle
  properties
    Location</pre>
```

```
Year
   end
   properties(Transient)
      Chart
   end
   properties(Access = private)
      ChartData
   end
   methods
      function rf = YearlyRainfall(data)
         setup(rf,data);
      end
      function set.ChartData(obj,V)
         setup(obj,V);
      end
      function V = get.ChartData(obj)
         V = obj.Chart.YData;
      end
   end
   methods(Access = private)
      function setup(rf,data)
         rf.Chart = bar(data);
      end
   end
end
```

Change to a Stairstep Chart

An advantage of the YearlyRainfall class design is the flexibility to modify the type of graph used without making previously saved objects incompatible. Loading the object recreates the graph based only on the data that is saved to the MAT-file.

For example, change the type of graph from a bar chart to a stair-step graph by modifying the setup method:

```
methods(Access = private)
  function setup(rf,data)
    rf.Chart = stairs(data);
  end
end
```

Improve Version Compatibility with Default Values

```
In this section...

"Version Compatibility" on page 12-7

"Using a Default Property Value" on page 12-7
```

Version Compatibility

Default property values can help you implement version compatibility for saved objects. For example, suppose that you add a property to version 2 of your class. Having a default value enables MATLAB to assign a value to the new property when loading a version 1 object.

Similarly, suppose version 2 of your class removes a property. If a version 2 object is saved and loaded into version 1, your loadobj method can use the default value from version 1.

Using a Default Property Value

The EmployeeInfo class shows how to use property default values as a way to enhance compatibility among versions. Version 1 of the EmployeeInfo class defines three properties — Name, JobTitle, and Department.

```
classdef EmployeeInfo
  properties
    Name
    JobTitle
    Department
  end
end
```

Version 2 of the EmployeeInfo class adds a property, Country, for the country name of the employee location. The Country property has a default value of the string 'USA'.

```
classdef EmployeeInfo
  properties
    Name
    JobTitle
    Department
    Country = 'USA';
```

end end

The character array, 'USA', is a good default value because:

- MATLAB assigns and empty double [] to properties that do not have default values defined by the class. Empty double is not a valid value for the Country property.
- In version 1, all employees were in the USA. Therefore, any version 1 object loaded into version 2 receives a valid value for the Country property.

Avoid Property Initialization Order Dependency

In this section...

"Control Property Loading" on page 12-9

"Dependent Property with Private Storage" on page 12-9

"Property Value Computed from Other Properties" on page 12-11

Control Property Loading

Problems loading properties can occur when property values depend on the order in which the properties are set.

Suppose your class design is such that both of the following are true:

- A property set method changes another property value.
- A property value is computed solely from other property values.

Then the final state of an object after changing a series of property values can depend on the order in which you set the properties. This order dependency can affect the result of loading an object.

The load function sets property values in a particular order. This order can be different from the order in which you set the properties in the saved object. As a result, the loaded object can have different property values than the object had when it was saved.

Restore Nondependent Properties

If a property set function changes the values of other properties, then define the Dependent attribute of that property as true. MATLAB does not save or restore dependent property values.

Use nondependent properties for storing the values set by the dependent property. Then the load function restores the nondependent properties with the same values that were saved. The load function does not call the dependent property set method because there is no value in the saved file for that property.

Dependent Property with Private Storage

The Odometer class avoids order dependences when loading objects by controlling which properties are restored when loading:

- The Units property is dependent. Its property set method sets the TotalDistance property. Therefore load does not call the Units property set method.
- The load function restores TotalDistance to whatever value it had when you saved the object.

```
classdef Odometer
   properties(Constant)
      ConversionFactor = 1.6
   end
   properties
      TotalDistance = 0
   properties(Dependent)
      Units
   properties(Access=private)
      PrivateUnits = 'mi'
   end
   methods
      function unit = get.Units(obj)
         unit = obj.PrivateUnits;
      end
      function obj = set.Units(obj,newUnits)
         % validate newUnits to be a string
         switch(newUnits)
            case 'mi'
               if strcmp(obj.PrivateUnits,'km')
                  obj.TotalDistance = obj.TotalDistance / ...
                     obj.ConversionFactor;
                  obj.PrivateUnits = newUnits;
               end
            case 'km'
               if strcmp(obj.PrivateUnits, 'mi')
                  obj.TotalDistance = obj.TotalDistance * ...
                     obj.ConversionFactor;
                  obj.PrivateUnits = newUnits;
               end
            otherwise
               error('Odometer:InvalidUnits', ...
                  'Units ''%s'' is not supported.', newUnits);
         end
      end
   end
end
```

Suppose that you create an instance of Odometer and set the following property values:

```
odObj = Odometer;
odObj.Units = 'km';
odObj.TotalDistance = 16;
```

When you save the object:

- ConversionFactor is not saved because it is a Constant property.
- TotalDistance is saved.
- Units is not saved because it is a Dependent property.
- PrivateUnits is saved and provides the storage for the current value of Units.

When you load the object:

- ConversionFactor is obtained from the class definition.
- TotalDistance is loaded.
- Units is not loaded, so its set method is not called.
- PrivateUnits is loaded from the saved object.

If the Units property was not Dependent, loading it calls its set method and causes the TotalDistance property to be set again.

Property Value Computed from Other Properties

The Odometer2 class TripDistance property depends only on the values of two other properties, TotalDistance and TripMarker.

The class avoids order dependence when initializing property values during the load process by making the TripDistance property dependent. MATLAB does not save or load a value for the TripDistance property, but does save and load values for the two properties used to calculate TripDistance in its property get method.

```
classdef Odometer2
  properties
    TotalDistance = 0
    TripMarker = 0
  end
  properties(Dependent)
    TripDistance
```

```
end
   methods
     function distance = get.TripDistance(obj)
         distance = obj.TotalDistance - obj.TripMarker;
      end
   end
end
```

Modify the Save and Load Process

In this section...

"When to Modify the Save and Load Process" on page 12-13

"How to Modify the Save and Load Process" on page 12-13

"Implementing saveobj and loadobj Methods" on page 12-14

"Additional Considerations" on page 12-14

"A Typical saveobj and loadobj Pattern" on page 12-15

"Regenerating from Object or struct" on page 12-16

"Related Examples" on page 12-17

When to Modify the Save and Load Process

The primary reason for modifying the save and load process is to support backward and forward compatibility of classes. Consider modifying the save and load process when you:

- Rename the class
- · Remove properties
- Define a circular reference of handle objects where initialization order is important
- Must call the constructor with arguments and, therefore, cannot use ConstructOnLoad

How to Modify the Save and Load Process

The most versatile technique for modifying the save and load process is to implement loadobj, and if necessary, saveobj methods for your class. MATLAB executes these methods when you call save or load on an object of the class.

The save function calls your class saveobj method before performing the save operation. The save function then saves the value returned by the saveobj method. You can use saveobj to return a modified object or a struct that contains property values.

load calls your class loadobj method after loading the object. The load function loads the value returned by the loadobj method into the workspace. A loadobj method can

modify the object being loaded or can reconstruct an object from the data saved by your saveobj method.

Implementing saveobj and loadobj Methods

Implement a saveobj method that modifies the object being saved, then implement a loadobj method to return the object to a specific state when loading it.

Implement the loadobj method as a Static method because loadobj can be called with a struct or other data type instead of an object of the class.

You can implement the saveobj method as an ordinary method (that is, calling it requires an instance of the class).

MATLAB saves the object class name so that load can determine which loadobj method to call in cases where your saveobj method saves only the object data in an array. Therefore, the class must be accessible to MATLAB when you load the object.

Use a loadobj method when:

- The class definition has changed since the object was saved, requiring you to modify the object before loading.
- A saveobj method modified the object during the save operation, perhaps saving
 data in a struct. In this case, the loadobj method must reconstruct the object from
 the output of saveobj.

Additional Considerations

When you decide to modify the default save and load process, keep the following points in mind:

- If loading any property value from the MAT-file produces an error, load passes a struct to loadobj. The struct field names correspond to the property names extracted from the file.
- loadobj must always be able to accept a struct as input and return an object, even if there is no saveobj or saveobj does not return a struct.
- If saveobj returns a struct, then load always passes that struct to loadobj.

• Subclass objects inherit superclass loadobj and saveobj methods. Therefore, if you do not implement a loadobj or saveobj method in the most specific class, MATLAB calls only the inherited methods.

If a superclass implements a loadobj or saveobj method, then your subclass can also implement a loadobj or saveobj method that calls the superclass methods as necessary. See "Save and Load Objects from Class Hierarchies" on page 12-27 for more information.

• The load function does not call the constructor by default. For more information, see "Initialize Objects" on page 12-25.

A Typical saveobj and loadobj Pattern

There are various ways you can use Saveobj and loadobj methods, depending on the requirements of your class. The pattern that is described here is a flexible way to solve various problems that you cannot address by simpler means.

The basic process is:

- Use saveobj to save all essential data in a struct and do not save the object.
- · Use loadobj to reconstruct the object from the saved data.

This approach is not useful in cases where you cannot save property values in a **struct** field. Data that you cannot save, such as a file identifier, you can possibly regenerate in the **loadobj** method.

saveobj

For this pattern, define saveobj as an ordinary method that accepts an object of the class and returns a struct.

- · Copy each property value to a structure field of the same name.
- You can save only the data that is necessary to rebuild the object. Avoid saving whole
 objects hierarchies, such as those created by graphs.

methods

```
function s = saveobj(obj)
  s.Prop1 = obj.Prop1;
  s.Prop2 = obj.Prop2
  s.Data = obj.GraphHandle.YData;
end
```

end

loadobj

Define loadobj as a static method. Create an object by calling the class constructor. Then assign values to properties from the struct passed to loadobj. Use the data to regenerate properties that were not saved.

```
methods(Static)
  function obj = loadobj(s)
   if isstruct(s)
      newObj = ClassConstructor;
      newObj.Prop1 = s.Prop1;
      newObj.Prop2 = s.Prop2
      newObj.GraphHandle = plot(s.Data);
      obj = newObj;
  else
      obj = s;
  end
  end
end
```

If the load function encounters an error, load passes loadobj a struct instead of an object. Your loadobj method must always be able to handle a struct as the input argument. The input to loadobj is always a scalar.

Regenerating from Object or struct

saveobj does not have to save the object data in a struct. Sometimes using only a loadobj method can be useful.

The GraphExpression class creates a graph of a MATLAB expression over a specified range of data. GraphExpression uses its loadobj method to regenerate the graph, which is not saved. The loadobj method works with either a struct or an object as input

```
classdef GraphExpression
  properties
    FuncHandle
    Range
  end
  methods
    function obj = GraphExpression(fh,rg)
```

```
obj.FuncHandle = fh;
         obj.Range = rg;
         makeGraph(obj)
      end
      function makeGraph(obj)
         rg = obj.Range;
         x = min(rg):max(rg);
         data = obj.FuncHandle(x);
         plot(data)
      end
   end
   methods (Static)
      function obj = loadobj(s)
         if isstruct(s)
            fh = s.FuncHandle;
            rg = s.Range;
            obj = GraphExpression(fh,rg);
         else
            makeGraph(s);
            obj = s;
         end
      end
   end
end
```

Related Examples

For examples that modify the save and load process, see:

- "Maintain Class Compatibility" on page 12-18
- "Restore Listeners" on page 12-30
- "Initialize Objects" on page 12-25

Maintain Class Compatibility

```
In this section...

"Rename Property" on page 12-18

"Update Property When Loading" on page 12-20

"Maintaining Compatible Versions of a Class" on page 12-21

"Version 2 of the PhoneBookEntry Class" on page 12-22
```

Rename Property

Suppose you want to rename a property, but do not want to cause errors in existing code that refer to the original property. For example, rename a public property called OfficeNumber to Location. Here is the original class definition:

```
classdef EmployeeList
  properties
    Name
    Email
    OfficeNumber % Rename as Location
  end
end
```

Use of a hidden dependent property can achieve the desired results.

- In the class definition, set the OfficeNumber property attributes to Dependent and Hidden.
- Create a property set method for OfficeNumber that sets the value of the Location property.
- Create a property get method for OfficeNumber that returns the value of the Location location property.

While the OfficeNumber property is hidden, existing code can continue to access this property. The Hidden attribute does not affect access.

Because OfficeNumber is dependent, there is no redundancy in storage required by adding the new property. MATLAB does not store or save dependent properties.

Here is the updated class definition.

```
classdef EmployeeList
   properties
      Name
      Email
      Location
   end
   properties (Dependent, Hidden)
      OfficeNumber
   end
   methods
      function obj = set.OfficeNumber(obj,val)
         obj.Location = val;
      end
      function val = get.OfficeNumber(obj)
         val = obj.Location;
      end
   end
end
```

Saving and Loading EmployeeList Objects

You can load old instances of the EmployeeList class in the presence of the new class version. Code that refers to the OfficeNumber property continues to work.

Forward and Backward Compatibility

Suppose you want to be able to load new EmployeeList objects into systems that still have the old version of the EmployeeList class. To achieve compatibility with old and new versions:

- Define the OfficeNumber property as Hidden, but not Dependent.
- Define the Location property as Dependent.

In this version of the EmployeeList class, the OfficeNumber property saves the value used by the Location property. Loading an object assigns values of the three original properties (Name, Email, and OfficeNumber), but does not assign a value to the new Location property. The lack of the Location property in the old class definition is not a problem.

```
classdef EmployeeList
  properties
    Name
    Email
```

```
end
properties (Dependent)
   Location
end
properties (Hidden)
   OfficeNumber
end
methods
   function obj = set.Location(obj,val)
      obj.OfficeNumber = val;
end
   function val = get.Location(obj)
   val = obj.OfficeNumber;
end
end
end
```

Update Property When Loading

Suppose that you modify a class so that a property value changes in its form or type. Previously saved objects of the class must be updated when loaded to have a conforming property value.

Consider a class that has an AccountID property. Suppose that all account numbers must migrate from eight-digit numeric values to 12-element character arrays.

You can accommodate this change by implementing a loadobj method.

The loadobj method:

- Tests to determine if the load function passed a struct or object. All loadobj methods must handle both struct and object when there is an error in load.
- Tests to determine if the AccountID number contains eight digits. If so, change it to a 12-element character array by calling the paddAccID method.

After updating the AccountID property, loadobj returns a MyAccount object that MATLAB loads into the workspace.

```
classdef MyAccount
properties
AccountID
end
```

```
methods
      function obj = padAccID(obj)
         ac = obj.AccountID;
         acstr = num2str(ac);
         if length(acstr) < 12</pre>
            obj.AccountID = [acstr,repmat('0',1,12-length(acstr))];
         end
      end
   end
   methods (Static)
      function obj = loadobj(a)
         if isstruct(a)
            obj = MyAccount;
            obj.AccountID = a.AccountID;
            obj = padAccID(obj);
         elseif isa(a,'MyAccount')
            obj = padAccID(a);
         end
      end
   end
end
```

You do not need to implement a **Saveobj** method. You are using **loadobj** only to ensure that older saved objects are brought up to date while loading.

Maintaining Compatible Versions of a Class

The PhoneBookEntry class uses a combination of techniques to maintain compatibility with new versions of the class.

Suppose that you define a class to represent an entry in a phone book. The PhoneBookEntry class defines three properties: Name, Address, and PhoneNumber.

```
classdef PhoneBookEntry
   properties
     Name
     Address
     PhoneNumber
   end
end
```

However, in future releases, the class will add more properties. To provide flexibility, PhoneBookEntry saves property data in a struct using its saveobj method.

```
methods
  function s = saveobj(obj)
    s.Name = obj.Name;
    s.Address = obj.Address;
    s.PhoneNumber = obj.PhoneNumber;
end
end
```

The loadobj method creates the PhoneBookEntry object, which is then loaded into the workspace.

```
methods (Static)
  function obj = loadobj(s)
   if isstruct(s)
      newObj = PhoneBookEntry;
      newObj.Name = s.Name;
      newObj.Address = s.Address;
      newObj.PhoneNumber = s.PhoneNumber;
      obj = newObj;
  else
      obj = s;
  end
  end
end
```

Version 2 of the PhoneBookEntry Class

In version 2 of the PhoneBookEntry class, you split the Address property into StreetAddress, City, State, and ZipCode properties.

With these changes, you could not load a version 2 object in a previous release. However, version 2 employs a number of techniques to enable compatibility:

- Preserve the Address property (which is used in version 1) as a Dependent property with private SetAccess.
- Define an Address property get method (get.Address) to build a string that is compatible with the version 2 Address property.
- The saveobj method invokes the get.Address method to assign the object data to a struct that is compatible with previous versions. The struct continues to have only an Address field built from the data in the new StreetAddress, City, State, and ZipCode properties.

- When the loadobj method sets the Address property, it invokes the property set method (set.Address), which extracts the substrings required by the StreetAddress, City, State, and ZipCode properties.
- The Transient (not saved) property SaveInOldFormat enables you to specify whether to save the version 2 object as a struct or an object.

```
classdef PhoneBookEntry
   properties
      Name
      StreetAddress
      Citv
      State
      ZipCode
      PhoneNumber
   properties (Constant)
      Sep = ', ';
   properties (Dependent, SetAccess=private)
      Address
   end
   properties (Transient)
      SaveInOldFormat = false;
   end
   methods (Static)
      function obj = loadobj(s)
         if isstruct(s)
            obj = PhoneBookEntry;
            obj.Name = s.Name;
            obj.Address = s.Address;
            obj.PhoneNumber = s.PhoneNumber;
         else
            obj = s;
         end
      end
   end
   methods
      function address = get.Address(obj)
         address = [obj.StreetAddress,obj.Sep,obj.City,obj.Sep,...
            obj.State,obj.Sep,obj.ZipCode];
      end
      function obj = set.Address(obj,address)
         addressItems = regexp(address,obj.Sep,'split');
         if length(addressItems) == 4
```

```
obj.StreetAddress = addressItems{1};
            obj.City = addressItems{2};
            obj.State = addressItems{3};
            obj.ZipCode = addressItems{4};
         else
            error('PhoneBookEntry:InvalidAddressFormat', ...
               'Invalid address format.');
         end
      end
      function s = saveobj(obj)
         if obj.SaveInOldFormat
            s.Name = obj.Name;
            s.Address = obj.Address;
            s.PhoneNumber = obj.PhoneNumber;
         end
      end
   end
end
```

Initialize Objects

```
In this section...

"Calling Constructor When Loading Objects" on page 12-25

"Initializing Objects in the loadobj Method" on page 12-25
```

Calling Constructor When Loading Objects

MATLAB does not call the class constructor when loading an object from a MAT-file. However, if you set the ConstructOnLoad class attribute to true, load does call the constructor with no arguments.

Enable ConstructOnLoad when you do not want to implement a loadobj method, but must perform some actions at construction time. For example, enable ConstructOnLoad when you are registering listeners for another object. Ensure that MATLAB can call the class constructor with no arguments without generating an error.

If the constructor requires input arguments, use a loadobj method.

Initializing Objects in the loadobj Method

Use a loadobj method when the class constructor requires input arguments to perform object initialization.

The LabResults class shares the constructor object initialization steps with the loadobj method by performing these steps in the assignStatus method.

Objects of the LabResults class:

- Hold values for the results of tests.
- Assign a status for each value based on a set of criteria.

```
classdef LabResult
  properties
     CurrentValue
  end
  properties (Transient)
     Status
```

```
end
   methods
      function obj = LabResult(cv)
         obj.CurrentValue = cv;
         obj = assignStatus(obj);
      end
      function obj = assignStatus(obj)
         v = obj.CurrentValue;
         if v < 10
            obj.Status = 'Too low';
         elseif v >= 10 && v < 100
            obj.Status = 'In range';
         else
            obj.Status = 'Too high';
         end
      end
   end
   methods (Static)
      function obj = loadobj(s)
         if isstruct(s)
            cv = s.CurrentValue;
            obj = LabResults(cv);
         else
            obj = assignStatus(s);
         end
      end
   end
end
```

The LabResults class uses loadobj to determine the status of a given test value. This approach provides a way to:

- Modify the criteria for determining status
- · Ensure that objects always use the current criteria

You do not need to implement a saveobj method.

Save and Load Objects from Class Hierarchies

In this section...

"Saving and Loading Subclass Objects" on page 12-27

"Reconstruct the Subclass Object from a Saved struct" on page 12-27

Saving and Loading Subclass Objects

If the most specific class of an object does not define a loadobj or saveobj method, this class can inherit loadobj or saveobj methods from a superclass.

If any class in the hierarchy defines saveobj or loadobj methods:

- Define saveobj for all classes in the hierarchy.
- Call superclass saveobj methods from the subclass saveobj method because the save function calls only the most specific saveobj method.
- The subclass loadobj method can call the superclass loadobj, or other methods as required, to assign values to their properties.

Reconstruct the Subclass Object from a Saved struct

Suppose you want to save a subclass object by first converting its property data to a struct in the class saveobj method. Then you reconstruct the object when loaded using its loadobj method. This action requires that:

- Superclasses implement saveobj methods to save their property data in the struct.
- The subclass saveobj method calls each superclass saveobj method and returns the completed struct to the save function. Then the save function writes the struct to the MAT-file.
- The subclass loadobj method creates a subclass object and calls superclass methods to assign their property values in the subclass object.
- The subclass loadobj method returns the reconstructed object to the load function, which loads the object into the workspace.

The following superclass (MySuper) and subclass (MySub) definitions show how to code these methods.

- The MySuper class defines a loadobj method to enable an object of this class to be loaded directly.
- The subclass loadobj method calls a method named reload after it constructs the subclass object.
- reload first calls the superclass reload method to assign superclass property values and then assigns the subclass property value.

```
classdef MySuper
   properties
      Χ
      Υ
   end
   methods
      function S = saveobj(obj)
         S.PointX = obj.X;
         S.PointY = obj.Y;
      function obj = reload(obj,S)
         obj.X = S.PointX;
         obj.Y = S.PointY;
      end
   end
   methods (Static)
      function obj = loadobj(S)
         if isstruct(s)
            obj = MySuper;
            obj = reload(obj,S);
         end
      end
   end
end
```

Call the superclass saveobj and loadobj methods from the subclass saveobj and loadobj methods.

```
classdef MySub < MySuper
  properties
    Z
  end
  methods
    function S = saveobj(obj)
    S = saveobj@MySuper(obj);
    S.PointZ = obj.Z;</pre>
```

```
end
function obj = reload(obj,S)
    obj = reload@MySuper(obj,S);
    obj.Z = S.PointZ;
end
end
methods (Static)
    function obj = loadobj(S)
        if isstruct(s)
        obj = MySub;
        obj = reload(obj,S);
        end
    end
end
end
```

Restore Listeners

```
In this section...

"Create Listener with loadobj" on page 12-30

"Use Transient Property to Load Listener" on page 12-30

"Using the BankAccount and AccountManager Classes" on page 12-32
```

Create Listener with loadobj

Suppose that you create a property listener and want to be able to save and restore the event source and the listener. One approach is to create a listener from the loadobj method.

Use Transient Property to Load Listener

The BankAccount class stores the account balance and an account status. A PostSet listener attached to the AccountBalance property controls the account status.

When the AccountBalance property value changes, the listener callback determines the account status. Important points include:

- The BankAccount class defines the AccountManagerListener property to contain the listener handle. This property enables the loadobj method to create a listener and return a reference to it in the object that is loaded into the workspace.
- The AccountManagerListener property is Transient because there is no need to store the listener handle with a BankAccount object. Create a listener that is attached to the new BankAccount object created during the load process.
- The AccountBalance listener sets the AccountStatus.
- Only the AccountManager class can access AccountStatus property.

```
classdef BankAccount < handle
  properties (SetObservable, AbortSet)
    AccountBalance
  end
  properties (Transient)
    AccountManagerListener
  end
  properties (Access = ?AccountManager)</pre>
```

```
AccountStatus
   end
   methods
      function obj = BankAccount(initialBalance)
         obj.AccountBalance = initialBalance;
         obj.AccountStatus = 'New Account';
         obj.AccountManagerListener = AccountManager.addAccount(obj);
      end
   end
   methods (Static)
      function obj = loadobj(obj)
         if isstruct(obj) % Handle possble error
            initialBalance = obj.AccountBalance;
            obj = BankAccount(initialBalance);
         else
            obj.AccountManagerListener = AccountManager.addAccount(obj);
         end
      end
   end
end
```

Assume the AccountManager class provides services for various types of accounts. For the BankAccount class, the AccountManager class defines two Static methods:

- assignStatus Callback for the AccountBalance property PostSet listener. This method determines the value of the BankAccount AccountStatus property.
- addAccount Creates the AccountBalance property PostSet listener. The BankAccount constructor and loadobj methods call this method.

```
classdef AccountManager
  methods (Static)
  function assignStatus(BA,~)
    if BA.AccountBalance < 0 && BA.AccountBalance >= -100
        BA.AccountStatus = 'overdrawn';
  elseif BA.AccountBalance < -100
        BA.AccountStatus = 'frozen';
  else
        BA.AccountStatus = 'open';
  end
end
function lh = addAccount(BA)
  lh = addlistener(BA,'AccountBalance','PostSet', ...
    @(src,evt)AccountManager.assignStatus(BA));
end</pre>
```

```
end
end
```

Using the BankAccount and AccountManager Classes

Create an instance of the BankAccount class.

Now set an account value to confirm that the AccountManager sets AccountStatus appropriately:

```
ba.AccountBalance = -10;
ba.AccountStatus
ans =
overdrawn
```

Related Information

```
"Property Attributes"
```

"Listen for Changes to Property Values"

Save and Load Dynamic Properties

In this section...

"Saving Dynamic Properties" on page 12-33

"When You Need saveobj and loadobj Methods" on page 12-33

"Implementing saveobj and loadobj Methods" on page 12-33

Saving Dynamic Properties

Use the addprop method to add dynamic properties to a class that is derived from the dynamicprops class. The save function saves dynamic properties with the object to which they are attached. For more information on dynamic properties, see "Dynamic Properties — Adding Properties to an Instance" on page 7-30.

When You Need saveobj and loadobj Methods

The save function saves dynamic properties and their values. However, save does not save dynamic property attributes because these attributes are not specified in the class definition. If you save an object that has dynamic properties with nondefault attributes values, use saveobj and loadobj to manage the saving and loading of attribute values.

If the dynamic property has nondefault attribute values, convert the object to a struct in the saveobj method. Save the dynamic property attribute values in the struct so that the loadobj method can restore these values.

Implementing saveobj and loadobj Methods

Your saveObj method can obtain the nondefault attribute values from the meta.DynamicProperty object associated with the dynamic property. Suppose the object that you are saving has a dynamic property called DynoProp. Create a struct in the saveObj method to save the data that the loadObj method uses to reconstruct the object.

Here is how the saveobj method works:

- Obtain the meta.DynamicProperty object for the dynamic property.
- Store the name and value of the dynamic property in struct s.

• Store the nondefault dynamic property attributes values for SetAccess and GetAccess in the struct. The loadobj function restores these values.

```
methods
  function s = saveobj(obj)
    metaDynoProp = findprop(obj, 'DynoProp');
    s.dynamicprops(1).name = metaDynoProp.Name;
    s.dynamicprops(1).value = obj.DynoProp;
    s.dynamicprops(1).setAccess = metaDynoProp.SetAccess;
    s.dynamicprops(1).getAccess = metaDynoProp.GetAccess;
    ...
end
end
```

Your loadobj method can add the dynamic property and set the attribute values:

- Create an instance of the class.
- Use addprop to add a new dynamic property to the object.
- Restore the attributes of the dynamic property.

```
methods (Static)
  function obj = loadobj(s)
    if isstruct(s)
        obj = ClassConstructor;
        ...
        metaDynoProp = addprop(obj,s.dynamicprops(1).name);
        obj.(s.dynamicprops(1).name) = s.dynamicprops(1).value;
        metaDynoProp.SetAccess = s.dynamicprops(1).setAccess;
        metaDynoProp.GetAccess = s.dynamicprops(1).getAccess;
    end
  end
end
```

Enumerations

- "Defining Named Values" on page 13-2
- "Working with Enumerations" on page 13-3
- "Enumerations Derived from Built-In Types" on page 13-14
- "Mutable (Handle) vs. Immutable (Value) Enumeration Members" on page 13-20
- "Enumerations That Encapsulate Data" on page 13-27
- "Saving and Loading Enumerations" on page 13-31

Defining Named Values

Kinds of Predefined Names

MATLAB supports two kinds of predefined names:

- Constant properties
- Enumerations

Constant Properties

Use constant properties when you want a collection of related constant values whose values can belong to different types (numeric values, character strings, and so on). Define properties with constant values by setting the property Constant attribute. Reference constant properties by name whenever you need access to that particular value.

See "Properties with Constant Values" on page 14-2 for more information.

Enumerations

Use enumerations when you want to create a fixed set of names representing a single type of value. You can derive enumeration classes from other classes to inherit the operations of the superclass. For example, if you define an enumeration class that subclasses a MATLAB numeric class like double or int32, the enumeration class inherits all of the mathematical and relational operations that MATLAB defines for those classes.

Using enumerations instead of character strings to represent a value, such as colors ('red'), can result in more readable code because:

- You can compare enumeration members with == instead of using strcmp
- Enumerations maintain type information, strings do not. For example, passing a string 'red' to functions means that every function must interpret what 'red' means. If you define red as an enumeration, the actual value of 'red' can change (from [1 0 0] to [.93 .14 .14], for example) without updating every function that accepts colors, as you would if you defined the color as a string 'red'.

Define enumerations by creating an enumeration block in the class definition.

See "Working with Enumerations" on page 13-3 for more information.

Working with Enumerations

In this section...

"Basic Knowledge" on page 13-3

"Using Enumeration Classes" on page 13-4

"Defining Methods in Enumeration Classes" on page 13-8

"Defining Properties in Enumeration Classes" on page 13-9

"Array Expansion Operations" on page 13-10

"Constructor Calling Sequence" on page 13-10

"Restrictions Applied to Enumeration Classes" on page 13-12

"Techniques for Defining Enumerations" on page 13-12

Basic Knowledge

The material presented in this section builds on an understanding of the information provided in the following sections.

Defining Classes and Class Members

- "Class Syntax Fundamentals"
- "Creating Subclasses Syntax and Techniques" on page 11-7
- "Mutable and Immutable Properties" on page 7-13
- · enumeration function displays enumeration names

Terminology and Concepts

This documentation uses terminology as described in the following list:

- Enumeration or Enumeration class A class that contains an enumeration block defining enumeration members.
- Enumeration member A named instance of an enumeration class.
- Enumeration member constructor arguments Values in parentheses next to the enumeration member name in the enumeration block. When you create an instance of an enumeration member, MATLAB passes the value or values in parenthesis to the class constructor.

 Underlying value — For enumerations derived from built-in classes, the value associated with an instance of an enumeration class (that is, an enumeration member).

Using Enumeration Classes

Create an enumeration class by adding an enumeration block to a class definition. For example, the WeekDays class enumerates a set of days of the week.

```
classdef WeekDays
   enumeration
        Monday, Tuesday, Wednesday, Thursday, Friday
   end
end
```

Constructing an Enumeration Member

Refer to an enumeration member using the class name and the member name:

```
ClassName . MemberName
```

For example, assign the enumeration member WeekDays. Tuesday to the variable today:

```
today = WeekDays.Tuesday;
```

today is a variable of class WeekDays:

whos

Name	Size	Bytes	Class	Attributes
today	1x1	56	WeekDays	
today				
today =				
Tuesday				

Default Methods

Enumeration classes have four methods by default:

```
methods(today)
```

Methods for class WeekDays:

WeekDays char eq ne

- Default constructor (WeekDays in this case)
- char converts enumeration members to character strings
- eq enables use of == in expressions
- ne enables use of ~= in expressions

Equality and inequality methods enable you to use enumeration members in if and switch statements and other functions that test for equality.

Because you can define enumeration members with descriptive names, conversion to **char** is useful. For example:

```
today = WeekDays.Friday;
['Today is ',char(today)]
ans =
```

Today is Friday

Testing for Membership in a Set

Suppose you want to determine if today is a meeting day for your team. Create a set of enumeration members corresponding to the days on which the team has meetings.

```
today = WeekDays.Tuesday;
teamMeetings = [WeekDays.Wednesday WeekDays.Friday];
```

Use equality to determine if today is part of the teamMeetings set:

```
any(today == teamMeetings)
ans =
    0
```

Using Enumerations in a Switch Statement

Enumerations work in switch statements:

```
function c = Reminder(day)
% Add error checking here
switch(day)
```

```
case WeekDays.Monday
         c = 'Department meeting at 10:00';
      case WeekDays.Tuesday
         c = 'Meeting Free Day!';
      case {WeekDays.Wednesday WeekDays.Friday}
         c = 'Team meeting at 2:00';
      case WeekDays. Thursday
         c = 'Volley ball night';
   end
end
Pass a member of the WeekDays enumeration class to the Reminder function:
today = WeekDays.Wednesday;
Reminder (today)
ans =
Team meeting at 2:00
See "Objects In Switch Statements" on page 4-38 for more information.
```

Getting Information About Enumerations

Obtain information about enumeration classes using the enumeration function. For example:

```
enumeration WeekDays
```

Enumeration members for class 'WeekDays':

Monday Tuesday Wednesday Thursday Friday

See also "Metaclass EnumeratedValues Property" on page 15-7

Testing for an Enumeration

Use the isenum function to determine if a variable is an enumeration. For example:

```
today = WeekDays.Wednesday;
isenum(today)
```

```
ans =
     1
isenum returns true for empty enumeration objects:
noday = WeekDays.empty;
isenum(noday)
ans =
```

You can also use the meta.class to determine if a variable's class is an enumeration class:

```
today = WeekDays.Wednesday;
mc = metaclass(today);
mc.Enumeration
ans =
```

1

Converting to Superclass Value

If an enumeration class specifies a superclass, in many cases you can convert an enumeration object to the superclass by passing the object to the superclass constructor. However, the superclass must be able to accept its own class as input and return an instance of the superclass. MATLAB built-in numeric classes, like double, single, and so on allow this conversion.

For example, the Bearing class derives from the uint32 built-in class:

```
classdef Bearing < uint32
  enumeration
    North (0)
    East (90)
    South (180)
    West (270)
  end
end</pre>
```

Assign the Bearing. East member to the variable a:

```
a = Bearing.East;
```

Pass a to the superclass constructor and return an object of the superclass, b:

```
b = uint32(a);
whos
Name Size Bytes Class Attributes

a 1x1 60 Bearing
b 1x1 4 uint32
```

The uint32 constructor accepts an instance of the subclass Bearing and returns and object of class uint32.

Defining Methods in Enumeration Classes

Define methods in an enumeration class like any MATLAB class. For example, here is the WeekDays class with a method called isMeetingDay added:

```
classdef WeekDays
  enumeration
    Monday, Tuesday, Wednesday, Thursday, Friday
  end
  methods
    function tf = isMeetingDay(obj)
        tf = ~(WeekDays.Tuesday == obj);
    end
  end
end

Call isMeetingDay with an instance of the WeekDays class:
today = WeekDays.Tuesday;
today.isMeetingDay
ans =
    0
```

You can pass the enumeration member to the method directly:

```
isMeetingDay(WeekDays.Wednesday)
ans =
```

1

Defining Properties in Enumeration Classes

Add properties to an enumeration class when you must store data related to the enumeration members. Set the property values in the class constructor. For example, the <code>SyntaxColors</code> class defines three properties whose values the constructor assigns to the values of the input arguments when you reference a class member.

```
classdef SyntaxColors
   properties
      R
      G
      В
   end
   methods
      function c = SyntaxColors(r, g, b)
         c.R = r; c.G = g; c.B = b;
      end
   end
   enumeration
      Error
              (1, 0, 0)
      Comment (0, 1, 0)
      Keyword (0, 0, 1)
      String (1, 0, 1)
   end
end
```

When you refer to an enumeration member, the constructor initializes the property values:

```
e = SyntaxColors.Error;
e.R
ans =
1
```

Because SyntaxColors is a value class (it does not derive from handle), only the class constructor can set property values:

```
e.R = 0
```

Setting the 'R' property of the 'SyntaxColors' class is not allowed.

See "Mutable (Handle) vs. Immutable (Value) Enumeration Members" on page 13-20 for more information on enumeration classes that define properties.

Array Expansion Operations

MATLAB enables assignment to any element of an array, even if the array does not exist. For example, you can create an array of WeekDays objects:

```
classdef WeekDays
   enumeration
       Monday, Tuesday, Wednesday, Thursday, Friday
   end
end
clear
ary(5) = WeekDays.Tuesday;
```

MATLAB must initialize the values of array elements ary(1:4). The default value of an enumeration class is the first enumeration member defined by the class in the enumeration block. The result of the assignment to the fifth element of the array ary is, therefore:

```
ary
ary =
Monday Monday Monday Tuesday
```

Constructor Calling Sequence

Each statement in an enumeration block is the name of an enumeration member, optionally followed by an argument list. If the enumeration class defines a constructor, MATLAB calls the constructor to create the enumerated instances.

MATLAB provides a default constructor for all enumeration classes that do not explicitly define a constructor. The default constructor creates an instance of the enumeration class:

- · Using no input arguments, if the enumeration member defines no input arguments
- Using the input arguments defined in the enumeration class for that member

For example, the input arguments for the Boolean class are 0 for Boolean. No and 1 for Boolean. Yes.

```
classdef Boolean < logical
  enumeration
    No (0)
    Yes (1)
  end
end</pre>
```

The values of 0 and 1 are of class logical because the default constructor passes the argument to the first superclass. That is,

```
n = Boolean.No;
```

results in a call to logical that is equivalent to the following statement in a constructor:

```
function obj = Boolean(val)
  obj@logical(val)
end
```

MATLAB passes the member argument only to the first superclass. For example, suppose Boolean derived from another class:

```
classdef Boolean < logical & MyBool
    enumeration
     No (0)
     Yes (1)
    end
end</pre>
```

The MyBool class can add some specialized behavior:

```
classdef MyBool
   methods
      function boolValues = testBools(obj)
      ...
   end
  end
end
```

Now, the default Boolean constructor behaves as if defined like this function:

```
function obj = Boolean(val)
  obj@logical(val) % Argument passed to first superclass constructor
```

obj@MyBool end % No arguments passed to subsequent constructors

Restrictions Applied to Enumeration Classes

Enumeration classes, which consist of a fixed set of possible values, restrict certain aspects of class use and definition:

- Enumeration classes are implicitly Sealed. You cannot define a subclass of an enumeration class because doing so would expand the set.
- You cannot call the constructor of an enumeration class directly. Only MATLAB can call enumeration class constructors to create the fixed set of members.

Note: It is possible to provide a conversion function in any class where the function is the name of an enumerated class and its purpose is to convert to the enumeration. It is possible to convert to an instance of an enumerated class (one of the defined set of members), but it is not possible to make a new instance of the class. See "Default Converter" on page 13-18 for related information.

- The properties of value-based enumeration classes are immutable. Only the constructor can assign property values. MATLAB implicitly defines the SetAccess attributes of all properties defined by value-based enumeration classes as immutable. You cannot set the SetAccess attribute to any other value.
- All properties inherited by a value-based enumeration class that are not defined as Constant must have immutable SetAccess.
- The properties of handle-based enumeration classes are mutable. You can set property values on instances of the enumeration class. See "Mutable (Handle) vs. Immutable (Value) Enumeration Members" on page 13-20 for more information.
- An enumeration member cannot have the same name as a property, method, or event defined by the same class.
- Enumerations do not support colon (a:b) operations. For example,
 FlowRate.Low:FlowRate.High causes an error even if the FlowRate class derives from a numeric superclass.

Techniques for Defining Enumerations

Enumerations enable you to define names that represent entities useful to your application, without using numeric values or character strings. All enumerations support

equality and inequality operations. Therefore, switch, if, and a number of comparison functions like isequal and ismember work with enumeration members.

You can define enumeration classes in ways that are most useful to your application, as described in the following sections.

Simple Enumerated Names

Simple enumeration classes have no superclasses and no properties. These classes define a set of related names that have no underlying values associated with them. Use this kind of enumeration when you want descriptive names, but your application does not require specific information associated with the name.

See the WeekDays class in the "Using Enumeration Classes" on page 13-4 and the "Defining Methods in Enumeration Classes" on page 13-8 sections.

Enumerations with Built-In Class Behaviors

Enumeration classes that subclass MATLAB built-in classes inherit most of the behaviors of those classes. For example, an enumeration class derived from the double class inherits the mathematical, relational, and set operations that work with variables of the class.

Enumerations do not support the colon (:) operator, even if the superclass does. See "Restrictions Applied to Enumeration Classes" on page 13-12 for more information.

See "Enumerations Derived from Built-In Types" on page 13-14.

Enumerations with Properties for Member Data

Enumeration classes that do not subclass MATLAB built-in numeric and logical classes can define properties. These classes can define constructors that set each member's unique property values.

The constructor can save input arguments in property values. For example, a Color class can specify a Red enumeration member color with three (Red, Green, Blue) values:

```
enumeration
Red (1,0,0)
end
```

See "Enumerations That Encapsulate Data" on page 13-27

Enumerations Derived from Built-In Types

```
In this section...

"Basic Knowledge" on page 13-14

"Why Derive Enumerations from Built-In Types" on page 13-14

"Aliasing Enumeration Names" on page 13-16

"Superclass Constructor Returns Underlying Value" on page 13-17

"Default Converter" on page 13-18
```

Basic Knowledge

The material presented in this section builds on an understanding of the information provided in the following sections.

- "Fundamental MATLAB Classes" for information on MATLAB built-in classes.
- enumeration function displays enumeration names

Why Derive Enumerations from Built-In Types

Note: Enumeration classes derived from built-in numeric and logical classes cannot define properties.

If an enumeration class subclasses a built-in numeric class, the subclass inherits ordering and arithmetic operations, which you can apply to the enumerated names.

For example, the Results class subclasses the int32 built-in class and associates an integer value with each of the four enumeration members — First, Second, Third, and NoPoints.

```
classdef Results < int32
  enumeration
    First (100)
    Second (50)
    Third (10)
    NoPoints (0)
  end
end</pre>
```

Because the enumeration member inherits the methods of the int32 class (not the colon operator), you can use these enumerations like numeric values (summed, sorted, averaged, and so on).

```
isa(Results.Second, 'int32')
ans =
For example, use enumeration names instead of numbers to rank two teams:
Team1 = [Results.First, Results.NoPoints, Results.Third, Results.Second];
Team2 = [Results.Second, Results.Third, Results.First, Results.First];
Perform int32 operations on these Results enumerations:
sum(Team1)
ans =
   160
mean(Team1)
ans =
    40
sort(Team2, 'descend')
ans =
    First
               First
                           Second
                                       Third
Team1 > Team2
ans =
 sum(Team1) < sum(Team2)
ans =
     1
```

Creating Enumeration Instances

When you first refer to an enumeration class that derives from a built-in class such as, int32, MATLAB passes the input arguments associated with the enumeration members

to the superclass constructor. For example, referencing the Second Results member, defined as:

```
Second (50)

means that MATLAB calls:

int32(50)

to initialize the int32 aspect of this Results object.
```

Aliasing Enumeration Names

Enumeration classes that derive from MATLAB built-in numeric and logical classes can define more than one name for an underlying value. The first name in the enumeration block with a given underlying value is the actual name for that underlying value and subsequent names are aliases.

Specify aliased names with the same superclass constructor argument as the actual name:

```
classdef Boolean < logical
   enumeration
    No (0)
    Yes (1)
    off (0)
    on (1)
   end
end</pre>
```

For example, the actual name of an instance of the Boolean.off enumeration member is No:

```
a = Boolean.No
a =
    No
b = Boolean.off
b =
```

No

Superclass Constructor Returns Underlying Value

The actual underlying value associated with an enumeration member is the value returned by the built-in superclass. For example, consider the Boolean class defined with constructor arguments that are of class double:

```
classdef Boolean < logical
  enumeration
    No (0)
    Yes (100)
  end
end</pre>
```

This class derives from the built-in logical class. Therefore, underlying values for an enumeration member depend only on what value logical returns when passed that value:

```
a = Boolean.Yes
a =
    Yes
logical(a)
ans =
    1
```

Subclassing a Numeric Built-In Class

The FlowRate enumeration class defines three members, Low, Medium, and High.

```
classdef FlowRate < int32
  enumeration
    Low (10)
    Medium (50)
    High (100)
  end
end</pre>
```

Referencing an instance of an enumeration member:

```
setFlow = FlowRate.Medium;
```

returns an instance that is the result of MATLAB calling the default constructor with the argument value of 50. MATLAB passes this argument to the first superclass constructor (int32(50) in this case), which results in an underlying value of 50 as a 32-bit integer for the FlowRate.Medium member.

Because FlowRate subclasses a MATLAB built-in numeric class (int32), it cannot define properties. However FlowRate inherits int32 methods including a converter method, which programs can use to obtain the underlying value:

```
setFlow = FlowRate.Medium;
int32(setFlow)
ans =
```

Default Converter

If an enumeration is a subclass of a built-in numeric class, it is possible to convert from built-in numeric data to the enumeration using the name of the enumeration class. For example:

```
a = Boolean(1)
a =
Yes
```

An enumerated class also accepts enumeration members of its own class as input arguments:

```
Boolean(a)
ans =
Yes
```

Nonscalar inputs to the converter method return an object of the same size:

```
Boolean([0,1])
ans =
```

No Yes

Create an empty enumeration array using the empty static method:

Boolean.empty

ans =

0x0 empty Boolean enumeration.

Mutable (Handle) vs. Immutable (Value) Enumeration Members

In this section...

"Basic Knowledge" on page 13-20

"Selecting Handle- or Value-Based Enumerations" on page 13-20

"Value-Based Enumeration Classes" on page 13-20

"Handle-Based Enumeration Classes" on page 13-22

"Using Enumerations to Represent a State" on page 13-25

Basic Knowledge

The material presented in this section builds on an understanding of the information provided in the following sections.

- "Comparing Handle and Value Classes" on page 6-2
- enumeration function displays enumeration names

See for general information about these two kinds of classes.

Selecting Handle- or Value-Based Enumerations

Use a handle enumeration when you want to enumerate a set of objects whose state might change over time. Use a value enumeration to enumerate a set of abstract (and immutable) values.

Value-Based Enumeration Classes

A value-based enumeration class has a fixed set of specific values. You cannot modify these values by changing the values of properties because doing so expands or changes the fixed set of values for this enumeration class.

Inherited Property SetAccess Must Be Immutable

Value-based enumeration class implicitly define the SetAccess attributes of all properties as immutable. You cannot set the SetAccess attribute to any other value.

However, all superclass properties must explicitly define property SetAccess as immutable. See "Property Attributes" on page 7-7 for more information on property attributes.

Enumeration Members Remain Constant

When you create an instance of a value-based enumeration class, this instance is unique until the class is cleared and reloaded. For example, given the following class:

```
classdef WeekDays
    enumeration
        Monday, Tuesday, Wednesday, Thursday, Friday
    end
end

MATLAB considers a and b as equivalent:

a = WeekDays.Monday;
b = WeekDays.Monday;
isequal(a,b)
ans =

1

a == b
```

Enumeration Member Properties Remain Constant

ans =

1

Value-based enumeration classes that define properties are immutable. For example, the Colors enumeration class associates RGB values with color names.

```
classdef Colors
  properties
    R = 0;
    G = 0;
    B = 0;
end
    methods
  function c = Colors(r, g, b)
        c.R = r; c.G = g; c.B = b;
end
```

```
end
        enumeration
        Red (1, 0, 0)
        Green (0, 1, 0)
        Blue (0, 0, 1)
        end
end

The constructor assigns the input arguments to R, G, and B properties:
red = Colors.Red;

You cannot change a property value:
red.G = 1;
Setting the 'G' property of the 'Colors' class is not allowed.
```

Handle-Based Enumeration Classes

Handle-based enumeration classes that define properties are mutable. Derive enumeration classes from the handle class when you must be able to change property values on instances of that class.

Note: You cannot derive an enumeration class from matlab.mixin.Copyable because the number of instances you can create are limited to the ones defined inside the enumeration block.

An Enumeration Member Remains Constant

Given a handle-based enumeration class with properties, changing the property value of an instance causes all references to that instance to reflect the changed value.

For example, the HandleColors enumeration class associates RGB values with color names, the same as the Colors class in the previous example. However, HandleColors derives from handle:

```
classdef HandleColors < handle
% Enumeration class derived from handle
   properties
    R = 0;</pre>
```

```
G = 0;
      B = 0;
   end
   methods
      function c = HandleColors(r, g, b)
         c.R = r; c.G = g; c.B = b;
      end
   end
   enumeration
      Red (1, 0, 0)
... % Other colors omitted
   end
end
Create an instance of HandleColors. Red and return the value of the R property:
a = HandleColors.Red;
a.R
ans =
    1
MATLAB constructs the HandleColors.Red enumeration member, which sets the R
property to 1, the G property to 0, and the B property to 0.
Change the value of the R property to .8:
a.R = .8;
After setting the value of the R property to .8, create another instance, b, of
HandleColors.Red:
b = HandleColors.Red;
```

The value of the R property of the newly created instance is also 0.8000. The MATLAB session has only one value for any enumeration member at any given time.

b.R

ans =

0.8000

Clearing the workspace variables does not change the current definition of the enumeration member HandleColors.Red:

```
clear
a = HandleColors.Red;
a.R
ans =
    0.8000
```

Clear the class to reload the definition of the HandleColors class (see clear classes):

```
clear classes
a = HandleColors.Red;
a.R
ans =
```

If you do not want to allow reassignment of a given property value, set that property's **SetAccess** attribute to **immutable**.

See "Property Attributes" on page 7-7 for more information about property attributes.

Equality of Handle-Based Enumerations

Suppose you assign two variables to a particular enumeration member:

```
a = HandleColors.Red;
b = HandleColors.Red;
You can compare a and b using isequal:
>> isequal(a,b)
ans =
```

The property values of a and b are the same, so isequal returns true. However, unlike nonenumeration handle classes, a and b are the same handle because there is only one enumeration member. Determine handle equality using == (the handle eq method).

```
>> a == b
ans =
```

See the handle eq method for information on how isequal and == differ when used with handles.

Using Enumerations to Represent a State

The MachineState class defines two enumeration members to represent the state of a machine, either running or not running.

```
classdef MachineState
enumeration
Running
NotRunning
end
end
```

The Machine class represents a machine with start and stop operations. The MachineState enumerations are easy to work with because of their eq and char methods, and they result in code that is easy to read.

```
classdef Machine < handle
   properties (SetAccess = Private)
      State = MachineState.NotRunning;
   end
   methods
      function start(machine)
         if machine.State == MachineState.NotRunning
            machine.State = MachineState.Running;
         end
         disp (machine.State.char)
      end
      function stop(machine)
         if machine.State == MachineState.Running
            machine.State = MachineState.NotRunning;
         disp (machine.State.char)
      end
```

end end

Create a Machine object and call start and stop methods:

% Create a Machine object
>> m = Machine;
% Start the machine
>> m.start
Running
% Stop the machine
>> m.stop
NotRunning

Enumerations That Encapsulate Data

In this section... "Basic Knowledge" on page 13-27 "Store Data in Properties" on page 13-27

Basic Knowledge

The material presented in this section builds on an understanding of the information provided in the following sections.

- "Fundamental MATLAB Classes" for information on MATLAB built-in classes.
- enumeration function displays enumeration names

Store Data in Properties

Note: Enumeration classes that subclass built-in numeric or logical classes cannot define or inherit properties. See "Enumerations Derived from Built-In Types" on page 13-14 for more information on this kind of enumeration class.

Define properties in an enumeration class if you want to associate specific data with enumeration members, but do not need to inherit arithmetic, ordering, or other operations that MATLAB defines for specific built-in classes.

Representing Colors

Suppose you want to use a particular set of colors in all your graphs. You can define an enumeration class to represent the RGB values of the colors in your color set. The Colors class defines names for the colors, each of which uses the RGB values as arguments to the class constructor:

```
classdef Colors
  properties
    R = 0;
    G = 0;
    B = 0;
end
```

```
methods
      function c = Colors(r, g, b)
         c.R = r; c.G = g; c.B = b;
      end
   end
   enumeration
      Blueish
                (18/255, 104/255, 179/255)
      Reddish
                (237/255,36/255,38/255)
      Greenish (155/255,190/255,61/255)
      Purplish
                (123/255,45/255,116/255)
      Yellowish (1,199/255,0)
      LightBlue (77/255,190/255,238/255)
   end
end
Suppose you want to specify the new shade of red named Reddish:
a = Colors.Reddish;
a.R
ans =
    0.9294
a.G
ans =
    0.1412
a.B
ans =
    0.1490
```

Use these values by accessing the enumeration member's properties. For example, the myPlot function accepts a Colors enumeration member as an input argument and accesses the RGB values defining the color from the property values.

```
function h = myPlot(x,y,LineColor)
% Simple plotting function
h = line('XData',x,'YData',y);
r = LineColor.R;
g = LineColor.G;
```

```
b = LineColor.B;
set(h,'Color',[r g b])
end
```

Create a plot using a reddish color line:

```
r = Colors.Reddish;
h = myPlot(1:10,1:10,r);
```

The Colors class encapsulates the definitions of a standard set of colors. These definitions can change in the Colors class without affecting functions that use the Colors enumerations.

Enumerations Defining Categories

Suppose the Cars class defines categories used to inventory automobiles. The Cars class derives from the CarPainter class, which derives from handle. The abstract CarPainter class defines a paint method, which modifies the Color property if a car is painted another color.

The Cars class uses Colors enumerations to specify a finite set of available colors. The exact definition of any given color can change independently of the Cars class.

```
classdef Cars < CarPainter
   enumeration
      Hybrid (2,'Manual',55,Colors.Reddish)
      Compact(4, 'Manual',32,Colors.Greenish)
      MiniVan(6, 'Automatic', 24, Colors. Blueish)
             (8, 'Automatic', 12, Colors. Yellowish)
      SUV
   end
   properties (SetAccess = private)
      Cvlinders
      Transmission
      MPG
      Color
   end
   methods
      function obj = Cars(cyl,trans,mpg,colr)
         obj.Cylinders = cyl;
         obj.Transmission = trans;
         obj.MPG = mpg;
         obj.Color = colr;
      end
      function paint(obj,colorobj)
```

```
if isa(colorobj, 'Colors')
             obj.Color = colorobj;
         else
             [~,cls] = enumeration('Colors');
             disp('Not an available color')
             disp(cls)
         end
      end
   end
end
The CarPainter class requires its subclasses to define a method called paint:
classdef CarPainter < handle
   methods (Abstract)
      paint(carobj,colorobj)
   end
end
Suppose you define an instance of the Cars class:
c1 = Cars.Compact;
The color of this car is Greenish, as defined by the Colors. Greenish enumeration:
c1.Color
ans =
    Greenish
Use the paint method to change the car color:
c1.paint(Colors.Reddish)
c1.Color
ans =
    Reddish
```

Saving and Loading Enumerations

In this section...

"Basic Knowledge" on page 13-31

"Built-In and Value-Based Enumeration Classes" on page 13-31

"Simple and Handle-Based Enumeration Classes" on page 13-31

"Causes: Loading as Struct Instead of Object" on page 13-32

Basic Knowledge

See the save and load functions and "Save and Load Process" on page 12-2 for general information on saving and loading objects.

See the enumeration function to list enumeration names.

Built-In and Value-Based Enumeration Classes

When you save enumerations that derive from built-in classes or that are value-based classes with properties, MATLAB saves the names of the enumeration members and the definition of each member.

When loading these types of enumerations, MATLAB preserves names over underlying values. If the saved named value is different from the current class definition, MATLAB uses the value defined in the current class, and then issues a warning.

Simple and Handle-Based Enumeration Classes

When you save simple enumerations (those having no properties, superclasses, or values associated with the member names) or those enumerations derived from the handle class, MATLAB saves the names and any underlying values.

However, when loading these types of enumerations, MATLAB does not check the values associated with the names in the current class definition. This behavior results from the fact that simple enumerations have no underlying values and handle-based enumerations can legally have values that are different than those defined by the class.

Causes: Loading as Struct Instead of Object

The addition of a new named value or a new property made to a class subsequent to saving an enumeration does not trigger a warning during load.

If there are changes to the enumeration class definition that do not prevent MATLAB from loading the object (that is, all of the named values in the MAT-File are present in the modified class definition), then MATLAB issues a warning that the class has changed and loads the enumeration.

In the following cases, MATLAB issues a warning and loads as much of the saved data as possible as a **struct**:

- MATLAB cannot find the class definition
- The class is no longer an enumeration class
- MATLAB cannot initialize the class
- There is one or more enumeration member in the loaded enumeration that is not in the class definition
- For value-based enumerations with properties, a property exists in the file, but is not present in the class definition

Struct Fields

The returned struct has the following fields:

- ValueNames A cell array of strings, one per unique value in the enumeration array.
- Values An array of the same dimension as ValueNames containing the corresponding values of the enumeration members named in ValueNames. Depending on the kind of enumeration class, Values can be one of the following:
 - If the enumeration class derives from a built-in class, the array is of the built-in class and the values in the array are the underlying values of each enumeration member.
 - Otherwise, a struct array representing the property name property values
 pairs of each enumeration member. For simple and handle-based enumerations,
 the struct array has no fields.
- ValueIndices a uint32 array of the same size as the original enumeration.
 Each element is an index into the ValueNames and Values arrays. The content of ValueIndices represents the value of each object in the original enumeration array.

Constant Properties

Properties with Constant Values

```
In this section...

"Defining Named Constants" on page 14-2

"Constant Property Assigned a Handle Object" on page 14-4

"Constant Property Assigned Any Class Instance" on page 14-4
```

Defining Named Constants

Use constant properties to define constant values that you can access by name. Create a class with constant properties by declaring the Constant attribute in the property blocks. Setting the Constant attribute means that, once initialized to the value specified in the property block, the value cannot be changed.

Assigning Values to Constant Properties

Assign any value to a Constant property, including a MATLAB expression. For example:

```
classdef NamedConst
  properties (Constant)
    R = pi/180;
    D = 1/NamedConst.R;
    AccCode = '0145968740001110202NPQ';
    RN = rand(5);
  end
end
```

MATLAB evaluates the expressions when loading the class (when you first reference a constant property from that class). Therefore, the values MATLAB assigns to RN are the result of a single call to the rand function and do not change with subsequent references to NamedConst.RN. Calling clear classes causes MATLAB to reload the class and reinitialize the constant properties.

Referencing Constant Properties

Refer to the constant using the class name and the property name:

```
ClassName.PropName
```

For example, to use the NamedConst class defined in the previous section, reference the constant for the degree to radian conversion, R:

```
radi = 45*NamedConst.R
radi =
    0.7854
```

Constants In Packages

To create a library for constant values that you can access by name, first create a package folder, and then define the various classes to organize the constants you want to provide. For example, to implement a set of constants that are useful for making astronomical calculations, define a AstroConstants class in a package called constants:

+constants/AstroConstants/AstroConstants.m

The class defines a set of Constant properties with values assigned:

```
classdef AstroConstants
  properties (Constant)
  C = 2.99792458e8;  % m/s
  G = 6.67259;  % m/kgs
  Me = 5.976e24;  % Earth mass (kg)
  Re = 6.378e6;  % Earth radius (m)
  end
end
```

To use this set of constants, reference them with a fully qualified class name. For example, the following function uses some of the constants defined in AstroContants:

```
function E = energyToOrbit(m,r) 
 E = constants.AstroConstants.G * constants.AstroConstants.Me * m * ... 
 (1/constants.AstroConstants.Re-0.5*r); end
```

Importing the package into the function eliminates the need to repeat the package name (see import):

```
function E = energyToOrbit(m,r)
import constants.*;
E = AstroConstants.G * AstroConstants.Me * m * ...
(1/AstroConstants.Re - 0.5 * r);
```

end

Constant Property Assigned a Handle Object

If a class defines a constant property with a value that is a handle object, you can assign values to the handle object's properties. However, you must create a local variable to access the handle object.

For example, the ConstMapClass class defines a constant property. The value of the constant property is a handle object (a containers.Map object).

```
classdef ConstMapClass < handle
  properties (Constant)
      ConstMapProp = containers.Map;
  end
end</pre>
```

To assign the current date to the Date key, first return the handle from the constant property, and then make the assignment using the local variable on the left side of the assignment statement:

```
localMap = ConstMapClass.ConstMapProp
localMap('Date') = datestr(clock);
```

You cannot use a reference to a constant property on the left side of an assignment statement. For example, MATLAB interprets the following statement as the creation of a struct named ConstantMapClass with a field ConstMapProp:

```
ConstMapClass.ConstMapProp('Date') = datestr(clock);
```

Constant Property Assigned Any Class Instance

You can assign an instance of the defining class to a constant property. MATLAB creates the instance assigned to the constant property when loading the class. You can use this technique only when the defining class is a handle class.

The MyProject is an example of such a class:

```
classdef MyProject < handle
  properties (Constant)
    ProjectInfo = MyProject;
end</pre>
```

```
properties
      Date
      Department
      ProjectNumber
   end
   methods (Access = private)
      function obj = MyProject
         obj.Date = datestr(clock);
         obj.Department = 'Engineering';
         obj.ProjectNumber = 'P29.367';
      end
   end
end
Reference property data via the Constant property:
MyProject.ProjectInfo.Date
ans =
18-Apr-2002 09:56:59
Because MyProject is a handle class, you can get the handle to the instance that is
assigned to the constant property:
p = MyProject.ProjectInfo;
Access the data in the MyProject class using this handle:
p.Department
ans =
Engineering
Modify the nonconstant properties of the MyProject class using this handle:
p.Department = 'Quality Assurance';
p is a handle to the instance of MyProject that is assigned to the ProjectInfo
constant property:
MyProject.ProjectInfo.Department
ans =
```

Quality Assurance

Clearing the class results in the assignment of a new instance of MyProject to the ProjectInfo property.

clear MyProject MyProject.ProjectInfo.Department

ans =

Engineering

You can assign an instance of the defining class as the default value of a property only when the property is declared as Constant

Information from Class Metadata

- "Class Metadata" on page 15-2
- "Inspecting Class and Object Metadata" on page 15-5
- "Finding Objects with Specific Values" on page 15-8
- "Getting Information About Properties" on page 15-12
- "Find Default Values in Property Metadata" on page 15-18

Class Metadata

In this section...

"What Is Class Metadata?" on page 15-2

"The meta Package" on page 15-2

"Metaclass Objects" on page 15-3

What Is Class Metadata?

Class metadata is information about class definitions that is available from instances of metaclasses. Use metaclass objects to obtain information about class definitions without the need to create instances of the class itself.

Each block in a class definition has an associated metaclass that defines the attributes for that block. Each attribute corresponds to a property in the metaclass. An instance of a metaclass has values assigned to each property that correspond to the values of the attributes of the associated class block.

Metadata enables the programmatic inspection of classes. Tools such as property inspectors, debuggers, and so on, use these techniques.

The meta Package

The meta package contains metaclasses that MATLAB uses for the definition of classes and class components. The class name indicates the component described by the metaclass:

```
meta.package
meta.class
meta.property
meta.DynamicProperty
meta.EnumeratedValue
meta.method
meta.event
```

Each metaclass has properties, methods, and events that contain information about the class or class component. See meta.package, meta.class, meta.property,

meta.DynamicProperty, meta.EnumeratedValue, meta.method and meta.event for more information on these metaclasses.

Metaclass Objects

Creating Metaclass Objects

You cannot instantiate metaclasses directly by calling the respective class constructor. Create metaclass objects from class instances or from the class name.

- ?ClassName Returns a meta.class object for the named class. Use meta.class.fromName with class names stored as characters in variables.
- meta.class.fromName('ClassName') returns the meta.class object for the named class (meta.class.fromName is a meta.class method).
- metaclass (obj) Returns a metaclass object for the class instance (metaclass)

```
% create metaclass object from class name using the ? operator
mobj = ?classname;
% create metaclass object from class name using the fromName method
mobj = meta.class.fromName('classname');
% create metaclass object from class instance
obj = myClass;
mobj = metaclass(obj);
```

The metaclass function returns the meta.class object (that is, an object of the meta.class class). You can obtain other metaclass objects (meta.property, meta.method, and so on) from the meta.class object.

Note: Metaclass is a term used here to refer to all of the classes in the meta package. meta.class is a class in the meta package whose instances contain information about MATLAB classes. Metadata is information about classes contained in metaclasses.

Metaclass Object Lifecycle

When you change a class definition, MATLAB reloads the class definition. If instances of the class exist, MATLAB updates those objects according to the new definition.

However, MATLAB does not update existing metaclass objects to the new class definition. If you change a class definition while metaclass objects of that class exist,

MATLAB deletes the metaclass objects and their handles become invalid. You must create a new metaclass object after updating the class.

See "Automatic Updates for Modified Classes" on page 4-50 for information on how to modify and reload classes.

Using Metaclass Objects

Here are ways to access the information in metaclass objects:

- Obtain a meta.class object from a class definition (using ?) or from a class instance (using metaclass).
- Use the meta.class properties, methods, and events to obtain information about the class or class instance from which you obtained the meta.class object. For example, get other metaclass objects, such as the meta.properties objects defined for each of the class properties.

See the following sections for examples that show how to use metadata:

- · "Inspecting Class and Object Metadata" on page 15-5
- "Finding Objects with Specific Values" on page 15-8
- "Getting Information About Properties" on page 15-12
- "Find Default Values in Property Metadata" on page 15-18

Inspecting Class and Object Metadata

```
In this section...

"Inspecting a Class" on page 15-5

"Metaclass EnumeratedValues Property" on page 15-7
```

Inspecting a Class

The EmployeeData class is a handle class with two properties, one of which has private Access and defines a set access method.

```
classdef EmployeeData < handle
   properties
      EmployeeName
   properties (Access = private)
      EmployeeNumber
   end
   methods
      function obj = EmployeeData(name,ss)
         if nargin > 0
            obj.EmployeeName = name;
            obj.EmployeeNumber = ss;
         end
      end
      function set.EmployeeName(obj,name)
         if ischar(name)
            obj.EmployeeName = name;
            error('Employee name must be a text string')
         end
      end
   end
end
```

Inspecting the Class Definition

Using the EmployeeData class, create a meta.class object using the ? operator:

```
mc = ?EmployeeData;
```

Determine from what classes EmployeeData derives:

```
a = mc.SuperclassList; % a is an array of meta.class objects
a.Name
ans =
handle
```

The EmployeeData class has only one superclass. For classes having more than one superclass, a would contain a meta.class object for each superclass. Use an indexed reference to refer to any particular superclass:

```
a(1).Name
or, directly from MC:
mc.SuperclassList(1).Name
ans =
handle
```

Inspecting Properties

Find the names of the properties defined by the EmployeeData class. First obtain an array of meta.properties objects from the meta.class PropertyList property.

```
mpArray = mc.PropertyList;
```

The length of mpArray indicates there are two meta.property objects, one for each property defined by the EmployeeData class:

```
length(mpArray)
ans =
    2
```

Now get a meta.property object from the array:

```
prop1 = mpArray(1);
prop1.Name
ans =
```

EmployeeName

The Name property of the meta.property object identifies the class property represented by that meta.property object.

Query other meta.property object properties to determine the attributes of the EmployeeName properties.

Inspecting an Instance of a Class

Create an EmployeeData object and determine property access settings:

```
EdObj = EmployeeData('My Name',1234567);
mcEdObj = metaclass(EdObj);
mpArray = mcEdObj.PropertyList;
EdObj.(mpArray(1).Name) % Dynamic field names work with objects
ans =
    My Name
EdObj.(mpArray(2).Name)
Getting the 'EmployeeNumber' property of the 'EmployeeData' class is not allowed.
mpArray(2).GetAccess
ans =
    private
```

Obtain a function handle to the property set access function:

```
mpArray(1).SetMethod
ans =
   @D:\MyDir\@EmployeeData\EmployeeData.m>EmployeeData.set.EmployeeName
```

Metaclass Enumerated Values Property

The meta.class EnumeratedValues property contains an array of meta.EnumeratedValue objects, one for each enumeration member. Use the meta.EnumeratedValue Name property to obtain the enumeration member names defined by an enumeration class. For example, given the WeekDays enumeration class:

```
classdef WeekDays
   enumeration
       Monday, Tuesday, Wednesday, Thursday, Friday
   end
end

Query enumeration names from the meta.class object:

mc = ?WeekDays;
mc.EnumerationMemberList(2).Name
ans =
Tuesday
```

Finding Objects with Specific Values

```
In this section...

"Find Handle Objects" on page 15-8

"Find by Attribute Settings" on page 15-9
```

Find Handle Objects

Use the handle class findobj method to find objects that have properties with specific values. For example, the following class defines a PhoneBook object to represent a telephone book entry in a data base. The PhoneBook class subclasses the dynamicprops class, which derives from handle.

```
classdef PhoneBook < dynamicprops
  properties
    Name
    Address
    Number
  end
  methods
    function obj = PhoneBook(n,a,p)
      obj.Name = n;
    obj.Address = a;
    obj.Number = p;
  end
  end
end</pre>
```

Assume three of the PhoneBook entries in the database are:

```
PB(1) = PhoneBook('Nancy Vidal','123 Washington Street','5081234567');
PB(2) = PhoneBook('Nancy Vidal','123 Main Street','5081234568');
PB(3) = PhoneBook('Nancy Wong','123 South Street','5081234569');
```

One of these three PhoneBook objects has a dynamic property:

```
PB(2).addprop('HighSpeedInternet');
PB(2).HighSpeedInternet = '1M';
```

Find Property/Value Pairs

Find the object representing employee Nancy Wong and display the name and number by concatenating the strings:

```
NW = findobj(PB,'Name','Nancy Wong');
[NW.Name,' - ',NW.Number]
ans =
Nancy Wong - 5081234569
```

Find Objects with Specific Property Names

Search for objects with specific property names using the -property option:

```
H = findobj(PB,'-property','HighSpeedInternet');
H.HighSpeedInternet
ans =
```

The -property option enables you to omit the value of the property and search for objects using only the property name.

Using Logical Expressions

Search for specific combinations of property names and values:

```
H = findobj(PB, 'Name', 'Nancy Vidal', '-and', 'Address', '123 Main Street');
H.Number
ans =
5081234568
```

Find by Attribute Settings

All meta-classes derive from the handle class so you can use the handle findobj method to find class members that have specific attribute settings.

For example, find the abstract methods in a class definition by searching the meta.class MethodList for meta.method objects with their Abstract property set to true:

```
% Use class name in string form because class is abstract
mc = meta.class.fromName('ClassName');
% Search list of meta.method objects for those
```

```
% methods that have their Abstract property set to true
absMethods = findobj(mc.MethodList, 'Abstract', true);
methodNames = {absMethods.Name};
```

The cell array, methodNames, contains the names of the abstract methods in the class.

Find Properties That Have Public Get Access

Find the names of all properties in the containers. Map class that have public GetAccess:

- Get the meta.class object
- Use findobj to search the array of meta.property objects

```
mc = ?containers.Map;
% findobj returns an array of meta.property objects
% use braces to convert the comman separated list to a cell array
mpArray = findobj(mc.PropertyList, 'GetAccess', 'public');
% create cell array of property names
names = {mpArray.Name};
```

Display the names of all containers. Map properties that have public GetAccess:

```
celldisp(names)
names{1} =
Count
 names{2} =
KeyType
names{3} =
ValueType
```

Find Static Methods

0

Determine if any containers. Map class methods are static:

```
isempty(findobj([mc.MethodList(:)], 'Static', true))
ans =
```

findobj returns an array of meta.method objects for the static methods. In this case, isempty returns false, indicating there are static methods defined by this class.

You can get the names of any static methods from the meta.method array:

```
staticMethodInfo = findobj([mc.MethodList(:)],'Static',true);
staticMethodInfo(:).Name
ans =
empty
```

The name of the static method (there is only one in this case) is empty. Here is the information from the meta.method object for the empty method:

staticMethodInfo

```
method with properties:
```

Getting Information About Properties

```
In this section...

"The meta.property object" on page 15-12

"How to Find Properties with Specific Attributes" on page 15-15
```

The meta.property object

The meta.property class is useful for determining the settings of property attributes. The writable properties of a meta.property object correspond to the attributes of the associated property. The values of the writable meta.property properties correspond to the attribute setting specified in the class definition.

For example, create a default containers. Map object and use the handle findprop method to get the meta.property object for the Count property:

```
mp = findprop(containers.Map, 'Count')
mp =
  property with properties:
                   Name: 'Count'
            Description: 'Number of pairs in the collection'
    DetailedDescription:
              GetAccess: 'public'
              SetAccess: 'private'
              Dependent: 1
               Constant: 0
               Abstract: 0
              Transient: 1
                 Hidden: 0
          GetObservable: 0
          SetObservable: 0
               AbortSet: 0
              GetMethod: []
              SetMethod: []
          DefiningClass: [1x1 meta.class]
```

The preceding meta.property display shows that the default Map object Count property has public GetAccess and private SetAccess, is Dependent, and Transient. See "Table of Property Attributes" on page 7-7 for a list of property attributes.

If you are working with a class that is not a handle class, get the meta.property objects from the meta.class object. All metaclasses are subclasses of the handle class. Use the metaclass function if you have an instance or the ? operator with the class name:

```
mc = ?containers.Map
mc =
  class with properties:
                     Name: 'containers.Map'
              Description: 'MATLAB Map Container'
      DetailedDescription: 'MATLAB Map Container'
                   Hidden: 0
                   Sealed: 0
          ConstructOnLoad: 1
         HandleCompatible: 1
          InferiorClasses: {0x1 cell}
        ContainingPackage: [1x1 meta.package]
             PropertyList: [4x1 meta.property]
               MethodList: [35x1 meta.method]
                EventList: [1x1 meta.event]
    EnumerationMemberList: [Ox1 meta.EnumeratedValue]
           SuperclassList: [1x1 meta.class]
```

The meta.class object property named PropertyList contains an array of meta.property objects, one for each property defined by the containers.Map class. For example, the name of the property associated with the meta.property object in element 1 is:

```
mc.PropertyList(1).Name
ans =
Count
```

The meta.class object contains a meta.property object for hidden properties too. Compare the result with the properties function, which returns only public properties:

```
properties('containers.Map')
Properties for class containers.Map:
```

```
Count
KeyType
ValueType
```

The serialization property is Hidden and has its GetAccess and SetAccess attributes set to private. Therefore, the properties function does not list it. However, you can get information about this property from its associated meta.property object (which is the fourth element in the array of meta.property objects in this case):

```
mc.PropertyList(4)
ans =
  class with properties:
                   Name: 'serialization'
            Description: 'Serialization property.'
    DetailedDescription: ''
              GetAccess: 'private'
              SetAccess: 'private'
              Dependent: 0
               Constant: 0
               Abstract: 0
              Transient: 0
                 Hidden: 1
          GetObservable: 0
          SetObservable: 0
               AbortSet: 0
              GetMethod: []
              SetMethod: []
          DefiningClass: [1x1 meta.class]
```

Indexing Metaclass Objects

Access other metaclass objects directly from the meta.class object properties. For example, the statement:

```
mc = ?containers.Map;
returns a meta.class object:
class(mc)
ans =
```

```
meta.class
```

Referencing the PropertyList meta.class property returns an array with one meta.property object for each property of the containers.Map class:

```
class(mc.PropertyList)
ans =
meta.property
Each array element is a single meta.property object:
mc.Properties(1)
ans =
  [1x1 meta.property]
```

The Name property of the meta.property object contains a character string that is the name of the property:

```
class(mc.PropertyList(1).Name)
ans =
char
```

Apply standard MATLAB indexing to access information in metaclass objects.

For example, because the meta.class PropertyList property contains an array of meta.property objects, the following expression accesses the first meta.property object in this array and returns the first and last (C and t) letters of the string contained in the meta.property Name property.

```
mc.PropertyList(1).Name([1 end])
ans =
Ct
```

How to Find Properties with Specific Attributes

This example implements a function that finds properties with specific attribute settings. For example, find objects that define constant properties (Constant attribute set to

true) or determine what properties are read-only (GetAccess = public, SetAccess = private). The findAttrValue function returns a cell array of property names that set the specified attribute.

This function accesses information from metaclasses using these techniques:

- If input argument, obj, is a string, use the meta.class.fromName static method to get the meta.class object.
- If input argument, Obj, is an object, use the metaclass function to get the meta.class object.
- Every property has an associated meta.property object. Obtain these objects from the meta.class PropertyList property.
- Use the handle class findprop method to determine if the requested property attribute is a valid attribute name. All property attributes are properties of the meta.property object. The statement, findobj (mp, 'PropertyName') determines whether the meta.property object, mp, has a property called PropertyName.
- Reference meta.property object properties using dynamic field names. For example, if attrName = 'Constant', then MATLAB converts the expression mp. (attrName) to mp.Constant
- The optional third argument enables you to specify the value of attributes whose values are not logical true or false (such as GetAccess and SetAccess).

```
function cl_out = findAttrValue(obj,attrName,varargin)
  % Determine if first input is object or class name
   if ischar(obj)
     mc = meta.class.fromName(obj);
   elseif isobject(obj)
     mc = metaclass(obj);
   end
  % Initialize and preallocate
  ii = 0; numb_props = length(mc.PropertyList);
  cl array = cell(1, numb props);
  % For each property, check the value of the queried attribute
  for c = 1:numb props
      % Get a meta.property object from the meta.class object
      mp = mc.PropertyList(c);
      % Determine if the specified attribute is valid on this object
      if isempty (findprop(mp,attrName))
         error('Not a valid attribute name')
      attrValue = mp.(attrName);
```

```
% If the attribute is set or has the specified value,
% save its name in cell array
if attrValue
    if islogical(attrValue) || strcmp(varargin{1},attrValue)
        ii = ii + 1;
        cl_array(ii) = {mp.Name};
    end
    end
end
end
% Return used portion of array
cl_out = cl_array(1:ii);
end
```

Find Property Attributes

Suppose you have the following containers. Map object:

```
mapobj = containers.Map({'rose','bicycle'},{'flower','machine'});
Find properties with private SetAccess:
findAttrValue(mapobj,'SetAccess','private')
ans =
    'Count' 'KeyType' 'ValueType' 'serialization'
Find properties with public GetAccess:
findAttrValue(mapobj,'GetAccess','public')
ans =
    'Count' 'KeyType' 'ValueType'
```

Find Default Values in Property Metadata

```
In this section...
"meta.property Object" on page 15-18
"meta.property Data" on page 15-18
```

meta.property Object

Class definitions can specify explicit default values for properties (see "Defining Default Values" on page 4-12). You can determine if a class defines explicit default values for a property and what the value of the default is from the property's meta.property object.

meta.property Data

Obtain the default value of a property from the property's associated meta.property object. The meta.class object for a class contains a meta.property object for every property defined by the class, including properties with private and protected access. For example:

```
mc = ?MException;
                      % meta.class object for MException class
mp = mc.PropertyList; % Array of meta.property objects
                      % meta.property object for 'type' property
mp(1)
ans =
  class with properties:
                   Name: 'type'
            Description: 'Type of error reporting'
    DetailedDescription: ''
              GetAccess: 'private'
              SetAccess: 'private'
              Dependent: 0
               Constant: 0
               Abstract: 0
              Transient: 0
                 Hidden: 0
          GetObservable: 1
          SetObservable: 1
               AbortSet: 0
              GetMethod: []
```

```
SetMethod: []
HasDefault: 1
DefaultValue: {}
DefiningClass: [1x1 meta.class]
```

Two meta.property object properties provide information on default values:

- HasDefault True if class specifies a default value for the property, false if it
 does not.
- DefaultValue Contains the default value, if the class defines a default value for the property.

These properties provide a programmatic way to obtain property default values without reading class definition files. Use these meta.property object properties to obtain property default values for built-in classes and classes defined in MATLAB code.

Querying a Default Value

The procedure for querying a default value involves:

- 1 Getting the meta.property object for the property whose default value you want to query.
- 2 Testing the logical value of the meta.property HasDefault property to determine if the property defines a default value. MATLAB returns an error when you query the DefaultValue property if the class does not define a default value for the property.
- 3 Obtaining the default value from the meta.property DefaultValue property if the HasDefault value is true.

Use the ? operator, the metaclass function, or the meta.class.fromName static method (works with string variable) to obtain a meta.class object. The meta.class object PropertyList property contains an array of meta.property objects. Identify which property corresponds to which meta.property object using the meta.property Name property.

For example, this class defines properties with default values:

```
classdef MyDefs
  properties
    Material = 'acrylic';
    InitialValue = 1.0;
end
```

end

Follow these steps to obtain the default value defined for the Material property. Include any error checking that is necessary for your application.

1 Get the meta.class object for the class:

```
mc = ?MyDefs;
```

2 Get an array of meta.property objects from the meta.class PropertyList property:

```
mp = mc.PropertyList;
```

3 The length of the mp array equals the number of properties. You can use the meta.property Name property to find the property of interest:

```
for k = 1:length(mp)
   if (strcmp(mp(k).Name, 'Material')
```

4 Before querying the default value of the Material property, test the HasDefault meta.property to determine if MyClass defines a default property for this property:

```
if mp(k).HasDefault
         dv = mp(k).DefaultValue;
      end
   end
end
```

The DefaultValue property is read only. Changing the default value in the class definition changes the value of DefaultValue property. You can query the default value of a property regardless of its access settings.

Abstract and dynamic properties cannot define default values. Therefore, MATLAB returns an error if you attempt to query the default value of properties with these attributes. Always test the logical value of the meta.property HasDefault property before querying the DefaultValue property to avoid generating an error.

Default Values Defined as Expressions

Class definitions can define property default values as MATLAB expressions (see "Expressions in Class Definitions" on page 5-8 for more information). MATLAB evaluates these expressions the first time the default value is needed, such as the first time you create an instance of the class.

Querying the meta.property DefaultValue property causes MATLAB to evaluate a default value expression, if it had not yet been evaluated. Therefore, querying a property default value can return an error or warning if errors or warnings occur when MATLAB evaluates the expression. See "Property With Expression That Errors" on page 15-22 for an example.

Property With No Explicit Default Value

MyClass does not explicitly define a default value for the Foo property:

```
classdef MyFoo
    properties
        Foo
    end
end
```

The meta.property instance for property Foo has a value of false for HasDefault. The class does not explicitly define a default value for Foo. Therefore, attempting to access the DefaultValue property causes an error:

```
mc = ?MyFoo;
mp = mc.PropertyList(1);
mp.HasDefault
ans =
     0

dv = mp.DefaultValue;
No default value has been defined for property Foo
```

Abstract Property

MyClass defines the Foo property as Abstract:

```
classdef MyAbst
  properties (Abstract)
    Foo
  end
end
```

The meta.property instance for property Foo has a value of false for its HasDefault property because you cannot define a default value for an Abstract property. Attempting to access DefaultValue causes an error:

```
mc = ?MyAbst;
mp = mc.PropertyList(1);
mp.HasDefault
ans =
     0

dv = mp.DefaultValue;
Property Foo is abstract and therefore cannot have a default value.
```

Property With Expression That Errors

MyPropEr defines the Foo property default value as an expression that errors.

```
classdef MyPropEr
  properties
    Foo = sin(pie/2);
  end
end
```

The meta.property instance for property Foo has a value of true for its HasDefault property because Foo does have a default value determined by the evaluation of the expression:

```
sin(pie/2)
```

However, this expression returns an error (pie is a function that creates a pie graph, not the value pi).

Querying the default value causes the evaluation of the expression and returns the error.

Property With Explicitly Defined Default Value of Empty ([])

MyEmptyProp assigns a default of [] (empty double) to the Foo property:

```
classdef MyEmptyProp
  properties
    Foo = [];
  end
end
```

The meta.property instance for property Foo has a value of true for its HasDefault property. Accessing DefaultValue returns the value []:

```
mc = ?MyEmptyProp;
mp = mc.PropertyList(1);
mp.HasDefault
ans =
    1

dv = mp.DefaultValue;
dv =
    []
```

Specializing Object Behavior

- "Methods That Modify Default Behavior" on page 16-2
- "Overloading numel, subsref, and subsasgn" on page 16-5
- "Concatenation Methods" on page 16-7
- "Object Converters" on page 16-8
- "Object Array Indexing" on page 16-11
- "Indexed Reference" on page 16-17
- "Indexed Assignment" on page 16-21
- "Object end Indexing" on page 16-25
- "Objects In Index Expressions" on page 16-27
- "Class with Modified Indexing" on page 16-29
- "Class Operator Implementations" on page 16-37

Methods That Modify Default Behavior

In this section...

"How to Customize Class Behavior" on page 16-2

"Which Methods Control Which Behaviors" on page 16-2

"Overloading and Overriding Functions and Methods" on page 16-3

How to Customize Class Behavior

There are functions that MATLAB calls implicitly when you perform certain actions with objects. For example, a statement like [B(1);A(3)] involves indexed reference and vertical concatenation.

You can change how user-defined objects behave by defining methods that control specific behaviors. To change a behavior, implement the appropriate method with the name and signature of the MATLAB function.

Which Methods Control Which Behaviors

The following table lists the methods to implement for your class and describes the behaviors that they control.

Class Method to Implement	Description
Concatenating Objects	
cat, horzcat, and vertcat	Customize behavior when concatenation objects
	See "Built-In Subclass With Properties"
Creating Empty Arrays	
empty	Create empty arrays of the specified class. See "Empty Arrays" on page 9-8
Displaying Objects	
disp	Called when you enter disp(obj) on the command line
display	
	Called when statements are not terminated by semicolons. disp is often used to implement display methods.

	ee "Overload the disp Function" on page 7-37			
Converting Objects to Other Classes				
converters like double and char C	Convert an object to a MATLAB built-in class			
	ee "The Character Converter" on page 18-16 nd "The Double Converter" on page 18-15			
Indexing Objects				
_	Cnables you to create nonstandard indexed eference and indexed assignment			
S	ee "Object Array Indexing" on page 16-11			
	sing an object; e.g., A(1:end)			
S	ee "Object end Indexing" on page 16-25			
numel D	Determine the number of elements in an array			
S	ee "Overloading numel, subsref, and subsasgn"			
size D	Determine the dimensions of an array			
S	ee "Understanding size and numel"			
subsindex S	upport using an object in indexing expressions			
	ee "Objects In Index Expressions" on page 6-27			
Saving and Loading Objects				
	Customize behavior when loading and saving bjects			
S	ee "Save and Load"			

Overloading and Overriding Functions and Methods

Overloading and overriding are terms that describe techniques for customizing class behavior. Here is how we use these terms in MATLAB.

Overloading

Overloading means that there is more than one function or method having the same name within the same scope. MATLAB dispatches to a particular function or method based on the dominant argument. For example, the timeseries class overloads the MATLAB plot function. When you call plot with a timeseries object as an input argument, MATLAB calls the timeseries class method named plot.

Overriding

Overriding means redefining a method inherited from a superclass. MATLAB dispatches to the most specific version of the method. That is, if the dominant argument is an instance of the subclass, then MATLAB calls the subclass method.

Use the InferiorClasses attribute to control class precedence.

More About

"Overloading numel, subsref, and subsasgn" on page 16-5

Overloading numel, subsref, and subsasgn

In this section...

"Considerations for Overloading" on page 16-5

"Syntax to Overload numel, subsref, and subsasgn" on page 16-5

Considerations for Overloading

Many MATLAB functions depend on the behavior of other functions, like size and numel. Therefore, you must be careful to ensure that what is returned by an overloaded version of these functions is a correct and accurate representation of the size of an object array.

Interactions with numel, subsref, and subsasgn

You might need to define a numel method to compensate when your class defines a specialized version of Size.

subsref uses the value returned by numel to compute the number of expected output arguments returned by subsref from subscripted reference (i.e., nargout).

Similarly, subsasgn uses numel to compute the expected number of input arguments to be assigned using subsasgn (i.e., nargin).

MATLAB determines the value of nargin for an overloaded subsasgn function from the value returned by numel, plus two (one for the variable to which you are making an assignment and one for the struct array of subscripts).

If MATLAB produces errors when calling your class's overloaded subsref or subsagn methods because nargout is wrong for subsref or nargin is wrong for subsasgn, then you need to overload numel to return a value that is consistent with your implementation of these indexing functions.

See for more information on implementing subsref and subsagn methods.

Syntax to Overload numel, subsref, and subsasgn

When resolving an indexed reference or assignment, MATLAB calls numel to determine the number of outputs that are expected from subsref or the number of inputs required by subsasgn. To support {} indexing, you need to overload numel to accept a variable number of input index values in addition to the object array. Define the overloaded numel with this syntax:

```
function n = numel(A,varargin)
   ...
end
```

where varargin represent indices into array A.

MATLAB uses the value returned by numel to determine:

- · How many outputs to return from subsref in the case of indexed reference
- How many inputs to pass to subsasgn in the case of indexed assignment

When overloading subsref, define the method to return multiple values for the indexed reference using varargout:

```
function [varargout] = subsref(A,S)
...
end
```

When overloading subsasgn, define the method to accept multiple values for the right hand side of the indexed assignment:

```
function A = subsagn(A,S,varargin)
```

More About

· "Understanding size and numel"

Concatenation Methods

In this section...

"Default Concatenation" on page 16-7

"Methods to Overload" on page 16-7

Default Concatenation

You can concatenate objects into arrays. For example, suppose you have three instances of the class MyClass, obj1, obj2, obj3. You can form arrays of these objects using brackets. Horizontal concatenation calls horzcat:

```
HorArray = [obj1,obj2,obj3];
```

HorArray is a 1-by-3 array of class MyClass. You can concatenate the objects along the vertical dimension, which calls vertcat:

```
VertArray = [obj1;obj2;obj3]
```

VertArray is a 3-by-1 array of class MyClass. Use the cat function to concatenate arrays along different dimensions. For example:

```
ndArray = cat(3,HorArray,HorArray);
```

ndArray is a 1-by-3-by-2 array.

Methods to Overload

Overload horzcat, vertcat, and cat to produce specialized behaviors in your class. You must overload both horzcat and vertcat whenever you want to modify object concatenation because MATLAB uses both functions for any concatenation operation.

Related Examples

"Built-In Subclass With Properties"

Object Converters

```
In this section...
"Why Implement a Converter" on page 16-8
"Converters for Package Classes" on page 16-8
"Converters and Subscripted Assignment" on page 16-9
```

Why Implement a Converter

You can convert an object of one class to an object of another class. A converter method has the same name as the class it converts to, such as char or double. Think of a converter method as an overloaded constructor method of another class—it takes an instance of its own class and returns an object of a different class.

Converters enable you to:

- Use methods defined for another class
- Ensure that expressions involving objects of mixed class types execute properly
- Control how instances are interpreted in other contexts

Suppose you define a polynomial class. If you create a double method for the polynomial class, you can use it to call other functions that require inputs of type double.

```
p = polynomial(...);
dp = double(p);
roots(dp)
```

p is a polynomial object, double is a method of the polynomial class, and roots is a standard MATLAB function whose input arguments are the coefficients of a polynomial.

Converters for Package Classes

Classes defined in packages can have names that are a dot-separated list of names. The last name is a class and preceding names are packages. Name the conversion methods using the package qualifiers in the method names. For example, a conversion method to convert objects of MyClass to objects of the PkgName.PkgClass class uses this method name:

```
classdef MyClass
```

```
methods
    function objPkgClass = PkgName.PkgClass(objMyclass)
    end
end
end
```

You cannot define a converter method that uses dots in the name in a separate file. You must define package-class converters in the classdef file.

Converters and Subscripted Assignment

When you make a subscripted assignment statement like:

```
A(1) = myobj;
```

MATLAB compares the class of the Right-Side variable to the class of the Left-Side variable. If the classes are different, MATLAB attempts to convert the Right-Side variable to the class of the Left-Side variable. To do this, MATLAB first searches for a method of the Right-Side class that has the same name as the Left-Side class. Such a method is a converter method, which is similar to a typecast operation in other languages.

If the Right-Side class does not define a method to convert from the Right-Side class to the Left-Side class, then MATLAB software calls the Left-Side class constructor and passes it to the Right-Side variable.

For example, suppose you make the following assignments:

```
A(1) = objA; % Object of class ClassA
A(2) = objB; % Object of class ClassB
```

MATLAB attempts to call a method of ClassB named ClassA. If no such converter method exists, MATLAB software calls the ClassA constructor, passing ObjB as an argument. If the ClassA constructor cannot accept ObjB as an argument, then MATLAB returns an error.

Use cell arrays to store objects of different classes.

Related Examples

"Converter Methods"

"The Double Converter" on page 18-15

Object Array Indexing

In this section...

"Default Indexed Reference and Assignment" on page 16-11

"What You Can Modify" on page 16-12

"When to Modify Indexing Behavior" on page 16-13

"Built-In subsref and subsasgn Called In Methods" on page 16-13

"Avoid Overriding Access Attributes" on page 16-15

Default Indexed Reference and Assignment

MATLAB provides support for object array indexing by default. Many class designs require no modification to this behavior.

Arrays enable you to reference and assign elements of the array using a subscripted notation. This notation specifies the indices of specific array elements. For example, suppose you create two arrays of numbers (using randi and concatenation).

Create a 3-by-4 array of integers between 1 and 9:

Create a 1-by-3 array of the numbers 3, 6, 9:

$$B = [3 6 9];$$

Reference and assign elements of either array using index values in parentheses:

When you execute a statement that involves indexed reference:

```
C = A(3,4);
```

MATLAB calls the built-in subsref function to determine how to interpret the statement. Similarly, if you execute a statement that involves indexed assignment:

```
C(4) = 7;
```

MATLAB calls the built-in subsasgn function to determine how to interpret the statement.

The MATLAB default subsref and subsasgn functions also work with user-defined objects. For example, create an array of objects of the same class:

```
for k=1:3
  objArray(k) = MyClass;
end
```

Referencing the second element in the object array, objArray, returns the object constructed when k = 2:

```
D = objArray(2);
class(D)
ans =
MyClass
```

You can assign an object to an array of objects of the same class, or an uninitialized variable:

```
newArray(3,4) = D;
```

Arrays of objects behave much like numeric arrays in MATLAB. You do not need to implement any special methods to provide standard array behavior with your class.

For general information about array indexing, see "Matrix Indexing".

What You Can Modify

You can modify your class's default indexed reference and/or assignment behavior by implementing class methods called subsref and subsasgn. For syntax description, see their respective reference pages.

Once you add a subsref or subsasgn method to your class, then MATLAB calls only the class method, not the built-in function. Therefore, you must implement in your class method all of the indexed reference and assignment operations that you want your class to support. These operations include:

- Dot notation calls to class methods
- Dot notation reference and assignment involving properties
- Any indexing using parentheses '()'
- Any indexing using braces '{}'

Implementing subsref and subsasgn methods gives you complete control over the interpretation of indexing expressions for objects of your class. Implementing the extent of behaviors that MATLAB provides by default is nontrivial.

When to Modify Indexing Behavior

Default indexing for object arrays and dot notation for access to properties and methods enables user-defined objects to behave like built-in classes. For example, suppose you define a class with a property called Data that contains an array of numeric data.

This statement:

```
obj.Data(2,3)
```

Returns the value contained in the second row, third column of the array. If you have an array of objects, use an expression like:

```
objArray(3).Data(2,3)
```

This statement returns the value contained in the second row, third column of the third element in the array.

Modify the default indexing behavior when your class design requires behavior that is different from that provided by MATLAB by default.

Built-In subsref and subsasgn Called In Methods

MATLAB does not call class-defined subsref or subsasgn methods within the class's own methods. Within class methods, MATLAB always calls the built-in subsref and subsasgn functions. This behavior occurs within the class-defined subsref and subsasgn methods too.

For example, within a class method, this dot reference:

```
obj.Prop
```

calls the built-in subsref function. To call the class-defined subsref method, use:

```
subsref(obj,substruct('.','Prop'))
```

Whenever a method requires the functionality of the class-defined subsref or subsasgn method, the class must call the overloaded methods as functions. Do not use the operators, '()', '{}', or '.'.

For example, suppose you define a class to represent polynomial. This class has a subsref method that evaluates the polynomial with the value of the independent variable equal to the subscript. Assume this statement defines the polynomial with its coefficients:

```
p = polynom([1 0 -2 -5]);
```

The MATLAB expression for the resulting polynomial is:

```
x^3 - 2*x - 5
```

This subscripted expression returns the value of the polynomial at x = 3:

```
p(3)
```

```
ans = 16
```

Suppose that you want to use this feature in another class method. To do so, call the subsref function directly. The evalEqual method accepts two polynom objects and a value at which to evaluate the polynomials:

methods

```
function ToF = evalEqual(p1,p2,x)
  % Create arguments for subsref
  subs.type = '()';
  subs.subs = {x};
  % Need to call subsref explicitly
  y1 = subsref(p1,subs);
  y2 = subsref(p2,subs);
  if y1 == y2
    ToF = true;
  else
```

```
ToF = false;
end
end
end
```

This behavior enables you to use standard MATLAB indexing to implement specialized behaviors. See "Class with Modified Indexing" on page 16-29 for examples of how to use both built-in and class-modified indexing.

Avoid Overriding Access Attributes

Because subsref is a class method, it has access to private class members. Avoid inadvertently giving access to private methods and properties as you handle various types of reference. Consider this subsref method defined for a class having private properties, x and y:

```
classdef MyPlot
   properties (Access = private)
      Х
      У
   end
   properties
      Maximum
      Minimum
      Average
   end
   methods
      function obj = MyPlot(x,y)
         obj.x = x;
         obj.y = y;
         obj.Maximum = max(y);
         obj.Minimum = min(v);
         obj.Average = mean(y);
      function B = subsref(A,S)
         switch S(1).type
            case '.'
               switch S(1).subs
                  case 'plot'
                      % Reference to A.x and A.y call built-in subsref
                     B = plot(A.x,A.y);
                  otherwise
                      % Enable dot notation for all properties and methods
```

```
B = A.(S.subs);
end
end
end
end
end
```

This subsref enables users to use dot notation to perform an action (create a plot) using the name 'plot'. The statement:

```
obj = MyPlot(1:10,1:10);
h = obj.plot;
```

calls the plot function and returns the handle to the graphics object.

You do not need to explicitly code each method and property name because the otherwise code in the inner switch block handles any name reference that you do not explicitly specify in case statements. However, using this technique exposes any private and protected class members via dot notation. For example, you can reference the private property, X, with this statement:

```
obj.x
ans =
```

The same issue applies to writing a subsasgn method that enables assignment to private or protected properties. Your subsref and subsasgn methods might need to code each specific property and method name explicitly to avoid violating the class design.

Related Examples

- "Indexed Reference" on page 16-17
- "Indexed Assignment" on page 16-21

Indexed Reference

In this section...

"Understanding Indexed Reference" on page 16-17

"Compound Indexed References" on page 16-18

"Writing subsref" on page 16-19

Understanding Indexed Reference

Object indexed references are in three forms — parentheses, braces, and name:

A(I) A{I}

A.name

Each of these statements causes a call by MATLAB to the subsref method of the class of A, or a call to the built-in subsref function, if the class of A does not implement a subsref method.

MATLAB passes two arguments to subsref:

```
B = subsref(A,S)
```

The first argument is the object being referenced, A. The second argument, S, is a struct with two fields:

- S.type is a string containing '()', '{}', or '.' specifying the indexing type used.
- S.subs is a cell array or string containing the actual index or name. A colon used as an index is passed in the cell array as the string ':'. Ranges specified using a colon (e.g., 2:5) are expanded to 2 3 4 5.

For example, the expression:

```
A(1:4,:)
```

Causes MATLAB to call subsref(A,S), where S is a 1-by-1 structure with a twoelement cell array. The cell array contains the numbers 1, 2, 3, 4, and the colon character:

```
S.type = '()'
S.subs = {1:4,':'}
```

Returning the contents of each cell of S. subs gives the index values for the first dimension and a string ':' for the second dimension:

The default subsref returns all array elements in rows 1 through 4 and all of the columns in the array.

Similarly, this expression:

```
A{1:4}
```

Uses a cell array containing the numbers 1, 2, 3, 4.

```
S.type = '{}'
S.subs = {1:4}
```

The default subsref returns the contents of all cell array elements in rows 1 through 4 and all of the columns in the array.

This expression:

A.Name

Calls subsref(A,S), where the struct S has these values:

```
S.type = '.'
S.subs = 'Name'
```

The default subsref returns the contents of the Name field in the struct array or the value of the property Name if A is an object with the specified property name.

Compound Indexed References

These simple calls are combined for more complicated indexing expressions. In such cases, length(S) is the number of indexing levels. For example,

```
A(1,2).PropertyName(1:4)
```

calls subsref(A,S), where S is a 3-by-1 array of structs with the values:

```
S(1).type = '()' S(2).type = '.' S(3).type = '()' S(1).subs = \{1,2\} S(2).subs = 'PropertyName' S(3).subs = \{1:4\}
```

Writing subsref

Your class's subsref method must interpret the indexing expressions passed in by MATLAB. Any behavior you want your class to support must be implemented by your subsref. However, your method can call the built-in subsref to handle indexing types that you do not want to change.

You can use a switch statement to determine the type of indexing used and to obtain the actual indices. The following three code fragments illustrate how to interpret the input arguments. In each case, the function must return the value (B) that is returned by your subsref function.

For a parentheses index:

```
% Parse A(n)
switch S.type
case '()'
   B = A(S.subs{:});
end
```

For a brace index (CellProperty contained a cell array):

```
% Parse A{n}
switch S.type
case '{}'
   B = A.CellProperty{S.subs{:}};
end
```

While braces are used for cell arrays in MATLAB, your subsref method can define its own meaning for this syntax.

Dot name indexing typically accesses property values. The name can be an arbitrary string for which you take an arbitrary action:

```
switch S.type
case '.'
  switch S.subs
```

```
case 'name1'
      B = A.name1;
   case 'name2'
      B = A.name2;
   end
end
```

If the dot name is a method call, passing arguments requires a second level of indexing.

Related Examples

- "Class with Modified Indexing" on page 16-29
- "Redefine Indexed Reference"

Indexed Assignment

In this section...

"Understanding Indexed Assignment" on page 16-21

"Indexed Assignment to Objects" on page 16-23

"Compound Indexed Assignments" on page 16-23

Understanding Indexed Assignment

Object indexed assignments are in three forms — parentheses, braces, and name:

```
A(I) = B
A{I} = B
A.name = B
```

Each of these statements causes MATLAB to call the subsasgn method of the class of A, or a call to the built-in function, if the class of A does not implement a subsasgn method.

MATLAB passes three arguments to subsasgn:

```
A = subsasgn(A,S,B)
```

The first argument, A, is the object being assigned the value in the third argument B.

The second argument, S, is a struct with two fields:

- S.type is a string containing '()', '{}', or '.' specifying the indexing type used.
- S. subs is a cell array or string containing the actual index or name. A colon used as an index is passed in the cell array as the string ':'. Ranges specified using a colon (e.g., 2:5) are expanded to 2 3 4 5.

For example, the assignment statement:

```
A(2,3) = B;

generates a call to subsasgn: A = subsasgn(A,S,B) where S is:

S.type = '()'

S.subs = {2,3}
```

The default subsasgn:

- Determines the class of A. If B is not the same class as A, then MATLAB tries to
 construct an object of the same class as A using B as an input argument (e.g., by
 calling a converter method, if one exists). If this attempt fails, MATLAB returns an
 error.
- If A and B are, or can be made, into the same class, then MATLAB assigns the value of B to the array element at row 2, column 3.
- If A does not exist before you execute the assignment statement, then MATLAB initializes the five array elements that come before A(2,3) with a default object of the class of A and B. For example, empty elements are initialized to zero in the case of a numeric array or an empty cell ([]) in the case of cell arrays.

Similarly, this expression

```
A\{2,3\} = B
```

Uses these values for the struct S:

```
S.type = '{}'
S.subs = {2,3}
```

The default subsasgn:

- Assigns B to the cell array element at row 2, column 3.
- If A does not exist before you execute the assignment statement, MATLAB initializes the five cells that come before A(2,3) with []. The result is a 2-by-3 cell array.

This expression:

```
A.Name = B
Calls A = subsasgn(A,S,B) where the struct S has these values:
S.type = '.'
S.subs = 'Name'
```

The default subsasgn:

- Assigns B to the struct field Name.
- If A does not exist before you execute the assignment statement, MATLAB creates
 a new struct variable, A with field Name and assigns the value of B to this field
 location.

- If struct A exists, but has no field Name, then MATLAB adds the field Name and assigns the value of B to the new field location.
- If struct A exists and has a Name field, then MATLAB assigns the value of B to Name.

You can redefine all or some of these assignment behaviors by implementing a subsasgn method for your class.

Indexed Assignment to Objects

If A is an object, this expression:

```
A.Name = B
Calls A = subsasgn(A,S,B) where, struct S has these values:
S.type = '.'
S.subs = 'Name'
```

The default subsasgn:

- Attempts to assign B to the Name property.
- If the class of A does not have a Name property, MATLAB returns an error.
- If the Name property has restricted access (private or protected), MATLAB determines if the assignment is allowed based on the context in which the assignment is made.
- If the class of A defines a set method for property Name, MATLAB calls the set method.
- MATLAB applies all other property attributes before determining whether to assigning B to the property Name.

Compound Indexed Assignments

These simple calls are combined for more complicated indexing expressions. In such cases, length(S) is the number of indexing levels. For example,

```
A(1,2).PropertyName(1:4) = B
```

calls subsasgn(A,S,B), where S is a 3-by-1 structure array with the values:

Related Examples

"Specialize Subscripted Assignment — subsasgn"

Object end Indexing

In this section...

"Define end Indexing for an Object" on page 16-25

"The end Method" on page 16-26

Define end Indexing for an Object

When you use end in an object indexing expression, such as A(4:end), the end function returns the index value corresponding to the last element in that dimension.

Classes can overload the end function to implement specialized behavior. If your class defines an end method, MATLAB calls that method to determine how to interpret the expression.

The end method has the calling syntax:

```
ind = end(A,k,n)
```

The arguments are described as follows:

- · A is the object
- k is the index in the expression using the end syntax
- n is the total number of indices in the expression
- ind is the index value to use in the expression

For example, consider the expression

```
A(end-1,:)
```

MATLAB calls the end method defined for the object A using the arguments

```
ind = end(A,1,2)
```

These arguments mean the end statement occurs in the first index element and there are two index elements. The end class method returns the index value for the last element of the first dimension (from which 1 is subtracted in this case). If your class implements an end method, ensure that it returns a value appropriate for the class.

The end Method

The end method for the MyDataClass example (see "Class with Modified Indexing") operates on the contents of the Data property. The objective of this method is to return a value that can replace end in any indexing expression, such as:

```
obj(4:end)
obj.Data(2,3:end)
```

This end method determines a positive integer value for end. The method returns the value so that MATLAB can use it in the indexing expression.

```
function ind = end(obj,k,n)
   szd = size(obj.Data);
   if k < n
        ind = szd(k);
   else
        ind = prod(szd(k:end));
   end
end</pre>
```

Related Examples

- "Class with Modified Indexing" on page 16-29
- · "Objects In Index Expressions" on page 16-27

Objects In Index Expressions

In this section...

"Using Objects as Indices" on page 16-27

"Scenarios for Implementing Objects as Indices" on page 16-27

"subsindex Implementation" on page 16-28

Using Objects as Indices

MATLAB can use objects as indices in indexed expressions. The rules of array indexing apply — indices must be positive integers. Therefore, MATLAB must be able to derive a value from the object that is a positive integer. MATLAB uses the positive integer in the indexed expression.

Indexing expressions like X(A), where A is an object, cause MATLAB to call the default subsindex function. However, if an indexing expression results in a call to an overloaded subsref or subsasgn method defined by the class of X, then MATLAB does not callsubsindex.

subsindex must return the value of the object as a zero-based integer index values in the range 0 to prod(size(X))-1.

Scenarios for Implementing Objects as Indices

If you want to enable indexing of one object by another object, such as X(A), you can implement this behavior in various ways:

- Define a subsindex method in the class of A, which converts A to an integer.
 MATLAB calls A's subsindex method to perform indexing operations, when the class of X does not overload the default subsref or subsasgn method.
- If the class of X overloads subsref or subsasgn, these methods can call the subsindex method of A explicitly. In this case, ensure that A implements a subsindex method with appropriate error checking in your program.
- If the class of X overloads subsref or subsasgn, these methods can contain code that
 determines an integer index value without relying on the class of A to implement a
 subsindex method.

subsindex Implementation

MATLAB calls the subsindex method defined for the object used as the index. For example, suppose you want to use object A to index into object B. B can be a single object or an array, depending on the class designs.

```
C = B(A);
```

Here are two examples of subsindex methods. The first assumes you can convert class A to a uint8. The second assumes class A stores an index value in a property.

The subsindex method implemented by class A can convert the object to double format to be used as an index:

```
function ind = subsindex(obj)
  ind = uint8(obj);
end
```

Class A can implement a method that returns a numeric value that is stored in a property:

```
function ind = subsindex(obj)
  ind = obj.ElementPosition;
end
```

Note: subsindex values are 0-based, not 1-based.

Related Examples

• "Object end Indexing" on page 16-25

Class with Modified Indexing

In this section...

"Modify Class Indexing" on page 16-29

"Class Description" on page 16-29

"Specialize Subscripted Reference — subsref" on page 16-31

"Specialize Subscripted Assignment — subsasgn" on page 16-31

"Implementing Addition for Object Data — double and plus" on page 16-32

"MyDataClass.m" on page 16-34

Modify Class Indexing

This example defines a class that modifies the default indexing behavior by implementing subsref and subsasgn methods. The class also implements type conversion and addition by implementing a double converter method and a plus method.

The objective of the class design is to:

- · Enable you to treat an object of the class as a numeric array
- · Be able to contain nonnumeric and numeric data in an object of the class

Class Description

The class has three properties:

- Data numeric test data
- · Description description of test data
- Date date test was conducted

Assume you have the following data (randi):

```
2 1 9 9
```

Create an instance of the class:

The constructor arguments pass the values for the Data and Description properties. The clock function assigns the value to the Date property from within the constructor. This approach captures the time and date information when the instance is created.

Here is the preliminary code listing without the subsref, subsasgn double, and plus methods.

```
classdef MyDataClass
   properties
      Data
      Description
   properties (SetAccess = private)
      Date
   end
   methods
      function obj = MyDataClass(data,desc)
         if nargin > 0
            obj.Data = data;
         end
         if nargin > 1
            obj.Description = desc;
         obj.Date = clock;
      end
   end
end
```

This class does not implement a fully robust class. For example, you cannot concatenate objects into an array without adding other methods, such as horzcat, vertcat, cat, size, and enhancements to subsref and subsasin. methods.

Specialize Subscripted Reference — subsref

Implement a subsref method to support both the default indexed reference behavior for scalar objects:

And add the functionality to index into the Data property with an expression like this:

```
obj(2,3)
```

Redefining '()' indexing means you cannot create arrays of MyDataClass objects and use '()' indexing to access individual objects. You can reference only scalar objects.

To achieve the design goals, the subsref method calls the builtin subsref function for '.' type indexing and defines its own version of '()' type indexing.

The result: obj(i) is equivalent to obj.Data(i).

```
function sref = subsref(obj,s)
   % obj(i) is equivalent to obj.Data(i)
   switch s(1).type
      case '.'
         sref = builtin('subsref',obj,s);
      case '()'
         if length(s) < 2
            sref = builtin('subsref',obj.Data,s);
            return
         else
            sref = builtin('subsref',obj,s);
         end
      case '{}'
         error('MYDataClass:subsref',...
            'Not a supported subscripted reference')
   end
end
```

Specialize Subscripted Assignment — subsasgn

Implement a subsasgn method to support the equivalent of the indexed reference behavior with indexed assignment. Support the default indexed assignment:

```
obj.Data(2,3) = 9;
```

And add the functionality to assign values to the Data property with an expression like this:

```
obj(2,3) = 9;
```

Like the subsref method, the subsasgn method calls the builtin subsasgn function for '.' type indexing and defines its own version of '()' type indexing.

The substruct function redefines the index type and index subscripts structure that MATLAB passes to subsref and subsasgn.

```
function obj = subsasgn(obj,s,val)
   if isempty(s) && isa(val, 'MyDataClass')
      obj = MyDataClass(val.Data,val.Description);
   end
   switch s(1).type
      case '.
         obj = builtin('subsasgn',obj,s,val);
      case '()'
         if length(s)<2
            if isa(val, 'MyDataClass')
               error('MyDataClass:subsasgn',...
                   'Object must be scalar')
            elseif isa(val, 'double')
               % Redefine the struct s to make the call: obj.Data(i)
               snew = substruct('.', 'Data', '()',s(1).subs(:));
               obj = subsasgn(obj,snew,val);
            end
         end
      case '{}'
         error('MyDataClass:subsasgn',...
            'Not a supported subscripted assignment')
   end
end
```

Implementing Addition for Object Data — double and plus

First, implement a double method that converts an object to an array of doubles. By implementing a double converter method, it is possible to add a MyDataClass object to another class of object, providing the other class implements a double method that also returns an array of doubles. For more information on type conversion, see "Object Converters" on page 16-8.

Allow direct addition of the Data property values by implementing a plus method. Implementing a plus method enables the use of the + operator for addition of MyDataClass objects.

Because the plus method implements addition by adding double arrays, MATLAB:

- Apply the rules of addition when adding MyDataClass objects
- Returns errors for any condition that can cause errors in default numeric addition. For example, dimension mismatch, and so on.

The plus method uses the double method to convert the object to numeric values before performing the addition:

```
function a = double(obj)
   a = obj.Data;
end

function c = plus(obj,b)
   c = double(obj) + double(b);
end
```

For example, the plus method enables you to add a scalar number to the object Data array.

Here are the values of the Data, displayed using indexed reference:

```
obj(:,:)
ans =

    8     9     3     9
    9     6     9     2
    2     1     9     9
```

Add 7 to the array contained in the Data property:

```
obj + 7

ans =

15     16     10     16
     16     13     16     9
     9     8     16     16
```

MyDataClass.m

This definition for MyDataClass includes the end indexing method discussed in "Object end Indexing" on page 16-25.

```
classdef MyDataClass
   % Example for "A Class with Modified Indexing"
   properties
      Data
      Description
   properties (SetAccess = private)
   end
   methods
      function obj = MyDataClass(data,desc)
         % Support 0-2 args
         if nargin > 0
            obj.Data = data;
         end
         if nargin > 1
            obj.Description = desc;
         obj.Date = clock;
      end
      function sref = subsref(obj,s)
         % obj(i) is equivalent to obj.Data(i)
         switch s(1).type
            case '.'
               sref = builtin('subsref',obj,s);
            case '()'
               if length(s)<2</pre>
                   sref = builtin('subsref',obj.Data,s);
               else
                   sref = builtin('subsref',obj,s);
               end
            case '{}'
               error('MyDataClass:subsref',...
                   'Not a supported subscripted reference')
         end
      end
```

```
function obj = subsasgn(obj,s,val)
         if isempty(s) && isa(val, 'MyDataClass')
            obj = MyDataClass(val.Data,val.Description);
         end
         switch s(1).type
            case '.'
               obj = builtin('subsasgn',obj,s,val);
            case '()'
               if length(s)<2</pre>
                   if isa(val,'MyDataClass')
                      error('MyDataClass:subsasgn',...
                         'Object must be scalar')
                   elseif isa(val, 'double')
                      snew = substruct('.', 'Data', '()',s(1).subs(:));
                      obj = subsasgn(obj,snew,val);
                   end
               end
            case '{}'
               error('MyDataClass:subsasgn',...
                   'Not a supported subscripted assignment')
         end
      end
      function a = double(obj)
         a = obj.Data;
      end
      function c = plus(obj,b)
         c = double(obj) + double(b);
      end
      function ind = end(obj,k,n)
         szd = size(obj.Data);
         if k < n
            ind = szd(k);
         else
            ind = prod(szd(k:end));
         end
      end
   end
end
```

Related Examples

- "Object end Indexing" on page 16-25
- "Built-In Subclass With Properties"

Class Operator Implementations

In this section...

"Defining Operators" on page 16-37

"MATLAB Operators and Associated Functions" on page 16-37

Defining Operators

You can implement MATLAB operators (+, *, >, etc.) to work with objects of your class. Do this by defining the associated class methods.

Each operator has an associated function (e.g., the + operator has an associated plus.m function). You can implement any operator by creating a class method with the appropriate name. This method can perform whatever steps are appropriate for the operation being implemented.

Object Precedence in Operations

User-defined classes have a higher precedence than built-in classes. For example, if **q** is an object of class **double** and **p** is a user-defined class, MyClass, both of these expressions:

$$q + p$$

 $p + q$

generate a call to the plus method in the MyClass, if it exists. Whether this method can add objects of class double and class MyClass depends on how you implement it.

When p and q are objects of different classes, MATLAB applies the rules of precedence to determine which method to use.

"Object Precedence in Methods" provides information on how MATLAB determines which method to call.

MATLAB Operators and Associated Functions

The following table lists the function names for MATLAB operators. Implementing operators to work with arrays (scalar expansion, vectorized arithmetic operations, and so on), might also require modifying indexing and concatenation.

0	Method to Define	Description	
Operation		Description	
a + b	plus(a,b)	Binary addition	
a - b	minus(a,b)	Binary subtraction	
-a	uminus(a)	Unary minus	
+a	uplus(a)	Unary plus	
a.*b	times(a,b)	Element-wise multiplication	
a*b	<pre>mtimes(a,b)</pre>	Matrix multiplication	
a./b	rdivide(a,b)	Right element-wise division	
a.\b	ldivide(a,b)	Left element-wise division	
a/b	mrdivide(a,b)	Matrix right division	
a\b	mldivide(a,b)	Matrix left division	
a.^b	power(a,b)	Element-wise power	
a^b	mpower(a,b)	Matrix power	
a < b	lt(a,b)	Less than	
a > b	gt(a,b)	Greater than	
a <= b	le(a,b)	Less than or equal to	
a >= b	ge(a,b)	Greater than or equal to	
a ~= b	ne(a,b)	Not equal to	
a == b	eq(a,b)	Equality	
a & b	and(a,b)	Logical AND	
a b	or(a,b)	Logical OR	
~a	not(a)	Logical NOT	
a:d:b	colon(a,d,b)	Colon operator	
a:b	colon(a,b)		
a'	ctranspose(a)	Complex conjugate transpose	
a.'	transpose(a)	Matrix transpose	
command window output	display(a)	Display method	
[a b]	horzcat(a,b,)	Horizontal concatenation	
[a; b]	vertcat(a,b,)	Vertical concatenation	

Operation	Method to Define	Description
a(s1,s2,sn)	subsref(a,s)	Subscripted reference
a(s1,,sn) = b	subsasgn(a,s,b)	Subscripted assignment
b(a)	subsindex(a)	Subscript index

Related Examples

• "Define Arithmetic Operators"

Customizing Object Display

- "Custom Display Interface" on page 17-2
- "How CustomDisplay Works" on page 17-7
- "Role of size Function in Custom Displays" on page 17-9
- "Customize Display for Heterogeneous Arrays" on page 17-10
- "Class with Default Object Display" on page 17-12
- "Choose a Technique for Display Customization" on page 17-16
- "Customize Property Display" on page 17-19
- "Customize Header, Property List, and Footer" on page 17-22
- "Customize Display of Scalar Objects" on page 17-28
- "Customize Display of Object Arrays" on page 17-32
- "Overload the disp Function" on page 17-37

Custom Display Interface

In this section...

"Default Object Display" on page 17-2

"CustomDisplay Class" on page 17-3

"Methods for Customizing Object Display" on page 17-3

Default Object Display

MATLAB adds default methods named disp and display to all MATLAB classes that do not implement their own methods with those names. These methods are not visible, but create the default simple display.

The default simple display consists of the following parts:

- · A header showing the class name, and the dimensions for nonscalar arrays.
- · A list of all nonhidden public properties, shown in the order of definition in the class.

The actual display depends on whether the object is scalar or nonscalar. Also, there are special displays for a scalar handle to a deleted object and empty object arrays. Objects in all of these states are displayed differently if the objects have no properties.

The details method creates the default detailed display. The detailed display adds these items to the simple display:

- Use of fully qualified class names
- · Link to handle class, if the object is a handle
- · Links to methods, events, and superclasses functions executed on the object.

See "Class with Default Object Display" on page 17-12 for an example of how MATLAB displays objects.

Properties Displayed by Default

MATLAB displays object properties that have public get access and are not hidden (see "Property Attributes" on page 7-7). Inherited abstract properties are excluded from

display. When the object being displayed is scalar, any dynamic properties attached to the object are also included.

CustomDisplay Class

The matlab.mixin.CustomDisplay class provides an interface that you can use to customize object display for your class. To use this interface, derive your class from CustomDisplay:

classdef MyClass < matlab.mixin.CustomDisplay</pre>

The CustomDisplay class is HandleCompatibile, so you can use it in combination with both value and handle superclasses.

Note: You cannot use matlab.mixin.CustomDisplay to derive a custom display for enumeration classes.

disp, display, and details

The CustomDisplay class defines three sealed public methods. These methods overload three MATLAB functions: disp, display, and details. The disp and display methods behave like the equivalent MATLAB functions, but use the customizations defined by classes derived from CustomDisplay.

The details method always uses the default detailed object display and does not apply customizations defined for the class.

The CustomDisplay interface does not allow you to override disp and display. Instead, override any combination of the customization methods defined for this purpose.

Methods for Customizing Object Display

There are two groups of methods that you use to customize object display for your class:

- *Part builder methods* build the strings used for the standard display. Override any of these methods to change the respective parts of the display.
- *State handler methods* are called for objects in specific states, like scalar, nonscalar, and so on. Override any of these methods to handle objects in a specific state.

All of these methods have protected access and must be defined as protected in your subclass of CustomDisplay (that is, Access = protected).

Parts of an Object Display

There are three parts that makeup the standard object display — header, property list, and footer

For example, here is the standard object display for a containers. Map object:

```
>> map1 = containers.Map({'Apr', 'Jul', 'Nov'}, [4,7,11])

map1 =

Map with properties: Header

Count: 3

KeyType: char
ValueType: double

Property List
```

The default object display does not include a footer. The detailed display provides more information:

```
>> details(map1)

3x1 containers.Map handle array with properties:

Count: 3
KeyType: 'char'
ValueType: 'double'

Methods, Events, Superclasses Footer
```

Part Builder Methods

Each part of the object display has an associated method that assembles the respective part of the display.

Method	Purpose	Default
getHeader	Create the string used for the header.	Returns the string, [class(obj), 'with properties:'] linking the class name to a help popup
getPropertyGroup	Define how and what properties display, including order, values, and grouping.	Returns an array of PropertyGroup objects, which determines how to display the properties
getFooter	Create the string used for the footer.	 There are two footers: Simple display — Returns an empty string Detailed display — Returns linked calls to methods, events, and superclasses for this class

Object States That Affect Display

There are four object states that affect how MATLAB displays objects:

- · Valid scalar object
- · Nonscalar object array
- Empty object array
- · Scalar handle to a deleted object

State Handler Methods

Each object state has an associated method that MATLAB calls whenever displaying objects that are in that particular state.

State Handler Method	Called for Object in This State
displayScalarObject	<pre>(isa(obj, 'handle') && isvalid(obj)) && prod(size(obj)) == 1</pre>
displayNonScalarObject	prod(size(obj)) > 1
displayEmptyObject	prod(size(obj)) == 0
displayScalarHandleToDeletedObject	isa(obj, 'handle') && isscalar(obj) && ~isvalid(obj)

Utility Methods

The CustomDisplay class provides utility methods that return strings that are used in various parts of the different display options. These static methods return text that simplifies the creation of customized object displays.

If the computer display does not support hypertext linking, the strings are returned without the links.

Method	Inputs	Outputs
convertDimensionsToString	Valid object array	Object dimensions converted to a string; determined by calling size(obj)
displayPropertyGroups	PropertyGroup array	Displays the titles and property groups defined
getClassNameForHeader	Object	Simple class name linked to the object's documentation
getDeletedHandleText	None	String'handle to deleted' linked to the documentation on deleted handles
getDetailedFooter	Object	String containing phrase 'Methods, Events, Superclasses', with each link executing the respective command on the input object
getDetailedHeader	Object	String containing linked class name, link to handle page (if handle class) and 'with properties:'
getHandleText	None	String 'handle' linked to a section of the documentation that describes handle objects
getSimpleHeader	Object	String containing linked class name and the phrase 'with properties:'

How CustomDisplay Works

In this section... "Steps to Display an Object" on page 17-7 "Methods Called for a Given Object State" on page 17-8

Steps to Display an Object

When displaying an object, MATLAB determines the state of the object and calls the appropriate method for that state (see "Object States That Affect Display" on page 17-5).

For example, suppose obj is a valid scalar object of a class derived from CustomDisplay. If you type obj at the command line without terminating the statement with a semicolon:

```
>> obi
```

The following sequence results in the display of obj:

- 1 MATLAB determines the class of obj and calls the disp method to display the object.
- 2 disp calls size to determine if obj is scalar or nonscalar
- **3** When obj is a scalar handle object, disp calls isvalid to determine if obj is the handle of a deleted object. Deleted handles in nonscalar arrays do not affect the display.
- disp calls the state handler method for an object of the state of obj. In this case, obj is a valid scalar that results in a call to:

```
displayScalarObject(obj)
```

5 displayScalarObject calls the display part-builder methods to provide the respective header, property list, and footer.

```
header = getHeader(obj);
disp(header)
...
groups = getPropertyGroups(obj)
displayPropertyGroups(obj,groups)
...
footer = getFooter
```

disp(footer)


MATLAB follows a similar sequence for nonscalar object arrays and empty object arrays.

In the case of scalar handles to deleted objects, disp calls the displayScalarHandleToDeletedObject method, which displays the default string for handles to deleted objects without calling any part-builder methods.

Methods Called for a Given Object State

The following diagram illustrates the methods called to display an object that derives from CustomDisplay. The disp method calls the state handler method that is appropriate for the state of the object or object array being displayed.

Only an instance of a handle class can be in a state of scalar handle to a deleted object.



Role of size Function in Custom Displays

In this section...

"How size Is Used" on page 17-9

"Precautions When Overloading size" on page 17-9

How size Is Used

In the process of building the custom display, **CustomDisplay** methods call the **size** function at several points:

- disp calls size to determine which state handler method to invoke.
- The default getHeader method calls size to determine whether to display a scalar or nonscalar header.
- The default displayPropertyGroups method calls size to determine if it should look up property values when the property group is a cell array of property names. By default, only scalar objects display the values of properties.

Precautions When Overloading size

If your class overloads the Size function, then MATLAB calls the overloading version. You must ensure that the implementation of Size is consistent with the way you want to display objects of the class.

An unusual or improper implementation of Size can result in undesirable display behavior. For example, suppose a class overloads Size reports an object as scalar when it is not. In this class, a property list consisting of a cell array of strings results in the property values of the first object of the array being displayed. This behavior can give the impression that all objects in the array have the same property values.

However, reporting an object as scalar when in fact the object is empty results in the object displaying as an empty object array. The default methods of the CustomDisplay interface always determine if the input is an empty array before attempting to access property values.

As you override CustomDisplay methods to implement your custom object display, consider how an overloading size method can affect the result.

Customize Display for Heterogeneous Arrays

You can call only sealed methods on nonscalar heterogeneous arrays. If you want to customize classes that are part of a heterogeneous hierarchy, you must override and declare as Sealed all the methods that are part of the CustomDisplay interface.

The versions of disp and display that are inherited from matlab.mixin.CustomDisplay are sealed. However, these methods call all of the part builder ("Part Builder Methods" on page 17-4) and state handler methods ("State Handler Methods" on page 17-5).

To use the CustomDisplay interface, the root class of the heterogeneous hierarchy can declare these methods as Sealed and Access = protected.

If you do not need to override a particular method, then call the superclass method, as shown in the following code.

For example, the following code shows modifications to the getPropertyGroups and displayScalarObject methods, while using the superclass implementation of all others.

```
classdef RootClass < matlab.mixin.CustomDisplay & matlab.mixin.Heterogeneous</pre>
   methods (Sealed, Access = protected)
      function header = getHeader(obj)
         header = getHeader@matlab.mixin.CustomDisplay(obj);
      function groups = getPropertyGroups(obj)
         % Override of this method
         % ...
      end
      function footer = getFooter(obj)
         footer = getFooter@matlab.mixin.CustomDisplay(obj);
      end
      function displayNonScalarObject(obj)
         displayNonScalarObject@matlab.mixin.CustomDisplay(obj);
      end
      function displayScalarObject(obj)
         % Override of this method
         % ...
      end
      function displayEmptyObject(obj)
         displayEmptyObject@matlab.mixin.CustomDisplay(obj);
```

```
end
function displayScalarHandleToDeletedObject(obj)
         displayScalarHandleToDeletedObject@matlab.mixin.CustomDisplay(obj);
    end
end
end
```

You do not need to declare the inherited static methods as Sealed.

Class with Default Object Display

```
In this section...

"The EmployeeInfo Class" on page 17-12

"Default Display — Scalar" on page 17-13

"Default Display — Nonscalar" on page 17-13

"Default Display — Empty Object Array" on page 17-14

"Default Display — Handle to Deleted Object" on page 17-15

"Default Display — Detailed Display" on page 17-15
```

The EmployeeInfo Class

The EmployeeInfo class defines a number of properties to store information about company employees. This simple class serves as the example class used in display customization sample classes.

EmployeeInfo derives from the matlab.mixin.CustomDisplay class to enable customization of the object display.

EmployeeInfo is also a handle class. Therefore instances of this class can be in the state referred to as a handle to a deleted object. This state does not occur with value classes (classes not derived from handle).

```
classdef EmployeeInfo < handle & matlab.mixin.CustomDisplay</pre>
   properties
      Name
      JobTitle
      Department
      Salary
      Password
   end
   methods
      function obj = EmployeeInfo
         obj.Name
                        = input('Name: ');
         obj.JobTitle = input('Job Title: ');
         obj.Department = input('Department: ');
                        = input('Salary: ');
         obj.Salary
                        = input('Password: ');
         obi.Password
      end
```

```
end
end
```

The matlab.mixin.CustomDisplay is handle compatible. Therefore, superclasses can be either handle or value classes.

Default Display — Scalar

Here is the creation and display of a scalar EmployeeInfo object. By default, MATLAB displays properties and their values for scalar objects.

Provide inputs for the constructor:

Testing for Scalar Objects

To test for scalar objects, use isscalar.

Default Display — Nonscalar

The default display for an array of objects does not show property values. For example, concatenating two EmployeeInfo objects generates this display:

```
>>[Emp123,Emp124]
ans

1x2 EmployeeInfo array with properties:

Name
    JobTitle
    Department
    Salary
    Password
```

Testing for Nonscalar Objects

To test for nonscalar objects, use a negated call to isscalar.

Default Display — Empty Object Array

An empty object array has at least one dimension equal to zero.

Testing for Empty Object Arrays

Use isempty to test for empty object arrays. An empty object array is not scalar because its dimensions can never be 1-by-1.

```
>> emt = EmployeeInfo.empty
emt =
   Ox0 EmployeeInfo array with properties:
   Name
   JobTitle
```

```
Department
Salary
Password
>> isscalar(emt)
ans =
0
```

Default Display — Handle to Deleted Object

When a handle object is deleted, the handle variable can remain in the workspace.

```
>> delete(Emp123)
>> Emp123
Emp123 =
  handle to deleted EmployeeInfo
```

Testing for Handles to Deleted Objects

To test for a handle to a deleted object, use isvalid.

Note: isvalid is a handle class method. Calling isvalid on a value class object causes an error.

Default Display — Detailed Display

The details method does not support customization and always returns the standard detailed display:

```
details(Emp123)
EmployeeInfo handle with properties:

Name: 'Bill Tork'
JobTitle: 'Software Engineer'
Department: 'Product Development'
Salary: 1000
Password: 'bill123'

Methods, Events, Superclasses
```

Choose a Technique for Display Customization

In this section...

"Ways to Implement a Custom Display" on page 17-16

"Sample Approaches Using the Interface" on page 17-17

Ways to Implement a Custom Display

How you customize object display for your class depends on what parts of the display you want to customize and what object states you want to use a custom display.

In general, if you are making small changes to the default layout, then override the relevant part builder methods ("Part Builder Methods" on page 17-4). For example, suppose you want to:

- Change the order or value of properties, display a subset of properties, or create property groups
- Modify the header string
- Add a footer

If you are defining a nonstandard display for a particular object state (scalar, for example), then the best approach is to override the appropriate state handler method ("State Handler Methods" on page 17-5).

In some cases, a combination of method overrides might be the best approach. For example, your implementation of displayScalarObject might

- Use some of the utility methods ("Utility Methods" on page 17-6) to build your own display strings using parts from the default display
- Call a part builder method to get the default string for that particular part of the display
- Implement a completely different display for scalar objects.

Once you override any CustomDisplay method, your override is called in all cases where the superclass method would have been called. For example, if you override the getHeader method, your override must handle all cases where a state handler method calls getHeader. (See "Methods Called for a Given Object State" on page 17-8)

Sample Approaches Using the Interface

Here are some simple cases that show what methods to use for the particular customized display.

Change the Display of Scalar Objects

Use a nonstandard layout for scalar object display that is fully defined in the displayScalarObject method:

```
classdef MyClass < matlab.mixin.CustomDisplay
    ...
    methods (Access = protected)
        function displayScalarObject(obj)
        % Implement the custom display for scalar object
    end
end
end</pre>
```

Custom Property List with Standard Layout

Use standard display layout, but create a custom property list for scalar and nonscalar display:

```
classdef MyClass < matlab.mixin.CustomDisplay
   ...
  methods(Access = protected)
     function groups = getPropertyGroups(obj)
     % Return PropertyGroup instances
    end
  end
end</pre>
```

Custom Property List for Scalar Only

Use standard display layout, but create a custom property list for scalar only. Call the superclass getPropertyGroups for the nonscalar case.

```
classdef MyClass < matlab.mixin.CustomDisplay
    properties
        Prop1
        Prop2
        Prop3
    end
    methods(Access = protected)
        function groups = getPropertyGroups(obj)</pre>
```

```
if isscalar(obj)
    % Scalar case: change order
    propList = {'Prop2','Prop1','Prop3'};
    groups = matlab.mixin.util.PropertyGroup(propList)
    else
        % Nonscalar case: call superclass method
        groups = getPropertyGroups@matlab.mixin.CustomDisplay(obj);
    end
    end
end
end
```

Custom Property List with Modified Values

Change the values displayed for some properties in the scalar case by creating property/value pairs in a struct. This getPropertyGroups method displays only Prop1 and Prop2, and displays the value of Prop2 as Prop1 divided by Prop3.

```
classdef MyClass < matlab.mixin.CustomDisplay</pre>
   properties
      Prop1
      Prop2
      Prop3
   methods(Access = protected)
      function groups = getPropertyGroups(obj)
         if isscalar(obj)
            % Specify the values to be displayed for properties
            propList = struct('Prop1',obj.Prop1,...
                'Prop2',obj.Prop1/obj.Prop3);
            groups = matlab.mixin.util.PropertyGroup(propList)
            % Nonscalar case: call superclass method
            groups = getPropertyGroups@matlab.mixin.CustomDisplay(obj);
      end
   end
end
```

Complete Class Definitions

For complete class implementations, see these sections:

• "Customize Property Display" on page 17-19

"Customize Header, Property List, and Footer" on page 17-22

"Customize Display of Scalar Objects" on page 17-28

"Customize Display of Object Arrays" on page 17-32

Customize Property Display

This example shows how to change the order and number of properties displayed for an object of your class.

```
In this section...

"Change the Property Order" on page 17-19

"Change the Values Displayed for Properties" on page 17-20
```

Change the Property Order

Suppose your class definition contains the following property definition:

```
properties
Name
JobTitle
Department
Salary
Password
end
```

In the default scalar object display, MATLAB displays all the public properties along with their values. However, you want to display only Department, JobTitle, and Name, in that order. You can do this by deriving from CustomDisplay and overriding the getPropertyGroups method.

Your override

- Defines method Access as protected to match the definition in the CustomDisplay superclass
- Creates a cell array of property names in the desired order
- Returns a PropertyGroup object constructed from the property list cell array

```
methods (Access = protected)
  function propgrp = getPropertyGroups(-)
    proplist = {'Department', 'JobTitle', 'Name'};
    propgrp = matlab.mixin.util.PropertyGroup(proplist);
  end
end
```

When you create a **PropertyGroup** object using a cell array of property names, MATLAB automatically

- Adds the property values for a scalar object display
- Uses the property names without values for a nonscalar object display (including empty object arrays)

The getPropertyGroups method is not called to create the display for a scalar handle to a deleted object.

Change the Values Displayed for Properties

Given the same class properties used in the previous section, you can change the value displayed for properties by building the property list as a struct and specifying values for property names. This override of the getPropertyGroups method uses the default property display for nonscalar objects by calling the superclass getPropertyGroups method. For scalar objects, the override:

- Changes the value displayed for the Password property to a '*' character for each character in the password string.
- Displays the string 'Not Available' for the Salary property.

The object display looks like this:

EmployeeInfo with properties:

```
Department: 'Product Development'
JobTitle: 'Software Engineer'
Name: 'Bill Tork'
Salary: 'Not available'
Password: '******'
```

Full Class Listing

```
classdef EmployeeInfo < handle & matlab.mixin.CustomDisplay</pre>
   properties
      Name
       JobTitle
      Department
      Salary
      Password
   end
   methods
       function obj = EmployeeInfo
                           = input('Name: ');
          obj.Name
          obj.JobTitle = input('Job Title: ');
obj.Department = input('Department: ');
          obj.Salary = input('Salary: ');
obj.Password = input('Password: ');
      end
   end
   methods (Access = protected)
       function propgrp = getPropertyGroups(obj)
          if ~isscalar(obj)
             propgrp = getPropertyGroups@matlab.mixin.CustomDisplay(obj);
          else
             pd(1:length(obj.Password)) = '*';
             propList = struct('Department',obj.Department,...
                  'JobTitle',obj.JobTitle,...
                 'Name',obj.Name,...
                 'Salary','Not avalable',...
'Password',pd);
             propgrp = matlab.mixin.util.PropertyGroup(propList);
          end
       end
   end
```

Customize Header, Property List, and Footer

This example shows how to customize each of the three parts of the display.

In this section...

"Design of Custom Display" on page 17-22

"getHeader Method Override" on page 17-24

"getPropertyGroups Override" on page 17-25

"getFooter Override" on page 17-25

Design of Custom Display

Note: This example uses the EmployeeInfo class described in the "Class with Default Object Display" on page 17-12 section.

For the header:

- Use default header for nonscalar object arrays.
- Build header string with linked class name and department name (from Department property)

For properties:

- Nonscalar object arrays display a subset of property names in a different order than the default.
- Scalar objects create two property groups that have titles (Public Info and Personal Info).

For the footer:

 Add a footer to the display, only when the object is a valid scalar that displays property values.

Here is the customized display of an object of the EmployeeInfo class.

Emp123 =

```
EmployeeInfo Dept: Product Development
   Public Info
        Name: 'Bill Tork'
    JobTitle: 'Software Engineer'
   Personal Info
      Salary: 1000
    Password: 'bill123'
Company Private
Here is the custom display of an array of EmployeeInfo objects:
[Emp123, Emp124]
ans =
  1x2 EmployeeInfo array with properties:
    Department
    Name
    JobTitle
Here is the display of an empty object array:
>> EmployeeInfo.empty(0,5)
ans =
  0x5 EmployeeInfo array with properties:
    Department
    Name
    JobTitle
Here is the display of a handle to a delete object (EmployeeInfo is a handle class):
>> delete(Emp123)
>> Emp123
Emp123 =
  handle to deleted EmployeeInfo
```

Implementation

The EmployeeInfo class overrides three matlab.mixin.CustomDisplay methods to implement the display shown:

- getHeader
- getPropertyGroups
- getFooter

Each method must produce the desired results with each of the following inputs:

- Scalar object
- Nonscalar object array
- Empty object array

getHeader Method Override

MATLAB calls getHeader to get the header string. The EmployeeInfo class overrides this method to implement the custom header for scalar display. Here is how it works:

- Nonscalar (including empty object) arrays call the superclass getHeader, which returns the default header.
- Scalar handles to deleted objects do not result in a call to getHeader.
- Scalar inputs build a custom header using the getClassNameForHeader static method to return a linked class name string, and the value of the Department property.

Here is the EmployeeInfo override of the getHeader method. The required protected access is inherited from the superclass.

```
methods (Access = protected)
  function header = getHeader(obj)
    if ~isscalar(obj)
     header = getHeader@matlab.mixin.CustomDisplay(obj);
    else
        className = matlab.mixin.CustomDisplay.getClassNameForHeader(obj);
        newHeader = [className, ' Dept: ',obj.Department];
        header = sprintf('%s\n',newHeader);
    end
end
```

getPropertyGroups Override

MATLAB calls getPropertyGroups to get the PropertyGroup objects, which control how properties are displayed. This method override defines two different property lists depending on the object's state:

• For nonscalar inputs, including empty arrays and arrays containing handles to deleted objects, create a property list as a cell array to reorder properties.

By default, MATLAB does not display property values for nonscalar inputs.

- For scalar inputs, create two property groups with titles. The scalar code branch lists properties in a different order than the nonscalar case and includes Salary and Password properties. MATLAB automatically assigns property values.
- Scalar handles to deleted objects do not result in a call to getPropertyGroups.

Both branches return a matlab.mixin.util.PropertyGroup object, which determines how to displays the object properties.

Here is the EmployeeInfo override of the getPropertyGroups method. The protected access is inherited from the superclass.

```
methods (Access = protected)
  function propgrp = getPropertyGroups(obj)
    if -isscalar(obj)
        propList = {'Department','Name','JobTitle'};
        propgrp = matlab.mixin.util.PropertyGroup(propList);
    else
        gTitle1 = 'Public Info';
        gTitle2 = 'Personal Info';
        propList1 = {'Name','JobTitle'};
        propList2 = {'Salary','Password'};
        propgrp(1) = matlab.mixin.util.PropertyGroup(propList1,gTitle1);
        propgrp(2) = matlab.mixin.util.PropertyGroup(propList2,gTitle2);
    end
    end
end
```

getFooter Override

MATLAB calls getFooter to get the footer string. The EmployeeInfo getFooter method defines a footer for the display, which is included only when the input is a valid scalar object. In all other cases, getFooter returns an empty string.

Scalar handles to deleted objects do not result in a call to getFooter.

```
methods (Access = protected)
  function footer = getFooter(obj)
    if isscalar(obj)
      footer = sprintf('%s\n','Company Private');
  else
      footer = '';
  end
  end
end
```

Complete Class Listing

```
classdef EmployeeInfo < handle & matlab.mixin.CustomDisplay</pre>
   properties
      Name
      JobTitle
      Department
      Salary
      Password
   end
   methods
      function obj = EmployeeInfo
         obj.Name
                       = input('Name: ');
         obj.JobTitle = input('Job Title: ');
         obj.Department = input('Department: ');
                     = input('Salary: ');
         obj.Salary
         obj.Password = input('Password: ');
      end
   end
   methods (Access = protected)
      function header = getHeader(obj)
         if ~isscalar(obj)
            header = getHeader@matlab.mixin.CustomDisplay(obj);
         else
            className = matlab.mixin.CustomDisplay.getClassNameForHeader(obj);
            newHeader = [className, 'Dept: ',obj.Department];
            header = sprintf('%s\n',newHeader);
         end
      end
      function propgrp = getPropertyGroups(obj)
         if ~isscalar(obj)
            propList = {'Department', 'Name', 'JobTitle'};
            propgrp = matlab.mixin.util.PropertyGroup(propList);
         else
            gTitle1 = 'Public Info';
            gTitle2 = 'Personal Info';
            propList1 = {'Name', 'JobTitle'};
            propList2 = {'Salary', 'Password'};
            propgrp(1) = matlab.mixin.util.PropertyGroup(propList1,gTitle1);
            propgrp(2) = matlab.mixin.util.PropertyGroup(propList2,gTitle2);
         end
```

```
end

function footer = getFooter(obj)
    if isscalar(obj)
        footer = sprintf('%s\n','Company Private');
    else
        footer = '';
    end
    end
end
end
```

Customize Display of Scalar Objects

This example shows how to customize the display of scalar objects.

```
In this section...

"Design Of Custom Display" on page 17-28

"displayScalarObject Method Override" on page 17-29

"getPropertyGroups Override" on page 17-30
```

Design Of Custom Display

Note: This example uses the EmployeeInfo class described in the "Class with Default Object Display" on page 17-12 section.

The objective of this customized display is to:

- Modify the header to include the department name obtained from the Department property
- · Group properties into two categories titled Public Info and Personal Info.
- · Modify which properties are displayed
- · Modify the values displayed for Personal Info category
- Use the default displayed for nonscalar objects, including empty arrays, and scalar deleted handles

For example, here is the customized display of an object of the EmployeeInfo class.

```
Emp123 =
EmployeeInfo Dept: Product Development
  Public Info
        Name: 'Bill Tork'
    JobTitle: 'Software Engineer'
  Personal Info
        Salary: 'Level: 10'
```

```
Password: '*****
```

Implementation

The EmployeeInfo class overrides two matlab.mixin.CustomDisplay methods to implement the display shown:

- displayScalarObject Called to display valid scalar objects
- getPropertyGroups Builds the property groups for display

displayScalarObject Method Override

MATLAB calls displayScalarObject to display scalar objects. The EmployeeInfo class overrides this method to implement the scalar display. Once overridden, this method must control all aspects of scalar object display, including creating the header, property groups, and footer, if used.

This implementation:

- Builds a custom header using the getClassNameForHeader static method to return a linked class name string and the value of the Department property to get the department name.
- Uses

sprintf to add a new line to the header string

- Displays the header with the built-in disp function.
- Calls the getPropertyGroups override to define the property groups (see following section).
- Displays the property groups using the displayPropertyGroups static method.

Here is the EmployeeInfo override of the displayScalarObject method. The required protected access is inherited from the superclass.

```
methods (Access = protected)
  function displayScalarObject(obj)
    className = matlab.mixin.CustomDisplay.getClassNameForHeader(obj);
    scalarHeader = [className, 'Dept: ',obj.Department];
    header = sprintf('%s\n',scalarHeader);
    disp(header)
    propgroup = getPropertyGroups(obj);
    matlab.mixin.CustomDisplay.displayPropertyGroups(obj,propgroup)
```

```
end
end
```

getPropertyGroups Override

MATLAB calls getPropertyGroups when displaying scalar or nonscalar objects. However, MATLAB does not call this method when displaying a scalar handle to a deleted object.

The EmployeeInfo class overrides this method to implement the property groups for scalar object display.

This implementation calls the superclass getPropertyGroups method if the input is not scalar. If the input is scalar, this method:

- Defines two titles for the two groups
- Creates a cell array of property names that are included in the first group. MATLAB adds the property values for the display
- Creates a Struct array of property names with associated property values for the second group. Using a Struct instead of a cell array enables you to replace the values that are displayed for the Salary and Password properties without changing the personal information stored in the object properties.
- Constructs two matlab.mixin.util.PropertyGroup objects, which are used by the displayScalarObject method.

Here is the EmployeeInfo override of the getPropertyGroups method. The required protected access is inherited from the superclass.

end end

Complete Class Listing

```
classdef EmployeeInfo4 < handle & matlab.mixin.CustomDisplay</pre>
   properties
      Name
      JobTitle
      Department
      Salary
      Password
   end
   methods
      function obj = EmployeeInfo4
         obj.Name
                        = input('Name: ');
         obj.JobTitle = input('Job Title: ');
         obj.Department = input('Department: ');
         obj.Salary
                       = input('Salary: ');
         obj.Password = input('Password: ');
      end
   end
   methods (Access = protected)
      function displayScalarObject(obj)
         className = matlab.mixin.CustomDisplay.getClassNameForHeader(obj);
         scalarHeader = [className, 'Dept: ',obj.Department];
         header = sprintf('%s\n',scalarHeader);
         disp(header)
         propgroup = getPropertyGroups(obj);
         \verb|matlab.mixin.CustomDisplay.displayPropertyGroups(obj,propgroup)|\\
      end
      function propgrp = getPropertyGroups(obj)
         if ~isscalar(obj)
            propgrp = getPropertyGroups@matlab.mixin.CustomDisplay(obj);
         else
            % property groups for scalars
            gTitle1 = 'Public Info';
            gTitle2 = 'Personal Info';
            propList1 = {'Name', 'JobTitle'};
            pd(1:length(obj.Password)) = '*';
            level = round(obj.Salary/100);
            propList2 = struct('Salary',...
               ['Level: ',num2str(level)],...
                'Password',pd);
            propgrp(1) = matlab.mixin.util.PropertyGroup(propList1,gTitle1);
            propgrp(2) = matlab.mixin.util.PropertyGroup(propList2,gTitle2);
         end
      end
   end
end
```

Customize Display of Object Arrays

This example shows how to customize the display of nonscalar objects, including empty object arrays.

In this section...

"Design of Custom Display" on page 17-32

"The displayNonScalarObject Override" on page 17-33

"The displayEmptyObject Override" on page 17-34

Design of Custom Display

Note: This example uses the EmployeeInfo class described in the "Class with Default Object Display" on page 17-12 section.

The objective of this customized display is to:

- Construct a custom header using some elements of the default header
- Display a subset of property-specific information for each object in the array.
- List handles to deleted objects in the array using a string with links to documentation for handle objects and the class.
- · Display empty objects with a slight modification to the default header

Here is the customized display of an array of three EmployeeInfo objects

Deleted object handles in the array indicate their state:

1x3 EmployeeInfo members:

1. Employee:

Name: 'Bill Tork'

Department: 'Product Development'

- 2. handle to deleted EmployeeInfo
- 3. Employee:

Name: 'Nancy Green'
Department: 'Documentation'

To achieve the desired result, the EmployeeInfo class overrides the following methods of the matlab.mixin.CustomDisplay class:

- displayNonScalarObject Called to display nonempty object arrays
- displayEmptyObject Called to display empty object arrays

The displayNonScalarObject Override

MATLAB calls the displayNonScalarObject method to display object arrays. The override of this method in the EmployeeInfo class:

- Builds a header string using convertDimensionsToString to obtain the array size and getClassNameForHeader to get the class name with a link to the help for that class.
- · Displays the modified header string.
- Loops through the elements in the array, building two different subheaders depending on the individual object state. In the loop, this method:
 - Detects handles to deleted objects (using the isvalid handle class method). Uses getDeletedHandleText and getClassNameForHeader to build a string for array elements that are handles to deleted objects.
 - · Builds a custom subheader for valid object elements in the array
- Creates a PropertyGroup object containing the Name and Department properties for valid objects
- Uses the displayPropertyGroups static method to generate the property display for valid objects.

Here is the implementation of displayNonScalarObjects:

```
methods (Access = protected)
   function displayNonScalarObject(objAry)
      dimStr = matlab.mixin.CustomDisplay.convertDimensionsToString(objAry);
      cName = matlab.mixin.CustomDisplay.getClassNameForHeader(objAry);
      headerStr = [dimStr, ' ',cName, ' members: '];
      header = sprintf('%s\n',headerStr);
      disp(header)
      for ix = 1:length(objAry)
         o = objAry(ix);
         if ~isvalid(0)
            str1 = matlab.mixin.CustomDisplay.getDeletedHandleText;
            str2 = matlab.mixin.CustomDisplay.getClassNameForHeader(o);
            headerInv = [str1, ' ',str2];
            tmpStr = [num2str(ix), '. ',headerInv];
            numStr = sprintf('%s\n',tmpStr);
            disp(numStr)
            numStr = [num2str(ix),'. Employee:'];
            disp(numStr)
            propList = struct('Name', o.Name,...
                Department', o. Department);
            propgrp = matlab.mixin.util.PropertyGroup(propList);
            matlab.mixin.CustomDisplay.displayPropertyGroups(o,propgrp);
         end
      end
   end
end
```

The displayEmptyObject Override

MATLAB calls the displayEmptyObject method to display empty object arrays. The implementation of this method in the EmployeeInfo class builds a custom header for empty objects following these steps:

- Gets the array dimensions in string format using the convertDimensionsToString static method.
- Gets a string with the class name linked to the helpPopup function using the getClassNameForHeader static method.
- Builds and displays the custom string for empty arrays.

```
methods (Access = protected)
  function displayEmptyObject(obj)
    dimstr = matlab.mixin.CustomDisplay.convertDimensionsToString(obj);
    className = matlab.mixin.CustomDisplay.getClassNameForHeader(obj);
    emptyHeader = [dimstr,' ',className,' with no employee information'];
    header = sprintf('%s\n',emptyHeader);
    disp(header)
end
```

end

For example, an empty EmployeeInfo object displays like this:

```
Empt = EmployeeInfo.empty(0,5)
Empt =
```

0x5 EmployeeInfo with no employee information

Complete Class Listing

```
classdef EmployeeInfo < handle & matlab.mixin.CustomDisplay</pre>
   properties
      Name
      JobTitle
      Department
      Salary
      Password
   end
   methods
      function obj = EmployeeInfo
                       = input('Name: ');
         obj.Name
         obj.JobTitle = input('Job Title: ');
         obj.Department = input('Department: ');
         obj.Salary
                       = input('Salary: ');
         obj.Password = input('Password: ');
      end
   end
   methods (Access = protected)
      function displayNonScalarObject(objAry)
         dimStr = matlab.mixin.CustomDisplay.convertDimensionsToString(objAry);
         cName = matlab.mixin.CustomDisplay.getClassNameForHeader(objAry);
         headerStr = [dimStr, ' ',cName, ' members: '];
         header = sprintf('%s\n',headerStr);
         disp(header)
         for ix = 1:length(objAry)
            o = objAry(ix);
            if ~isvalid(0)
               str1 = matlab.mixin.CustomDisplay.getDeletedHandleText;
               str2 = matlab.mixin.CustomDisplay.getClassNameForHeader(o);
               headerInv = [str1, ' ',str2];
               tmpStr = [num2str(ix), '. ',headerInv];
               numStr = sprintf('%s\n',tmpStr);
               disp(numStr)
            else
               numStr = [num2str(ix), '. Employee'];
               disp(numStr)
               propList = struct('Name', o.Name,...
                   'Department', o. Department);
               propgrp = matlab.mixin.util.PropertyGroup(propList);
               matlab.mixin.CustomDisplay.displayPropertyGroups(o,propgrp);
            end
         end
```

```
end

function displayEmptyObject(obj)
    dimstr = matlab.mixin.CustomDisplay.convertDimensionsToString(obj);
    className = matlab.mixin.CustomDisplay.getClassNameForHeader(obj);
    emptyHeader = [dimstr, ' ',className, ' with no employee information'];
    header = sprintf('%s\n',emptyHeader);
    disp(header)
    end
end
end
```

Overload the disp Function

In this section...

"Display Methods" on page 17-37

"Implement disp or disp and display" on page 17-37

"Relationship Between disp and display" on page 17-37

Display Methods

Subclassing matlab.mixin.CustomDisplay is the best approach to customizing object display. However, if you do not derive your class from CustomDisplay, you can overload the disp function to change how MATLAB displays objects of your class.

MATLAB calls an object's display method whenever an object is referred to in a statement that is not terminated by a semicolon. For example, the following statement creates the variable a. MATLAB calls display, which displays the value of a in the command line.

display then calls disp.

Implement disp or disp and display

The built-in display function prints the name of the variable that is being displayed, if an assignment is made, or otherwise uses ans as the variable name. Then display calls disp to handle the actual display of the values.

If the variable that is being displayed is an object of a class that overloads disp, then MATLAB always calls the overloaded method. Overload disp or disp and display to customize the display of objects. Overloading only display is not sufficient to properly implement a custom display for your class.

Relationship Between disp and display

MATLAB invokes the built-in display function when:

- MATLAB executes a statement that returns a value and is not terminated with a semicolon.
- There is no left-side variable, then MATLAB prints ans = followed by the value.
- Code explicitly invokes the display function.

If you invoke display explicitly:

- If the input argument is an existing variable, display prints the variable name and equal sign, followed by the value.
- If the input is the result of an expression, display does not print ans =.

MATLAB invokes the built-in disp function when:

- · The built-in display function calls disp.
- Code explicitly invokes disp.

For empty built-in types (numeric types, char, struct, and cell) the display function displays:

- [] for numeric types
- "OxO struct array with no fields." for empty structs.
- "Empty cell array: 0-by-1" for empty cell arrays.
- '' for empty char arrays

disp differs from display in these ways:

- disp does not print the variable name or ans.
- disp prints nothing for built-in types (numeric types, char, struct, and cell) when the value is empty.

Implementing a Class for Polynomials

Class Design for Polynomials

In this section...

"Object Requirements" on page 18-2

"DocPolynom Class Members" on page 18-2

"DocPolynom Class Synopsis" on page 18-4

"The DocPolynom Constructor" on page 18-13

"Remove Irrelevant Coefficients" on page 18-14

"Convert DocPolynom Objects to Other Types" on page 18-15

"Overload disp for DocPolynom" on page 18-17

"Display Evaluated Expression" on page 18-18

"Redefine Indexed Reference" on page 18-18

"Define Arithmetic Operators" on page 18-21

Object Requirements

This example implements a class to represent polynomials in the MATLAB language. The design requirements are:

- Value class behavior—a polynomial object should behave like MATLAB numeric variables when copied and passed to functions.
- Specialized display and indexing
- Objects can be scalar only. The specialization of display and indexing functionality preclude normal array behavior.
- · Arithmetic operations
- Double converter simplifying the use of polynomial object with existing MATLAB functions that accept numeric inputs.

DocPolynom Class Members

The class definition specifies a property for data storage and defines a folder (@DocPolynom) that contains the class definition.

The following table summarizes the properties defined for the DocPolynom class.

DocPolynom Class Properties

Name	Class	Default	Description
coef	double	[]	Vector of polynomial coefficients [highest order lowest order]

The following table summarizes the methods for the DocPolynom class.

DocPolynom Class Methods

Name	Description
DocPolynom	Class constructor
double	Converts a DocPolynom object to a double (i.e., returns its coefficients in a vector)
char	Creates a formatted display of the ${\tt DocPolynom}$ object as powers of ${\tt x}$ and is used by the ${\tt disp}$ method
disp	Determines how MATLAB displays a ${\tt DocPolynom}$ objects on the command line
subsref	Enables you to specify a value for the independent variable as a subscript, access the coef property with dot notation, and call methods with dot notation.
plus	Implements addition of DocPolynom objects
minus	Implements subtraction of DocPolynom objects
mtimes	Implements multiplication of DocPolynom objects

Using the DocPolynom Class

The following examples illustrate basic use of the DocPolynom class.

Create **DocPolynom** objects to represent the following polynomials. Note that the argument to the constructor function contains the polynomial coefficients $f(x) = x^3 - 2x - 5$ and $f(x) = 2x^4 + 3x^2 + 2x - 7$.

```
p1 = DocPolynom([1 0 -2 -5])
p1 =
     x^3 - 2*x - 5

p2 = DocPolynom([2 0 3 2 -7])
```

```
p2 = 2*x^4 + 3*x^2 + 2*x - 7
```

Find the roots of the polynomial by passing the coefficients to the roots function.

```
roots(p1.coef)
```

```
ans =

2.0946 + 0.0000i
-1.0473 + 1.1359i
-1.0473 - 1.1359i
```

Add the two polynomials p1 and p2.

MATLAB calls the plus method defined for the DocPolynom class when you add two DocPolynom objects.

```
p1 + p2
ans =
2*x^4 + x^3 + 3*x^2 - 12
```

DocPolynom Class Synopsis

Example Code	Discussion
classdef DocPolynom	Value class that implements a data type for polynomials.
properties coef end	Vector of polynomial coefficients [highest order lowest order]
methods	For general information about methods, see "Ordinary Methods"
<pre>function obj = DocPolynom(c) if nargin > 0 if isa(c, 'DocPolynom') obj.coef = c.coef; else obj.coef = c(:).'; end end end</pre>	Class constructor creates objects using: Coefficient vector of existing object Coefficient vector passed as argument

Example Code	Discussion
	See "The DocPolynom Constructor" on page 18-13
<pre>function obj = set.coef(obj,val) if ~isa(val, 'double') error('Coefficients must be doubles') end ind = find(val(:).'~=0); if ~isempty(ind); obj.coef = val(ind(1):end); else obj.coef = val; end end</pre>	 Set method for coef property: Allows coefficients only of type double Removes leading zeros from the coefficient vector. See "Remove Irrelevant Coefficients" on page 18-14
<pre>function c = double(obj) c = obj.coef; end</pre>	Convert DocPolynom object to double by returning the coefficients. See "Convert DocPolynom Objects to Other Types" on page 18-15

```
Example Code
                                                   Discussion
function str = char(obj)
                                                   Convert DocPolynom object
   if all(obj.coef == 0)
                                                   to char that represents the
      s = '0';
                                                   expression:
      str = s;
                                                   y = f(x)
      return
   else
                                                   See "Convert DocPolynom
      d = length(obj.coef)-1;
                                                   Objects to Other Types" on page
      s = cell(1,d);
                                                   18-15
      ind = 1;
      for a = obj.coef;
         if a ~= 0;
             if ind ~= 1
                if a > 0
                   s(ind) = {' + '};
                   ind = ind + 1;
                else
                   s(ind) = { ' - ' };
                   a = -a;
                   ind = ind + 1;
                end
             end
             if a ~= 1 || d == 0
                if a == -1
                   s(ind) = {'-'};
                   ind = ind + 1;
                else
                   s(ind) = \{num2str(a)\};
                   ind = ind + 1;
                   if d > 0
                       s(ind) = {'*'};
                      ind = ind + 1;
                   end
                end
             end
             if d >= 2
                s(ind) = \{['x^{'} int2str(d)]\};
                ind = ind + 1;
             elseif d == 1
                s(ind) = {'x'};
                ind = ind + 1;
             end
          end
```

Example Code	Discussion
<pre>d = d - 1; end end str = [s{:}]; end</pre>	
<pre>function disp(obj) c = char(obj); if iscell(c) disp([' ' c{:}]) else disp(c) end end</pre>	Overload disp function. Display objects as output of char method. For information about this code, see "Overload disp for DocPolynom" on page 18-17
<pre>function dispPoly(obj,x) p = char(obj); e = @(x)eval(p); y = zeros(length(x)); disp(['y = ',p]) for k = 1:length(x) y(k) = e(x(k)); disp([' ',num2str(y(k)), ' = f(x = ',</pre>	Return evaluated expression with formatted output. Uses output of char method to evaluate polynomial at specified values of independent variable. For information about this code, see "Display Evaluated
end	Expression" on page 18-18

Example Code	Discussion
<pre>function b = subsref(a,s) switch s(1).type case '()' ind = s.subs{:}; b = polyval(a.coef,ind); case '.' switch s(1).subs case 'coef' b = a.coef; case 'disp' disp(a) otherwise</pre>	Redefine indexed reference for DocPolynom objects. For information about this code, see "Redefine Indexed Reference" on page 18-18
<pre>if length(s)>1</pre>	

```
Example Code
                                                   Discussion
      function r = plus(obj1,obj2)
                                                   Define three arithmetic
         obj1 = DocPolynom(obj1);
                                                   operators:
         obj2 = DocPolynom(obj2);
         k = length(obj2.coef) - length(obj1.co •
                                                      Polynomial addition
         zp = zeros(1,k);
                                                      Polynomial subtraction
         zm = zeros(1,-k);
         r = DocPolynom([zp,obj1.coef] + [zm,ob •
                                                      Polynomial multiplication
      end
                                                   For information about this
      function r = minus(obj1,obj2)
                                                   code, see "Define Arithmetic
         obj1 = DocPolynom(obj1);
                                                   Operators" on page 18-21
         obj2 = DocPolynom(obj2);
         k = length(obj2.coef) - length(obj1.co For general information about
         zp = zeros(1,k);
                                                   defining operators, see "Class
         zm = zeros(1, -k);
         r = DocPolynom([zp,obj1.coef] - [zm,ob] Operator Implementations"
      end
      function r = mtimes(obj1,obj2)
         obj1 = DocPolynom(obj1);
         obj2 = DocPolynom(obj2);
         r = DocPolynom(conv(obj1.coef,obj2.coe
      end
   end
  end
                                                   end statements for methods
end
                                                   and for classdef.
```

Expand for Class Code

```
classdef DocPolynom
  % Documentation example
  % A value class that implements a data type for polynomials
  % See Implementing a Class for Polynomials in the
  % MATLAB documentation for more information.

properties
    coef
end

% Class methods
methods
function obj = DocPolynom(c)
```

```
if nargin > 0
      if isa(c, 'DocPolynom')
         obj.coef = c.coef;
      else
         obj.coef = c(:).';
      end
   end
end % DocPolynom
function obj = set.coef(obj,val)
   if ~isa(val, 'double')
      error('Coefficients must be doubles')
   end
   % Remove leading zeros
   ind = find(val(:).^{-20});
   if ~isempty(ind);
      obj.coef = val(ind(1):end);
  else
      obj.coef = val;
   end
end % set.coef
function c = double(obj)
   c = obj.coef;
end % double
function str = char(obj)
   % Created a formated display of the polynom
  % as powers of x
   if all(obj.coef == 0)
      s = '0';
      str = s;
      return
   else
      d = length(obj.coef)-1;
      s = cell(1,d);
      ind = 1;
      for a = obj.coef;
         if a ~= 0;
            if ind ~= 1
               if a > 0
                  s(ind) = {' + '};
                  ind = ind + 1;
               else
                  s(ind) = {' - '};
```

```
a = -a; %\#ok < FXSET >
                   ind = ind + 1;
               end
            end
            if a ~= 1 || d == 0
               if a == -1
                  s(ind) = {'-'};
                   ind = ind + 1;
               else
                   s(ind) = \{num2str(a)\};
                   ind = ind + 1;
                   if d > 0
                      s(ind) = {'*'};
                      ind = ind + 1;
                   end
               end
            end
            if d >= 2
               s(ind) = \{['x^{'} int2str(d)]\};
               ind = ind + 1;
            elseif d == 1
               s(ind) = {'x'};
               ind = ind + 1;
            end
         end
         d = d - 1;
      end
   end
   str = [s{:}];
end % char
function disp(obj)
   % DISP Display object in MATLAB syntax
   c = char(obj);
   if iscell(c)
                  ' c{:}])
      disp(['
   else
      disp(c)
   end
end % disp
function dispPoly(obj,x)
   % evaluate obj at x
   p = char(obj);
```

```
e = @(x)eval(p);
   y = zeros(length(x));
   disp(['y = ',p])
   for k = 1:length(x)
     y(k) = e(x(k));
      disp([' ',num2str(y(k)),...
         ' = f(x = ', ...
         num2str(x(k)),')'])
   end
end
function b = subsref(a,s)
   % SUBSREF Implementing the following syntax:
  % obj([1 ...])
  % obj.coef
  % obj.disp
  % out = obj.method(args)
  % out = obj.method
   switch s(1).type
      case '()'
         ind = s.subs{:};
         b = polyval(a.coef,ind);
      case '.'
         switch s(1).subs
            case 'coef'
               b = a.coef;
            case 'disp'
               disp(a)
            otherwise
               if length(s)>1
                  b = a.(s(1).subs)(s(2).subs{:});
               else
                  b = a.(s.subs);
               end
         end
      otherwise
         error('Specify value for x as obj(x)')
   end
end % subsref
function r = plus(obj1,obj2)
   % PLUS Implement obj1 + obj2 for DocPolynom
   obj1 = DocPolynom(obj1);
   obj2 = DocPolynom(obj2);
```

```
k = length(obj2.coef) - length(obj1.coef);
         zp = zeros(1,k);
         zm = zeros(1,-k);
         r = DocPolynom([zp,obj1.coef] + [zm,obj2.coef]);
      end % plus
      function r = minus(obj1,obj2)
         % MINUS Implement obj1 - obj2 for DocPolynoms.
         obi1 = DocPolvnom(obi1);
         obj2 = DocPolynom(obj2);
         k = length(obj2.coef) - length(obj1.coef);
         zp = zeros(1,k);
         zm = zeros(1,-k);
         r = DocPolynom([zp,obj1.coef] - [zm,obj2.coef]);
      end % minus
      function r = mtimes(obj1,obj2)
                    Implement obj1 * obj2 for DocPolynoms.
         % MTIMES
         obj1 = DocPolynom(obj1);
         obj2 = DocPolynom(obj2);
         r = DocPolynom(conv(obj1.coef,obj2.coef));
      end % mtimes
   end % methods
end % classdef
```

The DocPolynom Constructor

The following function is the DocPolynom class constructor, which is in the file @DocPolynom/DocPolynom.m:

methods

```
function obj = DocPolynom(c)
   if isa(c,'DocPolynom')
      obj.coef = c.coef;
   else
      obj.coef = c(:).';
   end
  end
end
```

Constructor Calling Syntax

It is possible to all the ${\tt DocPolynom}$ constructor with two different arguments:

- Input argument is a DocPolynom object If you call the constructor function with an input argument that is already a DocPolynom object, the constructor returns a new DocPolynom object with the same coefficients as the input argument. The isa function checks for this input.
- Input argument is a coefficient vector If the input argument is not a DocPolynom
 object, the constructor attempts to reshape the values into a vector and assign them to
 the coef property.

The coef property set method restricts property values to doubles. See "Remove Irrelevant Coefficients" on page 18-14 for a description of the property set method.

An example use of the DocPolynom constructor is the statement:

```
p = DocPolynom([1 0 -2 -5])
p =
    x^3 - 2*x -5
```

This statement creates an instance of the <code>DocPolynom</code> class with the specified coefficients. Note the display of the object shows the equivalent polynomial using MATLAB language syntax. The <code>DocPolynom</code> class implements this display using the <code>disp</code> and <code>char</code> class methods.

Remove Irrelevant Coefficients

MATLAB software represents polynomials as row vectors containing coefficients ordered by descending powers. Zeros in the coefficient vector represent terms that drop out of the polynomial. Leading zeros, therefore, can be ignored when forming the polynomial.

Some DocPolynom class methods use the length of the coefficient vector to determine the degree of the polynomial. It is useful, therefore, to remove leading zeros from the coefficient vector so that its length represents the true value.

The DocPolynom class stores the coefficient vector in a property that uses a set method to remove leading zeros from the specified coefficients before setting the property value.

methods

```
function obj = set.coef(obj,val)
  if ~isa(val,'double')
    error('Coefficients must be doubles')
  end
  ind = find(val(:).'~=0);
  if ~isempty(ind);
```

```
obj.coef = val(ind(1):end);
else
    obj.coef = val;
end
end
end
```

Convert DocPolynom Objects to Other Types

The DocPolynom class defines two methods to convert DocPolynom objects to other classes:

- double Converts to the double numeric type so functions can perform mathematical operations on the coefficients.
- · char Converts to string used to format output for display in the command window

The Double Converter

The double converter method for the DocPolynom class simply returns the coefficient vector:

```
methods
   function c = double(obj)
      c = obj.coef;
   end
end
For the DocPolynom object p:
p = DocPolynom([1 0 -2 -5]);
the statement:
c = double(p)
returns:
C=
    1
          0
                -2
                       - 5
which is of class double:
class(c)
ans =
   double
```

The Character Converter

The char method produces a character string that represents the polynomial displayed as powers of x. The string returned is a syntactically correct MATLAB expression.

The char method uses a cell array to collect the string components that make up the displayed polynomial.

The disp method uses char to format the DocPolynom object for display. The evalPoly method uses char to create the MATLAB expression to evaluate,

Users of DocPolynom objects are not likely to call the char or disp methods directly, but these methods enable the DocPolynom class to behave like other data classes in MATLAB.

Here is the char method.

```
methods
   function str = char(obj)
      if all(obj.coef == 0)
         s = '0';
         str = s;
         return
      else
         d = length(obj.coef)-1;
         s = cell(1,d);
         ind = 1;
         for a = obj.coef;
            if a ~= 0;
               if ind ~= 1
                  if a > 0
                     s(ind) = {' + '};
                     ind = ind + 1;
                     s(ind) = {' - '};
                     a = -a;
                     ind = ind + 1;
                  end
               end
               if a ~= 1 || d == 0
                  if a == -1
                     s(ind) = {'-'};
                     ind = ind + 1;
                     s(ind) = \{num2str(a)\};
                     ind = ind + 1;
                     if d > 0
                        s(ind) = {'*'};
                        ind = ind + 1;
                     end
                  end
```

Overload disp for DocPolynom

To provide a more useful display of DocPolynom objects, this class overloads disp in the class definition.

This disp method relies on the char method to produce a string representation of the polynomial, which it then displays on the screen.

The char method returns a cell array or the character '0' if the coefficients are all zero.

methods

```
function disp(obj)
    c = char(obj);
    if iscell(c)
        disp([' ' c{:}])
    else
        disp(c)
    end
end
end
```

When MATLAB Calls the disp Method

The statement:

```
p = DocPolynom([1 0 -2 -5])
```

creates a DocPolynom object. Because the statement is not terminated with a semicolon, the resulting output is displayed on the command line:

```
p =
```

```
x^3 - 2*x - 5
```

Display Evaluated Expression

The char converter method forms a MATLAB expression for the polynomial represented by a DocPolynom object. The dispPoly method evaluates the expression returned by the char method with a specified value for x.

```
methods
   function dispPoly(obj,x)
      p = char(obj);
      e = @(x)eval(p);
      y = zeros(length(x));
      disp(['y = ',p])
      for k = 1:length(x)
         y(k) = e(x(k));
          disp([' ',num2str(y(k)),...
                 = f(x = ', ...
               num2str(x(k)),')'])
      end
   end
end
Create a DocPolynom object p:
p = DocPolynom([1 0 -2 -5])
x^3 - 2*x - 5
Evaluate the polynomial at x equal to three values, [3 5 9]:
dispPoly(p,[3 5 9])
y = x^3 - 2*x - 5
  16 = f(x = 3)
  110 = f(x = 5)
  706 = f(x = 9)
```

Redefine Indexed Reference

The DocPolynom class redefines indexed reference to better serve the use of objects representing polynomials. In the DocPolynom class, a subscripted reference to an object

causes an evaluation of the polynomial with the value of the independent variable equal to the subscript.

For example, given the following polynomial:

$$f(x) = x^3 - 2x - 5$$

Create a DocPolynom object p:

The following subscripted expression evaluates the value of the polynomial at x = 3 and at x = 4, and returns the resulting values:

```
p([3 4])
ans =
16 51
```

Indexed Reference Design Objectives

Redefine the default subscripted reference behavior by implementing a subsref method.

If a class defines a subsref method, MATLAB calls this method for objects of this class whenever a subscripted reference occurs. The subsref method must define all the indexed reference behaviors, not just a specific case that you want to change.

The DocPolynom subsref method implements the following behaviors:

- $p(x = [a_1...a_n])$ Evaluate polynomial at x = a.
- p.coef Access coef property value
- p.disp Display the polynomial as a MATLAB expression without assigning an output.
- obj = p.method(args) Use dot notation to call methods arguments and return a modified object.
- obj = p.method Use dot notation to call methods without arguments and return a modified object.

subsref Implementation Details

The subsref method overloads the subsref function.

For example, consider a call to the polyval function:

The polyval function requires the:

- Polynomial coefficients
- · Values of the independent variable at which to evaluate the polynomial

The polyval function returns the value of f(x) at these values. subsref calls polyval through the statements:

```
case '()'
  ind = s.subs{:};
  b = polyval(a.coef,ind);
```

When implementing subsref to support method calling with arguments using dot notation, both the type and subs structure fields contain multiple elements.

The subsref method implements all subscripted reference explicitly, as show in the following code listing.

methods

```
function b = subsref(a,s)
    switch s(1).type
    case '()'
        ind = s.subs{:};
        b = polyval(a.coef,ind);
    case '.'
        switch s(1).subs
        case 'coef'
            b = a.coef;
        case 'disp'
        disp(a)
        otherwise
```

Define Arithmetic Operators

Several arithmetic operations are meaningful on polynomials. The DocPolynom class implements these methods:

Method and Syntax	Operator Implemented
plus(a,b)	Addition
minus(a,b)	Subtraction
mtimes(a,b)	Matrix multiplication

When overloading arithmetic operators, consider the data types you must support. The plus, minus, andmtimes methods are defined for the DocPolynom class to handle addition, subtraction, and multiplication on DocPolynom — DocPolynom and DocPolynom — double combinations of operands.

Define + Operator

If either p or q is a <code>DocPolynom</code> object, this expression:

```
p + q
```

Generates a call to a function <code>QDocPolynom/plus</code>, unless the other object is of higher precedence.

The following method overloads the plus (+) operator for the DocPolynom class:

```
methods
  function r = plus(obj1,obj2)
   obj1 = DocPolynom(obj1);
  obj2 = DocPolynom(obj2);
  k = length(obj2.coef) - length(obj1.coef);
```

```
zp = zeros(1,k);
zm = zeros(1,-k);
r = DocPolynom([zp,obj1.coef] + [zm,obj2.coef]);
end
end
```

Here is how the function works:

Ensure that both input arguments are DocPolynom objects so that expressions such as

```
p + 1
```

that involve both a DocPolynom and a double, work correctly.

- Access the two coefficient vectors and, if necessary, pad one of them with zeros to
 make both the same length. The actual addition is simply the vector sum of the two
 coefficient vectors.
- Call the DocPolynom constructor to create a properly typed object that is the result of adding the polynomials.

Define - Operator

Implement the minus operator (-) using the same approach as the plus (+) operator.

The \min us method computes p - q. The dominant argument must be a DocPolynom object.

```
methods
  function r = minus(obj1,obj2)
    obj1 = DocPolynom(obj1);
    obj2 = DocPolynom(obj2);
    k = length(obj2.coef) - length(obj1.coef);
    zp = zeros(1,k);
    zm = zeros(1,-k);
    r = DocPolynom([zp,obj1.coef] - [zm,obj2.coef]);
  end
end
```

Define the * Operator

Implement the mtimes method to compute the product p*q. The mtimes method implements *matrix* multiplication since the multiplication of two polynomials is the convolution (CONV) of their coefficient vectors:

```
methods
  function r = mtimes(obj1,obj2)
```

```
obj1 = DocPolynom(obj1);
obj2 = DocPolynom(obj2);
r = DocPolynom(conv(obj1.coef,obj2.coef));
end
end
```

Using the Arithmetic Operators

Given the DocPolynom object:

```
p = DocPolynom([1 0 -2 -5]);
```

The following two arithmetic operations call the ${\tt DocPolynom\ plus}$ and ${\tt mtimes}$ methods:

Designing Related Classes

- "A Simple Class Hierarchy" on page 19-2
- "Containing Assets in a Portfolio" on page 19-20

A Simple Class Hierarchy


In this section...

- "Shared and Specialized Properties" on page 19-2
- "Designing a Class for Financial Assets" on page 19-3
- "DocAsset Class Definition" on page 19-4
- "Summary of the DocAsset Class" on page 19-4
- "The DocAsset Constructor Method" on page 19-5
- "The DocAsset Display Method" on page 19-6
- "Designing a Class for Stock Assets" on page 19-7
- "DocStock Class Definition" on page 19-7
- "Summary of the DocStock Class" on page 19-7
- "Designing a Class for Bond Assets" on page 19-10
- "DocBond Class Definition" on page 19-10
- "Summary of the DocBond Class" on page 19-10
- "Designing a Class for Savings Assets" on page 19-14
- "DocSavings Class Definition" on page 19-14
- "Summary of the DocSavings Class" on page 19-14
- "DocAsset Class Code Listing" on page 19-17
- "DocStock Class Code Listing" on page 19-17
- "DocBond Class Code Listing" on page 19-18
- "DocSavings Class Code Listing" on page 19-19

Shared and Specialized Properties

As an example of how subclasses are specializations of more general classes, consider an asset class that can be used to represent any item that has monetary value. Some examples of assets are stocks, bonds, and savings accounts. This example implements four classes — DocAsset, and the subclasses DocStock, DocBond, DocSavings.

The DocAsset class holds the data that is common to all of the specialized asset subclasses in class properties. The subclasses inherit the super class properties in addition to defining their own properties. The subclasses are all *kinds* of assets.



The following diagram shows the properties defined for the classes of assets.

The DocStock, DocBond, and DocSavings classes inherit properties from the DocAsset class. In this example, the DocAsset class provides storage for data common to all subclasses and shares methods with these subclasses.

Designing a Class for Financial Assets

This class provides storage and access for information common to all asset children. It is not intended to be instantiated directly, so it does not require an extensive set of methods. The class contains the following methods:

Constructor

A local setter function for one property

DocAsset Class Definition

For a full code listing for the DocAsset class, see "DocAsset Class Code Listing" on page 19-17

To use the class, create a folder named <code>@DocAsset</code> and save the class code as <code>DocAsset.m</code> in this folder. The parent folder of <code>@DocAsset</code> must be on the MATLAB path.

Summary of the DocAsset Class

The class is defined in one file, DocAsset.m, which you must place in an @ folder of the same name. The parent folder of the @DocAsset folder must be on the MATLAB path. See the addpath function for more information.

The following table summarizes the properties defined for the DocAsset class.

DocAsset Class Properties

Name	Class	Default	Description
Description	char	1.1	Description of asset
CurrentValue	double	0	Current value of asset
Date	char	date	Date when record is created (set by date function)
Туре	char	'savings'	Type of asset (stock, bond, savings)

The following table summarizes the methods for the DocAsset class.

DocAsset Class Methods

Name	Description
DocAsset	Class constructor
disp	Displays information about this object
set.Type	Set function for Type. Property tests for correct value when property is set.

The DocAsset Constructor Method

This class has four properties that store data common to all of the asset subclasses. All except Date are passed to the constructor by a subclass constructor. Date is a private property and is set by a call to the date function.

- Description A character string that describes the particular asset (e.g., stock name, savings bank name, bond issuer, and so on).
- Date The date the object was created. This property's set access is private so that
 only the constructor assigns the value using the date command when creating the
 object.
- Type The type of asset (e.g., savings, bond, stock). A local set function provides error checking whenever an object is created.
- CurrentValue The current value of the asset.

Property Definition Block

The following code block shows how the properties are defined. Note the set function defined for the Type property. It restricts the property's values to one of three strings: bond, stock, or savings.

```
properties
   Description = '';
   CurrentValue = 0;
end
properties(SetAccess = private)
   Date % Set value in constructor
   Type = 'savings'; % Provide a default value
end
```

Constructor Method Code

The DocAsset class is not derived from another class, so you do not need to call a superclass constructor. MATLAB constructs an object when you assign values to the specified output argument (a in the following code):

```
function a = DocAsset(description, type, current_value)
% DocAsset constructor
  if nargin > 0
     a.Description = description;
     a.Date = date;
     a.Type = type;
```

```
a.CurrentValue = current_value;
end
end % DocAsset
```

Set Function for Type Property

In this class design, there are only three types of assets—bonds, stocks, and savings. Therefore, the possible values for the Type property are restricted to one of three possible stings by defining a set function as follows:

```
function obj = set.Type(obj,type)
  if ~(strcmpi(type,'bond') || strcmpi(type,'stock') || strcmpi(type,'savings'))
    error('Type must be either bond, stock, or savings')
  end
  obj.Type = type;
end %Type set function
```

The MATLAB runtime calls this function whenever an attempt is made to set the Type property, even from within the class constructor function or by assigning an initial value. Therefore, the following statement in the class definition would produce an error:

```
properties
   Type = 'cash';
end
```

The only exception is the **set.Type** function itself, where the statement:

```
obj.Type = type;
```

does not result in a recursive call to set. Type.

The DocAsset Display Method

The asset disp method is designed to be called from child-class disp methods. Its purpose is to display the data it stores for the child object. The method simply formats the data for display in a way that is consistent with the formatting of the child's disp method:

```
function disp(a)
% Display a DocAsset object
  fprintf('Description: %s\nDate: %s\nType: %s\nCurrentValue:%9.2f\n',...
  a.Description,a.Date,a.Type,a.CurrentValue);
end % disp
```

The DocAsset subclass display methods can now call this method to display the data stored in the parent class. This approach isolates the subclass disp methods from changes to the DocAsset class.

Designing a Class for Stock Assets

Stocks are one type of asset. A class designed to store and manipulate information about stock holdings needs to contain the following information about the stock:

- · The number of shares
- The price per share

In addition, the base class (DocAsset) maintains general information including a description of the particular asset, the date the record was created, the type of asset, and its current value.

DocStock Class Definition

For a full code listing for the DocAsset class, see "DocStock Class Code Listing" on page 19-17

To use the class, create a folder named @DocStock and save the class code as DocStock.m in this folder. The parent folder of @DocStock must be on the MATLAB path.

Summary of the DocStock Class

This class is defined in one file, DocStock.m, which you must place in an @ folder of the same name. The parent folder of the @DocStock folder must be on the MATLAB path. See the addpath function for more information.

DocStock is a subclass of the DocAsset class.

The following table summarizes the properties defined for the DocStock class.

DocStock Class Properties

Name	Class	Default	Description
NumShares	double	0	Number of shares of a particular stock
SharePrice	double	0	Current value of asset
Properties Inherited from the DocAsset Class			
Description	char	1.1	Description of asset

Name	Class	Default	Description
CurrentValue	double	0	Current value of asset
Date	char	date	Date when record is created (set by date function)
Type	char	1 1	Type of asset (stock, bond, savings)

The following table summarizes the methods for the DocStock class.

DocStock Class Methods

Name	Description
DocStock	Class constructor
disp	Displays information about the object

Specifying the Base Class

The < symbol specifies the DocAsset class as the base class for the DocStock class in the classdef line:

classdef DocStock < DocAsset</pre>

Property Definition Block

The following code shows how the properties are defined:

```
properties
  NumShares = 0;
  SharePrice = 0;
end
```

Using the DocStock Class

Suppose you want to create a record of a stock asset for 200 shares of a company called Xdotcom with a share price of \$23.47.

Call the DocStock constructor function with the following arguments:

- · Stock name or description
- · Number of shares
- Share price

For example, the following statement:

```
XdotcomStock = DocStock('Xdotcom',200,23.47);
```

creates a DocStock object, XdotcomStock, that contains information about a stock asset in Xdotcom Corp. The asset consists of 200 shares that have a per share value of \$23.47.

The DocStock Constructor Method

The constructor first creates an instance of a DocAsset object since the DocStock class is derived from the DocAsset class (see "The DocAsset Constructor Method" on page 19-5). The constructor returns the DocStock object after setting value for its two properties:

```
function s = DocStock(description,num_shares,share_price)
  if nargin ~= 3 % Support no argument constructor syntax
    description = '';
    num_shares = 0;
    share_price = 0;
    end
    s = s@DocAsset(description,'stock',share_price*num_shares);
    s.NumShares = num_shares;
    s.SharePrice = share_price;
end % DocStock
```

The DocStock disp Method

When you issue the statement (without terminating with a semicolon):

```
XdotcomStock = DocStock('Xdotcom',100,25)
```

the MATLAB runtime looks for a method in the @DocStock folder called disp. The disp method for the DocStock class produces this output:

```
Description: Xdotcom
Date: 17-Nov-1998
Type: stock
Current Value: $2500.00
Number of shares: 100
Share price: $25.00
```

The following function is the DocStock disp method. When this function returns from the call to the DocAsset disp method, it uses fprintf to display the Numshares and SharePrice property values on the screen:

```
function disp(s)
  disp@DocAsset(s)
  fprintf('Number of shares: %g\nShare price: %3.2f\n',...
  s.NumShares,s.SharePrice);
end % disp
```

Designing a Class for Bond Assets

The DocBond class is similar to the DocStock class in that it is derived from the DocAsset class to represent a specific type of asset.

DocBond Class Definition

For a full code listing for the DocBond class, see "DocBond Class Code Listing" on page 19-18

To use the class, create a folder named <code>QDocBond</code> and save the class code as <code>DocBond.m</code> in this folder. The parent folder of <code>QDocBond</code> must be on the MATLAB path.

Summary of the DocBond Class

This class is defined in one file, DocBond.m, which you must place in an @ folder of the same name. The parent folder of the @DocBond folder must on the MATLAB path.

DocStock is a subclass of the DocAsset class.

The following table summarize the properties defined for the DocBond class

DocBond Class Properties

Name	Class	Default	Description
FaceValue	double	0	Face value of the bond
SharePrice	double	0	Current value of asset
Properties Inherit	ed from the I	OocAsset Class	5
Description	char	1.1	Description of asset
CurrentValue	double	0	Current value of asset
Date	char	date	Date when record is created (set by date function)

Name	Class	Default	Description
Туре	char	1.1	Type of asset (stock, bond, savings)

The following table summarizes the methods for the DocStock class.

DocBond Class Methods

Name	Description
DocBond	Class constructor
disp	Displays information about this object and calls the DocAsset disp method
calc_value	Utility function to calculate the bond's current value

Specifying the Base Class

The < symbol specifies the DocAsset class as the base class for the DocBond class in the classdef line:

classdef DocBond < DocAsset</pre>

Property Definition Block

The following code block shows how the properties are defined:

```
properties
   FaceValue = 0;
   Yield = 0;
   CurrentBondYield = 0;
end
```

Using the DocBond Class

Suppose you want to create a record of an asset that consists of an xyzbond with a face value of \$100 and a current yield of 4.3%. The current yield for the equivalent bonds today is 6.2%, which means that the market value of this particular bond is less than its face value.

Call the DocBond constructor function with the following arguments:

Bond name or description

- Bond's face value
- Bond's interest rate or yield
- Current interest rate being paid by equivalent bonds (used to calculate the current value of the asset)

For example, this statement:

```
b = DocBond('xyzbond', 100, 4.3, 6.2);
```

creates a DocBond object, b, that contains information about a bond asset xyzbond with a face value of \$100, a yield of 4.3%, and also contains information about the current yield of such bonds (6.2% in this case) that is used to calculate the current value.

Note The calculations performed in this example are intended only to illustrate the use of MATLAB classes and do not represent a way to determine the actual value of any monetary investment.

The DocBond Constructor Method

The **DocBond** constructor method requires four arguments. It also supports the no argument syntax by defining default values for the missing input arguments:

```
function b = DocBond(description, face_value, yield, current_yield)
  if nargin ~= 4
    description = '';
    face_value = 0;
    yield = 0;
    current_yield = 0;
  end
  market_value = DocBond.calc_value(face_value, yield, current_yield);
  b = b@DocAsset(description, 'bond', market_value);
  b.FaceValue = face_value;
  b.Yield = yield;
  b.CurrentBondYield = current_yield;
end % DocBond
```

The calc_value Method

The DocBond class determines the market value of bond assets using a simple formula that scales the face value by the ratio of the bond's interest yield to the current yield for equivalent bonds.

Calculation of the asset's market value requires that the yields be nonzero, and should be positive just to make sense. While the calc_value method issues no errors for bad yield values, it does ensure bad values are not used in the calculation of market value.

The asset's market value is passed to the DocAsset base-class constructor when it is called within the DocBond constructor. calc_value has its Static attribute set to true because it does not accept a DocBond object as an input argument. The output of calc value is used by the base-class (DocAsset) constructor:

```
methods (Static)
  function market_value = calc_value(face_value,yield,current_yield)
    if current_yield <= 0 || yield <= 0
        market_value = face_value;
    else
        market_value = face_value*yield/current_yield;
    end
  end % calc_value
end % methods</pre>
```

The DocBond disp Method

When you issue this statement (without terminating it with a semicolon):

```
b = DocBond('xyzbond', 100, 4.3, 6.2)
```

the MATLAB runtime looks for a method in the @DocBond folder called disp. The disp method for the DocBond class produces this output:

```
Description: xyzbond
Date: 17-Nov-1998
Type: bond
Current Value: $69.35
Face value of bonds: $100
Yield: 4.30%
```

The following function is the DocBond disp method. When this function returns from the call to the DocAsset disp method, it uses fprintf to display the FaceValue, Yield, and CurrentValue property values on the screen:

```
function disp(b)
   disp@DocAsset(b) % Call DocAsset disp method
   fprintf('Face value of bonds: $%g\nYield: %3.2f%%\n',...
        b.FaceValue,b.Yield);
end % disp
```

Designing a Class for Savings Assets

The DocSavings class is similar to the DocStock and DocBond class in that it is derived from the DocAsset class to represent a specific type of asset.

DocSavings Class Definition

For a full code listing for the DocAsset class, see "DocSavings Class Code Listing" on page 19-19

To use the class, create a folder named @DocSavings and save the class code as DocSavings.m in this folder. The parent folder of @DocSavings must be on the MATLAB path.

Summary of the DocSavings Class

This class is defined in one file, DocSavings.m, which you must place in an @ folder of the same name. The parent folder of the @DocSavings folder must on the MATLAB path. See the addpath function for more information.

The following table summarizes the properties defined for the DocSavings class.

DocSavings Class Properties

Name	Class	Default	Description
InterestRate	double	1.1	Current interest rate paid on the savings account
Properties Inherite	ed from the DocAsser	t Class	
Description	char	1.1	Description of asset
CurrentValue	double	0	Current value of asset
Date	char	date	Date when record is created (set by date function)
Туре	char	1 1	The type of asset (stock, bond, savings)

The following table summarizes the methods for the DocSavings class.

DocSavings Class Methods

Name	Description
DocSavings	Class constructor
disp	Displays information about this object and calls the DocAsset disp method

Specifying the Base Class

The < symbol specifies the DocAsset class as the base class for the DocBond class in the classdef line:

classdef DocSavings < DocAsset

Property Definition Block

The following code shows how the property is defined:

```
properties
   InterestRate = 0;
end
```

Using the DocSavings Class

Suppose you want to create a record of an asset that consists of a savings account with a current balance of \$1000 and an interest rate of 2.9%.

Call the DocSavings constructor function with the following arguments:

- · Bank account description
- · Account balance
- · Interest rate paid on savings account

For example, this statement:

```
sv = DocSavings('MyBank',1000,2.9);
```

creates a DocSavings object, sv, that contains information about an account in MyBank with a balance of \$1000 and an interest rate of 2.9%.

The DocSavings Constructor Method

The savings account interest rate is saved in the DocSavings class InterestRate property. The asset description and the current value (account balance) are saved in the inherited DocAsset object properties.

The constructor calls the base class constructor (DocAsset.m) to create an instance of the object. It then assigns a value to the InterestRate property. The constructor supports the no argument syntax by providing default values for the missing arguments.

```
function s = DocSavings(description,balance,interest_rate)
  if nargin ~= 3
    description = '';
  balance = 0;
  interest_rate = 0;
  end
  s = s@DocAsset(description,'savings',balance);
  s.InterestRate = interest_rate;
end % DocSavings
```

The DocSavings disp Method

When you issue this statement (without terminating it with a semicolon):

```
sv = DocSavings('MyBank', 1000, 2.9)
```

the MATLAB runtime looks for a method in the @DocSavings folder called disp. The disp method for the DocSavings class produces this output:

```
Description: MyBank
Date: 17-Nov-1998
Type: savings
Current Value: $1000.00
Interest Rate: 2.90%
```

The following function is the DocSaving disp method. When this function returns from the call to the DocAsset disp method, it uses fprintf to display the Numshares and SharePrice property values on the screen:

```
function disp(b)
  disp@DocAsset(b) % Call DocAsset disp method
  fprintf('%s%3.2f%%\n','Interest Rate: ',s.InterestRate);
end % disp
```

DocAsset Class Code Listing

```
classdef DocAsset
   % file: @DocAsset/DocAsset.m
   properties
      Description = '';
      CurrentValue = 0;
   end
   properties (SetAccess = private)
      Date
      Type = 'savings';
   end
   % Class methods
   methods
      function a = DocAsset(description,type,current_value)
         % DocAsset Constructor function
         if nargin > 0
            a.Description = description;
            a.Date = date;
            a.Type = type;
            a.CurrentValue = current_value;
         end
      end % DocAsset
      function disp(a)
         % Display a DocAsset object
         fprintf('Description: %s\nDate: %s\nType: %s\nCurrent Value: $%4.2f\n',...
            a.Description,a.Date,a.Type,a.CurrentValue);
      end % disp
      function obj = set.Type(obj,type)
         if ~(strcmpi(type,'bond') || strcmpi(type,'stock') || strcmpi(type,'savings'))
            error('Type must be either bond, stock, or savings')
         obj.Type = type;
      end % Set.Type
   end
end % classdef
```

DocStock Class Code Listing

```
classdef DocStock < DocAsset

properties
    NumShares = 0;
    SharePrice = 0;
end

methods
    function s = DocStock(description, num_shares, share_price)
    if nargin ~= 3</pre>
```

```
description = '';
    num_shares = 0;
    share_price = 0;
end
    s = s@DocAsset(description, 'stock', share_price*num_shares);
    s.NumShares = num_shares;
    s.SharePrice = share_price;
end

function disp(s)
    disp@DocAsset(s)
    fprintf('Number of shares: %g\nShare price: $%2.2f\n',...
    s.NumShares,s.SharePrice);
end
end
end
```

DocBond Class Code Listing

```
classdef DocBond < DocAsset</pre>
   properties
      FaceValue = 0;
      Yield = 0;
      CurrentBondYield = 0;
   end
   methods
      function b = DocBond(description, face value, yield, current yield)
         if nargin ~= 4
            description = '';
            face_value = 0;
            yield = 0;
            current_yield = 0;
         market_value = DocBond.calc_value(face_value, yield, current_yield);
         b = b@DocAsset(description, 'bond', market_value);
         b.FaceValue = face value;
         b.Yield = yield;
         b.CurrentBondYield = current yield;
      end
      function disp(b)
         disp@DocAsset(b)
         fprintf('Face value of bonds: $%g\nYield: %3.2f%\n',...
            b.FaceValue,b.Yield);
      end
   end
   methods (Static = true)
      function market_value = calc_value(face_value,yield,current_yield)
         if current_yield <= 0 || yield <= 0</pre>
            market value = face value;
```

DocSavings Class Code Listing

```
classdef DocSavings < DocAsset</pre>
   properties
      InterestRate = 0;
   end
   methods
      function s = DocSavings(description,balance,interest_rate)
         if nargin ~= 3
            description = '';
            balance = 0;
            interest rate = 0;
         end
         s = s@DocAsset(description, 'savings', balance);
         s.InterestRate = interest_rate;
      end
      function disp(s)
         disp@DocAsset(s)
         fprintf('%s%3.2f%%\n','Interest Rate: ',s.InterestRate);
      end
   end
end
```

Containing Assets in a Portfolio

In this section...

"Kinds of Containment" on page 19-20

"Designing the DocPortfolio Class" on page 19-20

"Displaying the Class Files" on page 19-21

"Summary of the DocPortfolio Class" on page 19-21

"The DocPortfolio Constructor Method" on page 19-23

"The DocPortfolio disp Method" on page 19-24

"The DocPortfolio pie3 Method" on page 19-24

"Visualizing a Portfolio" on page 19-25

"DocPortfolio Class Code Listing" on page 19-26

Kinds of Containment

Aggregation is the containment of objects by other objects. The basic relationship is that each contained object "is a part of" the container object. Composition is a more strict form of aggregation in which the contained objects are parts of the containing object and are not associated with any other objects. Portfolio objects form a composition with asset objects because the asset objects are value classes, which are copied when the constructor method creates the DocPortfolio object.

For example, consider a financial portfolio class as a container for a set of assets (stocks, bonds, savings, and so on). It can group, analyze, and return useful information about the individual assets. The contained objects are not accessible directly, but only via the portfolio class methods.

"A Simple Class Hierarchy" on page 19-2 provides information about the assets collected by this portfolio class.

Designing the DocPortfolio Class

The DocPortfolio class is designed to contain the various assets owned by an individual client and to provide information about the status of his or her investment portfolio. This example implements a somewhat over-simplified portfolio class that:

· Contains an individual's assets

- · Displays information about the portfolio contents
- · Displays a 3-D pie chart showing the relative mix of asset types in the portfolio

Displaying the Class Files

For a full code listing for the DocAsset class, see "DocPortfolio Class Code Listing" on page 19-26

To use the class, create a folder named <code>@DocPortfolio</code> and save the class code as <code>DocPortfolio.m</code> in this folder. The parent folder of <code>@DocPortfolio</code> must be on the MATLAB path.

Summary of the DocPortfolio Class

This class is defined in one file, DocPortfolio.m, which you must place in an @ folder of the same name. The parent folder of the @DocPortfolio folder must on the MATLAB path. See the addpath function for more information.

The following table summarizes the properties defined for the DocPortfolio class.

DocPortfolio Class Properties

Name	Class	Default	Description
Name	char	1.1	Name of client owning the portfolio
IndAssets	cell	{}	A cell array containing individual asset objects
TotalValue	double	0	Value of all assets (calculated in the constructor method)

The following table summarizes the methods for the DocPortfolio class.

DocBond Class Methods

Name	Description
DocPortfolio	Class constructor
disp	Displays information about this object and calls the DocAsset disp method
pie3	Overloaded version of pie3 function designed to take a single portfolio object as an argument

Property Definition Block

The following code block shows how the properties are defined:

```
properties
   Name = '';
end
properties (SetAccess = private)
   IndAssets = {};
   TotalValue = 0;
end
```

How Class Properties Are Used

- Name Stores the name of the client as a character string. The client's name is passed to the constructor as an input argument.
- IndAsset A cell array that stores asset objects (i.e., DocStock, DocBond, and DocSavings objects). These asset objects are passed to the DocPortfolio constructor as input arguments and assigned to the property from within the constructor function.
- IndAsset The structure of this property is known only to DocPortfolio class member functions so the property's SetAccess attribute is set to private.
- TotalValue Stores the total value of the client's assets. The class constructor
 determines the value of each asset by querying the asset's CurrentValue property
 and summing the result. Access to the TotalValue property is restricted to
 DocPortfolio class member functions by setting the property's SetAccess
 attribute to private.

Using the DocPortfolio Class

The DocPortfolio class is designed to provide information about the financial assets owned by a client. There are three possible types of assets that a client can own: stocks, bonds, and savings accounts.

The first step is to create an asset object to represent each type of asset owned by the client:

```
XYZStock = DocStock('XYZ Stocks',200,12.34);
USTBonds = DocBond('U.S. Treasury Bonds',1600,3.2,2.8);
SaveAccount = DocSavings('MyBank Acc # 123',2000,6);
VictoriaSelna = DocPortfolio('Victoria Selna',...
```

```
XYZStock,...
SaveAccount,...
USTBonds)
```

The DocPortfolio object displays the following information:

VictoriaSelna =

Assets for Client: Victoria Selna

Description: XYZ Stocks

Date: 11-Mar-2008

Type: stock

Current Value: \$2468.00 Number of shares: 200 Share price: \$12.34

Description: MyBank Acc # 123

Date: 11-Mar-2008

Type: savings

Current Value: \$2000.00 Interest Rate: 6.00%

Description: U.S. Treasury Bonds

Date: 11-Mar-2008

Type: bond

Current Value: \$1828.57 Face value of bonds: \$1600

Yield: 3.20%

Total Value: \$6296.57

"The DocPortfolio pie3 Method" on page 19-24 provides a graphical display of the portfolio.

The DocPortfolio Constructor Method

The DocPortfolio constructor method takes as input arguments a client's name and a variable length list of asset objects (DocStock, DocBond, and DocSavings objects in this example).

The IndAssets property is a cell array used to store all asset objects. From these objects, the constructor determines the total value of the client's assets. This value is stored in the TotalValue property:

```
function p = DocPortfolio(name, varargin)
```

```
if nargin > 0
    p.Name = name;
    for k = 1:length(varargin)
        p.IndAssets{k} = varargin(k);
        asset_value = p.IndAssets{k}{1}.CurrentValue;
        p.TotalValue = p.TotalValue + asset_value;
    end
end
end
end
```

The DocPortfolio disp Method

The portfolio disp method lists the contents of each contained object by calling the object's disp method. It then lists the client name and total asset value:

```
function disp(p)
  fprintf('\nAssets for Client: %s\n',p.Name);
  for k = 1:length(p.IndAssets)
     disp(p.IndAssets{k}{1}) % Dispatch to corresponding disp
  end
  fprintf('\nTotal Value: $%0.2f\n',p.TotalValue);
end % disp
```

The DocPortfolio pie3 Method

The DocPortfolio class overloads the MATLAB pie3 function to accept a portfolio object and display a 3-D pie chart illustrating the relative asset mix of the client's portfolio. MATLAB calls the @DocPortfolio/pie3.m version of pie3 whenever the input argument is a single portfolio object:

```
function pie3(p)
% Step 1: Get the current value of each asset
    stock_amt = 0; bond_amt = 0; savings_amt = 0;
    for k = 1:length(p.IndAssets)
        if isa(p.IndAssets{k},'DocStock')
            stock_amt = stock_amt + p.IndAssets{k}.CurrentValue;
        elseif isa(p.IndAssets{k},'DocBond')
            bond_amt = bond_amt + p.IndAssets{k}.CurrentValue;
        elseif isa(p.IndAssets{k},'DocSavings')
            savings_amt = savings_amt + p.IndAssets{k}.CurrentValue;
        end % if
    end % for
% Step 2: Create labels and data for the pie graph
        k = 1;
        if stock_amt ~= 0
```

```
label(k) = {'Stocks'};
      pie vector(k) = stock amt;
      k = k + 1:
   end % if
   if bond amt ~= 0
      label(k) = {'Bonds'};
      pie vector(k) = bond amt;
      k = k + 1;
   end % if
   if savings amt ~= 0
      label(k) = {'Savings'};
      pie vector(k) = savings amt;
% Step 3: Call pie3, adjust fonts and colors
   pie3(pie_vector,label);set(gcf,'Renderer','zbuffer')
   set(findobj(gca, 'Type', 'Text'),...
   'FontSize',14,'FontWeight','bold')
   colormap prism
   stg(1) = {['Portfolio Composition for ',p.Name]};
   stg(2) = {['Total Value of Assets: $',num2str(p.TotalValue,'%0.2f')]};
   title(stg,'FontSize',10)
end % pie3
```

There are three parts in the overloaded pie3 method.

- Step 1 Get the CurrentValue property of each contained asset object and determine the total value in each category.
- Step 2 Create the pie chart labels and build a vector of graph data, depending on which objects are present in the portfolio.
- Step 3 Call the MATLAB pie3 function, make some font and colormap adjustments, and add a title.

Visualizing a Portfolio

You can use a DocPortfolio object to present an individual's financial portfolio. For example, given the following assets:

you can use the class's pie3 method to display the relative mix of assets as a pie chart.

pie3(VictoriaSelna)

Portfolio Composition for Victoria Selna Total Value of Assets: \$6296.57



DocPortfolio Class Code Listing

```
classdef DocPortfolio
   properties
     Name = '';
   properties (SetAccess = private)
      IndAssets = {};
      TotalValue = 0;
   end
   methods
      function p = DocPortfolio(name, varargin)
         if nargin > 0
            p.Name = name;
            for k = 1:length(varargin) % Store objects in a cell array
               p.IndAssets{k} = varargin(k);
               asset_value = p.IndAssets{k}{1}.CurrentValue;
               p.TotalValue = p.TotalValue + asset_value;
            end
```

```
end
      end
      function disp(p)
         fprintf('\nAssets for Client: %s\n',p.Name);
         for k = 1:length(p.IndAssets)
            disp(p.IndAssets{k}{1})
         fprintf('\nTotal Value: $%0.2f\n',p.TotalValue);
      end
      function pie3(p)
         stock amt = 0; bond amt = 0; savings amt = 0;
         for k=1:length(p.IndAssets)
            if isa(p.IndAssets{k}{1}, 'DocStock')
               stock_amt = stock_amt + p.IndAssets{k}{1}.CurrentValue;
            elseif isa(p.IndAssets{k}{1}, 'DocBond')
               bond amt = bond amt + p.IndAssets{k}{1}.CurrentValue;
            elseif isa(p.IndAssets{k}{1}, 'DocSavings')
               savings_amt = savings_amt + p.IndAssets{k}{1}.CurrentValue;
            end
         end
         i = 1;
         if stock amt ~= 0
            label(i) = {'Stocks'};
            pie vector(i) = stock amt;
            i = i + 1;
         end
         if bond amt ~= 0
            label(i) = {'Bonds'};
            pie vector(i) = bond amt;
            i = i + 1;
         end
         if savings amt ~= 0
            label(i) = {'Savings'};
            pie vector(i) = savings amt;
         pie3(pie vector,label)
         set(findobj(gca, 'Type', 'Text'), 'FontSize', 14, 'FontWeight', 'bold')
         set(gcf,'Renderer','zbuffer')
         colormap prism
         stg(1) = {['Portfolio Composition for ',p.Name]};
         stg(2) = {['Total Value of Assets: $',num2str(p.TotalValue,'%0.2f')]};
         title(stg,'FontSize',10)
      end
   end
end
```