


# Updater

## User Guide



Document ID	Updater User Guide
Date	2006-08-23
Version	0.8.1.5
Author	Geert van Horrik
Website	<a href="http://www.gvhsoftware.org">http://www.gvhsoftware.org</a>

## **Disclaimer**

This software is provided by G.C.F. van Horrik and contributors "as is" and any express or implied warranties, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose are disclaimed. In no event shall G.C.F. van Horrik or contributors be liable for any direct, indirect, incidental, special, exemplary, or consequential damage (including, but not limited to, procurement of substitute goods or services; loss of use, data, or profits; or business interruption) however caused and on any theory of liability, whether in contract, strict liability, or tort (including negligence or otherwise) arising in any way out of the use of this software, even if advised of the possibility of such damage.

All rights are reserved. Reproduction in whole or in part is prohibited without the written consent of the copyright owner.

## Preface

I am developing Updater since I needed an easy update feature for other applications I was developing. I noticed that I was constantly copying the source code from one poorly written update solution to another. At that moment, I decided to write an advanced auto-update solution myself since I could not find any free, open source update solutions with the features I needed.

Primarily, I wrote the solution for myself so I could easily add it to my other software projects. But, when surfing the internet, I noticed more and more users were looking for an advanced auto-update solution which was easy to integrate, contained a lot of features and was customizable. I decided to improve Updater and share it with everyone that is interested.

If you have any comments, suggestions or bug reports, don't hesitate to contact me via <http://www.gvhsoftware.org>. I would appreciate it if you want to share your experiences with me so I can keep improving Updater.

Updater is free, and will be free as long as possible. This means I don't want to invest a lot of money into Updater. If you think Updater is useful and you are using it intensively, consider making [a donation](#) so I can keep providing you with new upgrades on Updater.

I also want to thank my girlfriend, Lonneke, for being so patient with me, since I have invested a lot of time in Updater. She also helped me with some ideas to improve Updater and kept me motivated all the time.

Finally, I hope Updater will be useful for you and you will enjoy using it!

Geert van Horrik

# Table of contents

<b>1. INTRODUCTION.....</b>	<b>1</b>
<b>2. FEATURES.....</b>	<b>2</b>
<b>3. STEPS.....</b>	<b>3</b>
3.1. Welcome.....	3
3.2. Check version .....	3
3.3. HTML message.....	3
3.4. License .....	3
3.5. Protection .....	3
3.6. Select update .....	3
3.7. Download.....	4
3.8. Install.....	4
3.9. Finish .....	4
3.10. Rollback .....	4
<b>4. ARCHITECTURE .....</b>	<b>5</b>
<b>5. MODES .....</b>	<b>7</b>
5.1. Full mode.....	7
5.2. Silent (automatic) mode.....	7
5.3. Very silent (automatic) mode .....	7
5.4. Hidden (automatic) mode .....	7
5.5. Restore mode .....	8
<b>6. COMMAND ACTIONS .....</b>	<b>9</b>
6.1. Download.....	9
6.2. Copy .....	9
6.3. Delete .....	9
6.4. Execute .....	9
6.5. Unzip.....	9
6.6. Set File Attributes.....	9
6.7. Register .....	10
6.8. Registry .....	10
6.9. Ini-files.....	10
<b>7. PARAMETERS.....</b>	<b>11</b>
<b>8. FILE LOCATIONS .....</b>	<b>12</b>
<b>9. SERVER EXAMPLE.....</b>	<b>13</b>

<b>10. SETTINGS FILE</b>	<b>15</b>
10.1. Updater	15
10.1.1. Run mode	15
10.1.2. Language	16
10.1.3. Self update	18
10.1.4. Logo small	19
10.1.5. Logo large	20
10.1.6. Icon	21
10.1.7. Custom notify	22
10.1.8. Link color – link	23
10.1.9. Link color – hover	24
10.2. Updateinfo	25
10.2.1. URL	25
10.2.2. Update selector	26
10.2.3. Server time-out	27
10.3. Application	28
10.3.1. Name	28
10.3.2. Version	29
10.3.3. Location	30
10.3.4. Root	31
10.4. Connection	32
10.4.1. Check connection	32
10.4.2. FTP username	33
10.4.3. FTP password	34
10.4.4. HTTP username	35
10.4.5. HTTP password	36
10.5. Proxy	37
10.5.1. Type	37
10.5.2. Username	38
10.5.3. Password	39
10.5.4. HTTP proxy	40
10.5.5. FTP proxy	41
10.5.6. Automatic configuration URL	42
10.6. Custom notify	43
10.6.1. Skin	43
10.6.2. Title color	44

10.6.3. Title rectangle .....	45
10.6.4. Description rectangle .....	46
10.6.5. Close rectangle .....	47
10.6.6. Title font face.....	48
10.6.7. Title font size .....	49
10.6.8. Title font style.....	50
10.6.9. Fade in speed .....	51
10.6.10. Fade out speed.....	52
10.6.11. Show time .....	53
10.6.12. Transparency .....	54
10.6.13. Transparent color.....	55
<b>11. UPDATE FILE .....</b>	<b>56</b>
11.1. XML Template .....	56
11.2. Constants.....	57
11.3. Custom constants.....	58
11.4. Sequenced updating .....	59
11.5. General information .....	61
11.6. Sections .....	64
11.7. Features.....	66
11.8. Files .....	67
11.8.1. Download .....	70
11.8.2. Copy.....	72
11.8.3. Delete.....	73
11.8.4. Execute.....	74
11.8.5. Unzip.....	75
11.8.6. Set File Attributes.....	76
11.8.7. Register .....	77
11.9. Registry .....	78
11.10. Ini .....	79
11.11. Events.....	80
11.11.1. Supported events .....	81
11.11.2. Supported event actions .....	82
11.12. Popup menu.....	90
11.13. HTML message .....	92
11.14. Shortcuts.....	93
11.15. Software protection.....	95

11.15.1. License check .....	96
11.15.2. File hashing .....	97
<b>12. SECTION FILE .....</b>	<b>98</b>
<b>13. SELF UPDATE FILE .....</b>	<b>99</b>
<b>14. USER INTERFACE .....</b>	<b>100</b>
14.1. Customizing .....	100
14.1.1. Full mode .....	100
14.1.2. Silent mode .....	101
14.2. Icon explanation .....	101

## Definitions, acronyms and abbreviations

Word	Explanation
DLL	Dynamic Link Library
FTP	File Transfer Protocol
HTTP	Hyper Text Transfer Protocol
LAN	Local Area Network
OCX	OLE Controle Extension



# 1. Introduction

This document explains all features available in Updater. This document is divided into several chapters to make it as easy as possible to find the information you might be looking for.

All features explained in this user guide can be used in the newest version of Updater. Be sure you are using the right user guide. To find out which user guide version to use, check out the Updater readme. The readme file is included in the Updater package which can be downloaded at <http://www.gvhsoftware.org>.

Only use this document when searching for features of Updater. It is recommended to use [Updater Tool](#) to create the update files. With the tool, it is possible to easily create [update files](#) in a clear, document based, user interface.

The [settings file](#) can also be edited by a tool which is located in the compiled Updater package, which can be downloaded at <http://www.gvhsoftware.org>. It is recommended to use this tool to minimize user errors.

## 2. Features

Updater is an application which enables the user to check if there is a new version available or an application. It is very easy to integrate Updater into any (existing) project. The key-features of Updater are:

- Selective updates
- Event driven with custom actions at each event
- Different user interfaces, from full wizard to hidden modes
- Proxy support
- Rollback & restore to rollback current updates or even restore an older version of the application
- Software protection to prevent users using illegal versions
- Multilingual
- Different (customizable) update actions:
  - Download
  - Copy
  - Run
  - Delete
  - Unzip
  - Set file attributes
  - Register
- Modify registry keys
- Modify ini-files

## 3. Steps

### ***3.1. Welcome***

This step will welcome the user to Updater and explain what actions Updater is going to perform to make sure the products the user is using in combination with Updater will be up-to-date.

### ***3.2. Check version***

Updater will check if there is a new version available. When a new version is available, Updater will show the new (most important) features available in the newest version.

When no new version is available, Updater will quit.

### ***3.3. HTML message***

Updater will show a HTML message in this step. It is possible to set the minimum time the user should take a look at the HTML message. The message can be customized, for example to advertise for some other interesting products available.

### ***3.4. License***

This step can be used to add a license which must be accepted by the user. If the user does not accept the license, he / she can't continue updating.

### ***3.5. Protection***

Software protection is a very important feature of Updater, since a lot of applications are *cracked* nowadays. The protection step checks if the files are not patched by comparing hashes. Also, a custom check method can be used by customizing the protection DLL.

### ***3.6. Select update***

When an application contains different parts, this function can be very useful. For example, an application can have a lot of plug-ins or DLL's. With Updater, it's possible to let the user decide which parts (in Updater, these parts are called [sections](#)) to update at that time.

### ***3.7. Download***

In this step, all files needed for the updates are downloaded.

### ***3.8. Install***

In this step, all actions will be performed to make sure the product gets updated.

### ***3.9. Finish***

Updater will explain to the user that the update is successful.

### ***3.10. Rollback***

This step will be started when the user cancels the update or when an error occurs. In this step, Updater rolls back all the actions already performed in the update to make sure the product will keep working.



After the start-up, the main process is starting a user interface. What kind of user interface is loaded is not important for the main process because all the user interfaces receive the same messages and should response in the same way. The user interface decides whether the user can interact or not. The user interface informs the main process that is it ready to start the next task. The user interface cannot decide which task is started. The main process knows which task is coming next.

The main process starts a new thread with the new task. This task will calculate all the actions necessary and start performing the actions. Again, it is not important what kind of task is started because all the tasks receive the same messages and should send the same messages. The task itself decides if the user should see a progress update or not by sending update progress messages with the status information. After a task has finished, the task will send a final message to the main update process.

These steps are repeated until all tasks are finished. After finishing all tasks, the user interface will send a message that the user wants to end the application by sending it a thread finish message.

Finally, the main process will clean up all objects and remove the temporary folders. The language xml is released and the log is closed. Finally, the main process itself is closed.

As visible, Updater is very flexible because all actions and user interfaces receive and send the same messages. This way, it is very easy to implement a new user interface in a very short amount of time. Most time will be spent to the designing of the new user interface.

Also, when a new task must be added, this is very easy because the other tasks in Updater will still work without adjusting them to the new tasks.

## 5. Modes

There are several different modes available. It is possible to switch to another mode at runtime. An explanation of the modes will follow.

To find out how to set the default mode, read chapter [run mode](#) (10.1.1).

### 5.1. *Full mode*

In this mode, the user will have full control over Updater. Updater will run as a wizard and will guide the user step by step.

The user will see all messages and is able to cancel the update process at any time.

### 5.2. *Silent (automatic) mode*

Silent mode will run in the system tray using icons. Each icon represents a state of the update process. The user is able to view the progress by hovering over the icon. The information will appear in a tooltip.

Each event is introduced by a tooltip balloon with additional information.

When the update is finished, it is possible to enable a popup menu so the user can perform actions using the popup menu.

All steps are started automatically, so the user can't start steps manually.

### 5.3. *Very silent (automatic) mode*

Very silent mode works exactly the same as silent mode. But, Updater will not show the tooltip balloon with additional information at each event.

### 5.4. *Hidden (automatic) mode*

This mode is fully hidden. No user interface is visible to the user. All steps are performed in the background, and there will be no interaction with the user. This means Updater will not ask the user when closing an application, but it will immediately close the application.

All steps are started automatically, so the user can't start steps manually.

This step is recommended for server applications where no users are controlling the computer.

## ***5.5. Restore mode***

Sometimes, it happens that an update contains bugs. In time-critical systems, this can be very dangerous and expensive.

Using this mode (which can only be started using [parameters](#)), the user will be able to restore an older version of the application.

Only use this mode when it is really needed to restore an older version of the product.



## 6. Command actions

To support the most common actions that might be performed when updating an application, Updater supports the actions described in this chapter.

### ***6.1. Download***

This action enables the developer to download files to the client. A detailed description about the implementation of this action can be found in chapter [download](#) (11.8.1).

### ***6.2. Copy***

This action enables the developer to copy a file on the client pc. A detailed description about the implementation of this action can be found in chapter [copy](#) (11.8.2).

### ***6.3. Delete***

This action enables the developer to delete a file on the client pc. A detailed description about the implementation of this action can be found in chapter [delete](#) (11.8.3).

### ***6.4. Execute***

This action enables the developer to execute a file on the client pc. A detailed description about the implementation of this action can be found in chapter [execute](#) (11.8.4).

### ***6.5. Unzip***

This action enables the developer to unzip a file on the client pc. A detailed description about the implementation of this action can be found in chapter [unzip](#) (11.8.5).

### ***6.6. Set File Attributes***

This action enables the developer to set the file attributes of a file on the client pc. A detailed description about the implementation of this action can be found in chapter [set file attributes](#) (11.8.6).

## ***6.7. Register***

This action enables the developer to register a file (OCX or DLL) on the client pc. A detailed description about the implementation of this action can be found in chapter [register](#) (11.8.7).

## ***6.8. Registry***

This action enables the developer to create or change registry settings on the client pc. A detailed description about the implementation of this action can be found in chapter [registry](#) (11.9).

## ***6.9. Ini-files***

This action enables the developer to create or change ini-files on the client pc. A detailed description about the implementation of this action can be found in chapter [ini](#) (11.10).

## 7. Parameters

There are several parameters available to control Updater. Most parameters are used to override the settings in the [settings file](#). When a parameters is available for a specific setting, the parameters is noted at the specified setting.

Some special [modes](#) require special parameters. These are the special parameters not used for settings available in the [settings file](#):

Parameter	Description
-restore	Run in restore mode
-proxysettings	Run in proxy settings mode
-log	View log of the latest update
-checkforupdates	<p>This parameter can be used to check for updates without actually using a UI or update immediately.</p> <p>This can be very useful when an application wants to inform the user that there is a new version available. The user can then start Updater to update the product.</p> <p>Updater return values:</p> <p><b>1</b> New version available.</p> <p><b>2</b> No new version available.</p>
-settingsfile [value]	Custom location of the settings file

When providing additional information with a parameters, use double quotes (" and ") to use data with spaces. It is recommended to always use double quotes. Some examples:

Updater.exe -updatefile test\myfile.xyz	works
Updater.exe -updatefile "test\myfile.xyz"	works
Updater.exe -updatefile my test\myfile.xyz	will not work
Updater.exe -updatefile "my test\myfile.xyz"	works

**Note:** No space is allowed between the minus (-) and the parameter name.

## 8. File locations

Updater needs some different files to work correctly. A list of the available files:

- [Settings file](#)
- [Update file](#)
- [Sections file](#)
- [Self update file](#)

The files should be located as following:



### **Client**

Settings file

Section file



### **Server**

Update file

Self update file \*

---

\* This file is normally hosted by [GVH Software](#). This file should only be hosted on a different location when a custom version of Updater is used.

## 9. Server example

When the updates are finished and the update file is generated by Updater Tool, it is time to put all the files on the server. There are several techniques that can be used, but the user guide will describe the most interesting technique.

This technique described below enables the developer to keep all versions on the server, so even sequenced updates are still available after several new versions.




Figure 9-1 Example of server file lay-out

The figure above shows that for each update, a new directory and new update file is created. This way, the settings file can always point to the newest update file by pointing to updatefile.xml.

When a new version is released, there are only 3 steps to perform:

1. Rename *update.xml* to *update\_[version].xml* so the update stays available when using sequenced updating.
2. Create new folder *update\_[newversion]* and copy the files needed for the update of that specific version to the new folder.
3. Create new *update.xml* file which includes the newest update.

The figure below shows how the server should look like when a new update, 0.5.0.0, is released. The highlighted files and folders are the files that are added and/or changed.




Figure 9-2 Example of server file lay-out after adding a new version

## 10. Settings file

The settings file is created to store settings for Updater. This file should be located in the folder where Updater.exe is located and must be named as settings.ini. There are several settings that can be defined in the settings file.

### 10.1. Updater

This group specifies all the settings for Updater. Use [UPDATER] in settings.ini for this group.

#### 10.1.1. Run mode

The default mode of Updater. This will be the default value, meaning this is the start mode. The mode can be changed at run-time at each [event](#).

##### Setting

runmode

##### Parameter

-mode [value]

##### Type

string

##### Possible values

[full](#)  
[silent](#)  
[verysilent](#)  
[hidden](#)

##### Remarks

Default value is full.

## 10.1.2. Language

Use this option to set the language that Updater will use. The chosen language must be located in the *lng* directory. The name of the xml file (language is located in an xml file) is the same as the name of the language. If the language is not found, Updater will use default language (English).

### Setting

language

### Parameter

-language [value]

### Type

string

### Possible values

[empty]	Automatic language detection
user	User can choose a language at start-up

### Remarks

A list which language will be chosen:

Language xml file	ID	Code	Language description
arabic.xml	unknown	-	-
chinese_simplified.xml	unknown	-	-
czech.xml	0x0405	CSY	Czech
danish.xml	0x0406	DAN	Danish
dutch.xml	0x0413 0x0813	NLD NLB	Dutch (Standard) Belgian (Flemish)
finnish.xml	0x040B	FIN	Finnish
french.xml	0x040C 0x080C 0x0C0C 0x100C	FRA FRB FRC FRS	French (Standard) Belgian Canadian Swiss
german.xml	0x0407	DEU	German (standard)



	0x0807 0x0C07	DES DEA	Swiss Austrian
greek.xml	0x0408	ELL	Greek
hungarian.xml	0x040E	HUN	Hungarian
icelandic.xml	0x040F	ISL	Icelandic
italian.xml	0x0410 0x0810	ITA ITS	Italian (standard) Swiss
lithuanian.xml	unknown	-	-
norwegian.xml	0x0414 0x0814	NOR NON	Norwegian (bokmal) Norwegian (nynorsk)
polish.xml	0x0415	PLK	Polish
portuguese.xml	0x0416	PTB	Portuguese
russian.xml	0x0419	RUS	Russian
slovak.xml	0x041B	SKY	Slovak
spanish.xml	0x040A  0x080A 0x0C0A	ESP  ESM ESN	Spanish (Standard/Traditional)  Mexican Spanish (Modern)
swedish.xml	0x041D	SVE	Swedish
turkish.xml	0x041F	TRK	Turkish

### 10.1.3. Self update

If the updates of Updater are hosted on another server than the default one, the location can be specified here.

#### Setting

selfupdate

#### Parameter

-selfupdatelocation [value]

#### Type

string

#### Possible values

Location of a file, located on a local or remote computer.

#### Remarks

Only use this feature when the default self update feature is not working.

### 10.1.4. Logo small

Use this option to customize the small logo at the top of Updater when running in [full mode](#).

#### Setting

logosmall

#### Type

string

#### Possible values

Location of a local file.

### 10.1.5. Logo large

Use this option to customize the large logo at the left of Updater when running in [full mode](#).

#### Setting

logolarge

#### Type

string

#### Possible values

Location of a local file.

### 10.1.6. Icon

Use this option to customize the default icon used by Updater. This will not replace the icons used to display the download and install progress in [silent](#) or [very silent](#) mode.

#### Setting

icon

#### Type

string

#### Possible values

Location of a local file.

### 10.1.7. Custom notify

Use this option to enable the custom notify messages in [silent mode](#).

#### Setting

customnotify

#### Type

boolean

#### Possible values

true  
false

### 10.1.8. Link color – link

Use this option to customize the link color of all the hyperlinks in Updater.

#### Setting

linkcolorlink

#### Type

RGB Color

#### Possible values

For each color group, a number between 0 and 255 can be used.

#### Remarks

Default color is light blue (R175, G175, B255).

### 10.1.9. Link color – hover

Use this option to customize the hover color of all the hyperlinks in Updater.

#### Setting

linkcolorhover

#### Type

RGB Color

#### Possible values

For each color group, a number between 0 and 255 can be used.

#### Remarks

Default color is blue (R0, G0, B255).



## ***10.2. Updateinfo***

This group specifies all the settings of the update info. Use [UPDATEINFO] in settings.ini for this group.

### **10.2.1. URL**

This option represents the location of the file with all update information. This option should be an URL or a file on the hard-disk. An example is *c:\updater\list.xml* or *http://www.gvhsoftware.org/updatelist.xml*.

#### **Setting**

url

#### **Parameter**

-updatefile [value]

#### **Type**

string

#### **Possible values**

Location of a file, located on a local or remote computer.

### 10.2.2. Update selector

Some products are released in different editions like professional and enterprise. This setting can include a dll which includes a function with this header:

```
string SelectUpdate();
```

This function will be called. In this function, the developer is able to determine which update file should be used for the installed version. The return value is the update file that should be used for Updater.

#### Setting

updateselector

#### Parameter

-updateselector [value]

#### Type

string

#### Possible values

Location of a file, located on a local or remote computer.

#### Remarks

When this setting is used, the setting [URL](#) is not required.

### 10.2.3. Server time-out

It is always possible that a server is not available. To prevent Updater to wait forever, it is possible to set the time-out time for a server. When the server is very fast, a short time-out time can be used. This way, the user won't have to wait a long time, until the default time-out is called.

#### Setting

servertimeout

#### Parameter

-timeout [value]

#### Type

integer

#### Possible values

Any integer value, value is parsed in milliseconds (1 second = 1000 ms).

#### Remarks

Default value is 5000 (5 seconds).

## ***10.3. Application***

This group specifies all the settings for the application. Use [APPLICATION] in settings.ini for this group.

### **10.3.1. Name**

The name of the application is used to inform the user that this application is being updated. It is possible that two (or even more) update processes of different applications are running. With the name, the user knows exactly which application he/she is currently updating.

#### **Setting**

name

#### **Parameter**

-appname [value]

#### **Type**

string

#### **Possible values**

Any string value

### 10.3.2. Version

This setting sets the current version of the application that will be updated. Updater needs a version to compare with the newest version. It is also possible to add a filename, for example %app%\MyApplication.exe. If the file exists, Updater will check the version of the application itself by reading the executable or dll information. If the file is not available on the hard-disk, Updater will handle this value as the current version.

#### Setting

version

#### Parameter

-appversion [value]

#### Type

string

#### Possible values

Version number (for example 2.4)

Location of an executable or dll on the hard-disk.

#### Remarks

Updater can parse some different version separators:

Version separator	Example
.	4.3.1
,	4,3,1
_	4_3_1
	4 3 1
-	4-3-1
[space]	4 3 1

### 10.3.3. Location

This setting will be used to get a valid value for the %app% [constant](#). Also, this value will be used to close the application and to start it again if requested. This value must contain the location of an executable.

**Setting**

location

**Parameter**

-applocation [value]

**Type**

string

**Possible values**

Location of a local file.

**Remarks**

It is not possible to use %approot% constants here, because the %app% variable is retrieved from this setting. If this field is left blank, %app% cannot be used anywhere in the [update file](#).

### 10.3.4. Root

Sometimes, the root of an application differs from the real application executable path. Therefore, this value can be used. This value is available in the update file using the %aproot% [constant](#). When this value is empty, %aproot% will have the same value as %app%.

#### Setting

root

#### Parameter

-aproot [value]

#### Type

string

#### Possible values

Local path.

#### Remarks

If this field is left blank, %aproot% will have the same value as %app%.

## **10.4. Connection**

This group specifies all the settings for the connection. Use [CONNECTION] in settings.ini for this group.

### **10.4.1. Check connection**

It is possible to check if the user is connected to the internet before starting with any update. When Updater is used in a LAN, this value should be false.

#### **Setting**

checkconnection

#### **Parameter**

-checkconnection

#### **Type**

boolean

#### **Possible values**

true  
false

#### **Remarks**

Default value is false.



## 10.4.2. FTP username

FTP username which can be used to authenticate a user to an FTP server.

### Setting

ftpusername

### Parameter

-ftpusername

### Type

string

### Possible values

Any string value.

### 10.4.3. FTP password

FTP password which can be used to authenticate a user to an FTP server.

**Setting**

ftppassword

**Parameter**

-ftppassword

**Type**

string

**Possible values**

Any string value.

### 10.4.4. HTTP username

HTTP username which can be used to authenticate a user to a HTTP server.

**Setting**

httpusername

**Parameter**

-httpusername

**Type**

string

**Possible values**

Any string value.

### 10.4.5. HTTP password

HTTP password which can be used to authenticate a user to a HTTP server.

**Setting**

httppassword

**Parameter**

-httppassword

**Type**

string

**Possible values**

Any string value.

## 10.5. Proxy

This group specifies all the settings for the proxy the user might be behind. Use [PROXY] in settings.ini for this group.

To enable the client user to change these settings in a user-friendly way, see the chapter about [parameters](#).

### 10.5.1. Type

This will set the proxy type. There are four types available:

Name	Description
directconnection	A direct connection to the target URL will be made.
autodetect	The proxy server will be auto detected. This is the default and most used value.
manual	It is also possible to specify the http and ftp proxies manual. Use this value to enable the manual proxy type.
autoconfigurl	When an auto config url is used, use this value to select this type.

#### Setting

type

#### Type

string

#### Possible values

directconnection  
autodetect  
manual  
autoconfigurl

#### Remarks

Default value is autodetect.

## 10.5.2. Username

The username to authenticate the client to his / her proxy server. This setting must be provided by the client user.

### Setting

username

### Type

string

### Possible values

Any string value.

### 10.5.3. Password

The password to authenticate the client to his / her proxy server. This setting must be provided by the client user.

#### Setting

password

#### Type

string

#### Possible values

Any string value.

### 10.5.4. HTTP proxy

This setting can be used to specify a manual HTTP proxy server.

#### Setting

http

#### Type

string

#### Possible values

The format is [IP]:[PORT], for example 127.0.0.1:80.

#### Remarks

This setting is only required when [proxy type](#) is manual.



### 10.5.5. FTP proxy

This setting can be used to specify a manual FTP proxy server.

#### Setting

ftp

#### Type

string

#### Possible values

The format is [IP]:[PORT], for example 127.0.0.1:80.

#### Remarks

This setting is only required when [proxy type](#) is manual.

### 10.5.6. Automatic configuration URL

This setting can be used to specify an automatic configuration URL.

**Setting**

autoconfigurl

**Type**

string

**Possible values**

Any string value.

**Remarks**

This setting is only required when [proxy type](#) is autoconfigurl.

## ***10.6. Custom notify***

This group specifies all the settings for the custom notification. Use [NOTIFY] in settings.ini for this group.

Custom notifications are only available for [silent mode](#).

### **10.6.1. Skin**

The skin that will be used for the custom notifications. Normally, this is a bitmap which contains some space for a title and description.

#### **Setting**

skin

#### **Type**

string

#### **Possible values**

Name of a bitmap file located in the same folder as the Updater executable.

## 10.6.2. Title color

The color of the title text.

### Setting

titlecolor

### Type

RGB Color

### Possible values

For each color group, a number between 0 and 255 can be used.

### Remarks

Default color is black (R255, G255, B255).

### 10.6.3. Title rectangle

The rectangle where the title will be shown. This rectangle is relative to the bitmap's left top position.

#### Setting

titlirect

#### Type

rectangle

#### Possible values

Any rectangle value

#### Remarks

The rectangle should be formatted like:  
[LEFT], [TOP], [RIGHT], [BOTTOM]  
0, 0, 150, 150

### 10.6.4. Description rectangle

The rectangle where the description will be shown. This rectangle is relative to the bitmap's left top position.

#### Setting

descriptionrect

#### Type

rectangle

#### Possible values

Any rectangle value

#### Remarks

The rectangle should be formatted like:  
[LEFT], [TOP], [RIGHT], [BOTTOM]  
0, 0, 150, 150

### 10.6.5. Close rectangle

The rectangle where the user is able to close the notification. This rectangle is relative to the bitmap's left top position.

#### Setting

closerect

#### Type

rectangle

#### Possible values

Any rectangle value

#### Remarks

The rectangle should be formatted like:  
[LEFT], [TOP], [RIGHT], [BOTTOM]  
0, 0, 150, 150

### 10.6.6. Title font face

The font face for the title text.

#### Setting

titlefontface

#### Type

string

#### Possible values

Any available font face name

#### Remarks

Default value is verdana.



### 10.6.7. Title font size

The font size for the title text.

#### Setting

titlefontsize

#### Type

integer

#### Possible values

Any font size

#### Remarks

Default value is 12.

## 10.6.8. Title font style

The font style for the title text.

### Setting

titlefontstyle

### Type

string

### Possible values

A combination of these values:

Value
Underline
Italic
Bold
Strikeout

An example of a combination of values:

***bold italic***

### 10.6.9. Fade in speed

The fade in speed of the notification.

#### Setting

speedfadein

#### Type

integer

#### Possible values

A value between 1 and 255 where 1 is slow and 255 is fast.

#### Remarks

Default value is 10.

### 10.6.10. Fade out speed

The fade out speed of the notification.

#### Setting

speedfadeout

#### Type

integer

#### Possible values

A value between 1 and 255 where 1 is slow and 255 is fast.

#### Remarks

Default value is 10.

### 10.6.11. Show time

The time the notification will be shown to the user. The user can close the notification when a valid [close rectangle](#) is provided. This value will make sure the notification will be closed after a specific period of time.

When the user is hovering the notification, the time will be paused so the user can keep the notification up as long as he / she wants.

#### Setting

showtime

#### Type

integer

#### Possible values

Any integer value, value is parsed in milliseconds / 10 (1 second = 1000 / 10 ms).

#### Remarks

Default value is 30 (3 seconds).

## 10.6.12. Transparency

The transparency of the notification.

### Setting

transparency

### Type

integer

### Possible values

A value between 1 and 255 where 1 is fully transparent and 255 is fully visible.

### Remarks

Default value is 200.

### 10.6.13. Transparent color

The color in the bitmap that should be removed from the bitmap. At all the locations where this color is located, the color will be replaced by the desktop background.

#### Setting

transparentcolor

#### Type

RGB Color

#### Possible values

For each color group, a number between 0 and 255 can be used.

#### Remarks

Default color is purple (R255, G0, B255).

## 11. Update file

The update file contains all the actions that will be performed by Updater to update the product.

This chapter will explain all the XML codes that should be used inside the update file. It is recommended to use [Updater Tool](#) to create the update files instead of writing the XML files by hand.

### 11.1. XML Template

The update file must have this format:

```
<?xml version="1.0" ?>
<UPDATEINFO>

</UPDATEINFO>
```



## 11.2. Constants

There are some default constants that can be used inside the update file. All constants are listed in the table below. When a value is needed which is not in the list, a [custom constant](#) can be defined.

Code	Directory
%app%	Application pathname
%approot%	Application root folder
%updater%	Pathname to Updater program
%updatertemp%	Pathname to Updater temp. All files will be downloaded to this folder. The pathname is constructed by appending \updater_temp to the system temp path
%temp%	Pathname to the system temp
%programfiles%	Pathname to System Program Files Path (same as %ProgramFiles% environment variable)
%system%	Pathname to System Files Path (same as %SystemRoot% environment variable)
%appdata%	Pathname to Application Data path
%userprofile%	Pathname to User Home directory
%commonappdata%	Pathname to Common Application Data path
%quicklaunchcurrentuser%	Pathname to the quick launch menu of current user
%quicklaunchallusers%	Pathname to the quick launch menu of all users
%menustartcurrentuser%	Pathname to the start menu of current user
%menustartallusers%	Pathname to the start menu of all users
%desktopcurrentuser%	Pathname to the desktop of current user
%desktopallusers%	Pathname to the desktop of all users
%windowsdirectory%	Pathname to the windows directory
%updateserver%	Location of the server where the update file is located
%updateserverpath%	Location of the update file folder on the server
%updateserverfile%	Location of the update file on the server

### 11.3. Custom constants

Constants can be used inside the update file to make the file more flexible. For example, it is very wise to store the web server location in a constant. When the address of the web server changes, the address only have to be changed once (which is the constant value).

The section of the constants must be defined as following:

```
<?xml version="1.0" ?>
<UPDATEINFO>

  <CONSTANTS>
    <CONSTANT name="%site%" value="http://www.site.com"></CONSTANT>
    <CONSTANT name="%version%" value="0.8.1.5"></CONSTANT>
  </CONSTANTS>

</UPDATEINFO>
```

When using constants, `%[CONSTANT]%` must be used (percentages surrounding the constants). It is even possible to override (re-assign) the default [constants](#), but this is not recommended.

The custom constants can only be used inside the update file. It is possible to use Updater defined constants in your constants, like:


```
<CONSTANT name="%myfile%" value="%programfiles%\File.exe"></CONSTANT>
```

Object	Type	Possible values
name	%string%	Any string value
value	string	Any string value

Object	Description
name	The name of the constant as it can be used inside the update file. This value should be surrounded by %. If the % are not used, Updater will add them when parsing the update file.
value	The value of the constant.

## 11.4. Sequenced updating

It is possible to update a product in sequences. This means the user can be obligated to update from version 0.1 to 0.4 in sequences. An example is given by the image below:



To use sequenced updating, all update files (also the older versions) should be located on the server.

Sequenced updates should be formatted as following:

```
<?xml version="1.0" ?>
<UPDATEINFO>

  <SEQUENCE>
    <MINIMUMVERSION>0.5.1.9</MINIMUMVERSION>
    <LOCATION>http://www.site.com/update_0.5.1.9.xml</LOCATION>
  </SEQUENCE>

</UPDATEINFO>
```

Updater will first read this part of the update file. If the current application version does not match at least the minimumversion in the update file, Updater will download the file located at the location element. This way, it is possible to create a chain of update files which will lead to the very first update which has no sequence fields or where the current application version matches the minimumversion field.

**Note:**

You can't use constants in this part of the update file.

Object	Type	Possible values
minimumversion	String	<a href="#">Version string</a>
location	String	Any string value

Object	Description
minimumversion	The minimum version required for the update.
location	The location of the previous update file that should be used when the user application version does not match the minimum version.

## 11.5. General information

This part of the update file contains all the general information needed by Updater. The general part must be formatted as following:

```
<?xml version="1.0" ?>
<UPDATEINFO>

  <GENERAL>
    <VERSION>0.8.1.5</VERSION>
    <CLOSEAPPLICATION>>false</CLOSEAPPLICATION>
    <CHECKSEPARATELY>>true</CHECKSEPARATELY>
    <ENABLEROLLBACK>>true</ENABLEROLLBACK>
    <LICENSE>You must agree to this license</LICENSE>
  </GENERAL>

</UPDATEINFO>
```


Object	Type	Possible values
version	string	<a href="#">Version string</a>
closeapplication	boolean	True False Restart Restartsystem Restartsystemapp User
checkseparately	boolean	True False
enablerollback	boolean	True False
showerrors	boolean	True False
selfupdate	boolean	True False
resumedownloads	boolean	True False
license	string	Any string value
forceupdate	boolean	True False

Object	Description
version	The new version of the application.
closeapplication	<p>Use this option to close the application that will be updated:</p> <p><b>True</b> the application needs to be closed</p> <p><b>False</b> the application does not need to be closed</p> <p><b>Restart</b> the application should close, but also start again after the update process</p> <p><b>Restartsystem</b> application is closed. System should be restarted after update</p> <p><b>Restartsystemapp</b> application is closed. System should be restarted after update, application should be loaded at first start up</p> <p><b>User</b> the user must close the application himself</p>
checkseparately	<p>If true, each file is version or date checked. Only the needed files are downloaded.</p> <p>Default, this value is false.</p>
enablerollback	<p>If true, all actions are rolled back when an error occurs or the user cancels the process.</p> <p>Default, this value is false.</p>
showerrors	<p>If true, errors will be notified to the user. If not, when an error occurs, Updater will jump to hidden mode and finish rollback.</p> <p><b>Note:</b> be aware that user will not know that an error occurred</p>
selfupdate	<p>If true, Updater will check if there is a new version for Updater and update itself if possible.</p> <p>Default, this value is true.</p> <p><b>Note:</b> Updater will update itself after the update of the application.</p>
resumedownloads	<p>If true, Updater will resume downloads if possible. This is useful when the internet connection is interrupted when downloading large files.</p>

	Default, this value is true.
license	The license that will be shown in the <a href="#">license step</a> .
forceupdate	<p>If true, user will not be able to stop the update after he starts it.</p> <p>Default, this value is false.</p> <p><b>Note:</b> After each task, the eventaction startnexttask must be used to step to the next task.</p>

## 11.6. Sections

Sections can be very handy when using different parts in an application. The image below shows an example of a situation where sections can be used:



It is possible to let the user decide which sections to update and which should not be updated. It is also possible to oblige the user to install one or more sections. The user can select sections in the [select update](#) step.

Sections can be added to the update file using the following formatting:

```
<?xml version="1.0" ?>

<SECTIONS>
  <SECTION name="main" title="Main application files" version="1.0"
    check="true" enabled="true" description="The main
    application files for application MyApplication"
    url="www.site.com/sections/main_info.html">
  </SECTION>
</SECTIONS>

</UPDATEINFO>
```

Object	Type	Possible values
name	string	Any string value
title	string	Any string value
check	boolean	True



		False
version	string	<a href="#">Version string</a>
enabled	boolean	True False
description	string	Any string value
url	string	Any string value

Object	Description
name	The name of the section as it can be used inside the update file to add a file or action to a specific section.
title	The title of the section as it will be available for the user.
check	If true, the section will be checked in the tree control where the user can select the sections to update.  Default, this value is true.
version	The newest version of the section.
enabled	If true, the section will be enabled so the user can check the update state of the section.  Default, this value is true.
description	The description of the section. The user will be able to read the description when he / she clicks on the section in the tree control.
url	When the description is too short, this url can be used to link the user to a website with more information about the section. When this value is used, Updater will add a link to the section description.

## 11.7. Features

When there is a new update available, Updater can show some of the most important features to the user.

When features are used, the following formatting must be used:

```
<?xml version="1.0" ?>
<UPDATEINFO>

  <FEATURES>
    <FEATURE>
      <TEXT>Feature 1</TEXT>
      <LINK>http://www.gvhssoftware.org/product/feature1.html</LINK>
    </FEATURE>
    <FEATURE>
      <TEXT>Feature 2</TEXT>
    </FEATURE>
  </FEATURES>

</UPDATEINFO>
```

It is possible to enable the user to read more information about a specific feature. This can be done by using the link object inside the feature element. When only the text object is used, the feature will be visible, but not clickable.

**Note:** The maximum amount of features that can be added to the update file is 5.

Object	Type	Possible values
text	string	Any string value
link	string	Any string value

Object	Description
text	The text of the new feature. Keep it short and simple.
link	The url of the location where the user can read some detailed information about the feature.

## 11.8. Files

Updater works with files which need to be updated. Each file can contain one or more file actions which makes sure the file will get updated.

To insert the general files section, use the following formatting:

```
<?xml version="1.0" ?>
<UPDATEINFO>

  <FILES>
  </FILES>

</UPDATEINFO>
```

Each file must at least use the following formatting:

```
<FILES>
  <FILE name="CD Database" location="%app%\CD Database.exe"
    version="0.1.0.0" check="version">
  </FILE>
</FILES>
```

Object	Type	Possible values
name	string	Any string value
check	string	Date Datetime Version Hash
location	string	Any string value
version	string	<a href="#">Version string</a>
date	date / time	Any date / time value
hash	MD5 file hash	Any MD5 file hash
section	string	Any existing <a href="#">section</a>

Object		Description
name		The name of the file as it will be used for progress updates to the user.
check	<sup>†</sup>	<p>The way Updater should check this file.</p> <p><b>Date</b> The files will be compared using the date of the files. The date is formatted as <i>yyyy-mm-dd</i>.</p> <p><b>Datetime</b> The files will be compared using the date and time of the files. The date and time is formatted as <i>yyyy-mm-dd/hh:mm:ss</i></p> <p><b>Version</b> The files will be compared using the version of the files.</p> <p><b>Hash</b> The files will be compared using the MD5 hash of the files.</p>
location	<sup>‡</sup>	The location of the file on the client pc. The location of the file is used for the calculation of the current date, date / time, version or hash of the file.
version	<sup>§</sup>	The newest version of the file.
date	<sup>**</sup>	The newest date or date / time of the file. When this value is empty, Updater will automatically retrieve the date / time of the file on the internet.
hash	<sup>††</sup>	The MD5 file hash of the newest file.
section	<sup>‡‡</sup>	The name of the section where this file belongs to.

---

<sup>†</sup> This field is only required when [checkseparately](#) is used.

<sup>‡</sup> This field is only required when check value is not empty.

<sup>§</sup> This field is only required when check value is **version**.

<sup>\*\*</sup> This field is only required when check value is **date** or **datetime**.

<sup>††</sup> This field is only required when check value is **hash**.

<sup>‡‡</sup> This field is only required when [sections](#) are used and this field must belong to a specific section.

There are several file actions supported in Updater. Each action is explained in this chapter and each action will be briefly explained.

Each action must use the following formatting:

```
<FILE ...>
  <ACTION type="actiontype"></ACTION>
</FILE>
```

**Note:** All actions are performed in the order they appear in the update file.

Object	Type	Possible values
type	string	File action type

Object	Description
type	The file action type. Each action explained in this chapter contains the action type to use for this field.

### 11.8.1. Download

This action can be used to download a file to the pc of the user. The file will be downloaded to the *%updatertemp%* folder.

It is possible to add mirrors (multiple download locations) by adding more location fields to this action. It is wise to add the fastest servers at the top. If the file does not exist on the server, or the server is unreachable, Updater will use the next download location. There is a maximum of 100 download locations for each download action. The locations are used in the order they appear in the updater file.

Some servers require authentication. To identify a user to the server, use the [%\[protocol\]username%](#) and [%\[protocol\]password%](#) variables in the location value.

The following formatting must be used:

```
<FILES>
  <ACTION type="download">
    <DESTINATION>setup/cddb.exe</DESTINATION>
    <LOCATION>%primarysite%/setup/cddb.exe</LOCATION>
    <LOCATION>%mirror1%/setup/cddb.exe</LOCATION>
  </ACTION>
</FILES>
```

Object	Type	Possible values
destination	string	Any string value
location	string	Any string value

Object	Description
destination	<p>The destination of the download action. There are three ways to use this field:</p> <p><b>1) Leave it empty</b>            Updater will strip the filename and use it as download destination. The example will be downloaded to <i>%updatertemp%\cddb.exe</i>.</p> <p><b>2) Relative path</b>            Updater will add this path to the <i>%updatertemp%</i> folder. For example, when <i>test</i> is used, Updater will download the example to <i>%updatertemp%\test\cddb.exe</i>.</p> <p>It is also possible to add a filename to the destination to rename the file when downloading.</p>

	<p><b>3) Full path</b></p> <p>Updater will use this full path to store the file. When no filename is used in the full path, Updater will use the original filename.</p> <p>It is also possible to add a filename to the destination to rename the file when downloading.</p>
location	<p>The location of the file on the internet. Updater will use the filename to store it on the hard-disk.</p> <p>For example, <i>http://www.site.com/files/myfile.exe</i> will be downloaded to <i>%updatertemp%\myfile.exe</i>.</p>

## 11.8.2. Copy

This action can be used to copy a file.

The following formatting must be used:

```
<FILES>
  <ACTION type="copy">
    <OLDLOCATION>%updatertemp%\cddb.exe</OLDLOCATION>
    <NEWLOCATION>%app%\cddb.exe</NEWLOCATION>
    <OVERWRITE>true</OVERWRITE>
  </ACTION>
</FILES>
```

Object	Type	Possible values
oldlocation	string	Any string value
newlocation	string	Any string value
overwrite	boolean	True False

Object	Description
oldlocation	The old location of the file.
newlocation	The new location of the file.
overwrite	If true, Updater will overwrite the file when it already exists. If false, Updater will not overwrite the file when it already exists.  Default, this value is false.



### 11.8.3. Delete

This action can be used to delete a file.

The following formatting must be used:

```
<FILES>
  <ACTION type="delete">
    <LOCATION>%updatertemp%\cddb.exe</LOCATION>
    <ASKUSER>true</ASKUSER>
  </ACTION>
</FILES>
```

Object	Type	Possible values
location	string	Any string value
askuser	boolean	True False

Object	Description
location	The location of the file that should be deleted.
askuser	If true, Updater will ask the user to confirm the deletion of the file. If false, Updater will delete the file without asking the user for confirmation.  Default, this value is true.

## 11.8.4. Execute

This action can be used to execute a file.

The following formatting must be used:

```
<FILES>
  <ACTION type="run">
    <LOCATION>%app%\cddb.exe</LOCATION>
    <PARAMETERS>-p "c:\program files\" -s</PARAMETERS>
    <WAIT>true</WAIT>
  </ACTION>
</FILES>
```

Object	Type	Possible values
location	string	Any string value
parameters	string	Any string value
wait	boolean	True False

Object	Description
location	The location of the file that should be executed.
parameters	The parameters that should be used when executing the file. This value is not required.
wait	If true, Updater will wait until the execution is finished and then continue updating. If false, Updater will execute the file and continue updating immediately.  Default, this value is true.

## 11.8.5. Unzip

This action can be used to unzip a file.

The following formatting must be used:

```
<FILES>
  <ACTION type="unzip">
    <LOCATION>%updatertemp%\MyZipFile.zip</LOCATION>
    <DESTINATION>%app%\MyZipFolder\</DESTINATION >
  </ACTION>
</FILES>
```

Object	Type	Possible values
location	string	Any string value
destination	string	Any string value

Object	Description
location	The location of the zip file that needs to be unzipped.
destination	The destination folder where the files will be unzipped to.

## 11.8.6. Set File Attributes

This action can be used to set the file attributes for a file or folder.

The following formatting must be used:

```
<FILES>
  <ACTION type="setfileattr">
    <LOCATION>%updatertemp%\MyZipFile.zip</LOCATION>
    <ATTRIBUTES>system readonly</ATTRIBUTES>
  </ACTION>
</FILES>
```

Object	Type	Possible values
location	string	Any string value
attributes <sup>§§</sup>	File or folder attribute	Hidden Readonly System Archive Compressed

Object	Description
location	The location of the file or folder that will get the new attributes.
attributes	One or more attributes for the file or folder.

---

<sup>§§</sup> A combination of several attributes is also possible.

### 11.8.7. Register

This action can be used to register a file. This action can be very useful when a DLL file or OCX file needs to be registered.

The following formatting must be used:

```
<FILES>
  <ACTION type="register">
    <LOCATION>%app%\MyControl.ocx</LOCATION>
    <ASKUSER>true</ASKUSER>
  </ACTION>
</FILES>
```

Object	Type	Possible values
location	string	Any string value
askuser	boolean	True False

Object	Description
location	The location of the file that needs to be registered.
askuser	If true, Updater will ask if the user wants to register the file. If not, Updater will register the file without asking the user for confirmation.  Default, this value is true.

## 11.9. Registry

This part alters or creates registry entries.

When the registry must be altered, the following formatting must be used:

```
<?xml version="1.0" ?>
<UPDATEINFO>

  <REGISTRY>
    <ITEM type="string">
      <KEY>HKEY_LOCAL_MACHINE\SOFTWARE\CD Database\Version</KEY>
      <VALUE>0.0.0.1</VALUE>
    </ITEM>
  </REGISTRY>

</UPDATEINFO>
```

Object	Type	Possible values
type	registry entry type	String Binary Dword
key	string	Registry key
value	string	Any string value

Object	Description
type	The type of the registry entry. Default, this value is string.
key	Complete key of the registry. Updater will split this value into separate parts itself
value	The value of the registry entry.

## 11.10. Ini

This part alters or creates ini-file entries.

When an ini-file must be altered, the following formatting must be used:

```
<?xml version="1.0" ?>
<UPDATEINFO>

  <INI>
    <ITEM>
      <LOCATION>%app%\settings.ini</LOCATION>
      <GROUP>app_info</GROUP>
      <KEY>version</KEY>
      <VALUE>0.0.0.1</VALUE>
    </ITEM>
  </INI>

</UPDATEINFO>
```

The object names are name as following:

```
[GROUP]
Key=value
```

Object	Type	Possible values
location	string	Any string value
group	string	Any string value
key	string	Any string value
value	string	Any string value

Object	Description
location	The location of the ini-file that contains the entry that should be altered.
group	Group in the ini-file.
key	The key in the ini-file.
value	The value of the key in the ini-file.

## 11.11. Events

Events are a very powerful extension to Updater. To enable events, use the following formatting:

```
<?xml version="1.0" ?>
<UPDATEINFO>

  <EVENTS>
  </EVENTS>

</UPDATEINFO>
```



### 11.11.1. Supported events

These events are supported:

Name	Fired when / Description
OnNewVersion	Fired when a new version is found.
OnNoNewVersion	Fired when no new version is found.
BeforeHtmlMessage	Fired before the user sees the html message.
AfterHtmlMessage	Fired after the user leaves the html message.
BeforeLicense	Fired before the user accepts the license agreements.
AfterLicense	Fired after the user accepted the license agreements.
BeforeProtection	Fired before the software protection starts.
AfterProtection	Fired when the software protection is finished successful.
BeforeSelectUpdate	Fired before the user can select the sections to update.
AfterSelectUpdate	Fired after the user has selected the sections to update.
BeforeDownload	Fired before files are downloaded.
AfterDownload	Fired after files are downloaded.
BeforeInstall	Fired before files are installed.
AfterInstall	Fired after files are installed.
BeforeRollback	Fired before changes are rolled back.
AfterRollback	Fired after changes are rolled back.
OnClose	<p>Will be fired only after a successful update of the application. This way, it is possible to execute files which will overwrite the Updater executable.</p> <p>Keep in mind that if the user cancels this process, no rollback will be performed.</p>

### 11.11.2. Supported event actions

There are several event actions supported in Updater. Each action is explained and each action will contain a small example.

Each event action must at least use the following formatting:

```
<?xml version="1.0" ?>
<UPDATEINFO>

  <EVENTS>
    <ACTION type="actiontype"></ACTION>
  </EVENTS>

</UPDATEINFO>
```

Object	Type	Possible values
type	string	Event action type

Object	Description
type	The event action type. Each action explained in this chapter contains the action type to use for this field.

#### 11.11.2.1. Close

This action will close Updater immediately. The user will not be asked for any confirmation.

The following formatting must be used:

```
<EVENTS>  
  <ACTION type="close"></ACTION>  
</EVENTS>
```

#### 11.11.2.2. Skip next task

This action can be used to skip tasks. For example, the install step can be skipped when only files need to be downloaded and executed when Updater quits.

The following formatting must be used:

```
<EVENTS>  
  <ACTION type="skipnexttask"></ACTION>  
</EVENTS>
```

### 11.11.2.3. Set mode

This action switches the [run mode](#) of Updater at runtime.

The following formatting must be used:

```
<EVENTS>
  <ACTION type="setmode">
    <MODE></MODE>
  </ACTION>
</EVENTS>
```

Object	Type	Possible values
mode	Run mode	Full Silent Verysilent Hidden

Object	Description
mode	The mode where Updater will change to. See chapter <a href="#">modes</a> for more information about the modes available in Updater.

#### 11.11.2.4. Execute file

This action can be used to execute a file at an event. Updater will not wait until the application closes again, but will continue immediately.

The following formatting must be used:

```
<EVENTS>
  <ACTION type="run">
    <LOCATION>%updatertemp%\setup.exe</LOCATION>
    <PARAMETERS></PARAMETERS>
  </ACTION>
</EVENTS>
```

Object	Type	Possible values
location	string	Any string value
parameters	string	Any string value

Object	Description
location	The location of the file that should be executed.
parameters	The parameters that should be used when executing the file. This value is not required.

#### 11.11.2.5. Start next task

This action can be used to start next tasks. This can be useful when the installation should start immediately after downloading the files. This way, [full mode](#) can be automated.

The following formatting must be used:

```
<EVENTS>  
  <ACTION type="startnexttask"></ACTION>  
</EVENTS>
```

**Note:** Only use this action in [full mode](#) since the other modes are already automatic.

### 11.11.2.6. Close application

This action can be used to close other applications, for example internet explorer windows. This action can also be very useful when an application consists of multiple executables. Since the [restartapplication](#) option can only close only one executable, this action can be very useful.

The following formatting must be used:

```
<EVENTS>
  <ACTION type="closeapplication">
    <TITLE>Internet Explorer</TITLE>
    <FILENAME>iexplore.exe</FILENAME>
    <ASKUSER>true</ASKUSER>
  </ACTION>
</EVENTS>
```

Object	Type	Possible values
title	string	Any string value
filename	string	Any string value
askuser	boolean	True False

Object	Description
title	The title that will be used to inform the user about the application that is going to be closed.  For example, use Internet Explorer for iexplore.exe.
filename	The filename of the application that must be closed.  This value must contain a full path, but some applications (such as iexplore.exe) can be closed without a path.
askuser	If the user should be asked for confirmation, this value must be true. If false, Updater will close the application immediately without asking.  Default, this value is true.



### 11.11.2.7. Show notifier

This action can be used to show the [custom notifies](#) with custom text. The notifier will override the default Updater messages.

The following formatting must be used:

```
<EVENTS>
  <ACTION type="shownotifier">
    <TITLE>Custom notification</TITLE>
    <DESCRIPTION>This is the description</DESCRIPTION>
  </ACTION>
</EVENTS>
```

Object	Type	Possible values
title	string	Any string value
description	string	Any string value

Object	Description
title	The title that will be used for the notification. Keep it short and simple.
description	The description that will be used for the description. It is possible to use HTML tags inside this value to format the text inside the description.

## 11.12. Popup menu

When in [silent mode](#), it is possible to create a popup menu. The user will be able to use the menu by right-clicking on the tray-icon when Updater is finished updating the application.

By default, the popup menu will only have two entries:

1. About Updater...
2. Exit

The popup menu can be customized by adding custom actions and icons. To customize the popup menu, the following formatting must be used:

```
<?xml version="1.0" ?>
<UPDATEINFO>

  <POPUPMENU>
    <ITEM>
      <TEXT>Launch readme</TEXT>
      <LOCATION>c:\windows\notepad.exe</LOCATION>
      <PARAMETERS>%app%\Readme.txt</PARAMETERS>
      <BITMAP>http://www.gvhsoftware.org/bitmap1.bmp</BITMAP>
    </ITEM>
  </POPUPMENU>

</UPDATEINFO>
```

Object	Type	Possible values
text	string	Any string value
location	string	Any string value
parameters	string	Any string value
bitmap	string	Any string value

Object	Description
text	Text of the popup menu item.  <b>Note:</b> Use a – when a separator must be added to the menu.
location	The location of the file that should be executed when the user clicks on the popup menu item.
parameters	The parameters that should be used when executing the file. This value is not required.
bitmap	The location of the bitmap. Updater will download this

	<p>file and use it in the popup menu item.</p> <p>When this value is not used, Updater will not show any image before the popup menu item.</p> <p>The image should be 14 x 14 pixels (h x w).</p>
--	---

### 11.13. HTML message

It is possible to show some advertisement to the user about new or existing products or events. The user will only see this [HTML message](#) when running in [full mode](#).

When a HTML message should be enabled in Updater, the following formatting must be used:

```
<?xml version="1.0" ?>
<UPDATEINFO>

  <HTMLMESSAGE>
    <URL>http://www.gvhsoftware.org</URL>
    <TIME>3</TIME>
  </HTMLMESSAGE>

</UPDATEINFO>
```

Object	Type	Possible values
url	string	Any string value
time	integer	0 to 60

Object	Description
url	<p>The url where the HTML page is located which contains the HTML message.</p> <p>The width of the HTML page must be 391 pixels to make sure no horizontal scrolling will be enabled.</p> <p>Be sure to use <i>target="_blank"</i> when using links inside the HTML message so the user will be linked to a new window with more information.</p>
time	<p>The minimum time the user must wait before continuing the update process.</p> <p>The user will see a count down in the next button so he / she can see how long it takes before he / she can continue.</p>

## 11.14. Shortcuts

Updater is able to create shortcuts on the client pc.

The following formatting must be used when creating shortcuts:

```
<?xml version="1.0" ?>
<UPDATEINFO>

  <SHORTCUTS askuser="true">
    <SHORTCUT>
      <TARGETFILE>%app%\MyApplication.exe</TARGETFILE>
      <WORKINGDIRECTORY>%app%</WORKINGDIRECTORY>
      <PARAMETERS>-s</PARAMETERS>
      <LINKFILE>%desktopallusers%\MyApplication.lnk</LINKFILE>
      <ICONFILE>%app%\img\MyIcon.ico</ICONFILE>
      <ICONINDEX>1</ICONINDEX>
      <SHOWMODE>SW_SHOWNORMAL</SHOWMODE>
      <DESCRIPTION>MyApplication shortcut</DESCRIPTION>
    </SHORTCUT>
  </SHORTCUTS>

</UPDATEINFO>
```

**Note:** Don't forget to take a look at the [constants](#) which can be very useful when creating shortcuts.

Object	Type	Possible values
targetfile	string	Any string value
workingdirectory	string	Any string value
parameters	string	Any string value
linkfile	string	Any string value
iconfile	string	Any string value
iconindex	integer	≥ 0
showmode	Show mode value	SW_SHOWNORMAL SW_SHOWMAXIMIZED SW_SHOWMINNOACTIVE
description	string	Any string value

Object	Description
targetfile	Location of the file that should be executed when the user uses the shortcut.

workingdirectory	The working directory of the executable.
parameters	The parameters that should be used to execute the application when the user uses the shortcut.
linkfile	Location of the link file. This value defines where the shortcut will be located, for example the desktop or quick launch menu.
iconfile	The location of the file that contains the icon that must be used to show in the shortcut. Only use this value when the executable does not contain the right icon itself.
iconindex	The index of the icon that must be used. This is needed when a DLL or executable contains more than one icon.
showmode	The mode in which the application must be launched when the user uses the shortcut.
description	The description that will be shown to the user when the user hovers the shortcut.

## 11.15. Software protection

[Software protection](#) is a very important feature of Updater.

There are two ways of protection. They can be used separate, but also together:

1. License check
2. File hashing

To enable software protection, the following formatting must be used:

```
<?xml version="1.0" ?>
<UPDATEINFO>

  <PROTECTION>
    <BUYLICENSE>
      <WEBSITE>http://www.gvhsoftware.org</WEBSITE>
    </BUYLICENSE>
  </PROTECTION>

</UPDATEINFO>
```

Object	Type	Possible values
website	string	Any string value

Object	Description
website	The website where the user can get a valid license when the software protection fails. This website is not shown when the software protection succeeds or when this value is empty.

### 11.15.1. License check

The license check can be used by creating a DLL with at least one function with header:

```
bool CheckLicense();
```

Updater will call this function. When the function returns true, Updater will consider the license as valid. Any code can be inserted in this DLL, so any license can be checked this way.

The DLL will be downloaded from a website to prevent that hackers will edit the file. The file will be deleted immediately after the check, and will not remain on the users system. This is a very secure way of license checking.

Add this code to the update file to enable the license check:

```
<PROTECTION>  
  
    <REGISTRATION>  
        <LOCATION> http://www.gvhsoftware.org/license.dll</LOCATION>  
    </REGISTRATION>  
  
</PROTECTION>
```

**Note:** There is an example of a protection DLL inside the Updater compiled project.

Object	Type	Possible values
location	string	Any string value

Object	Description
location	The location where the DLL is located on the internet. Updater will download the DLL from this location to check the license.



## 11.15.2. File hashing

File hashing can check if a specific file is replaced by a different file. Since this is a very common way of software cracking, Updater supports file hash checking.

To enable file hashing, the following formatting must be used:

```
<PROTECTION>

  <HASHING>
    <HASH file="%app%\MyApp.exe" hash="b03900cf3fbc1f2c...">
  </HASHING>

</PROTECTION>
```

**Note:** There is no specified limit to the amount of file hashes.

Object	Type	Possible values
file	string	Any string value
hash	MD5 file hash	Any MD5 file hash

Object	Description
file	The filename that should be hash checked.
hash	The hash that the file should have.  <b>Note:</b> Keep in mind the user will still have the old version of the file, so the hash of the old version file should be used here.

## 12. Section file

This file is located on the hard-disk of the client user. This file is used to store all the version information used by [sections](#) by that specific user.

If this file is not available on the client's computer, it will install all the updates the user selects and store the newest version in a new generated file.

This file must be named as sections.xml and must be located in the same folder as the executable for Updater.

The file is formatted as followed:

```
<?xml version="1.0" ?>
<SECTIONS>
  <SECTION name="[sectionname]" version="[ section version]" />
</SECTIONS>
```

## 13. Self update file

This file is located at a server of [GVH Software](#). This file is used to check for new version for Updater itself.

Updater will check if a new version is available when self-update is enabled in the [update file](#). When a new version is available, Updater will download the new version.

Updater will not handle a self-update as a real update. This means Updater will download a new version of itself only when there is a new version available of the product that uses Updater too.

This file can, but only should, be hosted on a different location when a custom version of Updater is used. In that case, use the following formatting for the file:

```
<?xml version="1.0" encoding="ISO-8859-1"?>
<SELFUPDATE>
  <VERSION>0.8.1.5</VERSION>
  <LOCATION>http://www.site.com/bin/updater/updater.exe</LOCATION>
</SELFUPDATE>
```

## 14. User interface

### 14.1. Customizing

This chapter will explain how to customize the user interface of Updater.

All modes are able to change the way hyperlinks are showed. The colors of the hyperlinks in Updater can be defined in the [settings file](#).

#### 14.1.1. Full mode

Full mode can be customized by using custom wizard images. There are two images used when running in full mode.

##### 1) Large image

This size of the image must be 314 x 164 pixels (h x w). The default logo looks like this:



*Figure 14-1 Default large image*

## 2) Small image

This size of the image must be 58 x 435 pixels (h x w). The default logo looks like this:




Figure 14-2 Default small image

### 14.1.2. Silent mode

Silent mode can be customized by the custom notifies which can be defined in the [settings file](#). There is a tool (UpdaterSettings) included in the Updater compiled package which can be useful when designing custom notifies.

## 14.2. Icon explanation

### 14.2.1.1. Check version icon



This icon represents version checking.

### 14.2.1.2. Download icon



This icon represents downloading.

### 14.2.1.3. Install icon



This icon represents installing.

**14.2.1.4. Succeeded**

This icon represents a successful update process.

**14.2.1.5. Not succeeded**

This icon represents an update process that is not succeeded.