

Tornado Installation Notes

1. Install a JVMCI enabled JVM.

Note: this is a special OpenJDK especially for Tornado

Prebuilt binaries are available here:

- OSX 10.11.6 https://www.dropbox.com/s/2aguj98jg5b5yh4/jdk1.8.0_131-osx-10.11.6.tgz?dl=0
- Linux 64-bit https://www.dropbox.com/s/nvtpsviqc6u8vvnv/jdk1.8.0_131_x86.tgz?dl=0

Extract it and set JAVA_HOME to point to it.

```
$ tar xvJf jdk1.8.0_131-osx-10.11.6.tgz
$ export JAVA_HOME=$PWD/jdk1.8.0_131/
```

1a. Get prebuilt graal

graal-0.22.jar: <https://www.dropbox.com/s/2xtboskkjvf8chu/graal-0.22.jar?dl=0>

truffle-0.22.jar: <https://www.dropbox.com/s/mva2m1ufv6ooie8/truffle-api-0.22.jar?dl=0>

1b. Build graal-core from source

```
$ mkdir graal
$ cd graal
$ git clone https://github.com/beehive-lab/graal-core.git
$ git checkout master
$ mx build
```

2a. Build Tornado from source

```
$ git clone <url>/tornado.git
$ cd tornado
$ vi etc/tornado.env
```

<you must set JAVA_HOME to the path of the JDK installed in step 1.>
<you must set TORNADO_ROOT to the path that the Tornado SDK was extracted into.>

<you must set GRAAL_ROOT to the path that contains graal.jar e.g.
"<graal core>/mxbuild/dists">

Below is an example tornado.env file:

```
export TORNADO_ROOT=/tmp/test/tornado
export JAVA_HOME=/tmp/test/jdk1.8.0_131
export GRAAL_ROOT=/tmp/test/graal/graal-core/mxbuild/dists/
export PATH=${TORNADO_ROOT}/bin:${PATH}
```

```
$ . etc/tornado.env
$ mvn install
```

2b. Use Tornado SDK

Grab it from here: <https://www.dropbox.com/s/lx6ne71qtnjfeom/tornado-sdk-0.0.2.tgz?dl=0>
Note: requires GraalVM 0.17

```
$ tar xvzf tornado-sdk-0.0.2.tgz
$ cd tornado-sdk-0.0.2/etc/
$ vi tornado.env
```

<you must set JAVA_HOME to the path of the JDK installed in step 1.>
<you must set TORNADO_ROOT to the path that the Tornado SDK was
extracted into.>

```
$ . tornado.env
```

3. Build The OpenCL Drivers

```
$ cd drivers/opengl
$ autoreconf -f -i -s
$ ./configure --prefix=${PWD} --with-jdk=${JAVA_HOME}
$ make clean
$ make
$ make install
```

4. Query the available devices

```
$ tornado tornado.drivers.opengl.OpenCL
usage: OpenCL <platform> <device>
```

```
[0]: platform: Apple
[0:0] device: Intel(R) Core(TM) i7-4850HQ CPU @ 2.30GHz
[0:1] device: Iris Pro
[0:2] device: GeForce GT 750M
```

To view specific details of a specific device pass the platform and device indices tornado.

```
$ tornado tornado.drivers.opengl.OpenCL 0 1
15:41:35.205 [main] WARN tornado.drivers.opengl.OCLDeviceContext -
device requires bump buffer: Iris Pro
id=0x1024500, name=Iris Pro, type=CL_DEVICE_TYPE_GPU, available=true
freq=1.2 GHz, max compute units=40
global mem. size=1.5 GiB, local mem. size=64.0 KiB
extensions:
  cl_APPLE_SetMemObjectDestructor
  cl_APPLE_ContextLoggingFunctions
  cl_APPLE_clut
```

```

cl_APPLE_query_kernel_names
cl_APPLE_gl_sharing
cl_khr_gl_event
cl_khr_global_int32_base_atomics
cl_khr_global_int32_extended_atomics
cl_khr_local_int32_base_atomics
cl_khr_local_int32_extended_atomics
cl_khr_byte_addressable_store
cl_khr_image2d_from_buffer
cl_khr_gl_depth_images
cl_khr_depth_images
cl_khr_3d_image_writes
unified memory      : true
device vendor       : Intel
device version      : OpenCL 1.2
driver version      : 1.2(Sep 25 2016 23:45:03)
OpenCL C version    : OpenCL C 1.2
Endianness          : little
address size        : 64

```

5. Run the HelloWorld example

[Optional: load tornado environment settings on first use]
\$. etc/tornado.env

```

$ tornado tornado.examples.HelloWorld
tornado[ 0, 0, 0]> hello
tornado[ 2, 0, 0]> hello
tornado[ 3, 0, 0]> hello
tornado[ 4, 0, 0]> hello
tornado[ 5, 0, 0]> hello
tornado[ 6, 0, 0]> hello
tornado[ 1, 0, 0]> hello
tornado[ 7, 0, 0]> hello

```

To change the target device you need to use the enumeration provided in step 3. e.g.
<platform:device>.

To force all tasks within a task-schedule, called “s0” to use a specific device use the following.

```

$ tornado -Ds0.device=0:1 tornado.examples.HelloWorld
tornado[ 0, 0, 0]> hello
tornado[ 2, 0, 0]> hello
tornado[ 3, 0, 0]> hello
tornado[ 4, 0, 0]> hello
tornado[ 5, 0, 0]> hello
tornado[ 6, 0, 0]> hello
tornado[ 1, 0, 0]> hello
tornado[ 7, 0, 0]> hello

```

To force a specific task, “t0”, within the task-schedule “s0” to use a specific device do the following.

```

$ tornado -Ds0.t0.device=0:1 tornado.examples.HelloWorld

```

```
tornado[ 0, 0, 0]> hello
tornado[ 2, 0, 0]> hello
tornado[ 3, 0, 0]> hello
tornado[ 4, 0, 0]> hello
tornado[ 5, 0, 0]> hello
tornado[ 6, 0, 0]> hello
tornado[ 1, 0, 0]> hello
tornado[ 7, 0, 0]> hello
```

6. Run some micro-benchmarks

```
$ runBenchmarks.sh
```

The results will be available under `${TORNADO_ROOT}/var/results`.

7. Explore the example code

Example code is located under `${TORNADO_ROOT}/share`.